Lab 3: Atmospheric Humidity

This assignment is worth 15 points.

Objectives

This laboratory is intended to give you some familiarity with these various expressions for atmospheric water content. We compare measurements of vapor density, vapor pressure, relative humidity, dew point temperature and vapor density deficit inside the classroom with measurements outdoors.

- Differentiate between the ways moisture is represented in the atmosphere, specifically, dew point temperature, absolute humidity, vapor pressure, saturation vapor pressure, relative humidity and vapor pressure deficit.
- Using equations, describe the relationship between different measures of atmospheric humidity

Table 1: Definitions for symbols/abbreviations and constants used in this lab.

Symbol	Name	Definition
\overline{T}	Temperature	Quantitatification of the heat present in an object (in K unless specified otherwise)
T_d	Dew-point temperature	Figure 2
T_w	Wet-bulb temperature	The temperature read by a ventilated thermometer covered in water at ambient temperature
RH	Relative Humidity	The $\%$ of absolute humidity relative to the maximum possible humidity at T
P_v	Vapor pressure	Partial pressure exerted by water vapor in the atmosphere; can be calculated using Equation 2
P_v^*	Saturation vapor pressure at T	Maximum possible vapor pressure for a parcel of air at T ; use Equation 3 or Figure 1

Symbol	Name	Definition
$\overline{ ho_v}$	Vapor density	Equation 2 or Equation 7
$ ho_v^*$	Saturation vapor	Figure 2
	density at T	
$ ho_{vw}^*$	Saturation vapor	Figure 2
	density at T_w	
VDD	Vapor density defect	Equation 5
VPD	Vapor pressure defect	Equation 6
R	Ideal gas constant	$8.31446261815324 \ \mathrm{x} \ 10^{-3} \ \mathrm{kPa} \ \mathrm{m}^{\ 3} \ \mathrm{g}^{\ -1} \ \mathrm{K}^{\ -1}$
γ	Psychrometric	$0.495~\mathrm{g}$ m $^{-3}$ K $^{-}1$
	constant (at 20 $^{\circ}$ C)	
M_{H_2O}	Molar mass of water	$18.01528 \text{ g mol}^{-1}$

Theory

Water vapor constitutes a fairly small part of our atmosphere Table 2. However, it plays a disproportionately important role in the Earth's climate system in your day to day life! We use the term **humidity** to describe the amount of water vapor present in a given parcel of air.

- The rate of evaporation of water from a surface depends on atmospheric humidity. Thus the rate at which a soil dries and vegetation consumes water, depends in part on the atmospheric humidity.
- Additionally, evaporation from the lungs and of sweat from the skin is an important mechanism for maintaining a consistent body temperature in mammals and birds. The efficiency of the evaporative cooling depends on evaporation rate which, in turn, depends partly on the atmospheric humidity.

Table 2: Relative proportion (in %) of different gasses that makeup the atmosphere. * These values are for dry air. ** Water vapor (H2O) varies drastically by location, and will alter the other values.

Gas	Abbreviation	Proportion
Nitrogen	N2	78.08% *
Oxygen	O2	20.95% *
Argon	Ar	0.93% *
Carbon Dioxide	CO2	0.04% *
Misc. Trace Gasses		<0.01% *
Water Vapor	H2O	0-3% **

The Ideal Gas Law

You may recall from a high school chemistry class, the Ideal Gas Law (Equation 1) can be used to describe the state of some a gas as a function of pressure (P), volume (V), temperature (T), and the amount of the gas (n) in moles; with R being the ideal gas constant (see Table 1). The amount in moles of a given gas can be defined as $n = \frac{m}{M}$, where m is the mass of the substance (in kg or g) and M is the Molar mass (in kg mol-1 or g mol-1) respectively. The molar mass of water (in g mol-1) is listed in Table 1. The Ideal Gas Law generally applies to water vapor as it does other gasses and can be used to help explain some important relationships.

$$PV = nRT \tag{1}$$

Two key metrics we use to describe atmospheric moisture in meteorology are:

1. Vapor density: ρ_n

- This metric quantifies the density of water vapor within a parcel of air and is typically given in g m-3
 - It describes mass of H2O vapor (in grams) per unit volume (cubic meter) of air, i.e. $\frac{m_{H2O}}{V}$.

2. Vapor pressure: P_n

- This metric quantifies the partial pressure exerted by the water vapor in a parcel of air and is typically given in kPa.
 - The pressure exerted by the water vapor in the atmosphere, is only a small portion of the total pressure exerted by the atmosphere. The pressure of the various gasses is proportional composition of gasses in the atmosphere (see Table 2)

We can redefine the ideal gas law in terms of ρ_v and P_v as Equation 2 to make our calculations easier:

$$\rho_v = \frac{P_v M}{RT} \tag{2}$$

Saturation

Under the pressures and temperature conditions experienced on Earth the atmosphere can only hold a small amount of water vapor before it becomes saturated. We add an asterisk to ρ_v^* and P_v^* to denote saturation vapor density and saturation vapor pressure respectively. Once the atmosphere reaches saturation point, H2O vapor in the air will begin to condense into its liquid form.

Determining exact value of ρ_v^* and P_v^* for a specific value of T isn't a straightforward calculation. This is because we need to consider the latent heat of vaporization (recall this term for lecture). When water changes phase, it adds (condensation/freezing) or removes (evaporation/melting) a massive amount of energy from its surrounding environment. Calculating ρ_v^* and P_v^* exactly involves using some calculus to evaluate a differential equation known as the Clausius–Clapeyron relation. But don't worry, we're not going to make you do any calculus here. Empirically derived relationships have been derived to help simplify the calculations. On such relationship, is known as the Buck equation (Equation 3). Note: this empirical equation requires T to be in $^{\circ}C$, instead of K, which is different from most from many others. The ideal gas law Equation 1 and it's variant Equation 2 require temperature to be in K.

$$P_v^* = 0.61121e^{(18.678 - \frac{T}{234.5})(\frac{T}{257.14+T})}$$
(3)

By evaluating Equation 3, we can come up with an accurate approximation for P_v^* to a high degree of accuracy (\pm 0.08%) within the ranges of temperatures and pressures typically observed on Earths surface. We can then plug the result into Equation 2 to solve for ρ_v . Remembering to convert our temperature values to K in order to evaluate this variant of the ideal gas law. The R code shown in Example 0.1 shows how you could perform these calculations in programmatically. Figure 1 shows the output of Equation 3, i.e., how P_v varies with T for selected temperatures. Figure 2 shows the output of Equation 2 for given values of T and P_v .

Example 0.1. Functions to evaluate the Buck Equation and Ideal Gas Law. Functions are pieces of code that can be defined once an run numerous times. They make performing calculations that need to be repeated much easier. Functions may take one or more inputs in parentheses (). They and will evaluate the instructions contained between the curly brackets {}. The "return()" command can optionally be used to return one or more outputs. This script evaluates the functions then saves the outputs to a .csv file, which you can download by clicking here.

```
Buck_Equation <- function(T){
    # Takes T in deg C and returns P_v in kPa
    P_v <- 0.61121*exp((18.678-T/234.5)*(T/(257.14+T)))
    return(P_v)
}

Ideal_Gas_Law_Vapor_Density <- function(T,P_v){
    # Takes T in deg C and vapor pressure in kPa; converts T to K; then returns the rho_v
    R <- 8.31446261815324e-3 # Ideal Gas Constant in kPa m$^3$ K$^{-1}$ mol$^{-1}$
    M <- 18.01528 # Molar mass of H20 in g m-3
    T_k <- T + 273.15
    rho_v = P_v*M/(R*T_k)</pre>
```

```
return (rho_v)
}

# Vector of air temperature in 1 deg C intervals over over the range -10 to 40 C
T <- c(-10:40)
P_v <- Buck_Equation(T)
rho_v <- Ideal_Gas_Law_Vapor_Density(T,P_v)

# A "data frame" is a like a table
Saturation_by_Temperature <- data.frame(T,rho_v,P_v)
write.csv(Saturation_by_Temperature,'www/Saturation_by_Temperature.csv',col.names = c("T definition")</pre>
```

Humidity

There are other ways of expressing the amount of moisture in the atmosphere; each has particular usefulness in certain applications. For example, **relative humidity** (RH); it is a given as a percentage (0-100%) and is the most commonly reported metric for humidity. When RH = 100, it indicates the atmosphere is saturated; when RH < 100, it indicates the atmosphere is not saturated. Relative humidity is the ratio of $/rho_v$ for a given parcel of air at a certain T relative to the maximum possible ρ_v^* the parcel of air could have at that T, as shown in Equation 4.

$$RH = \frac{\rho_v}{\rho_v^*} \tag{4}$$

Note: if you have a parcel with a known ρ_v and a known T, you can use Figure 2 to lookup the value of ρ_v^* to evaluate Equation 4. Alternatively - you could also evaluate Equation 3 and Equation 2 to get ρ_v^* and then evaluate Equation 4. This metric is useful because it can convey the relative saturation of the atmosphere without us having to know the absolute values. However, it can also be deceptive, because the two air parcels (one at 0 ° C and one at 20 ° C) that both have RH = 100 will contain significantly different amounts of water vapor in absolute terms.

The other commonly reported metric in every-day life is the **dewpoint** (T_d) . This is the air temperature at which a parcel of air with a given ρ_v would be saturated. If you have a parcel of air with known ρ_v , the value of T that corresponds to ρ_v in Figure 2 would be it's dewpoint. This metric is useful because it quantifies the absolute moisture content of a parcel of air (unlike RH). However - two parcels of air can have the same T_d while having drastically different air temperatures. Both RH and T_d are limited (in different ways) because they don't convey the full picture; but they are still useful in day-to-day life as they are relatively easy to understand.




Figure 1: Saturation vapor pressure P_v^* as a function of temperature T, calculated using Equation 3




Figure 2: Saturation vapor density ρ_v^* as a function of temperature T and P_v using Equation 2. **Note** these values were calculated using T in \mathbf{K} , but the values on the x axis are shown in ${}^{\circ}\mathbf{C}$ because Celsius is the unit wear are more familiar with in our day to day lives.

Vapor Deficits

For calculating evaporation rates, the difference between the maximum and the actual vapor density is useful useful. This metric is called the **vapor density deficit** (VDD):

$$VDD = \rho_v^* - \rho_v \tag{5}$$

Alternatively, we can calculate the **vapor pressure deficit** (VPD). It represents the difference between the actual and saturation vapor pressures of a parcel at temperature T. This metric is particularly helpful when thinking about water exchange in plants. As the VPD increases, the rate of water loss from a plants leaves increase.

$$VPD = P_{v}^* - P_{v} \tag{6}$$

• Note: that smaller values of VDD and VPD mean a parcel is closer saturation.

Questions

Question 1 [0.5 points]

Describe the relationship between air temperature and atmospheric saturation. How to P_v^* and ρ_v^* vary as a function of air temperature?

Answer:

- Both P_v^* and ρ_v^* increase **exponentially** with T.
 - -0.25 pts if they only say that the values increase with T but do not specify the increase is **exponential**.
 - * Don't need to use the specific word exponential saying something like "the rate of increase, increases with temperature" would also be valid albeit overly verbose.

Question 2 [0.5 points]

The highest dew point ever recorded, 35 ° C, was recorded at Dhahran, Saudi Arabia, on July 8, 2003. With an air temperature of 42 ° C. What were the approximate values of ρ_v and P_v for this record breaking observation?

Answer:

- From Figure 2 we can see the value of ρ_v was 39.5642045 g m⁻³
- From Figure 1 we can see the value of P_n was 5.6267521 kPa

Question 3 [1 points]

The record low temperature recorded in Vancouver, BC was -18 °C on December 29th, 1968. What are the saturation vapor pressure (P_v^*) and saturation vapor density (ρ_v^*) values at that air temperature?

Answer:

• Following the steps outlined in Example 0.1:

```
- P_v = 0.1489745 \text{ kPa} - \rho_v = 1.2650952 \text{ g m}^{-3}
```

Question 4 [0.25 points]

Multiple Choice: select the correct answer(s) from those listed

What would the dewpoint (T_d) of a parcel of air be with a $P_v=0.61121$ kPa and a T=25 ° C?

```
a. 23.0266116 \text{ g m}^{-3}
```

b. 23.0266116 kPa

c. 3.1685314 kPa

d. 25 $^{\circ}$ C

e. $0 \, ^{\circ} \, \mathrm{C}$

Answer:

• From Figure 2 we can see the value of T_d is 0

Question 5 [0.5 points]

Did knowing that T=25 ° C help you answer the question above? Explain.

Answer:

You can figure out T_d from P_v alone - knowing T doesn't give you any extra information.

Question 6 [2 points]

What would the relative humidity of the parcel of air with $P_v=0.61121$ kPa and a T=25 ° C be?

Answer:

The short way

- 1. Find P_v^* at T
- $3.1685314~{\rm kPa}$
 - 2. Calculate RH
- 0.1929001~%

The long way

- 1. Figure out the T_d from Figure 1: i.e., at what T_d would the observed P_v be P_v^*
- 0 °C
 - 2. Find the ρ_v corresponding to T_d Figure 2
- 4.8483736 g m-3
 - 3. Find ρ_v^* corresponding to T Figure 2

23.0266116 g m-3

- 4. Calculate RH
- 0.2105552~%

Question 7 [0.25 points]

Multiple Choice: select the correct answer(s) from those listed

A airmass (homogeneous parcel of air) off the coast of British Columbia has the following characteristics: T=10 ° C, RH=95%. Over the course of a few days, it moves eastward into British Columbia's interior, and in the process its temperature drops considerably, to -10 ° C. Which of the following would also **need** happen to the airmass on its journey east?

- a. A portion of the water vapor in the airmass would evaporate
- b. A portion of the water vapor in the airmass would condense
- c. Its impossible to say with only the information provided
- d. The relative humidity of the airmass would decrease

e. The relative humidity of the airmass would increase

Answer:

- B & E (.125 pt each); (one correct & one incorrect = 0 pts)
- rho_v^* at 10 ° C is 9.3959171. So for RH = 95%; $\rho_v = 8.9261213$
- The value of T in Figure 2 for this value of ρ_v is the T_d
- The air would cool until it reaches T_d . When $T = T_d$; RH = 100%
- To cool below this temperature a portion of the water vapor in the air will condense
 - This will produce clouds and precipitation

Question 8 [0.25 points]

Multiple Choice: select the correct answer(s) from those listed

All else equal, we would expect a field of healthy corn in the middle of July to consume $_$ water on a day when the VPD is 0.5 kPa compared to a day when the VPD is 1.2 kPa.

- a. More
- b. Less
- c. Roughly the same
- d. Any of the above outcomes are possible

Answer:

• Less

Experimental Observations


Measuring Atmospheric Humidity

A common and simple type of instrument used to measure humidity is the psychrometer (Figure 3). There are two variants of this instrument, but they have the same key components. They consist of a pair of a ventilated pair of thermometers, one of which has a wetted wick covering the bulb of the thermometer. The wet-bulb is cooled by evaporation to a value known as the "wet-bulb temperature" (T_w) . If we have a measurement of both T (aka "dry-bulb" temperature) and T_w (aka "wet-bulb" temperature) we can calculate ρ_v using Equation 7; where ρ_{vw}^* is the saturation vapor density at T_w and γ is the psychrometric constant (see Table 1). The value of ρ_{vw}^* can be found by looking up T_w in Figure 2, or by plugging T_w into Equation 3 and Equation 2.

Wet bulb temperature (T_w) is also a useful metric, because it gives us the minimum temperature to which an object can be cooled via evaporation, under different temperature and

humidity conditions. This has important ramifications for public safety; humans cannot survive exposure to $T_w > 35\,^{\circ}C$ for more than six hours. Wet-bulb temperatures above 35 $^{\circ}C$ are relatively rare, but they do occur in some parts of the world, and are unfortunately becoming more common as a result of climate change.

$$\rho_v = \rho_{vw}^* - \gamma (T - T_w) \tag{7}$$



(b) Diagram of an Assman psychrometer

Figure 3: Comparison of the two types of psychrometers. A sling psychrometer Figure 3a is operated by manually swinging the device in a circle to ventilate the saturated wick. The Assman psychrometers Figure 3b instead has a mechanical or electrically powered fan that is used to ventilate the saturated wick.

Experimental procedure

In this experiment, you will be using an Assmann psychrometer (see Figure 3b) to make measurements of water vapor content of the air and calculate ρ_v . First you will collect a measurement in the lab, then you will go outside and collect another set of measurements. You can follow the procedures listed below.

(1) Examine the psychrometer and notice the wick on the wet-bulb thermometer. Use distilled water to wet the wick thoroughly.

- (2) When you are ready to begin; wind up the clockwork ventilation fan and start the fan to begin ventilating the wet-bulb thermometers.
- (3) Read measurements on both the dry- and wet-bulb thermometers every 15 s for 3 or 4 minutes, until the readings of both thermometers stabilize and record your final values of T (dry-bulb) and T_w (wet-bulb). **Note** make sure the ventilation fan doesn't stop during the measurement; if it does rewind the spring to restart the fan.
- (4) Re-wet the wick on the wet-bulb thermometer. Then take the psychrometer outside and repeat the measurement as described above. **Note** it may take longer for the values to stabilize if the air temperature outside is significantly different from that in the air temperature in the lab.
- (5) Use your readings of T and T_w to determine: T_d , RH, ρ_v , rho_v^* , VDD, P_v , P_v^* , VPD for both inside and outside. *Hint*: You may need to reference Figure 1, Figure 2, Equation 7, Equation 3, and/or Equation 2 to determine these values.

Questions

Question 9 [7.5 points]

Report your observed values of T and T_w ; along with your calculated values of ρ_v , P_v , T_d , RH, VDD, and VPD and for both your indoors and outdoor measurements with the Assmann psychrometer. Show your work where applicable. you can use this template to organize your answers. You can round your results to 2 decimal points, but make sure not to round your answers until all intermediate calculations are complete. *Note* in the template, the "_" and "^" characters are used to represent subscripts and superscripts respectively.

Answer:

If you have R studio installed, you can use the code below check answers. There are 30 values to report in the template table (10 for indoor, 10 for outdoor, and 10 units) - so give 0.25 pts per entry. You can give half credit (0.125) for entries that are incorrect > if they show how they did the calculation and you can see where they went wrong. TAs - you can also find the R file with the Answer key I provided

```
Buck_Equation <- function(T){
    # Takes T in deg C and returns P_v in kPa
    P_v <- 0.61121*exp((18.678-T/234.5)*(T/(257.14+T)))
    return(P_v)
}

Ideal_Gas_Law_Vapor_Density <- function(T,P_v){
    # Takes T in deg C and vapor pressure in kPa; converts T to K; then returns the rho_v</pre>
```

```
R < -8.31446261815324e-3 \# Ideal Gas Constant in kPa m$^3$ K$^{-1}$ mol$^{-1}$
    M \leftarrow 18.01528 \text{ # Molar mass of H2O in g m-3}
    T_k \leftarrow T + 273.15
    rho_v = P_v*M/(R*T_k)
    return (rho_v)
}
Ideal_Gas_Law_Vapor_Pressure <- function(T,rho_v){</pre>
    # Takes T in deg C and vapor density in g m-3; converts T to K; then returns the P_v i
    R < -8.31446261815324e-3 # Ideal Gas Constant in kPa m$^3$ K$^{-1}$ mol$^{-1}$
    M \leftarrow 18.01528 \text{ # Molar mass of H2O in g m-3}
    T_k \leftarrow T + 273.15
    P_v = rho_v*R*T_k/M
    return (P_v)
}
rho_v_from_Pysychrometer <- function(T,T_w,rho_vw_saturation){</pre>
    # Takes T and T_w in deg C and rho_vw_saturation in kPa; returns rho_v in kPa
    gamma <- 0.495 # g m-3 K-1
    rho_v = rho_vw_saturation - gamma*(T-T_w)
    return(rho_v)
}
# Indoor obs
T_in <- 18
T_w_in <- 16
# Outdoor obs
T_out <- 10
T_w_out <- 9
# Dump to dataframe
T \leftarrow c(T_{in}, T_{out})
T_w \leftarrow c(T_w_{in}, T_w_{out})
Obs <- data.frame(T,T_w)</pre>
Obs$P_v_saturation <- Buck_Equation(Obs$T)</pre>
Obs$P_vw_saturation <- Buck_Equation(Obs$T_w)</pre>
Obs$rho_v_saturation <- Ideal_Gas_Law_Vapor_Density(Obs$T,Obs$P_v_saturation)</pre>
Obs$rho_vw_saturation <- Ideal_Gas_Law_Vapor_Density(Obs$T_w,Obs$P_vw_saturation)</pre>
```

```
Obs$rho_v <- rho_v_from_Pysychrometer(Obs$T,Obs$T_w,Obs$rho_vw_saturation)
Obs$P_v <- Ideal_Gas_Law_Vapor_Pressure(Obs$T,Obs$rho_v)</pre>
# Solve Buck_Equation for a range of possible T (students can just reference the chart/tab
T_{dew\_range} \leftarrow c(-10:40)
P_v_saturation_range <- Buck_Equation(T_dew_range)</pre>
# Find the closest value
# Students can just look these up in Fig 1 - no need to invert the buck equation
Obs$T_dew[row_number] <- T_dew_range[which(abs(P_v_saturation_range-Obs$P_v[row_number])==
row_number = 2
Obs$T_dew[row_number] <- T_dew_range[which(abs(P_v_saturation_range-Obs$P_v[row_number])==
Obs$RH <- Obs$rho_v/Obs$rho_v_saturation</pre>
Obs$VDD <- Obs$rho_v_saturation-Obs$rho_v</pre>
Obs$VPD <- Obs$P_v_saturation-Obs$P_v</pre>
Rounded <- round(t(Obs[,c('T','T_w','T_dew','RH','rho_v','rho_v_saturation','VDD','P_v','F
                     digits = 2)
Results <- cbind(Rounded,
                c('C','C','K','g m-3','g m-3','g m-3','kPa','kPa','kPa')
colnames(Results) <- c('Inside','Outside','Units')</pre>
row.names(Results) <- c('T','T_w','T_d','RH','rho_v','rho_v^*','VDD','P_v','P_v^*','VPD')
# Example Results > replace T_in, T_w_in, T_out, and T_w_out above to check student calculat
Results
```

```
Inside Outside Units
Τ
        "18"
               "10"
                         "C"
                "9"
                         "C"
\mathtt{T}_{-}\mathtt{w}
        "16"
T_d
                "8"
                         "C"
        "15"
        "0.82" "0.89" "%"
RH
rho_v
        "12.63" "8.32"
                        "g m-3"
rho_v^* "15.36" "9.4"
                         "g m-3"
VDD
        "2.73" "1.08"
                        "g m-3"
P_v
        "1.7" "1.09" "kPa"
P v^*
        "2.06" "1.23"
                        "kPa"
VPD
        "0.37" "0.14" "kPa"
```

Question 10 [2.25 points]

- a. Were your measured water vapor densities (ρ_v) indoors and outdoors equal? Is this reasonable? Explain why.
- b. Were your measured vapor pressure deficits (VPD) indoors and outdoors equal? Is this reasonable? Explain why.
- c. How did your measured T and T_w values compare to your calculated T_d values?

Answer:

- a. Expect inside and outside vapor densities to be similar; either can be the larger value depending on weather conditions. The students must use their own vapor densities and offer plausible explanations. e.g. dry or rainy weather outside, people breathing out moisture inside, heating dries out building & etc. a warm room will tend to reduce ρ_v a little. 1pt
- b. Expect inside and outside vapor densities to be more different; inside will likely be larger if its a cool day, if outdoor temp is close to room temp then they'll be more similar, if measurements occur on hot day and the lab were air conditioned then we'd see expect outdoors to have the larger VPD. The students must use their own VPD and offer plausible explanations. e.g. cool weather outside vs heated conditions inside resulting in different P_v^* 1pt
- c. $T_d \leq T_w \leq T$.25pt

Extra context: (not required for credit) If the atmosphere is saturated (ie. RH = 100) then the three values will be equal - otherwise, T_w will be between T_d and T