EGNSS4CAP WEB SERVICE SOURCE CODE OVERVIEW

Here you can find technical overview of implemented web services and their features.

https://installation-server.tld/ws/comm login.php

- check user by login and pswd
- input
 - o HTTPS, POST
 - o parameters
 - login string(255)
 - pswd string(255)
- output
 - o JSON
 - status string ok/error
 - error msg string error message if an error occurs
 - user number user ID for login, if exists

https://installation-server.tld/ws/comm_shapes.php

- sends geometry shapes for rectangle
- input
 - o HTTPS, POST
 - o parameters
 - max lat float
 - min lat float
 - max lng float
 - min lng float
- output
 - o JSON
 - status string ok/error
 - error_msg string error message if an error occurs
 - shapes array
 - identificator string shape identificator
 - wgs geometry json geometry of shape

https://installation-server.tld/ws/comm task photos.php

- sends photos for task or user
- input
 - o HTTPS, POST
 - o parameters

- task id number task identificator
- user id number user identificator
- output
 - o JSON
 - status string ok/error
 - error msg string error message if an error occurs
 - photos array
 - note string user note
 - lat float latitude of photo
 - lng float longitute of photo
 - photo_heading number photo azimuth
 - created datetime date and time of photo creation
 - photo string base64 encoded photo
 - digest string hash of photo

https://installation-server.tld/ws/comm_tasks.php

- sends tasks for user
- input
 - o HTTPS, POST
 - parameters
 - user id number user identificator
- output
 - o JSON
 - status string ok/error
 - error msg string error message if an error occurs
 - tasks array
 - id number task identificator
 - status string task status
 - name string task name
 - text string description of task
 - text returned string description why is returned
 - date created datetime date of create task
 - task due date datetime task due date
 - note string task note
 - number of photos number number of photos for task
 - flag valid string task is accepted
 - flag invalid string task is declined

https://installation-server.tld/ws/comm update.php

- receive task data from phone
- input
 - o HTTPS, POST
 - o parameters

- task id number task identificator
- user id number user identificator
- status string task statuses
- note string task note
- photos array
 - note string photo note
 - lat float photo latitude
 - lng float photo longitude
 - altitude
 - bearing
 - magnetic azimuth
 - photo heading
 - pitch
 - roll
 - photo_angle
 - orientation
 - horizontalViewAngle
 - verticalViewAngle
 - accuracy
 - deviceManufacture
 - deviceModel
 - devicePlatform
 - deviceVersion
 - satsInfo
 - extraSatCount
 - NMEAMessage
 - networkInfo
 - created datetime date of photo creation
 - digest string photo hash
 - photo string base64 encoded photo
- output
 - o JSON
 - status string ok/error
 - error_msg string error message if an error occurs