5 Extending the Alternative: A Scaling Device and Queues

Many machines used in automated processes have some means of monitoring their operation, for example, by calculating running averages of specific values and ensuring they stay within a specified range. If they go out of range then the machine recalibrates itself. In this chapter we shall build a model of such a device, but without having to interface to a real machine!

5.1 The Scaling Device Definition

The scaling device¹ reads incoming integers that arrive every second. The device then multiplies the incoming value by its current scaling factor, which it then outputs, together with the original value. The scaling factor is doubled at a regular interval, of say, 5 seconds. In addition, there is a controlling function that suspends the operation of the scaling device again at regular intervals, of say, 7 seconds to simulate the testing of its operation. When it is suspended the scaling device outputs its current scaling factor to the controller. At some time later, the controller, having computed another scaling factor, will inject the new scaling factor into the controller, which resumes its normal mode of operation. While the scaling device is suspended by the controller it outputs all input values unscaled.

The structure of the system, showing the channels that will be used for the communications specified above is shown in Figure 5-1.




Figure 5-1 Structure of the Scaling Device

The processes GNumbers, GFixedDelay and GPrint are available in the package groovyPlugAndPlay. Thus the discussion revolves around the structure of the remaining two processes.

¹ Belapurkar A, http://www-128.ibm.com/developerworks/java/library/j-csp2/

5.1.1 The Controller Process

The code that implements the Controller process is shown in Listing 6-1.

```
class Controller implements CSProcess {
02
           def long testInterval = 7000
           def long computeInterval = 700
03
04
           Def int addition = 1
05
06
           def ChannelInput factor def ChannelOutput suspend
           def ChannelOutput injector
07
08
           void run() {
09
10
              def currentFactor = 0
def timer = new CSTimer()
11
              def timeout = timer.read()
12
13
14
15
16
17
18
19
20
21
22
              while (true) {
                timeout = timeout + testInterval
timer.after ( timeout )
suspend.write (0)
                currentFactor = factor.read()
                currentFactor = currentFactor + addition
                 timer.sleep(computeInterval)
                 injector.write ( currentFactor )
           }
```

Listing 5-1 Code of the Controller Process

From Figure 5-1 we can see that Controller has three channel properties {4-6}. In addition, it has two timeout values, one testInterval {2} determines the period between successive tests of the scaling device. The other, computeInterval {3} is used to simulate the time it takes to compute the revised scaling factor.

The JCSP class CSTimer provides a means of manipulating time in a consistent and coherent manner. An instance of CSTimer, called timer is defined $\{10\}$. The timer can be read at any instant and the current long value of the system clock in milliseconds is returned, which also justifies the type long for the interval properties defined previously. The value of timeout is set to the current time $\{11\}$. The device operates as a never ending loop $\{12\text{-}21\}$, which for most machine tools is reasonable.

Within the loop the timeout is incremented by the testInterval {13}, which must be some time in the future. The after operation on timer causes the process to be suspended until the value of the current time is after the indicated alarm time. While a process is suspended in this manner it will consume no processing resource. Once the testInterval has elapsed, the Controller writes a signal to the Scale process to suspend its operation {15}. The value communicated does not matter, so the value 0 is perfectly adequate. The Controller then reads the current scaling factor from the Scale process into currentFactor using the channel factor {16}. The value of currentFactor is then incremented {17} by the value contained in the property addition {4}, to simulate a change in the scaling factor. The time to undertake this recalculation is then simulated by suspending the process for the computeInterval by calling the sleep method on the timer {18}. The sleep method deschedules the process for the specified sleeping time. The process consumes no processor resource while it is sleeping. In this case the effect of after and sleep are the same, achieved in a different manner. In some situations, the after method will be the more appropriate because it provides relative time. The sleep method provides an absolute value. Once the process has been rescheduled, it writes {19} the newly computed currentFactor on the injector channel to the Scale process.

5.1.2 The Scale Process

The structure of the Scale process is shown in Listings 5-2 and 5-3. The operation of the Scale process can be partitioned into two distinct parts; when it is operating in the normal mode and when it is suspended. In the normal mode it will accept inputs from the channels timedData and suspend, see Figure 5-1. It will also respond to timer alarms indicating that the scaling factor should be doubled. In the suspended mode it will only respond to inputs from the channels timedData and injector. To reflect these situations a set of guards will be needed for each mode. Furthermore, the suspended set will only be considered when the process has moved from the normal mode into the suspended mode.

```
23
         class Scale implements CSProcess {
            def int scaling = 2
            Def int multiplier = 2
def ChannelOutput outChannel
25
26
27
28
29
            def ChannelOutput factor
            def ChannelInput inChannel
            def ChannelInput suspend
30
            def ChannelInput injector
31
32
33
            void run () {
  def SECOND = 1000
               def DOUBLE_INTERVAL = 5 * SECOND
34
35
36
37
               def NORMAL_SUSPEND = 0
def NORMAL_TIMER = 1
               def NORMAL_IN
               def SUSPENDED_INJECT = 0
def SUSPENDED_IN = 1
38
39
               def timer = new CSTimer()
def normalAlt = new ALT ( [ suspend, timer, inChannel ] )
def suspendedAlt = new ALT ( [ injector, inChannel ] )
40
41
42
               def timeout = timer.read() + DOUBLE_INTERVAL
43
               timer.setAlarm ( timeout )
```

Listing 5-2 The Properties and Initialisation of the Scale Process

The channel properties are defined {24-30}, together with the initial scaling value {24} and the multiplier that will be applied to the scaling factor {25}. The inChannel property {28} is connected to timedData of Figure 5-1 and outChannel to scaledData {26}. Within the run() method a number of constants are defined; DOUBLE_INTERVAL {33} specifies the number of milliseconds between the doubling of the scaling factor. The remainder are constants {34-38} used to identify which case is to be considered when the switch statements associated with the alternatives are processed. A timer is defined {39}, followed by the two different alternatives {40, 41}. Both of the alternatives will be accessed using a priSelect method and thus the ordering of the guards in the alternatives is important and should always start with the highest priority going to the lowest in sequence. The alternative normalAlt applies when the device is not in a suspended state. The highest priority guard is that associated with the suspend channel. The next highest will result from a timer alarm and the lowest is the input of some data on the inChannel. In the suspended state the suspendedAlt will apply and this is just an alternation over the injector and inChannel channels because timer alarms are ignored. At {42} the timeout for the first doubling of the scaling factor is defined by reading the timer and adding the doubling interval. An alarm on the timer is made by calling the method setAlarm {43} with the required time, which must be some time in the future. This means that normalAlt will be enabled on the timer alternative once the value of the timer has increased beyond timeout. A timer contained within an alternative guard that is disabled, consumes no processor resource, until the alarm is enabled.

```
while (true) {
45
                switch ( normalAlt.priSelect() ) {
46
                  case NORMAL_SUSPEND:
47
                     suspend.read()
48
                     factor.write(scaling)
                     def suspended = true
49
50
                     println "Suspended'
51
52
                     while ( suspended ) {
                        switch ( suspendedAlt.priSelect() ) {
                                                                                1015
53
54
55
56
57
58
59
                          case SUSPENDED_INJECT:
                             scaling = injector.read()
println "Injected scaling is ${scaling}"
                             suspended = false
                             timeout = timer.read() + DOUBLE_INTERVAL
timer.setAlarm ( timeout )
                             Break
60
                          case SUSPENDED_IN:
                             def invalue = inChannel.read()
61
62
63
64
65
66
67
                             def result = new ScaledData()
                             result.original = inValue
                             result.scaled = invalue
                             outChannel.write ( result )
                             break
                        } // end-switch
//end-while
68
                     break
70
71
72
73
74
75
                  case NORMAL_TIMER:
                     timeout = timer.read() + DOUBLE_INTERVAL
timer.setAlarm ( timeout )
                     scaling = scaling * multiplier
println "Normal Timer: new scaling
                                                                  is ${scaling}"
                     break
76
77
78
79
80
81
82
                  case NORMAL_IN:
                     def invalue = inChannel.read()
                     def result = new ScaledData()
result.original = inValue
                     result.scaled = invalue *
                     outChannel.write ( result
                     break
83
84
                   //end-switch
                //end-while
85
             //end-run
86
```

Listing 5-3 The Scale Process Main Loop

The main loop of the device Listing 5-3, comprises {44-84} and is created by means of a never ending while loop. At the start of the main loop the device is presumed to be in the normal state and thus we switch on the normalAlt {45}. If none of the guards is ready the process waits until one becomes enabled. Each time an alternative is executed the guards are evaluated to determine which are enabled and then a selection is made form the ready ones according to the type of select operation undertaken.

If the enabled alternative results from an input on the suspend channel then the case NORMAL_SUSPEND will be obeyed {46}. First, the channel suspend must be read {47}, the value of which can be ignored because this is just a signal to enter the suspend state. Recall that the Controller process wrote a nominal value {15} of 0. The scale process then writes its current scaling factor to the factor channel {48}. The property suspended is defined and set true {49}. A message is printed {50} and then the loop associated with the suspended state is entered {51}. In this state the process switches on suspendedAlt {52}, which has two alternatives.

If the enabled alternative is an input on the injector channel the case SUSPENDED_INJECT is obeyed {53}. The new value of scaling is read from the injector channel {54} and a message displaying the new factor printed {55}. The value of suspended is now reset {56} to false, which will cause the

controlling while loop {51} to terminate. Because the injector input is also taken as an indication that normal operation can resume, the timer alarm can be reset {57-58}.

In the suspended state, the only other alternative that can occur, results from input on the inChannel, this causes the SUSPENED_IN case to be obeyed {60}. The channel inChannel is read into inValue {61}. A variable result of type ScaledData is defined {62}, see Listing 5-4. The device in the suspended state does not apply the scaling to any incoming data and so both the original and scaled values of result are set to inValue {63-64}. The result object is then written to outChannel {65}.

The remaining cases relate to the operation of the device in the normal state. If a timer alarm occurs the code associated with the NORMAL_TIMER case is obeyed {70}. The timer's timeout alarm is reset for the next doubling period {71-72}. The scaling is multiplied by multiplier, which is two for doubling {73} as required by the device specification and an appropriate message printed {74}. The final case deals with inputs from inChannel {76}. The value is read from inChannel into inValue {77} and placed in the original property {79} of a new result object {78}. A scaled value is placed in the scaled property of a new result object {80}, which is then written to outChannel {81}.

5.1.3 The ScaledData Object

The ScaledData object is used to pass a pair of values from the Scale process to the GPrint process see Figure 5-1. Its structure is shown in Listing 6-3.

```
87    class ScaledData implements Serializable {
88         def int original
89         def int scaled

90         def String toString () {
91              def s = " " + original + "\t\t" + scaled
92              return s
93         }
94     }
```

Listing 5-4 The ScaledData Object

The properties of the object; original and scaled are defined {88, 89} and then a toString() method is defined {90-93} that is used when the object is printed.

More importantly, this is the first instance of user defined objects being communicated between processes. The first aspect to notice is there are no public data manipulation methods, other than implicit getters and setters that are created by the Groovy environment automatically, because in the parallel environment we encapsulate the data so that it is processed only within processes. It is not possible for one process to access another object's properties in another process to modify its state by calling public methods.

Concurrent processes pass object references over channels and thus a sending process has to guarantee that once it has written an object to a channel it does not modify that object in any way. This is most easily achieved by defining a new object instance for each write operation, see {62, 78}. In some cases, it may be necessary, for memory management reasons, to reuse an object and to ensure that a written object is not overwritten a deep copy is taken. An interface JCSPCopy which contains a single method copy() is provided in the org.jcsp.groovy package to facilitate this requirement. The programmer has to write the code to achieve the deep copy of the object. This can then be applied recursively to any nested objects.

If an object is to be passed between networked processes then a copy of the object is passed between the processes and so the object must implement the interface serializable. In this case it is not necessary to undertake the method copy because the serialization mechanism achieves this requirement.

5.1.4 Exercising the Scale Device Network

Listing 5-5 gives the script that implements the process network shown in Figure 5-1.

```
95
96
97
        def data = Channel.createOne2One()
        def timedData = Channel.createOne2One()
def scaledData = Channel.createOne2One()
98
        def oldScale = Channel.createOne2One()
99
100
        def newScale = Channel.createOne2One()
        def pause = Channel.createOne2One()
101
        def network = [ new GNumbers ( outChannel: data.out() ),
                           new GFixedDelay (delay: 1000
102
103
                                                 inChannel: data.in(),
104
                                                 outChannel: timedData.out() ),
                           105
106
                                          factor: oldScale.out(),
                                          suspend: pause.in(),
injector: newScale.in(),
scaling: 2),
110
                           new Controller (testInterval: 7000
                                                computeInterval: 700
                                                factor: oldScale.in(),
suspend: pause.out(),
injector: newScale.out() )
115
                           new GPrint (inChannel: scaledData.in(), heading: "Original Sc
                                                                         Scaled'
                                           delay: 0)
119
120
        new PAR ( network ).run()
```

Listing 5-5 Script to Exercise the Scale Device

All the output appears in the Eclipse console window with the messages from the Scale process intermingled with those from the output of the original and scaled data which appear in GPrint. The delay property {123} of GPrint is set to 0 so that any output is produced immediately. There is sufficient delay within the system caused by the GFixedDelay process to observe the process interactions.

5.2 Managing A Circular Queue Using Alternative Pre-conditions

A *queue* is a common data structure used in many applications. A number of cases have to be considered as follows.

- 1. data can only be put into the queue if there is space in the queue
- 2. data can only be taken from the queue if the queue is not empty

In a sequential implementation these states have to be tested before the queue can be manipulated and dealing with the situations where either a put or get to or from the queue cannot be undertaken can be problematic. A parallel implementation is much easier to design and specify because we can use an alternative with pre-conditions to ensure that operations only take place when it is safe. Figure 5-2 shows the basic structure that will be used to explain the operation of a queue.

The QProducer process puts a sequence of integers to the Queue process, where they are stored in a wrap-around List. The QConsumer process attempts to get data from the Queue, which if there is data available, is received by the process.




Figure 5-2 The Queue Process Network

5.2.1 QProducer and QConsumer Processes

The source of the QProducer process is given in Listing 5-6.

```
121
        class QProducer implements CSProcess {
           def ChannelOutput put
def int iterations = 100
122
123
           def delay = 0
124
125
           void run () {
126
             def timer = new CSTimer()
println "QProducer has started"
127
128
                  ( i in 1 .. iterations ) {
129
130
                put.write(i)
                timer.sleep (delay)
131
132
             put.write(null)
133
134
```

Listing 5-6 The OProducer Process script

The timer {126} is used to create a delay {130} between each write {129} to the put channel. A sequence of integers from 1 up to iterations {123} is output on the put channel. It should be noted that the write on the put channel may be delayed {129} if the queue has no available space. Once all the values have been written to the put channel a null value is also written (132) to indicate that processing has finished. This will be used to terminate the subsequent Queue and QConsumer processes.

The QConsumer process is specified in Listing 5-7. The use of the timer and associated delay {138, 140, 147} is the same as in QProducer. A Boolean running is defined {142} and is used to control the main loop of the process. The main loop of the process {143-151} initially writes a signal value of 1 on the get channel. The writing of this signal {144} may be delayed if the queue contains no available data. A value is read from the receive channel {145} into the object v. This read operation will take place immediately. The value that has been read is printed {146} after which the process may be delayed {147}. If the value read is null {148} then running is set to false {149} and the process will terminate at the next iteration of the while loop {143}.

```
135
          class QConsumer implements CSProcess {
             def ChannelOutput get
def ChannelInput receive
def long delay = 0
136
137
138
139
             void run () {
140
               def timer = new CSTimer()
println "QConsumer has started"
141
142
                def running = true
143
               while (running) {
144
                   get.write(1)
                  def v = receive.read()
println "QConsumer has read ${v}"
145
146
                  timer.sleep (delay)
if ( v == null ) {
147
148
149
                       running = false
150
151
152
               }
            }
```

Listing 5-7 The QConsumer Process

5.2.2 The Queue Process

The source for the Queue process is shown in Listing 5-8. The channel properties are defined {155-157} corresponding to Figure 5-2 and the size of the queue is specified in the property elements and is initially 5 {158}. The alternative associated with the Queue process is defined as qAlt, which has guards comprising the put and get channels {160}. A Boolean array, preCon, which has the same number of elements as there are guards in qAlt, is defined {161}. Two constants PUT and GET are defined {162, 163} that are used to index the preCon array and also to identify the cases in the switch statement associated with identifying the selected guard in the alternative.

The array precon is used to record whether or not a new element can be put into the queue storage and similarly whether an element is available. Initially, therefore precon[PUT] is set true {164} because there is bound to be space for a new element in the queue data structure because it must be empty. Similarly, precon[GET] is set false {165} because there is no data available in the queue. The List data {166} provides the storage for the circular queue structure. The properties count, front and rear {167-169} record the state of the queue storage in terms of the number of data values in the queue, the location into which data can be added and removed from the queue respectively. The process is implemented as a loop {171-192}, which is controlled by a Boolean running {170} that is set false when a null value is communicated to the QConsumer process {183-185}.

The property index {172} indicates the alternative guard that has been selected. In order to be selected a guard must have its associated preCon element set to true and its channel must be enabled to read an input. Note how the pre-condition array is passed as a parameter to the alternative priSelect method {172}. A choice is then made depending upon which guard has been selected.

In the case of PUT the value read from put is placed in data[front] {175}. A message is then printed {176} and then the values of count and front are updated appropriately {177-178}. When GET is selected, the signal communication on the get channel is read and ignored {181}. The value in data[rear] is then written to channel receive {193}. The value in data[rear] is then tested to determine whether the Queue process should terminate {183-185}. After which, the values of count and rear are updated {186-187}. At the end of each loop of the queue process, the values stored in the elements of the preCon array are updated based upon the relative values of count and elements {190, 191}.

```
154
        class Queue implements CSProcess {
155
156
           def ChannelInput
def ChannelInput
                                  put
                                  get
           def ChannelOutput receive
157
158
           def int elements = 5
159
           void run() {
160
             def qAlt = new ALT ( [ put, get ] )
             def preCon = new boolean[2]
def PUT = 0
161
162
             def GET = 1
163
             preCon[PUT] = true
164
             preCon[GET] = false
165
             def data = []
def count = 0
def front = 0
166
167
168
             def rear = 0
169
170
             def running = true
171
             while (running) {
172
                def index = qAlt.priSelect(preCon)
173
                switch (index) {
174
                   case PUT:
                     data[front] = put.read()
println "Q: put ${data[front]} at ${front}"
front = (front + 1) % elements
175
176
177
178
                     count = count + 1
                     Break
180
                   case GET:
181
                     get.read()
                     receive.write( data[rear])
if (data[rear] == null) {
182
183
                            running = false
184
185
186
                     rear = (rear + 1) \% elements
187
188
                     count = count - 1
                     break
189
                }
                preCon[PUT] = (count < elements)</pre>
190
                preCon[GET] = (count > 0)
191
192
             println "Q finished"
193
194
```

Listing 5-8 The Queue Process Definition

The benefit of this alternative based formulation is that the pre-condition array modifies the behaviour of its underlying mechanism. Thus if the queue is full then preCon[PUT] is false and even if there is a communication on the put channel it will not be permitted. Similarly, if preCon[GET] is false then no signal on the get channel can be read, even if QConsumer has tried to write to it.

5.5 Summary

This chapter has explored the alternative mechanism together with its associated pre-condition Boolean array. It has shown by means of an example based upon a realistic system and one found in many program development applications that alternative has the ability to capture many aspects of real world systems and to provide a flexible means of modelling such systems.

5.6 Exercises

1. The accompanying web site contains a script, called TestQ, in package ChapterExercises/src/c5 to run the queue network. The delays associated with QProducer and QConsumer can be modified. By varying the delay times demonstrate that the system works in the manner expected. Correct operation can be determined by the QConsumer process outputting the messages "QConsumer has

read 1" to "QConsumer has read 50" in sequence. What do you conclude from these experiments?

2. Reformulate the scaling device so that it uses pre-conditions rather than nested alternatives. Which is the more elegant formulation? Why?

