www.MINEPORTAL.in

(All Mining Solutions)

DOWNLOAD MINEPORTAL APP FROM GOOGLE PLAY STORE

- > ONLINE TEST SERIES FOR
- DGMS COAL/METAL FIRST & SECOND CLASS
- GATE MINING
- COAL INDIA EXAMS
- OTHER PSUs MINING EXAMS
- > FREE STUDY MATERIAL-MINEPORTAL NOTES & USER NOTES
- > MINING VIDEO LECTURES
- > DISCUSSION FORUM
- > WHATSAPP CHAT SUPPORT FOR MINING EXAMS & QUERY RELATED TO MINING

CALL/WHATSAPP-8804777500

VISITING SITE- www.MINEPORTAL.in

Facebook- www.fb.com/mineportal.in

EMAIL- INFO@MINEPORTAL.IN



TOPIC-BLASTHOLE RAISING METHOD


www.MINEPORTAL.in

BLASTHOLE RAISING METHOD

LONG-HOLE RAISING

- Long-parallel holes
- Cylindrical or burn cut pattern
- Hole length and inclination
- Both level should accessible
- Drilled from top level to bottom

- Marking the raise
- Equipment installation
- Drilling
- Raise correlation



- Blowing and plugging the holes
- Charging and blasting
- length of round that is usually, 2.5 to 3 m
- stemming material
- explosive ANFO with suitable primer/booster
- delay detonators

Limitations

- This technique can be applied only if raise site can be accessed from both the levels.
- Raises upto 40 m lengths and 45° inclinations can be driven.
- Accurate drilling and proper blasting is the key to the success of this method.
- Disturbed ground with joints, fissures etc. may result frequent jamming of drill rods and bits.

Advantages

- Safety
- Productivity
- Better working conditions
- Better raise configuration
- Flexibility and simplicity
- Economical

BLASTHOLE RAISING METHOD

DROP RAISING

- It is advance version of long hole raising tech.
- vertical crater retreat (VCR)
- crater theory are spherical or its geometric equivalent
- stressed zone of elliptical shape

VCR concept


- The term 'crater' in blasting terminology is applied for creation of a surface cavity in a rock mass as result of detonating an explosive charge into it.
- It gained importance in surface blasting operations, and in the recent past, in underground blasting operations too.

- Spherical charge is defined as the one which is having a length to diameter (L: D) ratio to 1:4 or less, and up to, but not exceeding a L:D 6:1.
- Thus, for holes of 165 mm dia. a charge of 990 mm length would constitute a spherical charge.


- The charge is fired in the upward direction, enabling crater to form towards a horizontal free face.
- In the underground mining, a spherical charge is blasted in the down ward direction towards a free face.
- The blasting operation when carried out in this manner, the method is known as Vertical Crater Retreat (VCR).

- A crater is consists of 5 holes, one at the center and rest four at the corners of a raise.
- Crater theory is valid for the central hole only, and for the rest of the holes, the charge depth increases from 10–20 cm between each hole,

Charge length, $l = 6 \times d$ d is big-blast-hole diameter in mm



Techniques to plug bottoms of bigblast holes



Optimum charge depth is 50% of the critical depth; $L_{opt} = 0.5 \times L_{crit}$

$$L_{crit} = S x Q^{1/3}$$

Charge weigh $Q = 3 x d^3 x \pi x \rho / 2$ (in kg); ρ explosive density in gm/cc

Thus,
$$L_{opt} = 0.5 \times S \times Q^{1/3}$$

S is the Strain Energy Factor usually 1.5 but depends upon explosive and type of rock.

Call/Whatsapp-8804777500 www.MINEPORTAL.in www.fb.com/mineportal.in

- Drilling: Down-the-hole (DTH)
- Blocking the blast holes
 - As in the conventional crater formation the charge covers the bottom of hole for some length and rest of the hole length remains empty.
- Inverting this figure or the scenario, it will reveal that the charge should be placed at a certain height (which can yield the desirable results) from the free face, and hence, blocking the hole at a certain height above the free face is essential.

- Blasting: amount depends upon its density and ratio of hole dia. to length (spherical charge)
- For example for a 165 mm dia. hole, the charge amount of an explosive of 1.40gm/cm3 density works out to be 27.2 kg;
- Hence, as per this calculation half the weight of the explosive is first dropped or charged, then booster primer with proper delay is lowered down.
- The rest of the explosive i.e. the other half is then charged.
 The hole is then stemmed, for a length of 1–2 m or so, using suitable material.
- The same procedure is repeated while charging rest of the holes.

• Performance:

• Scope, advantages and limitations: