


Пиринг VPC

Защитите свои сервисы с помощью пиринга Virtual Private Cloud

Вы используете пиринг виртуальных частных облаков (Virtual Private Cloud, VPC), чтобы обеспечить доступ к сервисам Tiger Cloud только через защищенную инфраструктуру AWS. Это сокращает потенциальное количество векторов атак и повышает уровень безопасности.

Архитектура изоляции данных обеспечивает высокозащищенное соединение между вашими приложениями и Tiger Cloud.



Приложения ваших клиентов работают в вашем VPC AWS Customer, а сервисы Tiger Cloud — в защищенном VPC Tiger Cloud. Вы контролируете безопасную связь между приложениями в вашем VPC и вашими сервисами с помощью выделенного VPC Peering. AWS PrivateLink, соединяющий VPC Tiger Cloud с выделенным VPC Peering, обеспечивает тот же уровень защиты, что и прямое подключение AWS PrivateLink. Он позволяет инициировать обмен данными только из вашего VPC Customer со службами, работающими в VPC Tiger Cloud. Tiger Cloud не может инициировать обмен данными с вашим VPC Customer.

Чтобы настроить это безопасное соединение, сначала создайте пиринговое VPC с помощью AWS PrivateLink в Tiger Console. После того как вы подтвердите и настроите пиринговое соединение с VPC вашего клиента, используйте группы безопасности AWS, чтобы ограничить доступ приложений в VPC вашего клиента к пиринговому VPC. Последний шаг — подключение отдельных сервисов к пиринговому VPC в Tiger Console.

- Вы создаете каждый пиринговый VPC на [уровне проекта Tiger Cloud](#).

- Вы **можете подключить**:

- До 50 клиентских VPC в пиринговом VPC.
- Один сервис Tiger Cloud в одном пиринговом VPC. Сервис и пиринговый VPC

На этой странице



Обзор

- Несколько сервисов Tiger Cloud в одном пиринговом VPC.

- Вы **не можете одновременно подключить** сервис Tiger Cloud к нескольким VPC Peering.

Количество VPC Peering, которые вы можете создать в своем проекте, зависит от вашего [тарифа](#). Если вам нужен еще один VPC Peering, обратитесь в службу поддержки по адресу support@tigerdata.com или измените тарифный план в [Tiger Console](#).

✔ Предварительные условия для этой процедуры

Чтобы выполнить эти действия, вам понадобятся:

- [Сервис Tiger Cloud](#).
- Разрешения в вашей учетной записи AWS для:
 - Принять запросы на пиринг VPC
 - Настроить правила таблицы маршрутизации
 - Настроить правила группы безопасности и брандмауэра

Настройка защищенного соединения между Tiger Cloud и AWS

Чтобы подключиться к сервису Tiger Cloud с помощью пиринга VPC, ваши приложения и инфраструктура уже должны работать в VPC Amazon Web Services (AWS). Вы можете подключить свой VPC к любому региону AWS. Однако ваш пиринговый VPC должен находиться в одном из [регионов, поддерживаемых Cloud](#).


Этапы создания защищенного соединения между сервисами Tiger Cloud и вашей инфраструктурой AWS:

1. [Создайте пиринговый VPC в Tiger Console](#)
2. [Завершите подключение VPC в AWS](#)
3. [Настройте группы безопасности в AWS](#)
4. [Прикрепите сервис Tiger Cloud к пиринговому VPC](#)


Создание пирингового VPC в Tiger Console

Create the VPC and the peering connection that enables you to securely route traffic between Tiger Cloud and your Customer VPC in a logically isolated virtual network.

На этой странице > Обзор



2 Choose your region and IP range, name your VPC, then click Create VPC



The IP ranges of the Peering VPC and Customer VPC should not overlap.

3 For as many peering connections as you need

a. In the VPC Peering column, click Add.

На этой странице > Обзор

Services Security Exporters Activity Settings CLI / MCP Members

Security

VPC Peering (AWS)

Private Endpoints

IP Allow Lists

Authentication

VPC

Name	VPC ID	Provisioned ID
vpc-97634	10366	

Peering connection

Enter your AWS VPC's connection details. After the peering is complete, you need to update your [firewall rules](#).

VPC's name	Region	Network
vpc-97634	eu-central-1	10.0.0.0/24

AWS Account ID

Enter your account ID

VPC ID / TGW ID

Enter your VPC/TGW ID

[How to configure a peering?](#)

Your account CIDRs (Optional)

10.0.0.0 /24

Cancel Add connection

- You **can attach**:
 - Up to 50 Customer VPCs to a Peering VPC.
 - A Tiger Cloud service to a single Peering VPC at a time. The service and the Peering VPC must be in the same AWS region. However, you can peer a Customer VPC and a Peering VPC that are in different regions.
 - Multiple Tiger Cloud services to the same Peering VPC.
- You **cannot attach** a Tiger Cloud service to multiple Peering VPCs at the same time.

The number of Peering VPCs you can create in your project depends on your [pricing plan](#). If you need another Peering VPC, either contact support@tigerdata.com or change your pricing plan in [Tiger Console](#).

Tiger Cloud sends a peering request to your AWS account so you can [complete the VPC connection in AWS](#).

Complete the VPC connection in AWS

When you receive the Tiger Cloud peering request in AWS, edit your routing table to match the IP Range and CIDR block between your Customer and Peering VPCs.

When you peer a VPC with multiple CIDRs, all CIDRs are added to the Tiger Cloud rules automatically. After you have finished peering, further changes in your VPC's CIDRs are not detected automatically. If you need to refresh the CIDRs, recreate the peering connection.

На этой странице >

Обзор

- 1 **In AWS > VPC Dashboard > Peering connections, select the peering connection request from Tiger Cloud**
Copy the peering connection ID to the clipboard. The connection request starts with pcx-.
- 2 **In the peering connection, click Route Tables, then select the Route Table ID that corresponds to your VPC**
- 3 **In Routes, click Edit routes**
You see the list of existing destinations.

Edit routes

На этой странице >

Обзор

10.1.200.0/24

local

Q local

10.0.200.0/24

local

Q local

Q 10.0.0.0/24

X

Peering

Q pcx-l

Q 0.0.0.0/0

X

Internet

Q igw-

Add route

If you do not already have a destination that corresponds to the IP range / CIDR block of your Peering VPC:

- Click Add route, and set: Destination: the CIDR block of your Peering VPC. For example: 10.0.0.7/17. Target: the peering connection ID you copied to your clipboard.
- Click Save changes.

Network traffic is secured between your AWS account and Tiger Cloud for this project.

Set up security groups in AWS

Security groups allow specific inbound and outbound traffic at the resource level. You can associate a VPC with one or more security groups, and each instance in your VPC may belong

to a different set of security groups. The security group choices for your VPC are:

- Create a security group to use for your Tiger Cloud VPC only.
- Associate your VPC with an existing security group.

На этой странице > Обзор

to create a security group specific to your Tiger Cloud peering VPC.

1 In AWS > VPC Dashboard > Security Groups, click **Create security group**

2 Enter the rules for this security group

VPC > Security Groups > Create security group

Create security group [Info](#)

Security group name [Info](#)

MyWebServerGroup

Name cannot be edited after creation.

Description [Info](#)

Allows SSH access to developers

VPC [Info](#)

Q vpc- X

Inbound rules [Info](#)

This security group has no inbound rules.

Add rule

Outbound rules [Info](#)

Type Info	Protocol Info	Port range Info	Destination Info	Description - optional Info	
All traffic ▼	All	All	Custom ▼ Q 0.0.0.0/0 X		Delete

Add rule

- VPC: select the VPC that is peered with Tiger Cloud.
- Inbound rules: leave empty.
- Outbound rules:
 - Type: Custom TCP
 - Protocol: TCP

- Port range: 5432
- Destination: Custom
- Info: the CIDR block of your Tiger Cloud Peering VPC.

На этой странице > Обзор

3 Click **Add rule**, then click **Create security group**

Attach a Tiger Cloud service to the peering VPC

Now that Tiger Cloud is communicating securely with your AWS infrastructure, you can attach one or more services to the Peering VPC.

After you attach a service to a Peering VPC, you can only access it through the peered AWS VPC. It is no longer accessible using the public internet.

- 1 In **Tiger Console > Services** select the service you want to connect to the Peering VPC
- 2 Click **Operations > Security > VPC**
- 3 Select the VPC, then click **Attach VPC**

Your service is now securely communicating with your AWS account inside a VPC.

Migrate a Tiger Cloud service between VPCs

To ensure that your applications continue to run without interruption, you keep service attached to the Peering VPC. However, you can change the Peering VPC your service is attached to, or disconnect from the Peering VPC and enable access to the service from the public internet.

Note

Tiger Cloud uses a different DNS for services that are attached to a Peering VPC. When you migrate a service between public access and a Peering VPC, you need to update

your connection string.

На этой странице > Обзор

2 **Click Operations > Security > VPC**

3 **Select the VPC, then click Attach VPC**

Migration takes a few minutes to complete and requires a change to DNS settings for the service. The service is not accessible during this time. If you receive a DNS error, allow some time for DNS propagation.

< **PREVIOUS**
Connect with a stricter SSL mode

NEXT >
AWS Transit Gateway

Privacy Preferences