



НА ЭТОЙ СТРАНИЦЕ



Документы > Установка > Серверный Linux-контейнер Octopus

Серверный Linux-контейнер Octopus


Запуск Octopus Server в контейнере позволяет избежать установки Octopus непосредственно на вашу инфраструктуру и упрощает процесс запуска Octopus до одной команды. Чтобы обновиться до последней версии Octopus, достаточно запустить новый контейнер с новой версией образа.

Мы уверены в надежности и производительности Linux-контейнера Octopus Server. [Octopus Cloud](#) запускает Linux-контейнер Octopus Server в кластерах AKS в Azure. Но чтобы использовать Linux-контейнер Octopus Server в Octopus Cloud, нам пришлось принять ряд проектных решений и углубить свои знания о концепциях Docker.

Мы рекомендуем использовать контейнер Octopus Server Linux, если вас устраивают **все** следующие условия:

- Вы знакомы с концепциями Docker, в частности с отладкой контейнеров, монтированием томов и сетевыми технологиями.
- Вы хорошо разбираетесь в одной из базовых технологий хостинга для контейнеров Docker: Kubernetes, ACS, ECS, AKS, EKS или в самом Docker.
- Вы понимаете, что Octopus Deploy — это приложение с отслеживанием состояния, а не без него, и требует дополнительного мониторинга.

Мы публикуем `linux/amd64` образы Docker для каждой версии Octopus Server, и они доступны на [DockerHub](#).



На этой странице описано, как запустить Octopus Server в Linux-контейнере.

Примечание: Если вы используете Linux-контейнеры на компьютере с Windows, убедитесь, что вы [перешли на Linux-контейнеры](#).

Начало работы

Существует несколько вариантов конфигурации, но ниже приведен простой пример запуска Linux-контейнера Octopus Server:

```
docker run --interactive --detach --name OctopusDeploy --  
publish 1322:8080 --env ACCEPT_EULA="Y" --env  
DB_CONNECTION_STRING="..." octopusdeploy/octopusdeploy
```



- Мы запускаем контейнер в автономном режиме с помощью `--detach`, чтобы он работал в фоновом режиме.
- Аргумент `--interactive` гарантирует, что STDIN останется открытым, что необходимо, поскольку именно закрытия `Octopus.Server.exe` ожидает запущенный процесс.
- Установка `--name OctopusServer` позволяет присвоить контейнеру легко запоминающееся имя. Это необязательно, но мы рекомендуем указать значимое для вас имя, чтобы при необходимости было проще выполнять действия с контейнером.
- Использование `--publish 1322:8080` сопоставляет порт контейнера 8080 с 1322 на хосте, чтобы экземпляр Octopus был доступен за пределами этого



В этом примере мы запускаем образ `octopusdeploy/octopusdeploy` без явного тега, используя `latest`-версию Octopus Server, опубликованную на DockerHub.

Запуск Octopus Server в контейнере

This section walks through some of the different ways you can run the Octopus Server Linux Container, from `docker compose` to using a full orchestration service such as Kubernetes:

- [Octopus Server Container with Docker Compose](#)
- [Octopus Server Container with systemd](#)
- [Octopus Server Container in Kubernetes](#)

Migration

You may already have Octopus Server running on Windows Server or in a Windows container you wish to run in a Linux Container. This section walks through the different options and considerations for migrating to an Octopus Server Linux Container.

- [Migrate to Octopus Server Linux Container from Windows Server](#)
- [Migrate to Octopus Server Linux Container from Windows Container](#)

Configuration

Support for authentication providers differs depending on how you host Octopus Server. Please see our [authentication provider compatibility section](#) to ensure any existing authentication provider is supported when running Octopus in a Linux Container.

When running an Octopus Server Image, you can supply the following values to configure the running Octopus Server instance.



If you do not specify a master key when Octopus is first run, Octopus will generate one for you, which you must pass as the `MASTER_KEY` environment variable with each subsequent run. However, it is also possible to create your own master key for Octopus to use when configuring the database.

Master keys must be a 128 bit string encoded in base 64. You can generate a random string to use as the master key with the command:

```
openssl rand 16 | base64
```



Environment variables

Read the Docker [docs](#) about setting environment variables.

Name	Description
<code>DB_CONNECTION_STRING</code>	Connection string to the database to use
<code>MASTER_KEY</code>	The Master Key to connect to an existing database. If not supplied, and the database does not exist, it will generate a new one. The Master Key is mandatory if the database exists.
<code>OCTOPUS_SERVER_BASE64_LICENSE</code>	Your license key for Octopus Deploy. If left empty, it will try to create a free license key for use
<code>ADMIN_USERNAME</code>	The admin user to create for the Octopus Server
<code>ADMIN_PASSWORD</code>	The password for the admin user for the Octopus Server



account

TASK_CAP

Sets the task cap for this node. If not specified, the default is 5.

DISABLE_DIND

The Linux image will by default attempt to run Docker-in-Docker to support [execution containers for workers](#). This requires the image to be launched with [privileged permissions](#). Setting DISABLE_DIND to Y prevents Docker-in-Docker from being run when the container is booted.

Exposed container ports

Read Docker [docs](#) about exposing ports.

Port	Description
8080	Port for API and HTTP portal
443	SSL Port for API and HTTP portal
10943	Port for Polling Tentacles to contact the server
8443	Port for gRPC clients to contact the server

Volume mounts

Read the Docker [docs](#) about mounting volumes.



metadata.json exists, then migrator Import takes place on startup

or container

/repository

Package path for the built-in package repository

Shared storage

/artifacts

Path where artifacts are stored

Shared storage

/taskLogs

Path where task logs are stored

Shared storage

/eventExports

Path where event audit logs are exported

Shared storage

/cache

Path where cached files e.g., signature and delta files (used for package acquisition), are stored

Host filesystem or container

Note: We recommend using shared storage when mounting the volumes for files that must be shared between multiple octopus container nodes, e.g., artifacts, packages, task logs, and event exports.

Upgrading

When the volumes are externally mounted to the host filesystem, upgrades between Octopus versions are much easier. We can picture the upgrade process with a container as being similar to [moving a standard Octopus Server](#) since containers, being immutable, don't themselves get updated.

Similar to moving an instance, to perform the container upgrade, you will need the Master Key you used to set up the original database. You can find the Master Key for an Octopus Server in a container with the container exec command:

```
> docker container exec <container name/ID>  
Octopus/Octopus.Server show-master-key --console --instance  
OctopusServer
```





When you have the Master Key, you can stop the running Octopus Server container instance (delete it if you plan on using the same name) and run *almost* the same command as before, but this time, pass in the Master Key as an environment variable and reference the new Octopus Server version. When this new container starts up, it will use the same credentials and detect that the database has already been set up and use the Master Key to access its sensitive values:

```
docker run --interactive --detach --name OctopusServer --  
publish 1322:8080 --env DB_CONNECTION_STRING="..." --env  
MASTER_KEY "5qJcW9E6B99teMmrOzaYNA=="  
octopusdeploy/octopusdeploy
```



The standard backup and restore procedures for the [data stored on the filesystem](#) and the connected [SQL Server](#) still apply as per regular Octopus installations.

Troubleshooting

If you're having trouble with the Octopus Server Linux Container, please use our [troubleshooting guide](#).

Learn more

- [Docker blog posts](#) - [Linux blog posts](#) - [Introducing the Octopus Server Linux Docker image](#) - [Octopus Deploy on Docker Hub](#) - [Octopus Tentacle on Docker Hub](#)

Help us continuously improve

Please let us know if you have any feedback about this page.

Send feedback



Octopus Deploy

Документы

Light



Dark

Previous article



**Troubleshoot Octopus
installation issues**

Next article



**Octopus Server with Docker
Compose on Linux**

PLATFORM

Continuous

Delivery

platform

Hub

AI tools

Enterprise

Support for

Argo

Codefresh CI

RESOURCES

Documentation

What's new

Publications

Blog

DevOps

handbook

OUR COMPANY

About us

Careers

Roadmap

Investor

relations

Brand

guidelines

HELP AND

SUPPORT

Contact

Sales

Support

Upgrade

Security and

legal

Community

Slack

Our awards



Sign up to our newsletter

Email:

Subscribe

Marketplaces

Azure
marketplace

AWS
marketplace



Octopus Deploy

Документы

Light



Dark

Deploy Policy