PC多媒体API文档

概览

播放器负责音视频解码、播放功能,底层依赖于p2p库的推流及音视频同步功能。

类型定义

• 呼叫类型

```
public class CallTypeEnum {
   public final static int CONN_TYPE_VIDEO_CALL = 0; //视频呼叫,双向音视频
   public final static int CONN_TYPE_MONITOR = 1; //监控,单向视频,双向音频(对讲)
   public final static int CONN_TYPE_PLAY_REC_FILE = 2; //录像回放
}
```

• 播放器状态类型

```
public class PlayerStateEnum {
   public final static int STATE_IDLE = 0;
                                             //播放器初始状态
   public final static int STATE_INITIALIZED = 1; //已经初始化
   public final static int STATE_PREPARING = 2; //准备中
   public final static int STATE_READY = 3;
                                             //准备完毕
   public final static int STATE_LOADING = 4;
                                             //加载
   public final static int STATE_PLAY = 5;
                                             //播放状态
   public final static int STATE_PAUSE = 6;
                                             //暂停
   public final static int STATE_STOP = 7;
                                             //停止
}
```

• 编码参数类型

```
public class AVConstants {
   /**
     * 音频类型
    public static final int AUDIO_TYPE_PCM = 0;
    public static final int AUDIO_TYPE_G711A = 1;
    public static final int AUDIO_TYPE_G711U = 2;
    public static final int AUDIO_TYPE_PT_G726 = 3;
    public static final int AUDIO_TYPE_PT_AAC = 4;
    public static final int AUDIO_TYPE_PT_AMR = 5;
    public static final int AUDIO_TYPE_PT_ADPCMA = 6;
    public static final int AUDIO_TYPE_MAX = 7;
    /**
    * 音频采样率
    */
    public static final int AUDIO_SAMPLE_RATE_8000 = 8000; //!< 8K samplerate</pre>
    public static final int AUDIO_SAMPLE_RATE_11025 = 11025; //!< 11.025K</pre>
samplerate
```

```
public static final int AUDIO_SAMPLE_RATE_12000 = 12000; //!< 12K</pre>
samplerate
    public static final int AUDIO_SAMPLE_RATE_16000 = 16000; //!< 16K</pre>
samplerate
    public static final int AUDIO_SAMPLE_RATE_22050 = 22050; //!< 22.050K</pre>
samplerate
    public static final int AUDIO_SAMPLE_RATE_24000 = 24000;
                                                             //!< 24K
samplerate
    public static final int AUDIO_SAMPLE_RATE_32000 = 32000;
                                                             //!< 32K
samplerate
    public static final int AUDIO_SAMPLE_RATE_44100 = 44100;
                                                             //! < 44.1 K
samplerate
    public static final int AUDIO_SAMPLE_RATE_48000 = 48000;
                                                             //!< 48K
    public static final int AUDIO_SAMPLE_RATE_64000 = 64000;
samplerate
    public static final int AUDIO_SAMPLE_RATE_96000 = 96000; //!< 96K</pre>
samplerate
    /**
    * 音频声音模式
    */
                                                          /*mono*/
    public static final int AUDIO_SOUND_MODE_MOMO = 0;
    public static final int AUDIO_SOUND_MODE_STEREO = 1;
                                                          /*stereo*/
    public static final int AUDIO_SOUND_MODE_NONE = 2;
    /**
     * 音频位宽
     */
    public static final int AUDIO_BIT_WIDTH_8 = 0;  /* 8bit width */
    public static final int AUDIO_BIT_WIDTH_16 = 1;  /* 16bit width*/
    public static final int AUDIO_BIT_WIDTH_32 = 2;  /* 32bit width*/
    public static final int AUDIO_BIT_WIDTH_NONE = 3;
    /**
     * 音频每帧采样数
     */
    public static final int AUDIO_SAMPLE_NUM_80 = 80;
                                                             //!<
    public static final int AUDIO_SAMPLE_NUM_160 = 160;
                                                              //!<
    public static final int AUDIO_SAMPLE_NUM_320 = 320;
                                                               //!<
    public static final int AUDIO_SAMPLE_NUM_480 = 480;
                                                               //!<
    public static final int AUDIO_SAMPLE_NUM_1024 = 1024;
                                                                //!<
    public static final int AUDIO_SAMPLE_NUM_2048 = 2048;
                                                                //!<
    /**
     * 视频类型
     */
    public static final int VIDEO_TYPE_NONE = 0;
                                                     //!<
    public static final int VIDEO_TYPE_H264 = 1;
                                                     //!<
    public static final int VIDEO_TYPE_MPEG4 = 2;
                                                     //!<
    public static final int VIDEO_TYPE_JPEG = 3;
                                                     //!<
    public static final int VIDEO_TYPE_MJPEG = 4;
                                                     //!<
    public static final int VIDEO_TYPE_H265 = 5;
                                                    //!<
}
```

播发器功能接口

1. 初始化播放器数据源

```
/**
* 初始化播放器数据源
*
* @param deviceId 设备id
* @param callType 类型参考CallTypeEnum
* @param definition 类型参考枚举DEFINITION
*/
void setDataResource(uint64_t deviceId, int callType, int definition);
```

2. 设置音视频渲染组件

```
/**

* 设置音视频渲染组件

*

* @param view 视频渲染组件

*/

void setVideoView(IotVideoView view);
```

3. 设置视频编码器

```
/**

* 设置视频编码器

* 说明: 音视频语音对讲时可配置,

* 如果设置,播放器视频编码将采用用户自定义的视频编码器。

* 如果不设置,将采用内置的编码器。

* @param encoder 视频编码器

*/
void setVideoEncoder(IVideoEncoder encoder)
```

4. 设置视频解码器

```
/**
 * 设置视频解码器
 *
 * 说明: 如果设置,播放器视频解码将采用用户自定义的视频解码器。
 * 如果不设置,将采用内置的解码器。
 * @param decoder 视频解码器
 */
void setVideoDecoder(IVideoDecoder decoder);
```

5. 设置音频编码器

```
/**

* 设置视频编码器

* 说明: 音视频语音对讲时可配置,

* 如果设置,播放器视频编码将采用用户自定义的视频编码器。

* 如果不设置,将采用内置的编码器。

* @param encoder 视频编码器

*/
void setVideoEncoder(IVideoEncoder encoder)
```

6. 设置音频解码器

```
/**

* 设置视频解码器

*

* 说明: 如果设置,播放器视频解码将采用用户自定义的视频解码器。

* 如果不设置,将采用内置的解码器。

* @param decoder 视频解码器

*/

void setVideoDecoder(IVideoDecoder decoder);
```

7. 设置视频渲染

```
/**
 * 设置视频渲染
 *
 * 说明: 如果用户自定义视频帧渲染可以设置该接口
 * 解码的视频帧(yuv420格式)已回调的形式返回
 */
void setVideoRender(IVideoRender listener);
```

8. 设置音频渲染

```
/**
 * 设置音频渲染
 *
 * 说明: 如果用户自定义音频渲染可以设置该接口
 * 解码的音频帧(PCM格式)已回调的形式返回
 */
void setAudioRender(IAudioRender listener);
```

9. 准备播放

```
/**
 * 准备播放
 *
 * 说明: prepare回调可以通过设置setPreparedListener进行监听
 */
void prepare();
```

10. 开始播放

```
/**
    * 开始播放
    *
    */
void play();
```

11. 停止播放

12. 释放资源

```
/**
    * 释放
    *
    * 说明:播放器使用完毕需要释放
    */
void release();
```

13. 静音状态判断

```
/**

* 静音

* @return true==静音, false==非静音

*/
boolean isMute();
```

14. 静音状态设置

```
/**

* 设置静音

* @param on true==静音, false==非静音

*/

void mute(boolean on);
```

15. 开始录像

```
/**
 * 录像
 *
 * @param path 录像文件路径
 * @param listener 录像回调
 */
void startRecord(String path, final IResultListener listener);
```

16. 停止录像

```
/**
        * 停止录像
        *
        */
void stopRecord();
```

17. 截图

```
/**
 * 视频画面截图
 *
 * @param path 截图文件路径
 * @param listener 截图回调
 */
void snapShot(String path, final IResultListener listener);
```

18. 获取播放状态类型

19. 获取播放的视频宽度

```
/**

* 获取视频宽

* 说明: prepare 后才能获取到该数据,否则返回0

* @return 视频宽度

*/
int getVideowidth()
```

20. 获取播放的视频高度

```
/**

* 获取视频宽

*

* 说明: prepare 后才能获取到该数据,否则返回O

* @return 视频高度

*/
int getVideoHeight()
```

21. 是否正在播放标识

```
/**

* 是否在播放

* @return true==播放, false==没有播放

*/
bool isPlaying()
```

22. 设置状态回调

```
/**
 * 设置准备回调
 *
 */
void setPreparedListener(IPreparedListener listener);
```

23. 设置时间回调

```
/**
 * 设置时间回调
 *
 */
void setTimeListener(ITimeListener);
```

24. 设置错误回调

```
/**
 * 设置错误回调
 *
 */
void setErrorListener(IErrorListener listener);
```