2 Socket 编程 UDP

UDP 网络编程

V1 版本 - echo server

简单的回显服务器和客户端代码

备注: 代码中会用到 地址转换函数 . 参考接下来的章节.

nocopy.hpp

```
C++
#pragma once
#include <iostream>

class nocopy
{
public:
    nocopy(){}
    nocopy(const nocopy &) = delete;
    const nocopy& operator = (const nocopy &) = delete;
    ~nocopy(){}
};
```

UdpServer.hpp

```
#include <iostream>
#include <string>
#include <cerrno>
#include <cstring>
#include <cunistd.h>
#include <strings.h>
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <arpa/inet.h>
#include "nocopy.hpp"
```

```
#include "Log.hpp"
#include "Comm.hpp"
#include "InetAddr.hpp"
const static uint16_t defaultport = 8888;
const static int defaultfd = -1;
const static int defaultsize = 1024;
class UdpServer : public nocopy
{
public:
   UdpServer(uint16_t port = defaultport)
        : _port(port), _sockfd(defaultfd)
   {
   }
   void Init()
       // 1. 创建 socket, 就是创建了文件细节
       _sockfd = socket(AF_INET, SOCK_DGRAM, 0);
       if (_sockfd < 0)</pre>
       {
            lg.LogMessage(Fatal, "socket errr, %d : %s\n", errno,
strerror(errno));
           exit(Socket_Err);
       }
       lg.LogMessage(Info, "socket success, sockfd: %d\n",
sockfd);
       // 2. 绑定, 指定网络信息
       struct sockaddr_in local;
       bzero(&local, sizeof(local)); // memset
       local.sin_family = AF_INET;
       local.sin_port = htons(_port);
       local.sin_addr.s_addr = INADDR_ANY; // 0
       // local.sin_addr.s_addr = inet_addr(_ip.c_str()); // 1. 4
字节 IP 2. 变成网络序列
       // 结构体填完,设置到内核中了吗??没有
       int n = ::bind(_sockfd, (struct sockaddr *)&local,
sizeof(local));
       if (n != 0)
```

```
lg.LogMessage(Fatal, "bind errr, %d : %s\n", errno,
strerror(errno));
            exit(Bind_Err);
    }
    void Start()
    {
        // 服务器永远不退出
        char buffer[defaultsize];
        for (;;)
        {
            struct sockaddr_in peer;
            socklen_t len = sizeof(peer); // 不能乱写
            ssize_t n = recvfrom(_sockfd, buffer, sizeof(buffer) -
1, 0, (struct sockaddr *)&peer, &len);
            if (n > 0)
            {
                InetAddr addr(peer);
                buffer[n] = 0;
                std::cout << "[" << addr.PrintDebug() << "]# " <<</pre>
buffer << std::endl;</pre>
                sendto(_sockfd, buffer, strlen(buffer), 0, (struct
sockaddr *)&peer, len);
        }
    }
    ~UdpServer()
    {
    }
private:
    // std::string _ip; // 后面要调整
    uint16_t _port;
    int sockfd;
};
```

InetAddr.hpp

```
C++
#pragma once
#include <iostream>
#include <string>
#include <sys/types.h>
#include <sys/socket.h>
```

```
#include <netinet/in.h>
#include <arpa/inet.h>
class InetAddr
{
public:
    InetAddr(struct sockaddr_in &addr):_addr(addr)
        _port = ntohs(_addr.sin_port);
        _ip = inet_ntoa(_addr.sin_addr);
    }
    std::string Ip() {return _ip;}
    uint16_t Port() {return _port;};
    std::string PrintDebug()
    {
        std::string info = _ip;
        info += ":";
        info += std::to_string(_port); // "127.0.0.1:4444"
        return info;
    ~InetAddr(){}
private:
    std::string _ip;
    uint16_t _port;
    struct sockaddr_in _addr;
};
```

Comm.hpp

```
C++
#pragma once
enum{
    Usage_Err = 1,
    Socket_Err,
    Bind_Err
};
```

- Log.hpp 已经有了,这里就不再复制粘贴了
- 云服务器不允许直接 bind 公有 IP,我们也不推荐编写服务器的时候,bind 明确的 IP,推荐直接写成 INADDR_ANY

```
C++
/* Address to accept any incoming messages. */
```

```
#define INADDR_ANY ((in_addr_t) 0x0000000)
```

在网络编程中,当一个进程需要绑定一个网络端口以进行通信时,可以使用 INADDR_ANY 作为 IP 地址参数。这样做意味着该端口可以接受来自任何 IP 地址的连接请求,无论是本地主机还是远程主机。例如,如果服务器有多个网卡(每个网卡上有不同的 IP 地址),使用 INADDR_ANY 可以省去确定数据是从服务器上具体哪个网卡/IP 地址上面获取的。

UdpClient.hpp

```
C++
#include <iostream>
#include <cerrno>
#include <cstring>
#include <string>
#include <unistd.h>
#include <sys/types.h> /* See NOTES */
#include <sys/socket.h>
#include <arpa/inet.h>
#include <netinet/in.h>
void Usage(const std::string &process)
    std::cout << "Usage: " << process << " server_ip server_port"</pre>
<< std::endl;
}
// ./udp_client server_ip server_port
int main(int argc, char *argv[])
    if (argc != 3)
    {
        Usage(argv[0]);
        return 1;
    }
    std::string serverip = argv[1];
    uint16_t serverport = std::stoi(argv[2]);
    // 1. 创建 socket
    int sock = socket(AF_INET, SOCK_DGRAM, 0);
    if (sock < 0)
        std::cerr << "socket error: " << strerror(errno) <<</pre>
```

```
std::endl;
       return 2;
   std::cout << "create socket success: " << sock << std::endl;</pre>
   // 2. client 要不要进行 bind? 一定要 bind 的!!
   // 但是,不需要显示 bind, client 会在首次发送数据的时候会自动进行
bind
   // 为什么? server 端的端口号,一定是众所周知,不可改变的,client 需
要 port, bind 随机端口.
   // 为什么? client 会非常多.
   // client 需要 bind,但是不需要显示 bind,让本地 OS 自动随机 bind,
选择随机端口号
   // 2.1 填充一下 server 信息
   struct sockaddr_in server;
   memset(&server, 0, sizeof(server));
   server.sin_family = AF_INET;
   server.sin_port = htons(serverport);
   server.sin_addr.s_addr = inet_addr(serverip.c_str());
   while (true)
   {
       // 我们要发的数据
       std::string inbuffer;
       std::cout << "Please Enter# ";</pre>
       std::getline(std::cin, inbuffer);
       // 我们要发给谁呀? server
       ssize_t n = sendto(sock, inbuffer.c_str(),
inbuffer.size(), 0, (struct sockaddr*)&server, sizeof(server));
       if(n > 0)
       {
           char buffer[1024];
           //收消息
           struct sockaddr in temp;
           socklen_t len = sizeof(temp);
           ssize_t m = recvfrom(sock, buffer, sizeof(buffer)-1,
0, (struct sockaddr*)&temp, &len); // 一般建议都是要填的.
           if(m > 0)
           {
               buffer[m] = 0;
               std::cout << "server echo# " << buffer <<
std::endl;
           }
```

client 端要不要显示 bind 的问题

V2 版本 - DictServer

实现一个简单的英译汉的网络字典

dict.txt

```
C++
apple: 苹果
banana: 香蕉
cat: 猫
dog: 狗
book: 书
pen: 笔
happy: 快乐的
sad: 悲伤的
run: 跑
jump: 跳
teacher: 老师
student: 学生
car: 汽车
bus: 公交车
love: 爱
hate: 恨
hello: 你好
goodbye: 再见
summer: 夏天
winter: 冬天
```

Dict.hpp

```
C++
#pragma once
#include <iostream>
#include <string>
#include <fstream>
#include <unordered map>
const std::string sep = ": ";
class Dict
private:
    void LoadDict()
    {
        std::ifstream in(_confpath);
        if(!in.is_open())
            std::cerr << "open file error" << std::endl; // 后面可
以用日志替代打印
            return;
        std::string line;
        while(std::getline(in, line))
            if(line.empty()) continue;
            auto pos = line.find(sep);
            if(pos == std::string::npos) continue;
            std::string key = line.substr(0, pos);
            std::string value = line.substr(pos + sep.size());
            _dict.insert(std::make_pair(key, value));
        in.close();
public:
    Dict(const std::string &confpath):_confpath(confpath)
    {
        LoadDict();
    std::string Translate(const std::string &key)
        auto iter = _dict.find(key);
        if(iter == _dict.end()) return std::string("Unknown");
        else return iter->second;
```

```
}
    ~Dict()
    {}
private:
    std::string _confpath;
    std::unordered_map<std::string, std::string> _dict;
};
```

UdpServer.hpp

```
C++
#pragma once
#include <iostream>
#include <string>
#include <cerrno>
#include <cstring>
#include <unistd.h>
#include <strings.h>
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <arpa/inet.h>
#include <unordered map>
#include <functional>
#include "nocopy.hpp"
#include "Log.hpp"
#include "Comm.hpp"
#include "InetAddr.hpp"
const static uint16 t defaultport = 8888;
const static int defaultfd = -1;
const static int defaultsize = 1024;
using func_t = std::function<void(const std::string &req,</pre>
std::string *resp)>;
class UdpServer : public nocopy
public:
    UdpServer(func_t func, uint16_t port = defaultport)
        : _func(func),_port(port),_sockfd(defaultfd)
    {
    }
```

```
void Init()
   {
       // 1. 创建 socket, 就是创建了文件细节
       _sockfd = socket(AF_INET, SOCK_DGRAM, 0);
       if (_sockfd < 0)
           lg.LogMessage(Fatal, "socket errr, %d : %s\n", errno,
strerror(errno));
           exit(Socket_Err);
       }
       lg.LogMessage(Info, "socket success, sockfd: %d\n",
sockfd);
       // 2. 绑定,指定网络信息
       struct sockaddr in local;
       bzero(&local, sizeof(local)); // memset
       local.sin_family = AF_INET;
       local.sin_port = htons(_port);
       local.sin_addr.s_addr = INADDR ANY; // 0
       // local.sin_addr.s_addr = inet_addr(_ip.c_str()); // 1. 4
字节 IP 2. 变成网络序列
       // 结构体填完,设置到内核中了吗??没有
       int n = ::bind(_sockfd, (struct sockaddr *)&local,
sizeof(local));
       if (n != 0)
           lg.LogMessage(Fatal, "bind errr, %d : %s\n", errno,
strerror(errno));
           exit(Bind_Err);
       }
   void Start()
   {
       // 服务器永远不退出
       char buffer[defaultsize];
       for (;;)
       {
           struct sockaddr_in peer;
           socklen_t len = sizeof(peer); // 不能乱写
           ssize_t n = recvfrom(_sockfd, buffer, sizeof(buffer) -
1, 0, (struct sockaddr *)&peer, &len);
```

```
if (n > 0)
            {
                InetAddr addr(peer);
                buffer[n] = 0;
                std::cout << "[" << addr.PrintDebug() << "]# " <<</pre>
buffer << std::endl;</pre>
                std::string value;
                _func(buffer, &value); // 回调业务翻译方法
                sendto(_sockfd, value.c_str(), value.size(), 0,
(struct sockaddr *)&peer, len);
        }
    }
    ~UdpServer()
    {
    }
private:
    // std::string _ip; // 后面要调整
    uint16_t _port;
    int _sockfd;
    func_t _func;
};
```

Main.cc

```
C++
#include "UdpServer.hpp"
#include "Comm.hpp"
#include "Dict.hpp"
#include <memory>

void Usage(std::string proc)
{
    std::cout << "Usage : \n\t" << proc << " local_port\n" << std::endl;
}

Dict gdict("./dict.txt");

void Execute(const std::string &req, std::string *resp)
{
    *resp = gdict.Translate(req);
}</pre>
```

```
// ./udp server 8888
int main(int argc, char *argv[])
    if(argc != 2)
    {
         Usage(argv[0]);
         return Usage_Err;
    }
    // std::string ip = argv[1];
    uint16_t port = std::stoi(argv[1]);
    std::unique_ptr<UdpServer> usvr =
std::make_unique<UdpServer>(Execute, port);
    usvr->Init();
    usvr->Start();
    return 0;
}
whb@bite01:~/code/109/lesson46/1.udp_server_server$ ./udp_client 127.0.0.1 8888
```

whoghited:-/code/le9/lessond6/1.udp_server_server\$./udp_client 127.0.0.1 8888 create socket success: 3
Please Enter# apple
Please Enter# goodbye server echo# 再见
Please Enter# haaaa server echo# Unknown

whb@bite01:~/code/109/lesson46/1.udp_server_server\$ /udp_server 8888 [Info][2024-6-12 16:48:41][2907106] socket success, sockfd: 3 [127.0.0.1:53965]# ppel [127.0.0.1:53965]# goodbye [127.0.0.1:53965]# haaaa ^c whb@bite01:~/code/109/lesson46/1.udp_server_server\$

V2 版本 - DictServer 封装版

下面是一个封装版的,大家下来可以看一下

udp_socket.hpp

```
#pragma once
#include <stdio.h>
#include <string.h>
#include <cassert>
#include <cassert>
#include <string>

#include <unistd.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <arpa/inet.h>
typedef struct sockaddr sockaddr;
typedef struct sockaddr_in sockaddr_in;
```

```
class UdpSocket {
public:
 UdpSocket() : fd_(-1) {
  }
  bool Socket() {
    fd_ = socket(AF_INET, SOCK_DGRAM, 0);
    if (fd_ < 0) {
      perror("socket");
      return false;
    }
    return true;
  }
  bool Close() {
    close(fd_);
    return true;
  }
  bool Bind(const std::string& ip, uint16_t port) {
    sockaddr_in addr;
    addr.sin_family = AF_INET;
    addr.sin_addr.s_addr = inet_addr(ip.c_str());
    addr.sin_port = htons(port);
    int ret = bind(fd_, (sockaddr*)&addr, sizeof(addr));
    if (ret < 0) {
      perror("bind");
      return false;
    }
    return true;
  }
  bool RecvFrom(std::string* buf, std::string* ip = NULL,
uint16_t* port = NULL) {
    char tmp[1024 * 10] = \{0\};
    sockaddr_in peer;
    socklen_t len = sizeof(peer);
    ssize_t read_size = recvfrom(fd_, tmp,
                                   sizeof(tmp) - 1, 0,
(sockaddr*)&peer, &len);
    if (read_size < 0) {</pre>
      perror("recvfrom");
      return false;
    }
```

```
// 将读到的缓冲区内容放到输出参数中
    buf->assign(tmp, read_size);
    if (ip != NULL) {
      *ip = inet_ntoa(peer.sin_addr);
    if (port != NULL) {
      *port = ntohs(peer.sin_port);
    }
   return true;
  }
  bool SendTo(const std::string& buf, const std::string& ip,
uint16_t port) {
    sockaddr_in addr;
    addr.sin_family = AF_INET;
    addr.sin_addr.s_addr = inet_addr(ip.c_str());
    addr.sin_port = htons(port);
    ssize_t write_size = sendto(fd_, buf.data(), buf.size(), 0,
(sockaddr*)&addr, sizeof(addr));
    if (write_size < 0) {</pre>
      perror("sendto");
      return false;
    }
   return true;
  }
private:
  int fd_;
};
```

UDP 通用服务器

udp_server.hpp

```
C
#pragma once
#include "udp_socket.hpp"

// C 式写法
// typedef void (*Handler)(const std::string& req, std::string* resp);
// C++ 11 式写法,能够兼容函数指针,仿函数,和 lambda
#include <functional>
typedef std::function<void (const std::string&, std::string* resp)> Handler;
```

```
class UdpServer {
public:
 UdpServer() {
   assert(sock_.Socket());
 }
 ~UdpServer() {
   sock_.Close();
 }
 bool Start(const std::string& ip, uint16_t port, Handler
handler) {
   // 1. 创建 socket
   // 2. 绑定端口号
   bool ret = sock_.Bind(ip, port);
   if (!ret) {
     return false;
   }
   // 3. 进入事件循环
   for (;;) {
     // 4. 尝试读取请求
     std::string req;
     std::string remote_ip;
     uint16_t remote_port = 0;
     bool ret = sock_.RecvFrom(&req, &remote_ip, &remote_port);
     if (!ret) {
       continue;
     std::string resp;
     // 5. 根据请求计算响应
     handler(req, &resp);
     // 6. 返回响应给客户端
     sock_.SendTo(resp, remote_ip, remote_port);
     printf("[%s:%d] req: %s, resp: %s\n", remote_ip.c_str(),
remote_port,
           req.c_str(), resp.c_str());
   }
   sock_.Close();
   return true;
 }
private:
 UdpSocket sock_;
```

```
};
```

实现英译汉服务器

以上代码是对 udp 服务器进行通用接口的封装. 基于以上封装, 实现一个查字典的服务器就很容易了.

dict_server.cc

```
C
#include "udp_server.hpp"
#include <unordered map>
#include <iostream>
std::unordered_map<std::string, std::string> g_dict;
void Translate(const std::string& req, std::string* resp) {
 auto it = g_dict.find(req);
 if (it == g_dict.end()) {
   *resp = "未查到!";
   return;
 }
 *resp = it->second;
}
int main(int argc, char* argv[]) {
 if (argc != 3) {
   printf("Usage ./dict_server [ip] [port]\n");
   return 1;
 }
 // 1. 数据初始化
 g_dict.insert(std::make_pair("hello", "你好"));
 g_dict.insert(std::make_pair("world", "世界"));
 g dict.insert(std::make pair("c++", "最好的编程语言"));
 g_dict.insert(std::make_pair("bit", "特别 NB"));
 // 2. 启动服务器
 UdpServer server;
 server.Start(argv[1], atoi(argv[2]), Translate);
 return 0;
}
```

UDP 通用客户端

udp_client.hpp

```
#pragma once
#include "udp_socket.hpp"
class UdpClient {
public:
 UdpClient(const std::string& ip, uint16_t port) : ip_(ip),
port_(port) {
   assert(sock_.Socket());
  }
 ~UdpClient() {
    sock_.Close();
  }
  bool RecvFrom(std::string* buf) {
    return sock_.RecvFrom(buf);
  }
  bool SendTo(const std::string& buf) {
    return sock_.SendTo(buf, ip_, port_);
  }
private:
 UdpSocket sock_;
 // 服务器端的 IP 和 端口号
 std::string ip ;
 uint16_t port_;
};
```

实现英译汉客户端

```
C
#include "udp_client.hpp"
#include <iostream>

int main(int argc, char* argv[]) {
   if (argc != 3) {
      printf("Usage ./dict_client [ip] [port]\n");
      return 1;
   }
   UdpClient client(argv[1], atoi(argv[2]));
   for (;;) {
      std::string word;
      std::cout << "请输入您要查的单词: ";</pre>
```

```
std::cin >> word;
if (!std::cin) {
    std::cout << "Good Bye" << std::endl;
    break;
}
client.SendTo(word);
std::string result;
client.RecvFrom(&result);
std::cout << word << " 意思是 " << result << std::endl;
}
return 0;
}</pre>
```

V3 版本 - 简单聊天室

UdpServer.hpp

```
C++
#pragma once
#include <iostream>
#include <string>
#include <cerrno>
#include <cstring>
#include <unistd.h>
#include <strings.h>
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <arpa/inet.h>
#include <functional>
#include <pthread.h>
// #include <mutex>
// #include <condition_variable>
#include "nocopy.hpp"
#include "Log.hpp"
#include "Comm.hpp"
#include "InetAddr.hpp"
#include "ThreadPool.hpp"
const static uint16_t defaultport = 8888;
const static int defaultfd = -1;
const static int defaultsize = 1024;
using task_t = std::function<void()>;
```

```
// using cb_t = std::function<std::string(std::string)>; // 定义了
一个函数类型
// 聚焦在 IO 上
class UdpServer : public nocopy
{
public:
   // UdpServer(cb_t OnMessage, uint16_t port = defaultport)
          : _port(port), _sockfd(defaultfd),
_OnMessage(OnMessage)
   UdpServer(uint16_t port = defaultport) : _port(port),
_sockfd(defaultfd)
   {
       pthread_mutex_init(&_user_mutex, nullptr);
   void Init()
       // 1. 创建 socket, 就是创建了文件细节
       _sockfd = socket(AF_INET, SOCK_DGRAM, 0);
       if (_sockfd < 0)</pre>
       {
           lg.LogMessage(Fatal, "socket errr, %d : %s\n", errno,
strerror(errno));
           exit(Socket_Err);
       }
       lg.LogMessage(Info, "socket success, sockfd: %d\n",
_sockfd);
       // 2. 绑定, 指定网络信息
       struct sockaddr in local;
       bzero(&local, sizeof(local)); // memset
       local.sin_family = AF_INET;
       local.sin_port = htons(_port);
       local.sin addr.s addr = INADDR ANY; // 0
       // local.sin addr.s addr = inet addr( ip.c str()); // 1. 4
字节 IP 2. 变成网络序列
       // 结构体填完,设置到内核中了吗??没有
       int n = ::bind(_sockfd, (struct sockaddr *)&local,
sizeof(local));
       if (n != 0)
```

```
{
            lg.LogMessage(Fatal, "bind errr, %d : %s\n", errno,
strerror(errno));
            exit(Bind Err);
        }
        ThreadPool<task_t>::GetInstance()->Start();
    }
    void AddOnlineUser(InetAddr addr)
        LockGuard lockguard(&_user_mutex);
        for (auto &user : _online_user)
            if (addr == user)
                return;
        _online_user.push_back(addr);
        lg.LogMessage(Debug, "%s:%d is add to onlineuser
list...\n", addr.Ip().c_str(), addr.Port());
    void Route(int sock, const std::string &message)
    {
        LockGuard lockguard(& user mutex);
        for (auto &user : _online_user)
            sendto(sock, message.c_str(), message.size(), 0,
(struct sockaddr *)&user.GetAddr(), sizeof(user.GetAddr()));
            lg.LogMessage(Debug, "server send message to %s:%d,
message: %s\n", user.Ip().c_str(), user.Port(), message.c_str());
   }
    void Start()
    {
        // 服务器永远不退出
        char buffer[defaultsize];
        for (;;)
        {
            struct sockaddr_in peer;
            socklen t len = sizeof(peer); // 不能乱写
            ssize_t n = recvfrom(_sockfd, buffer, sizeof(buffer) -
1, 0, (struct sockaddr *)&peer, &len);
            if (n > 0)
```

```
InetAddr addr(peer);
               AddOnlineUser(addr);
                buffer[n] = 0;
                std::string message = "[";
               message += addr.Ip();
               message += ":";
               message += std::to_string(addr.Port());
               message += "]# ";
               message += buffer;
               task_t task = std::bind(&UdpServer::Route, this,
_sockfd, message);
                ThreadPool<task t>::GetInstance()->Push(task);
               // 处理消息
               // std::string response = _OnMessage(buffer);
               // std::cout << "[" << addr.PrintDebug() << "]# "
<< buffer << std::endl;
               // sendto(_sockfd, response.c_str(),
response.size(), 0, (struct sockaddr *)&peer, len);
        }
   }
   ~UdpServer()
   {
       pthread_mutex_destroy(&_user_mutex);
   }
private:
   // std::string _ip; // 后面要调整
   uint16 t port;
   int _sockfd;
   std::vector<InetAddr> _online_user; // 会被多个线程同时访问的
   pthread_mutex_t _user_mutex;
   // cb_t _OnMessage; // 回调
};
```

• 引入线程池, 这里就不重复贴代码了

InetAddr.hpp

```
C++
#pragma once
#include <iostream>
```

```
#include <string>
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <arpa/inet.h>
class InetAddr
public:
    InetAddr(struct sockaddr_in &addr):_addr(addr)
        _port = ntohs(_addr.sin_port);
        _ip = inet_ntoa(_addr.sin_addr);
    }
    std::string Ip() {return _ip;}
    uint16_t Port() {return _port;};
    std::string PrintDebug()
    {
        std::string info = _ip;
        info += ":";
        info += std::to_string(_port); // "127.0.0.1:4444"
        return info;
    }
    const struct sockaddr_in& GetAddr()
    {
        return _addr;
    bool operator == (const InetAddr&addr)
    {
        //other code
        return this->_ip == addr._ip && this->_port == addr._port;
    }
    ~InetAddr(){}
private:
    std::string _ip;
    uint16_t _port;
    struct sockaddr_in _addr;
};
```

• 在 InetAddr 中,重载一下==方便对用户是否是同一个进行比较

UdpClient.hpp


```
C++
#include <iostream>
```

```
#include <cerrno>
#include <cstring>
#include <string>
#include <unistd.h>
#include <sys/types.h> /* See NOTES */
#include <sys/socket.h>
#include <arpa/inet.h>
#include <netinet/in.h>
#include "Thread.hpp"
#include "InetAddr.hpp"
void Usage(const std::string &process)
    std::cout << "Usage: " << process << " server_ip server_port"</pre>
<< std::endl;
class ThreadData
{
public:
    ThreadData(int sock, struct sockaddr_in &server) :
_sockfd(sock), _serveraddr(server)
    {
    }
    ~ThreadData()
    {
    }
public:
    int _sockfd;
    InetAddr _serveraddr;
};{
void RecverRoutine(ThreadData &td)
{
    char buffer[4096];
    while (true)
    {
        struct sockaddr_in temp;
        socklen_t len = sizeof(temp);
        ssize_t n = recvfrom(td._sockfd, buffer, sizeof(buffer) -
1, 0, (struct sockaddr *)&temp, &len); // 一般建议都是要填的.
        if (n > 0)
        {
```

```
buffer[n] = 0;
           std::cerr << buffer << std::endl; // 方便一会查看效果
       }
       else
           break;
   }
}
// 该线程只负责发消息
void SenderRoutine(ThreadData &td)
   while (true)
   {
       // 我们要发的数据
       std::string inbuffer;
       std::cout << "Please Enter# ";</pre>
       std::getline(std::cin, inbuffer);
       auto server = td._serveraddr.GetAddr();
       // 我们要发给谁呀? server
       ssize_t n = sendto(td._sockfd, inbuffer.c_str(),
inbuffer.size(), 0, (struct sockaddr *)&server, sizeof(server));
       if (n <= 0)
           std::cout << "send error" << std::endl;</pre>
   }
}
// ./udp_client server_ip server_port
int main(int argc, char *argv[])
{
   if (argc != 3)
   {
       Usage(argv[0]);
       return 1;
   }
   std::string serverip = argv[1];
   uint16_t serverport = std::stoi(argv[2]);
   // 1. 创建 socket
   // udp 是全双工的。既可以读,也可以写,可以同时读写,不会多线程读写
的问题
   int sock = socket(AF_INET, SOCK_DGRAM, 0);
   if (sock < 0)
```

```
{
       std::cerr << "socket error: " << strerror(errno) <<</pre>
std::endl;
       return 2;
   std::cout << "create socket success: " << sock << std::endl;</pre>
   // 2. client 要不要进行 bind? 一定要 bind 的!! 但是,不需要显示
bind, client 会在首次发送数据的时候会自动进行 bind
   // 为什么? server 端的端口号,一定是众所周知,不可改变的,client 需
要 port, bind 随机端口.
   // 为什么? client 会非常多.
   // client 需要 bind,但是不需要显示 bind,让本地 OS 自动随机 bind,
选择随机端口号
   // 2.1 填充一下 server 信息
   struct sockaddr in server;
   memset(&server, 0, sizeof(server));
   server.sin_family = AF_INET;
   server.sin_port = htons(serverport);
   server.sin addr.s addr = inet addr(serverip.c str());
   ThreadData td(sock, server);
   Thread<ThreadData> recver("recver", RecverRoutine, td);
   Thread<ThreadData> sender("sender", SenderRoutine, td);
   recver.Start();
   sender.Start();
   recver.Join();
   sender.Join();
   close(sock);
   return 0;
}
```

- UDP 协议支持全双工,一个 sockfd,既可以读取,又可以写入,对于客户端和服务端同样如此
- 多线程客户端,同时读取和写入
- 测试的时候,使用管道进行演示



补充参考内容

地址转换函数

本节只介绍基于 IPv4 的 socket 网络编程,sockaddr_in 中的成员 struct in_addr sin addr 表示 32 位 的 IP 地址

但是我们通常用点分十进制的字符串表示 IP 地址,以下函数可以在字符串表示 和 in_addr 表示之间转换;

字符串转 in addr 的函数:

```
#include <arpa/inet.h>
int inet_aton(const char *strptr, struct in_addr *addrptr);
in_addr_t inet_addr(const char *strptr);
int inet_pton(int family, const char *strptr, void *addrptr);
```

in addr 转字符串的函数:

```
char *inet_ntoa(struct in_addr inaddr);
const char *inet_ntop(int family, const void *addrptr, char *strptr,
size_t len);
```

其中 inet_pton 和 inet_ntop 不仅可以转换 IPv4 的 in_addr,还可以转换 IPv6 的 in6_addr,因此函数接口是 void *addrptr。

代码示例:

```
1 #include <stdio.h>
2 #include <sys/socket.h>
3 #include <netinet/in.h>
4 #include <arpa/inet.h>
5
6 int main() {
7    struct sockaddr_in addr;
8    inet_aton("127.0.0.1", &addr.sin_addr);
9    uint32_t* ptr = (uint32_t*)(&addr.sin_addr);
10    printf("addr. %x\n", *ptr);
11    printf("addr_str: %s\n", inet_ntoa(addr.sin_addr));
12    return 0;
13 }
```

关于 inet_ntoa

inet_ntoa 这个函数返回了一个 char*, 很显然是这个函数自己在内部为我们申请了一块内存来保存 ip 的结果. 那么是否需要调用者手动释放呢?

```
The inet_ntoa() function converts the Internet host address in, given in network byte order, to a string in IPv4 dotted-decimal notation. The string is returned in a statically allocated buffer, which subsequent calls will overwrite.
```

man 手册上说, inet_ntoa 函数, 是把这个返回结果放到了静态存储区. 这个时候不需要我们手动进行释放.

那么问题来了, 如果我们调用多次这个函数, 会有什么样的效果呢? 参见如下代码:

```
1 #include <stdio.h>
2 #include <netinet/in.h>
3 #include <arpa/inet.h>
4
5 int main() {
6    struct sockaddr_in addr1;
7    struct sockaddr_in addr2;
8    addr1.sin_addr.s_addr = 0;
9    addr2.sin_addr.s_addr = 0xfffffff;
10    char* ptr1 = inet_ntoa(addr1.sin_addr);
11    char* ptr2 = inet_ntoa(addr2.sin_addr);
12    printf("ptr1: %s, ptr2: %s\n", ptr1, ptr2);
13    return 0;
14 }
```

运行结果如下:

```
[tangzhong@tz addr_convert]$ ./a.out
ptr1: 255.255.255.255, ptr2: 255.255.255
```

因为 inet_ntoa 把结果放到自己内部的一个静态存储区,这样第二次调用时的结果会覆盖掉上一次的结果.

- 思考: 如果有多个线程调用 inet_ntoa, 是否会出现异常情况呢?
- 在 APUE 中, 明确提出 inet ntoa 不是线程安全的函数;
- 但是在 centos7 上测试,并没有出现问题,可能内部的实现加了互斥锁;
- 同学们课后自己写程序验证一下在自己的机器上 inet_ntoa 是否会出现多线程的问题;
- 在多线程环境下,推荐使用 inet_ntop, 这个函数由调用者提供一个缓冲区保存结果,可以规避线程安全问题;

多线程调用 inet_ntoa 代码示例如下(同学们课后自己测试):

```
#include <stdio.h>
#include <unistd.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <arpa/inet.h>
#include <pthread.h>
void* Func1(void* p) {
  struct sockaddr_in* addr = (struct sockaddr_in*)p;
 while (1) {
    char* ptr = inet_ntoa(addr->sin_addr);
    printf("addr1: %s\n", ptr);
 }
  return NULL;
}
void* Func2(void* p) {
  struct sockaddr_in* addr = (struct sockaddr_in*)p;
 while (1) {
    char* ptr = inet_ntoa(addr->sin_addr);
    printf("addr2: %s\n", ptr);
  }
 return NULL;
}
int main() {
  pthread_t tid1 = 0;
  struct sockaddr_in addr1;
  struct sockaddr_in addr2;
  addr1.sin_addr.s_addr = 0;
  addr2.sin_addr.s_addr = 0xffffffff;
  pthread_create(&tid1, NULL, Func1, &addr1);
  pthread_t tid2 = 0;
  pthread_create(&tid2, NULL, Func2, &addr2);
  pthread_join(tid1, NULL);
  pthread_join(tid2, NULL);
 return 0;
}
```