Photon Unity Networking v1.99

Generated by Doxygen 1.8.7

Tue Aug 20 2019 15:05:47

Contents

1	Mair	n Page		1					
2	Gen	neral Documentation							
	2.1	Photor	1	3					
		2.1.1	Master Server And Lobby	4					
		2.1.2	Remote Procedure Calls	7					
		2.1.3	Instantiating Networked Objects	8					
3	Netv	work Sir	mulation GUI	13					
4	Netv	work Sta	atistics GUI	15					
5	Pub	lic API I	Module	17					
6	Mod	lule Doo	cumentation	19					
	6.1	Public	API	19					
		6.1.1	Detailed Description	21					
		6.1.2	Enumeration Type Documentation	21					
			6.1.2.1 ClientState	21					
			6.1.2.2 DisconnectCause	21					
			6.1.2.3 PhotonLogLevel	22					
			6.1.2.4 PhotonNetworkingMessage	22					
			6.1.2.5 PhotonTargets	26					
		6.1.3	Function Documentation	27					
			6.1.3.1 OnPhotonSerializeView	27					
	6.2	Option	nal Gui Elements	28					
		6.2.1	Detailed Description	28					
7	Nam	nespace	e Documentation	29					
	7.1	Packag	ge ExitGames	29					
	7.2	Packag	ge ExitGames.Client	29					
	7.3	Packa	ge ExitGames.Client.GUI	29					
		7.3.1	Enumeration Type Documentation	29					
			7.3.1.1 GizmoType	29					

iv CONTENTS

	7.4	Packaç	ge Photon		 30
		7.4.1	Typedef	Documentation	 30
			7.4.1.1	Hashtable	 30
	7.5	Packaç	ge Photon.	.Chat	 30
		7.5.1	Enumera	ation Type Documentation	 31
			7.5.1.1	ChatDisconnectCause	 31
			7.5.1.2	ChatState	 32
			7.5.1.3	CustomAuthenticationType	 32
	7.6	Packag	ge Photon.	.Realtime	 32
	7.7	Packa	ge UnityEr	ngine	 32
	7.8	Packa	ge UnityEr	ngine.SceneManagement	 33
		7.8.1	Enumera	ation Type Documentation	 33
			7.8.1.1	LoadSceneMode	 33
8	Clas	s Docu	mentation	n	35
	8.1			Class Reference	 35
		8.1.1	•	Description	35
		8.1.2		Data Documentation	35
			8.1.2.1	IsInactive	 35
			8.1.2.2	PlayerName	 35
			8.1.2.3	Userld	 35
	8.2	Photor	n.Chat.Autl	thenticationValues Class Reference	 36
		8.2.1	Detailed	Description	 36
		8.2.2	Construc	ctor & Destructor Documentation	 36
			8.2.2.1	AuthenticationValues	 36
			8.2.2.2	AuthenticationValues	 37
		8.2.3	Member	Function Documentation	 37
			8.2.3.1	AddAuthParameter	 37
			8.2.3.2	SetAuthPostData	 37
			8.2.3.3	SetAuthPostData	 37
			8.2.3.4	ToString	 37
		8.2.4	Property	Documentation	 37
			8.2.4.1	AuthGetParameters	 37
			8.2.4.2	AuthPostData	 38
			8.2.4.3	AuthType	 38
			8.2.4.4	Token	 38
			8.2.4.5	UserId	 38
	8.3	Auther		alues Class Reference	38
		8.3.1		Description	39
		8.3.2	Construc	ctor & Destructor Documentation	 39

CONTENTS

		8.3.2.1	AuthenticationValues	39
		8.3.2.2	AuthenticationValues	39
	8.3.3	Member	Function Documentation	39
		8.3.3.1	AddAuthParameter	39
		8.3.3.2	SetAuthPostData	39
		8.3.3.3	SetAuthPostData	40
		8.3.3.4	SetAuthPostData	40
		8.3.3.5	ToString	40
	8.3.4	Property	Documentation	40
		8.3.4.1	AuthGetParameters	40
		8.3.4.2	AuthPostData	40
		8.3.4.3	AuthType	40
		8.3.4.4	Token	40
		8.3.4.5	Userld	41
8.4	Photon	.Chat.Cha	annelCreationOptions Class Reference	41
	8.4.1	Member	Data Documentation	41
		8.4.1.1	Default	41
	8.4.2	Property	Documentation	41
		8.4.2.1	MaxSubscribers	41
		8.4.2.2	PublishSubscribers	41
8.5	Photon	.Chat.Cha	annelWellKnownProperties Class Reference	41
	8.5.1	Member	Data Documentation	41
		8.5.1.1	MaxSubscribers	41
		8.5.1.2	PublishSubscribers	41
8.6	Photon	.Chat.Cha	atChannel Class Reference	42
	8.6.1	Detailed	Description	43
	8.6.2	Construc	ctor & Destructor Documentation	43
		8.6.2.1	ChatChannel	43
	8.6.3	Member	Function Documentation	43
		8.6.3.1	Add	43
		8.6.3.2	Add	43
		8.6.3.3	ClearMessages	43
		8.6.3.4	ToStringMessages	43
		8.6.3.5	TruncateMessages	43
	8.6.4	Member	Data Documentation	43
		8.6.4.1	MessageLimit	43
		8.6.4.2	Messages	43
		8.6.4.3	Name	44
		8.6.4.4	Senders	44
		8.6.4.5	Subscribers	44

vi CONTENTS

	8.6.5	Property	Documentation	44
		8.6.5.1	IsPrivate	44
		8.6.5.2	LastMsgld	44
		8.6.5.3	MaxSubscribers	44
		8.6.5.4	MessageCount	44
		8.6.5.5	PublishSubscribers	44
8.7	Photon	.Chat.Cha	atClient Class Reference	44
	8.7.1	Detailed	Description	47
	8.7.2	Construc	tor & Destructor Documentation	47
		8.7.2.1	ChatClient	47
	8.7.3	Member	Function Documentation	47
		8.7.3.1	AddFriends	47
		8.7.3.2	CanChatInChannel	47
		8.7.3.3	Connect	48
		8.7.3.4	ConnectAndSetStatus	48
		8.7.3.5	Disconnect	48
		8.7.3.6	GetPrivateChannelNameByUser	48
		8.7.3.7	PublishMessage	49
		8.7.3.8	RemoveFriends	49
		8.7.3.9	SendAcksOnly	50
		8.7.3.10	SendPrivateMessage	50
		8.7.3.11	SendPrivateMessage	50
		8.7.3.12	Service	50
		8.7.3.13	SetOnlineStatus	51
		8.7.3.14	SetOnlineStatus	51
		8.7.3.15	StopThread	51
		8.7.3.16	Subscribe	51
		8.7.3.17	Subscribe	52
		8.7.3.18	Subscribe	53
		8.7.3.19	Subscribe	53
		8.7.3.20	TryGetChannel	53
		8.7.3.21	TryGetChannel	54
		8.7.3.22	TryGetPrivateChannelByUser	54
		8.7.3.23	Unsubscribe	54
	8.7.4	Member	Data Documentation	55
		8.7.4.1	chatPeer	55
		8.7.4.2	DefaultMaxSubscribers	55
		8.7.4.3	MessageLimit	55
		8.7.4.4	PrivateChannels	55
		8.7.4.5	PublicChannels	55

CONTENTS vii

	8.7.5	Property	Documentation	55
		8.7.5.1	Appld	55
		8.7.5.2	AppVersion	55
		8.7.5.3	AuthValues	55
		8.7.5.4	CanChat	55
		8.7.5.5	ChatRegion	55
		8.7.5.6	DebugOut	56
		8.7.5.7	DisconnectedCause	56
		8.7.5.8	FrontendAddress	56
		8.7.5.9	NameServerAddress	56
		8.7.5.10	SocketImplementationConfig	56
		8.7.5.11	State	56
		8.7.5.12	TransportProtocol	56
		8.7.5.13	UseBackgroundWorkerForSending	56
		8.7.5.14	UserId	56
8.8	Photon	.Chat.Cha	tEventCode Class Reference	57
	8.8.1	Detailed	Description	57
	8.8.2	Member	Data Documentation	57
		8.8.2.1	ChatMessages	57
		8.8.2.2	FriendsList	57
		8.8.2.3	PrivateMessage	57
		8.8.2.4	StatusUpdate	57
		8.8.2.5	Subscribe	57
		8.8.2.6	Unsubscribe	58
		8.8.2.7	Users	58
		8.8.2.8	UserSubscribed	58
		8.8.2.9	UserUnsubscribed	58
8.9	Photon	.Chat.Cha	tOperationCode Class Reference	58
	8.9.1	Detailed	Description	58
	8.9.2	Member	Data Documentation	58
		8.9.2.1	AddFriends	58
		8.9.2.2	Authenticate	59
		8.9.2.3	ChannelHistory	59
		8.9.2.4	Publish	59
		8.9.2.5	RemoveFriends	59
		8.9.2.6	SendPrivate	59
		8.9.2.7	Subscribe	59
		8.9.2.8	Unsubscribe	59
		8.9.2.9	UpdateStatus	59
8.10	Photon	.Chat.Cha	tParameterCode Class Reference	59

viii CONTENTS

	8.10.1	Detailed Description	60
	8.10.2	Member Data Documentation	60
		8.10.2.1 Channel	60
		8.10.2.2 Channels	60
		8.10.2.3 ChannelSubscribers	60
		8.10.2.4 ChannelUserCount	61
		8.10.2.5 Friends	61
		8.10.2.6 HistoryLength	61
		8.10.2.7 Message	61
		8.10.2.8 Messages	61
		8.10.2.9 Msgld	61
		8.10.2.10 Msglds	61
		8.10.2.11 Properties	61
		8.10.2.12 Secret	61
		8.10.2.13 Sender	61
		8.10.2.14 Senders	61
		8.10.2.15 SkipMessage	62
		8.10.2.16 Status	62
		8.10.2.17 SubscribeResults	62
		8.10.2.18 Userld	62
		8.10.2.19 WebFlags	62
8.11	Photon	.Chat.ChatPeer Class Reference	62
	8.11.1	Detailed Description	63
	8.11.2	Constructor & Destructor Documentation	63
		8.11.2.1 ChatPeer	63
	8.11.3	Member Function Documentation	63
		8.11.3.1 AuthenticateOnNameServer	63
		8.11.3.2 Connect	63
	8.11.4	Member Data Documentation	63
		8.11.4.1 NameServerHost	63
		8.11.4.2 NameServerHttp	63
	8.11.5	Property Documentation	63
		8.11.5.1 NameServerAddress	63
8.12	Photon	.Chat.ChatUserStatus Class Reference	63
	8.12.1	Detailed Description	64
	8.12.2	Member Data Documentation	64
		8.12.2.1 Away	64
		8.12.2.2 DND	64
		8.12.2.3 Invisible	64
		8.12.2.4 LFG	64

CONTENTS

		8.12.2.5	Offline	 64
		8.12.2.6	Online	 64
		8.12.2.7	Playing	 65
8.13 Er	ncrypt	ionDataPa	arameters Class Reference	 65
8.	13.1	Member [Data Documentation	 65
		8.13.1.1	Mode	 65
		8.13.1.2	Secret1	 65
		8.13.1.3	Secret2	 65
8.14 Ph	hoton.	Chat.Erro	rCode Class Reference	 65
8.	14.1	Detailed [Description	 66
8.	14.2	Member [Data Documentation	 66
		8.14.2.1	CustomAuthenticationFailed	 66
		8.14.2.2	GameClosed	 66
		8.14.2.3	GameDoesNotExist	 66
		8.14.2.4	GameFull	 66
		8.14.2.5	GameIdAlreadyExists	 66
		8.14.2.6	InternalServerError	 67
		8.14.2.7	InvalidAuthentication	 67
		8.14.2.8	InvalidOperationCode	 67
		8.14.2.9	InvalidRegion	 67
		8.14.2.10	MaxCcuReached	 67
		8.14.2.11	NoRandomMatchFound	 67
		8.14.2.12	Ok	 67
		8.14.2.13	OperationNotAllowedInCurrentState	 67
		8.14.2.14	ServerFull	 68
		8.14.2.15	UserBlocked	 68
8.15 Er	rrorCo	de Class	Reference	 68
8.	15.1	Detailed [Description	 69
8.	15.2	Member [Data Documentation	 69
		8.15.2.1	AlreadyMatched	 69
		8.15.2.2	AuthenticationTicketExpired	 69
		8.15.2.3	CustomAuthenticationFailed	 69
		8.15.2.4	ExternalHttpCallFailed	 70
		8.15.2.5	GameClosed	 70
		8.15.2.6	GameDoesNotExist	 70
		8.15.2.7	GameFull	 70
		8.15.2.8	GameIdAlreadyExists	 70
		8.15.2.9	HttpLimitReached	 70
		8.15.2.10	InternalServerError	 70
		8.15.2.11	InvalidAuthentication	 70

CONTENTS

	8.15.2.12 InvalidEncryptionParameters	70
	8.15.2.13 InvalidOperation	70
	8.15.2.14 InvalidOperationCode	70
	8.15.2.15 InvalidRegion	71
	8.15.2.16 JoinFailedFoundActiveJoiner	71
	8.15.2.17 JoinFailedFoundExcludedUserId	71
	8.15.2.18 JoinFailedFoundInactiveJoiner	71
	8.15.2.19 JoinFailedPeerAlreadyJoined	71
	8.15.2.20 JoinFailedWithRejoinerNotFound	71
	8.15.2.21 MaxCcuReached	71
	8.15.2.22 NoRandomMatchFound	71
	8.15.2.23 Ok	72
	8.15.2.24 OperationNotAllowedInCurrentState	72
	8.15.2.25 PluginMismatch	72
	8.15.2.26 PluginReportedError	72
	8.15.2.27 ServerFull	72
	8.15.2.28 SlotError	72
	8.15.2.29 UserBlocked	72
8.16 Event	Code Class Reference	72
8.16.1	Detailed Description	73
8.16.2	Member Data Documentation	73
	8.16.2.1 AppStats	73
	8.16.2.2 AuthEvent	73
	8.16.2.3 AzureNodeInfo	73
	8.16.2.4 CacheSliceChanged	73
	8.16.2.5 ErrorInfo	74
	8.16.2.6 GameList	74
	8.16.2.7 GameListUpdate	74
	8.16.2.8 Join	74
	8.16.2.9 Leave	74
	8.16.2.10 LobbyStats	74
	8.16.2.11 Match	74
	8.16.2.12 PropertiesChanged	74
	8.16.2.13 QueueState	74
	8.16.2.14 SetProperties	74
8.17 Extens	sions Class Reference	75
8.17.1	Detailed Description	75
8.17.2	Member Function Documentation	75
	8.17.2.1 AlmostEquals	75
	8.17.2.2 AlmostEquals	76

CONTENTS xi

		8.17.2.3	AlmostEquals	76
		8.17.2.4	AlmostEquals	76
		8.17.2.5	Contains	76
		8.17.2.6	GetCachedParemeters	76
		8.17.2.7	GetPhotonView	76
		8.17.2.8	GetPhotonViewsInChildren	76
		8.17.2.9	Merge	76
		8.17.2.10	MergeStringKeys	76
		8.17.2.11	StripKeysWithNullValues	77
		8.17.2.12	StripToStringKeys	77
		8.17.2.13	ToStringFull	77
		8.17.2.14	ToStringFull	77
	8.17.3	Member E	Data Documentation	77
		8.17.3.1	ParametersOfMethods	78
8.18	FindFri	endsOption	ns Class Reference	78
	8.18.1	Detailed D	Description	78
	8.18.2	Member E	Data Documentation	78
		8.18.2.1	CreatedOnGs	78
		8.18.2.2	Open	78
		8.18.2.3	Visible	78
8.19	Friendl	nfo Class F	Reference	78
	8.19.1	Detailed D	Description	79
	8.19.2	Member F	Function Documentation	79
		8.19.2.1	ToString	79
	8.19.3	Property I	Documentation	79
		8.19.3.1	IsInRoom	79
		8.19.3.2	IsOnline	79
		8.19.3.3	Name	79
		8.19.3.4	Room	79
		8.19.3.5	Userld	79
8.20	GameC	ObjectExter	nsions Class Reference	79
	8.20.1	Detailed D	Description	79
	8.20.2	Member F	Function Documentation	79
		8.20.2.1	GetActive	79
8.21	GameF	PropertyKey	y Class Reference	79
	8.21.1	Detailed D	Description	80
	8.21.2	Member E	Data Documentation	80
		8.21.2.1	CleanupCacheOnLeave	80
		8.21.2.2	EmptyRoomTtl	80
		8.21.2.3	ExpectedUsers	80

xii CONTENTS

		8.21.2.4	IsOpen	80
		8.21.2.5	IsVisible	81
		8.21.2.6	MasterClientId	81
		8.21.2.7	MaxPlayers	81
		8.21.2.8	PlayerCount	81
		8.21.2.9	PlayerTtl	81
		8.21.2.10	PropsListedInLobby	81
		8.21.2.11	Removed	81
8.22	ExitGa	mes.Client	t.GUI.GizmoTypeDrawer Class Reference	81
	8.22.1	Member I	Function Documentation	81
		8.22.1.1	Draw	81
8.23	HelpUF	RL Class F	Reference	81
	8.23.1	Detailed I	Description	82
	8.23.2	Construc	tor & Destructor Documentation	82
		8.23.2.1	HelpURL	82
8.24	Photon	.Chat.ICha	atClientListener Interface Reference	82
	8.24.1	Detailed I	Description	82
	8.24.2	Member I	Function Documentation	83
		8.24.2.1	DebugReturn	83
		8.24.2.2	OnChatStateChange	84
		8.24.2.3	OnConnected	84
		8.24.2.4	OnDisconnected	84
		8.24.2.5	OnGetMessages	84
		8.24.2.6	OnPrivateMessage	84
		8.24.2.7	OnStatusUpdate	84
		8.24.2.8	OnSubscribed	85
		8.24.2.9	OnUnsubscribed	85
		8.24.2.10	OnUserSubscribed	85
		8.24.2.11	OnUserUnsubscribed	85
8.25	IPunCa	allbacks Int	terface Reference	85
	8.25.1	Detailed I	Description	87
	8.25.2	Member I	Function Documentation	87
		8.25.2.1	OnConnectedToMaster	87
		8.25.2.2	OnConnectedToPhoton	87
		8.25.2.3	OnConnectionFail	88
		8.25.2.4	OnCreatedRoom	88
		8.25.2.5	OnCustomAuthenticationFailed	88
		8.25.2.6	OnCustomAuthenticationResponse	88
		8.25.2.7	OnDisconnectedFromPhoton	89
		8.25.2.8	OnFailedToConnectToPhoton	89

CONTENTS xiii

	8.25.2.9 OnJoinedLobby	89
	8.25.2.10 OnJoinedRoom	89
	8.25.2.11 OnLeftLobby	89
	8.25.2.12 OnLeftRoom	89
	8.25.2.13 OnLobbyStatisticsUpdate	90
	8.25.2.14 OnMasterClientSwitched	90
	8.25.2.15 OnOwnershipRequest	90
	8.25.2.16 OnOwnershipTransfered	90
	8.25.2.17 OnPhotonCreateRoomFailed	90
	8.25.2.18 OnPhotonCustomRoomPropertiesChanged	91
	8.25.2.19 OnPhotonInstantiate	91
	8.25.2.20 OnPhotonJoinRoomFailed	91
	8.25.2.21 OnPhotonMaxCccuReached	91
	8.25.2.22 OnPhotonPlayerActivityChanged	91
	8.25.2.23 OnPhotonPlayerConnected	92
	8.25.2.24 OnPhotonPlayerDisconnected	92
	8.25.2.25 OnPhotonPlayerPropertiesChanged	92
	8.25.2.26 OnPhotonRandomJoinFailed	92
	8.25.2.27 OnReceivedRoomListUpdate	93
	8.25.2.28 OnUpdatedFriendList	93
	8.25.2.29 OnWebRpcResponse	93
8.26 IPun	Observable Interface Reference	93
8.26	.1 Detailed Description	93
8.27 IPun	PrefabPool Interface Reference	94
8.27	.1 Detailed Description	94
8.27	.2 Member Function Documentation	94
	8.27.2.1 Destroy	94
	8.27.2.2 Instantiate	94
8.28 Phot	ton.MonoBehaviour Class Reference	95
8.28	.1 Detailed Description	95
8.28	.2 Property Documentation	95
	8.28.2.1 networkView	95
	8.28.2.2 photonView	95
8.29 Oper	rationCode Class Reference	95
8.29	.1 Detailed Description	96
8.29	.2 Member Data Documentation	96
	8.29.2.1 Authenticate	96
	8.29.2.2 AuthenticateOnce	96
	8.29.2.3 ChangeGroups	96
	8.29.2.4 CreateGame	97

XIV

		8.29.2.5	ExchangeKeysForEncryption	97
		8.29.2.6	FindFriends	97
		8.29.2.7	GetGameList	97
		8.29.2.8	GetLobbyStats	97
		8.29.2.9	GetProperties	97
		8.29.2.10	GetRegions	97
		8.29.2.11	Join	97
		8.29.2.12	JoinGame	97
		8.29.2.13	JoinLobby	97
		8.29.2.14	JoinRandomGame	97
		8.29.2.15	Leave	97
		8.29.2.16	LeaveLobby	97
		8.29.2.17	RaiseEvent	98
		8.29.2.18	ServerSettings	98
		8.29.2.19	SetProperties	98
		8.29.2.20	WebRpc	98
8.30	Photon	.Chat.Para	meterCode Class Reference	98
	8.30.1	Detailed I	Description	98
	8.30.2	Member I	Data Documentation	99
		8.30.2.1	Address	99
		8.30.2.2	ApplicationId	99
		8.30.2.3	AppVersion	99
		8.30.2.4	ClientAuthenticationData	99
		8.30.2.5	ClientAuthenticationParams	99
		8.30.2.6	ClientAuthenticationType	99
		8.30.2.7	Region	99
		8.30.2.8	Secret	99
		8.30.2.9	UserId	99
8.31	Parame	eterCode C	Class Reference	99
	8.31.1	Detailed I	Description	103
	8.31.2	Member I	Data Documentation	103
		8.31.2.1	ActorList	103
		8.31.2.2	ActorNr	103
		8.31.2.3	Add	103
		8.31.2.4	Address	103
		8.31.2.5	ApplicationId	103
		8.31.2.6	AppVersion	103
		8.31.2.7	AzureLocalNodeld	103
		8.31.2.8	AzureMasterNodeld	103
		8.31.2.9	AzureNodeInfo	103

CONTENTS xv

8.31.2.10 Broadcast	103
8.31.2.11 Cache	104
8.31.2.12 CacheSliceIndex	104
8.31.2.13 CheckUserOnJoin	104
8.31.2.14 CleanupCacheOnLeave	104
8.31.2.15 ClientAuthenticationData	104
8.31.2.16 ClientAuthenticationParams	104
8.31.2.17 ClientAuthenticationType	104
8.31.2.18 Code	104
8.31.2.19 CustomEventContent	104
8.31.2.20 CustomInitData	104
8.31.2.21 Data	104
8.31.2.22 EmptyRoomTTL	105
8.31.2.23 EncryptionData	105
8.31.2.24 EncryptionMode	105
8.31.2.25 EventForward	105
8.31.2.26 ExpectedProtocol	105
8.31.2.27 ExpectedValues	105
8.31.2.28 FindFriendsOptions	105
8.31.2.29 FindFriendsRequestList	105
8.31.2.30 FindFriendsResponseOnlineList	105
8.31.2.31 FindFriendsResponseRoomldList	105
8.31.2.32 GameCount	105
8.31.2.33 GameList	105
8.31.2.34 GameProperties	106
8.31.2.35 Group	106
8.31.2.36 Info	106
8.31.2.37 IsComingBack	
8.31.2.38 IsInactive	106
8.31.2.39 JoinMode	106
8.31.2.40 LobbyName	106
8.31.2.41 LobbyStats	106
8.31.2.42 LobbyType	106
8.31.2.43 MasterClientId	106
8.31.2.44 MasterPeerCount	107
8.31.2.45 MatchMakingType	107
8.31.2.46 NickName	107
8.31.2.47 PeerCount	107
8.31.2.48 PlayerProperties	107
8.31.2.49 PlayerTTL	107

xvi CONTENTS

		8.31.2.50	PluginName
		8.31.2.51	Plugins
		8.31.2.52	PluginVersion
		8.31.2.53	Position
		8.31.2.54	Properties
		8.31.2.55	PublishUserId
		8.31.2.56	ReceiverGroup
		8.31.2.57	Region
		8.31.2.58	Remove
		8.31.2.59	RoomName
		8.31.2.60	RoomOptionFlags
		8.31.2.61	Secret
		8.31.2.62	SuppressRoomEvents
		8.31.2.63	TargetActorNr
		8.31.2.64	UriPath
		8.31.2.65	UserId
		8.31.2.66	WebRpcParameters
		8.31.2.67	WebRpcReturnCode
		8.31.2.68	WebRpcReturnMessage
8.32	Photon	AnimatorV	Tiew Class Reference
			Description
	8.32.2	Member I	Enumeration Documentation
		8.32.2.1	ParameterType
		8.32.2.2	SynchronizeType
	8.32.3	Member I	Function Documentation
		8.32.3.1	CacheDiscreteTriggers
		8.32.3.2	DoesLayerSynchronizeTypeExist
		8.32.3.3	DoesParameterSynchronizeTypeExist
		8.32.3.4	GetLayerSynchronizeType
		8.32.3.5	GetParameterSynchronizeType
		8.32.3.6	GetSynchronizedLayers
		8.32.3.7	GetSynchronizedParameters
		8.32.3.8	OnPhotonSerializeView
		8.32.3.9	SetLayerSynchronized
		8.32.3.10	SetParameterSynchronized
8.33	Photon	LagSimula	ttionGui Class Reference
			Description
	8.33.2		Function Documentation
			OnGUI
		8.33.2.2	Start

CONTENTS xvii

	8.33.3	Member Data Documentation	3
		8.33.3.1 Visible	3
		8.33.3.2 Windowld	3
		8.33.3.3 WindowRect	3
	8.33.4	Property Documentation	3
		8.33.4.1 Peer	3
8.34	Photon	MessageInfo Struct Reference	3
	8.34.1	Detailed Description	4
	8.34.2	Constructor & Destructor Documentation	4
		8.34.2.1 PhotonMessageInfo	4
	8.34.3	Member Function Documentation	4
		8.34.3.1 ToString	4
	8.34.4	Member Data Documentation	4
		8.34.4.1 photonView	4
		8.34.4.2 sender	4
	8.34.5	Property Documentation	4
		8.34.5.1 timestamp	4
8.35	Photon	Network Class Reference	4
	8.35.1	Detailed Description	1:1
	8.35.2	Member Function Documentation	1:1
		8.35.2.1 AllocateSceneViewID	1:1
		8.35.2.2 AllocateViewID	!1
		8.35.2.3 CacheSendMonoMessageTargets	!1
		8.35.2.4 CallEvent	1:1
		8.35.2.5 CloseConnection	1:1
		8.35.2.6 ConnectToBestCloudServer	1:1
		8.35.2.7 ConnectToMaster	2
		8.35.2.8 ConnectToRegion	2
		8.35.2.9 ConnectUsingSettings	2
		8.35.2.10 CreateRoom	:3
		8.35.2.11 CreateRoom	3:
		8.35.2.12 CreateRoom	4
		8.35.2.13 Destroy	4
		8.35.2.14 Destroy	:5
		8.35.2.15 DestroyAll	6
		8.35.2.16 DestroyPlayerObjects	6
		8.35.2.17 DestroyPlayerObjects	:6
		8.35.2.18 Disconnect	:7
		8.35.2.19 EventCallback	:7
		8.35.2.20 FetchServerTimestamp	:7

xviii CONTENTS

8.35.2.21 FindFriends
8.35.2.22 FindGameObjectsWithComponent
8.35.2.23 GetCustomRoomList
8.35.2.24 GetPing
8.35.2.25 GetRoomList
8.35.2.26 InitializeSecurity
8.35.2.27 Instantiate
8.35.2.28 Instantiate
8.35.2.29 InstantiateSceneObject
8.35.2.30 JoinLobby
8.35.2.31 JoinLobby
8.35.2.32 JoinOrCreateRoom
8.35.2.33 JoinOrCreateRoom
8.35.2.34 JoinRandomRoom
8.35.2.35 JoinRandomRoom
8.35.2.36 JoinRandomRoom
8.35.2.37 JoinRoom
8.35.2.38 JoinRoom
8.35.2.39 LeaveLobby
8.35.2.40 LeaveRoom
8.35.2.41 LoadLevel
8.35.2.42 LoadLevel
8.35.2.43 LoadLevelAsync
8.35.2.44 LoadLevelAsync
8.35.2.45 NetworkStatisticsReset
8.35.2.46 NetworkStatisticsToString
8.35.2.47 OverrideBestCloudServer
8.35.2.48 RaiseEvent
8.35.2.49 Reconnect
8.35.2.50 ReconnectAndRejoin
8.35.2.51 RefreshCloudServerRating
8.35.2.52 ReJoinRoom
8.35.2.53 RemovePlayerCustomProperties
8.35.2.54 RemoveRPCs
8.35.2.55 RemoveRPCs
8.35.2.56 RemoveRPCsInGroup
8.35.2.57 SendOutgoingCommands
8.35.2.58 SetInterestGroups
8.35.2.59 SetInterestGroups
8.35.2.60 SetLevelPrefix

CONTENTS xix

	8.35.2.61	SetMasterClient	139
	8.35.2.62	SetPlayerCustomProperties	140
	8.35.2.63	SetReceivingEnabled	140
	8.35.2.64	SetReceivingEnabled	140
	8.35.2.65	SetSendingEnabled	140
	8.35.2.66	SetSendingEnabled	140
	8.35.2.67	SetSendingEnabled	140
	8.35.2.68	SetSendingEnabled	140
	8.35.2.69	SwitchToProtocol	141
	8.35.2.70	UnAllocateViewID	141
	8.35.2.71	WebRpc	141
8.35.3	Member D	Data Documentation	142
	8.35.3.1	BackgroundTimeout	142
	8.35.3.2	InstantiateInRoomOnly	142
	8.35.3.3	logLevel	142
	8.35.3.4	MAX_VIEW_IDS	142
	8.35.3.5	maxConnections	142
	8.35.3.6	PhotonServerSettings	143
	8.35.3.7	precisionForFloatSynchronization	143
	8.35.3.8	$precision For Quaternion Synchronization \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $	143
	8.35.3.9	precisionForVectorSynchronization	143
	8.35.3.10	PrefabCache	143
	8.35.3.11	SendMonoMessageTargets	143
	8.35.3.12	SendMonoMessageTargetType	143
	8.35.3.13	StartRpcsAsCoroutine	143
	8.35.3.14	UsePrefabCache	144
	8.35.3.15	UseRpcMonoBehaviourCache	144
	8.35.3.16	versionPUN	144
8.35.4	Property [Documentation	144
	8.35.4.1	AuthValues	144
	8.35.4.2	autoCleanUpPlayerObjects	144
	8.35.4.3	autoJoinLobby	144
	8.35.4.4	automaticallySyncScene	145
	8.35.4.5	CloudRegion	145
	8.35.4.6	connected	145
	8.35.4.7	connectedAndReady	145
	8.35.4.8	connecting	145
	8.35.4.9	connectionState	145
	8.35.4.10	connectionStateDetailed	145
	8.35.4.11	countOfPlayers	145

CONTENTS

		8.35.4.12 countOfPlayersInRooms	45
		8.35.4.13 countOfPlayersOnMaster	46
		8.35.4.14 countOfRooms	46
		8.35.4.15 CrcCheckEnabled	46
		8.35.4.16 EnableLobbyStatistics	46
		8.35.4.17 Friends	46
		8.35.4.18 FriendsListAge	46
		8.35.4.19 gameVersion	46
		8.35.4.20 inRoom	46
		8.35.4.21 insideLobby	47
		8.35.4.22 isMasterClient	47
		8.35.4.23 isMessageQueueRunning	47
		8.35.4.24 isNonMasterClientInRoom	47
		8.35.4.25 lobby	47
		8.35.4.26 LobbyStatistics	47
		8.35.4.27 masterClient	47
		8.35.4.28 MaxResendsBeforeDisconnect	48
		8.35.4.29 NetworkStatisticsEnabled	48
		8.35.4.30 offlineMode	48
		8.35.4.31 otherPlayers	48
		8.35.4.32 PacketLossByCrcCheck	48
		8.35.4.33 player	
		8.35.4.34 playerList	48
		8.35.4.35 playerName	49
		8.35.4.36 PrefabPool	49
		8.35.4.37 QuickResends	149
		8.35.4.38 ResentReliableCommands	49
		8.35.4.39 room	49
		8.35.4.40 sendRate	49
		8.35.4.41 sendRateOnSerialize	49
		8.35.4.42 Server	49
		8.35.4.43 ServerAddress	50
		8.35.4.44 ServerTimestamp	50
		8.35.4.45 time	50
		8.35.4.46 UseAlternativeUdpPorts	50
	8.35.5	Event Documentation	50
			150
8.36	Photon	.Realtime.PhotonPing Class Reference	50
	8.36.1	Member Function Documentation	
		8.36.1.1 Dispose	51

CONTENTS xxi

		8.36.1.2 Done	51
		8.36.1.3 StartPing	51
	8.36.2	Member Data Documentation	51
		8.36.2.1 DebugString	51
		8.36.2.2 Successful	51
8.37	Photon	PingManager Class Reference	51
	8.37.1	Member Function Documentation	52
		8.37.1.1 PingSocket	52
		8.37.1.2 ResolveHost	52
	8.37.2	Member Data Documentation	52
		8.37.2.1 Attempts	52
		8.37.2.2 IgnoreInitialAttempt	52
		8.37.2.3 MaxMilliseconsPerPing	52
		8.37.2.4 UseNative	52
	8.37.3	Property Documentation	52
		8.37.3.1 BestRegion	52
		8.37.3.2 Done	52
8.38	Photon	Player Class Reference	52
	8.38.1	Detailed Description	54
	8.38.2	Constructor & Destructor Documentation	54
		8.38.2.1 PhotonPlayer	54
	8.38.3	Member Function Documentation	54
		8.38.3.1 CompareTo	54
		8.38.3.2 CompareTo	54
		8.38.3.3 Equals	54
		8.38.3.4 Equals	54
		8.38.3.5 Equals	54
		8.38.3.6 Find	54
		8.38.3.7 Get	55
		8.38.3.8 GetHashCode	55
		8.38.3.9 GetNext	55
		8.38.3.10 GetNextFor	55
		8.38.3.11 GetNextFor	55
		8.38.3.12 SetCustomProperties	55
		8.38.3.13 ToString	55
		8.38.3.14 ToStringFull	
	8.38.4	Member Data Documentation	6
		8.38.4.1 IsLocal	6
		8.38.4.2 TagObject	
	8.38.5	Property Documentation	6

xxii CONTENTS

		8.38.5.1 AllProperties
		8.38.5.2 allProperties
		8.38.5.3 CustomProperties
		8.38.5.4 customProperties
		8.38.5.5 ID
		8.38.5.6 Islnactive
		8.38.5.7 islnactive
		8.38.5.8 isLocal
		8.38.5.9 IsMasterClient
		8.38.5.10 isMasterClient
		8.38.5.11 name
		8.38.5.12 NickName
		8.38.5.13 Userld
		8.38.5.14 userld
8.39	Photon	Rigidbody2DView Class Reference
	8.39.1	Detailed Description
	8.39.2	Member Function Documentation
		8.39.2.1 OnPhotonSerializeView
8.40	Photon	RigidbodyView Class Reference
	8.40.1	Detailed Description
	8.40.2	Member Function Documentation
		8.40.2.1 OnPhotonSerializeView
8.41	Photon	StatsGui Class Reference
	8.41.1	Detailed Description
	8.41.2	Member Function Documentation
		8.41.2.1 OnGUI
		8.41.2.2 Start
		8.41.2.3 TrafficStatsWindow
		8.41.2.4 Update
	8.41.3	Member Data Documentation
		8.41.3.1 buttonsOn
		8.41.3.2 healthStatsVisible
		8.41.3.3 statsOn
		8.41.3.4 statsRect
		8.41.3.5 statsWindowOn
		8.41.3.6 trafficStatsOn
		8.41.3.7 Windowld
8.42	Photon	Stream Class Reference
	8.42.1	Detailed Description
	8.42.2	Constructor & Destructor Documentation

CONTENTS xxiii

		8.42.2.1 PhotonStream
	8.42.3	Member Function Documentation
		8.42.3.1 PeekNext
		8.42.3.2 ReceiveNext
		8.42.3.3 SendNext
		8.42.3.4 Serialize
		8.42.3.5 Serialize
		8.42.3.6 Serialize
		8.42.3.7 Serialize
		8.42.3.8 Serialize
		8.42.3.9 Serialize
		8.42.3.10 Serialize
		8.42.3.11 Serialize
		8.42.3.12 Serialize
		8.42.3.13 Serialize
		8.42.3.14 SetReadStream
		8.42.3.15 ToArray
	8.42.4	Property Documentation
		8.42.4.1 Count
		8.42.4.2 isReading
		8.42.4.3 isWriting
8.43		StreamQueue Class Reference
		Detailed Description
	8.43.2	Constructor & Destructor Documentation
		8.43.2.1 PhotonStreamQueue
	8.43.3	Member Function Documentation
		8.43.3.1 Deserialize
		8.43.3.2 HasQueuedObjects
		8.43.3.3 ReceiveNext
		8.43.3.4 Reset
		8.43.3.5 SendNext
		8.43.3.6 Serialize
8.44		TransformView Class Reference
		Detailed Description
	8.44.2	Member Function Documentation
		8.44.2.1 OnPhotonSerializeView
		8.44.2.2 SetSynchronizedValues
	8.44.3	Member Data Documentation
		8.44.3.1 m_PositionModel
		8.44.3.2 m_RotationModel

xxiv CONTENTS

		8.44.3.3	m_ScaleModel	 . 166
8.45	Photon	TransformV	/iewPositionControl Class Reference	 . 167
	8.45.1	Constructo	or & Destructor Documentation	 . 167
		8.45.1.1	PhotonTransformViewPositionControl	 . 167
	8.45.2	Member F	function Documentation	 . 167
		8.45.2.1	GetExtrapolatedPositionOffset	 . 167
		8.45.2.2	GetNetworkPosition	 . 167
		8.45.2.3	OnPhotonSerializeView	 . 167
		8.45.2.4	SetSynchronizedValues	 . 167
		8.45.2.5	UpdatePosition	 . 168
8.46	Photon	TransformV	/iewPositionModel Class Reference	 . 168
	8.46.1	Member E	Enumeration Documentation	 . 168
		8.46.1.1	ExtrapolateOptions	 . 168
		8.46.1.2	InterpolateOptions	 . 169
	8.46.2	Member D	Oata Documentation	 . 169
		8.46.2.1	DrawErrorGizmo	 . 169
		8.46.2.2	ExtrapolateIncludingRoundTripTime	 . 169
		8.46.2.3	ExtrapolateNumberOfStoredPositions	 . 169
		8.46.2.4	ExtrapolateOption	 . 169
		8.46.2.5	ExtrapolateSpeed	 . 169
		8.46.2.6	InterpolateLerpSpeed	 . 169
		8.46.2.7	InterpolateMoveTowardsAcceleration	 . 169
		8.46.2.8	InterpolateMoveTowardsDeceleration	 . 169
		8.46.2.9	InterpolateMoveTowardsSpeed	 . 169
		8.46.2.10	InterpolateOption	 . 169
		8.46.2.11	InterpolateSpeedCurve	 . 169
		8.46.2.12	SynchronizeEnabled	 . 169
		8.46.2.13	TeleportEnabled	 . 169
		8.46.2.14	TeleportIfDistanceGreaterThan	 . 169
8.47	Photon	TransformV	/iewRotationControl Class Reference	 . 169
	8.47.1	Constructo	or & Destructor Documentation	 . 170
		8.47.1.1	PhotonTransformViewRotationControl	 . 170
	8.47.2	Member F	function Documentation	 . 170
		8.47.2.1	GetNetworkRotation	 . 170
		8.47.2.2	GetRotation	 . 170
		8.47.2.3	OnPhotonSerializeView	 . 170
8.48	Photon	TransformV	/iewRotationModel Class Reference	 . 170
	8.48.1		numeration Documentation	
		8.48.1.1	InterpolateOptions	 . 170
	8.48.2	Member D	Oata Documentation	 . 171

CONTENTS xxv

		8.48.2.1	InterpolateLerpSpeed	
		8.48.2.2	InterpolateOption	171
		8.48.2.3	InterpolateRotateTowardsSpeed	171
		8.48.2.4	SynchronizeEnabled	171
8.49	Photon	Transform\	ViewScaleControl Class Reference	171
	8.49.1	Construct	for & Destructor Documentation	171
		8.49.1.1	PhotonTransformViewScaleControl	171
	8.49.2	Member F	Function Documentation	171
		8.49.2.1	GetNetworkScale	171
		8.49.2.2	GetScale	171
		8.49.2.3	OnPhotonSerializeView	171
8.50	Photon	Transform\	ViewScaleModel Class Reference	171
	8.50.1	Member E	Enumeration Documentation	172
		8.50.1.1	InterpolateOptions	172
	8.50.2	Member [Data Documentation	172
		8.50.2.1	InterpolateLerpSpeed	172
		8.50.2.2	InterpolateMoveTowardsSpeed	172
		8.50.2.3	InterpolateOption	172
		8.50.2.4	SynchronizeEnabled	172
8.51	Photon	View Class	s Reference	172
	8.51.1	Detailed [Description	173
	8.51.2	Member F	Function Documentation	174
		8.51.2.1	DeserializeView	174
		8.51.2.2	Find	174
		8.51.2.3	Get	174
		8.51.2.4	Get	174
		8.51.2.5	OnMasterClientSwitched	174
		8.51.2.6	RefreshRpcMonoBehaviourCache	174
		8.51.2.7	RequestOwnership	174
		8.51.2.8	RPC	174
		8.51.2.9	RPC	175
		8.51.2.10	RpcSecure	175
		8.51.2.11	RpcSecure	175
		8.51.2.12	SerializeView	176
		8.51.2.13	ToString	176
		8.51.2.14	TransferOwnership	176
		8.51.2.15	TransferOwnership	176
	8.51.3	Member [Data Documentation	176
		8.51.3.1	currentMasterID	176
		8.51.3.2	group	176

XXVI

		8.51.3.3	instantiationId	76
		8.51.3.4	ObservedComponents	76
		8.51.3.5	onSerializeRigidBodyOption	76
		8.51.3.6	onSerializeTransformOption	76
		8.51.3.7	ownerld	76
		8.51.3.8	ownershipTransfer	76
		8.51.3.9	OwnerShipWasTransfered	76
		8.51.3.10	prefixBackup	77
		8.51.3.11	synchronization	77
	8.51.4	Property	Documentation	77
		8.51.4.1	CreatorActorNr	77
		8.51.4.2	instantiationData	77
		8.51.4.3	isMine	77
		8.51.4.4	isOwnerActive	77
		8.51.4.5	isSceneView	77
		8.51.4.6	owner	77
		8.51.4.7	OwnerActorNr	77
		8.51.4.8	prefix	77
		8.51.4.9	viewID	77
8.52	Photon	.Realtime.	PingMono Class Reference	77
	8.52.1	Detailed	Description	78
	8.52.2	Member	Function Documentation	78
		8.52.2.1	Dispose	78
		8.52.2.2	Done	78
		8.52.2.3	StartPing	78
8.53	PingMo	noEditor (Class Reference	78
	8.53.1	Detailed	Description	79
	8.53.2	Member	Function Documentation	79
		8.53.2.1	Dispose	79
		8.53.2.2	Done	79
		8.53.2.3	StartPing	79
8.54	Photon	.PunBeha	viour Class Reference	79
	8.54.1	Detailed	Description	31
	8.54.2	Member	Function Documentation	31
		8.54.2.1	OnConnectedToMaster	31
		8.54.2.2	OnConnectedToPhoton	31
		8.54.2.3	OnConnectionFail	31
		8.54.2.4	OnCreatedRoom	31
		8.54.2.5	OnCustomAuthenticationFailed	32
		8.54.2.6	OnCustomAuthenticationResponse	32

CONTENTS xxvii

	8.54.2./ UnDisconnectedFromPhoton
	8.54.2.8 OnFailedToConnectToPhoton
	8.54.2.9 OnJoinedLobby
	8.54.2.10 OnJoinedRoom
	8.54.2.11 OnLeftLobby
	8.54.2.12 OnLeftRoom
	8.54.2.13 OnLobbyStatisticsUpdate
	8.54.2.14 OnMasterClientSwitched
	8.54.2.15 OnOwnershipRequest
	8.54.2.16 OnOwnershipTransfered
	8.54.2.17 OnPhotonCreateRoomFailed
	8.54.2.18 OnPhotonCustomRoomPropertiesChanged
	8.54.2.19 OnPhotonInstantiate
	8.54.2.20 OnPhotonJoinRoomFailed
	8.54.2.21 OnPhotonMaxCccuReached
	8.54.2.22 OnPhotonPlayerActivityChanged
	8.54.2.23 OnPhotonPlayerConnected
	8.54.2.24 OnPhotonPlayerDisconnected
	8.54.2.25 OnPhotonPlayerPropertiesChanged
	8.54.2.26 OnPhotonRandomJoinFailed
	8.54.2.27 OnReceivedRoomListUpdate
	8.54.2.28 OnUpdatedFriendList
	8.54.2.29 OnWebRpcResponse
PunRP	C Class Reference
8.55.1	Detailed Description
RaiseE	ventOptions Class Reference
8.56.1	Detailed Description
8.56.2	Member Function Documentation
	8.56.2.1 Reset
8.56.3	Member Data Documentation
	8.56.3.1 CachingOption
	8.56.3.2 Default
	8.56.3.3 Encrypt
	8.56.3.4 ForwardToWebhook
	8.56.3.5 InterestGroup
	8.56.3.6 Receivers
	8.56.3.7 SequenceChannel
	8.56.3.8 TargetActors
Region	Class Reference
8.57.1	Constructor & Destructor Documentation
	PunRP0 8.55.1 RaiseEv 8.56.1 8.56.2 8.56.3

xxviii CONTENTS

		8.57.1.1	Region		 	 	 	 		189
		8.57.1.2	Region		 	 	 	 		189
	8.57.2	Member I	Function Documentation		 	 	 	 		189
		8.57.2.1	Parse		 	 	 	 		189
		8.57.2.2	ToString		 	 	 	 		189
	8.57.3	Member I	Data Documentation		 	 	 	 		189
		8.57.3.1	Cluster		 	 	 	 		189
		8.57.3.2	Code		 	 	 	 		190
		8.57.3.3	HostAndPort		 	 	 	 	-	190
		8.57.3.4	Ping		 	 	 	 		190
8.58	Room (Class Refe	rence		 	 	 	 		190
	8.58.1	Detailed I	Description		 	 	 	 		191
	8.58.2	Member I	Function Documentation		 	 	 	 	-	191
		8.58.2.1	ClearExpectedUsers		 	 	 	 	-	191
		8.58.2.2	SetCustomProperties .		 	 	 	 		191
		8.58.2.3	SetExpectedUsers		 	 	 	 	-	192
		8.58.2.4	SetPropertiesListedInLol	oby	 	 	 	 		192
		8.58.2.5	ToString		 	 	 	 	-	192
		8.58.2.6	ToStringFull		 	 	 	 		192
	8.58.3	Property	Documentation		 	 	 	 	-	193
		8.58.3.1	AutoCleanUp		 	 	 	 		193
		8.58.3.2	autoCleanUp		 	 	 	 		193
		8.58.3.3	EmptyRoomTtl		 	 	 	 		193
		8.58.3.4	ExpectedUsers		 	 	 	 		193
		8.58.3.5	expectedUsers		 	 	 	 	-	193
		8.58.3.6	IsOpen		 	 	 	 	-	193
		8.58.3.7	IsVisible		 	 	 	 		193
		8.58.3.8	MaxPlayers		 	 	 	 		193
		8.58.3.9	maxPlayers		 	 	 	 		193
		8.58.3.10	Name		 	 	 	 		193
		8.58.3.11	name		 	 	 	 		194
		8.58.3.12	open		 	 	 	 	-	194
		8.58.3.13	PlayerCount		 	 	 	 	-	194
		8.58.3.14	playerCount		 	 	 	 	-	194
		8.58.3.15	PlayerTtl		 	 	 	 	•	194
		8.58.3.16	PropertiesListedInLobby		 	 	 	 	•	194
		8.58.3.17	propertiesListedInLobby		 	 	 	 	•	194
		8.58.3.18	visible		 	 	 	 	•	194
8.59	Roomlr	nfo Class F	Reference		 	 	 	 	•	194
	8.59.1	Detailed I	Description		 	 	 	 	-	195

CONTENTS xxix

	8.59.2	Member Function Documentation
		8.59.2.1 Equals
		8.59.2.2 GetHashCode
		8.59.2.3 ToString
		8.59.2.4 ToStringFull
	8.59.3	Member Data Documentation
		8.59.3.1 autoCleanUpField
		8.59.3.2 emptyRoomTtlField
		8.59.3.3 expectedUsersField
		8.59.3.4 maxPlayersField
		8.59.3.5 nameField
		8.59.3.6 openField
		8.59.3.7 playerTtlField
		8.59.3.8 visibleField
	8.59.4	Property Documentation
		8.59.4.1 CustomProperties
		8.59.4.2 customProperties
		8.59.4.3 IsLocalClientInside
		8.59.4.4 isLocalClientInside
		8.59.4.5 IsOpen
		8.59.4.6 IsVisible
		8.59.4.7 MaxPlayers
		8.59.4.8 maxPlayers
		8.59.4.9 Name
		8.59.4.10 name
		8.59.4.11 open
		8.59.4.12 PlayerCount
		8.59.4.13 playerCount
		8.59.4.14 removedFromList
		8.59.4.15 visible
8.60	RoomO	ptions Class Reference
	8.60.1	Detailed Description
	8.60.2	Member Data Documentation
		8.60.2.1 CustomRoomProperties
		8.60.2.2 CustomRoomPropertiesForLobby
		8.60.2.3 EmptyRoomTtl
		8.60.2.4 MaxPlayers
		8.60.2.5 PlayerTtl
		8.60.2.6 Plugins
	8.60.3	Property Documentation

CONTENTS

		8.60.3.1	CleanupCacheOnLeave	200
		8.60.3.2	cleanupCacheOnLeave	200
		8.60.3.3	customRoomProperties	200
		8.60.3.4	customRoomPropertiesForLobby	200
		8.60.3.5	DeleteNullProperties	200
		8.60.3.6	IsOpen	200
		8.60.3.7	isOpen	200
		8.60.3.8	IsVisible	200
		8.60.3.9	isVisible	200
		8.60.3.10	maxPlayers	200
		8.60.3.11	plugins	201
		8.60.3.12	PublishUserId	201
		8.60.3.13	publishUserId	201
		8.60.3.14	SuppressRoomEvents	201
		8.60.3.15	suppressRoomEvents	201
8.61	UnityE	ngine.Scer	neManagement.SceneManager Class Reference	201
	8.61.1	Detailed I	Description	201
	8.61.2	Member I	Function Documentation	201
		8.61.2.1	LoadScene	201
		8.61.2.2	LoadScene	201
		8.61.2.3	LoadSceneAsync	201
		8.61.2.4	LoadSceneAsync	201
8.62	Scenel	ManagerHe	elper Class Reference	201
	8.62.1	Property	Documentation	202
		8.62.1.1	ActiveSceneBuildIndex	202
		8.62.1.2	ActiveSceneName	202
8.63	Server	Settings C	lass Reference	202
	8.63.1	Detailed I	Description	203
	8.63.2	Member I	Enumeration Documentation	203
		8.63.2.1	HostingOption	203
	8.63.3	Member I	Function Documentation	203
		8.63.3.1	IsAppld	203
		8.63.3.2	ResetBestRegionCodeInPreferences	203
		8.63.3.3	ToString	203
		8.63.3.4	UseCloud	203
		8.63.3.5	UseCloud	203
		8.63.3.6	UseCloudBestRegion	203
		8.63.3.7	UseMyServer	204
	8.63.4	Member I	Data Documentation	204
		8.63.4.1	AppID	204

CONTENTS xxxi

		8.63.4.2	ChatAppID	204
		8.63.4.3	DisableAutoOpenWizard	204
		8.63.4.4	EnabledRegions	204
		8.63.4.5	EnableLobbyStatistics	204
		8.63.4.6	HostType	204
		8.63.4.7	JoinLobby	204
		8.63.4.8	NetworkLogging	204
		8.63.4.9	PreferredRegion	204
		8.63.4.10	Protocol	204
		8.63.4.11	PunLogging	204
		8.63.4.12	RpcList	204
		8.63.4.13	RunInBackground	204
		8.63.4.14	ServerAddress	204
		8.63.4.15	ServerPort	204
		8.63.4.16	VoiceAppID	204
		8.63.4.17	VoiceServerPort	204
	8.63.5	Property [Documentation	204
		8.63.5.1	BestRegionCodeInPreferences	204
8.64	Photon	AnimatorVi	iew.SynchronizedLayer Class Reference	204
	8.64.1	Member D	Data Documentation	205
		8.64.1.1	LayerIndex	205
		8.64.1.2	SynchronizeType	205
8.65	Photon	AnimatorVi	ew.SynchronizedParameter Class Reference	205
	8.65.1	Member E	Oata Documentation	205
		8.65.1.1	Name	205
		8.65.1.2	SynchronizeType	205
			Type	
8.66	TypedL	obby Class	Reference	205
	8.66.1	Detailed D	Description	206
	8.66.2	Construct	or & Destructor Documentation	206
		8.66.2.1	TypedLobby	206
		8.66.2.2	TypedLobby	206
	8.66.3	Member F	function Documentation	206
		8.66.3.1	ToString	206
	8.66.4	Member D	Oata Documentation	206
		8.66.4.1	Default	206
		8.66.4.2	Name	206
		8.66.4.3	Type	206
	8.66.5		Documentation	
		8.66.5.1	IsDefault	206

xxxii CONTENTS

	8.67	TypedL	.obbyInfo (Class Reference		206
		8.67.1	Member	Function Documentation		206
			8.67.1.1	ToString		207
		8.67.2	Member	Data Documentation		207
			8.67.2.1	PlayerCount		207
			8.67.2.2	RoomCount		207
	8.68	WebRp	cRespons	se Class Reference		207
		8.68.1	Detailed	Description		207
		8.68.2	Construc	tor & Destructor Documentation		207
			8.68.2.1	WebRpcResponse		207
		8.68.3	Member	Function Documentation		207
			8.68.3.1	ToStringFull		207
		8.68.4	Property	Documentation		208
			8.68.4.1	DebugMessage		208
			8.68.4.2	Name		208
			8.68.4.3	Parameters		208
			8.68.4.4	ReturnCode		208
9	File I	Docume	entation			209
	9.1	C:/Dev	/photon-sc	dk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/general.md	File Reference	209
	9.2	C:/Dev	/photon-so	dk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/main.md Fi	le Reference .	209
	9.3		•	dk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/optionalGui		209
	9.4		•	dk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/photonState		209
	9.5	C:/Dev	/photon-sc	dk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/publicApi.m	nd File Reference	<mark>e</mark> 209
	9.6		•	dk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity etwork/CustomTypes.cs File Reference		209
		9.6.1	Detailed	Description		209
	9.7		•	dk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity etwork/Enums.cs File Reference	•	210
		9.7.1	Detailed	Description		211
		9.7.2	Enumera	tion Type Documentation		211
			9.7.2.1	CloudRegionCode		211
			9.7.2.2	CloudRegionFlag		211
			9.7.2.3	ConnectionState		212
			9.7.2.4	EncryptionMode		212
	9.8		•	dk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity etwork/Extensions.cs File Reference	•	212
		9.8.1	Typedef I	Documentation		213
			9.8.1.1	Hashtable		213
			9.8.1.2	SupportClassPun		213

CONTENTS xxxiii

9	.9			lk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photonetwork/FriendInfo.cs File Reference			213
9	.10	C:/Dev/	/photon-sd	k-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon	Unity	Networking/←	
		Plugins	/PhotonNe	etwork/GizmoType.cs File Reference			213
9	.11			lk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photonetwork/LoadbalancingPeer.cs File Reference			213
		9.11.1	Enumera	tion Type Documentation			215
			9.11.1.1	AuthModeOption			215
			9.11.1.2	CustomAuthenticationType			215
			9.11.1.3	EventCaching			215
			9.11.1.4	JoinMode			216
			9.11.1.5	LobbyType			216
			9.11.1.6	MatchmakingMode			216
			9.11.1.7	PropertyTypeFlag			217
			9.11.1.8	ReceiverGroup			217
9	.12	C:/Dev/	/photon-sd	lk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon	Unity	Networking/←	
		Plugins	/PhotonNe	etwork/NetworkingPeer.cs File Reference			217
		9.12.1	Typedef [Documentation			218
			9.12.1.1	Hashtable			218
			9.12.1.2	SupportClassPun			218
		9.12.2	Enumera	tion Type Documentation			218
			9.12.2.1	ServerConnection			218
9	.13			lk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon etwork/PhotonClasses.cs File Reference			218
		9.13.1	Detailed I	Description			219
		9.13.2	Typedef [Documentation			219
			9.13.2.1	Hashtable			219
			9.13.2.2	SupportClassPun			219
9	.14		•	lk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photonetwork/PhotonHandler.cs File Reference			219
				Documentation			
		5.14.1		Debug			
				Hashtable			
				SupportClassPun			
0	15	C:/Dov		lk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon			220
9	.13		•	etwork/PhotonLagSimulationGui.cs File Reference	-		220
		9.15.1	Detailed I	Description			220
9	.16		•	k-dotnet/Unity/PhotonNetworking-Classic/Assets/Photonetwork/PhotonNetwork.cs File Reference	-		220
		9.16.1	Typedef [Documentation			220
			9.16.1.1	Debug			220
			9.16.1.2	Hashtable			220

CONTENTS

9.17		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon //PhotonNetwork/PhotonPing.cs File Reference	-		221
9.18		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon //PhotonNetwork/PhotonPlayer.cs File Reference	•	•	221
	9.18.1	Typedef Documentation			221
		9.18.1.1 Hashtable			221
9.19		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon //PhotonNetwork/PhotonStatsGui.cs File Reference	•	•	221
	9.19.1	Detailed Description			221
9.20		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon /PhotonNetwork/PhotonStreamQueue.cs File Reference		•	222
9.21		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon //PhotonNetwork/PhotonView.cs File Reference	-		222
	9.21.1	Enumeration Type Documentation			222
		9.21.1.1 OnSerializeRigidBody			222
		9.21.1.2 OnSerializeTransform			222
		9.21.1.3 OwnershipOption			223
		9.21.1.4 ViewSynchronization			223
9.22		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon //PhotonNetwork/PingCloudRegions.cs File Reference			223
	9.22.1	Typedef Documentation			223
		9.22.1.1 Debug			223
		9.22.1.2 SupportClassPun			223
9.23		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon //PhotonNetwork/Room.cs File Reference	-		223
9.24		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon //PhotonNetwork/RoomInfo.cs File Reference			224
9.25		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon /PhotonNetwork/RPC.cs File Reference			224
	9.25.1	Detailed Description			224
9.26		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon/PhotonNetwork/ServerSettings.cs File Reference			224
	9.26.1	Detailed Description			224
9.27		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon/PhotonNetwork/Views/PhotonAnimatorView.cs File Reference	•	•	224
9.28		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon/PhotonNetwork/Views/PhotonRigidbody2DView.cs File Reference	Unity	Networking/←	225
9.29		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon/PhotonNetwork/Views/PhotonRigidbodyView.cs File Reference		Networking/←	225
9.30		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon/PhotonNetwork/Views/PhotonTransformView.cs File Reference	Unity	Networking/←	225
9.31		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon //PhotonNetwork/Views/PhotonTransformViewPositionControl.cs File	Unity Referen	Networking/↔	225
9.32		/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon //PhotonNetwork/Views/PhotonTransformViewPositionModel.cs File F	Unity Reference	Networking/← e	226

CONTENTS XXXV

9.33	$C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/\leftrightarrow Plugins/PhotonNetwork/Views/PhotonTransformViewRotationControl.cs \\ File & Reference \\ \dots \dots \dots \\ \vdots \\ Networking/\leftrightarrow PhotonNetwork/Views/PhotonTransformViewRotationControl.cs \\ File & Reference \\ \dots \dots \dots \\ \vdots \\ Networking/\leftrightarrow PhotonNetwork/Views/PhotonTransformViewRotationControl.cs \\ File & Reference \\ \dots \dots \\ \dots \\ Networking/\leftrightarrow PhotonNetwork/Views/PhotonTransformViewRotationControl.cs \\ File & Reference \\ \dots \\ \dots \\ \dots \\ \dots \\ Networking/\leftrightarrow PhotonNetwork/Views/PhotonTransformViewRotationControl.cs \\ File & Reference \\ \dots \\ $	226
9.34	$C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/ \\ \vdash Plugins/PhotonNetwork/Views/PhotonTransformViewRotationModel.cs \\ \vdash Reference \\ \vdash$	226
9.35	$\label{lem:control} C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon & Unity & Networking/\\ Plugins/PhotonNetwork/Views/PhotonTransformViewScaleControl.cs & File Reference & $	226
9.36	$C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/\longleftrightarrow \\ Plugins/PhotonNetwork/Views/PhotonTransformViewScaleModel.cs \\ File Reference \\ $	226
9.37	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/Channel ← CreationOptions.cs File Reference	226
9.38	$C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChannelWell \leftarrow KnownProperties.cs File Reference$	227
9.39	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChatChannel.cs File Reference	227
9.40	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChatClient.cs File Reference	227
9.41	$C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChatDisconnect \leftarrow Cause.cs \ File \ Reference \\ \ldots \\ \ldots \\ \ldots \\ \ldots$	228
9.42	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChatEvent ← Code.cs File Reference	228
9.43	$C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChatOperation \\ \leftarrow Code.cs\ File\ Reference \\ \ldots \\ \ldots \\ \ldots \\ \ldots$	228
9.44	$C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChatParameter \leftarrow Code.cs\ File\ Reference \ $	228
9.45	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChatPeer.cs File Reference	229
9.46	C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChatState.cs File Reference	229
9.47	$C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/ChatUser \leftrightarrow Status.cs \ File \ Reference \\ \ldots \\ \ldots$	230
9.48	$C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChatApi/IChatClient \leftarrow Listener.cs File Reference$	230
Index		231

Main Page

Introduction

Photon is a real-time multiplayer game development framework that is fast, lean and flexible. Photon consists of a server and multiple client SDKs for major platforms.

Photon Unity Network (PUN) is our is our take on a Unity specific, high-level solution: Matchmaking, easy to use callbacks, components to synchronize GameObjects, Remote Procedure Calls (RPCs) and similar features provide a great start. Beyond that is a solid, extensive API for more advanced control.

Full source code is available, so you can scale this plugin to support any type of multiplayer game you come up with.

This plugin is compatible with the managed Photon Cloud service, which runs Photon Servers for you. A setup window registers you (for free) in less than a minute.

Most notable features:

- · Dead-easy API
- Lots of demos and an extensive PUN Basics Tutorial
- Server available as hosted service (free for development) or as "On Premise"
- · Load-balanced! Scales across servers (with no extra effort)
- · Outstanding performance of the Photon Server
- Dedicated servers. No NAT punch-through needed
- Offline mode: re-use your multiplayer code in singleplayer game modes

First Steps

Import PUN into a new, empty project. Register via the pop up "wizard" (ALT+P) to get you a free Photon Cloud subscription (saving an initial Appld for you). Now you're ready to run and dissect the Demos.

Make sure to open and code the PUN Basics Tutorial.

General Documentation (API)

Continue reading the General Documentation.

Check out the growing doc pages online: http://doc.photonengine.com/en-us/pun/current

2 Main Page

General Documentation

Brief overview of Photon, subscriptions, hosting options and how to start.

2.1 Photon

Unlike Unity's built-in networking or Bolt, PUN always connects to a dedicated server which provides rooms, match-making and in-room communication for players. Behind the scenes Photon Unity Networking uses more than one server: Several "Game Servers" run the actual rooms (matches) while a "Master Server" keeps track of rooms and match players.

You have two options for the server side.

Exit Games Cloud

The Exit Games Cloud is a service which provides hosted and load balanced Photon Servers for you, fully managed by Exit Games. Free trials are available and subscription costs for commercial use are competitively low.

The service runs a fixed logic, so you can't implement your own server-side game logic. Instead, the clients need to be authoritative.

Clients are separated by "application id", which relates to your game title and a "game version". With that, your players won't clash with those of another developer or older game iterations.

Subscriptions bought in Asset Store

Follow these steps when you bought an asset that includes a Photon Cloud subscription:

- Open the Dashboard and login.
 https://dashboard.photonengine.com
- Select the application to upgrade and click "Add Coupon / PUN+".
- · Enter your Unity Invoice Number.

Find your Unity Invoice Number in the Unity AssetStore:

https://www.assetstore.unity3d.com/en/#!/account/transactions

From the drop-down select the payment method used in your purchase.

Navigate to your purchase and copy the number following the "#" symbol (excluding the "#" and spaces).

4 General Documentation

Photon Server SDK

As alternative to the Photon Cloud service, you can run your own server and develop server side logic on top of our "Load Balancing" C# solution. This gives you full control of the server logic.

The Photon Server SDK can be downloaded on: www.exitgames.com/en/OnPremise/Download

Starting the Server: doc.exitgames.com/en/onpremise/current/getting-started/photon-server-in-5m:

Photon Unity Networking - First steps

When you import PUN, the "Wizard" window will popup. Either enter your email address to register for the cloud, skip this step to enter the Appld of an existing account or switch to "self hosted" Photon to enter your server's address.

This creates a configuration for either the cloud service or your own Photon server in the project: PhotonServer← Settings.

PUN consists of quite a few files, however there's only one that truly matters: **PhotonNetwork**. This class contains all functions and variables needed. If you ever have custom requirements, you can always modify the source files - this plugin is just an implementation of **Photon** after all.

To use PUN from UnityScript, move both folders "PhotonNetwork" and "UtilityScripts" to the Assets\ folder.

To show you how this API works, here are a few examples right away.

2.1.1 Master Server And Lobby

PUN always uses a master server and one or more game servers. The master server manages currently running games on the various game servers and will provide a game server address when you join or create a room. PUN (the client) automatically switches to that game server.

Individual matches are known as Rooms. They are independent of each other and identified by name. Rooms are grouped into one or multiple lobbies. Lobbies are an optional part in matchmaking. If you don't use custom lobbies explicitly, PUN will use a single lobby for all rooms.

By default, PUN will join the default lobby after connecting. This lobby sends a list of existing rooms to the client, so the player can pick a room (by name or some properties listed). Access the current list by using PhotonNetwork. GetRoomList(). The lists is updated in intervals to keep traffic low.

Clients don't have to join a lobby to join or create rooms. If you don't want to show a list of rooms in your client, set PhotonNetwork.autoJoinLobby = false before you connect and your clients will skip the lobby.

You can use more than one lobby to organize room-lists as needed for your game. PhotonNetwork.JoinLobby is the method to join a specific lobby. You can make them up on the client side - the server will keep track of them. As long as name and type are the same, the TypedLobby will be the same for all clients, too.

A client is always just in one lobby and while being in a lobby, creating a room will relate to this lobby, too. Multiple lobbies mean the clients get shorter rooms lists, which is good. There is no limit to the rooms lists.

A parameter in JoinRoom, JoinRandomRoom and CreateRoom enables you to select a lobby without joining it.

Players won't notice each other in the Lobby and can't send data (to prevent issues when it's getting crowded).

The servers are all run on dedicated machines - there is no such thing as player-hosted 'servers'. You don't have to bother remembering about the server organization though, as the API all hides this for you.

```
PhotonNetwork.ConnectUsingSettings("v1.0");
```

The code above is required to make use of any PhotonNetwork features. It sets your client's game version and uses the setup-wizard's config (stored in: PhotonServerSettings). The wizard can also be used when you host Photon yourself. Alternatively, use Connect() and you can ignore the PhotonServerSettings file.

2.1 Photon 5

Versioning

The Photon Cloud uses your appID to separate your players from everyone else's.

Within one Appld, you can deliberately separate clients/players by the "Game Version" string, which is set in the "connect" methods (as parameter).

Note: As we can't guarantee that different Photon Unity Networking versions are compatible with each other, we add the PUN version to your game's version. This literally adds "_" + PhotonNetwork.versionPUN to your Game Version string.

Creating and Joining Games

Next, you'll want to join or create a room. The following code showcases some required functions:

```
//Join a room
PhotonNetwork.JoinRoom(roomName);

//Create this room.
PhotonNetwork.CreateRoom(roomName);

// Fails if it already exists and calls: OnPhotonCreateGameFailed

//Tries to join any random game:
PhotonNetwork.JoinRandomRoom();

//Fails if there are no matching games: OnPhotonRandomJoinFailed
```

A list of currently running games is provided by the master server's lobby. It can be joined like other rooms but only provides and updates the list of rooms. The PhotonNetwork plugin will automatically join the lobby after connecting. When you're joining a room, the list will no longer update.

To display the list of rooms (in a lobby):

```
foreach (RoomInfo game in PhotonNetwork.GetRoomList())
{
    GUILayout.Label(game.name + " " + game.playerCount + "/" + game.maxPlayers);
}
```

Alternatively, the game can use random matchmaking: It will try to join any room and fail if none has room for another player. In that case: Create a room without name and wait until other players join it randomly.

Advanced Matchmaking & Room Properties

Fully random matchmaking is not always something players enjoy. Sometimes you just want to play a certain map or just two versus two.

In Photon Cloud and Loadbalancing, you can set arbitrary room properties and filter for those in JoinRandom.

Room Properties and the Lobby

Room properties are synced to all players in the room and can be useful to keep track of the current map, round, starttime, etc. They are handled as Hashtable with string keys. Preferably short keys.

You can forward selected properties to the lobby, too. This makes them available for listing them and for random matchmaking, too. Not all room properties are interesting in the lobby, so you define the set of properties for the lobby on room creation.

6 General Documentation

Note that "ai" is not a key in the room-properties yet. It won't show up in the lobby until it's set in the game via Room.SetCustomProperties(). When you change the values for "map" or "ai", they will be updated in the lobby with a short delay, too.

Keep the list short to make sure performance doesn't suffer from loading the list.

Filtering Room Properties in Join Random

In JoinRandom, you could pass a Hashtable with expected room properties and max player value. These work as filters when the server selects a "fitting" room for you.

If you pass more filter properties, chances are lower that a room matches them. Better limit the options.

Make sure you never filter for properties that are not known to the lobby (see above).

MonoBehaviour Callbacks

PUN uses several callbacks to let your game know about state changes like "connected" or "joined a game". All you have to do is implement the fitting method in any MonoBehaviour and it gets called when the event happens.

To get a good overview of available callbacks, take a look at the class Photon.PunBehaviour. If you make your script a PunBehaviour (instead of a MonoBehaviour), you can override individual callbacks easily. If you begin to type "override", your coding IDE should provide you a list of callbacks, so they are easy to find while coding, too.

This covers the basics of setting up game rooms. Next up is actual communication in games.

Sending messages in rooms

Inside a room you are able to send network messages to other connected players. Furthermore you are able to send buffered messages that will also be sent to players that connect in the future (for spawning your player for instance).

Sending messages can be done using two methods. Either RPCs or by using the PhotonView property On SerializePhotonView. There is more network interaction though. You can listen for callbacks for certain network events (e.g. OnPhotonInstantiate, OnPhotonPlayerConnected) and you can trigger some of these events (Photon Network.Instantiate). Don't worry if you're confused by the last paragraph, next up we'll explain for each of these subjects.

Using Groups in PUN

Groups are not synchronized when they are changed on any PhotonView. It's up to the developer to keep photonviews in the same groups on all clients, if that's needed. Using different group numbers for the same photonview on several clients will cause some inconsistent behaviour.

Some network messages are checked for their receiver group at the receiver side only, namely:

- RPCS that are targeted to a single player (or MasterClient)
- RPCS that are buffered (AllBuffered/OthersBuffered).
- This includes PhotonNetwork.Instantiate (as it is buffered).

Technical reason for this: the photon server only supports interestgroups for messages that are not cached and are not targetted at sepcific actor(s). This might change in the future.

2.1 Photon 7

PhotonView

PhotonView is a script component that is used to send messages (RPCs and OnSerializePhotonView). You need to attach the PhotonView to your games gameobjects. Note that the PhotonView is very similar to Unity's NetworkView.

At all times, you need at least one PhotonView in your game in order to send messages and optionally instantiate/allocate other PhotonViews.

To add a PhotonView to a gameobject, simply select a gameobject and use: "Components/Miscellaneous/Photon View".

Observe Transform

If you attach a Transform to a PhotonView's Observe property, you can choose to sync Position, Rotation and Scale or a combination of those across the players. This can be a great help for prototyping or smaller games. Note: A change to any observed value will send out all observed values - not just the single value that's changed. Also, updates are not smoothed or interpolated.

Observe MonoBehaviour

A PhotonView can be set to observe a MonoBehaviour. In this case, the script's OnPhotonSerializeView method will be called. This method is called for writing an object's state and for reading it, depending on whether the script is controlled by the local player.

The simple code below shows how to add character state synchronization with just a few lines of code more:

If you send something "ReliableDeltaCompressed", make sure to always write data to the stream in the same order. If you write no data to the PhotonStream, the update is not sent. This can be useful in pauses. Now on, to yet another way to communicate: RPCs.

2.1.2 Remote Procedure Calls

Remote Procedure Calls (RPCs) are exactly what the name implies: methods that can be called on remote clients in the same room. To enable remote calls for a method of a MonoBehaviour, you must apply the attribute: [PunRPC]. A PhotonView instance is needed on the same GameObject, to call the marked functions.

```
[PunRPC]
void ChatMessage(string a, string b)
{
    Debug.Log("ChatMessage " + a + " " + b);
}
```

To call the method from any script, you need access to a PhotonView object. If your script derives from Photon.

MonoBehaviour, it has a photonView field. Any regular MonoBehaviour or GameObject can use: PhotonView.

Get(this) to get access to its PhotonView component and then call RPCs on it.

8 General Documentation

```
PhotonView photonView = PhotonView.Get(this);
photonView.RPC("ChatMessage", PhotonTargets.All, "jup", "and jup!");
```

So, instead of directly calling the target method, you call RPC() on a PhotonView. Provide the name of the method to call, which players should call the method and then provide a list of parameters.

Careful: The parameters list used in RPC() has to match the number of expected parameters! If the receiving client can't find a matching method, it will log an error. There is one exception to this rule: The last parameter of a RPC method can be of type PhotonMessageInfo, which will provide some context for each call.

```
[PunRPC]
void ChatMessage(string a, string b, PhotonMessageInfo info)
{
    Debug.Log(String.Format("Info: {0} {1} {2}", info.sender, info.photonView, info.timestamp));
}
```

Timing for RPCs and Loading Levels

RPCs are called on specific PhotonViews and always target the matching one on the remote client. If the remote client does not know the fitting PhotonView, the RPC is lost.

A typical cause for lost RPCs is when clients load and set up levels. One client is faster or in the room for a longer time and sends important RPCs for objects that are not yet loaded on the other clients. The same happens when RPCs are buffered.

The solution is to pause the message queue, during scene loading. This code shows how how you can do it:

```
private IEnumerator MoveToGameScene()
{
    // Temporary disable processing of futher network messages
    PhotonNetwork.isMessageQueueRunning = false;
    Application.LoadLevel(levelName);
}
```

Alternatively you can use PhotonNetwork.LoadLevel. It temporarily disables the message queue as well.

Disabling the message queue will delay incoming and outgoing messages until the queue is unlocked. Obviously, it's very important to unlock the queue when you're ready to go on.

RPCs that belonged to the previously loaded scene but still arrived will now be discarded. But you should be able to define a break between both scenes by RPC.

Various topics

2.1.3 Instantiating Networked Objects

In about every game you need to instantiate one or more player objects for every player. There are various options to do so which are listed below.

PhotonNetwork.Instantiate

PUN can automatically take care of spawning an object by passing a starting position, rotation and a prefab name to the PhotonNetwork.Instantiate method. Requirement: The prefab should be available directly under a Resources/ folder so that the prefab can be loaded at run time. Watch out with webplayers: Everything in the resources folder will be streamed at the very first scene per default. Under the webplayer settings you can specify the first level that uses assets from the Resources folder by using the "First streamed level". If you set this to your first game scene, your preloader and mainmenu will not be slowed down if they don't use the Resources folder assets.

```
void SpawnMyPlayerEverywhere()
{
    PhotonNetwork.Instantiate("MyPrefabName", new Vector3(0,0,0), Quaternion.identity, 0);
    //The last argument is an optional group number, feel free to ignore it for now.
}
```

2.1 Photon 9

Gain more control: Manually instantiate

If don't want to rely on the Resources folders to instantiate objects over the network you'll have to manually Instantiate objects as shown in the example at the end of this section.

The main reason for wanting to instantiate manually is gaining control over what is downloaded when for streaming webplayers. The details about streaming and the Resources folder in Unity can be found here.

If you spawn manually, you will have to assign a PhotonViewID yourself, these viewID's are the key to routing network messages to the correct gameobject/scripts. The player who wants to own and spawn a new object should allocate a new viewID using PhotonNetwork.AllocateViewID();. This PhotonViewID should then be send to all other players using a PhotonView that has already been set up (for example an existing scene PhotonView). You will have to keep in mind that this RPC needs to be buffered so that any clients that connect later will also receive the spawn instructions. Then the RPC message that is used to spawn the object will need a reference to your desired prefab and instantiate this using Unity's GameObject.Instantiate. Finally you will need to set setup the PhotonViews attached to this prefab by assigning all PhotonViews a PhotonViewID.

If you want to use asset bundles to load your network objects from, all you have to do is add your own assetbundle loading code and replace the "playerPrefab" from the example with the prefab from your asset bundle.

Offline mode

Offline mode is a feature to be able to re-use your multiplayer code in singleplayer game modes as well.

Mike Hergaarden: At M2H we had to rebuild our games several times as game portals usually require you to remove multiplayer functionality completely. Furthermore, being able to use the same code for single and multiplayer saves a lot of work on itself.

The most common features that you'll want to be able to use in singleplayer are sending RPCs and using PhotonNetwork.Instantiate. The main goal of offline mode is to disable nullreferences and other errors when using PhotonNetwork functionality while not connected. You would still need to keep track of the fact that you're running a singleplayer game, to set up the game etc. However, while running the game, all code should be reusable.

You need to manually enable offline mode, as PhotonNetwork needs to be able to distinguish erroneous from intended behaviour. Enabling this feature is very easy:

```
PhotonNetwork.offlineMode = true;
```

You can now reuse certain multiplayer methods without generating any connections and errors. Furthermore there is no noticeable overhead. Below follows a list of PhotonNetwork functions and variables and their results during offline mode:

PhotonNetwork.player The player ID is always -1 PhotonNetwork.playerName Works as expected. Photon← Network.playerList Contains only the local player PhotonNetwork.otherPlayers Always empty PhotonNetwork.time returns Environment.TickCount or a more precise timer if enabled; PhotonNetwork.isMasterClient Always true

10 General Documentation

PhotonNetwork.AllocateViewID() Works as expected. PhotonNetwork.Instantiate Works as expected Photon← Network.Destroy Works as expected. PhotonNetwork.RemoveRPCs/RemoveRPCsInGroup/SetReceiving← Enabled/SetSendingEnabled/SetLevelPrefix While these make no sense in Singleplayer, they will not hurt either. PhotonView.RPC Works as expected.

Note that using other methods than the ones above can yield unexpected results and some will simply do nothing. E.g. PhotonNetwork.room will, obviously, return null. If you intend on starting a game in singleplayer, but move it to multiplayer at a later stage, you might want to consider hosting a 1 player game instead; this will preserve buffered RPCs and Instantiation calls, whereas offline mode Instantiations will not automatically carry over after Connecting.

Either set PhotonNetwork.offlineMode = false; or Simply call Connect() to stop offline mode.

Limitations

Views and players

For performance reasons, the PhotonNetwork API supports up to 1000 PhotonViews per player and a maximum of 2,147,483 players (note that this is WAY higher than your hardware can support!). You can easily allow for more PhotonViews per player, at the cost of maximum players. This works as follows: PhotonViews send out a viewID for every network message. This viewID is an integer and it is composed of the player ID and the player's view ID. The maximum size of an int is 2,147,483,647, divided by our MAX_VIEW_IDS(1000) that allows for over 2 million players, each having 1000 view IDs. As you can see, you can easily increase the player count by reducing the MAX_VIEW_IDS. The other way around, you can give all players more VIEW_IDS at the cost of less maximum players. It is important to note that most games will never need more than a few view ID's per player (one or two for the character..and that's usually it). If you need much more then you might be doing something wrong! It is extremely inefficient to assign a PhotonView and ID for every bullet that your weapon fires, instead keep track of your fire bullets via the player or weapon's PhotonView.

There is room for improving your bandwidth performance by reducing the int to a short (value range: 32,768 to 32,768). By setting MAX_VIEW_IDS to 32 you can then still support 1023 players Search for "//LIMITS NETWO RKVIEWS&PLAYERS" for all occurrences of the int viewID. Furthermore, currently the API is not using uint/ushort but only the positive range of the numbers. This is done for simplicity and the usage of viewIDs is not a crucial performance issue for most situations.

Groups and Scoping

The PhotonNetwork plugin does not support network groups fully. See above: "Using Groups in PUN".

Unity's "scope" feature is not implemented.

Feedback

We are interested in your feedback, as this solution is an ongoing project for us. Let us know if something was too hidden, missing or not working. To let us know, post in our Forum: forum.exitgames.com

F.A.Q.

Can I use multiple PhotonViews per GameObject? Why?

Yes this is perfectly fine. You will need multiple PhotonViews if you need to observe 2 or more targets; You can only observe one per PhotonView. For your RPC's you'll only ever need one PhotonView and this can be the same PhotonView that is already observing something. RPC's never clash with an observed target.

2.1 Photon



To use PUN from UnityScript, move both folders "PhotonNetwork" and "UtilityScripts" to the Assets\ folder. Now PUN compiles before UnityScript and that makes it available from regular UnityScript code.

12 **General Documentation**

Network Simulation GUI

Simple GUI element to control the built-in network condition simulation.

The Photon client library can simulate network conditions for lag (message delay) and loss, which can be a good tool for developer when testing with a local server or on near perfect network conditions.

To use it, add the component PhotonNetSimSettingsGui to an enabled GameObject in your scene. At runtime, the top left of the screen shows the current roundtrip time (RTT) and the controls for network simulation:

- RTT: The roundtrip time is the average of milliseconds until a message was acknowledged by the server. The variance value (behind the +/-) shows how stable the rtt is (a lower value being better).
- "Sim" toggle: Enables and disables the simulation. A sudden, big change of network conditions might result in disconnects.
- "Lag" slider: Adds a fixed delay to all outgoing and incoming messages. In milliseconds.
- "Jit" slider: Adds a random delay of "up to X milliseconds" per message.
- "Loss" slider: Drops the set percentage of messages. You can expect less than 2% drop in the internet today.

14 **Network Simulation GUI**

Network Statistics GUI

The PhotonStatsGui is a simple GUI component to track and show network-metrics at runtime.

Usage

Just add the PhotonStatsGui component to any active GameObject in the hierarchy. A window appears (at runtime) and shows the message count.

A few toggles let you configure the window:

- buttons: Show buttons for "stats on", "reset stats" and "to log"
- traffic: Show lower level network traffic (bytes per direction)
- · health: Show timing of sending, dispatches and their longest gaps

Message Statistics

The top most values showns are counter for "messages". Any operation, response and event are counted. Shown are the total count of outgoing, incoming and the sum of those messages as total and as average for the timespan that is tracked.

Traffic Statistics

These are the byte and packet counters. Anything that leaves or arrives via network is counted here. Even if there are few messages, they could be huge by accident and still cause less powerful clients to drop connection. You also see that there are packages sent when you don't send messages. They keeps the connection alive.

Health Statistics

The block beginning with "longest delta between" is about the performance of your client. We measure how much time passed between consecutive calls of send and dispatch. Usually they should be called ten times per second. If these values go beyond one second, you should check why Update() calls are delayed.

Button "Reset"

This resets the stats but keeps tracking them. This is useful to track message counts for different situations.

Button "To Log"

Pressing this simply logs the current stat values. This can be useful to have a overview how things evolved or just as reference.

16 Network Statistics GUI

Button "Stats On" (Enabling Traffic Stats)

The Photon library can track various network statistics but usually this feature is turned off. The PhotonStatsGui will enable the tracking and show those values.

The "stats on" toggle in the Gui controls if traffic stats are collected at all. The "Traffic Stats On" checkbox in the Inspector is the same value.

Public API Module

The Public API module rounds up the most commonly used classes of PUN.

These classes are grouped into a "module" to make it easier to find the important stuff in PUN. Classes like Photon⊷ Network and Photon.PunBehaviour are good entry points to learn how to code with PUN.

Opposed to that, there are several classes that are for internal use by the PUN framework. Even some of the internally used classes are public. This is for ease of use and in parts a result of how Unity works.

Open the Public API module

18 **Public API Module**

Module Documentation

6.1 Public API

Groups the most important classes that you need to understand early on.

Classes

interface IPunObservable

Defines the OnPhotonSerializeView method to make it easy to implement correctly for observable scripts.

interface IPunCallbacks

This interface is used as definition of all callback methods of PUN, except OnPhotonSerializeView. Preferably, implement them individually.

· class Photon.PunBehaviour

This class provides a .photonView and all callbacks/events that PUN can call. Override the events/methods you want to use.

• struct PhotonMessageInfo

Container class for info about a particular message, RPC or update.

class PhotonStream

This container is used in OnPhotonSerializeView() to either provide incoming data of a PhotonView or for you to provide it.

· class PhotonNetwork

The main class to use the PhotonNetwork plugin. This class is static.

class PhotonPlayer

Summarizes a "player" within a room, identified (in that room) by actorID.

class PhotonView

PUN's NetworkView replacement class for networking. Use it like a NetworkView.

· class Room

This class resembles a room that PUN joins (or joined). The properties are settable as opposed to those of a Room⊷ Info and you can close or hide "your" room.

· class RoomInfo

A simplified room with just the info required to list and join, used for the room listing in the lobby. The properties are not settable (open, MaxPlayers, etc).

Enumerations

enum PhotonNetworkingMessage {
 PhotonNetworkingMessage.OnConnectedToPhoton, PhotonNetworkingMessage.OnLeftRoom, Photon⊷
 NetworkingMessage.OnMasterClientSwitched, PhotonNetworkingMessage.OnPhotonCreateRoomFailed,
 PhotonNetworkingMessage.OnPhotonJoinRoomFailed, PhotonNetworkingMessage.OnCreatedRoom,

20 Module Documentation

PhotonNetworkingMessage.OnJoinedLobby, PhotonNetworkingMessage.OnLeftLobby,

PhotonNetworkingMessage.OnDisconnectedFromPhoton, PhotonNetworkingMessage.OnConnectionFail, PhotonNetworkingMessage.OnFailedToConnectToPhoton, PhotonNetworkingMessage.OnReceivedRoom ListUpdate,

PhotonNetworkingMessage.OnJoinedRoom, PhotonNetworkingMessage.OnPhotonPlayerConnected, PhotonNetworkingMessage.OnPhotonPlayerDisconnected, PhotonNetworkingMessage.OnPhoton⊷ RandomJoinFailed.

PhotonNetworkingMessage.OnPhotonSerializeView, PhotonNetworkingMessage.OnPhotonSerializeView, PhotonNetworkingMessage.OnPhotonInstantiate, PhotonNetworkingMessage.OnPhotonMaxCccuReached, PhotonNetworkingMessage.OnPhotonCustomRoomPropertiesChanged, PhotonNetworkingMessage.OnPhotonNetworkingMessage.OnUpdatedFriendList, PhotonNetworkingMessage.OnCustomAuthenticationFailed,

PhotonNetworkingMessage.OnCustomAuthenticationResponse, PhotonNetworkingMessage.OnWebRpc← Response, PhotonNetworkingMessage.OnOwnershipRequest, PhotonNetworkingMessage.OnLobby← StatisticsUpdate,

PhotonNetworkingMessage.OnPhotonPlayerActivityChanged, PhotonNetworkingMessage.OnOwnership ← Transfered }

This enum defines the set of MonoMessages Photon Unity Networking is using as callbacks. Implemented by Pun← Behaviour.

• enum PhotonLogLevel { PhotonLogLevel.ErrorsOnly, PhotonLogLevel.Informational, PhotonLogLevel.Full }

Used to define the level of logging output created by the PUN classes. Either log errors, info (some more) or full.

enum PhotonTargets {

PhotonTargets.All, PhotonTargets.Others, PhotonTargets.MasterClient, PhotonTargets.AllBuffered, PhotonTargets.OthersBuffered, PhotonTargets.AllViaServer, PhotonTargets.AllBufferedViaServer}

Enum of "target" options for RPCs. These define which remote clients get your RPC call.

enum ClientState {

ClientState.Uninitialized, ClientState.PeerCreated, ClientState.Queued, ClientState.Authenticated, ClientState.JoinedLobby, ClientState.DisconnectingFromMasterserver, ClientState.ConnectingToGameserver, ClientState.ConnectedToGameserver,

ClientState.Joining, ClientState.Joined, ClientState.Leaving, ClientState.DisconnectingFromGameserver, ClientState.ConnectingToMasterserver, ClientState.QueuedComingFromGameserver, ClientState.Disconnecting, ClientState.Disconnected,

 $\label{lem:connectedToMaster} ClientState. ConnectingToNameServer, \ ClientState. ConnectedToName \\ \hspace{0.5cm} Server, \ ClientState. DisconnectingFromNameServer, \\ \hspace{0.5cm} ClientState. \\ \hspace{0.5cm} ClientState.$

ClientState.Authenticating }

Detailed connection / networking peer state. PUN implements a loadbalancing and authentication workflow "behind the scenes", so some states will automatically advance to some follow up state. Those states are commented with "(will-change)".

enum DisconnectCause {

DisconnectCause.DisconnectByServerUserLimit = StatusCode.DisconnectByServerUserLimit, Disconnect← Cause.ExceptionOnConnect = StatusCode.ExceptionOnConnect, DisconnectCause.DisconnectByServer← Timeout = StatusCode.DisconnectByServerTimeout, DisconnectCause.DisconnectByServerLogic = Status← Code.DisconnectByServerLogic,

DisconnectCause.Exception = StatusCode.Exception, DisconnectCause.InvalidAuthentication = Error← Code.InvalidAuthentication, DisconnectCause.MaxCcuReached = ErrorCode.MaxCcuReached, Disconnect← Cause.InvalidRegion = ErrorCode.InvalidRegion.

DisconnectCause.SecurityExceptionOnConnect = StatusCode.SecurityExceptionOnConnect, Disconnect← Cause.DisconnectByClientTimeout = StatusCode.TimeoutDisconnect, DisconnectCause.InternalReceive← Exception = StatusCode.ExceptionOnReceive, DisconnectCause.AuthenticationTicketExpired = 32753 }

Summarizes the cause for a disconnect. Used in: OnConnectionFail and OnFailedToConnectToPhoton.

Functions

· void IPunObservable.OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the Photon⊷ View.

6.1 Public API 21

6.1.1 Detailed Description

Groups the most important classes that you need to understand early on.

6.1.2 Enumeration Type Documentation

6.1.2.1 enum ClientState

Detailed connection / networking peer state. PUN implements a loadbalancing and authentication workflow "behind the scenes", so some states will automatically advance to some follow up state. Those states are commented with "(will-change)".

Enumerator

Uninitialized Not running. Only set before initialization and first use.

PeerCreated Created and available to connect.

Queued Not used at the moment.

Authenticated The application is authenticated. PUN usually joins the lobby now.(will-change) Unless Auto

JoinLobby is false.

JoinedLobby Client is in the lobby of the Master Server and gets room listings. Use Join, Create or Join← Random to get into a room to play.

DisconnectingFromMasterserver Disconnecting.(will-change)

Connecting To Gameserver (to join/create a room and play).(will-change)

ConnectedToGameserver Similar to Connected state but on game server. Still in process to join/create room.(will-change)

Joining In process to join/create room (on game server).(will-change)

Joined Final state of a room join/create sequence. This client can now exchange events / call RPCs with other clients.

Leaving Leaving a room.(will-change)

DisconnectingFromGameserver Workflow is leaving the game server and will re-connect to the master server.(will-change)

ConnectingToMasterserver Workflow is connected to master server and will establish encryption and authenticate your app.(will-change)

QueuedComingFromGameserver Same Queued but coming from game server.(will-change)

Disconnecting PUN is disconnecting. This leads to Disconnected.(will-change)

Disconnected No connection is setup, ready to connect. Similar to PeerCreated.

ConnectedToMaster Final state for connecting to master without joining the lobby (AutoJoinLobby is false).

ConnectingToNameServer Client connects to the NameServer. This process includes low level connecting and setting up encryption. When done, state becomes ConnectedToNameServer.

Connected To Name Server Client is connected to the Name Server and established enctryption already. You should call OpGetRegions or ConnectToRegionMaster.

DisconnectingFromNameServer When disconnecting from a Photon NameServer.(will-change)

Authenticating When connecting to a Photon Server, this state is intermediate before you can call any operations.(will-change)

6.1.2.2 enum DisconnectCause

Summarizes the cause for a disconnect. Used in: OnConnectionFail and OnFailedToConnectToPhoton.

Extracted from the status codes from ExitGames.Client.Photon.StatusCode.

22 Module Documentation

See also

PhotonNetworkingMessage

Enumerator

DisconnectByServerUserLimit Server actively disconnected this client. Possible cause: The server's user limit was hit and client was forced to disconnect (on connect).

ExceptionOnConnect Connection could not be established. Possible cause: Local server not running.

DisconnectByServerTimeout Timeout disconnect by server (which decided an ACK was missing for too long).

DisconnectByServerLogic Server actively disconnected this client. Possible cause: Server's send buffer full (too much data for client).

Exception Some exception caused the connection to close.

InvalidAuthentication (32767) The Photon Cloud rejected the sent Appld. Check your Dashboard and make sure the Appld you use is complete and correct.

MaxCcuReached (32757) Authorization on the Photon Cloud failed because the concurrent users (CCU) limit of the app's subscription is reached.

InvalidRegion (32756) Authorization on the Photon Cloud failed because the app's subscription does not allow to use a particular region's server.

SecurityExceptionOnConnect The security settings for client or server don't allow a connection (see remarks). A common cause for this is that browser clients read a "crossdomain" file from the server. If that file is unavailable or not configured to let the client connect, this exception is thrown. Photon usually provides this crossdomain file for Unity. If it fails, read: https://doc.photonengine.←com/en-us/onpremise/current/operations/policy-files

DisconnectByClientTimeout Timeout disconnect by client (which decided an ACK was missing for too long). **InternalReceiveException** Exception in the receive-loop. Possible cause: Socket failure.

AuthenticationTicketExpired (32753) The Authentication ticket expired. Handle this by connecting again (which includes an authenticate to get a fresh ticket).

6.1.2.3 enum PhotonLogLevel

Used to define the level of logging output created by the PUN classes. Either log errors, info (some more) or full.

Enumerator

ErrorsOnly Show only errors. Minimal output. Note: Some might be "runtime errors" which you have to expect.

Informational Logs some of the workflow, calls and results.

Full Every available log call gets into the console/log. Only use for debugging.

6.1.2.4 enum PhotonNetworkingMessage

This enum defines the set of MonoMessages Photon Unity Networking is using as callbacks. Implemented by PunBehaviour.

Much like "Update()" in Unity, PUN will call methods in specific situations. Often, these methods are triggered when network operations complete (example: when joining a room).

All those methods are defined and described in this enum and implemented by PunBehaviour (which makes it easy to implement them as override).

Each entry is the name of such a method and the description tells you when it gets used by PUN.

Make sure to read the remarks per entry as some methods have optional parameters.

6.1 Public API 23

Enumerator

OnConnectedToPhoton Called when the initial connection got established but before you can use the server. OnJoinedLobby() or OnConnectedToMaster() are called when PUN is ready. This callback is only useful to detect if the server can be reached at all (technically). Most often, it's enough to implement OnFailed← ToConnectToPhoton() and OnDisconnectedFromPhoton().

OnJoinedLobby() or OnConnectedToMaster() are called when PUN is ready.

When this is called, the low level connection is established and PUN will send your Appld, the user, etc in the background. This is not called for transitions from the masterserver to game servers.

Example: void OnConnectedToPhoton() { ... }

OnLeftRoom Called when the local user/client left a room. When leaving a room, PUN brings you back to the Master Server. Before you can use lobbies and join or create rooms, OnJoinedLobby() or OnConnected← ToMaster() will get called again.

Example: void OnLeftRoom() { ... }

OnMasterClientSwitched Called after switching to a new MasterClient when the current one leaves. This is not called when this client enters a room. The former MasterClient is still in the player list when this method get called.

Example: void OnMasterClientSwitched(PhotonPlayer newMasterClient) { ... }

OnPhotonCreateRoomFailed Called when a CreateRoom() call failed. Optional parameters provide Error Code and message. Most likely because the room name is already in use (some other client was faster than you). PUN logs some info if the PhotonNetwork.logLevel is >= PhotonLogLevel.Informational.

Example: void OnPhotonCreateRoomFailed() { ... }

Example: void OnPhotonCreateRoomFailed(object[] codeAndMsg) { // codeAndMsg[0] is short Error← Code. codeAndMsg[1] is string debug msg. }

OnPhotonJoinRoomFailed Called when a JoinRoom() call failed. Optional parameters provide ErrorCode and message. Most likely error is that the room does not exist or the room is full (some other client was faster than you). PUN logs some info if the PhotonNetwork.logLevel is >= PhotonLogLevel.Informational. Example: void OnPhotonJoinRoomFailed() { ... }

Example: void OnPhotonJoinRoomFailed(object[] codeAndMsg[0] is short ErrorCode. codeAndMsg[1] is string debug msg. }

OnCreatedRoom Called when this client created a room and entered it. OnJoinedRoom() will be called as well. This callback is only called on the client which created a room (see PhotonNetwork.CreateRoom).

As any client might close (or drop connection) anytime, there is a chance that the creator of a room does not execute OnCreatedRoom.

If you need specific room properties or a "start signal", it is safer to implement OnMasterClientSwitched() and to make the new MasterClient check the room's state.

Example: void OnCreatedRoom() { ... }

OnJoinedLobby Called on entering a lobby on the Master Server. The actual room-list updates will call OnReceivedRoomListUpdate(). Note: When PhotonNetwork.autoJoinLobby is false, OnConnectedTo← Master() will be called and the room list won't become available.

While in the lobby, the roomlist is automatically updated in fixed intervals (which you can't modify). The room list gets available when OnReceivedRoomListUpdate() gets called after OnJoinedLobby().

Example: void OnJoinedLobby() { ... }

OnLeftLobby Called after leaving a lobby. When you leave a lobby, CreateRoom and JoinRandomRoom automatically refer to the default lobby.

Example: void OnLeftLobby() { ... }

OnDisconnectedFromPhoton Called after disconnecting from the Photon server. In some cases, other callbacks are called before OnDisconnectedFromPhoton is called. Examples: OnConnectionFail() and On← FailedToConnectToPhoton().

Example: void OnDisconnectedFromPhoton() { ... }

OnConnectionFail Called when something causes the connection to fail (after it was established), followed by a call to OnDisconnectedFromPhoton(). If the server could not be reached in the first place, OnFailed← ToConnectToPhoton is called instead. The reason for the error is provided as StatusCode.

Example: void OnConnectionFail(DisconnectCause cause) { ... }

24 Module Documentation

OnFailedToConnectToPhoton Called if a connect call to the Photon server failed before the connection was established, followed by a call to OnDisconnectedFromPhoton(). OnConnectionFail only gets called when a connection to a Photon server was established in the first place.

Example: void OnFailedToConnectToPhoton(DisconnectCause cause) { ... }

OnReceivedRoomListUpdate Called for any update of the room-listing while in a lobby (PhotonNetwork. insideLobby) on the Master Server or when a response is received for PhotonNetwork.GetCustomRoom List(). PUN provides the list of rooms by PhotonNetwork.GetRoomList().

Each item is a RoomInfo which might include custom properties (provided you defined those as lobby-listed when creating a room).

Not all types of lobbies provide a listing of rooms to the client. Some are silent and specialized for serverside matchmaking.

Example: void OnReceivedRoomListUpdate() { ... }

OnJoinedRoom Called when entering a room (by creating or joining it). Called on all clients (including the Master Client). This method is commonly used to instantiate player characters. If a match has to be started "actively", you can instead call an PunRPC triggered by a user's button-press or a timer.

When this is called, you can usually already access the existing players in the room via PhotonNetwork.

playerList. Also, all custom properties should be already available as Room.customProperties. Check Room.playerCount to find out if enough players are in the room to start playing.

Example: void OnJoinedRoom() { ... }

OnPhotonPlayerConnected Called when a remote player entered the room. This PhotonPlayer is already added to the playerlist at this time. If your game starts with a certain number of players, this callback can be useful to check the Room.playerCount and find out if you can start.

Example: void OnPhotonPlayerConnected(PhotonPlayer newPlayer) { ... }

OnPhotonPlayerDisconnected Called when a remote player left the room. This PhotonPlayer is already removed from the playerlist at this time. When your client calls PhotonNetwork.leaveRoom, PUN will call this method on the remaining clients. When a remote client drops connection or gets closed, this callback gets executed. after a timeout of several seconds.

Example: void OnPhotonPlayerDisconnected(PhotonPlayer otherPlayer) { ... }

OnPhotonRandomJoinFailed Called after a JoinRandom() call failed. Optional parameters provide Error← Code and message. Most likely all rooms are full or no rooms are available. When using multiple lobbies (via JoinLobby or TypedLobby), another lobby might have more/fitting rooms. PUN logs some info if the PhotonNetwork.logLevel is >= PhotonLogLevel.Informational.

Example: void OnPhotonRandomJoinFailed() { ... }

Example: void OnPhotonRandomJoinFailed(object[] codeAndMsg) { // codeAndMsg[0] is short Error Code. codeAndMsg[1] is string debug msg. }

OnConnectedToMaster Called after the connection to the master is established and authenticated but only when PhotonNetwork.autoJoinLobby is false. If you set PhotonNetwork.autoJoinLobby to true, On← JoinedLobby() will be called instead of this.

You can join rooms and create them even without being in a lobby. The default lobby is used in that case. The list of available rooms won't become available unless you join a lobby via PhotonNetwork.joinLobby.

Example: void OnConnectedToMaster() { ... }

OnPhotonSerializeView Implement to customize the data a PhotonView regularly synchronizes. Called every 'network-update' when observed by PhotonView. This method will be called in scripts that are assigned as Observed component of a PhotonView. PhotonNetwork.sendRateOnSerialize affects how often this method is called. PhotonNetwork.sendRate affects how often packages are sent by this client.

Implementing this method, you can customize which data a PhotonView regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView only gets called when it is assigned to a PhotonView* as PhotonView.observed script.

To make use of this method, the PhotonStream is essential. It will be in "writing" mode" on the client that controls a PhotonView (PhotonStream.isWriting == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

6.1 Public API 25

Note that OnPhotonSerializeView is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Example: void OnPhotonSerializeView(PhotonStream stream, PhotonMessageInfo info) { ... }

OnPhotonInstantiate Called on all scripts on a GameObject (and children) that have been Instantiated using PhotonNetwork.Instantiate. PhotonMessageInfo parameter provides info about who created the object and when (based off PhotonNetworking.time).

Example: void OnPhotonInstantiate(PhotonMessageInfo info) { ... }

OnPhotonMaxCccuReached Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting. When this happens, the user might try again later. You can't create or join rooms in OnPhotonMaxCcuReached(), cause the client will be disconnecting. You can raise the CCU limits with a new license (when you host yourself) or extended subscription (when using the Photon Cloud). The Photon Cloud will mail you when the CCU limit was reached. This is also visible in the Dashboard (webpage).

Example: void OnPhotonMaxCccuReached() { ... }

OnPhotonCustomRoomPropertiesChanged Called when a room's custom properties changed. The propertiesThatChanged contains all that was set via Room.SetCustomProperties. Since v1.25 this method has one parameter: Hashtable propertiesThatChanged. Changing properties must be done by Room.SetCustomProperties, which causes this callback locally, too.

Example: void OnPhotonCustomRoomPropertiesChanged(Hashtable propertiesThatChanged) { ... }

OnPhotonPlayerPropertiesChanged Called when custom player-properties are changed. Player and the changed properties are passed as object[]. Since v1.25 this method has one parameter: object[] player← AndUpdatedProps, which contains two entries.

[0] is the affected PhotonPlayer.

[1] is the Hashtable of properties that changed.

We are using a object[] due to limitations of Unity's GameObject.SendMessage (which has only one optional parameter).

Changing properties must be done by PhotonPlayer.SetCustomProperties, which causes this callback locally, too.

Example:

```
void OnPhotonPlayerPropertiesChanged(object[] playerAndUpdatedProps) {
    PhotonPlayer player = playerAndUpdatedProps[0] as PhotonPlayer;
    Hashtable props = playerAndUpdatedProps[1] as Hashtable;
    //...
}
```

OnUpdatedFriendList Called when the server sent the response to a FindFriends request and updated PhotonNetwork.Friends. The friends list is available as PhotonNetwork.Friends, listing name, online state and the room a user is in (if any).

Example: void OnUpdatedFriendList() { ... }

OnCustomAuthenticationFailed Called when the custom authentication failed. Followed by disconnect! Custom Authentication can fail due to user-input, bad tokens/secrets. If authentication is successful, this method is not called. Implement OnJoinedLobby() or OnConnectedToMaster() (as usual).

During development of a game, it might also fail due to wrong configuration on the server side. In those cases, logging the debugMessage is very important.

Unless you setup a custom authentication service for your app (in the <code>Dashboard</code>), this won't be called! Example: void OnCustomAuthenticationFailed(string debugMessage) { ... }

OnCustomAuthenticationResponse Called when your Custom Authentication service responds with additional data. Custom Authentication services can include some custom data in their response. When present, that data is made available in this callback as Dictionary. While the keys of your data have to be strings, the values can be either string or a number (in Json). You need to make extra sure, that the value type is the one you expect. Numbers become (currently) int64.

Example: void OnCustomAuthenticationResponse(Dictionary<string, object> data) { ... }

https://doc.photonengine.com/en-us/pun/current/connection-and-authentication/custom-au

26 Module Documentation

OnWebRpcResponse Called by PUN when the response to a WebRPC is available. See PhotonNetwork. ← WebRPC. Important: The response.ReturnCode is 0 if Photon was able to reach your web-service. The content of the response is what your web-service sent. You can create a WebResponse instance from it. Example: WebRpcResponse webResponse = new WebRpcResponse(operationResponse);

Please note: Class OperationResponse is in a namespace which needs to be "used": using ExitGames. ← Client.Photon; // includes OperationResponse (and other classes)

The OperationResponse.ReturnCode by Photon is: 0 for "OK" -3 for "Web-Service not configured" (see Dashboard / WebHooks) -5 for "Web-Service does now have RPC path/name" (at least for Azure)

Example: void OnWebRpcResponse(OperationResponse response) { ... }

OnOwnershipRequest Called when another player requests ownership of a PhotonView from you (the current owner). The parameter viewAndPlayer contains:

PhotonView view = viewAndPlayer[0] as PhotonView;

PhotonPlayer requestingPlayer = viewAndPlayer[1] as PhotonPlayer;

void OnOwnershipRequest(object[] viewAndPlayer) {} //

OnLobbyStatisticsUpdate Called when the Master Server sent an update for the Lobby Statistics, updating PhotonNetwork.LobbyStatistics. This callback has two preconditions: EnableLobbyStatistics must be set to true, before this client connects. And the client has to be connected to the Master Server, which is providing the info about lobbies.

OnPhotonPlayerActivityChanged Called when a remote Photon Player activity changed. This will be called ONLY is PlayerTtl is greater then 0. Use PhotonPlayer.IsInactive to check the current activity state

Example: void OnPhotonPlayerActivityChanged(PhotonPlayer otherPlayer) {...}

This callback has precondition: PlayerTtl must be greater then 0

OnOwnershipTransfered Called when a PhotonView Owner is transfered to a Player. The parameter view

AndPlayers contains:

PhotonView view = viewAndPlayers[0] as PhotonView;

PhotonPlayer newOwner = viewAndPlayers[1] as PhotonPlayer;

PhotonPlayer oldOwner = viewAndPlayers[2] as PhotonPlayer;

void OnOwnershipTransfered(object[] viewAndPlayers) {} //

6.1.2.5 enum PhotonTargets

Enum of "target" options for RPCs. These define which remote clients get your RPC call.

Enumerator

All Sends the RPC to everyone else and executes it immediately on this client. Player who join later will not execute this RPC.

Others Sends the RPC to everyone else. This client does not execute the RPC. Player who join later will not execute this RPC.

MasterClient Sends the RPC to MasterClient only. Careful: The MasterClient might disconnect before it executes the RPC and that might cause dropped RPCs.

AllBuffered Sends the RPC to everyone else and executes it immediately on this client. New players get the RPC when they join as it's buffered (until this client leaves).

OthersBuffered Sends the RPC to everyone. This client does not execute the RPC. New players get the RPC when they join as it's buffered (until this client leaves).

AllViaServer Sends the RPC to everyone (including this client) through the server. This client executes the RPC like any other when it received it from the server. Benefit: The server's order of sending the RPCs is the same on all clients.

AllBufferedViaServer Sends the RPC to everyone (including this client) through the server and buffers it for players joining later. This client executes the RPC like any other when it received it from the server. Benefit: The server's order of sending the RPCs is the same on all clients.

6.1 Public API 27

6.1.3 Function Documentation

6.1.3.1 void IPunObservable.OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the Photon

View.

This method will be called in scripts that are assigned as Observed component of a PhotonView.

PhotonNetwork.sendRateOnSerialize affects how often this method is called.

PhotonNetwork.sendRate affects how often packages are sent by this client.

Implementing this method, you can customize which data a PhotonView regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView only gets called when it is assigned to a PhotonView* as Photon← View.observed script.

To make use of this method, the PhotonStream is essential. It will be in "writing" mode" on the client that controls a PhotonView (PhotonStream.isWriting == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that OnPhotonSerializeView is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implemented in PhotonAnimatorView, PhotonTransformView, PhotonRigidbody2DView, and PhotonRigidbodyView.

28 Module Documentation

6.2 Optional Gui Elements

Useful GUI elements for PUN.

Classes

• class PhotonLagSimulationGui

This MonoBehaviour is a basic GUI for the Photon client's network-simulation feature. It can modify lag (fixed delay), jitter (random lag) and packet loss.

• class PhotonStatsGui

Basic GUI to show traffic and health statistics of the connection to Photon, toggled by shift+tab.

6.2.1 Detailed Description

Useful GUI elements for PUN.

Namespace Documentation

7.1 Package ExitGames

Namespaces

• package Client

7.2 Package ExitGames.Client

Namespaces

• package GUI

7.3 Package ExitGames.Client.GUI

Classes

• class GizmoTypeDrawer

Enumerations

• enum GizmoType { GizmoType.WireSphere, GizmoType.Sphere, GizmoType.WireCube, GizmoType.Cube }

7.3.1 Enumeration Type Documentation

7.3.1.1 enum ExitGames.Client.GUI.GizmoType

Enumerator

WireSphere

Sphere

WireCube

Cube

7.4 Package Photon

Namespaces

- · package Chat
- package Realtime

Classes

· class MonoBehaviour

This class adds the property photonView, while logging a warning when your game still uses the networkView.

· class PunBehaviour

This class provides a .photonView and all callbacks/events that PUN can call. Override the events/methods you want to use.

Typedefs

• using Hashtable = ExitGames.Client.Photon.Hashtable

7.4.1 Typedef Documentation

7.4.1.1 using Photon.Hashtable = typedef ExitGames.Client.Photon.Hashtable

7.5 Package Photon.Chat

Classes

· class AuthenticationValues

Container for user authentication in Photon. Set AuthValues before you connect - all else is handled.

- class ChannelCreationOptions
- class ChannelWellKnownProperties
- · class ChatChannel

A channel of communication in Photon Chat, updated by ChatClient and provided as READ ONLY.

class ChatClient

Central class of the Photon Chat API to connect, handle channels and messages.

class ChatEventCode

Wraps up internally used constants in Photon Chat events. You don't have to use them directly usually.

· class ChatOperationCode

Wraps up codes for operations used internally in Photon Chat. You don't have to use them directly usually.

class ChatParameterCode

Wraps up codes for parameters (in operations and events) used internally in Photon Chat. You don't have to use them directly usually.

· class ChatPeer

Provides basic operations of the Photon Chat server. This internal class is used by public ChatClient.

· class ChatUserStatus

Contains commonly used status values for SetOnlineStatus. You can define your own.

class ErrorCode

ErrorCode defines the default codes associated with Photon client/server communication.

interface IChatClientListener

Callback interface for Chat client side. Contains callback methods to notify your app about updates. Must be provided to new ChatClient in constructor

· class ParameterCode

Class for constants. Codes for parameters of Operations and Events.

Enumerations

enum ChatDisconnectCause {

ChatDisconnectCause.None, ChatDisconnectCause.DisconnectByServerUserLimit, ChatDisconnect← Cause.ExceptionOnConnect, ChatDisconnectCause.DisconnectByServer,

ChatDisconnectCause.TimeoutDisconnect, ChatDisconnectCause.Exception, ChatDisconnectCause.← InvalidAuthentication, ChatDisconnectCause.MaxCcuReached,

 $Chat D is connect Cause. Invalid Region, \quad Chat D is connect Cause. Operation Not Allowed In Current State, \quad Chat \leftarrow D is connect Cause. Custom Authentication Failed \}$

Enumeration of causes for Disconnects (used in ChatClient.DisconnectedCause).

enum CustomAuthenticationType : byte {

CustomAuthenticationType.Custom = 0, CustomAuthenticationType.Steam = 1, CustomAuthenticationType. ← Facebook = 2, CustomAuthenticationType.Oculus = 3,

CustomAuthenticationType.PlayStation = 4, CustomAuthenticationType.Xbox = 5, CustomAuthentication → Type.Viveport = 10, CustomAuthenticationType.None = byte.MaxValue }

Options for optional "Custom Authentication" services used with Photon. Used by OpAuthenticate after connecting to Photon.

enum ChatState {

ChatState.Uninitialized, ChatState.ConnectingToNameServer, ChatState.ConnectedToNameServer, Chat←State.Authenticating,

ChatState.Authenticated, ChatState.DisconnectingFromNameServer, ChatState.ConnectingToFrontEnd, ChatState.ConnectedToFrontEnd,

ChatState.DisconnectingFromFrontEnd, ChatState.QueuedComingFromFrontEnd, ChatState.Disconnecting, ChatState.Disconnected }

Possible states for a Chat Client.

7.5.1 Enumeration Type Documentation

7.5.1.1 enum Photon.Chat.ChatDisconnectCause

Enumeration of causes for Disconnects (used in ChatClient.DisconnectedCause).

Read the individual descriptions to find out what to do about this type of disconnect.

Enumerator

None No error was tracked.

DisconnectByServerUserLimit OnStatusChanged: The CCUs count of your Photon Server License is exhausted (temporarily).

ExceptionOnConnect OnStatusChanged: The server is not available or the address is wrong. Make sure the port is provided and the server is up.

DisconnectByServer OnStatusChanged: The server disconnected this client. Most likely the server's send buffer is full (receiving too much from other clients).

TimeoutDisconnect OnStatusChanged: This client detected that the server's responses are not received in due time. Maybe you send / receive too much?

Exception OnStatusChanged: Some internal exception caused the socket code to fail. Contact Exit Games.

InvalidAuthentication OnOperationResponse: Authenticate in the Photon Cloud with invalid Appld. Update your subscription or contact Exit Games.

MaxCcuReached OnOperationResponse: Authenticate (temporarily) failed when using a Photon Cloud subscription without CCU Burst. Update your subscription.

InvalidRegion OnOperationResponse: Authenticate when the app's Photon Cloud subscription is locked to some (other) region(s). Update your subscription or change region.

OperationNotAllowedInCurrentState OnOperationResponse: Operation that's (currently) not available for this client (not authorized usually). Only tracked for op Authenticate.

CustomAuthenticationFailed OnOperationResponse: Authenticate in the Photon Cloud with invalid client values or custom authentication setup in Cloud Dashboard.

7.5.1.2 enum Photon.Chat.ChatState

Possible states for a Chat Client.

Enumerator

Uninitialized Peer is created but not used yet.

ConnectingToNameServer Connecting to name server.

ConnectedToNameServer Connected to name server.

Authenticating Authenticating on current server.

Authenticated Finished authentication on current server.

DisconnectingFromNameServer Disconnecting from name server. This is usually a transition from name server to frontend server.

ConnectingToFrontEnd Connecting to frontend server.

ConnectedToFrontEnd Connected to frontend server.

DisconnectingFromFrontEnd Disconnecting from frontend server.

QueuedComingFromFrontEnd Currently not used.

Disconnecting The client disconnects (from any server).

Disconnected The client is no longer connected (to any server).

7.5.1.3 enum Photon.Chat.CustomAuthenticationType : byte

Options for optional "Custom Authentication" services used with Photon. Used by OpAuthenticate after connecting to Photon.

Enumerator

Custom Use a custom authentification service. Currently the only implemented option.

Steam Authenticates users by their Steam Account. Set auth values accordingly!

Facebook Authenticates users by their Facebook Account. Set auth values accordingly!

Oculus Authenticates users by their Oculus Account and token.

PlayStation Authenticates users by their PSN Account and token.

Xbox Authenticates users by their Xbox Account and XSTS token.

Viveport Authenticates users by their HTC VIVEPORT Account and user token.

None Disables custom authentification. Same as not providing any AuthenticationValues for connect (more precisely for: OpAuthenticate).

7.6 Package Photon.Realtime

Classes

- class PhotonPing
- class PingMono

Uses C# Socket class from System.Net.Sockets (as Unity usually does).

7.7 Package UnityEngine

Namespaces

package SceneManagement

7.8 Package UnityEngine.SceneManagement

Classes

• class SceneManager

Minimal implementation of the SceneManager for older Unity, up to v5.2.

Enumerations

• enum LoadSceneMode { LoadSceneMode.Single, LoadSceneMode.Additive }

7.8.1 Enumeration Type Documentation

7.8.1.1 enum UnityEngine.SceneManagement.LoadSceneMode

Enumerator

Single

Additive

Class Documentation

8.1 ActorProperties Class Reference

Class for constants. These (byte) values define "well known" properties for an Actor / Player.

Public Attributes

- const byte PlayerName = 255
 - (255) Name of a player/actor.
- const byte Islnactive = 254

(254) Tells you if the player is currently in this game (getting events live).

• const byte UserId = 253

(253) Userld of the player. Sent when room gets created with RoomOptions.PublishUserld = true.

8.1.1 Detailed Description

Class for constants. These (byte) values define "well known" properties for an Actor / Player.

Pun uses these constants internally. "Custom properties" have to use a string-type as key. They can be assigned at will.

8.1.2 Member Data Documentation

- 8.1.2.1 const byte ActorProperties.IsInactive = 254
- (254) Tells you if the player is currently in this game (getting events live).

A server-set value for async games, where players can leave the game and return later.

- 8.1.2.2 const byte ActorProperties.PlayerName = 255
- (255) Name of a player/actor.
- 8.1.2.3 const byte ActorProperties.UserId = 253
- (253) Userld of the player. Sent when room gets created with RoomOptions.PublishUserld = true.

36 Class Documentation

8.2 Photon.Chat.AuthenticationValues Class Reference

Container for user authentication in Photon. Set AuthValues before you connect - all else is handled.

Public Member Functions

· AuthenticationValues ()

Creates empty auth values without any info.

AuthenticationValues (string userId)

Creates minimal info about the user. If this is authenticated or not, depends on the set AuthType.

virtual void SetAuthPostData (string stringData)

Sets the data to be passed-on to the auth service via POST.

virtual void SetAuthPostData (byte[] byteData)

Sets the data to be passed-on to the auth service via POST.

virtual void AddAuthParameter (string key, string value)

Adds a key-value pair to the get-parameters used for Custom Auth (AuthGetParameters).

override string ToString ()

Transform this object into string.

Properties

• CustomAuthenticationType AuthType [get, set]

The type of custom authentication provider that should be used. Currently only "Custom" or "None" (turns this off).

string AuthGetParameters [get, set]

This string must contain any (http get) parameters expected by the used authentication service. By default, username and token.

• object AuthPostData [get, set]

Data to be passed-on to the auth service via POST. Default: null (not sent). Either string or byte[] (see setters).

• string Token [get, set]

After initial authentication, Photon provides a token for this client / user, which is subsequently used as (cached) validation.

• string Userld [get, set]

The Userld should be a unique identifier per user. This is for finding friends, etc..

8.2.1 Detailed Description

Container for user authentication in Photon. Set AuthValues before you connect - all else is handled.

On Photon, user authentication is optional but can be useful in many cases. If you want to FindFriends, a unique ID per user is very practical.

There are basically three options for user authentification: None at all, the client sets some Userld or you can use some account web-service to authenticate a user (and set the Userld server-side).

Custom Authentication lets you verify end-users by some kind of login or token. It sends those values to Photon which will verify them before granting access or disconnecting the client.

The Photon Cloud Dashboard will let you enable this feature and set important server values for it. https://dashboard.photonengine.com

8.2.2 Constructor & Destructor Documentation

8.2.2.1 Photon.Chat.AuthenticationValues.AuthenticationValues ()

Creates empty auth values without any info.

8.2.2.2 Photon.Chat.AuthenticationValues.AuthenticationValues (string userId)

Creates minimal info about the user. If this is authenticated or not, depends on the set AuthType.

Parameters

userld	Some UserId to set in Photon.

8.2.3 Member Function Documentation

8.2.3.1 virtual void Photon.Chat.AuthenticationValues.AddAuthParameter (string key, string value) [virtual]

Adds a key-value pair to the get-parameters used for Custom Auth (AuthGetParameters).

This method does uri-encoding for you.

Parameters

key	Key for the value to set.
value	Some value relevant for Custom Authentication.

8.2.3.2 virtual void Photon.Chat.AuthenticationValues.SetAuthPostData (string stringData) [virtual]

Sets the data to be passed-on to the auth service via POST.

Parameters

stringData	String data to be used in the body of the POST request. Null or empty string will set Auth
	PostData to null.

8.2.3.3 virtual void Photon.Chat.AuthenticationValues.SetAuthPostData (byte[] byteData) [virtual]

Sets the data to be passed-on to the auth service via POST.

Parameters

byteData	Binary token / auth-data to pass on.

8.2.3.4 override string Photon.Chat.AuthenticationValues.ToString ()

Transform this object into string.

Returns

string representation of this object.

8.2.4 Property Documentation

8.2.4.1 string Photon.Chat.AuthenticationValues.AuthGetParameters [get], [set]

This string must contain any (http get) parameters expected by the used authentication service. By default, username and token.

Maps to operation parameter 216. Standard http get parameters are used here and passed on to the service that's defined in the server (Photon Cloud Dashboard).

8.2.4.2 object Photon.Chat.AuthenticationValues.AuthPostData [get], [set]

Data to be passed-on to the auth service via POST. Default: null (not sent). Either string or byte[] (see setters). Maps to operation parameter 214.

8.2.4.3 CustomAuthenticationType Photon.Chat.AuthenticationValues.AuthType [get], [set]

The type of custom authentication provider that should be used. Currently only "Custom" or "None" (turns this off).

8.2.4.4 string Photon.Chat.AuthenticationValues.Token [get], [set]

After initial authentication, Photon provides a token for this client / user, which is subsequently used as (cached) validation.

8.2.4.5 string Photon.Chat.AuthenticationValues.UserId [get], [set]

The Userld should be a unique identifier per user. This is for finding friends, etc..

8.3 Authentication Values Class Reference

Container for user authentication in Photon. Set AuthValues before you connect - all else is handled.

Public Member Functions

• AuthenticationValues ()

Creates empty auth values without any info.

AuthenticationValues (string userId)

Creates minimal info about the user. If this is authenticated or not, depends on the set AuthType.

virtual void SetAuthPostData (string stringData)

Sets the data to be passed-on to the auth service via POST.

virtual void SetAuthPostData (byte[] byteData)

Sets the data to be passed-on to the auth service via POST.

Sets data to be passed-on to the auth service as Json (Content-Type: "application/json") via Post.

virtual void AddAuthParameter (string key, string value)

Adds a key-value pair to the get-parameters used for Custom Auth (AuthGetParameters).

• override string ToString ()

Properties

CustomAuthenticationType AuthType [get, set]

The type of custom authentication provider that should be used. Currently only "Custom" or "None" (turns this off).

• string AuthGetParameters [get, set]

This string must contain any (http get) parameters expected by the used authentication service. By default, username and token.

• object AuthPostData [get, set]

Data to be passed-on to the auth service via POST. Default: null (not sent). Either string or byte[] (see setters).

• string Token [get, set]

After initial authentication, Photon provides a token for this client / user, which is subsequently used as (cached) validation.

• string Userld [get, set]

The Userld should be a unique identifier per user. This is for finding friends, etc..

8.3.1 Detailed Description

Container for user authentication in Photon. Set AuthValues before you connect - all else is handled.

On Photon, user authentication is optional but can be useful in many cases. If you want to FindFriends, a unique ID per user is very practical.

There are basically three options for user authentification: None at all, the client sets some Userld or you can use some account web-service to authenticate a user (and set the Userld server-side).

Custom Authentication lets you verify end-users by some kind of login or token. It sends those values to Photon which will verify them before granting access or disconnecting the client.

The AuthValues are sent in OpAuthenticate when you connect, so they must be set before you connect. Should you not set any AuthValues, PUN will create them and set the playerName as userId in them. If the AuthValues.userId is null or empty when it's sent to the server, then the Photon Server assigns a userId!

The Photon Cloud Dashboard will let you enable this feature and set important server values for it. https://dashboard.photonengine.com

8.3.2 Constructor & Destructor Documentation

8.3.2.1 AuthenticationValues.AuthenticationValues ()

Creates empty auth values without any info.

8.3.2.2 AuthenticationValues. AuthenticationValues (string userId)

Creates minimal info about the user. If this is authenticated or not, depends on the set AuthType.

Parameters

userld	Some UserId to set in Photon.

8.3.3 Member Function Documentation

8.3.3.1 virtual void Authentication Values. Add Auth Parameter (string key, string value) [virtual]

Adds a key-value pair to the get-parameters used for Custom Auth (AuthGetParameters).

This method does uri-encoding for you.

Parameters

key	Key for the value to set.
value	Some value relevant for Custom Authentication.

8.3.3.2 virtual void Authentication Values. Set Auth Post Data (string string Data) [virtual]

Sets the data to be passed-on to the auth service via POST.

AuthPostData is just one value. Each SetAuthPostData replaces any previous value. It can be either a string, a byte[] or a dictionary. Each SetAuthPostData replaces any previous value.

Parameters

stringData	String data to be used in the body of the POST request. Null or empty string will set Auth-
	PostData to null.

8.3.3.3 virtual void AuthenticationValues.SetAuthPostData (byte[] byteData) [virtual]

Sets the data to be passed-on to the auth service via POST.

AuthPostData is just one value. Each SetAuthPostData replaces any previous value. It can be either a string, a byte[] or a dictionary. Each SetAuthPostData replaces any previous value.

Parameters

byteData	Binary token / auth-data to pass on.

8.3.3.4 virtual void AuthenticationValues.SetAuthPostData (Dictionary < string, object > dictData) [virtual]

Sets data to be passed-on to the auth service as Json (Content-Type: "application/json") via Post.

AuthPostData is just one value. Each SetAuthPostData replaces any previous value. It can be either a string, a byte[] or a dictionary. Each SetAuthPostData replaces any previous value.

Parameters

dictData	A authentication-data dictionary will be converted to Json and passed to the Auth webservice
	via HTTP Post.

8.3.3.5 override string AuthenticationValues.ToString ()

8.3.4 Property Documentation

 $\textbf{8.3.4.1} \quad \textbf{string AuthenticationValues.AuthGetParameters} \quad [\texttt{get}], [\texttt{set}]$

This string must contain any (http get) parameters expected by the used authentication service. By default, username and token.

Maps to operation parameter 216. Standard http get parameters are used here and passed on to the service that's defined in the server (Photon Cloud Dashboard).

8.3.4.2 object AuthenticationValues.AuthPostData [get], [set]

Data to be passed-on to the auth service via POST. Default: null (not sent). Either string or byte[] (see setters). Maps to operation parameter 214.

8.3.4.3 CustomAuthenticationType AuthenticationValues.AuthType [get], [set]

The type of custom authentication provider that should be used. Currently only "Custom" or "None" (turns this off).

8.3.4.4 string Authentication Values. Token [get], [set]

After initial authentication, Photon provides a token for this client / user, which is subsequently used as (cached) validation.

8.3.4.5 string Authentication Values. UserId [get], [set]

The Userld should be a unique identifier per user. This is for finding friends, etc..

See remarks of AuthValues for info about how this is set and used.

8.4 Photon.Chat.ChannelCreationOptions Class Reference

Static Public Attributes

static ChannelCreationOptions Default = new ChannelCreationOptions()
 Default values of channel creation options.

Properties

• bool PublishSubscribers [get, set]

Whether or not the channel to be created will allow client to keep a list of users.

• int MaxSubscribers [get, set]

Limit of the number of users subscribed to the channel to be created.

8.4.1 Member Data Documentation

8.4.1.1 ChannelCreationOptions Photon.Chat.ChannelCreationOptions.Default = new ChannelCreationOptions()

Default values of channel creation options.

8.4.2 Property Documentation

8.4.2.1 int Photon.Chat.ChannelCreationOptions.MaxSubscribers [get], [set]

Limit of the number of users subscribed to the channel to be created.

8.4.2.2 bool Photon.Chat.ChannelCreationOptions.PublishSubscribers [get], [set]

Whether or not the channel to be created will allow client to keep a list of users.

8.5 Photon.Chat.ChannelWellKnownProperties Class Reference

Public Attributes

- const byte MaxSubscribers = 255
- const byte PublishSubscribers = 254

8.5.1 Member Data Documentation

- 8.5.1.1 const byte Photon.Chat.ChannelWellKnownProperties.MaxSubscribers = 255
- 8.5.1.2 const byte Photon.Chat.ChannelWellKnownProperties.PublishSubscribers = 254

8.6 Photon.Chat.ChatChannel Class Reference

A channel of communication in Photon Chat, updated by ChatClient and provided as READ ONLY.

Public Member Functions

• ChatChannel (string name)

Used internally to create new channels. This does NOT create a channel on the server! Use ChatClient.Subscribe.

void Add (string sender, object message, int msgld)

Used internally to add messages to this channel.

• void Add (string[] senders, object[] messages, int lastMsgld)

Used internally to add messages to this channel.

• void TruncateMessages ()

Reduces the number of locally cached messages in this channel to the MessageLimit (if set).

void ClearMessages ()

Clear the local cache of messages currently stored. This frees memory but doesn't affect the server.

string ToStringMessages ()

Provides a string-representation of all messages in this channel.

Public Attributes

· readonly string Name

Name of the channel (used to subscribe and unsubscribe).

readonly List< string > Senders = new List<string>()

Senders of messages in chronological order. Senders and Messages refer to each other by index. Senders[x] is the sender of Messages[x].

readonly List< object > Messages = new List<object>()

Messages in chronological order. Senders and Messages refer to each other by index. Senders[x] is the sender of Messages[x].

· int MessageLimit

If greater than 0, this channel will limit the number of messages, that it caches locally.

readonly HashSet< string > Subscribers = new HashSet<string>()

Subscribed users.

Properties

```
• bool IsPrivate [get, set]
```

Is this a private 1:1 channel?

• int MessageCount [get]

Count of messages this client still buffers/knows for this channel.

• int LastMsgld [get, set]

ID of the last message received.

• bool PublishSubscribers [get, set]

Whether or not this channel keeps track of the list of its subscribers.

• int MaxSubscribers [get, set]

Maximum number of channel subscribers. 0 means infinite.

8.6.1 Detailed Description

A channel of communication in Photon Chat, updated by ChatClient and provided as READ ONLY.

Contains messages and senders to use (read!) and display by your GUI. Access these by: ChatClient.Public Channels ChatClient.PrivateChannels

8.6.2 Constructor & Destructor Documentation

8.6.2.1 Photon.Chat.ChatChannel.ChatChannel (string name)

Used internally to create new channels. This does NOT create a channel on the server! Use ChatClient.Subscribe.

8.6.3 Member Function Documentation

8.6.3.1 void Photon.Chat.ChatChannel.Add (string sender, object message, int msgld)

Used internally to add messages to this channel.

8.6.3.2 void Photon.Chat.ChatChannel.Add (string[] senders, object[] messages, int lastMsgld)

Used internally to add messages to this channel.

8.6.3.3 void Photon.Chat.ChatChannel.ClearMessages ()

Clear the local cache of messages currently stored. This frees memory but doesn't affect the server.

8.6.3.4 string Photon.Chat.ChatChannel.ToStringMessages ()

Provides a string-representation of all messages in this channel.

Returns

All known messages in format "Sender: Message", line by line.

8.6.3.5 void Photon.Chat.ChatChannel.TruncateMessages ()

Reduces the number of locally cached messages in this channel to the MessageLimit (if set).

8.6.4 Member Data Documentation

8.6.4.1 int Photon.Chat.ChatChannel.MessageLimit

If greater than 0, this channel will limit the number of messages, that it caches locally.

8.6.4.2 readonly List<object> Photon.Chat.ChatChannel.Messages = new List<object>()

Messages in chronological order. Senders and Messages refer to each other by index. Senders[x] is the sender of Messages[x].

8.6.4.3 readonly string Photon.Chat.ChatChannel.Name

Name of the channel (used to subscribe and unsubscribe).

8.6.4.4 readonly List<string> Photon.Chat.ChatChannel.Senders = new List<string>()

Senders of messages in chronological order. Senders and Messages refer to each other by index. Senders[x] is the sender of Messages[x].

8.6.4.5 readonly HashSet<string> Photon.Chat.ChatChannel.Subscribers = new HashSet<string>()

Subscribed users.

8.6.5 Property Documentation

8.6.5.1 bool Photon.Chat.ChatChannel.lsPrivate [get], [set]

Is this a private 1:1 channel?

8.6.5.2 int Photon.Chat.ChatChannel.LastMsgld [get], [set]

ID of the last message received.

8.6.5.3 int Photon.Chat.ChatChannel.MaxSubscribers [get], [set]

Maximum number of channel subscribers. 0 means infinite.

8.6.5.4 int Photon.Chat.ChatChannel.MessageCount [get]

Count of messages this client still buffers/knows for this channel.

8.6.5.5 bool Photon.Chat.ChatChannel.PublishSubscribers [get], [set]

Whether or not this channel keeps track of the list of its subscribers.

8.7 Photon.Chat.ChatClient Class Reference

Central class of the Photon Chat API to connect, handle channels and messages.

Inherits IPhotonPeerListener.

Public Member Functions

• bool CanChatInChannel (string channelName)

Checks if this client is ready to publish messages inside a public channel.

- ChatClient (IChatClientListener listener, ConnectionProtocol protocol=ConnectionProtocol.Udp)
 Chat client constructor.
- bool Connect (string appld, string appVersion, AuthenticationValues authValues)

Connects this client to the Photon Chat Cloud service, which will also authenticate the user (and set a Userld).

• bool ConnectAndSetStatus (string appId, string appVersion, AuthenticationValues authValues, int status=ChatUserStatus.Online, object message=null)

Connects this client to the Photon Chat Cloud service, which will also authenticate the user (and set a Userld). This also sets an online status once connected. By default it will set user status to ChatUserStatus.Online. See SetOnlineStatus(int,object) for more information.

• void Service ()

Must be called regularly to keep connection between client and server alive and to process incoming messages.

void SendAcksOnly ()

Obsolete: Better use UseBackgroundWorkerForSending and Service().

· void Disconnect ()

Disconnects from the Chat Server by sending a "disconnect command", which prevents a timeout server-side.

void StopThread ()

Locally shuts down the connection to the Chat Server. This resets states locally but the server will have to timeout this peer.

• bool Subscribe (string[] channels)

Sends operation to subscribe to a list of channels by name.

bool Subscribe (string[] channels, int[] lastMsglds)

Sends operation to subscribe to a list of channels by name and possibly retrieve messages we did not receive while unsubscribed.

• bool Subscribe (string[] channels, int messagesFromHistory)

Sends operation to subscribe client to channels, optionally fetching a number of messages from the cache.

bool Unsubscribe (string[] channels)

Unsubscribes from a list of channels, which stops getting messages from those.

bool PublishMessage (string channelName, object message, bool forwardAsWebhook=false)

Sends a message to a public channel which this client subscribed to.

bool SendPrivateMessage (string target, object message, bool forwardAsWebhook=false)

Sends a private message to a single target user. Calls OnPrivateMessage on the receiving client.

bool SendPrivateMessage (string target, object message, bool encrypt, bool forwardAsWebhook)

Sends a private message to a single target user. Calls OnPrivateMessage on the receiving client.

• bool SetOnlineStatus (int status)

Sets the user's status without changing your status-message.

bool SetOnlineStatus (int status, object message)

Sets the user's status without changing your status-message.

bool AddFriends (string[] friends)

Adds friends to a list on the Chat Server which will send you status updates for those.

bool RemoveFriends (string[] friends)

Removes the provided entries from the list on the Chat Server and stops their status updates.

string GetPrivateChannelNameByUser (string userName)

Get you the (locally used) channel name for the chat between this client and another user.

• bool TryGetChannel (string channelName, bool isPrivate, out ChatChannel channel)

Simplified access to either private or public channels by name.

bool TryGetChannel (string channelName, out ChatChannel channel)

Simplified access to all channels by name. Checks public channels first, then private ones.

bool TryGetPrivateChannelByUser (string userId, out ChatChannel channel)

Simplified access to private channels by target user.

• bool Subscribe (string channel, int lastMsgld=0, int messagesFromHistory=-1, ChannelCreationOptions creationOptions=null)

Subscribe to a single channel and optionally sets its well-know channel properties in case the channel is created.

Public Attributes

• const int DefaultMaxSubscribers = 100

Default maximum value possible for ChatChannel.MaxSubscribers when ChatChannel.PublishSubscribers is enabled

int MessageLimit

If greater than 0, new channels will limit the number of messages they cache locally.

· readonly Dictionary< string,

ChatChannel > PublicChannels

Public channels this client is subscribed to.

• readonly Dictionary< string,

ChatChannel > PrivateChannels

Private channels in which this client has exchanged messages.

• ChatPeer chatPeer = null

The Chat Peer used by this client.

Properties

• string NameServerAddress [get, set]

The address of last connected Name Server.

• string FrontendAddress [get, set]

The address of the actual chat server assigned from NameServer. Public for read only.

• string ChatRegion [get, set]

Settable only before you connect! Defaults to "EU".

• ChatState State [get, set]

Current state of the ChatClient. Also use CanChat.

• ChatDisconnectCause DisconnectedCause [get, set]

Disconnection cause. Check this inside IChatClientListener.OnDisconnected.

• bool CanChat [get]

Checks if this client is ready to send messages.

• string AppVersion [get, set]

The version of your client. A new version also creates a new "virtual app" to separate players from older client versions.

• string Appld [get, set]

The AppID as assigned from the Photon Cloud.

• AuthenticationValues AuthValues [get, set]

Settable only before you connect!

• string UserId [get, set]

The unique ID of a user/person, stored in AuthValues. UserId. Set it before you connect.

• bool UseBackgroundWorkerForSending [get, set]

Defines if a background thread will call SendOutgoingCommands, while your code calls Service to dispatch received messages.

ConnectionProtocol TransportProtocol [get, set]

Exposes the TransportProtocol of the used PhotonPeer. Settable while not connected.

· Dictionary< ConnectionProtocol,

Type > SocketImplementationConfig [get]

Defines which IPhotonSocket class to use per ConnectionProtocol.

• DebugLevel DebugOut [get, set]

Sets the level (and amount) of debug output provided by the library.

8.7.1 Detailed Description

Central class of the Photon Chat API to connect, handle channels and messages.

This class must be instantiated with a IChatClientListener instance to get the callbacks. Integrate it into your game loop by calling Service regularly. If the target platform supports Threads/Tasks, set UseBackgroundWorkerFor⇔ Sending = true, to let the ChatClient keep the connection by sending from an independent thread.

Call Connect with an Appld that is setup as Photon Chat application. Note: Connect covers multiple messages between this client and the servers. A short workflow will connect you to a chat server.

Each ChatClient resembles a user in chat (set in Connect). Each user automatically subscribes a channel for incoming private messages and can message any other user privately. Before you publish messages in any non-private channel, that channel must be subscribed.

PublicChannels is a list of subscribed channels, containing messages and senders. PrivateChannels contains all incoming and sent private messages.

8.7.2 Constructor & Destructor Documentation

8.7.2.1 Photon.Chat.ChatClient.ChatClient (IChatClientListener listener, ConnectionProtocol protocol = ConnectionProtocol.Udp)

Chat client constructor.

Parameters

listener	The chat listener implementation.
protocol	Connection protocol to be used by this client. Default is ConnectionProtocol.Udp.

8.7.3 Member Function Documentation

8.7.3.1 bool Photon.Chat.ChatClient.AddFriends (string[] friends)

Adds friends to a list on the Chat Server which will send you status updates for those.

AddFriends and RemoveFriends enable clients to handle their friend list in the Photon Chat server. Having users on your friends list gives you access to their current online status (and whatever info your client sets in it).

Each user can set an online status consisting of an integer and an arbitrary (serializable) object. The object can be null, Hashtable, object[] or anything else Photon can serialize.

The status is published automatically to friends (anyone who set your user ID with AddFriends).

Photon flushes friends-list when a chat client disconnects, so it has to be set each time. If your community API gives you access to online status already, you could filter and set online friends in AddFriends.

Actual friend relations are not persistent and have to be stored outside of Photon.

Parameters

friends	Array of friend userlds.

Returns

If the operation could be sent.

8.7.3.2 bool Photon.Chat.ChatClient.CanChatInChannel (string channelName)

Checks if this client is ready to publish messages inside a public channel.

Parameters

channelName	The channel to do the check with.

Returns

Whether or not this client is ready to publish messages inside the public channel with the specified channel with the specified channel Name.

8.7.3.3 bool Photon.Chat.ChatClient.Connect (string appld, string applversion, AuthenticationValues authValues)

Connects this client to the Photon Chat Cloud service, which will also authenticate the user (and set a UserId).

Parameters

appld	Get your Photon Chat Appld from the Dashboard.
appVersion	Any version string you make up. Used to separate users and variants of your clients, which
	might be incompatible.
authValues	Values for authentication. You can leave this null, if you set a Userld before. If you set authValues, they will override any Userld set before.

Returns

8.7.3.4 bool Photon.Chat.ChatClient.ConnectAndSetStatus (string appld, string applversion, AuthenticationValues authValues, int status = ChatUserStatus.Online, object message = null)

Connects this client to the Photon Chat Cloud service, which will also authenticate the user (and set a Userld). This also sets an online status once connected. By default it will set user status to ChatUserStatus.Online. See SetOnlineStatus(int,object) for more information.

Parameters

appld	Get your Photon Chat Appld from the Dashboard.
appVersion	Any version string you make up. Used to separate users and variants of your clients, which
	might be incompatible.
authValues	Values for authentication. You can leave this null, if you set a Userld before. If you set
	authValues, they will override any Userld set before.
status	User status to set when connected. Predefined states are in class ChatUserStatus. Other
	values can be used at will.
message	Optional status Also sets a status-message which your friends can get.

Returns

If the connection attempt could be sent at all.

8.7.3.5 void Photon.Chat.ChatClient.Disconnect ()

Disconnects from the Chat Server by sending a "disconnect command", which prevents a timeout server-side.

8.7.3.6 string Photon.Chat.ChatClient.GetPrivateChannelNameByUser (string userName)

Get you the (locally used) channel name for the chat between this client and another user.

Parameters

userName	Remote user's name or Userld.
----------	-------------------------------

Returns

The (locally used) channel name for a private channel.

Do not subscribe to this channel. Private channels do not need to be explicitly subscribed to. Use this for debugging purposes mainly.

8.7.3.7 bool Photon.Chat.ChatClient.PublishMessage (string *channelName*, object *message*, bool *forwardAsWebhook* = false)

Sends a message to a public channel which this client subscribed to.

Before you publish to a channel, you have to subscribe it. Everyone in that channel will get the message.

Parameters

channelName	Name of the channel to publish to.
message	Your message (string or any serializable data).
forwardAs⇔	Optionally, public messages can be forwarded as webhooks. Configure webhooks for your
Webhook	Chat app to use this.

Returns

False if the client is not yet ready to send messages.

8.7.3.8 bool Photon.Chat.ChatClient.RemoveFriends (string[] friends)

Removes the provided entries from the list on the Chat Server and stops their status updates.

Photon flushes friends-list when a chat client disconnects. Unless you want to remove individual entries, you don't have to RemoveFriends.

AddFriends and RemoveFriends enable clients to handle their friend list in the Photon Chat server. Having users on your friends list gives you access to their current online status (and whatever info your client sets in it).

Each user can set an online status consisting of an integer and an arbitratry (serializable) object. The object can be null, Hashtable, object[] or anything else Photon can serialize.

The status is published automatically to friends (anyone who set your user ID with AddFriends).

Photon flushes friends-list when a chat client disconnects, so it has to be set each time. If your community API gives you access to online status already, you could filter and set online friends in AddFriends.

Actual friend relations are not persistent and have to be stored outside of Photon.

AddFriends and RemoveFriends enable clients to handle their friend list in the Photon Chat server. Having users on your friends list gives you access to their current online status (and whatever info your client sets in it).

Each user can set an online status consisting of an integer and an arbitratry (serializable) object. The object can be null, Hashtable, object[] or anything else Photon can serialize.

The status is published automatically to friends (anyone who set your user ID with AddFriends).

Actual friend relations are not persistent and have to be stored outside of Photon.

Parameters

friends	Array of friend userlds.

Returns

If the operation could be sent.

8.7.3.9 void Photon.Chat.ChatClient.SendAcksOnly ()

Obsolete: Better use UseBackgroundWorkerForSending and Service().

8.7.3.10 bool Photon.Chat.ChatClient.SendPrivateMessage (string *target*, object *message*, bool *forwardAsWebhook* = false)

Sends a private message to a single target user. Calls OnPrivateMessage on the receiving client.

Parameters

target	Username to send this message to.
message	The message you want to send. Can be a simple string or anything serializable.
forwardAs⇔	Optionally, private messages can be forwarded as webhooks. Configure webhooks for your
Webhook	Chat app to use this.

Returns

True if this clients can send the message to the server.

8.7.3.11 bool Photon.Chat.ChatClient.SendPrivateMessage (string *target*, object *message*, bool *encrypt*, bool *forwardAsWebhook*)

Sends a private message to a single target user. Calls OnPrivateMessage on the receiving client.

Parameters

target	Username to send this message to.
message	The message you want to send. Can be a simple string or anything serializable.
encrypt	Optionally, private messages can be encrypted. Encryption is not end-to-end as the server
	decrypts the message.
forwardAs⇔	Optionally, private messages can be forwarded as webhooks. Configure webhooks for your
Webhook	Chat app to use this.

Returns

True if this clients can send the message to the server.

8.7.3.12 void Photon.Chat.ChatClient.Service ()

Must be called regularly to keep connection between client and server alive and to process incoming messages.

This method limits the effort it does automatically using the private variable msDeltaForServiceCalls. That value is lower for connect and multiplied by 4 when chat-server connection is ready.

8.7.3.13 bool Photon.Chat.ChatClient.SetOnlineStatus (int status)

Sets the user's status without changing your status-message.

The predefined status values can be found in class ChatUserStatus. State ChatUserStatus.Invisible will make you offline for everyone and send no message.

You can set custom values in the status integer. Aside from the pre-configured ones, all states will be considered visible and online. Else, no one would see the custom state.

This overload does not change the set message.

Parameters

status	Predefined states are in class ChatUserStatus. Other values can be used at will.
--------	--

Returns

True if the operation gets called on the server.

8.7.3.14 bool Photon.Chat.ChatClient.SetOnlineStatus (int status, object message)

Sets the user's status without changing your status-message.

The predefined status values can be found in class ChatUserStatus. State ChatUserStatus.Invisible will make you offline for everyone and send no message.

You can set custom values in the status integer. Aside from the pre-configured ones, all states will be considered visible and online. Else, no one would see the custom state.

The message object can be anything that Photon can serialize, including (but not limited to) Hashtable, object[] and string. This value is defined by your own conventions.

Parameters

status	Predefined states are in class ChatUserStatus. Other values can be used at will.
message	Also sets a status-message which your friends can get.

Returns

True if the operation gets called on the server.

8.7.3.15 void Photon.Chat.ChatClient.StopThread ()

Locally shuts down the connection to the Chat Server. This resets states locally but the server will have to timeout this peer.

8.7.3.16 bool Photon.Chat.ChatClient.Subscribe (string[] channels)

Sends operation to subscribe to a list of channels by name.

Parameters

channels	List of channels to subscribe to. Avoid null or empty values.

Returns

If the operation could be sent at all (Example: Fails if not connected to Chat Server).

8.7.3.17 bool Photon.Chat.ChatClient.Subscribe (string[] channels, int[] lastMsglds)

Sends operation to subscribe to a list of channels by name and possibly retrieve messages we did not receive while unsubscribed.

Parameters

channels	List of channels to subscribe to. Avoid null or empty values.
lastMsglds	ID of last message received per channel. Useful when re subscribing to receive only mes-
	sages we missed.

Returns

If the operation could be sent at all (Example: Fails if not connected to Chat Server).

8.7.3.18 bool Photon.Chat.ChatClient.Subscribe (string[] channels, int messagesFromHistory)

Sends operation to subscribe client to channels, optionally fetching a number of messages from the cache.

Subscribes channels will forward new messages to this user. Use PublishMessage to do so. The messages cache is limited but can be useful to get into ongoing conversations, if that's needed.

Parameters

channels	List of channels to subscribe to. Avoid null or empty values.
messages⇔	0: no history. 1 and higher: number of messages in history1: all available history.
FromHistory	

Returns

If the operation could be sent at all (Example: Fails if not connected to Chat Server).

8.7.3.19 bool Photon.Chat.ChatClient.Subscribe (string *channel*, int *lastMsgld* = 0, int *messagesFromHistory* = -1, ChannelCreationOptions *creationOptions* = null)

Subscribe to a single channel and optionally sets its well-know channel properties in case the channel is created.

Parameters

channel	name of the channel to subscribe to
lastMsgld	ID of the last received message from this channel when re subscribing to receive only missed
	messages, default is 0
messages⇔	how many missed messages to receive from history, default is none/-1
FromHistory	
creationOptions	options to be used in case the channel to subscribe to will be created.

Returns

8.7.3.20 bool Photon.Chat.ChatClient.TryGetChannel (string channelName, bool isPrivate, out ChatChannel channel)

Simplified access to either private or public channels by name.

Parameters

channelName	Name of the channel to get. For private channels, the channel-name is composed of both
	user's names.

isPrivate	Define if you expect a private or public channel.
channel	Out parameter gives you the found channel, if any.

Returns

True if the channel was found.

Public channels exist only when subscribed to them. Private channels exist only when at least one message is exchanged with the target user privately.

8.7.3.21 bool Photon.Chat.ChatClient.TryGetChannel (string channelName, out ChatChannel channel)

Simplified access to all channels by name. Checks public channels first, then private ones.

Parameters

channelName	Name of the channel to get.
channel	Out parameter gives you the found channel, if any.

Returns

True if the channel was found.

Public channels exist only when subscribed to them. Private channels exist only when at least one message is exchanged with the target user privately.

8.7.3.22 bool Photon.Chat.ChatClient.TryGetPrivateChannelByUser (string userId, out ChatChannel channel)

Simplified access to private channels by target user.

Parameters

userld	UserId of the target user in the private channel.
channel	Out parameter gives you the found channel, if any.

Returns

True if the channel was found.

8.7.3.23 bool Photon.Chat.ChatClient.Unsubscribe (string[] channels)

Unsubscribes from a list of channels, which stops getting messages from those.

The client will remove these channels from the PublicChannels dictionary once the server sent a response to this request.

The request will be sent to the server and IChatClientListener.OnUnsubscribed gets called when the server actually removed the channel subscriptions.

Unsubscribe will fail if you include null or empty channel names.

Parameters

channels	Names of channels to unsubscribe.
----------	-----------------------------------

Returns

False, if not connected to a chat server.

8.7.4 Member Data Documentation

8.7.4.1 ChatPeer Photon.Chat.ChatClient.chatPeer = null

The Chat Peer used by this client.

8.7.4.2 const int Photon.Chat.ChatClient.DefaultMaxSubscribers = 100

Default maximum value possible for ChatChannel.MaxSubscribers when ChatChannel.PublishSubscribers is enabled

8.7.4.3 int Photon.Chat.ChatClient.MessageLimit

If greater than 0, new channels will limit the number of messages they cache locally.

This can be useful to limit the amount of memory used by chats. You can set a MessageLimit per channel but this value gets applied to new ones.

Note: Changing this value, does not affect ChatChannels that are already in use!

8.7.4.4 readonly Dictionary < string, ChatChannel > Photon. Chat. ChatClient. Private Channels

Private channels in which this client has exchanged messages.

8.7.4.5 readonly Dictionary < string, ChatChannel > Photon. Chat. ChatClient. Public Channels

Public channels this client is subscribed to.

8.7.5 Property Documentation

8.7.5.1 string Photon.Chat.ChatClient.Appld [get], [set]

The AppID as assigned from the Photon Cloud.

8.7.5.2 string Photon.Chat.ChatClient.AppVersion [get], [set]

The version of your client. A new version also creates a new "virtual app" to separate players from older client versions.

8.7.5.3 Authentication Values Photon. Chat. Chat Client. Auth Values [get], [set]

Settable only before you connect!

8.7.5.4 bool Photon.Chat.ChatClient.CanChat [get]

Checks if this client is ready to send messages.

8.7.5.5 string Photon.Chat.ChatClient.ChatRegion [get], [set]

Settable only before you connect! Defaults to "EU".

8.7.5.6 DebugLevel Photon.Chat.ChatClient.DebugOut [get], [set]

Sets the level (and amount) of debug output provided by the library.

This affects the callbacks to IChatClientListener.DebugReturn. Default Level: Error.

 $\textbf{8.7.5.7} \quad \textbf{ChatDisconnectCause Photon.Chat.ChatClient.DisconnectedCause} \quad \texttt{[get], [set]}$

Disconnection cause. Check this inside IChatClientListener.OnDisconnected.

8.7.5.8 string Photon.Chat.ChatClient.FrontendAddress [get], [set]

The address of the actual chat server assigned from NameServer. Public for read only.

8.7.5.9 string Photon.Chat.ChatClient.NameServerAddress [get], [set]

The address of last connected Name Server.

8.7.5.10 Dictionary < Connection Protocol, Type > Photon. Chat. Chat Client. Socket Implementation Config [qet]

Defines which IPhotonSocket class to use per ConnectionProtocol.

Several platforms have special Socket implementations and slightly different APIs. To accommodate this, switching the socket implementation for a network protocol was made available. By default, UDP and TCP have socket implementations assigned.

You only need to set the SocketImplementationConfig once, after creating a PhotonPeer and before connecting. If you switch the TransportProtocol, the correct implementation is being used.

8.7.5.11 ChatState Photon.Chat.ChatClient.State [get], [set]

Current state of the ChatClient. Also use CanChat.

8.7.5.12 ConnectionProtocol Photon.Chat.ChatClient.TransportProtocol [get], [set]

Exposes the TransportProtocol of the used PhotonPeer. Settable while not connected.

8.7.5.13 bool Photon.Chat.ChatClient.UseBackgroundWorkerForSending [get], [set]

Defines if a background thread will call SendOutgoingCommands, while your code calls Service to dispatch received messages.

The benefit of using a background thread to call SendOutgoingCommands is this:

Even if your game logic is being paused, the background thread will keep the connection to the server up. On a lower level, acknowledgements and pings will prevent a server-side timeout while (e.g.) Unity loads assets.

Your game logic still has to call Service regularly, or else incoming messages are not dispatched. As this typically triggers UI updates, it's easier to call Service from the main/UI thread.

8.7.5.14 string Photon.Chat.ChatClient.UserId [get], [set]

The unique ID of a user/person, stored in AuthValues.UserId. Set it before you connect.

This value wraps AuthValues.UserId. It's not a nickname and we assume users with the same userID are the same person.

8.8 Photon.Chat.ChatEventCode Class Reference

Wraps up internally used constants in Photon Chat events. You don't have to use them directly usually.

Public Attributes

- const byte ChatMessages = 0
 - (0) Event code for messages published in public channels.
- const byte Users = 1
 - (1) Not Used.
- const byte PrivateMessage = 2
 - (2) Event code for messages published in private channels
- const byte FriendsList = 3
 - (3) Not Used.
- const byte StatusUpdate = 4
 - (4) Event code for status updates.
- const byte Subscribe = 5
 - (5) Event code for subscription acks.
- const byte Unsubscribe = 6
 - (6) Event code for unsubscribe acks.
- const byte UserSubscribed = 8
 - (7) Event code for new user subscription to a channel where ChatChannel. PublishSubscribers is enabled.
- const byte UserUnsubscribed = 9
 - (8) Event code for when user unsubscribes from a channel where ChatChannel.PublishSubscribers is enabled.

8.8.1 Detailed Description

Wraps up internally used constants in Photon Chat events. You don't have to use them directly usually.

8.8.2 Member Data Documentation

- 8.8.2.1 const byte Photon.Chat.ChatEventCode.ChatMessages = 0
- (0) Event code for messages published in public channels.
- 8.8.2.2 const byte Photon.Chat.ChatEventCode.FriendsList = 3
- (3) Not Used.
- 8.8.2.3 const byte Photon.Chat.ChatEventCode.PrivateMessage = 2
- (2) Event code for messages published in private channels
- 8.8.2.4 const byte Photon.Chat.ChatEventCode.StatusUpdate = 4
- (4) Event code for status updates.
- 8.8.2.5 const byte Photon.Chat.ChatEventCode.Subscribe = 5
- (5) Event code for subscription acks.

- 8.8.2.6 const byte Photon.Chat.ChatEventCode.Unsubscribe = 6
- (6) Event code for unsubscribe acks.
- 8.8.2.7 const byte Photon.Chat.ChatEventCode.Users = 1
- (1) Not Used.
- 8.8.2.8 const byte Photon.Chat.ChatEventCode.UserSubscribed = 8
- (7) Event code for new user subscription to a channel where ChatChannel.PublishSubscribers is enabled.
- 8.8.2.9 const byte Photon.Chat.ChatEventCode.UserUnsubscribed = 9
- (8) Event code for when user unsubscribes from a channel where ChatChannel.PublishSubscribers is enabled.

8.9 Photon.Chat.ChatOperationCode Class Reference

Wraps up codes for operations used internally in Photon Chat. You don't have to use them directly usually.

Public Attributes

- const byte Authenticate = 230
 - (230) Operation Authenticate.
- const byte Subscribe = 0
 - (0) Operation to subscribe to chat channels.
- const byte Unsubscribe = 1
 - (1) Operation to unsubscribe from chat channels.
- const byte Publish = 2
 - (2) Operation to publish a message in a chat channel.
- const byte SendPrivate = 3
 - (3) Operation to send a private message to some other user.
- const byte ChannelHistory = 4
 - (4) Not used yet.
- const byte UpdateStatus = 5
 - (5) Set your (client's) status.
- const byte AddFriends = 6
 - (6) Add friends the list of friends that should update you of their status.
- const byte RemoveFriends = 7
 - (7) Remove friends from list of friends that should update you of their status.

8.9.1 Detailed Description

Wraps up codes for operations used internally in Photon Chat. You don't have to use them directly usually.

- 8.9.2 Member Data Documentation
- 8.9.2.1 const byte Photon.Chat.ChatOperationCode.AddFriends = 6
- (6) Add friends the list of friends that should update you of their status.

- 8.9.2.2 const byte Photon.Chat.ChatOperationCode.Authenticate = 230
- (230) Operation Authenticate.
- 8.9.2.3 const byte Photon.Chat.ChatOperationCode.ChannelHistory = 4
- (4) Not used yet.
- 8.9.2.4 const byte Photon.Chat.ChatOperationCode.Publish = 2
- (2) Operation to publish a message in a chat channel.
- 8.9.2.5 const byte Photon.Chat.ChatOperationCode.RemoveFriends = 7
- (7) Remove friends from list of friends that should update you of their status.
- 8.9.2.6 const byte Photon.Chat.ChatOperationCode.SendPrivate = 3
- (3) Operation to send a private message to some other user.
- 8.9.2.7 const byte Photon.Chat.ChatOperationCode.Subscribe = 0
- (0) Operation to subscribe to chat channels.
- 8.9.2.8 const byte Photon.Chat.ChatOperationCode.Unsubscribe = 1
- (1) Operation to unsubscribe from chat channels.
- 8.9.2.9 const byte Photon.Chat.ChatOperationCode.UpdateStatus = 5
- (5) Set your (client's) status.

8.10 Photon.Chat.ChatParameterCode Class Reference

Wraps up codes for parameters (in operations and events) used internally in Photon Chat. You don't have to use them directly usually.

Public Attributes

- const byte Channels = 0
 - (0) Array of chat channels.
- const byte Channel = 1
 - (1) Name of a single chat channel.
- const byte Messages = 2
 - (2) Array of chat messages.
- const byte Message = 3
 - (3) A single chat message.
- const byte Senders = 4
 - (4) Array of names of the users who sent the array of chat messages.

- const byte Sender = 5
 - (5) Name of a the user who sent a chat message.
- const byte ChannelUserCount = 6
 - (6) Not used.
- const byte UserId = 225
 - (225) Name of user to send a (private) message to.
- const byte Msgld = 8
 - (8) Id of a message.
- const byte Msglds = 9
 - (9) Not used.
- const byte Secret = 221
 - (221) Secret token to identify an authorized user.
- const byte SubscribeResults = 15
 - (15) Subscribe operation result parameter. A bool[] with result per channel.
- const byte Status = 10
 - (10) Status
- const byte Friends = 11
 - (11) Friends
- const byte SkipMessage = 12
 - (12) SkipMessage is used in SetOnlineStatus and if true, the message is not being broadcast.
- const byte HistoryLength = 14
 - (14) Number of message to fetch from history. 0: no history. 1 and higher: number of messages in history. -1: all history.
- const byte WebFlags = 21
 - (21) WebFlags object for changing behaviour of webhooks from client.
- const byte Properties = 22
 - (22) Properties of channel or user.
- const byte ChannelSubscribers = 23
 - (23) Array of Userlds of users already subscribed to a channel.

8.10.1 Detailed Description

Wraps up codes for parameters (in operations and events) used internally in Photon Chat. You don't have to use them directly usually.

8.10.2 Member Data Documentation

- 8.10.2.1 const byte Photon.Chat.ChatParameterCode.Channel = 1
- (1) Name of a single chat channel.
- 8.10.2.2 const byte Photon.Chat.ChatParameterCode.Channels = 0
- (0) Array of chat channels.
- 8.10.2.3 const byte Photon.Chat.ChatParameterCode.ChannelSubscribers = 23
- (23) Array of Userlds of users already subscribed to a channel.

Used in Subscribe event when PublishSubscribers is enabled. Does not include local user who just subscribed. Maximum length is (ChatChannel.MaxSubscribers - 1).

8.10.2.4 const byte Photon.Chat.ChatParameterCode.ChannelUserCount = 6 (6) Not used. 8.10.2.5 const byte Photon.Chat.ChatParameterCode.Friends = 11 (11) Friends 8.10.2.6 const byte Photon.Chat.ChatParameterCode.HistoryLength = 14 (14) Number of message to fetch from history. 0: no history. 1 and higher: number of messages in history. -1: all history. 8.10.2.7 const byte Photon.Chat.ChatParameterCode.Message = 3 (3) A single chat message. 8.10.2.8 const byte Photon.Chat.ChatParameterCode.Messages = 2 (2) Array of chat messages. 8.10.2.9 const byte Photon.Chat.ChatParameterCode.Msgld = 8 (8) Id of a message. 8.10.2.10 const byte Photon.Chat.ChatParameterCode.Msglds = 9 (9) Not used. 8.10.2.11 const byte Photon.Chat.ChatParameterCode.Properties = 22 (22) Properties of channel or user. In event ChatEventCode.Subscribe it's always channel properties. 8.10.2.12 const byte Photon.Chat.ChatParameterCode.Secret = 221 (221) Secret token to identify an authorized user. The code is used in LoadBalancing and copied over here. 8.10.2.13 const byte Photon.Chat.ChatParameterCode.Sender = 5 (5) Name of a the user who sent a chat message. 8.10.2.14 const byte Photon.Chat.ChatParameterCode.Senders = 4

(4) Array of names of the users who sent the array of chat messages.

- 8.10.2.15 const byte Photon.Chat.ChatParameterCode.SkipMessage = 12
- (12) SkipMessage is used in SetOnlineStatus and if true, the message is not being broadcast.
- 8.10.2.16 const byte Photon.Chat.ChatParameterCode.Status = 10
- (10) Status
- 8.10.2.17 const byte Photon.Chat.ChatParameterCode.SubscribeResults = 15
- (15) Subscribe operation result parameter. A bool[] with result per channel.
- 8.10.2.18 const byte Photon.Chat.ChatParameterCode.UserId = 225
- (225) Name of user to send a (private) message to.

The code is used in LoadBalancing and copied over here.

- 8.10.2.19 const byte Photon.Chat.ChatParameterCode.WebFlags = 21
- (21) WebFlags object for changing behaviour of webhooks from client.

8.11 Photon.Chat.ChatPeer Class Reference

Provides basic operations of the Photon Chat server. This internal class is used by public ChatClient. Inherits PhotonPeer.

Public Member Functions

- ChatPeer (IPhotonPeerListener listener, ConnectionProtocol protocol)

 Chat Peer constructor.
- bool Connect ()

Connects to NameServer.

bool AuthenticateOnNameServer (string appId, string appVersion, string region, AuthenticationValues auth
 Values)

Authenticates on NameServer.

Public Attributes

- const string NameServerHost = "ns.exitgames.com"
 - Name Server Host Name for Photon Cloud. Without port and without any prefix.
- const string NameServerHttp = "http://ns.exitgamescloud.com:80/photon/n"

Name Server for HTTP connections to the Photon Cloud. Includes prefix and port.

Properties

• string NameServerAddress [get]

Name Server Address for Photon Cloud (based on current protocol). You can use the default values and usually won't have to set this value.

8.11.1 Detailed Description

Provides basic operations of the Photon Chat server. This internal class is used by public ChatClient.

8.11.2 Constructor & Destructor Documentation

8.11.2.1 Photon.Chat.ChatPeer.ChatPeer (IPhotonPeerListener listener, ConnectionProtocol protocol)

Chat Peer constructor.

Parameters

listener	Chat listener implementation.
protocol	Protocol to be used by the peer.

8.11.3 Member Function Documentation

8.11.3.1 bool Photon.Chat.ChatPeer.AuthenticateOnNameServer (string appld, string applversion, string region, AuthenticationValues authValues)

Authenticates on NameServer.

Returns

If the authentication operation request could be sent.

8.11.3.2 bool Photon.Chat.ChatPeer.Connect ()

Connects to NameServer.

Returns

If the connection attempt could be sent.

8.11.4 Member Data Documentation

8.11.4.1 const string Photon.Chat.ChatPeer.NameServerHost = "ns.exitgames.com"

Name Server Host Name for Photon Cloud. Without port and without any prefix.

8.11.4.2 const string Photon.Chat.ChatPeer.NameServerHttp = "http://ns.exitgamescloud.com:80/photon/n"

Name Server for HTTP connections to the Photon Cloud. Includes prefix and port.

8.11.5 Property Documentation

8.11.5.1 string Photon.Chat.ChatPeer.NameServerAddress [get]

Name Server Address for Photon Cloud (based on current protocol). You can use the default values and usually won't have to set this value.

8.12 Photon.Chat.ChatUserStatus Class Reference

Contains commonly used status values for SetOnlineStatus. You can define your own.

Public Attributes

```
• const int Offline = 0
```

(0) Offline.

- const int Invisible = 1
 - (1) Be invisible to everyone. Sends no message.
- const int Online = 2
 - (2) Online and available.
- const int Away = 3
 - (3) Online but not available.
- const int DND = 4
 - (4) Do not disturb.
- const int LFG = 5
 - (5) Looking For Game/Group. Could be used when you want to be invited or do matchmaking.
- const int Playing = 6
 - (6) Could be used when in a room, playing.

8.12.1 Detailed Description

Contains commonly used status values for SetOnlineStatus. You can define your own.

While "online" (value 2 and up), the status message will be sent to anyone who has you on his friend list.

Define custom online status values as you like with these rules: 0: Means "offline". It will be used when you are not connected. In this status, there is no status message. 1: Means "invisible" and is sent to friends as "offline". They see status 0, no message but you can chat. 2: And any higher value will be treated as "online". Status can be set.

8.12.2 Member Data Documentation

- 8.12.2.1 const int Photon.Chat.ChatUserStatus.Away = 3
- (3) Online but not available.
- 8.12.2.2 const int Photon, Chat, ChatUserStatus, DND = 4
- (4) Do not disturb.
- 8.12.2.3 const int Photon.Chat.ChatUserStatus.Invisible = 1
- (1) Be invisible to everyone. Sends no message.
- 8.12.2.4 const int Photon.Chat.ChatUserStatus.LFG = 5
- (5) Looking For Game/Group. Could be used when you want to be invited or do matchmaking.
- 8.12.2.5 const int Photon.Chat.ChatUserStatus.Offline = 0
- (0) Offline.
- 8.12.2.6 const int Photon.Chat.ChatUserStatus.Online = 2
- (2) Online and available.

- 8.12.2.7 const int Photon.Chat.ChatUserStatus.Playing = 6
- (6) Could be used when in a room, playing.

8.13 EncryptionDataParameters Class Reference

Public Attributes

```
• const byte Mode = 0
```

Key for encryption mode

• const byte Secret1 = 1

Key for first secret

• const byte Secret2 = 2

Key for second secret

8.13.1 Member Data Documentation

8.13.1.1 const byte EncryptionDataParameters.Mode = 0

Key for encryption mode

8.13.1.2 const byte EncryptionDataParameters.Secret1 = 1

Key for first secret

8.13.1.3 const byte EncryptionDataParameters.Secret2 = 2

Key for second secret

8.14 Photon.Chat.ErrorCode Class Reference

ErrorCode defines the default codes associated with Photon client/server communication.

Public Attributes

- const int Ok = 0
 - (0) is always "OK", anything else an error or specific situation.
- const int OperationNotAllowedInCurrentState = -3
 - (-3) Operation can't be executed yet (e.g. OpJoin can't be called before being authenticated, RaiseEvent cant be used before getting into a room).
- const int InvalidOperationCode = -2
 - (-2) The operation you called is not implemented on the server (application) you connect to. Make sure you run the fitting applications.
- const int InternalServerError = -1
 - (-1) Something went wrong in the server. Try to reproduce and contact Exit Games.
- const int InvalidAuthentication = 0x7FFF
 - (32767) Authentication failed. Possible cause: Appld is unknown to Photon (in cloud service).
- const int GameIdAlreadyExists = 0x7FFF 1
 - (32766) Gameld (name) already in use (can't create another). Change name.

const int GameFull = 0x7FFF - 2

(32765) Game is full. This rarely happens when some player joined the room before your join completed.

const int GameClosed = 0x7FFF - 3

(32764) Game is closed and can't be joined. Join another game.

const int ServerFull = 0x7FFF - 5

(32762) Not in use currently.

• const int UserBlocked = 0x7FFF - 6

(32761) Not in use currently.

• const int NoRandomMatchFound = 0x7FFF - 7

(32760) Random matchmaking only succeeds if a room exists that is neither closed nor full. Repeat in a few seconds or create a new room.

const int GameDoesNotExist = 0x7FFF - 9

(32758) Join can fail if the room (name) is not existing (anymore). This can happen when players leave while you join.

• const int MaxCcuReached = 0x7FFF - 10

(32757) Authorization on the Photon Cloud failed because the concurrent users (CCU) limit of the app's subscription is reached.

const int InvalidRegion = 0x7FFF - 11

(32756) Authorization on the Photon Cloud failed because the app's subscription does not allow to use a particular region's server.

const int CustomAuthenticationFailed = 0x7FFF - 12

(32755) Custom Authentication of the user failed due to setup reasons (see Cloud Dashboard) or the provided user data (like username or token). Check error message for details.

8.14.1 Detailed Description

ErrorCode defines the default codes associated with Photon client/server communication.

8.14.2 Member Data Documentation

8.14.2.1 const int Photon.Chat.ErrorCode.CustomAuthenticationFailed = 0x7FFF - 12

(32755) Custom Authentication of the user failed due to setup reasons (see Cloud Dashboard) or the provided user data (like username or token). Check error message for details.

8.14.2.2 const int Photon.Chat.ErrorCode.GameClosed = 0x7FFF - 3

(32764) Game is closed and can't be joined. Join another game.

8.14.2.3 const int Photon.Chat.ErrorCode.GameDoesNotExist = 0x7FFF - 9

(32758) Join can fail if the room (name) is not existing (anymore). This can happen when players leave while you join.

8.14.2.4 const int Photon.Chat.ErrorCode.GameFull = 0x7FFF - 2

(32765) Game is full. This rarely happens when some player joined the room before your join completed.

8.14.2.5 const int Photon.Chat.ErrorCode.GameIdAlreadyExists = 0x7FFF - 1

(32766) Gameld (name) already in use (can't create another). Change name.

- 8.14.2.6 const int Photon.Chat.ErrorCode.InternalServerError = -1
- (-1) Something went wrong in the server. Try to reproduce and contact Exit Games.
- 8.14.2.7 const int Photon.Chat.ErrorCode.InvalidAuthentication = 0x7FFF
- (32767) Authentication failed. Possible cause: Appld is unknown to Photon (in cloud service).
- 8.14.2.8 const int Photon.Chat.ErrorCode.InvalidOperationCode = -2
- (-2) The operation you called is not implemented on the server (application) you connect to. Make sure you run the fitting applications.
- 8.14.2.9 const int Photon.Chat.ErrorCode.InvalidRegion = 0x7FFF 11

(32756) Authorization on the Photon Cloud failed because the app's subscription does not allow to use a particular region's server.

Some subscription plans for the Photon Cloud are region-bound. Servers of other regions can't be used then. Check your master server address and compare it with your Photon Cloud Dashboard's info. https://cloud.ephotonengine.com/dashboard

OpAuthorize is part of connection workflow but only on the Photon Cloud, this error can happen. Self-hosted Photon servers with a CCU limited license won't let a client connect at all.

- 8.14.2.10 const int Photon.Chat.ErrorCode.MaxCcuReached = 0x7FFF 10
- (32757) Authorization on the Photon Cloud failed because the concurrent users (CCU) limit of the app's subscription is reached.

Unless you have a plan with "CCU Burst", clients might fail the authentication step during connect. Affected client are unable to call operations. Please note that players who end a game and return to the master server will disconnect and re-connect, which means that they just played and are rejected in the next minute / re-connect. This is a temporary measure. Once the CCU is below the limit, players will be able to connect an play again.

OpAuthorize is part of connection workflow but only on the Photon Cloud, this error can happen. Self-hosted Photon servers with a CCU limited license won't let a client connect at all.

- 8.14.2.11 const int Photon.Chat.ErrorCode.NoRandomMatchFound = 0x7FFF 7
- (32760) Random matchmaking only succeeds if a room exists that is neither closed nor full. Repeat in a few seconds or create a new room.
- 8.14.2.12 const int Photon.Chat.ErrorCode.Ok = 0
- (0) is always "OK", anything else an error or specific situation.
- 8.14.2.13 const int Photon.Chat.ErrorCode.OperationNotAllowedInCurrentState = -3
- (-3) Operation can't be executed yet (e.g. OpJoin can't be called before being authenticated, RaiseEvent cant be used before getting into a room).

Before you call any operations on the Cloud servers, the automated client workflow must complete its authorization. In PUN, wait until State is: JoinedLobby or ConnectedToMaster

```
8.14.2.14 const int Photon.Chat.ErrorCode.ServerFull = 0x7FFF - 5
(32762) Not in use currently.
8.14.2.15 const int Photon.Chat.ErrorCode.UserBlocked = 0x7FFF - 6
```

8.15 ErrorCode Class Reference

ErrorCode defines the default codes associated with Photon client/server communication.

Public Attributes

const int Ok = 0

(32761) Not in use currently.

- (0) is always "OK", anything else an error or specific situation.
- const int OperationNotAllowedInCurrentState = -3
 - (-3) Operation can't be executed yet (e.g. OpJoin can't be called before being authenticated, RaiseEvent cant be used before getting into a room).
- const int InvalidOperationCode = -2
 - (-2) The operation you called is not implemented on the server (application) you connect to. Make sure you run the fitting applications.
- const int InvalidOperation = -2
 - (-2) The operation you called could not be executed on the server.
- const int InternalServerError = -1
 - (-1) Something went wrong in the server. Try to reproduce and contact Exit Games.
- const int InvalidAuthentication = 0x7FFF
 - (32767) Authentication failed. Possible cause: Appld is unknown to Photon (in cloud service).
- const int GameIdAlreadyExists = 0x7FFF 1
 - (32766) Gameld (name) already in use (can't create another). Change name.
- const int GameFull = 0x7FFF 2
 - (32765) Game is full. This rarely happens when some player joined the room before your join completed.
- const int GameClosed = 0x7FFF 3
 - (32764) Game is closed and can't be joined. Join another game.
- const int AlreadyMatched = 0x7FFF 4
- const int ServerFull = 0x7FFF 5
 - (32762) Not in use currently.
- const int UserBlocked = 0x7FFF 6
 - (32761) Not in use currently.
- const int NoRandomMatchFound = 0x7FFF 7
 - (32760) Random matchmaking only succeeds if a room exists thats neither closed nor full. Repeat in a few seconds or create a new room.
- const int GameDoesNotExist = 0x7FFF 9
 - (32758) Join can fail if the room (name) is not existing (anymore). This can happen when players leave while you join.
- const int MaxCcuReached = 0x7FFF 10
 - (32757) Authorization on the Photon Cloud failed becaus the concurrent users (CCU) limit of the app's subscription is reached.
- const int InvalidRegion = 0x7FFF 11
 - (32756) Authorization on the Photon Cloud failed because the app's subscription does not allow to use a particular region's server.
- const int CustomAuthenticationFailed = 0x7FFF 12

(32755) Custom Authentication of the user failed due to setup reasons (see Cloud Dashboard) or the provided user data (like username or token). Check error message for details.

const int AuthenticationTicketExpired = 0x7FF1

(32753) The Authentication ticket expired. Usually, this is refreshed behind the scenes. Connect (and authorize) again.

const int PluginReportedError = 0x7FFF - 15

(32752) A server-side plugin (or webhook) failed to execute and reported an error. Check the OperationResponse. ← DebugMessage.

• const int PluginMismatch = 0x7FFF - 16

(32751) CreateRoom/JoinRoom/Join operation fails if expected plugin does not correspond to loaded one.

const int JoinFailedPeerAlreadyJoined = 32750

(32750) for join requests. Indicates the current peer already called join and is joined to the room.

const int JoinFailedFoundInactiveJoiner = 32749

(32749) for join requests. Indicates the list of InactiveActors already contains an actor with the requested ActorNr or Userld.

const int JoinFailedWithRejoinerNotFound = 32748

(32748) for join requests. Indicates the list of Actors (active and inactive) did not contain an actor with the requested ActorNr or UserId.

const int JoinFailedFoundExcludedUserId = 32747

(32747) for join requests. Note: for future use - Indicates the requested UserId was found in the ExcludedList.

• const int JoinFailedFoundActiveJoiner = 32746

(32746) for join requests. Indicates the list of ActiveActors already contains an actor with the requested ActorNr or Userld.

const int HttpLimitReached = 32745

(32745) for SetProerties and Raisevent (if flag HttpForward is true) requests. Indicates the maximum allowd http requests per minute was reached.

const int ExternalHttpCallFailed = 32744

(32744) for WebRpc requests. Indicates the the call to the external service failed.

• const int SlotError = 32742

(32742) Server error during matchmaking with slot reservation. E.g. the reserved slots can not exceed MaxPlayers.

• const int InvalidEncryptionParameters = 32741

(32741) Server will react with this error if invalid encryption parameters provided by token

8.15.1 Detailed Description

ErrorCode defines the default codes associated with Photon client/server communication.

8.15.2 Member Data Documentation

8.15.2.1 const int ErrorCode.AlreadyMatched = 0x7FFF - 4

8.15.2.2 const int ErrorCode.AuthenticationTicketExpired = 0x7FF1

(32753) The Authentication ticket expired. Usually, this is refreshed behind the scenes. Connect (and authorize) again.

8.15.2.3 const int ErrorCode.CustomAuthenticationFailed = 0x7FFF - 12

(32755) Custom Authentication of the user failed due to setup reasons (see Cloud Dashboard) or the provided user data (like username or token). Check error message for details.

- 8.15.2.4 const int ErrorCode.ExternalHttpCallFailed = 32744
- (32744) for WebRpc requests. Indicates the the call to the external service failed.
- 8.15.2.5 const int ErrorCode.GameClosed = 0x7FFF 3
- (32764) Game is closed and can't be joined. Join another game.
- 8.15.2.6 const int ErrorCode.GameDoesNotExist = 0x7FFF 9
- (32758) Join can fail if the room (name) is not existing (anymore). This can happen when players leave while you join.
- 8.15.2.7 const int ErrorCode.GameFull = 0x7FFF 2
- (32765) Game is full. This rarely happens when some player joined the room before your join completed.
- 8.15.2.8 const int ErrorCode.GameIdAlreadyExists = 0x7FFF 1
- (32766) Gameld (name) already in use (can't create another). Change name.
- 8.15.2.9 const int ErrorCode.HttpLimitReached = 32745
- (32745) for SetProerties and Raisevent (if flag HttpForward is true) requests. Indicates the maximum allowd http requests per minute was reached.
- 8.15.2.10 const int ErrorCode.InternalServerError = -1
- (-1) Something went wrong in the server. Try to reproduce and contact Exit Games.
- 8.15.2.11 const int ErrorCode.InvalidAuthentication = 0x7FFF
- (32767) Authentication failed. Possible cause: Appld is unknown to Photon (in cloud service).
- 8.15.2.12 const int ErrorCode.InvalidEncryptionParameters = 32741
- (32741) Server will react with this error if invalid encryption parameters provided by token
- 8.15.2.13 const int ErrorCode.InvalidOperation = -2
- (-2) The operation you called could not be executed on the server.

Make sure you are connected to the server you expect.

This code is used in several cases: The arguments/parameters of the operation might be out of range, missing entirely or conflicting. The operation you called is not implemented on the server (application). Server-side plugins affect the available operations.

- 8.15.2.14 const int ErrorCode.InvalidOperationCode = -2
- (-2) The operation you called is not implemented on the server (application) you connect to. Make sure you run the fitting applications.

8.15.2.15 const int ErrorCode.InvalidRegion = 0x7FFF - 11

(32756) Authorization on the Photon Cloud failed because the app's subscription does not allow to use a particular region's server.

Some subscription plans for the Photon Cloud are region-bound. Servers of other regions can't be used then. Check your master server address and compare it with your Photon Cloud Dashboard's info. https://www.ephotonengine.com/dashboard

OpAuthorize is part of connection workflow but only on the Photon Cloud, this error can happen. Self-hosted Photon servers with a CCU limited license won't let a client connect at all.

8.15.2.16 const int ErrorCode.JoinFailedFoundActiveJoiner = 32746

(32746) for join requests. Indicates the list of ActiveActors already contains an actor with the requested ActorNr or UserId.

8.15.2.17 const int ErrorCode.JoinFailedFoundExcludedUserId = 32747

(32747) for join requests. Note: for future use - Indicates the requested UserId was found in the ExcludedList.

8.15.2.18 const int ErrorCode.JoinFailedFoundInactiveJoiner = 32749

(32749) for join requests. Indicates the list of InactiveActors already contains an actor with the requested ActorNr or UserId.

8.15.2.19 const int ErrorCode.JoinFailedPeerAlreadyJoined = 32750

(32750) for join requests. Indicates the current peer already called join and is joined to the room.

8.15.2.20 const int ErrorCode.JoinFailedWithRejoinerNotFound = 32748

(32748) for join requests. Indicates the list of Actors (active and inactive) did not contain an actor with the requested ActorNr or Userld.

8.15.2.21 const int ErrorCode.MaxCcuReached = 0x7FFF - 10

(32757) Authorization on the Photon Cloud failed becaus the concurrent users (CCU) limit of the app's subscription is reached.

Unless you have a plan with "CCU Burst", clients might fail the authentication step during connect. Affected client are unable to call operations. Please note that players who end a game and return to the master server will disconnect and re-connect, which means that they just played and are rejected in the next minute / re-connect. This is a temporary measure. Once the CCU is below the limit, players will be able to connect an play again.

OpAuthorize is part of connection workflow but only on the Photon Cloud, this error can happen. Self-hosted Photon servers with a CCU limited license won't let a client connect at all.

8.15.2.22 const int ErrorCode.NoRandomMatchFound = 0x7FFF - 7

(32760) Random matchmaking only succeeds if a room exists thats neither closed nor full. Repeat in a few seconds or create a new room.

- 8.15.2.23 const int ErrorCode.Ok = 0
- (0) is always "OK", anything else an error or specific situation.
- 8.15.2.24 const int ErrorCode.OperationNotAllowedInCurrentState = -3
- (-3) Operation can't be executed yet (e.g. OpJoin can't be called before being authenticated, RaiseEvent cant be used before getting into a room).

Before you call any operations on the Cloud servers, the automated client workflow must complete its authorization. In PUN, wait until State is: JoinedLobby (with AutoJoinLobby = true) or ConnectedToMaster (AutoJoinLobby = false)

- 8.15.2.25 const int ErrorCode.PluginMismatch = 0x7FFF 16
- (32751) CreateRoom/JoinRoom/Join operation fails if expected plugin does not correspond to loaded one.
- 8.15.2.26 const int ErrorCode.PluginReportedError = 0x7FFF 15
- (32752) A server-side plugin (or webhook) failed to execute and reported an error. Check the OperationResponse. ← DebugMessage.
- 8.15.2.27 const int ErrorCode.ServerFull = 0x7FFF 5
- (32762) Not in use currently.
- 8.15.2.28 const int ErrorCode.SlotError = 32742
- (32742) Server error during matchmaking with slot reservation. E.g. the reserved slots can not exceed MaxPlayers.
- 8.15.2.29 const int ErrorCode.UserBlocked = 0x7FFF 6
- (32761) Not in use currently.

8.16 EventCode Class Reference

Class for constants. These values are for events defined by Photon Loadbalancing.

Public Attributes

- const byte GameList = 230
 - (230) Initial list of RoomInfos (in lobby on Master)
- const byte GameListUpdate = 229
 - (229) Update of RoomInfos to be merged into "initial" list (in lobby on Master)
- const byte QueueState = 228
 - (228) Currently not used. State of queueing in case of server-full
- const byte Match = 227
 - (227) Currently not used. Event for matchmaking
- const byte AppStats = 226
 - (226) Event with stats about this application (players, rooms, etc)

- const byte LobbyStats = 224
 - (224) This event provides a list of lobbies with their player and game counts.
- const byte AzureNodeInfo = 210
 - (210) Internally used in case of hosting by Azure
- const byte Join = (byte)255
 - (255) Event Join: someone joined the game. The new actorNumber is provided as well as the properties of that actor (if set in OpJoin).
- const byte Leave = (byte)254
 - (254) Event Leave: The player who left the game can be identified by the actorNumber.
- const byte PropertiesChanged = (byte)253
 - (253) When you call OpSetProperties with the broadcast option "on", this event is fired. It contains the properties being set.
- const byte SetProperties = (byte)253
 - (253) When you call OpSetProperties with the broadcast option "on", this event is fired. It contains the properties being set.
- const byte ErrorInfo = 251
 - (252) When player left game unexpected and the room has a playerTtl != 0, this event is fired to let everyone know about the timeout.
- const byte CacheSliceChanged = 250
 - (250) Sent by Photon whent he event cache slice was changed. Done by OpRaiseEvent.
- const byte AuthEvent = 223
 - (223) Sent by Photon to update a token before it times out.

8.16.1 Detailed Description

Class for constants. These values are for events defined by Photon Loadbalancing.

They start at 255 and go DOWN. Your own in-game events can start at 0. Pun uses these constants internally.

- 8.16.2 Member Data Documentation
- 8.16.2.1 const byte EventCode.AppStats = 226
- (226) Event with stats about this application (players, rooms, etc)
- 8.16.2.2 const byte EventCode.AuthEvent = 223
- (223) Sent by Photon to update a token before it times out.
- 8.16.2.3 const byte EventCode.AzureNodeInfo = 210
- (210) Internally used in case of hosting by Azure
- 8.16.2.4 const byte EventCode.CacheSliceChanged = 250
- (250) Sent by Photon whent he event cache slice was changed. Done by OpRaiseEvent.

- 8.16.2.5 const byte EventCode.ErrorInfo = 251
- (252) When player left game unexpected and the room has a playerTtl != 0, this event is fired to let everyone know about the timeout.

Obsolete. Replaced by Leave. public const byte Disconnect = LiteEventCode.Disconnect;

(251) Sent by Photon Cloud when a plugin-call or webhook-call failed. Usually, the execution on the server continues, despite the issue. Contains: ParameterCode.Info.

See also

https://doc.photonengine.com/en-us/pun/current/gameplay/web-extensions/webhooks::options

- 8.16.2.6 const byte EventCode.GameList = 230
- (230) Initial list of RoomInfos (in lobby on Master)
- 8.16.2.7 const byte EventCode.GameListUpdate = 229
- (229) Update of RoomInfos to be merged into "initial" list (in lobby on Master)
- 8.16.2.8 const byte EventCode.Join = (byte)255
- (255) Event Join: someone joined the game. The new actorNumber is provided as well as the properties of that actor (if set in OpJoin).
- 8.16.2.9 const byte EventCode.Leave = (byte)254
- (254) Event Leave: The player who left the game can be identified by the actorNumber.
- 8.16.2.10 const byte EventCode.LobbyStats = 224
- (224) This event provides a list of lobbies with their player and game counts.
- 8.16.2.11 const byte EventCode.Match = 227
- (227) Currently not used. Event for matchmaking
- 8.16.2.12 const byte EventCode.PropertiesChanged = (byte)253
- (253) When you call OpSetProperties with the broadcast option "on", this event is fired. It contains the properties being set.
- 8.16.2.13 const byte EventCode.QueueState = 228
- (228) Currently not used. State of gueueing in case of server-full
- 8.16.2.14 const byte EventCode.SetProperties = (byte)253
- (253) When you call OpSetProperties with the broadcast option "on", this event is fired. It contains the properties being set.

8.17 Extensions Class Reference

This static class defines some useful extension methods for several existing classes (e.g. Vector3, float and others).

Static Public Member Functions

- static ParameterInfo[] GetCachedParemeters (this MethodInfo mo)
- static PhotonView[] GetPhotonViewsInChildren (this UnityEngine.GameObject go)
- static PhotonView GetPhotonView (this UnityEngine.GameObject go)
- static bool AlmostEquals (this Vector3 target, Vector3 second, float sqrMagnitudePrecision)

compares the squared magnitude of target - second to given float value

static bool AlmostEquals (this Vector2 target, Vector2 second, float sqrMagnitudePrecision)

compares the squared magnitude of target - second to given float value

• static bool AlmostEquals (this Quaternion target, Quaternion second, float maxAngle)

compares the angle between target and second to given float value

static bool AlmostEquals (this float target, float second, float floatDiff)

compares two floats and returns true of their difference is less than floatDiff

• static void Merge (this IDictionary target, IDictionary addHash)

Merges all keys from addHash into the target. Adds new keys and updates the values of existing keys in target.

static void MergeStringKeys (this IDictionary target, IDictionary addHash)

Merges keys of type string to target Hashtable.

• static string ToStringFull (this IDictionary origin)

Helper method for debugging of IDictionary content, inlcuding type-information. Using this is not performant.

static string ToStringFull (this object[] data)

Helper method for debugging of object[] content. Using this is not performant.

• static Hashtable StripToStringKeys (this IDictionary original)

This method copies all string-typed keys of the original into a new Hashtable.

· static void StripKeysWithNullValues (this IDictionary original)

This removes all key-value pairs that have a null-reference as value. Photon properties are removed by setting their value to null. Changes the original passed IDictionary!

• static bool Contains (this int[] target, int nr)

Checks if a particular integer value is in an int-array.

Static Public Attributes

static Dictionary< MethodInfo,
 ParameterInfo[]> ParametersOfMethods = new Dictionary<MethodInfo, ParameterInfo[]>()

8.17.1 Detailed Description

This static class defines some useful extension methods for several existing classes (e.g. Vector3, float and others).

8.17.2 Member Function Documentation

8.17.2.1 static bool Extensions.AlmostEquals (this Vector3 target, Vector3 second, float sqrMagnitudePrecision) [static]

compares the squared magnitude of target - second to given float value

8.17.2.2 static bool Extensions.AlmostEquals (this Vector2 target, Vector2 second, float sqrMagnitudePrecision) [static]

compares the squared magnitude of target - second to given float value

8.17.2.3 static bool Extensions.AlmostEquals (this Quaternion target, Quaternion second, float maxAngle) [static] compares the angle between target and second to given float value

8.17.2.4 static bool Extensions.AlmostEquals (this float target, float second, float floatDiff) [static] compares two floats and returns true of their difference is less than floatDiff

8.17.2.5 static bool Extensions.Contains (this int[] target, int nr) [static]

Checks if a particular integer value is in an int-array.

This might be useful to look up if a particular actorNumber is in the list of players of a room.

Parameters

target	The array of ints to check.
nr	The number to lookup in target.

Returns

True if nr was found in target.

8.17.2.6 static ParameterInfo [] Extensions.GetCachedParemeters (this MethodInfo *mo*) [static]

8.17.2.7 static PhotonView Extensions.GetPhotonView (this UnityEngine.GameObject go) [static]

8.17.2.8 static PhotonView [] Extensions.GetPhotonViewsInChildren (this UnityEngine.GameObject go) [static]

8.17.2.9 static void Extensions.Merge (this IDictionary target, IDictionary addHash) [static]

Merges all keys from addHash into the target. Adds new keys and updates the values of existing keys in target.

Parameters

target	The IDictionary to update.
addHash	The IDictionary containing data to merge into target.

8.17.2.10 static void Extensions.MergeStringKeys (this IDictionary target, IDictionary addHash) [static]

Merges keys of type string to target Hashtable.

Does not remove keys from target (so non-string keys CAN be in target if they were before).

Parameters

target	The target IDicitionary passed in plus all string-typed keys from the addHash.
largot	The target is offering passes in place an entire types region the assistant.

addHash A IDictionary that should be merged partly into target to update it.

8.17.2.11 static void Extensions.StripKeysWithNullValues (this IDictionary original) [static]

This removes all key-value pairs that have a null-reference as value. Photon properties are removed by setting their value to null. Changes the original passed IDictionary!

Parameters

original The IDictionary to strip of keys with null-values.

8.17.2.12 static Hashtable Extensions.StripToStringKeys (this IDictionary original) [static]

This method copies all string-typed keys of the original into a new Hashtable.

Does not recurse (!) into hashes that might be values in the root-hash. This does not modify the original.

Parameters

original	The original IDictonary to get string-typed keys from.

Returns

New Hashtable containing only string-typed keys of the original.

8.17.2.13 static string Extensions.ToStringFull (this IDictionary origin) [static]

Helper method for debugging of IDictionary content, inlcuding type-information. Using this is not performant.

Should only be used for debugging as necessary.

Parameters

origin	Some Dictionary or Hashtable.

Returns

String of the content of the IDictionary.

8.17.2.14 static string Extensions.ToStringFull (this object[] data) [static]

Helper method for debugging of object[] content. Using this is not performant.

Should only be used for debugging as necessary.

Parameters

data	Any object[].

Returns

A comma-separated string containing each value's ToString().

8.17.3 Member Data Documentation

8.17.3.1 Dictionary < MethodInfo, ParameterInfo[] > Extensions.ParametersOfMethods = new Dictionary < MethodInfo, ParameterInfo[] > () [static]

8.18 FindFriendsOptions Class Reference

Options for OpFindFriends can be combined to filter which rooms of friends are returned.

Public Attributes

• bool CreatedOnGs = false

Include a friend's room only if it is created and confirmed by the game server.

• bool Visible = false

Include a friend's room only if it is visible (using Room.IsVisible).

bool Open = false

Include a friend's room only if it is open (using Room.IsOpen).

8.18.1 Detailed Description

Options for OpFindFriends can be combined to filter which rooms of friends are returned.

8.18.2 Member Data Documentation

8.18.2.1 bool FindFriendsOptions.CreatedOnGs = false

Include a friend's room only if it is created and confirmed by the game server.

8.18.2.2 bool FindFriendsOptions.Open = false

Include a friend's room only if it is open (using Room.IsOpen).

8.18.2.3 bool FindFriendsOptions.Visible = false

Include a friend's room only if it is visible (using Room.IsVisible).

8.19 FriendInfo Class Reference

Used to store info about a friend's online state and in which room he/she is.

Public Member Functions

• override string ToString ()

Properties

```
string Name [get]
string UserId [get, set]
bool IsOnline [get, set]
string Room [get, set]
bool IsInRoom [get]
```

8.19.1 Detailed Description

Used to store info about a friend's online state and in which room he/she is.

8.19.2 Member Function Documentation

```
8.19.2.1 override string FriendInfo.ToString ( )
```

8.19.3 Property Documentation

```
8.19.3.1 bool FriendInfo.IsInRoom [get]
8.19.3.2 bool FriendInfo.IsOnline [get], [set]
8.19.3.3 string FriendInfo.Name [get]
8.19.3.4 string FriendInfo.Room [get], [set]
8.19.3.5 string FriendInfo.UserId [get], [set]
```

8.20 GameObjectExtensions Class Reference

Small number of extension methods that make it easier for PUN to work cross-Unity-versions.

Static Public Member Functions

static bool GetActive (this GameObject target)
 Unity-version-independent replacement for active GO property.

8.20.1 Detailed Description

Small number of extension methods that make it easier for PUN to work cross-Unity-versions.

8.20.2 Member Function Documentation

```
8.20.2.1 static bool GameObjectExtensions.GetActive ( this GameObject target ) [static]
```

Unity-version-independent replacement for active GO property.

Returns

Unity 3.5: active. Any newer Unity: activeInHierarchy.

8.21 GamePropertyKey Class Reference

Class for constants. These (byte) values are for "well known" room/game properties used in Photon Loadbalancing.

Public Attributes

• const byte MaxPlayers = 255

(255) Max number of players that "fit" into this room. 0 is for "unlimited".

const byte IsVisible = 254

(254) Makes this room listed or not in the lobby on master.

• const byte IsOpen = 253

(253) Allows more players to join a room (or not).

• const byte PlayerCount = 252

(252) Current count of players in the room. Used only in the lobby on master.

const byte Removed = 251

(251) True if the room is to be removed from room listing (used in update to room list in lobby on master)

• const byte PropsListedInLobby = 250

(250) A list of the room properties to pass to the RoomInfo list in a lobby. This is used in CreateRoom, which defines this list once per room.

const byte CleanupCacheOnLeave = 249

(249) Equivalent of Operation Join parameter CleanupCacheOnLeave.

const byte MasterClientId = (byte)248

(248) Code for MasterClientId, which is synced by server. When sent as op-parameter this is (byte)203. As room property this is (byte)248.

const byte ExpectedUsers = (byte)247

(247) Code for ExpectedUsers in a room. Matchmaking keeps a slot open for the players with these userIDs.

• const byte PlayerTtl = (byte)246

(246) Player Time To Live. How long any player can be inactive (due to disconnect or leave) before the user gets removed from the playerlist (freeing a slot).

const byte EmptyRoomTtl = (byte)245

(245) Room Time To Live. How long a room stays available (and in server-memory), after the last player becomes inactive. After this time, the room gets persisted or destroyed.

8.21.1 Detailed Description

Class for constants. These (byte) values are for "well known" room/game properties used in Photon Loadbalancing.

Pun uses these constants internally. "Custom properties" have to use a string-type as key. They can be assigned at will.

8.21.2 Member Data Documentation

8.21.2.1 const byte GamePropertyKey.CleanupCacheOnLeave = 249

(249) Equivalent of Operation Join parameter CleanupCacheOnLeave.

8.21.2.2 const byte GamePropertyKey.EmptyRoomTtl = (byte)245

(245) Room Time To Live. How long a room stays available (and in server-memory), after the last player becomes inactive. After this time, the room gets persisted or destroyed.

8.21.2.3 const byte GamePropertyKey.ExpectedUsers = (byte)247

(247) Code for ExpectedUsers in a room. Matchmaking keeps a slot open for the players with these userIDs.

8.21.2.4 const byte GamePropertyKey.IsOpen = 253

(253) Allows more players to join a room (or not).

- 8.21.2.5 const byte GamePropertyKey.IsVisible = 254
- (254) Makes this room listed or not in the lobby on master.
- 8.21.2.6 const byte GamePropertyKey.MasterClientId = (byte)248
- (248) Code for MasterClientId, which is synced by server. When sent as op-parameter this is (byte)203. As room property this is (byte)248.

Tightly related to ParameterCode.MasterClientId.

- 8.21.2.7 const byte GamePropertyKey.MaxPlayers = 255
- (255) Max number of players that "fit" into this room. 0 is for "unlimited".
- 8.21.2.8 const byte GamePropertyKey.PlayerCount = 252
- (252) Current count of players in the room. Used only in the lobby on master.
- 8.21.2.9 const byte GamePropertyKey.PlayerTtl = (byte)246
- (246) Player Time To Live. How long any player can be inactive (due to disconnect or leave) before the user gets removed from the playerlist (freeing a slot).
- 8.21.2.10 const byte GamePropertyKey.PropsListedInLobby = 250
- (250) A list of the room properties to pass to the RoomInfo list in a lobby. This is used in CreateRoom, which defines this list once per room.
- 8.21.2.11 const byte GamePropertyKey.Removed = 251
- (251) True if the room is to be removed from room listing (used in update to room list in lobby on master)

8.22 ExitGames.Client.GUI.GizmoTypeDrawer Class Reference

Static Public Member Functions

- static void Draw (Vector3 center, GizmoType type, Color color, float size)
- 8.22.1 Member Function Documentation
- 8.22.1.1 static void ExitGames.Client.GUI.GizmoTypeDrawer.Draw (Vector3 center, GizmoType type, Color color, float size) [static]

8.23 HelpURL Class Reference

Empty implementation of the upcoming HelpURL of Unity 5.1. This one is only for compatibility of attributes. Inherits Attribute.

Public Member Functions

HelpURL (string url)

8.23.1 Detailed Description

Empty implementation of the upcoming HelpURL of Unity 5.1. This one is only for compatibility of attributes.

http://feedback.unity3d.com/suggestions/override-component-documentation-slash-help-link

8.23.2 Constructor & Destructor Documentation

8.23.2.1 HelpURL.HelpURL (string url)

8.24 Photon Chat I Chat Client Listener Interface Reference

Callback interface for Chat client side. Contains callback methods to notify your app about updates. Must be provided to new ChatClient in constructor

Public Member Functions

• void DebugReturn (DebugLevel level, string message)

All debug output of the library will be reported through this method. Print it or put it in a buffer to use it on-screen.

void OnDisconnected ()

Disconnection happened.

· void OnConnected ()

Client is connected now.

void OnChatStateChange (ChatState state)

The ChatClient's state changed. Usually, OnConnected and OnDisconnected are the callbacks to react to.

void OnGetMessages (string channelName, string[] senders, object[] messages)

Notifies app that client got new messages from server Number of senders is equal to number of messages in 'messages'. Sender with number '0' corresponds to message with number '0', sender with number '1' corresponds to message with number '1' and so on

void OnPrivateMessage (string sender, object message, string channelName)

Notifies client about private message

void OnSubscribed (string[] channels, bool[] results)

Result of Subscribe operation. Returns subscription result for every requested channel name.

void OnUnsubscribed (string[] channels)

Result of Unsubscribe operation. Returns for channel name if the channel is now unsubscribed.

void OnStatusUpdate (string user, int status, bool gotMessage, object message)

New status of another user (you get updates for users set in your friends list).

void OnUserSubscribed (string channel, string user)

A user has subscribed to a public chat channel

void OnUserUnsubscribed (string channel, string user)

A user has unsubscribed from a public chat channel

8.24.1 Detailed Description

Callback interface for Chat client side. Contains callback methods to notify your app about updates. Must be provided to new ChatClient in constructor

8.24.2 Member Function Documentation

8.24.2.1 void Photon.Chat.IChatClientListener.DebugReturn (DebugLevel level, string message)

All debug output of the library will be reported through this method. Print it or put it in a buffer to use it on-screen.

Parameters

level	DebugLevel (severity) of the message.
message	Debug text. Print to System.Console or screen.

8.24.2.2 void Photon.Chat.IChatClientListener.OnChatStateChange (ChatState state)

The ChatClient's state changed. Usually, OnConnected and OnDisconnected are the callbacks to react to.

Parameters

state	The new state.

8.24.2.3 void Photon.Chat.IChatClientListener.OnConnected ()

Client is connected now.

Clients have to be connected before they can send their state, subscribe to channels and send any messages.

8.24.2.4 void Photon.Chat.IChatClientListener.OnDisconnected ()

Disconnection happened.

8.24.2.5 void Photon.Chat.IChatClientListener.OnGetMessages (string channelName, string[] senders, object[] messages)

Notifies app that client got new messages from server Number of senders is equal to number of messages in 'messages'. Sender with number '0' corresponds to message with number '0', sender with number '1' corresponds to message with number '1' and so on

Parameters

channelName	channel from where messages came
senders	list of users who sent messages
messages	list of messages it self

8.24.2.6 void Photon.Chat.IChatClientListener.OnPrivateMessage (string sender, object message, string channelName)

Notifies client about private message

Parameters

sender	user who sent this message
message	message it self
channelName	channelName for private messages (messages you sent yourself get added to a channel per
	target username)

8.24.2.7 void Photon.Chat.IChatClientListener.OnStatusUpdate (string user, int status, bool gotMessage, object message)

New status of another user (you get updates for users set in your friends list).

Parameters

user	Name of the user.
status	New status of that user.
gotMessage	True if the status contains a message you should cache locally. False: This status update
	does not include a message (keep any you have).
message	Message that user set.

8.24.2.8 void Photon.Chat.IChatClientListener.OnSubscribed (string[] channels, bool[] results)

Result of Subscribe operation. Returns subscription result for every requested channel name.

If multiple channels sent in Subscribe operation, OnSubscribed may be called several times, each call with part of sent array or with single channel in "channels" parameter. Calls order and order of channels in "channels" parameter may differ from order of channels in "channels" parameter of Subscribe operation.

Parameters

channels	Array of channel names.
results	Per channel result if subscribed.

8.24.2.9 void Photon.Chat.IChatClientListener.OnUnsubscribed (string[] channels)

Result of Unsubscribe operation. Returns for channel name if the channel is now unsubscribed.

If multiple channels sent in Unsubscribe operation, OnUnsubscribed may be called several times, each call with part of sent array or with single channel in "channels" parameter. Calls order and order of channels in "channels" parameter may differ from order of channels in "channels" parameter of Unsubscribe operation.

Parameters

channels	Array of channel names that are no longer subscribed.
onamiolo	Thray of onarmor harros that are no longer subscribed.

8.24.2.10 void Photon.Chat.IChatClientListener.OnUserSubscribed (string channel, string user)

A user has subscribed to a public chat channel

Parameters

channel	Name of the chat channel
user	UserId of the user who subscribed

8.24.2.11 void Photon.Chat.IChatClientListener.OnUserUnsubscribed (string channel, string user)

A user has unsubscribed from a public chat channel

Parameters

channel	Name of the chat channel
user	UserId of the user who unsubscribed

8.25 IPunCallbacks Interface Reference

This interface is used as definition of all callback methods of PUN, except OnPhotonSerializeView. Preferably, implement them individually.

Inherited by Photon.PunBehaviour.

Public Member Functions

void OnConnectedToPhoton ()

Called when the initial connection got established but before you can use the server. OnJoinedLobby() or On← ConnectedToMaster() are called when PUN is ready.

void OnLeftRoom ()

Called when the local user/client left a room.

void OnMasterClientSwitched (PhotonPlayer newMasterClient)

Called after switching to a new MasterClient when the current one leaves.

void OnPhotonCreateRoomFailed (object[] codeAndMsg)

Called when a CreateRoom() call failed. The parameter provides ErrorCode and message (as array).

void OnPhotonJoinRoomFailed (object[] codeAndMsg)

Called when a JoinRoom() call failed. The parameter provides ErrorCode and message (as array).

void OnCreatedRoom ()

Called when this client created a room and entered it. OnJoinedRoom() will be called as well.

void OnJoinedLobby ()

Called on entering a lobby on the Master Server. The actual room-list updates will call OnReceivedRoomListUpdate().

void OnLeftLobby ()

Called after leaving a lobby.

void OnFailedToConnectToPhoton (DisconnectCause cause)

Called if a connect call to the Photon server failed before the connection was established, followed by a call to On← DisconnectedFromPhoton().

void OnConnectionFail (DisconnectCause cause)

Called when something causes the connection to fail (after it was established), followed by a call to OnDisconnected FromPhoton().

• void OnDisconnectedFromPhoton ()

Called after disconnecting from the Photon server.

void OnPhotonInstantiate (PhotonMessageInfo info)

Called on all scripts on a GameObject (and children) that have been Instantiated using PhotonNetwork.Instantiate.

void OnReceivedRoomListUpdate ()

Called for any update of the room-listing while in a lobby (PhotonNetwork.insideLobby) on the Master Server or when a response is received for PhotonNetwork.GetCustomRoomList().

void OnJoinedRoom ()

Called when entering a room (by creating or joining it). Called on all clients (including the Master Client).

void OnPhotonPlayerConnected (PhotonPlayer newPlayer)

Called when a remote player entered the room. This PhotonPlayer is already added to the playerlist at this time.

• void OnPhotonPlayerDisconnected (PhotonPlayer otherPlayer)

Called when a remote player left the room. This PhotonPlayer is already removed from the playerlist at this time.

void OnPhotonRandomJoinFailed (object[] codeAndMsg)

Called when a JoinRandom() call failed. The parameter provides ErrorCode and message.

void OnConnectedToMaster ()

Called after the connection to the master is established and authenticated but only when PhotonNetwork.autoJoin Lobby is false.

void OnPhotonMaxCccuReached ()

Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting.

• void OnPhotonCustomRoomPropertiesChanged (Hashtable propertiesThatChanged)

Called when a room's custom properties changed. The propertiesThatChanged contains all that was set via Room. ← SetCustomProperties.

void OnPhotonPlayerPropertiesChanged (object[] playerAndUpdatedProps)

Called when custom player-properties are changed. Player and the changed properties are passed as object[].

void OnUpdatedFriendList ()

Called when the server sent the response to a FindFriends request and updated PhotonNetwork.Friends.

· void OnCustomAuthenticationFailed (string debugMessage)

Called when the custom authentication failed. Followed by disconnect!

void OnCustomAuthenticationResponse (Dictionary< string, object > data)

Called when your Custom Authentication service responds with additional data.

void OnWebRpcResponse (OperationResponse response)

Called by PUN when the response to a WebRPC is available. See PhotonNetwork. WebRPC.

void OnOwnershipRequest (object[] viewAndPlayer)

Called when another player requests ownership of a PhotonView from you (the current owner).

void OnLobbyStatisticsUpdate ()

Called when the Master Server sent an update for the Lobby Statistics, updating PhotonNetwork.LobbyStatistics.

void OnPhotonPlayerActivityChanged (PhotonPlayer otherPlayer)

Called when a remote Photon Player activity changed. This will be called ONLY if PlayerTtl is greater than 0.

void OnOwnershipTransfered (object[] viewAndPlayers)

Called when ownership of a PhotonView is transferred to another player.

8.25.1 Detailed Description

This interface is used as definition of all callback methods of PUN, except OnPhotonSerializeView. Preferably, implement them individually.

This interface is available for completeness, more than for actually implementing it in a game. You can implement each method individually in any MonoMehaviour, without implementing IPunCallbacks.

PUN calls all callbacks by name. Don't use implement callbacks with fully qualified name. Example: IPun← Callbacks.OnConnectedToPhoton won't get called by Unity's SendMessage().

PUN will call these methods on any script that implements them, analog to Unity's events and callbacks. The situation that triggers the call is described per method.

OnPhotonSerializeView is NOT called like these callbacks! It's usage frequency is much higher and it is implemented in: IPunObservable.

8.25.2 Member Function Documentation

8.25.2.1 void IPunCallbacks.OnConnectedToMaster ()

Called after the connection to the master is established and authenticated but only when PhotonNetwork.autoJoin← Lobby is false.

If you set PhotonNetwork.autoJoinLobby to true, OnJoinedLobby() will be called instead of this.

You can join rooms and create them even without being in a lobby. The default lobby is used in that case. The list of available rooms won't become available unless you join a lobby via PhotonNetwork.joinLobby.

Implemented in Photon.PunBehaviour.

8.25.2.2 void IPunCallbacks.OnConnectedToPhoton ()

Called when the initial connection got established but before you can use the server. OnJoinedLobby() or On← ConnectedToMaster() are called when PUN is ready.

This callback is only useful to detect if the server can be reached at all (technically). Most often, it's enough to implement OnFailedToConnectToPhoton() and OnDisconnectedFromPhoton().

OnJoinedLobby() or OnConnectedToMaster() are called when PUN is ready.

When this is called, the low level connection is established and PUN will send your Appld, the user, etc in the background. This is not called for transitions from the masterserver to game servers.

Implemented in Photon.PunBehaviour.

8.25.2.3 void IPunCallbacks.OnConnectionFail (DisconnectCause cause)

Called when something causes the connection to fail (after it was established), followed by a call to On← DisconnectedFromPhoton().

If the server could not be reached in the first place, OnFailedToConnectToPhoton is called instead. The reason for the error is provided as DisconnectCause.

Implemented in Photon.PunBehaviour.

8.25.2.4 void IPunCallbacks.OnCreatedRoom ()

Called when this client created a room and entered it. OnJoinedRoom() will be called as well.

This callback is only called on the client which created a room (see PhotonNetwork.CreateRoom).

As any client might close (or drop connection) anytime, there is a chance that the creator of a room does not execute OnCreatedRoom.

If you need specific room properties or a "start signal", it is safer to implement OnMasterClientSwitched() and to make the new MasterClient check the room's state.

Implemented in Photon.PunBehaviour.

8.25.2.5 void IPunCallbacks.OnCustomAuthenticationFailed (string debugMessage)

Called when the custom authentication failed. Followed by disconnect!

Custom Authentication can fail due to user-input, bad tokens/secrets. If authentication is successful, this method is not called. Implement OnJoinedLobby() or OnConnectedToMaster() (as usual).

During development of a game, it might also fail due to wrong configuration on the server side. In those cases, logging the debugMessage is very important.

Unless you setup a custom authentication service for your app (in the Dashboard), this won't be called!

Parameters

debugMessage	Contains a debug message why authentication failed.	This has to be fixed during develop-
	ment time.	

Implemented in Photon.PunBehaviour.

8.25.2.6 void IPunCallbacks.OnCustomAuthenticationResponse (Dictionary < string, object > data)

Called when your Custom Authentication service responds with additional data.

Custom Authentication services can include some custom data in their response. When present, that data is made available in this callback as Dictionary. While the keys of your data have to be strings, the values can be either string or a number (in Json). You need to make extra sure, that the value type is the one you expect. Numbers become (currently) int64.

Example: void OnCustomAuthenticationResponse(Dictionary<string, object> data) { ... }

https://doc.photonengine.com/en-us/pun/current/connection-and-authentication/custom-authentication

8.25.2.7 void IPunCallbacks.OnDisconnectedFromPhoton ()

Called after disconnecting from the Photon server.

In some cases, other callbacks are called before OnDisconnectedFromPhoton is called. Examples: OnConnection← Fail() and OnFailedToConnectToPhoton().

Implemented in Photon.PunBehaviour.

8.25.2.8 void IPunCallbacks.OnFailedToConnectToPhoton (DisconnectCause cause)

Called if a connect call to the Photon server failed before the connection was established, followed by a call to OnDisconnectedFromPhoton().

This is called when no connection could be established at all. It differs from OnConnectionFail, which is called when an existing connection fails.

Implemented in Photon.PunBehaviour.

```
8.25.2.9 void IPunCallbacks.OnJoinedLobby ( )
```

Called on entering a lobby on the Master Server. The actual room-list updates will call OnReceivedRoomList← Update().

Note: When PhotonNetwork.autoJoinLobby is false, OnConnectedToMaster() will be called and the room list won't become available.

While in the lobby, the roomlist is automatically updated in fixed intervals (which you can't modify). The room list gets available when OnReceivedRoomListUpdate() gets called after OnJoinedLobby().

Implemented in Photon.PunBehaviour.

```
8.25.2.10 void IPunCallbacks.OnJoinedRoom ( )
```

Called when entering a room (by creating or joining it). Called on all clients (including the Master Client).

This method is commonly used to instantiate player characters. If a match has to be started "actively", you can call an PunRPC triggered by a user's button-press or a timer.

When this is called, you can usually already access the existing players in the room via PhotonNetwork.playerList. Also, all custom properties should be already available as Room.customProperties. Check Room.playerCount to find out if enough players are in the room to start playing.

Implemented in Photon.PunBehaviour.

```
8.25.2.11 void IPunCallbacks.OnLeftLobby ( )
```

Called after leaving a lobby.

When you leave a lobby, CreateRoom and JoinRandomRoom automatically refer to the default lobby.

Implemented in Photon.PunBehaviour.

```
8.25.2.12 void IPunCallbacks.OnLeftRoom ( )
```

Called when the local user/client left a room.

When leaving a room, PUN brings you back to the Master Server. Before you can use lobbies and join or create rooms, OnJoinedLobby() or OnConnectedToMaster() will get called again.

8.25.2.13 void IPunCallbacks.OnLobbyStatisticsUpdate ()

Called when the Master Server sent an update for the Lobby Statistics, updating PhotonNetwork.LobbyStatistics.

This callback has two preconditions: EnableLobbyStatistics must be set to true, before this client connects. And the client has to be connected to the Master Server, which is providing the info about lobbies.

Implemented in Photon.PunBehaviour.

8.25.2.14 void IPunCallbacks.OnMasterClientSwitched (PhotonPlayer newMasterClient)

Called after switching to a new MasterClient when the current one leaves.

This is not called when this client enters a room. The former MasterClient is still in the player list when this method get called.

Implemented in Photon.PunBehaviour.

8.25.2.15 void IPunCallbacks.OnOwnershipRequest (object[] viewAndPlayer)

Called when another player requests ownership of a PhotonView from you (the current owner).

The parameter viewAndPlayer contains:

PhotonView view = viewAndPlayer[0] as PhotonView;

PhotonPlayer requestingPlayer = viewAndPlayer[1] as PhotonPlayer;

Parameters

viewAndPlayer The PhotonView is viewAndPlayer[0] and the requesting player is viewAndPlayer[1].

Implemented in Photon.PunBehaviour.

8.25.2.16 void IPunCallbacks.OnOwnershipTransfered (object[] viewAndPlayers)

Called when ownership of a PhotonView is transferred to another player.

The parameter viewAndPlayers contains:

PhotonView view = viewAndPlayers[0] as PhotonView;

PhotonPlayer newOwner = viewAndPlayers[1] as PhotonPlayer;

PhotonPlayer oldOwner = viewAndPlayers[2] as PhotonPlayer;

void OnOwnershipTransfered(object[] viewAndPlayers) {} //

Implemented in Photon.PunBehaviour.

8.25.2.17 void IPunCallbacks.OnPhotonCreateRoomFailed (object[] codeAndMsg)

Called when a CreateRoom() call failed. The parameter provides ErrorCode and message (as array).

Most likely because the room name is already in use (some other client was faster than you). PUN logs some info if the PhotonNetwork.logLevel is >= PhotonLogLevel.Informational.

Parameters

codeAndMsg[0] is short ErrorCode and codeAndMsg[1] is a string debug msg.

8.25.2.18 void IPunCallbacks.OnPhotonCustomRoomPropertiesChanged (Hashtable propertiesThatChanged)

Called when a room's custom properties changed. The propertiesThatChanged contains all that was set via Room.SetCustomProperties.

Since v1.25 this method has one parameter: Hashtable propertiesThatChanged.

Changing properties must be done by Room.SetCustomProperties, which causes this callback locally, too.

Parameters

propertiesThat← Changed

Implemented in Photon.PunBehaviour.

8.25.2.19 void IPunCallbacks.OnPhotonInstantiate (PhotonMessageInfo info)

Called on all scripts on a GameObject (and children) that have been Instantiated using PhotonNetwork.Instantiate.

PhotonMessageInfo parameter provides info about who created the object and when (based off Photon← Networking.time).

Implemented in Photon.PunBehaviour.

8.25.2.20 void IPunCallbacks.OnPhotonJoinRoomFailed (object[] codeAndMsg)

Called when a JoinRoom() call failed. The parameter provides ErrorCode and message (as array).

Most likely error is that the room does not exist or the room is full (some other client was faster than you). PUN logs some info if the PhotonNetwork.logLevel is >= PhotonLogLevel.Informational.

Parameters

codeAndMsg | codeAndMsg[0] is short ErrorCode and codeAndMsg[1] is string debug msg.

Implemented in Photon.PunBehaviour.

8.25.2.21 void IPunCallbacks.OnPhotonMaxCccuReached ()

Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting.

When this happens, the user might try again later. You can't create or join rooms in OnPhotonMaxCcuReached(), cause the client will be disconnecting. You can raise the CCU limits with a new license (when you host yourself) or extended subscription (when using the Photon Cloud). The Photon Cloud will mail you when the CCU limit was reached. This is also visible in the Dashboard (webpage).

Implemented in Photon.PunBehaviour.

8.25.2.22 void IPunCallbacks.OnPhotonPlayerActivityChanged (PhotonPlayer otherPlayer)

Called when a remote Photon Player activity changed. This will be called ONLY if PlayerTtl is greater than 0.

Use PhotonPlayer.IsInactive to check a player's current activity state.

Example: void OnPhotonPlayerActivityChanged(PhotonPlayer otherPlayer) {...}

This callback has precondition: PlayerTtl must be greater than 0.

8.25.2.23 void IPunCallbacks.OnPhotonPlayerConnected (PhotonPlayer newPlayer)

Called when a remote player entered the room. This PhotonPlayer is already added to the playerlist at this time.

If your game starts with a certain number of players, this callback can be useful to check the Room.playerCount and find out if you can start.

Implemented in Photon.PunBehaviour.

8.25.2.24 void IPunCallbacks.OnPhotonPlayerDisconnected (PhotonPlayer otherPlayer)

Called when a remote player left the room. This PhotonPlayer is already removed from the playerlist at this time.

When your client calls PhotonNetwork.leaveRoom, PUN will call this method on the remaining clients. When a remote client drops connection or gets closed, this callback gets executed. after a timeout of several seconds.

Implemented in Photon.PunBehaviour.

8.25.2.25 void IPunCallbacks.OnPhotonPlayerPropertiesChanged (object[] playerAndUpdatedProps)

Called when custom player-properties are changed. Player and the changed properties are passed as object[].

Since v1.25 this method has one parameter: object[] playerAndUpdatedProps, which contains two entries. [0] is the affected PhotonPlayer.

[1] is the Hashtable of properties that changed.

We are using a object[] due to limitations of Unity's GameObject.SendMessage (which has only one optional parameter).

Changing properties must be done by PhotonPlayer.SetCustomProperties, which causes this callback locally, too. Example:

```
void OnPhotonPlayerPropertiesChanged(object[] playerAndUpdatedProps) {
   PhotonPlayer player = playerAndUpdatedProps[0] as PhotonPlayer;
   Hashtable props = playerAndUpdatedProps[1] as Hashtable;
   //...
}
```

Parameters

playerAnd⇔	Contains PhotonPlayer and the properties that changed See remarks.
UpdatedProps	

Implemented in Photon.PunBehaviour.

8.25.2.26 void IPunCallbacks.OnPhotonRandomJoinFailed (object[] codeAndMsg)

Called when a JoinRandom() call failed. The parameter provides ErrorCode and message.

Most likely all rooms are full or no rooms are available.

When using multiple lobbies (via JoinLobby or TypedLobby), another lobby might have more/fitting rooms. PUN logs some info if the PhotonNetwork.logLevel is >= PhotonLogLevel.Informational.

Parameters

```
codeAndMsg[0] is short ErrorCode. codeAndMsg[1] is string debug msg.
```

```
8.25.2.27 void IPunCallbacks.OnReceivedRoomListUpdate ( )
```

Called for any update of the room-listing while in a lobby (PhotonNetwork.insideLobby) on the Master Server or when a response is received for PhotonNetwork.GetCustomRoomList().

PUN provides the list of rooms by PhotonNetwork.GetRoomList().

Each item is a RoomInfo which might include custom properties (provided you defined those as lobby-listed when creating a room).

Not all types of lobbies provide a listing of rooms to the client. Some are silent and specialized for server-side matchmaking.

Implemented in Photon.PunBehaviour.

```
8.25.2.28 void IPunCallbacks.OnUpdatedFriendList ( )
```

Called when the server sent the response to a FindFriends request and updated PhotonNetwork.Friends.

The friends list is available as PhotonNetwork.Friends, listing name, online state and the room a user is in (if any). Implemented in Photon.PunBehaviour.

```
8.25.2.29 void IPunCallbacks.OnWebRpcResponse (OperationResponse response)
```

Called by PUN when the response to a WebRPC is available. See PhotonNetwork.WebRPC.

Important: The response.ReturnCode is 0 if Photon was able to reach your web-service.

The content of the response is what your web-service sent. You can create a WebRpcResponse from it.

Example: WebRpcResponse webResponse = new WebRpcResponse(operationResponse);

Please note: Class OperationResponse is in a namespace which needs to be "used": using ExitGames.Client.Photon; // includes OperationResponse (and other classes)

The OperationResponse.ReturnCode by Photon is:

```
0 for "OK"
-3 for "Web-Service not configured" (see Dashboard / WebHooks)
-5 for "Web-Service does now have RPC path/name" (at least for Azure)
```

Implemented in Photon.PunBehaviour.

8.26 IPunObservable Interface Reference

Defines the OnPhotonSerializeView method to make it easy to implement correctly for observable scripts.

Inherited by PhotonAnimatorView, PhotonRigidbody2DView, PhotonRigidbodyView, and PhotonTransformView.

Public Member Functions

void OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)
 Called by PUN several times per second, so that your script can write and read synchronization data for the Photon
 View.

8.26.1 Detailed Description

Defines the OnPhotonSerializeView method to make it easy to implement correctly for observable scripts.

8.27 IPunPrefabPool Interface Reference

Defines all the methods that a Object Pool must implement, so that PUN can use it.

Public Member Functions

• GameObject Instantiate (string prefabld, Vector3 position, Quaternion rotation)

This is called when PUN wants to create a new instance of an entity prefab. Must return valid GameObject with PhotonView.

void Destroy (GameObject gameObject)

This is called when PUN wants to destroy the instance of an entity prefab.

8.27.1 Detailed Description

Defines all the methods that a Object Pool must implement, so that PUN can use it.

To use a Object Pool for instantiation, you can set PhotonNetwork.ObjectPool. That is used for all objects, as long as ObjectPool is not null. The pool has to return a valid non-null GameObject when PUN calls Instantiate. Also, the position and rotation must be applied.

Please note that pooled GameObjects don't get the usual Awake and Start calls. OnEnable will be called (by your pool) but the networking values are not updated yet when that happens. OnEnable will have outdated values for PhotonView (isMine, etc.). You might have to adjust scripts.

PUN will call OnPhotonInstantiate (see IPunCallbacks). This should be used to setup the re-used object with regards to networking values / ownership.

8.27.2 Member Function Documentation

8.27.2.1 void IPunPrefabPool.Destroy (GameObject gameObject)

This is called when PUN wants to destroy the instance of an entity prefab.

A pool needs some way to find out which type of GameObject got returned via Destroy(). It could be a tag or name or anything similar.

Parameters

gameObject The ins	tance to destroy.
--------------------	-------------------

8.27.2.2 GameObject IPunPrefabPool.Instantiate (string prefabld, Vector3 position, Quaternion rotation)

This is called when PUN wants to create a new instance of an entity prefab. Must return valid GameObject with PhotonView.

Parameters

prefabld	The id of this prefab.
position	The position we want the instance instantiated at.
rotation	The rotation we want the instance to take.

Returns

The newly instantiated object, or null if a prefab with *prefabld* was not found.

8.28 Photon. Mono Behaviour Class Reference

This class adds the property photonView, while logging a warning when your game still uses the networkView. Inherits MonoBehaviour.

Inherited by Photon.PunBehaviour, and PhotonView.

Properties

• PhotonView photonView [get]

A cached reference to a PhotonView on this GameObject.

new PhotonView networkView [get]

This property is only here to notify developers when they use the outdated value.

8.28.1 Detailed Description

This class adds the property photonView, while logging a warning when your game still uses the networkView.

8.28.2 Property Documentation

8.28.2.1 new PhotonView Photon.MonoBehaviour.networkView [get]

This property is only here to notify developers when they use the outdated value.

If Unity 5.x logs a compiler warning "Use the new keyword if hiding was intended" or "The new keyword is not required", you may suffer from an Editor issue. Try to modify networkView with a if-def condition:

#if UNITY_EDITOR new #endif public PhotonView networkView

8.28.2.2 PhotonView Photon.MonoBehaviour.photonView [get]

A cached reference to a PhotonView on this GameObject.

If you intend to work with a PhotonView in a script, it's usually easier to write this.photonView.

If you intend to remove the PhotonView component from the GameObject but keep this Photon.MonoBehaviour, avoid this reference or modify this code to use PhotonView.Get(obj) instead.

8.29 OperationCode Class Reference

Class for constants. Contains operation codes. Pun uses these constants internally.

Public Attributes

- const byte ExchangeKeysForEncryption = 250
- const byte Join = 255

(255) Code for OpJoin, to get into a room.

• const byte AuthenticateOnce = 231

(231) Authenticates this peer and connects to a virtual application

const byte Authenticate = 230

(230) Authenticates this peer and connects to a virtual application

• const byte JoinLobby = 229

```
(229) Joins lobby (on master)const byte LeaveLobby = 228
```

(228) Leaves lobby (on master)

• const byte CreateGame = 227

(227) Creates a game (or fails if name exists)

• const byte JoinGame = 226

(226) Join game (by name)

const byte JoinRandomGame = 225

(225) Joins random game (on master)

• const byte Leave = (byte)254

(254) Code for OpLeave, to get out of a room.

const byte RaiseEvent = (byte)253

(253) Raise event (in a room, for other actors/players)

• const byte SetProperties = (byte)252

(252) Set Properties (of room or actor/player)

• const byte GetProperties = (byte)251

(251) Get Properties

const byte ChangeGroups = (byte)248

(248) Operation code to change interest groups in Rooms (Lite application and extending ones).

• const byte FindFriends = 222

(222) Request the rooms and online status for a list of friends (by name, which should be unique).

• const byte GetLobbyStats = 221

(221) Request statistics about a specific list of lobbies (their user and game count).

• const byte GetRegions = 220

(220) Get list of regional servers from a NameServer.

• const byte WebRpc = 219

(219) WebRpc Operation.

• const byte ServerSettings = 218

(218) Operation to set some server settings. Used with different parameters on various servers.

const byte GetGameList = 217

(217) Get the game list matching a supplied sql filter (SqlListLobby only)

8.29.1 Detailed Description

Class for constants. Contains operation codes. Pun uses these constants internally.

8.29.2 Member Data Documentation

8.29.2.1 const byte OperationCode.Authenticate = 230

(230) Authenticates this peer and connects to a virtual application

8.29.2.2 const byte OperationCode.AuthenticateOnce = 231

(231) Authenticates this peer and connects to a virtual application

8.29.2.3 const byte OperationCode.ChangeGroups = (byte)248

(248) Operation code to change interest groups in Rooms (Lite application and extending ones).

- 8.29.2.4 const byte OperationCode.CreateGame = 227
- (227) Creates a game (or fails if name exists)
- 8.29.2.5 const byte OperationCode.ExchangeKeysForEncryption = 250
- 8.29.2.6 const byte OperationCode.FindFriends = 222
- (222) Request the rooms and online status for a list of friends (by name, which should be unique).
- 8.29.2.7 const byte OperationCode.GetGameList = 217
- (217) Get the game list matching a supplied sql filter (SqlListLobby only)
- 8.29.2.8 const byte OperationCode.GetLobbyStats = 221
- (221) Request statistics about a specific list of lobbies (their user and game count).
- 8.29.2.9 const byte OperationCode.GetProperties = (byte)251
- (251) Get Properties
- 8.29.2.10 const byte OperationCode.GetRegions = 220
- (220) Get list of regional servers from a NameServer.
- 8.29.2.11 const byte OperationCode.Join = 255
- (255) Code for OpJoin, to get into a room.
- 8.29.2.12 const byte OperationCode.JoinGame = 226
- (226) Join game (by name)
- 8.29.2.13 const byte OperationCode.JoinLobby = 229
- (229) Joins lobby (on master)
- 8.29.2.14 const byte OperationCode.JoinRandomGame = 225
- (225) Joins random game (on master)
- 8.29.2.15 const byte OperationCode.Leave = (byte)254
- (254) Code for OpLeave, to get out of a room.
- 8.29.2.16 const byte OperationCode.LeaveLobby = 228
- (228) Leaves lobby (on master)

```
8.29.2.17 const byte OperationCode.RaiseEvent = (byte)253(253) Raise event (in a room, for other actors/players)
```

8.29.2.18 const byte OperationCode.ServerSettings = 218

(218) Operation to set some server settings. Used with different parameters on various servers.

```
8.29.2.19 const byte OperationCode.SetProperties = (byte)252
```

(252) Set Properties (of room or actor/player)

8.29.2.20 const byte OperationCode.WebRpc = 219

(219) WebRpc Operation.

8.30 Photon.Chat.ParameterCode Class Reference

Class for constants. Codes for parameters of Operations and Events.

Public Attributes

• const byte ApplicationId = 224

(224) Your application's ID: a name on your own Photon or a GUID on the Photon Cloud

• const byte Secret = 221

(221) Internally used to establish encryption

• const byte AppVersion = 220

(220) Version of your application

const byte ClientAuthenticationType = 217

(217) This key's (byte) value defines the target custom authentication type/service the client connects with. Used in OpAuthenticate

const byte ClientAuthenticationParams = 216

(216) This key's (string) value provides parameters sent to the custom authentication type/service the client connects with. Used in OpAuthenticate

const byte ClientAuthenticationData = 214

(214) This key's (string or byte[]) value provides parameters sent to the custom authentication service setup in Photon Dashboard. Used in OpAuthenticate

• const byte Region = 210

(210) Used for region values in OpAuth and OpGetRegions.

• const byte Address = 230

(230) Address of a (game) server to use.

const byte UserId = 225

(225) User's ID

8.30.1 Detailed Description

Class for constants. Codes for parameters of Operations and Events.

- 8.30.2 Member Data Documentation
- 8.30.2.1 const byte Photon.Chat.ParameterCode.Address = 230
- (230) Address of a (game) server to use.
- 8.30.2.2 const byte Photon.Chat.ParameterCode.ApplicationId = 224
- (224) Your application's ID: a name on your own Photon or a GUID on the Photon Cloud
- 8.30.2.3 const byte Photon.Chat.ParameterCode.AppVersion = 220
- (220) Version of your application
- 8.30.2.4 const byte Photon.Chat.ParameterCode.ClientAuthenticationData = 214
- (214) This key's (string or byte[]) value provides parameters sent to the custom authentication service setup in Photon Dashboard. Used in OpAuthenticate
- 8.30.2.5 const byte Photon.Chat.ParameterCode.ClientAuthenticationParams = 216
- (216) This key's (string) value provides parameters sent to the custom authentication type/service the client connects with. Used in OpAuthenticate
- 8.30.2.6 const byte Photon.Chat.ParameterCode.ClientAuthenticationType = 217
- (217) This key's (byte) value defines the target custom authentication type/service the client connects with. Used in OpAuthenticate
- 8.30.2.7 const byte Photon.Chat.ParameterCode.Region = 210
- (210) Used for region values in OpAuth and OpGetRegions.
- 8.30.2.8 const byte Photon.Chat.ParameterCode.Secret = 221
- (221) Internally used to establish encryption
- 8.30.2.9 const byte Photon.Chat.ParameterCode.UserId = 225
- (225) User's ID

8.31 ParameterCode Class Reference

Class for constants. Codes for parameters of Operations and Events.

Public Attributes

• const byte SuppressRoomEvents = 237

(237) A bool parameter for creating games. If set to true, no room events are sent to the clients on join and leave. Default: false (and not sent).

const byte EmptyRoomTTL = 236

(236) Time To Live (TTL) for a room when the last player leaves. Keeps room in memory for case a player re-joins soon. In milliseconds.

const byte PlayerTTL = 235

(235) Time To Live (TTL) for an 'actor' in a room. If a client disconnects, this actor is inactive first and removed after this timeout. In milliseconds.

• const byte EventForward = 234

(234) Optional parameter of OpRaiseEvent and OpSetCustomProperties to forward the event/operation to a webservice.

• const byte IsComingBack = (byte)233

(233) Optional parameter of OpLeave in async games. If false, the player does abandons the game (forever). By default players become inactive and can re-join.

• const byte Islnactive = (byte)233

(233) Used in EvLeave to describe if a user is inactive (and might come back) or not. In rooms with PlayerTTL, becoming inactive is the default case.

• const byte CheckUserOnJoin = (byte)232

(232) Used when creating rooms to define if any userid can join the room only once.

• const byte ExpectedValues = (byte)231

(231) Code for "Check And Swap" (CAS) when changing properties.

• const byte Address = 230

(230) Address of a (game) server to use.

const byte PeerCount = 229

(229) Count of players in this application in a rooms (used in stats event)

const byte GameCount = 228

(228) Count of games in this application (used in stats event)

const byte MasterPeerCount = 227

(227) Count of players on the master server (in this app, looking for rooms)

const byte UserId = 225

(225) User's ID

const byte ApplicationId = 224

(224) Your application's ID: a name on your own Photon or a GUID on the Photon Cloud

• const byte Position = 223

(223) Not used currently (as "Position"). If you get queued before connect, this is your position

const byte MatchMakingType = 223

(223) Modifies the matchmaking algorithm used for OpJoinRandom. Allowed parameter values are defined in enum MatchmakingMode.

• const byte GameList = 222

(222) List of RoomInfos about open / listed rooms

• const byte Secret = 221

(221) Internally used to establish encryption

• const byte AppVersion = 220

(220) Version of your application

• const byte AzureNodeInfo = 210

(210) Internally used in case of hosting by Azure

const byte AzureLocalNodeld = 209

(209) Internally used in case of hosting by Azure

const byte AzureMasterNodeld = 208

(208) Internally used in case of hosting by Azure

• const byte RoomName = (byte)255

(255) Code for the gameld/roomName (a unique name per room). Used in OpJoin and similar.

const byte Broadcast = (byte)250

(250) Code for broadcast parameter of OpSetProperties method.

const byte ActorList = (byte)252

(252) Code for list of players in a room. Currently not used.

const byte ActorNr = (byte)254

(254) Code of the Actor of an operation. Used for property get and set.

const byte PlayerProperties = (byte)249

(249) Code for property set (Hashtable).

const byte CustomEventContent = (byte)245

(245) Code of data/custom content of an event. Used in OpRaiseEvent.

const byte Data = (byte)245

(245) Code of data of an event. Used in OpRaiseEvent.

• const byte Code = (byte)244

(244) Code used when sending some code-related parameter, like OpRaiseEvent's event-code.

• const byte GameProperties = (byte)248

(248) Code for property set (Hashtable).

const byte Properties = (byte)251

(251) Code for property-set (Hashtable). This key is used when sending only one set of properties. If either Actor← Properties or GameProperties are used (or both), check those keys.

const byte TargetActorNr = (byte)253

(253) Code of the target Actor of an operation. Used for property set. Is 0 for game

const byte ReceiverGroup = (byte)246

(246) Code to select the receivers of events (used in Lite, Operation RaiseEvent).

• const byte Cache = (byte)247

(247) Code for caching events while raising them.

• const byte CleanupCacheOnLeave = (byte)241

(241) Bool parameter of CreateRoom Operation. If true, server cleans up roomcache of leaving players (their cached events get removed).

const byte Group = 240

(240) Code for "group" operation-parameter (as used in Op RaiseEvent).

• const byte Remove = 239

(239) The "Remove" operation-parameter can be used to remove something from a list. E.g. remove groups from player's interest groups.

const byte PublishUserId = 239

(239) Used in Op Join to define if Userlds of the players are broadcast in the room. Useful for FindFriends and reserving slots for expected users.

const byte Add = 238

(238) The "Add" operation-parameter can be used to add something to some list or set. E.g. add groups to player's interest groups.

• const byte Info = 218

(218) Content for EventCode. ErrorInfo and internal debug operations.

const byte ClientAuthenticationType = 217

(217) This key's (byte) value defines the target custom authentication type/service the client connects with. Used in OpAuthenticate

const byte ClientAuthenticationParams = 216

(216) This key's (string) value provides parameters sent to the custom authentication type/service the client connects with. Used in OpAuthenticate

• const byte JoinMode = 215

(215) Makes the server create a room if it doesn't exist. OpJoin uses this to always enter a room, unless it exists and is full/closed.

• const byte ClientAuthenticationData = 214

(214) This key's (string or byte[]) value provides parameters sent to the custom authentication service setup in Photon Dashboard. Used in OpAuthenticate

- const byte MasterClientId = (byte)203
 - (203) Code for MasterClientId, which is synced by server. When sent as op-parameter this is code 203.
- const byte FindFriendsRequestList = (byte)1
 - (1) Used in Op FindFriends request. Value must be string[] of friends to look up.
- const byte FindFriendsOptions = 2
 - (2) Used in Op FindFriends request. An integer containing option-flags to filter the results.
- const byte FindFriendsResponseOnlineList = (byte)1
 - (1) Used in Op FindFriends response. Contains bool[] list of online states (false if not online).
- const byte FindFriendsResponseRoomldList = (byte)2
 - (2) Used in Op FindFriends response. Contains string[] of room names ("" where not known or no room joined).
- const byte LobbyName = (byte)213
 - (213) Used in matchmaking-related methods and when creating a room to name a lobby (to join or to attach a room to).
- const byte LobbyType = (byte)212
 - (212) Used in matchmaking-related methods and when creating a room to define the type of a lobby. Combined with the lobby name this identifies the lobby.
- const byte LobbyStats = (byte)211
 - (211) This (optional) parameter can be sent in Op Authenticate to turn on Lobby Stats (info about lobby names and their user- and game-counts). See: PhotonNetwork.Lobbies
- const byte Region = (byte)210
 - (210) Used for region values in OpAuth and OpGetRegions.
- const byte UriPath = 209
 - (209) Path of the WebRPC that got called. Also known as "WebRpc Name". Type: string.
- const byte WebRpcParameters = 208
 - (208) Parameters for a WebRPC as: Dictionary<string, object>. This will get serialized to JSon.
- const byte WebRpcReturnCode = 207
 - (207) ReturnCode for the WebRPC, as sent by the web service (not by Photon, which uses ErrorCode). Type: byte.
- const byte WebRpcReturnMessage = 206
 - (206) Message returned by WebRPC server. Analog to Photon's debug message. Type: string.
- const byte CacheSliceIndex = 205
 - (205) Used to define a "slice" for cached events. Slices can easily be removed from cache. Type: int.
- const byte Plugins = 204
 - (204) Informs the server of the expected plugin setup.
- const byte NickName = 202
 - (202) Used by the server in Operation Responses, when it sends the nickname of the client (the user's nickname).
- const byte PluginName = 201
 - (201) Informs user about name of plugin load to game
- const byte PluginVersion = 200
 - (200) Informs user about version of plugin load to game
- const byte ExpectedProtocol = 195
 - (195) Protocol which will be used by client to connect master/game servers. Used for nameserver.
- const byte CustomInitData = 194
 - (194) Set of custom parameters which are sent in auth request.
- const byte EncryptionMode = 193
 - (193) How are we going to encrypt data.
- const byte EncryptionData = 192
 - (192) Parameter of Authentication, which contains encryption keys (depends on AuthMode and EncryptionMode).
- const byte RoomOptionFlags = 191
 - (191) An int parameter summarizing several boolean room-options with bit-flags.

8.31.1 Detailed Description

Class for constants. Codes for parameters of Operations and Events.

Pun uses these constants internally.

8.31.2 Member Data Documentation

- 8.31.2.1 const byte ParameterCode.ActorList = (byte)252
- (252) Code for list of players in a room. Currently not used.
- 8.31.2.2 const byte ParameterCode.ActorNr = (byte)254
- (254) Code of the Actor of an operation. Used for property get and set.
- 8.31.2.3 const byte ParameterCode.Add = 238
- (238) The "Add" operation-parameter can be used to add something to some list or set. E.g. add groups to player's interest groups.
- 8.31.2.4 const byte ParameterCode.Address = 230
- (230) Address of a (game) server to use.
- 8.31.2.5 const byte ParameterCode.ApplicationId = 224
- (224) Your application's ID: a name on your own Photon or a GUID on the Photon Cloud
- 8.31.2.6 const byte ParameterCode.AppVersion = 220
- (220) Version of your application
- 8.31.2.7 const byte ParameterCode.AzureLocalNodeld = 209
- (209) Internally used in case of hosting by Azure
- 8.31.2.8 const byte ParameterCode.AzureMasterNodeld = 208
- (208) Internally used in case of hosting by Azure
- 8.31.2.9 const byte ParameterCode.AzureNodeInfo = 210
- (210) Internally used in case of hosting by Azure
- 8.31.2.10 const byte ParameterCode.Broadcast = (byte)250
- (250) Code for broadcast parameter of OpSetProperties method.

- 8.31.2.11 const byte ParameterCode.Cache = (byte)247
- (247) Code for caching events while raising them.
- 8.31.2.12 const byte ParameterCode.CacheSliceIndex = 205
- (205) Used to define a "slice" for cached events. Slices can easily be removed from cache. Type: int.
- 8.31.2.13 const byte ParameterCode.CheckUserOnJoin = (byte)232
- (232) Used when creating rooms to define if any userid can join the room only once.
- 8.31.2.14 const byte ParameterCode.CleanupCacheOnLeave = (byte)241
- (241) Bool parameter of CreateRoom Operation. If true, server cleans up roomcache of leaving players (their cached events get removed).
- 8.31.2.15 const byte ParameterCode.ClientAuthenticationData = 214
- (214) This key's (string or byte[]) value provides parameters sent to the custom authentication service setup in Photon Dashboard. Used in OpAuthenticate
- 8.31.2.16 const byte ParameterCode.ClientAuthenticationParams = 216
- (216) This key's (string) value provides parameters sent to the custom authentication type/service the client connects with. Used in OpAuthenticate
- 8.31.2.17 const byte ParameterCode.ClientAuthenticationType = 217
- (217) This key's (byte) value defines the target custom authentication type/service the client connects with. Used in OpAuthenticate
- 8.31.2.18 const byte ParameterCode.Code = (byte)244
- (244) Code used when sending some code-related parameter, like OpRaiseEvent's event-code.
- This is not the same as the Operation's code, which is no longer sent as part of the parameter Dictionary in Photon 3.
- 8.31.2.19 const byte ParameterCode.CustomEventContent = (byte)245
- (245) Code of data/custom content of an event. Used in OpRaiseEvent.
- 8.31.2.20 const byte ParameterCode.CustomInitData = 194
- (194) Set of custom parameters which are sent in auth request.
- 8.31.2.21 const byte ParameterCode.Data = (byte)245
- (245) Code of data of an event. Used in OpRaiseEvent.

- 8.31.2.22 const byte ParameterCode.EmptyRoomTTL = 236
- (236) Time To Live (TTL) for a room when the last player leaves. Keeps room in memory for case a player re-joins soon. In milliseconds.
- 8.31.2.23 const byte ParameterCode.EncryptionData = 192
- (192) Parameter of Authentication, which contains encryption keys (depends on AuthMode and EncryptionMode).
- 8.31.2.24 const byte ParameterCode.EncryptionMode = 193
- (193) How are we going to encrypt data.
- 8.31.2.25 const byte ParameterCode.EventForward = 234
- (234) Optional parameter of OpRaiseEvent and OpSetCustomProperties to forward the event/operation to a webservice.
- 8.31.2.26 const byte ParameterCode.ExpectedProtocol = 195
- (195) Protocol which will be used by client to connect master/game servers. Used for nameserver.
- 8.31.2.27 const byte ParameterCode.ExpectedValues = (byte)231
- (231) Code for "Check And Swap" (CAS) when changing properties.
- 8.31.2.28 const byte ParameterCode.FindFriendsOptions = 2
- (2) Used in Op FindFriends request. An integer containing option-flags to filter the results.
- 8.31.2.29 const byte ParameterCode.FindFriendsRequestList = (byte)1
- (1) Used in Op FindFriends request. Value must be string[] of friends to look up.
- 8.31.2.30 const byte ParameterCode.FindFriendsResponseOnlineList = (byte)1
- (1) Used in Op FindFriends response. Contains bool[] list of online states (false if not online).
- 8.31.2.31 const byte ParameterCode.FindFriendsResponseRoomldList = (byte)2
- (2) Used in Op FindFriends response. Contains string[] of room names ("" where not known or no room joined).
- 8.31.2.32 const byte ParameterCode.GameCount = 228
- (228) Count of games in this application (used in stats event)
- 8.31.2.33 const byte ParameterCode.GameList = 222
- (222) List of RoomInfos about open / listed rooms

- 8.31.2.34 const byte ParameterCode.GameProperties = (byte)248
- (248) Code for property set (Hashtable).
- 8.31.2.35 const byte ParameterCode.Group = 240
- (240) Code for "group" operation-parameter (as used in Op RaiseEvent).
- 8.31.2.36 const byte ParameterCode.Info = 218
- (218) Content for EventCode. ErrorInfo and internal debug operations.
- 8.31.2.37 const byte ParameterCode.IsComingBack = (byte)233
- (233) Optional parameter of OpLeave in async games. If false, the player does abandons the game (forever). By default players become inactive and can re-join.
- 8.31.2.38 const byte ParameterCode.lsInactive = (byte)233
- (233) Used in EvLeave to describe if a user is inactive (and might come back) or not. In rooms with PlayerTTL, becoming inactive is the default case.
- 8.31.2.39 const byte ParameterCode.JoinMode = 215
- (215) Makes the server create a room if it doesn't exist. OpJoin uses this to always enter a room, unless it exists and is full/closed.
- (215) The JoinMode enum defines which variant of joining a room will be executed: Join only if available, create if not exists or re-join.

Replaces CreatelfNotExists which was only a bool-value.

- 8.31.2.40 const byte ParameterCode.LobbyName = (byte)213
- (213) Used in matchmaking-related methods and when creating a room to name a lobby (to join or to attach a room to).
- 8.31.2.41 const byte ParameterCode.LobbyStats = (byte)211
- (211) This (optional) parameter can be sent in Op Authenticate to turn on Lobby Stats (info about lobby names and their user- and game-counts). See: PhotonNetwork.Lobbies
- 8.31.2.42 const byte ParameterCode.LobbyType = (byte)212
- (212) Used in matchmaking-related methods and when creating a room to define the type of a lobby. Combined with the lobby name this identifies the lobby.
- 8.31.2.43 const byte ParameterCode.MasterClientId = (byte)203
- (203) Code for MasterClientId, which is synced by server. When sent as op-parameter this is code 203.

Tightly related to GamePropertyKey.MasterClientId.

- 8.31.2.44 const byte ParameterCode.MasterPeerCount = 227
- (227) Count of players on the master server (in this app, looking for rooms)
- 8.31.2.45 const byte ParameterCode.MatchMakingType = 223
- (223) Modifies the matchmaking algorithm used for OpJoinRandom. Allowed parameter values are defined in enum MatchmakingMode.
- 8.31.2.46 const byte ParameterCode.NickName = 202
- (202) Used by the server in Operation Responses, when it sends the nickname of the client (the user's nickname).
- 8.31.2.47 const byte ParameterCode.PeerCount = 229
- (229) Count of players in this application in a rooms (used in stats event)
- 8.31.2.48 const byte ParameterCode.PlayerProperties = (byte)249
- (249) Code for property set (Hashtable).
- 8.31.2.49 const byte ParameterCode.PlayerTTL = 235
- (235) Time To Live (TTL) for an 'actor' in a room. If a client disconnects, this actor is inactive first and removed after this timeout. In milliseconds.
- 8.31.2.50 const byte ParameterCode.PluginName = 201
- (201) Informs user about name of plugin load to game
- 8.31.2.51 const byte ParameterCode.Plugins = 204
- (204) Informs the server of the expected plugin setup.

The operation will fail in case of a plugin mismatch returning error code PluginMismatch 32751(0x7FFF - 16). Setting string[]{} means the client expects no plugin to be setup. Note: for backwards compatibility null omits any check.

- 8.31.2.52 const byte ParameterCode.PluginVersion = 200
- (200) Informs user about version of plugin load to game
- 8.31.2.53 const byte ParameterCode.Position = 223
- (223) Not used currently (as "Position"). If you get queued before connect, this is your position
- 8.31.2.54 const byte ParameterCode.Properties = (byte)251
- (251) Code for property-set (Hashtable). This key is used when sending only one set of properties. If either Actor← Properties or GameProperties are used (or both), check those keys.

- 8.31.2.55 const byte ParameterCode.PublishUserId = 239
- (239) Used in Op Join to define if Userlds of the players are broadcast in the room. Useful for FindFriends and reserving slots for expected users.
- 8.31.2.56 const byte ParameterCode.ReceiverGroup = (byte)246
- (246) Code to select the receivers of events (used in Lite, Operation RaiseEvent).
- 8.31.2.57 const byte ParameterCode.Region = (byte)210
- (210) Used for region values in OpAuth and OpGetRegions.
- 8.31.2.58 const byte ParameterCode.Remove = 239
- (239) The "Remove" operation-parameter can be used to remove something from a list. E.g. remove groups from player's interest groups.
- 8.31.2.59 const byte ParameterCode.RoomName = (byte)255
- (255) Code for the gameId/roomName (a unique name per room). Used in OpJoin and similar.
- 8.31.2.60 const byte ParameterCode.RoomOptionFlags = 191
- (191) An int parameter summarizing several boolean room-options with bit-flags.
- 8.31.2.61 const byte ParameterCode.Secret = 221
- (221) Internally used to establish encryption
- 8.31.2.62 const byte ParameterCode.SuppressRoomEvents = 237
- (237) A bool parameter for creating games. If set to true, no room events are sent to the clients on join and leave. Default: false (and not sent).
- 8.31.2.63 const byte ParameterCode.TargetActorNr = (byte)253
- (253) Code of the target Actor of an operation. Used for property set. Is 0 for game
- 8.31.2.64 const byte ParameterCode.UriPath = 209
- (209) Path of the WebRPC that got called. Also known as "WebRpc Name". Type: string.
- 8.31.2.65 const byte ParameterCode.UserId = 225
- (225) User's ID
- 8.31.2.66 const byte ParameterCode.WebRpcParameters = 208
- (208) Parameters for a WebRPC as: Dictionary<string, object>. This will get serialized to JSon.

- 8.31.2.67 const byte ParameterCode.WebRpcReturnCode = 207
- (207) ReturnCode for the WebRPC, as sent by the web service (not by Photon, which uses ErrorCode). Type: byte.
- 8.31.2.68 const byte ParameterCode.WebRpcReturnMessage = 206
- (206) Message returned by WebRPC server. Analog to Photon's debug message. Type: string.

8.32 PhotonAnimatorView Class Reference

This class helps you to synchronize Mecanim animations Simply add the component to your GameObject and make sure that the PhotonAnimatorView is added to the list of observed components

Inherits MonoBehaviour, and IPunObservable.

Classes

- · class SynchronizedLayer
- · class SynchronizedParameter

Public Types

- enum ParameterType { ParameterType.Float = 1, ParameterType.Int = 3, ParameterType.Bool = 4, ParameterType.Trigger = 9 }
- enum SynchronizeType { SynchronizeType.Disabled = 0, SynchronizeType.Discrete = 1, SynchronizeType.

 Continuous = 2 }

Public Member Functions

void CacheDiscreteTriggers ()

Caches the discrete triggers values for keeping track of raised triggers, and will be reseted after the sync routine got performed

bool DoesLayerSynchronizeTypeExist (int layerIndex)

Check if a specific layer is configured to be synchronize

• bool DoesParameterSynchronizeTypeExist (string name)

Check if the specified parameter is configured to be synchronized

• List< SynchronizedLayer > GetSynchronizedLayers ()

Get a list of all synchronized layers

• List< SynchronizedParameter > GetSynchronizedParameters ()

Get a list of all synchronized parameters

SynchronizeType GetLayerSynchronizeType (int layerIndex)

Gets the type how the layer is synchronized

• SynchronizeType GetParameterSynchronizeType (string name)

Gets the type how the parameter is synchronized

void SetLayerSynchronized (int layerIndex, SynchronizeType synchronizeType)

Sets the how a layer should be synchronized

• void SetParameterSynchronized (string name, ParameterType type, SynchronizeType synchronizeType)

Sets the how a parameter should be synchronized

• void OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the Photon⊷ View.

8.32.1 Detailed Description

This class helps you to synchronize Mecanim animations Simply add the component to your GameObject and make sure that the PhotonAnimatorView is added to the list of observed components

When Using Trigger Parameters, make sure the component that sets the trigger is higher in the stack of Components on the GameObject than 'PhotonAnimatorView' Triggers are raised true during one frame only.

8.32.2 Member Enumeration Documentation

8.32.2.1 enum PhotonAnimatorView.ParameterType

Enumerator

Float

Int

Bool

Trigger

8.32.2.2 enum PhotonAnimatorView.SynchronizeType

Enumerator

Disabled

Discrete

Continuous

8.32.3 Member Function Documentation

8.32.3.1 void PhotonAnimatorView.CacheDiscreteTriggers ()

Caches the discrete triggers values for keeping track of raised triggers, and will be reseted after the sync routine got performed

8.32.3.2 bool PhotonAnimatorView.DoesLayerSynchronizeTypeExist (int layerIndex)

Check if a specific layer is configured to be synchronize

Parameters

laverIndex	Index of the laver.

Returns

True if the layer is synchronized

8.32.3.3 bool PhotonAnimatorView.DoesParameterSynchronizeTypeExist (string name)

Check if the specified parameter is configured to be synchronized

Parameters

name The name of the parameter.

Returns

True if the parameter is synchronized

8.32.3.4 SynchronizeType PhotonAnimatorView.GetLayerSynchronizeType (int layerIndex)

Gets the type how the layer is synchronized

Parameters

layerIndex Index of the layer.

Returns

Disabled/Discrete/Continuous

8.32.3.5 SynchronizeType PhotonAnimatorView.GetParameterSynchronizeType (string name)

Gets the type how the parameter is synchronized

Parameters

name The name of the parameter.

Returns

Disabled/Discrete/Continuous

 $8.32.3.6 \quad List < Synchronized Layer > Photon Animator View. Get Synchronized Layers (\quad)$

Get a list of all synchronized layers

Returns

List of SynchronizedLayer objects

 $8.32.3.7 \quad List < Synchronized Parameter > Photon Animator View. Get Synchronized Parameters (\quad)$

Get a list of all synchronized parameters

Returns

List of SynchronizedParameter objects

8.32.3.8 void PhotonAnimatorView.OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the Photon⊷ View.

This method will be called in scripts that are assigned as Observed component of a PhotonView. PhotonNetwork.sendRateOnSerialize affects how often this method is called.

PhotonNetwork.sendRate affects how often packages are sent by this client.

Implementing this method, you can customize which data a PhotonView regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView only gets called when it is assigned to a PhotonView* as Photon
✓ View.observed script.

To make use of this method, the PhotonStream is essential. It will be in "writing" mode" on the client that controls a PhotonView (PhotonStream.isWriting == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that OnPhotonSerializeView is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implements IPunObservable.

8.32.3.9 void PhotonAnimatorView.SetLayerSynchronized (int layerIndex, SynchronizeType synchronizeType)

Sets the how a layer should be synchronized

Parameters

layerIndex	Index of the layer.
synchronizeType	Disabled/Discrete/Continuous

8.32.3.10 void PhotonAnimatorView.SetParameterSynchronized (string *name*, ParameterType *type*, SynchronizeType *synchronizeType*)

Sets the how a parameter should be synchronized

Parameters

name	The name of the parameter.
type	The type of the parameter.
synchronizeType	Disabled/Discrete/Continuous

8.33 PhotonLagSimulationGui Class Reference

This MonoBehaviour is a basic GUI for the Photon client's network-simulation feature. It can modify lag (fixed delay), jitter (random lag) and packet loss.

Inherits MonoBehaviour.

Public Member Functions

- void Start ()
- void OnGUI ()

Public Attributes

• Rect WindowRect = new Rect(0, 100, 120, 100)

Positioning rect for window.

```
• int Windowld = 101
```

Unity GUI Window ID (must be unique or will cause issues).

• bool Visible = true

Shows or hides GUI (does not affect settings).

Properties

• PhotonPeer Peer [get, set]

The peer currently in use (to set the network simulation).

8.33.1 Detailed Description

This MonoBehaviour is a basic GUI for the Photon client's network-simulation feature. It can modify lag (fixed delay), jitter (random lag) and packet loss.

8.33.2 Member Function Documentation

```
8.33.2.1 void PhotonLagSimulationGui.OnGUI ( )
```

8.33.2.2 void PhotonLagSimulationGui.Start ()

8.33.3 Member Data Documentation

8.33.3.1 bool PhotonLagSimulationGui.Visible = true

Shows or hides GUI (does not affect settings).

8.33.3.2 int PhotonLagSimulationGui.Windowld = 101

Unity GUI Window ID (must be unique or will cause issues).

8.33.3.3 Rect PhotonLagSimulationGui.WindowRect = new Rect(0, 100, 120, 100)

Positioning rect for window.

8.33.4 Property Documentation

8.33.4.1 PhotonPeer PhotonLagSimulationGui.Peer [get], [set]

The peer currently in use (to set the network simulation).

8.34 PhotonMessageInfo Struct Reference

Container class for info about a particular message, RPC or update.

Public Member Functions

- PhotonMessageInfo (PhotonPlayer player, int timestamp, PhotonView view)
- override string ToString ()

Public Attributes

· readonly PhotonPlayer sender

The sender of a message / event. May be null.

· readonly PhotonView photonView

Properties

• double timestamp [get]

8.34.1 Detailed Description

Container class for info about a particular message, RPC or update.

8.34.2 Constructor & Destructor Documentation

- 8.34.2.1 PhotonMessageInfo.PhotonMessageInfo (PhotonPlayer player, int timestamp, PhotonView view)
- 8.34.3 Member Function Documentation
- 8.34.3.1 override string PhotonMessageInfo.ToString ()
- 8.34.4 Member Data Documentation
- 8.34.4.1 readonly PhotonView PhotonMessageInfo.photonView
- 8.34.4.2 readonly PhotonPlayer PhotonMessageInfo.sender

The sender of a message / event. May be null.

8.34.5 Property Documentation

8.34.5.1 double PhotonMessageInfo.timestamp [get]

8.35 PhotonNetwork Class Reference

The main class to use the PhotonNetwork plugin. This class is static.

Public Member Functions

• delegate void EventCallback (byte eventCode, object content, int senderId)

Defines the delegate usable in OnEventCall.

Static Public Member Functions

- static void SwitchToProtocol (ConnectionProtocol cp)
 - While offline, the network protocol can be switched (which affects the ports you can use to connect).
- static bool ConnectUsingSettings (string gameVersion)
 - Connect to Photon as configured in the editor (saved in PhotonServerSettings file).
- static bool ConnectToMaster (string masterServerAddress, int port, string appID, string gameVersion)

Connect to a Photon Master Server by address, port, appID and game(client) version.

static bool Reconnect ()

Can be used to reconnect to the master server after a disconnect.

• static bool ReconnectAndRejoin ()

When the client lost connection during gameplay, this method attempts to reconnect and rejoin the room.

static bool ConnectToBestCloudServer (string gameVersion)

Connect to the Photon Cloud region with the lowest ping (on platforms that support Unity's Ping).

static bool ConnectToRegion (CloudRegionCode region, string gameVersion)

Connects to the Photon Cloud region of choice.

static void OverrideBestCloudServer (CloudRegionCode region)

Overwrites the region that is used for ConnectToBestCloudServer(string gameVersion).

static void RefreshCloudServerRating ()

Pings all cloud servers again to find the one with best ping (currently).

static void NetworkStatisticsReset ()

Resets the traffic stats and re-enables them.

• static string NetworkStatisticsToString ()

Only available when NetworkStatisticsEnabled was used to gather some stats.

static void InitializeSecurity ()

Used for compatibility with Unity networking only. Encryption is automatically initialized while connecting.

• static void Disconnect ()

Makes this client disconnect from the photon server, a process that leaves any room and calls OnDisconnected← FromPhoton on completion.

static bool FindFriends (string[] friendsToFind, FindFriendsOptions options=null)

Requests the rooms and online status for a list of friends and saves the result in PhotonNetwork.Friends.

static bool CreateRoom (string roomName)

Creates a room with given name but fails if this room(name) is existing already. Creates random name for roomName null.

static bool CreateRoom (string roomName, RoomOptions roomOptions, TypedLobby)

Creates a room but fails if this room is existing already. Can only be called on Master Server.

static bool CreateRoom (string roomName, RoomOptions roomOptions, TypedLobby typedLobby, string[] expectedUsers)

Creates a room but fails if this room is existing already. Can only be called on Master Server.

static bool JoinRoom (string roomName)

Join room by roomname and on success calls OnJoinedRoom(). This is not affected by lobbies.

static bool JoinRoom (string roomName, string[] expectedUsers)

Join room by roomname and on success calls OnJoinedRoom(). This is not affected by lobbies.

static bool JoinOrCreateRoom (string roomName, RoomOptions roomOptions, TypedLobby)

Lets you either join a named room or create it on the fly - you don't have to know if someone created the room already.

 static bool JoinOrCreateRoom (string roomName, RoomOptions roomOptions, TypedLobby typedLobby, string[] expectedUsers)

Lets you either join a named room or create it on the fly - you don't have to know if someone created the room already.

static bool JoinRandomRoom ()

Joins any available room of the currently used lobby and fails if none is available.

static bool JoinRandomRoom (Hashtable expectedCustomRoomProperties, byte expectedMaxPlayers)

Attempts to join an open room with fitting, custom properties but fails if none is currently available.

 static bool JoinRandomRoom (Hashtable expectedCustomRoomProperties, byte expectedMaxPlayers, MatchmakingMode matchingType, TypedLobby typedLobby, string sqlLobbyFilter, string[] expected Users=null)

Attempts to join an open room with fitting, custom properties but fails if none is currently available.

• static bool ReJoinRoom (string roomName)

Can be used to return to a room after a disconnect and reconnect.

static bool JoinLobby ()

On MasterServer this joins the default lobby which list rooms currently in use.

static bool JoinLobby (TypedLobby)

On a Master Server you can join a lobby to get lists of available rooms.

static bool LeaveLobby ()

Leave a lobby to stop getting updates about available rooms.

static bool LeaveRoom (bool becomeInactive=true)

Leave the current room and return to the Master Server where you can join or create rooms (see remarks).

static bool GetCustomRoomList (TypedLobby typedLobby, string sqlLobbyFilter)

Fetches a custom list of games from the server, matching a SQL-like "where" clause, then triggers OnReceived← RoomListUpdate callback.

static RoomInfo[] GetRoomList ()

Gets currently cached rooms of the last rooms list sent by the server as RoomInfo array. This list is either available and updated automatically and periodically while in a lobby (check insideLobby) or received as a response to Photon⊷ Network.GetCustomRoomList().

static void SetPlayerCustomProperties (Hashtable customProperties)

Sets this (local) player's properties and synchronizes them to the other players (don't modify them directly).

static void RemovePlayerCustomProperties (string[] customPropertiesToDelete)

Locally removes Custom Properties of "this" player. Important: This does not synchronize the change! Useful when you switch rooms.

static bool RaiseEvent (byte eventCode, object eventContent, bool sendReliable, RaiseEventOptions options)

Sends fully customizable events in a room. Events consist of at least an EventCode (0..199) and can have content.

static int AllocateViewID ()

Allocates a viewID that's valid for the current/local player.

static int AllocateSceneViewID ()

Enables the Master Client to allocate a viewID that is valid for scene objects.

static void UnAllocateViewID (int viewID)

Unregister a viewID (of manually instantiated and destroyed networked objects).

• static GameObject Instantiate (string prefabName, Vector3 position, Quaternion rotation, byte group)

Instantiate a prefab over the network. This prefab needs to be located in the root of a "Resources" folder.

static GameObject Instantiate (string prefabName, Vector3 position, Quaternion rotation, byte group, object[] data)

Instantiate a prefab over the network. This prefab needs to be located in the root of a "Resources" folder.

• static GameObject InstantiateSceneObject (string prefabName, Vector3 position, Quaternion rotation, byte group, object[] data)

Instantiate a scene-owned prefab over the network. The PhotonViews will be controllable by the MasterClient. This prefab needs to be located in the root of a "Resources" folder.

static int GetPing ()

The current roundtrip time to the photon server.

static void FetchServerTimestamp ()

Refreshes the server timestamp (async operation, takes a roundtrip).

static void SendOutgoingCommands ()

Can be used to immediately send the RPCs and Instantiates just called, so they are on their way to the other players.

static bool CloseConnection (PhotonPlayer kickPlayer)

Request a client to disconnect (KICK). Only the master client can do this

static bool SetMasterClient (PhotonPlayer masterClientPlayer)

Asks the server to assign another player as Master Client of your current room.

static void Destroy (PhotonView targetView)

Network-Destroy the GameObject associated with the PhotonView, unless the PhotonView is static or not under this client's control.

static void Destroy (GameObject targetGo)

Network-Destroy the GameObject, unless it is static or not under this client's control.

static void DestroyPlayerObjects (PhotonPlayer targetPlayer)

Network-Destroy all GameObjects, PhotonViews and their RPCs of targetPlayer. Can only be called on local player (for "self") or Master Client (for anyone).

static void DestroyPlayerObjects (int targetPlayerId)

Network-Destroy all GameObjects, PhotonViews and their RPCs of this player (by ID). Can only be called on local player (for "self") or Master Client (for anyone).

static void DestroyAll ()

Network-Destroy all GameObjects, PhotonViews and their RPCs in the room. Removes anything buffered from the server. Can only be called by Master Client (for anyone).

static void RemoveRPCs (PhotonPlayer targetPlayer)

Remove all buffered RPCs from server that were sent by targetPlayer. Can only be called on local player (for "self") or Master Client (for anyone).

static void RemoveRPCs (PhotonView targetPhotonView)

Remove all buffered RPCs from server that were sent via targetPhotonView. The Master Client and the owner of the targetPhotonView may call this.

static void RemoveRPCsInGroup (int targetGroup)

Remove all buffered RPCs from server that were sent in the targetGroup, if this is the Master Client or if this controls the individual PhotonView.

static void CacheSendMonoMessageTargets (Type type)

Populates SendMonoMessageTargets with currently existing GameObjects that have a Component of type.

static HashSet< GameObject > FindGameObjectsWithComponent (Type type)

Finds the GameObjects with Components of a specific type (using FindObjectsOfType).

- static void SetReceivingEnabled (int group, bool enabled)
- static void SetInterestGroups (byte group, bool enabled)

Enable/disable receiving events from a given Interest Group.

- static void SetReceivingEnabled (int[] enableGroups, int[] disableGroups)
- static void SetInterestGroups (byte[] disableGroups, byte[] enableGroups)

Enable/disable receiving on given Interest Groups (applied to PhotonViews).

- static void SetSendingEnabled (int group, bool enabled)
- static void SetSendingEnabled (byte group, bool enabled)

Enable/disable sending on given group (applied to PhotonViews)

- static void SetSendingEnabled (int[] enableGroups, int[] disableGroups)
- static void SetSendingEnabled (byte[] disableGroups, byte[] enableGroups)

Enable/disable sending on given groups (applied to PhotonViews)

static void SetLevelPrefix (short prefix)

Sets level prefix for PhotonViews instantiated later on. Don't set it if you need only one!

static void LoadLevel (int levelNumber)

Wraps loading a level to pause the network message-queue. Optionally syncs the loaded level in a room.

• static AsyncOperation LoadLevelAsync (int levelNumber)

Wraps single asynchronous loading of a level to pause the network message-queue. Optionally syncs the loaded level in a room.

• static void LoadLevel (string levelName)

Wraps loading a level to pause the network message-queue. Optionally syncs the loaded level in a room.

static AsyncOperation LoadLevelAsync (string levelName)

Wraps single asynchronous loading of a level to pause the network message-queue. Optionally syncs the loaded level in a room.

static bool WebRpc (string name, object parameters)

This operation makes Photon call your custom web-service by name (path) with the given parameters.

• static bool CallEvent (byte eventCode, object content, int senderId)

Public Attributes

const string versionPUN = "1.99"

Version number of PUN. Also used in GameVersion to separate client version from each other.

Static Public Attributes

static readonly int MAX_VIEW_IDS = 1000

The maximum number of assigned PhotonViews per player (or scene). See the General Documentation topic "—Limitations" on how to raise this limitation.

Serialized server settings, written by the Setup Wizard for use in ConnectUsingSettings.

static bool InstantiateInRoomOnly = true

If true, Instantiate methods will check if you are in a room and fail if you are not.

static PhotonLogLevel logLevel = PhotonLogLevel.ErrorsOnly

Network log level. Controls how verbose PUN is.

• static float precisionForVectorSynchronization = 0.000099f

The minimum difference that a Vector2 or Vector3(e.g. a transforms rotation) needs to change before we send it via a PhotonView's OnSerialize/ObservingComponent.

• static float precisionForQuaternionSynchronization = 1.0f

The minimum angle that a rotation needs to change before we send it via a PhotonView's OnSerialize/Observing← Component.

static float precisionForFloatSynchronization = 0.01f

The minimum difference between floats before we send it via a PhotonView's OnSerialize/ObservingComponent.

• static bool UseRpcMonoBehaviourCache

While enabled, the MonoBehaviours on which we call RPCs are cached, avoiding costly GetComponents<Mono← Behaviour>() calls.

• static bool UsePrefabCache = true

While enabled (true), Instantiate uses PhotonNetwork.PrefabCache to keep game objects in memory (improving instantiation of the same prefab).

· static Dictionary< string,

GameObject > PrefabCache = new Dictionary < string, GameObject > ()

Keeps references to GameObjects for frequent instantiation (out of memory instead of loading the Resources).

static HashSet< GameObject > SendMonoMessageTargets

If not null, this is the (exclusive) list of GameObjects that get called by PUN SendMonoMessage().

static Type SendMonoMessageTargetType = typeof(MonoBehaviour)

Defines which classes can contain PUN Callback implementations.

static bool StartRpcsAsCoroutine = true

Can be used to skip starting RPCs as Coroutine, which can be a performance issue.

static int maxConnections

Only used in Unity Networking. In PUN, set the number of players in PhotonNetwork.CreateRoom.

static float BackgroundTimeout = 60.0f

Defines how many seconds PUN keeps the connection, after Unity's OnApplicationPause(true) call. Default: 60 seconds.

Properties

• static string gameVersion [get, set]

Version string for your this build. Can be used to separate incompatible clients. Sent during connect.

static string ServerAddress [get]

Currently used server address (no matter if master or game server).

static CloudRegionCode CloudRegion [get]

Currently used Cloud Region (if any). As long as the client is not on a Master Server or Game Server, the region is not yet defined.

• static bool connected [get]

False until you connected to Photon initially. True in offline mode, while connected to any server and even while switching servers.

• static bool connecting [get]

True when you called ConnectUsingSettings (or similar) until the low level connection to Photon gets established.

static bool connectedAndReady [get]

A refined version of connected which is true only if your connection to the server is ready to accept operations like join, leave, etc.

static ConnectionState connectionState [get]

Simplified connection state

• static ClientState connectionStateDetailed [get]

Detailed connection state (ignorant of PUN, so it can be "disconnected" while switching servers).

• static ServerConnection Server [get]

The server (type) this client is currently connected or connecting to.

• static Authentication Values Auth Values [get, set]

A user's authentication values used during connect.

• static Room room [get]

Get the room we're currently in. Null if we aren't in any room.

• static PhotonPlayer player [get]

The local PhotonPlayer. Always available and represents this player. CustomProperties can be set before entering a room and will be synced as well.

• static PhotonPlayer masterClient [get]

The Master Client of the current room or null (outside of rooms).

• static string playerName [get, set]

Set to synchronize the player's nickname with everyone in the room(s) you enter. This sets PhotonNetwork.player. WickName.

static PhotonPlayer[] playerList [get]

The list of players in the current room, including the local player.

static PhotonPlayer[] otherPlayers [get]

The list of players in the current room, excluding the local player.

• static List< FriendInfo > Friends [get, set]

Read-only list of friends, their online status and the room they are in. Null until initialized by a FindFriends call.

static int FriendsListAge [get]

Age of friend list info (in milliseconds). It's 0 until a friend list is fetched.

• static IPunPrefabPool PrefabPool [get, set]

An Object Pool can be used to keep and reuse instantiated object instances. It replaced Unity's default Instantiate and Destroy methods.

• static bool offlineMode [get, set]

Offline mode can be set to re-use your multiplayer code in singleplayer game modes. When this is on Photon Network will not create any connections and there is near to no overhead. Mostly usefull for reusing RPC's and PhotonNetwork.Instantiate

• static bool automaticallySyncScene [get, set]

Defines if all clients in a room should load the same level as the Master Client (if that used PhotonNetwork.LoadLevel).

• static bool autoCleanUpPlayerObjects [get, set]

This setting defines per room, if network-instantiated GameObjects (with PhotonView) get cleaned up when the creator of it leaves.

static bool autoJoinLobby [get, set]

Set in PhotonServerSettings asset. Defines if the PhotonNetwork should join the "lobby" when connected to the Master server.

• static bool EnableLobbyStatistics [get, set]

Set in PhotonServerSettings asset. Enable to get a list of active lobbies from the Master Server.

static List
 TypedLobbyInfo > LobbyStatistics [get, set]

If turned on, the Master Server will provide information about active lobbies for this application.

• static bool insideLobby [get]

True while this client is in a lobby.

static TypedLobby lobby [get, set]

The lobby that will be used when PUN joins a lobby or creates a game.

• static int sendRate [get, set]

Defines how many times per second PhotonNetwork should send a package. If you change this, do not forget to also change 'sendRateOnSerialize'.

• static int sendRateOnSerialize [get, set]

Defines how many times per second OnPhotonSerialize should be called on PhotonViews.

static bool isMessageQueueRunning [get, set]

Can be used to pause dispatching of incoming evtents (RPCs, Instantiates and anything else incoming).

• static double time [get]

Photon network time, synched with the server.

static int ServerTimestamp [get]

The current server's millisecond timestamp.

• static bool isMasterClient [get]

Are we the master client?

• static bool inRoom [get]

Is true while being in a room (connectionStateDetailed == ClientState.Joined).

• static bool isNonMasterClientInRoom [get]

True if we are in a room (client) and NOT the room's masterclient

• static int countOfPlayersOnMaster [get]

The count of players currently looking for a room (available on MasterServer in 5sec intervals).

• static int countOfPlayersInRooms [get]

Count of users currently playing your app in some room (sent every 5sec by Master Server). Use PhotonNetwork.—playerList.Length or PhotonNetwork.room.PlayerCount to get the count of players in the room you're in!

static int countOfPlayers [get]

The count of players currently using this application (available on MasterServer in 5sec intervals).

• static int countOfRooms [get]

The count of rooms currently in use (available on MasterServer in 5sec intervals).

• static bool NetworkStatisticsEnabled [get, set]

Enables or disables the collection of statistics about this client's traffic.

static int ResentReliableCommands [get]

Count of commands that got repeated (due to local repeat-timing before an ACK was received).

static bool CrcCheckEnabled [get, set]

Crc checks can be useful to detect and avoid issues with broken datagrams. Can be enabled while not connected.

static int PacketLossByCrcCheck [get]

If CrcCheckEnabled, this counts the incoming packages that don't have a valid CRC checksum and got rejected.

static int MaxResendsBeforeDisconnect [get, set]

Defines the number of times a reliable message can be resent before not getting an ACK for it will trigger a disconnect. Default: 5.

• static int QuickResends [get, set]

In case of network loss, reliable messages can be repeated quickly up to 3 times.

• static bool UseAlternativeUdpPorts [get, set]

Switch to alternative ports for a UDP connection to the Public Cloud.

Events

static EventCallback OnEventCall

Register your RaiseEvent handling methods here by using "+=".

8.35.1 Detailed Description

The main class to use the PhotonNetwork plugin. This class is static.

8.35.2 Member Function Documentation

```
8.35.2.1 static int PhotonNetwork.AllocateSceneViewID() [static]
```

Enables the Master Client to allocate a viewID that is valid for scene objects.

Returns

A viewID that can be used for a new PhotonView or -1 in case of an error.

```
8.35.2.2 static int PhotonNetwork.AllocateViewID() [static]
```

Allocates a viewID that's valid for the current/local player.

Returns

A viewID that can be used for a new PhotonView.

```
8.35.2.3 static void PhotonNetwork.CacheSendMonoMessageTargets ( Type type ) [static]
```

Populates SendMonoMessageTargets with currently existing GameObjects that have a Component of type.

Parameters

type	If null, this will use SendMonoMessageTargets as component-type (MonoBehaviour by de-
	fault).

```
8.35.2.4 static bool PhotonNetwork.CallEvent (byte eventCode, object content, int senderId ) [static]
```

8.35.2.5 static bool PhotonNetwork.CloseConnection (PhotonPlayer kickPlayer) [static]

Request a client to disconnect (KICK). Only the master client can do this

Only the target player gets this event. That player will disconnect automatically, which is what the others will notice, too.

Parameters

```
kickPlayer The PhotonPlayer to kick.
```

8.35.2.6 static bool PhotonNetwork.ConnectToBestCloudServer (string gameVersion) [static]

Connect to the Photon Cloud region with the lowest ping (on platforms that support Unity's Ping).

Will save the result of pinging all cloud servers in PlayerPrefs. Calling this the first time can take +-2 seconds. The ping result can be overridden via PhotonNetwork.OverrideBestCloudServer(..) This call can take up to 2 seconds if it is the first time you are using this, all cloud servers will be pinged to check for the best region.

The PUN Setup Wizard stores your appID in a settings file and applies a server address/port. To connect to the Photon Cloud, a valid AppId must be in the settings file (shown in the Photon Cloud Dashboard). https://www.photonengine.com/dashboard

Connecting to the Photon Cloud might fail due to:

- Invalid Appld (calls: OnFailedToConnectToPhoton(). check exact Appld value)
- Network issues (calls: OnFailedToConnectToPhoton())
- Invalid region (calls: OnConnectionFail() with DisconnectCause.InvalidRegion)
- Subscription CCU limit reached (calls: OnConnectionFail() with DisconnectCause.MaxCcuReached. also calls: OnPhotonMaxCccuReached())

Parameters

gameVersion	This client's version number. Users are separated from each other by gameversion (which
	allows you to make breaking changes).

Returns

If this client is going to connect to cloud server based on ping. Even if true, this does not guarantee a connection but the attempt is being made.

8.35.2.7 static bool PhotonNetwork.ConnectToMaster (string masterServerAddress, int port, string applD, string gameVersion) [static]

Connect to a Photon Master Server by address, port, appID and game(client) version.

To connect to the Photon Cloud, a valid Appld must be in the settings file (shown in the Photon Cloud Dashboard). https://www.photonengine.com/dashboard

Connecting to the Photon Cloud might fail due to:

- Invalid Appld (calls: OnFailedToConnectToPhoton(). check exact Appld value)
- Network issues (calls: OnFailedToConnectToPhoton())
- Invalid region (calls: OnConnectionFail() with DisconnectCause.InvalidRegion)
- Subscription CCU limit reached (calls: OnConnectionFail() with DisconnectCause.MaxCcuReached. also calls: OnPhotonMaxCccuReached())

Parameters

masterServer⊷	The server's address (either your own or Photon Cloud address).
Address	
port	The server's port to connect to.
appID	Your application ID (Photon Cloud provides you with a GUID for your game).
gameVersion	This client's version number. Users are separated by gameversion (which allows you to make
	breaking changes).

8.35.2.8 static bool PhotonNetwork.ConnectToRegion (CloudRegionCode region, string gameVersion) [static]

Connects to the **Photon** Cloud region of choice.

8.35.2.9 static bool PhotonNetwork.ConnectUsingSettings (string gameVersion) [static]

Connect to Photon as configured in the editor (saved in PhotonServerSettings file).

This method will disable offlineMode (which won't destroy any instantiated GOs) and it will set isMessageQueue← Running to true.

Your server configuration is created by the PUN Wizard and contains the Appld and region for Photon Cloud games and the server address if you host Photon yourself. These settings usually don't change often.

To ignore the config file and connect anywhere call: PhotonNetwork.ConnectToMaster.

To connect to the Photon Cloud, a valid Appld must be in the settings file (shown in the Photon Cloud Dashboard). https://www.photonengine.com/dashboard

Connecting to the **Photon** Cloud might fail due to:

- Invalid Appld (calls: OnFailedToConnectToPhoton(). check exact Appld value)
- Network issues (calls: OnFailedToConnectToPhoton())
- Invalid region (calls: OnConnectionFail() with DisconnectCause.InvalidRegion)
- Subscription CCU limit reached (calls: OnConnectionFail() with DisconnectCause.MaxCcuReached. also calls: OnPhotonMaxCccuReached())

Parameters

gameVersion	This client's version number. Users are separated from each other by gameversion (which
	allows you to make breaking changes).

8.35.2.10 static bool PhotonNetwork.CreateRoom (string roomName) [static]

Creates a room with given name but fails if this room(name) is existing already. Creates random name for room

Name null

If you don't want to create a unique room-name, pass null or "" as name and the server will assign a roomName (a GUID as string).

The created room is automatically placed in the currently used lobby (if any) or the default-lobby if you didn't explicitly join one.

Call this only on the master server. Internally, the master will respond with a server-address (and roomName, if needed). Both are used internally to switch to the assigned game server and roomName.

PhotonNetwork.autoCleanUpPlayerObjects will become this room's AutoCleanUp property and that's used by all clients that join this room.

Parameters

_		
	roomName	Unique name of the room to create.

Returns

If the operation got queued and will be sent.

8.35.2.11 static bool PhotonNetwork.CreateRoom (string *roomName*, RoomOptions *roomOptions*, TypedLobby typedLobby) [static]

Creates a room but fails if this room is existing already. Can only be called on Master Server.

When successful, this calls the callbacks OnCreatedRoom and OnJoinedRoom (the latter, cause you join as first player). If the room can't be created (because it exists already), OnPhotonCreateRoomFailed gets called.

If you don't want to create a unique room-name, pass null or "" as name and the server will assign a roomName (a GUID as string).

Rooms can be created in any number of lobbies. Those don't have to exist before you create a room in them (they get auto-created on demand). Lobbies can be useful to split room lists on the server-side already. That can help keep the room lists short and manageable. If you set a typedLobby parameter, the room will be created in that lobby (no matter if you are active in any). If you don't set a typedLobby, the room is automatically placed in the currently active lobby (if any) or the default-lobby.

Call this only on the master server. Internally, the master will respond with a server-address (and roomName, if needed). Both are used internally to switch to the assigned game server and roomName.

PhotonNetwork.autoCleanUpPlayerObjects will become this room's autoCleanUp property and that's used by all clients that join this room.

Parameters

roomName	Unique name of the room to create. Pass null or "" to make the server generate a name.
roomOptions	Common options for the room like MaxPlayers, initial custom room properties and similar.
	See RoomOptions type
typedLobby	If null, the room is automatically created in the currently used lobby (which is "default" when
	you didn't join one explicitly).

Returns

If the operation got queued and will be sent.

8.35.2.12 static bool PhotonNetwork.CreateRoom (string roomName, RoomOptions roomOptions, TypedLobby typedLobby, string[] expectedUsers) [static]

Creates a room but fails if this room is existing already. Can only be called on Master Server.

When successful, this calls the callbacks OnCreatedRoom and OnJoinedRoom (the latter, cause you join as first player). If the room can't be created (because it exists already), OnPhotonCreateRoomFailed gets called.

If you don't want to create a unique room-name, pass null or "" as name and the server will assign a roomName (a GUID as string).

Rooms can be created in any number of lobbies. Those don't have to exist before you create a room in them (they get auto-created on demand). Lobbies can be useful to split room lists on the server-side already. That can help keep the room lists short and manageable. If you set a typedLobby parameter, the room will be created in that lobby (no matter if you are active in any). If you don't set a typedLobby, the room is automatically placed in the currently active lobby (if any) or the default-lobby.

Call this only on the master server. Internally, the master will respond with a server-address (and roomName, if needed). Both are used internally to switch to the assigned game server and roomName.

PhotonNetwork.autoCleanUpPlayerObjects will become this room's autoCleanUp property and that's used by all clients that join this room.

You can define an array of expectedUsers, to block player slots in the room for these users. The corresponding feature in Photon is called "Slot Reservation" and can be found in the doc pages.

Parameters

roomName	Unique name of the room to create. Pass null or "" to make the server generate a name.
roomOptions	Common options for the room like MaxPlayers, initial custom room properties and similar.
	See RoomOptions type
typedLobby	If null, the room is automatically created in the currently used lobby (which is "default" when
	you didn't join one explicitly).
expectedUsers	Optional list of users (by Userld) who are expected to join this game and who you want to
	block a slot for.

Returns

If the operation got queued and will be sent.

8.35.2.13 static void PhotonNetwork.Destroy (PhotonView targetView) [static]

Network-Destroy the GameObject associated with the PhotonView, unless the PhotonView is static or not under this client's control.

Destroying a networked GameObject while in a Room includes:

- · Removal of the Instantiate call from the server's room buffer.
- · Removing RPCs buffered for PhotonViews that got created indirectly with the PhotonNetwork.Instantiate call.
- Sending a message to other clients to remove the GameObject also (affected by network lag).

Usually, when you leave a room, the GOs get destroyed automatically. If you have to destroy a GO while not in a room, the Destroy is only done locally.

Destroying networked objects works only if they got created with PhotonNetwork.Instantiate(). Objects loaded with a scene are ignored, no matter if they have PhotonView components.

The GameObject must be under this client's control:

- · Instantiated and owned by this client.
- · Instantiated objects of players who left the room are controlled by the Master Client.
- Scene-owned game objects are controlled by the Master Client.
- GameObject can be destroyed while client is not in a room.

Returns

Nothing. Check error debug log for any issues.

8.35.2.14 static void PhotonNetwork.Destroy (GameObject targetGo) [static]

Network-Destroy the GameObject, unless it is static or not under this client's control.

Destroying a networked GameObject includes:

- · Removal of the Instantiate call from the server's room buffer.
- Removing RPCs buffered for PhotonViews that got created indirectly with the PhotonNetwork.Instantiate call.
- Sending a message to other clients to remove the GameObject also (affected by network lag).

Usually, when you leave a room, the GOs get destroyed automatically. If you have to destroy a GO while not in a room, the Destroy is only done locally.

Destroying networked objects works only if they got created with PhotonNetwork.Instantiate(). Objects loaded with a scene are ignored, no matter if they have PhotonView components.

The GameObject must be under this client's control:

- · Instantiated and owned by this client.
- Instantiated objects of players who left the room are controlled by the Master Client.
- · Scene-owned game objects are controlled by the Master Client.
- GameObject can be destroyed while client is not in a room.

Returns

Nothing. Check error debug log for any issues.

```
8.35.2.15 static void PhotonNetwork.DestroyAll() [static]
```

Network-Destroy all GameObjects, PhotonViews and their RPCs in the room. Removes anything buffered from the server. Can only be called by Master Client (for anyone).

Can only be called by Master Client (for anyone). Unlike the Destroy methods, this will remove anything from the server's room buffer. If your game buffers anything beyond Instantiate and RPC calls, that will be cleaned as well from server.

Destroying all includes:

- · Remove anything from the server's room buffer (Instantiate, RPCs, anything buffered).
- · Sending a message to other clients to destroy everything locally, too (affected by network lag).

Destroying networked objects works only if they got created with PhotonNetwork.Instantiate(). Objects loaded with a scene are ignored, no matter if they have PhotonView components.

Returns

Nothing. Check error debug log for any issues.

```
8.35.2.16 static void PhotonNetwork.DestroyPlayerObjects ( PhotonPlayer targetPlayer ) [static]
```

Network-Destroy all GameObjects, PhotonViews and their RPCs of targetPlayer. Can only be called on local player (for "self") or Master Client (for anyone).

Destroying a networked GameObject includes:

- · Removal of the Instantiate call from the server's room buffer.
- Removing RPCs buffered for PhotonViews that got created indirectly with the PhotonNetwork.Instantiate call.
- Sending a message to other clients to remove the GameObject also (affected by network lag).

Destroying networked objects works only if they got created with PhotonNetwork.Instantiate(). Objects loaded with a scene are ignored, no matter if they have PhotonView components.

Returns

Nothing. Check error debug log for any issues.

```
8.35.2.17 static void PhotonNetwork.DestroyPlayerObjects (int targetPlayerId) [static]
```

Network-Destroy all GameObjects, PhotonViews and their RPCs of this player (by ID). Can only be called on local player (for "self") or Master Client (for anyone).

Destroying a networked GameObject includes:

- · Removal of the Instantiate call from the server's room buffer.
- Removing RPCs buffered for PhotonViews that got created indirectly with the PhotonNetwork.Instantiate call.
- · Sending a message to other clients to remove the GameObject also (affected by network lag).

Destroying networked objects works only if they got created with PhotonNetwork.Instantiate(). Objects loaded with a scene are ignored, no matter if they have PhotonView components.

Returns

Nothing. Check error debug log for any issues.

8.35.2.18 static void PhotonNetwork.Disconnect() [static]

Makes this client disconnect from the photon server, a process that leaves any room and calls OnDisconnected← FromPhoton on completion.

When you disconnect, the client will send a "disconnecting" message to the server. This speeds up leave/disconnect messages for players in the same room as you (otherwise the server would timeout this client's connection). When used in offlineMode, the state-change and event-call OnDisconnectedFromPhoton are immediate. Offline mode is set to false as well. Once disconnected, the client can connect again. Use ConnectUsingSettings.

8.35.2.19 delegate void PhotonNetwork.EventCallback (byte eventCode, object content, int senderId)

Defines the delegate usable in OnEventCall.

Any eventCode < 200 will be forwarded to your delegate(s).

Parameters

eventCode	The code assigend to the incoming event.
content	The content the sender put into the event.
senderld	The ID of the player who sent the event. It might be 0, if the "room" sent the event.

8.35.2.20 static void PhotonNetwork.FetchServerTimestamp() [static]

Refreshes the server timestamp (async operation, takes a roundtrip).

Can be useful if a bad connection made the timestamp unusable or imprecise.

8.35.2.21 static bool PhotonNetwork.FindFriends (string[] friendsToFind, FindFriendsOptions options = null)
[static]

Requests the rooms and online status for a list of friends and saves the result in PhotonNetwork.Friends.

Works only on Master Server to find the rooms played by a selected list of users.

The result will be stored in PhotonNetwork.Friends when available. That list is initialized on first use of OpFind← Friends (before that, it is null). To refresh the list, call FindFriends again (in 5 seconds or 10 or 20).

Users identify themselves by setting a unique userld in the PhotonNetwork.AuthValues. See remarks of AuthenticationValues for info about how this is set and used.

The list of friends must be fetched from some other source (not provided by Photon).

Internal: The server response includes 2 arrays of info (each index matching a friend from the request): Parameter Code.FindFriendsResponseOnlineList = bool[] of online states ParameterCode.FindFriendsResponseRoomIdList = string[] of room names (empty string if not in a room)

Parameters

friendsToFind	Array of friend (make sure to use unique playerName or AuthValues).
options	Options that affect the result of the FindFriends operation.

Returns

If the operation could be sent (requires connection, only one request is allowed at any time). Always false in offline mode.

8.35.2.22 static HashSet < GameObject > PhotonNetwork.FindGameObjectsWithComponent (Type type) [static]

Finds the GameObjects with Components of a specific type (using FindObjectsOfType).

Parameters

type	Type must be a Component

Returns

HashSet with GameObjects that have a specific type of Component.

8.35.2.23 static bool PhotonNetwork.GetCustomRoomList (TypedLobby, typedLobby, string sqlLobbyFilter) [static]

Fetches a custom list of games from the server, matching a SQL-like "where" clause, then triggers OnReceived← RoomListUpdate callback.

Operation is only available for lobbies of type SqlLobby. Note: You don't have to join that lobby. This is an async request.

When done, OnReceivedRoomListUpdate gets called. Use GetRoomList() to access it.

https://doc.photonengine.com/en-us/pun/current/lobby-and-matchmaking/matchmaking-and-lobby::sql_lobby_type
Parameters

typedLobby	The lobby to query. Has to be of type SqlLobby.
sqlLobbyFilter	The sql query statement.

Returns

If the operation could be sent (has to be connected).

8.35.2.24 static int PhotonNetwork.GetPing() [static]

The current roundtrip time to the photon server.

Returns

Roundtrip time (to server and back).

8.35.2.25 static RoomInfo [] PhotonNetwork.GetRoomList () [static]

Gets currently cached rooms of the last rooms list sent by the server as RoomInfo array. This list is either available and updated automatically and periodically while in a lobby (check insideLobby) or received as a response to PhotonNetwork.GetCustomRoomList().

This list is a cached copy of the internal rooms list so it can be accessed each frame if needed. Per RoomInfo you can check if the room is full by comparing playerCount and MaxPlayers before you allow a join.

The name of a room must be used to join it (via JoinRoom).

Closed rooms are also listed by lobbies but they can't be joined. While in a room, any player can set Room.visible and Room.open to hide rooms from matchmaking and close them.

Returns

Cached RoomInfo[] of last room list sent by the server.

8.35.2.26 static void PhotonNetwork.InitializeSecurity () [static]

Used for compatibility with Unity networking only. Encryption is automatically initialized while connecting.

8.35.2.27 static GameObject PhotonNetwork.Instantiate (string *prefabName*, Vector3 *position*, Quaternion *rotation*, byte *group*) [static]

Instantiate a prefab over the network. This prefab needs to be located in the root of a "Resources" folder.

Instead of using prefabs in the Resources folder, you can manually Instantiate and assign PhotonViews. See doc.

Parameters

prefabName	Name of the prefab to instantiate.
position	Position Vector3 to apply on instantiation.
rotation	Rotation Quaternion to apply on instantiation.
group	The group for this PhotonView.

Returns

The new instance of a GameObject with initialized PhotonView.

8.35.2.28 static GameObject PhotonNetwork.Instantiate (string *prefabName*, Vector3 *position*, Quaternion *rotation*, byte *group*, object[] *data*) [static]

Instantiate a prefab over the network. This prefab needs to be located in the root of a "Resources" folder.

Instead of using prefabs in the Resources folder, you can manually Instantiate and assign PhotonViews. See doc.

Parameters

prefabName	Name of the prefab to instantiate.
position	Position Vector3 to apply on instantiation.
rotation	Rotation Quaternion to apply on instantiation.
group	The group for this PhotonView.
data	Optional instantiation data. This will be saved to it's PhotonView.instantiationData.

Returns

The new instance of a GameObject with initialized PhotonView.

8.35.2.29 static GameObject PhotonNetwork.InstantiateSceneObject (string *prefabName*, Vector3 *position*, Quaternion *rotation*, byte *group*, object[] *data*) [static]

Instantiate a scene-owned prefab over the network. The PhotonViews will be controllable by the MasterClient. This prefab needs to be located in the root of a "Resources" folder.

Only the master client can Instantiate scene objects. Instead of using prefabs in the Resources folder, you can manually Instantiate and assign PhotonViews. See doc.

Parameters

prefabName	Name of the prefab to instantiate.
position	Position Vector3 to apply on instantiation.
rotation	Rotation Quaternion to apply on instantiation.
group	The group for this PhotonView.
data	Optional instantiation data. This will be saved to it's PhotonView.instantiationData.

Returns

The new instance of a GameObject with initialized PhotonView.

```
8.35.2.30 static bool PhotonNetwork.JoinLobby ( ) [static]
```

On MasterServer this joins the default lobby which list rooms currently in use.

The room list is sent and refreshed by the server. You can access this cached list by PhotonNetwork.GetRoomList().

Per room you should check if it's full or not before joining. Photon also lists rooms that are full, unless you close and hide them (room.open = false and room.visible = false).

In best case, you make your clients join random games, as described here: https://doc.photonengine.com/en-us/pun/current/lobby-and-matchmaking/matchmaking-and-lobby

You can show your current players and room count without joining a lobby (but you must be on the master server). Use: countOfPlayers, countOfPlayersOnMaster, countOfPlayersInRooms and countOfRooms.

You can use more than one lobby to keep the room lists shorter. See JoinLobby(TypedLobby lobby). When creating new rooms, they will be "attached" to the currently used lobby or the default lobby.

You can use JoinRandomRoom without being in a lobby! Set autoJoinLobby = false before you connect, to not join a lobby. In that case, the connect-workflow will call OnConnectedToMaster (if you implement it) when it's done.

```
8.35.2.31 static bool PhotonNetwork.JoinLobby ( TypedLobby typedLobby ) [static]
```

On a Master Server you can join a lobby to get lists of available rooms.

The room list is sent and refreshed by the server. You can access this cached list by PhotonNetwork.GetRoomList().

Any client can "make up" any lobby on the fly. Splitting rooms into multiple lobbies will keep each list shorter. However, having too many lists might ruin the matchmaking experience.

In best case, you create a limited number of lobbies. For example, create a lobby per game-mode: "koth" for king of the hill and "ffa" for free for all, etc.

There is no listing of lobbies at the moment.

Sql-typed lobbies offer a different filtering model for random matchmaking. This might be more suited for skillbased-games. However, you will also need to follow the conventions for naming filterable properties in sql-lobbies! Both is explained in the matchmaking doc linked below.

In best case, you make your clients join random games, as described here: http://confluence.com/display/PTN/Op+JoinRandomGame

Per room you should check if it's full or not before joining. Photon does list rooms that are full, unless you close and hide them (room.open = false and room.visible = false).

You can show your games current players and room count without joining a lobby (but you must be on the master server). Use: countOfPlayers, countOfPlayersOnMaster, countOfPlayersInRooms and countOfRooms.

When creating new rooms, they will be "attached" to the currently used lobby or the default lobby.

You can use JoinRandomRoom without being in a lobby! Set autoJoinLobby = false before you connect, to not join a lobby. In that case, the connect-workflow will call OnConnectedToMaster (if you implement it) when it's done.

Parameters

```
typedLobby A typed lobby to join (must have name and type).
```

```
8.35.2.32 static bool PhotonNetwork.JoinOrCreateRoom ( string roomName, RoomOptions roomOptions, TypedLobby typedLobby ) [static]
```

Lets you either join a named room or create it on the fly - you don't have to know if someone created the room already.

This makes it easier for groups of players to get into the same room. Once the group exchanged a roomName, any player can call JoinOrCreateRoom and it doesn't matter who actually joins or creates the room.

The parameters roomOptions and typedLobby are only used when the room actually gets created by this client. You know if this client created a room, if you get a callback OnCreatedRoom (before OnJoinedRoom gets called as well).

Parameters

roomName	Name of the room to join. Must be non null.
roomOptions	Options for the room, in case it does not exist yet. Else these values are ignored.
typedLobby	Lobby you want a new room to be listed in. Ignored if the room was existing and got joined.

Returns

If the operation got queued and will be sent.

8.35.2.33 static bool PhotonNetwork.JoinOrCreateRoom (string roomName, RoomOptions roomOptions, TypedLobby typedLobby, string[] expectedUsers) [static]

Lets you either join a named room or create it on the fly - you don't have to know if someone created the room already.

This makes it easier for groups of players to get into the same room. Once the group exchanged a roomName, any player can call JoinOrCreateRoom and it doesn't matter who actually joins or creates the room.

The parameters roomOptions and typedLobby are only used when the room actually gets created by this client. You know if this client created a room, if you get a callback OnCreatedRoom (before OnJoinedRoom gets called as well).

You can define an array of expectedUsers, to block player slots in the room for these users. The corresponding feature in Photon is called "Slot Reservation" and can be found in the doc pages.

Parameters

roomName	Name of the room to join. Must be non null.
roomOptions	Options for the room, in case it does not exist yet. Else these values are ignored.
typedLobby	Lobby you want a new room to be listed in. Ignored if the room was existing and got joined.
expectedUsers	Optional list of users (by Userld) who are expected to join this game and who you want to
	block a slot for.

Returns

If the operation got queued and will be sent.

8.35.2.34 static bool PhotonNetwork.JoinRandomRoom() [static]

Joins any available room of the currently used lobby and fails if none is available.

Rooms can be created in arbitrary lobbies which get created on demand. You can join rooms from any lobby without actually joining the lobby. Use the JoinRandomRoom overload with TypedLobby parameter.

This method will only match rooms attached to one lobby! If you use many lobbies, you might have to repeat Join

RandomRoom, to find some fitting room. This method looks up a room in the currently active lobby or (if no lobby is joined) in the default lobby.

If this fails, you can still create a room (and make this available for the next who uses JoinRandomRoom). Alternatively, try again in a moment.

8.35.2.35 static bool PhotonNetwork.JoinRandomRoom (Hashtable expectedCustomRoomProperties, byte expectedMaxPlayers) [static]

Attempts to join an open room with fitting, custom properties but fails if none is currently available.

Rooms can be created in arbitrary lobbies which get created on demand. You can join rooms from any lobby without actually joining the lobby. Use the JoinRandomRoom overload with TypedLobby parameter.

This method will only match rooms attached to one lobby! If you use many lobbies, you might have to repeat Join⊷ RandomRoom, to find some fitting room. This method looks up a room in the currently active lobby or (if no lobby is joined) in the default lobby.

If this fails, you can still create a room (and make this available for the next who uses JoinRandomRoom). Alternatively, try again in a moment.

Parameters

expected↔	Filters for rooms that match these custom properties (string keys and values). To ignore, pass
CustomRoom⊷	null.
Properties	
<i>expectedMax</i> ←	Filters for a particular maxplayer setting. Use 0 to accept any maxPlayer value.
Players	

Returns

If the operation got queued and will be sent.

8.35.2.36 static bool PhotonNetwork.JoinRandomRoom (Hashtable expectedCustomRoomProperties, byte expectedMaxPlayers, MatchmakingMode matchingType, TypedLobby typedLobby, string sqlLobbyFilter, string[] expectedUsers = null) [static]

Attempts to join an open room with fitting, custom properties but fails if none is currently available.

Rooms can be created in arbitrary lobbies which get created on demand. You can join rooms from any lobby without actually joining the lobby with this overload.

This method will only match rooms attached to one lobby! If you use many lobbies, you might have to repeat Join⊷ RandomRoom, to find some fitting room. This method looks up a room in the specified lobby or the currently active lobby (if none specified) or in the default lobby (if none active).

If this fails, you can still create a room (and make this available for the next who uses JoinRandomRoom). Alternatively, try again in a moment.

In offlineMode, a room will be created but no properties will be set and all parameters of this JoinRandomRoom call are ignored. The event/callback OnJoinedRoom gets called (see enum PhotonNetworkingMessage).

You can define an array of expectedUsers, to block player slots in the room for these users. The corresponding feature in Photon is called "Slot Reservation" and can be found in the doc pages.

Parameters

expected←	Filters for rooms that match these custom properties (string keys and values). To ignore, pass
CustomRoom⇔	null.
Properties	
<i>expectedMax</i> ←	Filters for a particular maxplayer setting. Use 0 to accept any maxPlayer value.
Players	
matchingType	Selects one of the available matchmaking algorithms. See MatchmakingMode enum for op-
	tions.
typedLobby	The lobby in which you want to lookup a room. Pass null, to use the default lobby. This does
	not join that lobby and neither sets the lobby property.
sqlLobbyFilter	A filter-string for SQL-typed lobbies.
expectedUsers	Optional list of users (by Userld) who are expected to join this game and who you want to
	block a slot for.

Returns

If the operation got queued and will be sent.

8.35.2.37 static bool PhotonNetwork.JoinRoom (string roomName) [static]

Join room by roomname and on success calls OnJoinedRoom(). This is not affected by lobbies.

On success, the method OnJoinedRoom() is called on any script. You can implement it to react to joining a room.

JoinRoom fails if the room is either full or no longer available (it might become empty while you attempt to join). Implement OnPhotonJoinRoomFailed() to get a callback in error case.

To join a room from the lobby's listing, use RoomInfo.Name as roomName here. Despite using multiple lobbies, a roomName is always "global" for your application and so you don't have to specify which lobby it's in. The Master Server will find the room. In the Photon Cloud, an application is defined by Appld, Game- and PUN-version.

PhotonNetworkingMessage.OnPhotonJoinRoomFailed PhotonNetworkingMessage.OnJoinedRoom

Parameters

roomName	Unique name of the room to join.

Returns

If the operation got queued and will be sent.

8.35.2.38 static bool PhotonNetwork.JoinRoom (string roomName, string[] expectedUsers) [static]

Join room by roomname and on success calls OnJoinedRoom(). This is not affected by lobbies.

On success, the method OnJoinedRoom() is called on any script. You can implement it to react to joining a room.

JoinRoom fails if the room is either full or no longer available (it might become empty while you attempt to join). Implement OnPhotonJoinRoomFailed() to get a callback in error case.

To join a room from the lobby's listing, use RoomInfo.Name as roomName here. Despite using multiple lobbies, a roomName is always "global" for your application and so you don't have to specify which lobby it's in. The Master Server will find the room. In the Photon Cloud, an application is defined by Appld, Game- and PUN-version.

You can define an array of expectedUsers, to block player slots in the room for these users. The corresponding feature in Photon is called "Slot Reservation" and can be found in the doc pages.

PhotonNetworkingMessage.OnPhotonJoinRoomFailed PhotonNetworkingMessage.OnJoinedRoom

Parameters

roomName	Unique name of the room to join.
expectedUsers	Optional list of users (by Userld) who are expected to join this game and who you want to
	block a slot for.

Returns

If the operation got queued and will be sent.

8.35.2.39 static bool PhotonNetwork.LeaveLobby() [static]

Leave a lobby to stop getting updates about available rooms.

This does not reset PhotonNetwork.lobby! This allows you to join this particular lobby later easily.

The values countOfPlayers, countOfPlayersOnMaster, countOfPlayersInRooms and countOfRooms are received even without being in a lobby.

You can use JoinRandomRoom without being in a lobby. Use autoJoinLobby to not join a lobby when you connect.

8.35.2.40 static bool PhotonNetwork.LeaveRoom (bool becomelnactive = true) [static]

Leave the current room and return to the Master Server where you can join or create rooms (see remarks).

This will clean up all (network) GameObjects with a PhotonView, unless you changed autoCleanUp to false. Returns to the Master Server.

In OfflineMode, the local "fake" room gets cleaned up and OnLeftRoom gets called immediately.

In a room with player TTL < 0, Leave Room just turns a client inactive. The player stays in the room's player list and can return later on. Setting become lnactive to false deliberately, means to "abandon" the room, despite the player TTL allowing you to come back.

In a room with playerTTL == 0, become inactive has no effect (clients are removed from the room right away).

Parameters

	becomelnactive	If this client becomes inactive in a room with player TTL $<$ 0. Defaults to true.
--	----------------	--

8.35.2.41 static void PhotonNetwork.LoadLevel (int levelNumber) [static]

Wraps loading a level to pause the network message-queue. Optionally syncs the loaded level in a room.

To sync the loaded level in a room, set PhotonNetwork.automaticallySyncScene to true. The Master Client of a room will then sync the loaded level with every other player in the room.

While loading levels, it makes sense to not dispatch messages received by other players. This method takes care of that by setting PhotonNetwork.isMessageQueueRunning = false and enabling the queue when the level was loaded.

You should make sure you don't fire RPCs before you load another scene (which doesn't contain the same Game← Objects and PhotonViews). You can call this in OnJoinedRoom.

This uses Application.LoadLevel in Unity version not yet featuring the SceneManager API.

Parameters

levelNumber	Number of the level to load. When using level numbers, make sure they are identical on all
	clients.

8.35.2.42 static void PhotonNetwork.LoadLevel (string *levelName*) [static]

Wraps loading a level to pause the network message-queue. Optionally syncs the loaded level in a room.

While loading levels, it makes sense to not dispatch messages received by other players. This method takes care of that by setting PhotonNetwork.isMessageQueueRunning = false and enabling the queue when the level was loaded.

To sync the loaded level in a room, set PhotonNetwork.automaticallySyncScene to true. The Master Client of a room will then sync the loaded level with every other player in the room.

You should make sure you don't fire RPCs before you load another scene (which doesn't contain the same Game← Objects and PhotonViews). You can call this in OnJoinedRoom.

This uses Application.LoadLevel in Unity version not yet featuring the SceneManager API.

Parameters

levelName Name of the level to load. Make sure it's available to all clients in the same room.

8.35.2.43 static AsyncOperation PhotonNetwork.LoadLevelAsync (int levelNumber) [static]

Wraps single asynchronous loading of a level to pause the network message-queue. Optionally syncs the loaded level in a room.

To sync the loaded level in a room, set PhotonNetwork.automaticallySyncScene to true. The Master Client of a room will then sync the loaded level with every other player in the room.

While loading levels, it makes sense to not dispatch messages received by other players. This method takes care of that by setting PhotonNetwork.isMessageQueueRunning = false and enabling the queue when the level was loaded.

You should make sure you don't fire RPCs before you load another scene (which doesn't contain the same Game
Objects and PhotonViews). You can call this in OnJoinedRoom.

This uses Application.LoadLevel in Unity version not yet featuring the SceneManager API.

Returns

The async operation.

Parameters

levelNumber	Number of the level to load. When using level numbers, make sure they are identical on all
levelivattibet	Number of the level to load. Which doing level hambers, make sure they are identical on an
	clients.
	Clients.

8.35.2.44 static AsyncOperation PhotonNetwork.LoadLevelAsync (string levelName) [static]

Wraps single asynchronous loading of a level to pause the network message-queue. Optionally syncs the loaded level in a room.

While loading levels, it makes sense to not dispatch messages received by other players. This method takes care of that by setting PhotonNetwork.isMessageQueueRunning = false and enabling the queue when the level was loaded.

To sync the loaded level in a room, set PhotonNetwork.automaticallySyncScene to true. The Master Client of a room will then sync the loaded level with every other player in the room.

You should make sure you don't fire RPCs before you load another scene (which doesn't contain the same Game← Objects and PhotonViews). You can call this in OnJoinedRoom.

This uses Application.LoadLevel in Unity version not yet featuring the SceneManager API.

Returns

The async operation.

Parameters

levelName	Name of the level to load. Make sure it's available to all clients in the same room.
mode	LoadSceneMode either single or additive

8.35.2.45 static void PhotonNetwork.NetworkStatisticsReset () [static]

Resets the traffic stats and re-enables them.

8.35.2.46 static string PhotonNetwork.NetworkStatisticsToString() [static]

Only available when NetworkStatisticsEnabled was used to gather some stats.

Returns

A string with vital networking statistics.

8.35.2.47 static void PhotonNetwork.OverrideBestCloudServer (CloudRegionCode region) [static]

Overwrites the region that is used for ConnectToBestCloudServer(string gameVersion).

This will overwrite the result of pinging all cloud servers.

Use this to allow your users to save a manually selected region in the player preferences.

Note: You can also use PhotonNetwork.ConnectToRegion to (temporarily) connect to a specific region.

8.35.2.48 static bool PhotonNetwork.RaiseEvent (byte eventCode, object eventContent, bool sendReliable, RaiseEventOptions options) [static]

Sends fully customizable events in a room. Events consist of at least an EventCode (0..199) and can have content.

To receive the events someone sends, register your handling method in PhotonNetwork.OnEventCall.

Example: private void OnEventHandler(byte eventCode, object content, int senderId) { Debug.Log("OnEvent← Handler"); }

PhotonNetwork.OnEventCall += this.OnEventHandler;

With the senderld, you can look up the PhotonPlayer who sent the event. It is best practice to assign a eventCode for each different type of content and action. You have to cast the content.

The eventContent is optional. To be able to send something, it must be a "serializable type", something that the client can turn into a byte[] basically. Most basic types and arrays of them are supported, including Unity's Vector2, Vector3, Quaternion. Transforms or classes some project defines are NOT supported! You can make your own class a "serializable type" by following the example in CustomTypes.cs.

The RaiseEventOptions have some (less intuitive) combination rules: If you set targetActors (an array of Photon← Player.ID values), the receivers parameter gets ignored. When using event caching, the targetActors, receivers and interestGroup can't be used. Buffered events go to all. When using cachingOption removeFromRoomCache, the eventCode and content are actually not sent but used as filter.

Parameters

eventCode	A byte identifying the type of event. You might want to use a code per action or to signal
	which content can be expected. Allowed: 0199.
eventContent	Some serializable object like string, byte, integer, float (etc) and arrays of those. Hashtables
	with byte keys are good to send variable content.
sendReliable	Makes sure this event reaches all players. It gets acknowledged, which requires bandwidth
	and it can't be skipped (might add lag in case of loss).
options	Allows more complex usage of events. If null, RaiseEventOptions.Default will be used (which
	is fine).

Returns

False if event could not be sent

8.35.2.49 static bool PhotonNetwork.Reconnect() [static]

Can be used to reconnect to the master server after a disconnect.

After losing connection, you can use this to connect a client to the region Master Server again. Cache the room name you're in and use ReJoin(roomname) to return to a game. Common use case: Press the Lock Button on a iOS device and you get disconnected immediately.

8.35.2.50 static bool PhotonNetwork.ReconnectAndRejoin() [static]

When the client lost connection during gameplay, this method attempts to reconnect and rejoin the room.

This method re-connects directly to the game server which was hosting the room PUN was in before. If the room was shut down in the meantime, PUN will call OnPhotonJoinRoomFailed and return this client to the Master Server.

Check the return value, if this client will attempt a reconnect and rejoin (if the conditions are met). If Reconnect AndRejoin returns false, you can still attempt a Reconnect and ReJoin.

Similar to PhotonNetwork.ReJoin, this requires you to use unique IDs per player (the UserID).

Returns

False, if there is no known room or game server to return to. Then, this client does not attempt the Reconnect ← And Rejoin.

8.35.2.51 static void PhotonNetwork.RefreshCloudServerRating() [static]

Pings all cloud servers again to find the one with best ping (currently).

 $\textbf{8.35.2.52} \quad \textbf{static bool PhotonNetwork.ReJoinRoom (string } \textit{roomName} \text{)} \quad \texttt{[static]}$

Can be used to return to a room after a disconnect and reconnect.

After losing connection, you might be able to return to a room and continue playing, if the client is reconnecting fast enough. Use Reconnect() and this method. Cache the room name you're in and use ReJoin(roomname) to return to a game.

Note: To be able to ReJoin any room, you need to use UserIDs! You also need to set RoomOptions.PlayerTtl.

Important: Instantiate() and use of RPCs is not yet supported. The ownership rules of PhotonViews prevent a seamless return to a game. Use Custom Properties and RaiseEvent with event caching instead.

Common use case: Press the Lock Button on a iOS device and you get disconnected immediately.

8.35.2.53 static void PhotonNetwork.RemovePlayerCustomProperties (string[] customPropertiesToDelete) [static]

Locally removes Custom Properties of "this" player. Important: This does not synchronize the change! Useful when you switch rooms.

Use this method with care. It can create inconsistencies of state between players! This only changes the player.

customProperties locally. This can be useful to clear your Custom Properties between games (let's say they store which turn you made, kills, etc).

SetPlayerCustomProperties() syncs and can be used to set values to null while in a room. That can be considered "removed" while in a room.

If customPropertiesToDelete is null or has 0 entries, all Custom Properties are deleted (replaced with a new Hashtable). If you specify keys to remove, those will be removed from the Hashtable but other keys are unaffected.

Parameters

custom⇔	List of Custom Property keys to remove. See remarks.
PropertiesTo⊷	
Delete	

8.35.2.54 static void PhotonNetwork.RemoveRPCs (PhotonPlayer targetPlayer) [static]

Remove all buffered RPCs from server that were sent by targetPlayer. Can only be called on local player (for "self") or Master Client (for anyone).

This method requires either:

• This is the targetPlayer's client.

• This client is the Master Client (can remove any PhotonPlayer's RPCs).

If the targetPlayer calls RPCs at the same time that this is called, network lag will determine if those get buffered or cleared like the rest.

Parameters

targetPlayer	This player's buffered RPCs get removed from server buffer.

8.35.2.55 static void PhotonNetwork.RemoveRPCs (PhotonView targetPhotonView) [static]

Remove all buffered RPCs from server that were sent via targetPhotonView. The Master Client and the owner of the targetPhotonView may call this.

This method requires either:

- The targetPhotonView is owned by this client (Instantiated by it).
- This client is the Master Client (can remove any PhotonView's RPCs).

Parameters

targetPhoton⊷	RPCs buffered for this PhotonView get removed from server buffer.
View	

8.35.2.56 static void PhotonNetwork.RemoveRPCsInGroup (int targetGroup) [static]

Remove all buffered RPCs from server that were sent in the targetGroup, if this is the Master Client or if this controls the individual PhotonView.

This method requires either:

- This client is the Master Client (can remove any RPCs per group).
- Any other client: each PhotonView is checked if it is under this client's control. Only those RPCs are removed.

Parameters

_		
	targetGroup	Interest group that gets all RPCs removed.

8.35.2.57 static void PhotonNetwork.SendOutgoingCommands() [static]

Can be used to immediately send the RPCs and Instantiates just called, so they are on their way to the other players.

This could be useful if you do a RPC to load a level and then load it yourself. While loading, no RPCs are sent to others, so this would delay the "load" RPC. You can send the RPC to "others", use this method, disable the message queue (by isMessageQueueRunning) and then load.

8.35.2.58 static void PhotonNetwork.SetInterestGroups (byte group, bool enabled) [static]

Enable/disable receiving events from a given Interest Group.

A client can tell the server which Interest Groups it's interested in. The server will only forward events for those Interest Groups to that client (saving bandwidth and performance).

See: https://doc.photonengine.com/en-us/pun/current/gameplay/interestgroups

 $\textbf{See:} \ \texttt{https://doc.photonengine.com/en-us/pun/current/demos-and-tutorials/package-demos/cull} \\$

Parameters

group	The interest group to affect.
enabled	Sets if receiving from group to enabled (or not).

8.35.2.59 static void PhotonNetwork.SetInterestGroups (byte[] disableGroups, byte[] enableGroups) [static]

Enable/disable receiving on given Interest Groups (applied to PhotonViews).

A client can tell the server which Interest Groups it's interested in. The server will only forward events for those Interest Groups to that client (saving bandwidth and performance).

See: https://doc.photonengine.com/en-us/pun/current/gameplay/interestgroups

See: https://doc.photonengine.com/en-us/pun/current/demos-and-tutorials/package-demos/cul

Parameters

disableGroups	The interest groups to disable (or null).
enableGroups	The interest groups to enable (or null).

8.35.2.60 static void PhotonNetwork.SetLevelPrefix (short *prefix*) [static]

Sets level prefix for PhotonViews instantiated later on. Don't set it if you need only one!

Important: If you don't use multiple level prefixes, simply don't set this value. The default value is optimized out of the traffic.

This won't affect existing PhotonViews (they can't be changed yet for existing PhotonViews).

Messages sent with a different level prefix will be received but not executed. This affects RPCs, Instantiates and synchronization.

Be aware that PUN never resets this value, you'll have to do so yourself.

Parameters

_		
	prefix	Max value is short.MaxValue = 32767

8.35.2.61 static bool PhotonNetwork.SetMasterClient (PhotonPlayer masterClientPlayer) [static]

Asks the server to assign another player as Master Client of your current room.

RPCs and RaiseEvent have the option to send messages only to the Master Client of a room. SetMasterClient affects which client gets those messages.

This method calls an operation on the server to set a new Master Client, which takes a roundtrip. In case of success, this client and the others get the new Master Client from the server.

SetMasterClient tells the server which current Master Client should be replaced with the new one. It will fail, if anything switches the Master Client moments earlier. There is no callback for this error. All clients should get the new Master Client assigned by the server anyways.

See also: PhotonNetwork.masterClient

On v3 servers: The ReceiverGroup.MasterClient (usable in RPCs) is not affected by this (still points to lowest player.ID in room). Avoid using this enum value (and send to a specific player instead).

If the current Master Client leaves, PUN will detect a new one by "lowest player ID". Implement OnMasterClient witched to get a callback in this case. The PUN-selected Master Client might assign a new one.

Make sure you don't create an endless loop of Master-assigning! When selecting a custom Master Client, all clients should point to the same player, no matter who actually assigns this player.

Locally the Master Client is immediately switched, while remote clients get an event. This means the game is tempoarily without Master Client like when a current Master Client leaves.

When switching the Master Client manually, keep in mind that this user might leave and not do it's work, just like any Master Client.

Parameters

rCliant.	The player to become the next Master Client.
ı Gilerit←	The player to become the next Master Cheft.
Dlavar	
Playel	
	rClient⇔ Player

Returns

False when this operation couldn't be done. Must be in a room (not in offlineMode).

8.35.2.62 static void PhotonNetwork.SetPlayerCustomProperties (Hashtable customProperties) [static]

Sets this (local) player's properties and synchronizes them to the other players (don't modify them directly).

While in a room, your properties are synced with the other players. CreateRoom, JoinRoom and JoinRandomRoom will all apply your player's custom properties when you enter the room. The whole Hashtable will get sent. Minimize the traffic by setting only updated key/values.

If the Hashtable is null, the custom properties will be cleared. Custom properties are never cleared automatically, so they carry over to the next room, if you don't change them.

Don't set properties by modifying PhotonNetwork.player.customProperties!

Parameters

custom⇔	Only string-typed keys will be used from this hashtable.	If null, custom properties are all
Properties	deleted.	

8.35.2.63 static void PhotonNetwork.SetReceivingEnabled (int group, bool enabled) [static]
8.35.2.64 static void PhotonNetwork.SetReceivingEnabled (int[] enableGroups, int[] disableGroups) [static]
8.35.2.65 static void PhotonNetwork.SetSendingEnabled (int group, bool enabled) [static]
8.35.2.66 static void PhotonNetwork.SetSendingEnabled (byte group, bool enabled) [static]

Enable/disable sending on given group (applied to PhotonViews)

This does not interact with the Photon server-side. It's just a client-side setting to suppress updates, should they be sent to one of the blocked groups.

This setting is not particularly useful, as it means that updates literally never reach the server or anyone else. Use with care.

Parameters

group	The interest group to affect.
enabled	Sets if sending to group is enabled (or not).

8.35.2.67 static void PhotonNetwork.SetSendingEnabled (int[] enableGroups, int[] disableGroups) [static]

8.35.2.68 static void PhotonNetwork.SetSendingEnabled (byte[] disableGroups, byte[] enableGroups) [static]

Enable/disable sending on given groups (applied to PhotonViews)

This does not interact with the Photon server-side. It's just a client-side setting to suppress updates, should they be sent to one of the blocked groups.

This setting is not particularly useful, as it means that updates literally never reach the server or anyone else. Use with care.

Parameters

enableGroups	The interest groups to enable sending on (or null).
disableGroups	The interest groups to disable sending on (or null).

8.35.2.69 static void PhotonNetwork.SwitchToProtocol (ConnectionProtocol cp) [static]

While offline, the network protocol can be switched (which affects the ports you can use to connect).

When you switch the protocol, make sure to also switch the port for the master server. Default ports are: TCP: 4530 UDP: 5055

This could look like this:

Connect(serverAddress, <udpport|tcpport>, appID, gameVersion)

Or when you use ConnectUsingSettings(), the PORT in the settings can be switched like so:

PhotonNetwork.PhotonServerSettings.ServerPort = 4530;

The current protocol can be read this way:

PhotonNetwork.networkingPeer.UsedProtocol

This does not work with the native socket plugin of PUN+ on mobile!

Parameters

ср	Network protocol to use as low level connection. UDP is default. TCP is not available on all
	platforms (see remarks).

8.35.2.70 static void PhotonNetwork.UnAllocateViewID (int *viewID*) [static]

Unregister a viewID (of manually instantiated and destroyed networked objects).

Parameters

viewID	A viewID manually allocated by this player.

8.35.2.71 static bool PhotonNetwork.WebRpc (string name, object parameters) [static]

This operation makes Photon call your custom web-service by name (path) with the given parameters.

This is a server-side feature which must be setup in the Photon Cloud Dashboard prior to use. https://doc. \leftarrow photonengine.com/en-us/pun/current/gameplay/web-extensions/webrpc The Parameters will be converted into J \leftarrow Son format, so make sure your parameters are compatible.

See PhotonNetworkingMessage.OnWebRpcResponse on how to get a response.

It's important to understand that the OperationResponse only tells if the WebRPC could be called. The content of the response contains any values your web-service sent and the error/success code. In case the web-service failed, an error code and a debug message are usually inside the OperationResponse.

The class WebRpcResponse is a helper-class that extracts the most valuable content from the WebRPC response.

Example callback implementation:

public void OnWebRpcResponse(OperationResponse response)

```
WebRpcResponse webResponse = new WebRpcResponse(operationResponse);
if (webResponse.ReturnCode != 0) { //...
}

switch (webResponse.Name) { //...
}
// and so on
```

8.35.3 Member Data Documentation

8.35.3.1 float PhotonNetwork.BackgroundTimeout = 60.0f [static]

Defines how many seconds PUN keeps the connection, after Unity's OnApplicationPause(true) call. Default: 60 seconds.

It's best practice to disconnect inactive apps/connections after a while but to also allow users to take calls, etc.. We think a reasonable backgroung timeout is 60 seconds.

To handle the timeout, implement: OnDisconnectedFromPhoton(), as usual. Your application will "notice" the background disconnect when it becomes active again (running the Update() loop).

If you need to separate this case from others, you need to track if the app was in the background (there is no special callback by PUN).

A value below 0.1 seconds will disable this timeout (careful: connections can be kept indefinitely).

Info: PUN is running a "fallback thread" to send ACKs to the server, even when Unity is not calling Update() regularly. This helps keeping the connection while loading scenes and assets and when the app is in the background.

Note: Some platforms (e.g. iOS) don't allow to keep a connection while the app is in background. In those cases, this value does not change anything, the app immediately loses connection in background.

Unity's OnApplicationPause() callback is broken in some exports (Android) of some Unity versions. Make sure OnApplicationPause() gets the callbacks you'd expect on the platform you target! Check PhotonHandler.On← ApplicationPause(bool pause), to see the implementation.

```
8.35.3.2 bool PhotonNetwork.InstantiateInRoomOnly = true [static]
```

If true, Instantiate methods will check if you are in a room and fail if you are not.

Instantiating anything outside of a specific room is very likely to break things. Turn this off only if you know what you

```
8.35.3.3 PhotonLogLevel PhotonNetwork.logLevel = PhotonLogLevel.ErrorsOnly [static]
```

Network log level. Controls how verbose PUN is.

```
8.35.3.4 readonly int PhotonNetwork.MAX_VIEW_IDS = 1000 [static]
```

The maximum number of assigned PhotonViews *per player* (or scene). See the General Documentation topic "Limitations" on how to raise this limitation.

```
8.35.3.5 int PhotonNetwork.maxConnections [static]
```

Only used in Unity Networking. In PUN, set the number of players in PhotonNetwork.CreateRoom.

8.35.3.6 ServerSettings PhotonNetwork.PhotonServerSettings = (ServerSettings)Resources.Load(PhotonNetwork. ← serverSettingsAssetFile, typeof(ServerSettings)) [static]

Serialized server settings, written by the Setup Wizard for use in ConnectUsingSettings.

8.35.3.7 float PhotonNetwork.precisionForFloatSynchronization = 0.01f [static]

The minimum difference between floats before we send it via a PhotonView's OnSerialize/ObservingComponent.

8.35.3.8 float PhotonNetwork.precisionForQuaternionSynchronization = 1.0f [static]

The minimum angle that a rotation needs to change before we send it via a PhotonView's OnSerialize/Observing← Component.

8.35.3.9 float PhotonNetwork.precisionForVectorSynchronization = 0.000099f [static]

The minimum difference that a Vector2 or Vector3(e.g. a transforms rotation) needs to change before we send it via a PhotonView's OnSerialize/ObservingComponent.

Note that this is the sqrMagnitude. E.g. to send only after a 0.01 change on the Y-axix, we use 0.01f*0.01f=0.0001f. As a remedy against float inaccuracy we use 0.000099f instead of 0.0001f.

8.35.3.10 Dictionary < string, GameObject > PhotonNetwork.PrefabCache = new Dictionary < string, GameObject > () [static]

Keeps references to GameObjects for frequent instantiation (out of memory instead of loading the Resources).

You should be able to modify the cache anytime you like, except while Instantiate is used. Best do it only in the main-Thread.

8.35.3.11 HashSet < GameObject > PhotonNetwork.SendMonoMessageTargets [static]

If not null, this is the (exclusive) list of GameObjects that get called by PUN SendMonoMessage().

For all callbacks defined in PhotonNetworkingMessage, PUN will use SendMonoMessage and call FindObjectsOf ← Type() to find all scripts and GameObjects that might want a callback by PUN.

PUN callbacks are not very frequent (in-game, property updates are most frequent) but FindObjectsOfType is time consuming and with a large number of GameObjects, performance might suffer.

Optionally, SendMonoMessageTargets can be used to supply a list of target GameObjects. This skips the Find ObjectsOfType() but any GameObject that needs callbacks will have to Add itself to this list.

If null, the default behaviour is to do a SendMessage on each GameObject with a MonoBehaviour.

8.35.3.12 Type PhotonNetwork.SendMonoMessageTargetType = typeof(MonoBehaviour) [static]

Defines which classes can contain PUN Callback implementations.

This provides the option to optimize your runtime for speed.

The more specific this Type is, the fewer classes will be checked with reflection for callback methods.

8.35.3.13 bool PhotonNetwork.StartRpcsAsCoroutine = true [static]

Can be used to skip starting RPCs as Coroutine, which can be a performance issue.

```
8.35.3.14 bool PhotonNetwork.UsePrefabCache = true [static]
```

While enabled (true), Instantiate uses PhotonNetwork.PrefabCache to keep game objects in memory (improving instantiation of the same prefab).

Setting UsePrefabCache to false during runtime will not clear PrefabCache but will ignore it right away. You could clean and modify the cache yourself. Read its comments.

```
8.35.3.15 bool PhotonNetwork.UseRpcMonoBehaviourCache [static]
```

While enabled, the MonoBehaviours on which we call RPCs are cached, avoiding costly GetComponents<Mono← Behaviour>() calls.

RPCs are called on the MonoBehaviours of a target PhotonView. Those have to be found via GetComponents.

When set this to true, the list of MonoBehaviours gets cached in each PhotonView. You can use photonView. \leftarrow RefreshRpcMonoBehaviourCache() to manually refresh a PhotonView's list of MonoBehaviours on demand (when a new MonoBehaviour gets added to a networked GameObject, e.g.).

```
8.35.3.16 const string PhotonNetwork.versionPUN = "1.99"
```

Version number of PUN. Also used in GameVersion to separate client version from each other.

8.35.4 Property Documentation

```
8.35.4.1 AuthenticationValues PhotonNetwork.AuthValues [static], [get], [set]
```

A user's authentication values used during connect.

Set these before calling Connect if you want custom authentication. These values set the userld, if and how that userld gets verified (server-side), etc..

If authentication fails for any values, PUN will call your implementation of OnCustomAuthenticationFailed(string debugMsg). See: PhotonNetworkingMessage.OnCustomAuthenticationFailed

```
8.35.4.2 bool PhotonNetwork.autoCleanUpPlayerObjects [static], [get], [set]
```

This setting defines per room, if network-instantiated GameObjects (with PhotonView) get cleaned up when the creator of it leaves.

This setting is done per room. It can't be changed in the room and it will override the settings of individual clients.

If room.AutoCleanUp is enabled in a room, the PUN clients will destroy a player's GameObjects on leave. This includes GameObjects manually instantiated (via RPCs, e.g.). When enabled, the server will clean RPCs, instantiated GameObjects and PhotonViews of the leaving player, too. and Players who join after someone left, won't get the events of that player anymore.

Under the hood, this setting is stored as a Custom Room Property. Enabled by default.

```
8.35.4.3 bool PhotonNetwork.autoJoinLobby [static], [get], [set]
```

Set in PhotonServerSettings asset. Defines if the PhotonNetwork should join the "lobby" when connected to the Master server.

If this is false, OnConnectedToMaster() will be called when connection to the Master is available. OnJoinedLobby() will NOT be called if this is false.

Enabled by default.

The room listing will not become available. Rooms can be created and joined (randomly) without joining the lobby (and getting sent the room list).

```
8.35.4.4 bool PhotonNetwork.automaticallySyncScene [static], [get], [set]
```

Defines if all clients in a room should load the same level as the Master Client (if that used PhotonNetwork.Load ← Level).

To synchronize the loaded level, the Master Client should use PhotonNetwork.LoadLevel. All clients will load the new scene when they get the update or when they join.

Internally, a Custom Room Property is set for the loaded scene. When a client reads that and is not in the same scene yet, it will immediately pause the Message Queue (PhotonNetwork.isMessageQueueRunning = false) and load. When the scene finished loading, PUN will automatically re-enable the Message Queue.

```
8.35.4.5 CloudRegionCode PhotonNetwork.CloudRegion [static], [get]
```

Currently used Cloud Region (if any). As long as the client is not on a Master Server or Game Server, the region is not yet defined.

```
8.35.4.6 bool PhotonNetwork.connected [static], [get]
```

False until you connected to Photon initially. True in offline mode, while connected to any server and even while switching servers.

```
8.35.4.7 bool PhotonNetwork.connectedAndReady [static], [get]
```

A refined version of connected which is true only if your connection to the server is ready to accept operations like join, leave, etc.

```
8.35.4.8 bool PhotonNetwork.connecting [static], [get]
```

True when you called ConnectUsingSettings (or similar) until the low level connection to Photon gets established.

```
8.35.4.9 ConnectionState PhotonNetwork.connectionState [static], [get]
```

Simplified connection state

```
8.35.4.10 ClientState PhotonNetwork.connectionStateDetailed [static], [get]
```

Detailed connection state (ignorant of PUN, so it can be "disconnected" while switching servers).

In OfflineMode, this is ClientState.Joined (after create/join) or it is ConnectedToMaster in all other cases.

```
8.35.4.11 int PhotonNetwork.countOfPlayers [static], [get]
```

The count of players currently using this application (available on MasterServer in 5sec intervals).

```
8.35.4.12 int PhotonNetwork.countOfPlayersInRooms [static], [get]
```

Count of users currently playing your app in some room (sent every 5sec by Master Server). Use PhotonNetwork.

playerList.Length or PhotonNetwork.room.PlayerCount to get the count of players in the room you're in!

```
8.35.4.13 int PhotonNetwork.countOfPlayersOnMaster [static], [get]
```

The count of players currently looking for a room (available on MasterServer in 5sec intervals).

```
8.35.4.14 int PhotonNetwork.countOfRooms [static], [get]
```

The count of rooms currently in use (available on MasterServer in 5sec intervals).

While inside the lobby you can also check the count of listed rooms as: PhotonNetwork.GetRoomList().Length. Since PUN v1.25 this is only based on the statistic event Photon sends (counting all rooms).

```
8.35.4.15 bool PhotonNetwork.CrcCheckEnabled [static], [get], [set]
```

Crc checks can be useful to detect and avoid issues with broken datagrams. Can be enabled while not connected.

```
8.35.4.16 bool PhotonNetwork.EnableLobbyStatistics [static], [get], [set]
```

Set in PhotonServerSettings asset. Enable to get a list of active lobbies from the Master Server.

Lobby Statistics can be useful if a game uses multiple lobbies and you want to show activity of each to players.

This value is stored in PhotonServerSettings.

PhotonNetwork.LobbyStatistics is updated when you connect to the Master Server. There is also a callback Pun

Behaviour.

```
8.35.4.17 List<FriendInfo> PhotonNetwork.Friends [static], [get], [set]
```

Read-only list of friends, their online status and the room they are in. Null until initialized by a FindFriends call.

Do not modify this list! It is internally handled by FindFriends and only available to read the values. The value of FriendListAge tells you how old the data is in milliseconds.

Don't get this list more often than useful (> 10 seconds). In best case, keep the list you fetch really short. You could (e.g.) get the full list only once, then request a few updates only for friends who are online. After a while (e.g. 1 minute), you can get the full list again (to update online states).

```
8.35.4.18 int PhotonNetwork.FriendsListAge [static], [get]
```

Age of friend list info (in milliseconds). It's 0 until a friend list is fetched.

```
8.35.4.19 string PhotonNetwork.gameVersion [static], [get], [set]
```

Version string for your this build. Can be used to separate incompatible clients. Sent during connect.

This is only sent when you connect so that is also the place you set it usually (e.g. in ConnectUsingSettings).

```
8.35.4.20 bool PhotonNetwork.inRoom [static], [get]
```

Is true while being in a room (connectionStateDetailed == ClientState.Joined).

Many actions can only be executed in a room, like Instantiate or Leave, etc. You can join a room in offline mode, too.

8.35.4.21 bool PhotonNetwork.insideLobby [static], [get]

True while this client is in a lobby.

Implement IPunCallbacks.OnReceivedRoomListUpdate() for a notification when the list of rooms becomes available or updated.

You are automatically leaving any lobby when you join a room! Lobbies only exist on the Master Server (whereas rooms are handled by Game Servers).

8.35.4.22 bool PhotonNetwork.isMasterClient [static], [get]

Are we the master client?

8.35.4.23 bool PhotonNetwork.isMessageQueueRunning [static], [get], [set]

Can be used to pause dispatching of incoming evtents (RPCs, Instantiates and anything else incoming).

While IsMessageQueueRunning == false, the OnPhotonSerializeView calls are not done and nothing is sent by a client. Also, incoming messages will be queued until you re-activate the message queue.

This can be useful if you first want to load a level, then go on receiving data of PhotonViews and RPCs. The client will go on receiving and sending acknowledgements for incoming packages and your RPCs/Events. This adds "lag" and can cause issues when the pause is longer, as all incoming messages are just queued.

8.35.4.24 bool PhotonNetwork.isNonMasterClientInRoom [static], [get]

True if we are in a room (client) and NOT the room's masterclient

8.35.4.25 TypedLobby PhotonNetwork.lobby [static], [get], [set]

The lobby that will be used when PUN joins a lobby or creates a game.

The default lobby uses an empty string as name. PUN will enter a lobby on the Master Server if autoJoinLobby is set to true. So when you connect or leave a room, PUN automatically gets you into a lobby again.

Check PhotonNetwork.insideLobby if the client is in a lobby. (Master Server And Lobby)

```
8.35.4.26 List<TypedLobbyInfo> PhotonNetwork.LobbyStatistics [static], [get], [set]
```

If turned on, the Master Server will provide information about active lobbies for this application.

Lobby Statistics can be useful if a game uses multiple lobbies and you want to show activity of each to players. Per lobby, you get: name, type, room- and player-count.

PhotonNetwork.LobbyStatistics is updated when you connect to the Master Server. There is also a callback Pun← Behaviour.OnLobbyStatisticsUpdate, which you should implement to update your UI (e.g.).

Lobby Statistics are not turned on by default. Enable them in the PhotonServerSettings file of the project.

8.35.4.27 PhotonPlayer PhotonNetwork.masterClient [static], [get]

The Master Client of the current room or null (outside of rooms).

Can be used as "authoritative" client/player to make descisions, run Al or other.

If the current Master Client leaves the room (leave/disconnect), the server will quickly assign someone else. If the current Master Client times out (closed app, lost connection, etc), messages sent to this client are effectively lost for the others! A timeout can take 10 seconds in which no Master Client is active.

Implement the method IPunCallbacks.OnMasterClientSwitched to be called when the Master Client switched.

Use PhotonNetwork.SetMasterClient, to switch manually to some other player / client.

With offlineMode == true, this always returns the PhotonNetwork.player.

```
8.35.4.28 int PhotonNetwork.MaxResendsBeforeDisconnect [static], [get], [set]
```

Defines the number of times a reliable message can be resent before not getting an ACK for it will trigger a disconnect. Default: 5.

Less resends mean quicker disconnects, while more can lead to much more lag without helping. Min: 3. Max: 10.

```
8.35.4.29 bool PhotonNetwork.NetworkStatisticsEnabled [static], [get], [set]
```

Enables or disables the collection of statistics about this client's traffic.

If you encounter issues with clients, the traffic stats are a good starting point to find solutions. Only with enabled stats, you can use GetVitalStats

```
8.35.4.30 bool PhotonNetwork.offlineMode [static], [get], [set]
```

Offline mode can be set to re-use your multiplayer code in singleplayer game modes. When this is on Photon Network will not create any connections and there is near to no overhead. Mostly usefull for reusing RPC's and PhotonNetwork.Instantiate

```
8.35.4.31 PhotonPlayer[]PhotonNetwork.otherPlayers [static], [get]
```

The list of players in the current room, excluding the local player.

This list is only valid, while the client is in a room. It automatically gets updated when someone joins or leaves.

This can be used to list all other players in a room. Each player's PhotonPlayer.customProperties are accessible (set and synchronized via PhotonPlayer.SetCustomProperties).

You can use a PhotonPlayer.TagObject to store an arbitrary object for reference. That is not synchronized via the network.

```
8.35.4.32 int PhotonNetwork.PacketLossByCrcCheck [static], [get]
```

If CrcCheckEnabled, this counts the incoming packages that don't have a valid CRC checksum and got rejected.

```
8.35.4.33 PhotonPlayer PhotonNetwork.player [static], [get]
```

The local PhotonPlayer. Always available and represents this player. CustomProperties can be set before entering a room and will be synced as well.

```
8.35.4.34 PhotonPlayer[]PhotonNetwork.playerList [static], [get]
```

The list of players in the current room, including the local player.

This list is only valid, while the client is in a room. It automatically gets updated when someone joins or leaves.

This can be used to list all players in a room. Each player's PhotonPlayer.customProperties are accessible (set and synchronized via PhotonPlayer.SetCustomProperties).

You can use a PhotonPlayer.TagObject to store an arbitrary object for reference. That is not synchronized via the network.

```
8.35.4.35 string PhotonNetwork.playerName [static], [get], [set]
```

Set to synchronize the player's nickname with everyone in the room(s) you enter. This sets PhotonNetwork.player. \leftarrow NickName.

The playerName is just a nickname and does not have to be unique or backed up with some account.

Set the value any time (e.g. before you connect) and it will be available to everyone you play with.

Access the names of players by: PhotonPlayer.NickName.

PhotonNetwork.otherPlayers is a list of other players - each contains the playerName the remote player set.

```
8.35.4.36 IPunPrefabPool PhotonNetwork.PrefabPool [static], [get], [set]
```

An Object Pool can be used to keep and reuse instantiated object instances. It replaced Unity's default Instantiate and Destroy methods.

To use a GameObject pool, implement IPunPrefabPool and assign it here. Prefabs are identified by name.

```
8.35.4.37 int PhotonNetwork.QuickResends [static], [get], [set]
```

In case of network loss, reliable messages can be repeated quickly up to 3 times.

When reliable messages get lost more than once, subsequent repeats are delayed a bit to allow the network to recover.

With this option, the repeats 2 and 3 can be sped up. This can help avoid timeouts but also it increases the speed in which gaps are closed.

When you set this, increase PhotonNetwork.MaxResendsBeforeDisconnect to 6 or 7.

```
8.35.4.38 int PhotonNetwork.ResentReliableCommands [static], [get]
```

Count of commands that got repeated (due to local repeat-timing before an ACK was received).

If this value increases a lot, there is a good chance that a timeout disconnect will happen due to bad conditions.

```
8.35.4.39 Room PhotonNetwork.room [static], [get]
```

Get the room we're currently in. Null if we aren't in any room.

```
8.35.4.40 int PhotonNetwork.sendRate [static], [get], [set]
```

Defines how many times per second PhotonNetwork should send a package. If you change this, do not forget to also change 'sendRateOnSerialize'.

Less packages are less overhead but more delay. Setting the sendRate to 50 will create up to 50 packages per second (which is a lot!). Keep your target platform in mind: mobile networks are slower and less reliable.

```
8.35.4.41 int PhotonNetwork.sendRateOnSerialize [static], [get], [set]
```

Defines how many times per second OnPhotonSerialize should be called on PhotonViews.

Choose this value in relation to PhotonNetwork.sendRate. OnPhotonSerialize will create updates and messages to be sent.

A lower rate takes up less performance but will cause more lag.

```
8.35.4.42 ServerConnection PhotonNetwork.Server [static], [get]
```

The server (type) this client is currently connected or connecting to.

Photon uses 3 different roles of servers: Name Server, Master Server and Game Server.

```
8.35.4.43 string PhotonNetwork.ServerAddress [static], [get]
```

Currently used server address (no matter if master or game server).

```
8.35.4.44 int PhotonNetwork.ServerTimestamp [static], [get]
```

The current server's millisecond timestamp.

This can be useful to sync actions and events on all clients in one room.

It will overflow from a positive to a negative value every so often, so be careful to use only time-differences to check the time delta when things happen.

This is the basis for PhotonNetwork.time.

```
8.35.4.45 double PhotonNetwork.time [static], [get]
```

Photon network time, synched with the server.

v1.55

This time value depends on the server's Environment.TickCount. It is different per server but inside a Room, all clients should have the same value (Rooms are on one server only).

This is not a DateTime!

Use this value with care:

It can start with any positive value.

It will "wrap around" from 4294967.295 to 0!

```
8.35.4.46 bool PhotonNetwork.UseAlternativeUdpPorts [static], [get], [set]
```

Switch to alternative ports for a UDP connection to the Public Cloud.

This should be used when a customer has issues with connection stability. Some players reported better connectivity for Steam games. The effect might vary, which is why the alternative ports are not the new default.

The alternative (server) ports are 27000 up to 27003.

The values are appplied by replacing any incoming server-address string accordingly. You only need to set this to true though.

This value does not affect TCP or WebSocket connections.

8.35.5 Event Documentation

```
8.35.5.1 EventCallback PhotonNetwork.OnEventCall [static]
```

Register your RaiseEvent handling methods here by using "+=".

Any eventCode < 200 will be forwarded to your delegate(s).

RaiseEvent

8.36 Photon.Realtime.PhotonPing Class Reference

Inherits IDisposable.

Inherited by Photon.Realtime.PingMono, and PingMonoEditor.

Public Member Functions

- virtual bool StartPing (string ip)
- virtual bool Done ()
- virtual void Dispose ()

Public Attributes

- string DebugString = ""
- · bool Successful

8.36.1 Member Function Documentation

```
8.36.1.1 virtual void Photon.Realtime.PhotonPing.Dispose() [virtual]
```

Reimplemented in Photon.Realtime.PingMono, and PingMonoEditor.

```
8.36.1.2 virtual bool Photon.Realtime.PhotonPing.Done() [virtual]
```

Reimplemented in Photon.Realtime.PingMono, and PingMonoEditor.

```
8.36.1.3 virtual bool Photon.Realtime.PhotonPing.StartPing ( string ip ) [virtual]
```

Reimplemented in Photon.Realtime.PingMono, and PingMonoEditor.

8.36.2 Member Data Documentation

- 8.36.2.1 string Photon.Realtime.PhotonPing.DebugString = ""
- 8.36.2.2 bool Photon.Realtime.PhotonPing.Successful

8.37 PhotonPingManager Class Reference

Public Member Functions

• IEnumerator PingSocket (Region region)

Static Public Member Functions

static string ResolveHost (string hostName)
 Attempts to resolve a hostname into an IP string or returns empty string if that fails.

Public Attributes

bool UseNative

Static Public Attributes

- static int Attempts = 5
- static bool IgnoreInitialAttempt = true
- static int MaxMilliseconsPerPing = 800

Properties

- Region BestRegion [get]
- bool Done [get]

8.37.1 Member Function Documentation

8.37.1.1 IEnumerator PhotonPingManager.PingSocket (Region region)

Affected by frame-rate of app, as this Coroutine checks the socket for a result once per frame.

8.37.1.2 static string PhotonPingManager.ResolveHost (string hostName) [static]

Attempts to resolve a hostname into an IP string or returns empty string if that fails.

To be compatible with most platforms, the address family is checked like this: if (ipAddress.AddressFamily.To ← String().Contains("6")) // ipv6...

Parameters

hostNam	e Hostname to resolve.	

Returns

IP string or empty string if resolution fails

8.37.2 Member Data Documentation

- **8.37.2.1** int PhotonPingManager.Attempts = 5 [static]
- **8.37.2.2** bool PhotonPingManager.lgnoreInitialAttempt = true [static]
- **8.37.2.3** int PhotonPingManager.MaxMilliseconsPerPing = 800 [static]
- 8.37.2.4 bool PhotonPingManager.UseNative

8.37.3 Property Documentation

- 8.37.3.1 Region PhotonPingManager.BestRegion [get]
- **8.37.3.2** bool PhotonPingManager.Done [get]

8.38 PhotonPlayer Class Reference

Summarizes a "player" within a room, identified (in that room) by actorID.

Public Member Functions

PhotonPlayer (bool isLocal, int actorID, string name)

Creates a PhotonPlayer instance.

override bool Equals (object p)

Makes PhotonPlayer comparable

- · override int GetHashCode ()

Updates the this player's Custom Properties with new/updated key-values.

- · PhotonPlayer Get (int id)
- PhotonPlayer GetNext ()
- PhotonPlayer GetNextFor (PhotonPlayer currentPlayer)
- PhotonPlayer GetNextFor (int currentPlayerId)
- int CompareTo (PhotonPlayer other)
- int CompareTo (int other)
- bool Equals (PhotonPlayer other)
- bool Equals (int other)
- override string ToString ()

Brief summary string of the PhotonPlayer. Includes name or player.ID and if it's the Master Client.

string ToStringFull ()

String summary of the PhotonPlayer: player.ID, name and all custom properties of this user.

Static Public Member Functions

static PhotonPlayer Find (int ID)

Try to get a specific player by id.

Public Attributes

• readonly bool IsLocal = false

Only one player is controlled by each client. Others are not local.

object TagObject

Can be used to store a reference that's useful to know "by player".

Properties

• int ID [get]

This player's actorID

• string NickName [get, set]

Nickname of this player.

• string UserId [get, set]

UserId of the player, available when the room got created with RoomOptions.PublishUserId = true.

• bool IsMasterClient [get]

True if this player is the Master Client of the current room.

• bool Islnactive [get, set]

Players might be inactive in a room when PlayerTTL for a room is > 0. If true, the player is not getting events from this room (now) but can return later.

• Hashtable CustomProperties [get, set]

Read-only cache for custom properties of player. Set via PhotonPlayer.SetCustomProperties.

• Hashtable AllProperties [get]

Creates a Hashtable with all properties (custom and "well known" ones).

- string name [get, set]
- string userId [get, set]
- boolisLocal [get]
- bool isMasterClient [get]
- boolisInactive [get, set]
- Hashtable customProperties [get, set]
- Hashtable allProperties [get]

8.38.1 Detailed Description

Summarizes a "player" within a room, identified (in that room) by actorID.

Each player has an actorId (or ID), valid for that room. It's -1 until it's assigned by server. Each client can set it's player's custom properties with SetCustomProperties, even before being in a room. They are synced when joining a room.

8.38.2 Constructor & Destructor Documentation

8.38.2.1 PhotonPlayer.PhotonPlayer (bool isLocal, int actorID, string name)

Creates a PhotonPlayer instance.

Parameters

isLocal	If this is the local peer's player (or a remote one).
actorID	ID or ActorNumber of this player in the current room (a shortcut to identify each player in
	room)
name	Name of the player (a "well known property").

8.38.3 Member Function Documentation

```
8.38.3.1 int PhotonPlayer.CompareTo ( PhotonPlayer other )
```

8.38.3.2 int PhotonPlayer.CompareTo (int other)

8.38.3.3 override bool PhotonPlayer.Equals (object p)

Makes PhotonPlayer comparable

8.38.3.4 bool PhotonPlayer.Equals (PhotonPlayer other)

8.38.3.5 bool PhotonPlayer.Equals (int other)

 $\textbf{8.38.3.6} \quad \textbf{static PhotonPlayer PhotonPlayer.Find (int \textit{ID})} \quad \texttt{[static]}$

Try to get a specific player by id.

Parameters

ID	ActorID

Returns

The player with matching actorID or null, if the actorID is not in use.

8.38.3.7	PhotonPlayer PhotonPlayer.Get (int id)
8.38.3.8	override int PhotonPlayer.GetHashCode ()
8.38.3.9	PhotonPlayer PhotonPlayer.GetNext ()
8.38.3.10	PhotonPlayer PhotonPlayer.GetNextFor (PhotonPlayer currentPlayer)
8.38.3.11	PhotonPlayer PhotonPlayer.GetNextFor (int currentPlayerId)
8.38.3.12	<pre>void PhotonPlayer.SetCustomProperties (Hashtable propertiesToSet, Hashtable expectedValues = null, bool webForward = false)</pre>

Updates the this player's Custom Properties with new/updated key-values.

Custom Properties are a key-value set (Hashtable) which is available to all players in a room. They can relate to the room or individual players and are useful when only the current value of something is of interest. For example: The map of a room. All keys must be strings.

The Room and the PhotonPlayer class both have SetCustomProperties methods. Also, both classes offer access to current key-values by: customProperties.

Always use SetCustomProperties to change values. To reduce network traffic, set only values that actually changed. New properties are added, existing values are updated. Other values will not be changed, so only provide values that changed or are new.

To delete a named (custom) property of this room, use null as value.

Locally, SetCustomProperties will update it's cache without delay. Other clients are updated through Photon (the server) with a fitting operation.

Check and Swap

SetCustomProperties have the option to do a server-side Check-And-Swap (CAS): Values only get updated if the expected values are correct. The expectedValues can be different key/values than the propertiesToSet. So you can check some key and set another key's value (if the check succeeds).

If the client's knowledge of properties is wrong or outdated, it can't set values with CAS. This can be useful to keep players from concurrently setting values. For example: If all players try to pickup some card or item, only one should get it. With CAS, only the first SetProperties gets executed server-side and any other (sent at the same time) fails.

The server will broadcast successfully changed values and the local "cache" of customProperties only gets updated after a roundtrip (if anything changed).

You can do a "webForward": Photon will send the changed properties to a WebHook defined for your application.

OfflineMode

While PhotonNetwork.offlineMode is true, the expectedValues and webForward parameters are ignored. In Offline ← Mode, the local customProperties values are immediately updated (without the roundtrip).

Parameters

propertiesToSet	The new properties to be set.
expectedValues	At least one property key/value set to check server-side. Key and value must be correct.
	Ignored in OfflineMode.
webForward	Set to true, to forward the set properties to a WebHook, defined for this app (in Dashboard). Ignored in OfflineMode.
	ignored in Chillie Mode.

8.38.3.13 override string PhotonPlayer.ToString ()

Brief summary string of the PhotonPlayer. Includes name or player.ID and if it's the Master Client.

```
8.38.3.14 string PhotonPlayer.ToStringFull ( )
```

String summary of the PhotonPlayer: player.ID, name and all custom properties of this user.

Use with care and not every frame! Converts the customProperties to a String on every single call.

8.38.4 Member Data Documentation

```
8.38.4.1 readonly bool PhotonPlayer.IsLocal = false
```

Only one player is controlled by each client. Others are not local.

```
8.38.4.2 object PhotonPlayer.TagObject
```

Can be used to store a reference that's useful to know "by player".

Example: Set a player's character as Tag by assigning the GameObject on Instantiate.

8.38.5 Property Documentation

```
8.38.5.1 Hashtable PhotonPlayer.AllProperties [get]
```

Creates a Hashtable with all properties (custom and "well known" ones).

If used more often, this should be cached.

```
8.38.5.2 Hashtable PhotonPlayer.allProperties [get]
```

```
8.38.5.3 Hashtable PhotonPlayer.CustomProperties [get], [set]
```

Read-only cache for custom properties of player. Set via PhotonPlayer.SetCustomProperties.

Don't modify the content of this Hashtable. Use SetCustomProperties and the properties of this class to modify values. When you use those, the client will sync values with the server.

SetCustomProperties

```
8.38.5.4 Hashtable PhotonPlayer.customProperties [get], [set]
```

```
8.38.5.5 int PhotonPlayer.ID [get]
```

This player's actorID

```
8.38.5.6 bool PhotonPlayer.Islnactive [get], [set]
```

Players might be inactive in a room when PlayerTTL for a room is > 0. If true, the player is not getting events from this room (now) but can return later.

```
8.38.5.7 bool PhotonPlayer.islnactive [get], [set]
```

8.38.5.8 bool PhotonPlayer.isLocal [get]

8.38.5.9 bool PhotonPlayer.IsMasterClient [get]

True if this player is the Master Client of the current room.

See also: PhotonNetwork.masterClient.

```
8.38.5.10 bool PhotonPlayer.isMasterClient [get]
8.38.5.11 string PhotonPlayer.name [get], [set]
8.38.5.12 string PhotonPlayer.NickName [get], [set]
```

Nickname of this player.

Set the PhotonNetwork.playerName to make the name synchronized in a room.

```
8.38.5.13 string PhotonPlayer.UserId [get], [set]
```

UserId of the player, available when the room got created with RoomOptions.PublishUserId = true.

Useful for PhotonNetwork.FindFriends and blocking slots in a room for expected players (e.g. in PhotonNetwork.↔ CreateRoom).

```
8.38.5.14 string PhotonPlayer.userId [get], [set]
```

8.39 PhotonRigidbody2DView Class Reference

This class helps you to synchronize the velocities of a 2d physics RigidBody. Note that only the velocities are synchronized and because Unitys physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a PhotonTransformView to synchronize the position. Simply add the component to your GameObject and make sure that the PhotonRigidbody2DView is added to the list of observed components

Inherits MonoBehaviour, and IPunObservable.

Public Member Functions

void OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)
 Called by PUN several times per second, so that your script can write and read synchronization data for the Photon
 View.

8.39.1 Detailed Description

This class helps you to synchronize the velocities of a 2d physics RigidBody. Note that only the velocities are synchronized and because Unitys physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a PhotonTransformView to synchronize the position. Simply add the component to your GameObject and make sure that the PhotonRigidbody2DView is added to the list of observed components

8.39.2 Member Function Documentation

8.39.2.1 void PhotonRigidbody2DView.OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the Photon⊷ View.

This method will be called in scripts that are assigned as Observed component of a PhotonView. PhotonNetwork.sendRateOnSerialize affects how often this method is called. PhotonNetwork.sendRate affects how often packages are sent by this client.

Implementing this method, you can customize which data a PhotonView regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView only gets called when it is assigned to a PhotonView* as Photon
✓ View.observed script.

To make use of this method, the PhotonStream is essential. It will be in "writing" mode" on the client that controls a PhotonView (PhotonStream.isWriting == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that OnPhotonSerializeView is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implements IPunObservable.

8.40 PhotonRigidbodyView Class Reference

This class helps you to synchronize the velocities of a physics RigidBody. Note that only the velocities are synchronized and because Unitys physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a PhotonTransformView to synchronize the position. Simply add the component to your GameObject and make sure that the PhotonRigidbodyView is added to the list of observed components

Inherits MonoBehaviour, and IPunObservable.

Public Member Functions

void OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)
 Called by PUN several times per second, so that your script can write and read synchronization data for the Photon
 View.

8.40.1 Detailed Description

This class helps you to synchronize the velocities of a physics RigidBody. Note that only the velocities are synchronized and because Unitys physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a PhotonTransformView to synchronize the position. Simply add the component to your GameObject and make sure that the PhotonRigidbodyView is added to the list of observed components

8.40.2 Member Function Documentation

8.40.2.1 void PhotonRigidbodyView.OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the Photon⊷ View.

This method will be called in scripts that are assigned as Observed component of a PhotonView. PhotonNetwork.sendRateOnSerialize affects how often this method is called.

PhotonNetwork.sendRate affects how often packages are sent by this client.

Implementing this method, you can customize which data a PhotonView regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView only gets called when it is assigned to a PhotonView* as Photon
✓ View.observed script.

To make use of this method, the PhotonStream is essential. It will be in "writing" mode" on the client that controls a PhotonView (PhotonStream.isWriting == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that OnPhotonSerializeView is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implements IPunObservable.

8.41 PhotonStatsGui Class Reference

Basic GUI to show traffic and health statistics of the connection to Photon, toggled by shift+tab. Inherits MonoBehaviour.

Public Member Functions

- void Start ()
- · void Update ()

Checks for shift+tab input combination (to toggle statsOn).

- · void OnGUI ()
- void TrafficStatsWindow (int windowID)

Public Attributes

• bool statsWindowOn = true

Shows or hides GUI (does not affect if stats are collected).

• bool statsOn = true

Option to turn collecting stats on or off (used in Update()).

· bool healthStatsVisible

Shows additional "health" values of connection.

bool trafficStatsOn

Shows additional "lower level" traffic stats.

bool buttonsOn

Show buttons to control stats and reset them.

• Rect statsRect = new Rect(0, 100, 200, 50)

Positioning rect for window.

• int Windowld = 100

Unity GUI Window ID (must be unique or will cause issues).

8.41.1 Detailed Description

Basic GUI to show traffic and health statistics of the connection to Photon, toggled by shift+tab.

The shown health values can help identify problems with connection losses or performance. Example: If the time delta between two consecutive SendOutgoingCommands calls is a second or more, chances rise for a disconnect being caused by this (because acknowledgements to the server need to be sent in due time).

```
8.41.2 Member Function Documentation
8.41.2.1 void PhotonStatsGui.OnGUI ( )
8.41.2.2 void PhotonStatsGui.Start ( )
8.41.2.3 void PhotonStatsGui.TrafficStatsWindow (int windowID)
8.41.2.4 void PhotonStatsGui.Update ( )
Checks for shift+tab input combination (to toggle statsOn).
8.41.3 Member Data Documentation
8.41.3.1 bool PhotonStatsGui.buttonsOn
Show buttons to control stats and reset them.
8.41.3.2 bool PhotonStatsGui.healthStatsVisible
Shows additional "health" values of connection.
8.41.3.3 bool PhotonStatsGui.statsOn = true
Option to turn collecting stats on or off (used in Update()).
8.41.3.4 Rect PhotonStatsGui.statsRect = new Rect(0, 100, 200, 50)
Positioning rect for window.
8.41.3.5 bool PhotonStatsGui.statsWindowOn = true
Shows or hides GUI (does not affect if stats are collected).
8.41.3.6 bool PhotonStatsGui.trafficStatsOn
Shows additional "lower level" traffic stats.
8.41.3.7 int PhotonStatsGui.Windowld = 100
```

Unity GUI Window ID (must be unique or will cause issues).

8.42 PhotonStream Class Reference

This container is used in OnPhotonSerializeView() to either provide incoming data of a PhotonView or for you to provide it.

Public Member Functions

• PhotonStream (bool write, object[] incomingData)

Creates a stream and initializes it. Used by PUN internally.

- void SetReadStream (object[] incomingData, byte pos=0)
- object ReceiveNext ()

Read next piece of data from the stream when isReading is true.

• object PeekNext ()

Read next piece of data from the stream without advancing the "current" item.

void SendNext (object obj)

Add another piece of data to send it when is Writing is true.

object[] ToArray ()

Turns the stream into a new object[].

void Serialize (ref bool myBool)

Will read or write the value, depending on the stream's isWriting value.

• void Serialize (ref int myInt)

Will read or write the value, depending on the stream's isWriting value.

void Serialize (ref string value)

Will read or write the value, depending on the stream's isWriting value.

void Serialize (ref char value)

Will read or write the value, depending on the stream's isWriting value.

• void Serialize (ref short value)

Will read or write the value, depending on the stream's isWriting value.

• void Serialize (ref float obj)

Will read or write the value, depending on the stream's isWriting value.

void Serialize (ref PhotonPlayer obj)

Will read or write the value, depending on the stream's isWriting value.

• void Serialize (ref Vector3 obj)

Will read or write the value, depending on the stream's isWriting value.

• void Serialize (ref Vector2 obj)

Will read or write the value, depending on the stream's isWriting value.

void Serialize (ref Quaternion obj)

Will read or write the value, depending on the stream's isWriting value.

Properties

• bool isWriting [get]

If true, this client should add data to the stream to send it.

• bool isReading [get]

If true, this client should read data send by another client.

• int Count [get]

Count of items in the stream.

8.42.1 Detailed Description

This container is used in OnPhotonSerializeView() to either provide incoming data of a PhotonView or for you to provide it.

The isWriting property will be true if this client is the "owner" of the PhotonView (and thus the GameObject). Add data to the stream and it's sent via the server to the other players in a room. On the receiving side, isWriting is false and the data should be read.

Send as few data as possible to keep connection quality up. An empty PhotonStream will not be sent.

Use either Serialize() for reading and writing or SendNext() and ReceiveNext(). The latter two are just explicit read and write methods but do about the same work as Serialize(). It's a matter of preference which methods you use.

See also

PhotonNetworkingMessage

```
8.42.2 Constructor & Destructor Documentation
```

8.42.2.1 PhotonStream.PhotonStream (bool write, object[] incomingData)

Creates a stream and initializes it. Used by PUN internally.

8.42.3 Member Function Documentation

```
8.42.3.1 object PhotonStream.PeekNext ( )
```

Read next piece of data from the stream without advancing the "current" item.

```
8.42.3.2 object PhotonStream.ReceiveNext ( )
```

Read next piece of data from the stream when isReading is true.

```
8.42.3.3 void PhotonStream.SendNext (object obj)
```

Add another piece of data to send it when is Writing is true.

```
8.42.3.4 void PhotonStream.Serialize ( ref bool myBool )
```

Will read or write the value, depending on the stream's isWriting value.

```
8.42.3.5 void PhotonStream.Serialize ( ref int myInt )
```

Will read or write the value, depending on the stream's isWriting value.

```
8.42.3.6 void PhotonStream.Serialize ( ref string value )
```

Will read or write the value, depending on the stream's isWriting value.

8.42.3.7 void PhotonStream.Serialize (ref char value)

Will read or write the value, depending on the stream's isWriting value.

```
8.42.3.8 void PhotonStream.Serialize ( ref short value )
Will read or write the value, depending on the stream's isWriting value.
8.42.3.9 void PhotonStream.Serialize ( ref float obj )
Will read or write the value, depending on the stream's isWriting value.
8.42.3.10 void PhotonStream.Serialize ( ref PhotonPlayer obj )
Will read or write the value, depending on the stream's isWriting value.
8.42.3.11 void PhotonStream.Serialize ( ref Vector3 obj )
Will read or write the value, depending on the stream's isWriting value.
8.42.3.12 void PhotonStream.Serialize ( ref Vector2 obj )
Will read or write the value, depending on the stream's isWriting value.
8.42.3.13 void PhotonStream.Serialize (ref Quaternion obj )
Will read or write the value, depending on the stream's isWriting value.
8.42.3.14 void PhotonStream.SetReadStream (object[] incomingData, byte pos = 0)
8.42.3.15 object [] PhotonStream.ToArray ( )
Turns the stream into a new object[].
8.42.4 Property Documentation
8.42.4.1 int PhotonStream.Count [get]
Count of items in the stream.
8.42.4.2 bool PhotonStream.isReading [get]
If true, this client should read data send by another client.
8.42.4.3 bool PhotonStream.isWriting [get]
```

8.43 PhotonStreamQueue Class Reference

If true, this client should add data to the stream to send it.

The PhotonStreamQueue helps you poll object states at higher frequencies then what PhotonNetwork.sendRate dictates and then sends all those states at once when Serialize() is called. On the receiving end you can call Deserialize() and then the stream will roll out the received object states in the same order and timeStep they were recorded in.

Public Member Functions

• PhotonStreamQueue (int sampleRate)

Initializes a new instance of the PhotonStreamQueue class.

· void Reset ()

Resets the PhotonStreamQueue. You need to do this whenever the amount of objects you are observing changes

void SendNext (object obj)

Adds the next object to the queue. This works just like PhotonStream.SendNext

· bool HasQueuedObjects ()

Determines whether the queue has stored any objects

object ReceiveNext ()

Receives the next object from the queue. This works just like PhotonStream.ReceiveNext

void Serialize (PhotonStream stream)

Serializes the specified stream. Call this in your OnPhotonSerializeView method to send the whole recorded stream.

void Deserialize (PhotonStream stream)

Descrializes the specified stream. Call this in your OnPhotonSerializeView method to receive the whole recorded stream.

8.43.1 Detailed Description

The PhotonStreamQueue helps you poll object states at higher frequencies then what PhotonNetwork.sendRate dictates and then sends all those states at once when Serialize() is called. On the receiving end you can call Deserialize() and then the stream will roll out the received object states in the same order and timeStep they were recorded in.

8.43.2 Constructor & Destructor Documentation

8.43.2.1 PhotonStreamQueue.PhotonStreamQueue (int sampleRate)

Initializes a new instance of the PhotonStreamQueue class.

Parameters

sampleRate How many times per second should the object states be sampled

8.43.3 Member Function Documentation

8.43.3.1 void PhotonStreamQueue.Deserialize (PhotonStream stream)

Descrializes the specified stream. Call this in your OnPhotonSerializeView method to receive the whole recorded stream.

Parameters

stream | The PhotonStream you receive as a parameter in OnPhotonSerializeView

8.43.3.2 bool PhotonStreamQueue.HasQueuedObjects ()

Determines whether the queue has stored any objects

8.43.3.3 object PhotonStreamQueue.ReceiveNext ()

Receives the next object from the queue. This works just like PhotonStream.ReceiveNext

Returns

8.43.3.4 void PhotonStreamQueue.Reset ()

Resets the PhotonStreamQueue. You need to do this whenever the amount of objects you are observing changes

8.43.3.5 void PhotonStreamQueue.SendNext (object obj)

Adds the next object to the queue. This works just like PhotonStream.SendNext

Parameters

obj The object you want to add to the queue

8.43.3.6 void PhotonStreamQueue.Serialize (PhotonStream stream)

 $Serializes \ the \ specified \ stream. \ Call \ this \ in \ your \ On Photon Serialize \ View \ method \ to \ send \ the \ whole \ recorded \ stream.$

Parameters

stream | The PhotonStream you receive as a parameter in OnPhotonSerializeView

8.44 PhotonTransformView Class Reference

This class helps you to synchronize position, rotation and scale of a GameObject. It also gives you many different options to make the synchronized values appear smooth, even when the data is only send a couple of times per second. Simply add the component to your GameObject and make sure that the PhotonTransformView is added to the list of observed components

Inherits MonoBehaviour, and IPunObservable.

Public Member Functions

void SetSynchronizedValues (Vector3 speed, float turnSpeed)

These values are synchronized to the remote objects if the interpolation mode or the extrapolation mode SynchronizeValues is used. Your movement script should pass on the current speed (in units/second) and turning speed (in angles/second) so the remote object can use them to predict the objects movement.

void OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the Photon⊷ View.

Public Attributes

- PhotonTransformViewPositionModel m PositionModel = new PhotonTransformViewPositionModel()
- PhotonTransformViewRotationModel m RotationModel = new PhotonTransformViewRotationModel()
- PhotonTransformViewScaleModel m_ScaleModel = new PhotonTransformViewScaleModel()

8.44.1 Detailed Description

This class helps you to synchronize position, rotation and scale of a GameObject. It also gives you many different options to make the synchronized values appear smooth, even when the data is only send a couple of times per second. Simply add the component to your GameObject and make sure that the PhotonTransformView is added to the list of observed components

8.44.2 Member Function Documentation

8.44.2.1 void PhotonTransformView.OnPhotonSerializeView (PhotonStream stream, PhotonMessageInfo info)

Called by PUN several times per second, so that your script can write and read synchronization data for the Photon⊷ View.

This method will be called in scripts that are assigned as Observed component of a PhotonView.

PhotonNetwork.sendRateOnSerialize affects how often this method is called.

PhotonNetwork.sendRate affects how often packages are sent by this client.

Implementing this method, you can customize which data a PhotonView regularly synchronizes. Your code defines what is being sent (content) and how your data is used by receiving clients.

Unlike other callbacks, *OnPhotonSerializeView only gets called when it is assigned to a PhotonView* as Photon
✓ View.observed script.

To make use of this method, the PhotonStream is essential. It will be in "writing" mode" on the client that controls a PhotonView (PhotonStream.isWriting == true) and in "reading mode" on the remote clients that just receive that the controlling client sends.

If you skip writing any value into the stream, PUN will skip the update. Used carefully, this can conserve bandwidth and messages (which have a limit per room/second).

Note that OnPhotonSerializeView is not called on remote clients when the sender does not send any update. This can't be used as "x-times per second Update()".

Implements IPunObservable.

8.44.2.2 void PhotonTransformView.SetSynchronizedValues (Vector3 speed, float turnSpeed)

These values are synchronized to the remote objects if the interpolation mode or the extrapolation mode SynchronizeValues is used. Your movement script should pass on the current speed (in units/second) and turning speed (in angles/second) so the remote object can use them to predict the objects movement.

Parameters

speed	The current movement vector of the object in units/second.
turnSpeed	The current turn speed of the object in angles/second.

8.44.3 Member Data Documentation

- 8.44.3.1 PhotonTransformViewPositionModel PhotonTransformView.m_PositionModel = new PhotonTransformViewPositionModel()
- 8.44.3.2 PhotonTransformViewRotationModel PhotonTransformView.m_RotationModel = new PhotonTransformViewRotationModel()
- 8.44.3.3 PhotonTransformViewScaleModel PhotonTransformView.m_ScaleModel = new PhotonTransformViewScaleModel()

8.45 PhotonTransformViewPositionControl Class Reference

Public Member Functions

- PhotonTransformViewPositionControl (PhotonTransformViewPositionModel model)
- void SetSynchronizedValues (Vector3 speed, float turnSpeed)

These values are synchronized to the remote objects if the interpolation mode or the extrapolation mode SynchronizeValues is used. Your movement script should pass on the current speed (in units/second) and turning speed (in angles/second) so the remote object can use them to predict the objects movement.

Vector3 UpdatePosition (Vector3 currentPosition)

Calculates the new position based on the values setup in the inspector

Vector3 GetNetworkPosition ()

Gets the last position that was received through the network

Vector3 GetExtrapolatedPositionOffset ()

Calculates an estimated position based on the last synchronized position, the time when the last position was received and the movement speed of the object

void OnPhotonSerializeView (Vector3 currentPosition, PhotonStream stream, PhotonMessageInfo info)

8.45.1 Constructor & Destructor Documentation

8.45.1.1 PhotonTransformViewPositionControl.PhotonTransformViewPositionControl (PhotonTransformViewPosition ← Model model)

8.45.2 Member Function Documentation

8.45.2.1 Vector3 PhotonTransformViewPositionControl.GetExtrapolatedPositionOffset ()

Calculates an estimated position based on the last synchronized position, the time when the last position was received and the movement speed of the object

Returns

Estimated position of the remote object

8.45.2.2 Vector3 PhotonTransformViewPositionControl.GetNetworkPosition ()

Gets the last position that was received through the network

Returns

- 8.45.2.3 void PhotonTransformViewPositionControl.OnPhotonSerializeView (Vector3 *currentPosition*, PhotonStream *stream*, PhotonMessageInfo *info*)
- 8.45.2.4 void PhotonTransformViewPositionControl.SetSynchronizedValues (Vector3 speed, float turnSpeed)

These values are synchronized to the remote objects if the interpolation mode or the extrapolation mode SynchronizeValues is used. Your movement script should pass on the current speed (in units/second) and turning speed (in angles/second) so the remote object can use them to predict the objects movement.

Parameters

speed	The current movement vector of the object in units/second.
turnSpeed	The current turn speed of the object in angles/second.

8.45.2.5 Vector3 PhotonTransformViewPositionControl.UpdatePosition (Vector3 currentPosition)

Calculates the new position based on the values setup in the inspector

Parameters

currentPosition	The current position.

Returns

The new position.

8.46 PhotonTransformViewPositionModel Class Reference

Public Types

- enum InterpolateOptions {
 InterpolateOptions.Disabled, InterpolateOptions.FixedSpeed, InterpolateOptions.EstimatedSpeed, Interpolate
 Options.SynchronizeValues,
 InterpolateOptions.Lerp }
- enum ExtrapolateOptions { ExtrapolateOptions.Disabled, ExtrapolateOptions.SynchronizeValues, Extrapolate
 Options.EstimateSpeedAndTurn, ExtrapolateOptions.FixedSpeed }

Public Attributes

- bool SynchronizeEnabled
- bool TeleportEnabled = true
- float TeleportIfDistanceGreaterThan = 3f
- InterpolateOptions InterpolateOption = InterpolateOptions.EstimatedSpeed
- float InterpolateMoveTowardsSpeed = 1f
- float InterpolateLerpSpeed = 1f
- float InterpolateMoveTowardsAcceleration = 2
- float InterpolateMoveTowardsDeceleration = 2
- AnimationCurve InterpolateSpeedCurve
- ExtrapolateOptions ExtrapolateOption = ExtrapolateOptions.Disabled
- float ExtrapolateSpeed = 1f
- bool ExtrapolateIncludingRoundTripTime = true
- int ExtrapolateNumberOfStoredPositions = 1
- bool DrawErrorGizmo = true

8.46.1 Member Enumeration Documentation

8.46.1.1 enum PhotonTransformViewPositionModel.ExtrapolateOptions

Enumerator

Disabled
SynchronizeValues
EstimateSpeedAndTurn
FixedSpeed

8.46.1.2 enum PhotonTransformViewPositionModel.InterpolateOptions

Enumerator

Disabled

FixedSpeed

EstimatedSpeed

Synchronize Values

Lerp

- 8.46.2 Member Data Documentation
- 8.46.2.1 bool PhotonTransformViewPositionModel.DrawErrorGizmo = true
- 8.46.2.2 bool PhotonTransformViewPositionModel.ExtrapolateIncludingRoundTripTime = true
- 8.46.2.3 int PhotonTransformViewPositionModel.ExtrapolateNumberOfStoredPositions = 1
- 8.46.2.4 ExtrapolateOptions PhotonTransformViewPositionModel.ExtrapolateOption = ExtrapolateOptions.Disabled
- 8.46.2.5 float PhotonTransformViewPositionModel.ExtrapolateSpeed = 1f
- 8.46.2.6 float PhotonTransformViewPositionModel.InterpolateLerpSpeed = 1f
- 8.46.2.7 float PhotonTransformViewPositionModel.InterpolateMoveTowardsAcceleration = 2
- 8.46.2.8 float PhotonTransformViewPositionModel.InterpolateMoveTowardsDeceleration = 2
- 8.46.2.9 float PhotonTransformViewPositionModel.InterpolateMoveTowardsSpeed = 1f
- 8.46.2.10 InterpolateOptions PhotonTransformViewPositionModel.InterpolateOption = InterpolateOptions.EstimatedSpeed
- $8.46.2.11 \quad Animation Curve\ Photon Transform View Position Model. Interpolate Speed Curve$

Initial value:

- 8.46.2.12 bool PhotonTransformViewPositionModel.SynchronizeEnabled
- 8.46.2.13 bool PhotonTransformViewPositionModel.TeleportEnabled = true
- 8.46.2.14 float PhotonTransformViewPositionModel.TeleportlfDistanceGreaterThan = 3f

8.47 PhotonTransformViewRotationControl Class Reference

Public Member Functions

- PhotonTransformViewRotationControl (PhotonTransformViewRotationModel model)
- Quaternion GetNetworkRotation ()

Gets the last rotation that was received through the network

- · Quaternion GetRotation (Quaternion currentRotation)
- void OnPhotonSerializeView (Quaternion currentRotation, PhotonStream stream, PhotonMessageInfo info)

8.47.1 Constructor & Destructor Documentation

8.47.1.1 PhotonTransformViewRotationControl.PhotonTransformViewRotationControl (PhotonTransformViewRotation ← Model model)

8.47.2 Member Function Documentation

8.47.2.1 Quaternion PhotonTransformViewRotationControl.GetNetworkRotation ()

Gets the last rotation that was received through the network

Returns

- 8.47.2.2 Quaternion PhotonTransformViewRotationControl.GetRotation (Quaternion currentRotation)
- 8.47.2.3 void PhotonTransformViewRotationControl.OnPhotonSerializeView (Quaternion *currentRotation*, PhotonStream *stream*, PhotonMessageInfo *info*)

8.48 PhotonTransformViewRotationModel Class Reference

Public Types

enum InterpolateOptions { InterpolateOptions.Disabled, InterpolateOptions.RotateTowards, Interpolate
 Options.Lerp }

Public Attributes

- · bool SynchronizeEnabled
- InterpolateOptions InterpolateOption = InterpolateOptions.RotateTowards
- float InterpolateRotateTowardsSpeed = 180
- float InterpolateLerpSpeed = 5

8.48.1 Member Enumeration Documentation

8.48.1.1 enum PhotonTransformViewRotationModel.InterpolateOptions

Enumerator

Disabled

RotateTowards

Lerp

8.48.2 Member Data Documentation

- 8.48.2.1 float PhotonTransformViewRotationModel.InterpolateLerpSpeed = 5
- $8.48.2.2 \quad Interpolate Options \ Photon Transform View Rotation Model. Interpolate Option = Interpolate Options. Rotate Towards and the properties of the$
- 8.48.2.3 float PhotonTransformViewRotationModel.InterpolateRotateTowardsSpeed = 180
- 8.48.2.4 bool PhotonTransformViewRotationModel.SynchronizeEnabled

8.49 PhotonTransformViewScaleControl Class Reference

Public Member Functions

- PhotonTransformViewScaleControl (PhotonTransformViewScaleModel model)
- Vector3 GetNetworkScale ()

Gets the last scale that was received through the network

- Vector3 GetScale (Vector3 currentScale)
- void OnPhotonSerializeView (Vector3 currentScale, PhotonStream stream, PhotonMessageInfo info)

8.49.1 Constructor & Destructor Documentation

8.49.1.1 PhotonTransformViewScaleControl.PhotonTransformViewScaleControl (PhotonTransformViewScaleModel model)

8.49.2 Member Function Documentation

8.49.2.1 Vector3 PhotonTransformViewScaleControl.GetNetworkScale ()

Gets the last scale that was received through the network

Returns

- 8.49.2.2 Vector3 PhotonTransformViewScaleControl.GetScale (Vector3 currentScale)
- 8.49.2.3 void PhotonTransformViewScaleControl.OnPhotonSerializeView (Vector3 *currentScale*, PhotonStream *stream*, PhotonMessageInfo *info*)

8.50 PhotonTransformViewScaleModel Class Reference

Public Types

enum InterpolateOptions { InterpolateOptions.Disabled, InterpolateOptions.MoveTowards, Interpolate
 Options.Lerp }

Public Attributes

- · bool SynchronizeEnabled
- InterpolateOptions InterpolateOption = InterpolateOptions.Disabled
- float InterpolateMoveTowardsSpeed = 1f
- · float InterpolateLerpSpeed

8.50.1 Member Enumeration Documentation

8.50.1.1 enum PhotonTransformViewScaleModel.InterpolateOptions

Enumerator

Disabled

MoveTowards

Lerp

8.50.2 Member Data Documentation

- 8.50.2.1 float PhotonTransformViewScaleModel.InterpolateLerpSpeed
- 8.50.2.2 float PhotonTransformViewScaleModel.InterpolateMoveTowardsSpeed = 1f
- 8.50.2.3 InterpolateOptions PhotonTransformViewScaleModel.InterpolateOption = InterpolateOptions.Disabled
- 8.50.2.4 bool PhotonTransformViewScaleModel.SynchronizeEnabled

8.51 PhotonView Class Reference

PUN's NetworkView replacement class for networking. Use it like a NetworkView.

Inherits Photon.MonoBehaviour.

Public Member Functions

• void RequestOwnership ()

Depending on the PhotonView's ownershipTransfer setting, any client can request to become owner of the Photon⊷ View.

void TransferOwnership (PhotonPlayer newOwner)

Transfers the ownership of this PhotonView (and GameObject) to another player.

void TransferOwnership (int newOwnerId)

Transfers the ownership of this PhotonView (and GameObject) to another player.

· void OnMasterClientSwitched (PhotonPlayer newMasterClient)

Check ownerld assignment for sceneObjects to keep being owned by the MasterClient.

- void SerializeView (PhotonStream stream, PhotonMessageInfo info)
- · void DeserializeView (PhotonStream stream, PhotonMessageInfo info)
- void RefreshRpcMonoBehaviourCache ()

Can be used to refesh the list of MonoBehaviours on this GameObject while PhotonNetwork. UseRpcMono← BehaviourCache is true.

• void RPC (string methodName, PhotonTargets target, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, inclunding this client).

• void RpcSecure (string methodName, PhotonTargets target, bool encrypt, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, inclunding this client).

• void RPC (string methodName, PhotonPlayer targetPlayer, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, inclunding this client).

- void RpcSecure (string methodName, PhotonPlayer targetPlayer, bool encrypt, params object[] parameters)
 - Call a RPC method of this GameObject on remote clients of this room (or on all, inclunding this client).
- override string ToString ()

Static Public Member Functions

- static PhotonView Get (Component component)
- static PhotonView Get (GameObject gameObj)
- · static PhotonView Find (int viewID)

Public Attributes

- · int ownerld
- byte group = 0
- · bool OwnerShipWasTransfered

Flag to check if ownership of this photonView was set during the lifecycle. Used for checking when joining late if event with mismatched owner and sender needs addressing.

- int prefixBackup = -1
- ViewSynchronization synchronization
- OnSerializeTransform onSerializeTransformOption = OnSerializeTransform.PositionAndRotation
- OnSerializeRigidBody onSerializeRigidBodyOption = OnSerializeRigidBody.All
- OwnershipOption ownershipTransfer = OwnershipOption.Fixed

Defines if ownership of this PhotonView is fixed, can be requested or simply taken.

- List< Component > ObservedComponents
- · int instantiationId
- int currentMasterID = -1

The current master ID so that we can compare when we receive OnMasterClientSwitched() callback It's public so that we can check it during ownerld assignments in networkPeer script TODO: Maybe we can have the networkPeer always aware of the previous MasterClient?

Properties

```
int prefix [get, set]object[] instantiationData [get, set]
```

This is the instantiationData that was passed when calling PhotonNetwork.Instantiate* (if that was used to spawn this prefab)

• int viewID [get, set]

The ID of the PhotonView. Identifies it in a networked game (per room).

bool isSceneView [get]

True if the PhotonView was loaded with the scene (game object) or instantiated with InstantiateSceneObject.

• PhotonPlayer owner [get]

The owner of a PhotonView is the player who created the GameObject with that view. Objects in the scene don't have an owner.

- int OwnerActorNr [get]
- bool isOwnerActive [get]
- int CreatorActorNr [get]
- boolisMine [get]

True if the PhotonView is "mine" and can be controlled by this client.

8.51.1 Detailed Description

PUN's NetworkView replacement class for networking. Use it like a NetworkView.

8.51.2 Member Function Documentation

8.51.2.1 void PhotonView.DeserializeView (PhotonStream stream, PhotonMessageInfo info)

8.51.2.2 static PhotonView PhotonView.Find (int *viewID*) [static]

8.51.2.3 static PhotonView PhotonView.Get (Component component) [static]

8.51.2.4 static PhotonView PhotonView.Get (GameObject gameObj) [static]

8.51.2.5 void PhotonView.OnMasterClientSwitched (PhotonPlayer newMasterClient)

Check ownerld assignment for sceneObjects to keep being owned by the MasterClient.

Parameters

newMasterClient	New master client.

8.51.2.6 void PhotonView.RefreshRpcMonoBehaviourCache ()

Can be used to refesh the list of MonoBehaviours on this GameObject while PhotonNetwork.UseRpcMono← BehaviourCache is true.

Set PhotonNetwork.UseRpcMonoBehaviourCache to true to enable the caching. Uses this.GetComponents< (
MonoBehaviour>() to get a list of MonoBehaviours to call RPCs on (potentially).

While PhotonNetwork.UseRpcMonoBehaviourCache is false, this method has no effect, because the list is refreshed when a RPC gets called.

8.51.2.7 void PhotonView.RequestOwnership ()

Depending on the PhotonView's ownershipTransfer setting, any client can request to become owner of the Photon⊷ View.

Requesting ownership can give you control over a PhotonView, if the ownershipTransfer setting allows that. The current owner might have to implement IPunCallbacks.OnOwnershipRequest to react to the ownership request.

The owner/controller of a PhotonView is also the client which sends position updates of the GameObject.

8.51.2.8 void PhotonView.RPC (string methodName, PhotonTargets target, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, inclunding this client).

Remote Procedure Calls are an essential tool in making multiplayer games with PUN. It enables you to make every client in a room call a specific method.

RPC calls can target "All" or the "Others". Usually, the target "All" gets executed locally immediately after sending the RPC. The "*ViaServer" options send the RPC to the server and execute it on this client when it's sent back. Of course, calls are affected by this client's lag and that of remote clients.

Each call automatically is routed to the same PhotonView (and GameObject) that was used on the originating client.

See: Remote Procedure Calls.

Parameters

methodName The name of a fitting method that was has the RPC attribute.

target	The group of targets and the way the RPC gets sent.
parameters	The parameters that the RPC method has (must fit this call!).

8.51.2.9 void PhotonView.RPC (string methodName, PhotonPlayer targetPlayer, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, inclunding this client).

Remote Procedure Calls are an essential tool in making multiplayer games with PUN. It enables you to make every client in a room call a specific method.

This method allows you to make an RPC calls on a specific player's client. Of course, calls are affected by this client's lag and that of remote clients.

Each call automatically is routed to the same PhotonView (and GameObject) that was used on the originating client.

See: Remote Procedure Calls.

Parameters

methodName	The name of a fitting method that was has the RPC attribute.
targetPlayer	The group of targets and the way the RPC gets sent.
parameters	The parameters that the RPC method has (must fit this call!).

8.51.2.10 void PhotonView.RpcSecure (string *methodName*, **PhotonTargets** *target*, bool *encrypt*, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, inclunding this client).

Remote Procedure Calls are an essential tool in making multiplayer games with PUN. It enables you to make every client in a room call a specific method.

RPC calls can target "All" or the "Others". Usually, the target "All" gets executed locally immediately after sending the RPC. The "*ViaServer" options send the RPC to the server and execute it on this client when it's sent back. Of course, calls are affected by this client's lag and that of remote clients.

Each call automatically is routed to the same PhotonView (and GameObject) that was used on the originating client.

See: Remote Procedure Calls.

param name="methodName">The name of a fitting method that was has the RPC attribute.

param name="target">The group of targets and the way the RPC gets sent.

param name="encrypt">

param name="parameters">The parameters that the RPC method has (must fit this call!).

8.51.2.11 void PhotonView.RpcSecure (string methodName, PhotonPlayer targetPlayer, bool encrypt, params object[] parameters)

Call a RPC method of this GameObject on remote clients of this room (or on all, inclunding this client).

Remote Procedure Calls are an essential tool in making multiplayer games with PUN. It enables you to make every client in a room call a specific method.

This method allows you to make an RPC calls on a specific player's client. Of course, calls are affected by this client's lag and that of remote clients.

Each call automatically is routed to the same PhotonView (and GameObject) that was used on the originating client.

See: Remote Procedure Calls.

param name="methodName">The name of a fitting method that was has the RPC attribute.

param name="targetPlayer">The group of targets and the way the RPC gets sent.

param name="encrypt">

param name="parameters">The parameters that the RPC method has (must fit this call!).

8.51.2.12 void PhotonView.SerializeView (PhotonStream stream, PhotonMessageInfo info)

8.51.2.13 override string PhotonView.ToString ()

8.51.2.14 void PhotonView.TransferOwnership (PhotonPlayer newOwner)

Transfers the ownership of this PhotonView (and GameObject) to another player.

The owner/controller of a PhotonView is also the client which sends position updates of the GameObject.

8.51.2.15 void PhotonView.TransferOwnership (int newOwnerld)

Transfers the ownership of this PhotonView (and GameObject) to another player.

The owner/controller of a PhotonView is also the client which sends position updates of the GameObject.

8.51.3 Member Data Documentation

8.51.3.1 int PhotonView.currentMasterID = -1

The current master ID so that we can compare when we receive OnMasterClientSwitched() callback It's public so that we can check it during ownerId assignments in networkPeer script TODO: Maybe we can have the networkPeer always aware of the previous MasterClient?

8.51.3.2 byte PhotonView.group = 0

8.51.3.3 int PhotonView.instantiationId

8.51.3.4 List < Component > Photon View. Observed Components

8.51.3.5 OnSerializeRigidBody PhotonView.onSerializeRigidBodyOption = OnSerializeRigidBody.All

8.51.3.6 OnSerializeTransform PhotonView.onSerializeTransformOption = OnSerializeTransform.PositionAnd← Rotation

8.51.3.7 int PhotonView.ownerId

8.51.3.8 OwnershipOption PhotonView.ownershipTransfer = OwnershipOption.Fixed

Defines if ownership of this PhotonView is fixed, can be requested or simply taken.

Note that you can't edit this value at runtime. The options are described in enum OwnershipOption. The current owner has to implement IPunCallbacks.OnOwnershipRequest to react to the ownership request.

8.51.3.9 bool PhotonView.OwnerShipWasTransfered

Flag to check if ownership of this photonView was set during the lifecycle. Used for checking when joining late if event with mismatched owner and sender needs addressing.

true if owner ship was transfered; otherwise, false.

```
8.51.3.10 int PhotonView.prefixBackup = -1
```

8.51.3.11 ViewSynchronization PhotonView.synchronization

8.51.4 Property Documentation

```
8.51.4.1 int PhotonView.CreatorActorNr [get]
```

```
8.51.4.2 object[] PhotonView.instantiationData [get], [set]
```

This is the instantiationData that was passed when calling PhotonNetwork.Instantiate* (if that was used to spawn this prefab)

```
8.51.4.3 bool PhotonView.isMine [get]
```

True if the PhotonView is "mine" and can be controlled by this client.

PUN has an ownership concept that defines who can control and destroy each PhotonView. True in case the owner matches the local PhotonPlayer. True if this is a scene photonview on the Master client.

```
8.51.4.4 bool PhotonView.isOwnerActive [get]
```

```
8.51.4.5 bool PhotonView.isSceneView [get]
```

True if the PhotonView was loaded with the scene (game object) or instantiated with InstantiateSceneObject.

Scene objects are not owned by a particular player but belong to the scene. Thus they don't get destroyed when their creator leaves the game and the current Master Client can control them (whoever that is). The ownerld is 0 (player IDs are 1 and up).

```
8.51.4.6 PhotonPlayer PhotonView.owner [get]
```

The owner of a PhotonView is the player who created the GameObject with that view. Objects in the scene don't have an owner.

The owner/controller of a PhotonView is also the client which sends position updates of the GameObject.

Ownership can be transferred to another player with PhotonView.TransferOwnership or any player can request ownership by calling the PhotonView's RequestOwnership method. The current owner has to implement IPun Callbacks.OnOwnershipRequest to react to the ownership request.

```
8.51.4.7 int PhotonView.OwnerActorNr [get]8.51.4.8 int PhotonView.prefix [get], [set]8.51.4.9 int PhotonView.viewID [get], [set]
```

The ID of the PhotonView. Identifies it in a networked game (per room).

See: Network Instantiation

8.52 Photon.Realtime.PingMono Class Reference

Uses C# Socket class from System.Net.Sockets (as Unity usually does).

Inherits Photon.Realtime.PhotonPing.

Public Member Functions

override bool StartPing (string ip)

Sends a "Photon Ping" to a server.

- override bool Done ()
- override void Dispose ()

Additional Inherited Members

8.52.1 Detailed Description

Uses C# Socket class from System.Net.Sockets (as Unity usually does).

Incompatible with Windows 8 Store/Phone API.

8.52.2 Member Function Documentation

```
8.52.2.1 override void Photon.Realtime.PingMono.Dispose() [virtual]
```

Reimplemented from Photon.Realtime.PhotonPing.

```
8.52.2.2 override bool Photon.Realtime.PingMono.Done() [virtual]
```

Reimplemented from Photon.Realtime.PhotonPing.

8.52.2.3 override bool Photon.Realtime.PingMono.StartPing (string ip) [virtual]

Sends a "Photon Ping" to a server.

Parameters

ip Address in IPv4 or IPv6 format. An address containing a '.' will be interpretet as IPv4.

Returns

True if the Photon Ping could be sent.

Reimplemented from Photon.Realtime.PhotonPing.

8.53 PingMonoEditor Class Reference

Uses C# Socket class from System.Net.Sockets (as Unity usually does).

Inherits Photon.Realtime.PhotonPing.

Public Member Functions

override bool StartPing (string ip)

Sends a "Photon Ping" to a server.

- override bool Done ()
- override void Dispose ()

Additional Inherited Members

8.53.1 Detailed Description

Uses C# Socket class from System.Net.Sockets (as Unity usually does).

Incompatible with Windows 8 Store/Phone API.

8.53.2 Member Function Documentation

```
8.53.2.1 override void PingMonoEditor.Dispose() [virtual]
```

Reimplemented from Photon.Realtime.PhotonPing.

8.53.2.2 override bool PingMonoEditor.Done() [virtual]

Reimplemented from Photon.Realtime.PhotonPing.

8.53.2.3 override bool PingMonoEditor.StartPing (string *ip*) [virtual]

Sends a "Photon Ping" to a server.

Parameters

ip Address in IPv4 or IPv6 format. An address containing a '.' will be interpretet as IPv4.

Returns

True if the Photon Ping could be sent.

Reimplemented from Photon.Realtime.PhotonPing.

8.54 Photon.PunBehaviour Class Reference

This class provides a .photonView and all callbacks/events that PUN can call. Override the events/methods you want to use.

Inherits Photon. Mono Behaviour, and IPun Callbacks.

Public Member Functions

virtual void OnConnectedToPhoton ()

Called when the initial connection got established but before you can use the server. OnJoinedLobby() or On← ConnectedToMaster() are called when PUN is ready.

• virtual void OnLeftRoom ()

Called when the local user/client left a room.

virtual void OnMasterClientSwitched (PhotonPlayer newMasterClient)

Called after switching to a new MasterClient when the current one leaves.

• virtual void OnPhotonCreateRoomFailed (object[] codeAndMsg)

Called when a CreateRoom() call failed. The parameter provides ErrorCode and message (as array).

virtual void OnPhotonJoinRoomFailed (object[] codeAndMsg)

Called when a JoinRoom() call failed. The parameter provides ErrorCode and message (as array).

• virtual void OnCreatedRoom ()

Called when this client created a room and entered it. OnJoinedRoom() will be called as well.

· virtual void OnJoinedLobby ()

Called on entering a lobby on the Master Server. The actual room-list updates will call OnReceivedRoomListUpdate().

virtual void OnLeftLobby ()

Called after leaving a lobby.

virtual void OnFailedToConnectToPhoton (DisconnectCause cause)

Called if a connect call to the Photon server failed before the connection was established, followed by a call to On← DisconnectedFromPhoton().

virtual void OnDisconnectedFromPhoton ()

Called after disconnecting from the Photon server.

• virtual void OnConnectionFail (DisconnectCause cause)

Called when something causes the connection to fail (after it was established), followed by a call to OnDisconnected← FromPhoton().

virtual void OnPhotonInstantiate (PhotonMessageInfo info)

Called on all scripts on a GameObject (and children) that have been Instantiated using PhotonNetwork.Instantiate.

virtual void OnReceivedRoomListUpdate ()

Called for any update of the room-listing while in a lobby (PhotonNetwork.insideLobby) on the Master Server or when a response is received for PhotonNetwork.GetCustomRoomList().

virtual void OnJoinedRoom ()

Called when entering a room (by creating or joining it). Called on all clients (including the Master Client).

virtual void OnPhotonPlayerConnected (PhotonPlayer newPlayer)

Called when a remote player entered the room. This PhotonPlayer is already added to the playerlist at this time.

virtual void OnPhotonPlayerDisconnected (PhotonPlayer otherPlayer)

Called when a remote player left the room. This PhotonPlayer is already removed from the playerlist at this time.

virtual void OnPhotonRandomJoinFailed (object[] codeAndMsg)

Called when a JoinRandom() call failed. The parameter provides ErrorCode and message.

virtual void OnConnectedToMaster ()

Called after the connection to the master is established and authenticated but only when PhotonNetwork.autoJoin← Lobby is false.

virtual void OnPhotonMaxCccuReached ()

Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting.

virtual void OnPhotonCustomRoomPropertiesChanged (Hashtable propertiesThatChanged)

Called when a room's custom properties changed. The propertiesThatChanged contains all that was set via Room. ← SetCustomProperties.

virtual void OnPhotonPlayerPropertiesChanged (object[] playerAndUpdatedProps)

Called when custom player-properties are changed. Player and the changed properties are passed as object[].

· virtual void OnUpdatedFriendList ()

Called when the server sent the response to a FindFriends request and updated PhotonNetwork.Friends.

virtual void OnCustomAuthenticationFailed (string debugMessage)

Called when the custom authentication failed. Followed by disconnect!

virtual void OnCustomAuthenticationResponse (Dictionary< string, object > data)

Called when your Custom Authentication service responds with additional data.

• virtual void OnWebRpcResponse (OperationResponse response)

Called by PUN when the response to a WebRPC is available. See PhotonNetwork. WebRPC.

virtual void OnOwnershipRequest (object[] viewAndPlayer)

Called when another player requests ownership of a PhotonView from you (the current owner).

virtual void OnLobbyStatisticsUpdate ()

Called when the Master Server sent an update for the Lobby Statistics, updating PhotonNetwork.LobbyStatistics.

• virtual void OnPhotonPlayerActivityChanged (PhotonPlayer otherPlayer)

Called when a remote Photon Player activity changed. This will be called ONLY if PlayerTtl is greater than 0.

virtual void OnOwnershipTransfered (object[] viewAndPlayers)

Called when ownership of a PhotonView is transfered to another player.

Additional Inherited Members

8.54.1 Detailed Description

This class provides a .photonView and all callbacks/events that PUN can call. Override the events/methods you want to use.

By extending this class, you can implement individual methods as override.

Visual Studio and MonoDevelop should provide the list of methods when you begin typing "override". Your implementation does not have to call "base.method()".

This class implements IPunCallbacks, which is used as definition of all PUN callbacks. Don't implement IPun← Callbacks in your classes. Instead, implent PunBehaviour or individual methods.

8.54.2 Member Function Documentation

```
8.54.2.1 virtual void Photon.PunBehaviour.OnConnectedToMaster() [virtual]
```

Called after the connection to the master is established and authenticated but only when PhotonNetwork.autoJoin← Lobby is false.

If you set PhotonNetwork.autoJoinLobby to true, OnJoinedLobby() will be called instead of this.

You can join rooms and create them even without being in a lobby. The default lobby is used in that case. The list of available rooms won't become available unless you join a lobby via PhotonNetwork.joinLobby.

Implements IPunCallbacks.

```
8.54.2.2 virtual void Photon.PunBehaviour.OnConnectedToPhoton() [virtual]
```

Called when the initial connection got established but before you can use the server. OnJoinedLobby() or On← ConnectedToMaster() are called when PUN is ready.

This callback is only useful to detect if the server can be reached at all (technically). Most often, it's enough to implement OnFailedToConnectToPhoton() and OnDisconnectedFromPhoton().

OnJoinedLobby() or OnConnectedToMaster() are called when PUN is ready.

When this is called, the low level connection is established and PUN will send your Appld, the user, etc in the background. This is not called for transitions from the masterserver to game servers.

Implements IPunCallbacks.

```
8.54.2.3 virtual void Photon.PunBehaviour.OnConnectionFail ( DisconnectCause cause ) [virtual]
```

Called when something causes the connection to fail (after it was established), followed by a call to On⊷ DisconnectedFromPhoton().

If the server could not be reached in the first place, OnFailedToConnectToPhoton is called instead. The reason for the error is provided as DisconnectCause.

Implements IPunCallbacks.

```
8.54.2.4 virtual void Photon.PunBehaviour.OnCreatedRoom() [virtual]
```

Called when this client created a room and entered it. OnJoinedRoom() will be called as well.

This callback is only called on the client which created a room (see PhotonNetwork.CreateRoom).

As any client might close (or drop connection) anytime, there is a chance that the creator of a room does not execute OnCreatedRoom.

If you need specific room properties or a "start signal", it is safer to implement OnMasterClientSwitched() and to make the new MasterClient check the room's state.

Implements IPunCallbacks.

8.54.2.5 virtual void Photon.PunBehaviour.OnCustomAuthenticationFailed (string debugMessage) [virtual]

Called when the custom authentication failed. Followed by disconnect!

Custom Authentication can fail due to user-input, bad tokens/secrets. If authentication is successful, this method is not called. Implement OnJoinedLobby() or OnConnectedToMaster() (as usual).

During development of a game, it might also fail due to wrong configuration on the server side. In those cases, logging the debugMessage is very important.

Unless you setup a custom authentication service for your app (in the Dashboard), this won't be called!

Parameters

debugMessage	Contains a debug message why authentication failed. This has to be fixed during develop-
	ment time.

Implements IPunCallbacks.

8.54.2.6 virtual void Photon.PunBehaviour.OnCustomAuthenticationResponse (Dictionary < string, object > data) [virtual]

Called when your Custom Authentication service responds with additional data.

Custom Authentication services can include some custom data in their response. When present, that data is made available in this callback as Dictionary. While the keys of your data have to be strings, the values can be either string or a number (in Json). You need to make extra sure, that the value type is the one you expect. Numbers become (currently) int64.

Example: void OnCustomAuthenticationResponse(Dictionary<string, object> data) { ... }

https://doc.photonengine.com/en-us/pun/current/connection-and-authentication/custom-authentication Implements IPunCallbacks.

 $\textbf{8.54.2.7} \quad \textbf{virtual void Photon.PunBehaviour.OnDisconnectedFromPhoton () } \quad [\texttt{virtual}]$

Called after disconnecting from the Photon server.

In some cases, other callbacks are called before OnDisconnectedFromPhoton is called. Examples: OnConnection Fail() and OnFailedToConnectToPhoton().

Implements IPunCallbacks.

8.54.2.8 virtual void Photon.PunBehaviour.OnFailedToConnectToPhoton (DisconnectCause cause) [virtual]

Called if a connect call to the Photon server failed before the connection was established, followed by a call to OnDisconnectedFromPhoton().

This is called when no connection could be established at all. It differs from OnConnectionFail, which is called when an existing connection fails.

Implements IPunCallbacks.

8.54.2.9 virtual void Photon.PunBehaviour.OnJoinedLobby() [virtual]

Called on entering a lobby on the Master Server. The actual room-list updates will call OnReceivedRoomList← Update().

Note: When PhotonNetwork.autoJoinLobby is false, OnConnectedToMaster() will be called and the room list won't become available.

While in the lobby, the roomlist is automatically updated in fixed intervals (which you can't modify). The room list gets available when OnReceivedRoomListUpdate() gets called after OnJoinedLobby().

Implements IPunCallbacks.

```
8.54.2.10 virtual void Photon.PunBehaviour.OnJoinedRoom() [virtual]
```

Called when entering a room (by creating or joining it). Called on all clients (including the Master Client).

This method is commonly used to instantiate player characters. If a match has to be started "actively", you can call an PunRPC triggered by a user's button-press or a timer.

When this is called, you can usually already access the existing players in the room via PhotonNetwork.playerList. Also, all custom properties should be already available as Room.customProperties. Check Room.playerCount to find out if enough players are in the room to start playing.

Implements IPunCallbacks.

```
8.54.2.11 virtual void Photon.PunBehaviour.OnLeftLobby() [virtual]
```

Called after leaving a lobby.

When you leave a lobby, CreateRoom and JoinRandomRoom automatically refer to the default lobby. Implements IPunCallbacks.

```
8.54.2.12 virtual void Photon.PunBehaviour.OnLeftRoom() [virtual]
```

Called when the local user/client left a room.

When leaving a room, PUN brings you back to the Master Server. Before you can use lobbies and join or create rooms, OnJoinedLobby() or OnConnectedToMaster() will get called again.

Implements IPunCallbacks.

```
8.54.2.13 virtual void Photon.PunBehaviour.OnLobbyStatisticsUpdate() [virtual]
```

Called when the Master Server sent an update for the Lobby Statistics, updating PhotonNetwork.LobbyStatistics.

This callback has two preconditions: EnableLobbyStatistics must be set to true, before this client connects. And the client has to be connected to the Master Server, which is providing the info about lobbies.

Implements IPunCallbacks.

```
8.54.2.14 virtual void Photon.PunBehaviour.OnMasterClientSwitched ( PhotonPlayer newMasterClient ) [virtual]
```

Called after switching to a new MasterClient when the current one leaves.

This is not called when this client enters a room. The former MasterClient is still in the player list when this method get called.

Implements IPunCallbacks.

8.54.2.15 virtual void Photon.PunBehaviour.OnOwnershipRequest (object[] viewAndPlayer) [virtual]

Called when another player requests ownership of a PhotonView from you (the current owner).

The parameter viewAndPlayer contains:

PhotonView view = viewAndPlayer[0] as PhotonView;

PhotonPlayer requestingPlayer = viewAndPlayer[1] as PhotonPlayer;

Parameters

viewAndPlayer The PhotonView is viewAndPlayer[0] and the requesting player is viewAndPlayer[1].

Implements IPunCallbacks.

8.54.2.16 virtual void Photon.PunBehaviour.OnOwnershipTransfered (object[] viewAndPlayers) [virtual]

Called when ownership of a PhotonView is transferred to another player.

The parameter viewAndPlayers contains:

PhotonView view = viewAndPlayers[0] as PhotonView;

PhotonPlayer newOwner = viewAndPlayers[1] as PhotonPlayer;

PhotonPlayer oldOwner = viewAndPlayers[2] as PhotonPlayer;

void OnOwnershipTransfered(object[] viewAndPlayers) {} //

Implements IPunCallbacks.

8.54.2.17 virtual void Photon.PunBehaviour.OnPhotonCreateRoomFailed (object[] codeAndMsg) [virtual]

Called when a CreateRoom() call failed. The parameter provides ErrorCode and message (as array).

Most likely because the room name is already in use (some other client was faster than you). PUN logs some info if the PhotonNetwork.logLevel is >= PhotonLogLevel.Informational.

Parameters

codeAndMsg codeAndMsg[0] is a short ErrorCode and codeAndMsg[1] is a string debug msg.

Implements IPunCallbacks.

8.54.2.18 virtual void Photon.PunBehaviour.OnPhotonCustomRoomPropertiesChanged (Hashtable *propertiesThatChanged*) [virtual]

Called when a room's custom properties changed. The propertiesThatChanged contains all that was set via Room.SetCustomProperties.

Since v1.25 this method has one parameter: Hashtable properties That Changed.

Changing properties must be done by Room.SetCustomProperties, which causes this callback locally, too.

Parameters

propertiesThat← Changed

Implements IPunCallbacks.

8.54.2.19 virtual void Photon.PunBehaviour.OnPhotonInstantiate (PhotonMessageInfo info) [virtual]

Called on all scripts on a GameObject (and children) that have been Instantiated using PhotonNetwork.Instantiate.

PhotonMessageInfo parameter provides info about who created the object and when (based off Photon

Networking.time).

Implements IPunCallbacks.

8.54.2.20 virtual void Photon.PunBehaviour.OnPhotonJoinRoomFailed (object[] codeAndMsg) [virtual]

Called when a JoinRoom() call failed. The parameter provides ErrorCode and message (as array).

Most likely error is that the room does not exist or the room is full (some other client was faster than you). PUN logs some info if the PhotonNetwork.logLevel is >= PhotonLogLevel.Informational.

Parameters

codeAndMsg[0] is short ErrorCode. codeAndMsg[1] is string debug msg.

Implements IPunCallbacks.

8.54.2.21 virtual void Photon.PunBehaviour.OnPhotonMaxCccuReached() [virtual]

Because the concurrent user limit was (temporarily) reached, this client is rejected by the server and disconnecting.

When this happens, the user might try again later. You can't create or join rooms in OnPhotonMaxCcuReached(), cause the client will be disconnecting. You can raise the CCU limits with a new license (when you host yourself) or extended subscription (when using the Photon Cloud). The Photon Cloud will mail you when the CCU limit was reached. This is also visible in the Dashboard (webpage).

Implements IPunCallbacks.

8.54.2.22 virtual void Photon.PunBehaviour.OnPhotonPlayerActivityChanged (PhotonPlayer otherPlayer) [virtual]

Called when a remote Photon Player activity changed. This will be called ONLY if PlayerTtl is greater than 0.

Use PhotonPlayer.IsInactive to check a player's current activity state.

Example: void OnPhotonPlayerActivityChanged(PhotonPlayer otherPlayer) {...}

This callback has precondition: PlayerTtl must be greater than 0.

Implements IPunCallbacks.

8.54.2.23 virtual void Photon.PunBehaviour.OnPhotonPlayerConnected(PhotonPlayer newPlayer) [virtual]

Called when a remote player entered the room. This PhotonPlayer is already added to the playerlist at this time.

If your game starts with a certain number of players, this callback can be useful to check the Room.playerCount and find out if you can start.

Implements IPunCallbacks.

8.54.2.24 virtual void Photon.PunBehaviour.OnPhotonPlayerDisconnected (PhotonPlayer otherPlayer) [virtual]

Called when a remote player left the room. This PhotonPlayer is already removed from the playerlist at this time.

When your client calls PhotonNetwork.leaveRoom, PUN will call this method on the remaining clients. When a remote client drops connection or gets closed, this callback gets executed. after a timeout of several seconds.

Implements IPunCallbacks.

```
8.54.2.25 virtual void Photon.PunBehaviour.OnPhotonPlayerPropertiesChanged (object[] playerAndUpdatedProps )
[virtual]
```

Called when custom player-properties are changed. Player and the changed properties are passed as object[].

Since v1.25 this method has one parameter: object[] playerAndUpdatedProps, which contains two entries. [0] is the affected PhotonPlayer.

[1] is the Hashtable of properties that changed.

We are using a object[] due to limitations of Unity's GameObject.SendMessage (which has only one optional parameter).

 $Changing \ properties \ must be \ done \ by \ \frac{PhotonPlayer.SetCustomProperties}{PhotonPlayer.SetCustomProperties}, \ which \ causes \ this \ callback \ locally, \ too.$

Example:

```
void OnPhotonPlayerPropertiesChanged(object[] playerAndUpdatedProps) {
   PhotonPlayer player = playerAndUpdatedProps[0] as PhotonPlayer;
   Hashtable props = playerAndUpdatedProps[1] as Hashtable;
   //...
}
```

Parameters

playerAnd⇔	Contains PhotonPlayer and the properties that changed See remarks.
UpdatedProps	

Implements IPunCallbacks.

8.54.2.26 virtual void Photon.PunBehaviour.OnPhotonRandomJoinFailed (object[] codeAndMsg) [virtual]

Called when a JoinRandom() call failed. The parameter provides ErrorCode and message.

Most likely all rooms are full or no rooms are available.

When using multiple lobbies (via JoinLobby or TypedLobby), another lobby might have more/fitting rooms.

PUN logs some info if the PhotonNetwork.logLevel is >= PhotonLogLevel.Informational.

Parameters

```
codeAndMsg | codeAndMsg[0] is short ErrorCode. codeAndMsg[1] is string debug msg.
```

Implements IPunCallbacks.

```
8.54.2.27 virtual void Photon.PunBehaviour.OnReceivedRoomListUpdate() [virtual]
```

Called for any update of the room-listing while in a lobby (PhotonNetwork.insideLobby) on the Master Server or when a response is received for PhotonNetwork.GetCustomRoomList().

PUN provides the list of rooms by PhotonNetwork.GetRoomList().

Each item is a RoomInfo which might include custom properties (provided you defined those as lobby-listed when creating a room).

Not all types of lobbies provide a listing of rooms to the client. Some are silent and specialized for server-side matchmaking.

Implements IPunCallbacks.

```
8.54.2.28 virtual void Photon.PunBehaviour.OnUpdatedFriendList() [virtual]
```

Called when the server sent the response to a FindFriends request and updated PhotonNetwork.Friends.

The friends list is available as PhotonNetwork.Friends, listing name, online state and the room a user is in (if any).

Implements IPunCallbacks.

8.54.2.29 virtual void Photon.PunBehaviour.OnWebRpcResponse (OperationResponse response) [virtual]

Called by PUN when the response to a WebRPC is available. See PhotonNetwork.WebRPC.

Important: The response.ReturnCode is 0 if Photon was able to reach your web-service. The content of the response is what your web-service sent. You can create a WebResponse instance from it. Example: WebRpccResponse webResponse = new WebRpcResponse(operationResponse);

Please note: Class OperationResponse is in a namespace which needs to be "used": using ExitGames.Client.← Photon; // includes OperationResponse (and other classes)

The OperationResponse.ReturnCode by Photon is:

```
0 for "OK"
-3 for "Web-Service not configured" (see Dashboard / WebHooks)
-5 for "Web-Service does now have RPC path/name" (at least for Azure)
```

Implements IPunCallbacks.

8.55 PunRPC Class Reference

Replacement for RPC attribute with different name. Used to flag methods as remote-callable. Inherits Attribute.

8.55.1 Detailed Description

Replacement for RPC attribute with different name. Used to flag methods as remote-callable.

8.56 RaiseEventOptions Class Reference

Aggregates several less-often used options for operation RaiseEvent. See field descriptions for usage details.

Public Member Functions

• void Reset ()

Reset this instance. For better memory handling than instanciating a new one always,

Public Attributes

EventCaching CachingOption

Defines if the server should simply send the event, put it in the cache or remove events that are like this one.

• byte InterestGroup

The number of the Interest Group to send this to. 0 goes to all users but to get 1 and up, clients must subscribe to the group first.

int[] TargetActors

A list of PhotonPlayer.IDs to send this event to. You can implement events that just go to specific users this way.

· ReceiverGroup Receivers

Sends the event to All, MasterClient or Others (default). Be careful with MasterClient, as the client might disconnect before it got the event and it gets lost.

· byte SequenceChannel

Events are ordered per "channel". If you have events that are independent of others, they can go into another sequence or channel.

bool ForwardToWebhook

Events can be forwarded to Webhooks, which can evaluate and use the events to follow the game's state.

bool Encrypt

Static Public Attributes

static readonly RaiseEventOptions Default = new RaiseEventOptions()

Default options: CachingOption: DoNotCache, InterestGroup: 0, targetActors: null, receivers: Others, sequence← Channel: 0.

8.56.1 Detailed Description

Aggregates several less-often used options for operation RaiseEvent. See field descriptions for usage details.

8.56.2 Member Function Documentation

8.56.2.1 void RaiseEventOptions.Reset ()

Reset this instance. For better memory handling than instanciating a new one always,

8.56.3 Member Data Documentation

8.56.3.1 EventCaching RaiseEventOptions.CachingOption

Defines if the server should simply send the event, put it in the cache or remove events that are like this one.

When using option: SliceSetIndex, SlicePurgeIndex or SlicePurgeUpToIndex, set a CacheSliceIndex. All other options except SequenceChannel get ignored.

8.56.3.2 readonly RaiseEventOptions RaiseEventOptions.Default = new RaiseEventOptions() [static]

Default options: CachingOption: DoNotCache, InterestGroup: 0, targetActors: null, receivers: Others, sequence Channel: 0.

- 8.56.3.3 bool RaiseEventOptions.Encrypt
- 8.56.3.4 bool RaiseEventOptions.ForwardToWebhook

Events can be forwarded to Webhooks, which can evaluate and use the events to follow the game's state.

$8.56.3.5 \quad \text{byte RaiseEventOptions.} InterestGroup \\$

The number of the Interest Group to send this to. 0 goes to all users but to get 1 and up, clients must subscribe to the group first.

8.56.3.6 ReceiverGroup RaiseEventOptions.Receivers

Sends the event to All, MasterClient or Others (default). Be careful with MasterClient, as the client might disconnect before it got the event and it gets lost.

8.56.3.7 byte RaiseEventOptions.SequenceChannel

Events are ordered per "channel". If you have events that are independent of others, they can go into another sequence or channel.

8.56.3.8 int [] RaiseEventOptions.TargetActors

A list of PhotonPlayer.IDs to send this event to. You can implement events that just go to specific users this way.

8.57 Region Class Reference

Public Member Functions

- Region (CloudRegionCode code)
- Region (CloudRegionCode code, string regionCodeString, string address)
- override string ToString ()

Static Public Member Functions

static CloudRegionCode Parse (string codeAsString)

Public Attributes

- CloudRegionCode Code
- string Cluster

Unlike the CloudRegionCode, this may contain cluster information.

- string HostAndPort
- int Ping

8.57.1 Constructor & Destructor Documentation

- 8.57.1.1 Region.Region (CloudRegionCode code)
- 8.57.1.2 Region.Region (CloudRegionCode code, string regionCodeString, string address)
- 8.57.2 Member Function Documentation
- 8.57.2.1 static CloudRegionCode Region.Parse (string codeAsString) [static]
- 8.57.2.2 override string Region.ToString ()
- 8.57.3 Member Data Documentation
- 8.57.3.1 string Region.Cluster

Unlike the CloudRegionCode, this may contain cluster information.

- 8.57.3.2 CloudRegionCode Region.Code
- 8.57.3.3 string Region.HostAndPort
- 8.57.3.4 int Region.Ping

8.58 Room Class Reference

This class resembles a room that PUN joins (or joined). The properties are settable as opposed to those of a RoomInfo and you can close or hide "your" room.

Inherits RoomInfo.

Public Member Functions

Updates the current room's Custom Properties with new/updated key-values.

void SetPropertiesListedInLobby (string[] propsListedInLobby)

Enables you to define the properties available in the lobby if not all properties are needed to pick a room.

void ClearExpectedUsers ()

Attempts to remove all current expected users from the server's Slot Reservation list.

void SetExpectedUsers (string[] expectedUsers)

Attempts to set the current expected users list.

override string ToString ()

Returns a summary of this Room instance as string.

new string ToStringFull ()

Returns a summary of this Room instance as longer string, including Custom Properties.

Properties

• new string Name [get, set]

The name of a room. Unique identifier (per Loadbalancing group) for a room/match.

• new bool IsOpen [get, set]

Defines if the room can be joined. This does not affect listing in a lobby but joining the room will fail if not open. If not open, the room is excluded from random matchmaking. Due to racing conditions, found matches might become closed before they are joined. Simply re-connect to master and find another. Use property "visible" to not list the room.

• new bool IsVisible [get, set]

Defines if the room is listed in its lobby. Rooms can be created invisible, or changed to invisible. To change if a room can be joined, use property: open.

• string[] PropertiesListedInLobby [get, set]

A list of custom properties that should be forwarded to the lobby and listed there.

bool AutoCleanUp [get]

Gets if this room uses autoCleanUp to remove all (buffered) RPCs and instantiated GameObjects when a player leaves.

• new int MaxPlayers [get, set]

Sets a limit of players to this room. This property is shown in lobby, too. If the room is full (players count == maxplayers), joining this room will fail.

new int PlayerCount [get]

Count of players in this room.

string[] ExpectedUsers [get]

List of users who are expected to join this room. In matchmaking, Photon blocks a slot for each of these UserIDs out of the MaxPlayers.

191

• int PlayerTtl [get, set]

Player Time To Live. How long any player can be inactive (due to disconnect or leave) before the user gets removed from the playerlist (freeing a slot).

• int EmptyRoomTtl [get, set]

Room Time To Live. How long a room stays available (and in server-memory), after the last player becomes inactive. After this time, the room gets persisted or destroyed.

```
new string name [get, set]new bool open [get, set]
```

- new bool visible [get, set]
- string[] propertiesListedInLobby [get, set]
- bool autoCleanUp [get]
- new int maxPlayers [get, set]
- new int playerCount [get]
- string[] expectedUsers [get]

Additional Inherited Members

8.58.1 Detailed Description

This class resembles a room that PUN joins (or joined). The properties are settable as opposed to those of a RoomInfo and you can close or hide "your" room.

8.58.2 Member Function Documentation

```
8.58.2.1 void Room.ClearExpectedUsers ( )
```

Attempts to remove all current expected users from the server's Slot Reservation list.

Note that this operation can conflict with new/other users joining. They might be adding users to the list of expected users before or after this client called ClearExpectedUsers.

This room's expectedUsers value will update, when the server sends a successful update.

Internals: This methods wraps up setting the ExpectedUsers property of a room.

```
8.58.2.2 void Room.SetCustomProperties ( Hashtable propertiesToSet, Hashtable expectedValues = null, bool webForward = false )
```

Updates the current room's Custom Properties with new/updated key-values.

Custom Properties are a key-value set (Hashtable) which is available to all players in a room. They can relate to the room or individual players and are useful when only the current value of something is of interest. For example: The map of a room. All keys must be strings.

The Room and the PhotonPlayer class both have SetCustomProperties methods. Also, both classes offer access to current key-values by: customProperties.

Always use SetCustomProperties to change values. To reduce network traffic, set only values that actually changed. New properties are added, existing values are updated. Other values will not be changed, so only provide values that changed or are new.

To delete a named (custom) property of this room, use null as value.

Locally, SetCustomProperties will update it's cache without delay. Other clients are updated through Photon (the server) with a fitting operation.

Check and Swap

SetCustomProperties have the option to do a server-side Check-And-Swap (CAS): Values only get updated if the expected values are correct. The expectedValues can be different key/values than the propertiesToSet. So you can check some key and set another key's value (if the check succeeds).

If the client's knowledge of properties is wrong or outdated, it can't set values with CAS. This can be useful to keep players from concurrently setting values. For example: If all players try to pickup some card or item, only one should get it. With CAS, only the first SetProperties gets executed server-side and any other (sent at the same time) fails.

The server will broadcast successfully changed values and the local "cache" of customProperties only gets updated after a roundtrip (if anything changed).

You can do a "webForward": Photon will send the changed properties to a WebHook defined for your application.

OfflineMode

While PhotonNetwork.offlineMode is true, the expectedValues and webForward parameters are ignored. In Offline ← Mode, the local customProperties values are immediately updated (without the roundtrip).

Parameters

propertiesToSet	The new properties to be set.
expectedValues	At least one property key/value set to check server-side. Key and value must be correct.
	Ignored in OfflineMode.
webForward	Set to true, to forward the set properties to a WebHook, defined for this app (in Dashboard).
	Ignored in OfflineMode.

8.58.2.3 void Room.SetExpectedUsers (string[] expectedUsers)

Attempts to set the current expected users list.

Note that this operation can conflict with new/other users joining. They might be adding users to the list of expected users before or after this client called SetExpectedUsers. If the list changes before this operation arrives, the server will not modify the list and SetExpectedUsers() fails.

This room's expectedUsers value will be sent by the server.

Internals: This methods wraps up setting the ExpectedUsers property of a room.

8.58.2.4 void Room.SetPropertiesListedInLobby (string[] propsListedInLobby)

Enables you to define the properties available in the lobby if not all properties are needed to pick a room.

It makes sense to limit the amount of properties sent to users in the lobby as this improves speed and stability.

Parameters

propsListedIn⇔	An array of custom room property names to forward to the lobby.
Lobby	

8.58.2.5 override string Room.ToString ()

Returns a summary of this Room instance as string.

Returns

Summary of this Room instance.

8.58.2.6 new string Room.ToStringFull ()

Returns a summary of this Room instance as longer string, including Custom Properties.

Returns

Summary of this Room instance.

8.58.3 Property Documentation

```
8.58.3.1 bool Room.AutoCleanUp [get]
```

Gets if this room uses autoCleanUp to remove all (buffered) RPCs and instantiated GameObjects when a player leaves.

```
8.58.3.2 bool Room.autoCleanUp [get]
8.58.3.3 int Room.EmptyRoomTtl [get], [set]
```

Room Time To Live. How long a room stays available (and in server-memory), after the last player becomes inactive. After this time, the room gets persisted or destroyed.

```
8.58.3.4 string [] Room.ExpectedUsers [get]
```

List of users who are expected to join this room. In matchmaking, Photon blocks a slot for each of these UserIDs out of the MaxPlayers.

The corresponding feature in Photon is called "Slot Reservation" and can be found in the doc pages. Define expected players in the PhotonNetwork methods: CreateRoom, JoinRoom and JoinOrCreateRoom.

```
8.58.3.5 string[]Room.expectedUsers [get]
8.58.3.6 new bool Room.IsOpen [get], [set]
```

Defines if the room can be joined. This does not affect listing in a lobby but joining the room will fail if not open. If not open, the room is excluded from random matchmaking. Due to racing conditions, found matches might become closed before they are joined. Simply re-connect to master and find another. Use property "visible" to not list the room.

```
8.58.3.7 new bool Room.lsVisible [get], [set]
```

Defines if the room is listed in its lobby. Rooms can be created invisible, or changed to invisible. To change if a room can be joined, use property: open.

```
8.58.3.8 new int Room.MaxPlayers [get], [set]
```

Sets a limit of players to this room. This property is shown in lobby, too. If the room is full (players count == maxplayers), joining this room will fail.

```
8.58.3.9 new int Room.maxPlayers [get], [set]
8.58.3.10 new string Room.Name [get], [set]
```

The name of a room. Unique identifier (per Loadbalancing group) for a room/match.

```
8.58.3.11 new string Room.name [get], [set]
8.58.3.12 new bool Room.open [get], [set]
8.58.3.13 new int Room.PlayerCount [get]
Count of players in this room.
8.58.3.14 new int Room.playerCount [get]
8.58.3.15 int Room.PlayerTtl [get], [set]
```

Player Time To Live. How long any player can be inactive (due to disconnect or leave) before the user gets removed from the playerlist (freeing a slot).

```
8.58.3.16 string[] Room.PropertiesListedInLobby [get], [set]
```

A list of custom properties that should be forwarded to the lobby and listed there.

```
8.58.3.17 string[]Room.propertiesListedInLobby [get], [set]
8.58.3.18 new bool Room.visible [get], [set]
```

8.59 RoomInfo Class Reference

A simplified room with just the info required to list and join, used for the room listing in the lobby. The properties are not settable (open, MaxPlayers, etc).

Inherited by Room.

Public Member Functions

• override bool Equals (object other)

Makes RoomInfo comparable (by name).

• override int GetHashCode ()

Accompanies Equals, using the name's HashCode as return.

• override string ToString ()

Simple printingin method.

• string ToStringFull ()

Simple printingin method.

Protected Attributes

• byte maxPlayersField = 0

Backing field for property.

• int emptyRoomTtlField = 0

Backing field for property.

• int playerTtlField = 0

Backing field for property.

• string[] expectedUsersField

Backing field for property.

• bool openField = true

Backing field for property.

• bool visibleField = true

Backing field for property.

bool autoCleanUpField = PhotonNetwork.autoCleanUpPlayerObjects

Backing field for property. False unless the GameProperty is set to true (else it's not sent).

· string nameField

Backing field for property.

Properties

• bool removedFromList [get, set]

Used internally in lobby, to mark rooms that are no longer listed.

• Hashtable CustomProperties [get]

Read-only "cache" of custom properties of a room. Set via Room.SetCustomProperties (not available for RoomInfo class!).

string Name [get]

The name of a room. Unique identifier (per Loadbalancing group) for a room/match.

• int PlayerCount [get, set]

Only used internally in lobby, to display number of players in room (while you're not in).

• bool IsLocalClientInside [get, set]

State if the local client is already in the game or still going to join it on gameserver (in lobby always false).

• byte MaxPlayers [get]

Sets a limit of players to this room. This property is shown in lobby, too. If the room is full (players count == maxplayers), joining this room will fail.

• bool IsOpen [get]

Defines if the room can be joined. This does not affect listing in a lobby but joining the room will fail if not open. If not open, the room is excluded from random matchmaking. Due to racing conditions, found matches might become closed before they are joined. Simply re-connect to master and find another. Use property "IsVisible" to not list the room.

• bool IsVisible [get]

Defines if the room is listed in its lobby. Rooms can be created invisible, or changed to invisible. To change if a room can be joined, use property: open.

- Hashtable customProperties [get]
- string name [get]
- int playerCount [get, set]
- bool isLocalClientInside [get, set]
- byte maxPlayers [get]
- bool open [get]
- bool visible [get]

8.59.1 Detailed Description

A simplified room with just the info required to list and join, used for the room listing in the lobby. The properties are not settable (open, MaxPlayers, etc).

This class resembles info about available rooms, as sent by the Master server's lobby. Consider all values as readonly. None are synced (only updated by events by server).

8.59.2 Member Function Documentation

8.59.2.1 override bool RoomInfo.Equals (object other)

Makes RoomInfo comparable (by name).

```
8.59.2.2 override int RoomInfo.GetHashCode ( )
Accompanies Equals, using the name's HashCode as return.
Returns
8.59.2.3 override string RoomInfo.ToString ( )
Simple printingin method.
Returns
     Summary of this RoomInfo instance.
8.59.2.4 string RoomInfo.ToStringFull ( )
Simple printingin method.
Returns
     Summary of this RoomInfo instance.
8.59.3 Member Data Documentation
8.59.3.1 bool RoomInfo.autoCleanUpField = PhotonNetwork.autoCleanUpPlayerObjects [protected]
Backing field for property. False unless the GameProperty is set to true (else it's not sent).
8.59.3.2 int RoomInfo.emptyRoomTtlField = 0 [protected]
Backing field for property.
8.59.3.3 string[]RoomInfo.expectedUsersField [protected]
Backing field for property.
8.59.3.4 byte RoomInfo.maxPlayersField = 0 [protected]
Backing field for property.
8.59.3.5 string RoomInfo.nameField [protected]
Backing field for property.
8.59.3.6 bool RoomInfo.openField = true [protected]
Backing field for property.
```

```
8.59.3.7 int RoomInfo.playerTtlField = 0 [protected]
```

Backing field for property.

```
8.59.3.8 bool RoomInfo.visibleField = true [protected]
```

Backing field for property.

8.59.4 Property Documentation

```
8.59.4.1 Hashtable RoomInfo.CustomProperties [get]
```

Read-only "cache" of custom properties of a room. Set via Room.SetCustomProperties (not available for RoomInfo class!).

All keys are string-typed and the values depend on the game/application.

Room.SetCustomProperties

```
8.59.4.2 Hashtable RoomInfo.customProperties [get]
```

```
8.59.4.3 bool RoomInfo.IsLocalClientInside [get], [set]
```

State if the local client is already in the game or still going to join it on gameserver (in lobby always false).

```
8.59.4.4 bool RoomInfo.isLocalClientInside [get], [set]
```

```
8.59.4.5 bool RoomInfo.IsOpen [get]
```

Defines if the room can be joined. This does not affect listing in a lobby but joining the room will fail if not open. If not open, the room is excluded from random matchmaking. Due to racing conditions, found matches might become closed before they are joined. Simply re-connect to master and find another. Use property "IsVisible" to not list the room.

As part of RoomInfo this can't be set. As part of a Room (which the player joined), the setter will update the server and all clients.

```
8.59.4.6 bool RoomInfo.IsVisible [get]
```

Defines if the room is listed in its lobby. Rooms can be created invisible, or changed to invisible. To change if a room can be joined, use property: open.

As part of RoomInfo this can't be set. As part of a Room (which the player joined), the setter will update the server and all clients.

```
8.59.4.7 byte Roominfo.MaxPlayers [get]
```

Sets a limit of players to this room. This property is shown in lobby, too. If the room is full (players count == maxplayers), joining this room will fail.

As part of RoomInfo this can't be set. As part of a Room (which the player joined), the setter will update the server and all clients.

```
8.59.4.8 byte RoomInfo.maxPlayers [get]8.59.4.9 string RoomInfo.Name [get]
```

The name of a room. Unique identifier (per Loadbalancing group) for a room/match.

```
8.59.4.10 string RoomInfo.name [get]
8.59.4.11 bool RoomInfo.open [get]
8.59.4.12 int RoomInfo.PlayerCount [get], [set]
```

Only used internally in lobby, to display number of players in room (while you're not in).

```
8.59.4.13 int RoomInfo.playerCount [get], [set]
8.59.4.14 bool RoomInfo.removedFromList [get], [set]
```

Used internally in lobby, to mark rooms that are no longer listed.

```
8.59.4.15 bool RoomInfo.visible [get]
```

8.60 RoomOptions Class Reference

Wraps up common room properties needed when you create rooms. Read the individual entries for more details.

Public Attributes

byte MaxPlayers

Max number of players that can be in the room at any time. 0 means "no limit".

int PlayerTtl

Time To Live (TTL) for an 'actor' in a room. If a client disconnects, this actor is inactive first and removed after this timeout. In milliseconds.

int EmptyRoomTtl

Time To Live (TTL) for a room when the last player leaves. Keeps room in memory for case a player re-joins soon. In milliseconds.

· Hashtable CustomRoomProperties

The room's custom properties to set. Use string keys!

• string[] CustomRoomPropertiesForLobby = new string[0]

Defines the custom room properties that get listed in the lobby.

• string[] Plugins

Informs the server of the expected plugin setup.

Properties

• bool lsVisible [get, set]

Defines if this room is listed in the lobby. If not, it also is not joined randomly.

• bool IsOpen [get, set]

Defines if this room can be joined at all.

bool CleanupCacheOnLeave [get, set]

Removes a user's events and properties from the room when a user leaves.

bool SuppressRoomEvents [get]

Tells the server to skip room events for joining and leaving players.

• bool PublishUserId [get, set]

Defines if the Userlds of players get "published" in the room. Useful for FindFriends, if players want to play another game together.

• bool DeleteNullProperties [get, set]

Optionally, properties get deleted, when null gets assigned as value. Defaults to off / false.

- boolisVisible [get, set]
- boolisOpen [get, set]
- byte maxPlayers [get, set]
- bool cleanupCacheOnLeave [get, set]
- Hashtable customRoomProperties [get, set]
- string[] customRoomPropertiesForLobby [get, set]
- string[] plugins [get, set]
- bool suppressRoomEvents [get]
- bool publishUserId [get, set]

8.60.1 Detailed Description

Wraps up common room properties needed when you create rooms. Read the individual entries for more details.

This directly maps to the fields in the Room class.

8.60.2 Member Data Documentation

8.60.2.1 Hashtable RoomOptions.CustomRoomProperties

The room's custom properties to set. Use string keys!

Custom room properties are any key-values you need to define the game's setup. The shorter your keys are, the better. Example: Map, Mode (could be "m" when used with "Map"), TileSet (could be "t").

8.60.2.2 string [] RoomOptions.CustomRoomPropertiesForLobby = new string[0]

Defines the custom room properties that get listed in the lobby.

Name the custom room properties that should be available to clients that are in a lobby. Use with care. Unless a custom property is essential for matchmaking or user info, it should not be sent to the lobby, which causes traffic and delays for clients in the lobby.

Default: No custom properties are sent to the lobby.

8.60.2.3 int RoomOptions.EmptyRoomTtl

Time To Live (TTL) for a room when the last player leaves. Keeps room in memory for case a player re-joins soon. In milliseconds.

8.60.2.4 byte RoomOptions.MaxPlayers

Max number of players that can be in the room at any time. 0 means "no limit".

8.60.2.5 int RoomOptions.PlayerTtl

Time To Live (TTL) for an 'actor' in a room. If a client disconnects, this actor is inactive first and removed after this timeout. In milliseconds.

```
8.60.2.6 string [] RoomOptions.Plugins
```

Informs the server of the expected plugin setup.

The operation will fail in case of a plugin missmatch returning error code PluginMismatch 32757(0x7FFF - 10). Setting string[]{} means the client expects no plugin to be setup. Note: for backwards compatibility null omits any check.

8.60.3 Property Documentation

```
8.60.3.1 bool RoomOptions.CleanupCacheOnLeave [get], [set]
```

Removes a user's events and properties from the room when a user leaves.

This makes sense when in rooms where players can't place items in the room and just vanish entirely. When you disable this, the event history can become too long to load if the room stays in use indefinitely. Default: true. Cleans up the cache and props of leaving users.

```
8.60.3.2 bool RoomOptions.cleanupCacheOnLeave [get], [set]
8.60.3.3 Hashtable RoomOptions.customRoomProperties [get], [set]
8.60.3.4 string[] RoomOptions.customRoomPropertiesForLobby [get], [set]
8.60.3.5 bool RoomOptions.DeleteNullProperties [get], [set]
```

Optionally, properties get deleted, when null gets assigned as value. Defaults to off / false.

When Op SetProperties is setting a key's value to null, the server and clients should remove the key/value from the Custom Properties. By default, the server keeps the keys (and null values) and sends them to joining players.

Important: Only when SetProperties does a "broadcast", the change (key, value = null) is sent to clients to update accordingly. This applies to Custom Properties for rooms and actors/players.

```
8.60.3.6 bool RoomOptions.lsOpen [get], [set]
```

Defines if this room can be joined at all.

If a room is closed, no player can join this. As example this makes sense when 3 of 4 possible players start their gameplay early and don't want anyone to join during the game. The room can still be listed in the lobby (set IsVisible to control lobby-visibility).

```
8.60.3.7 bool RoomOptions.isOpen [get],[set]
8.60.3.8 bool RoomOptions.lsVisible [get],[set]
```

Defines if this room is listed in the lobby. If not, it also is not joined randomly.

A room that is not visible will be excluded from the room lists that are sent to the clients in lobbies. An invisible room can be joined by name but is excluded from random matchmaking.

Use this to "hide" a room and simulate "private rooms". Players can exchange a roomname and create it invisble to avoid anyone else joining it.

```
8.60.3.9 bool RoomOptions.isVisible [get], [set]
8.60.3.10 byte RoomOptions.maxPlayers [get], [set]
```

```
8.60.3.11 string[]RoomOptions.plugins [get], [set]
8.60.3.12 bool RoomOptions.PublishUserId [get], [set]
```

Defines if the Userlds of players get "published" in the room. Useful for FindFriends, if players want to play another game together.

When you set this to true, Photon will publish the Userlds of the players in that room. In that case, you can use PhotonPlayer.Userld, to access any player's userID. This is useful for FindFriends and to set "expected users" to reserve slots in a room (see PhotonNetwork.JoinRoom e.g.).

```
8.60.3.13 bool RoomOptions.publishUserId [get], [set]8.60.3.14 bool RoomOptions.SuppressRoomEvents [get]
```

Tells the server to skip room events for joining and leaving players.

Using this makes the client unaware of the other players in a room. That can save some traffic if you have some server logic that updates players but it can also limit the client's usability.

PUN will break if you use this, so it's not settable.

```
8.60.3.15 bool RoomOptions.suppressRoomEvents [get]
```

8.61 UnityEngine.SceneManagement.SceneManager Class Reference

Minimal implementation of the SceneManager for older Unity, up to v5.2.

Static Public Member Functions

- static void LoadScene (string name)
- static void LoadScene (int buildIndex)
- static AsyncOperation LoadSceneAsync (string name, LoadSceneMode mode=LoadSceneMode.Single)
- static AsyncOperation LoadSceneAsync (int buildIndex, LoadSceneMode mode=LoadSceneMode.Single)

8.61.1 Detailed Description

Minimal implementation of the SceneManager for older Unity, up to v5.2.

8.61.2 Member Function Documentation

```
8.61.2.1 static void UnityEngine.SceneManagement.SceneManager.LoadScene(string name) [static]
8.61.2.2 static void UnityEngine.SceneManagement.SceneManager.LoadScene(int buildIndex) [static]
8.61.2.3 static AsyncOperation UnityEngine.SceneManagement.SceneManager.LoadSceneAsync(string name, LoadSceneMode mode = LoadSceneMode.Single) [static]
8.61.2.4 static AsyncOperation UnityEngine.SceneManagement.SceneManager.LoadSceneAsync(int buildIndex, LoadSceneMode mode = LoadSceneMode.Single) [static]
```

8.62 SceneManagerHelper Class Reference

Properties

```
    static string ActiveSceneName [get]
    static int ActiveSceneBuildIndex [get]
```

8.62.1 Property Documentation

```
8.62.1.1 int SceneManagerHelper.ActiveSceneBuildIndex [static], [get]
8.62.1.2 string SceneManagerHelper.ActiveSceneName [static], [get]
```

8.63 ServerSettings Class Reference

Collection of connection-relevant settings, used internally by PhotonNetwork.ConnectUsingSettings. Inherits ScriptableObject.

Public Types

```
    enum HostingOption {
        HostingOption.NotSet = 0, HostingOption.PhotonCloud = 1, HostingOption.SelfHosted = 2, HostingOption.
        OfflineMode = 3,
        HostingOption.BestRegion = 4 }
```

Public Member Functions

- void UseCloudBestRegion (string cloudAppid)
- void UseCloud (string cloudAppid)
- void UseCloud (string cloudAppid, CloudRegionCode code)
- void UseMyServer (string serverAddress, int serverPort, string application)
- override string ToString ()

Static Public Member Functions

- static bool IsAppld (string val)
 Checks if a string is a Guid by attempting to create one.

 in the control of the property of the
- static void ResetBestRegionCodeInPreferences ()

Public Attributes

```
string AppID = ""string VoiceAppID = ""
```

- string ChatAppID = ""
- HostingOption HostType = HostingOption.NotSet
- CloudRegionCode PreferredRegion
- CloudRegionFlag EnabledRegions = (CloudRegionFlag)(-1)
- ConnectionProtocol Protocol = ConnectionProtocol.Udp
- string ServerAddress = ""
- int ServerPort = 5055
- int VoiceServerPort = 5055
- bool JoinLobby
- · bool EnableLobbyStatistics

- PhotonLogLevel PunLogging = PhotonLogLevel.ErrorsOnly
- DebugLevel NetworkLogging = DebugLevel.ERROR
- bool RunInBackground = true
- List< string > RpcList = new List<string>()
- · bool DisableAutoOpenWizard

Properties

• static CloudRegionCode BestRegionCodeInPreferences [get]

Gets the best region code in preferences. This composes the PhotonHandler, since its Internal and can not be accessed by the custom inspector

8.63.1 Detailed Description

Collection of connection-relevant settings, used internally by PhotonNetwork.ConnectUsingSettings.

8.63.2 Member Enumeration Documentation

8.63.2.1 enum ServerSettings.HostingOption

Enumerator

NotSet

PhotonCloud

SelfHosted

OfflineMode

BestRegion

8.63.3 Member Function Documentation

```
8.63.3.1 static bool ServerSettings.lsAppld ( string val ) [static]
```

Checks if a string is a Guid by attempting to create one.

Parameters

val	The potential guid to check.

Returns

True if new Guid(val) did not fail.

- 8.63.3.2 static void ServerSettings.ResetBestRegionCodeInPreferences() [static]8.63.3.3 override string ServerSettings.ToString()
- 8.63.3.4 void ServerSettings.UseCloud (string cloudAppid)
- 8.63.3.5 void ServerSettings.UseCloud (string cloudAppid, CloudRegionCode code)
- 8.63.3.6 void ServerSettings.UseCloudBestRegion (string cloudAppid)

```
void ServerSettings.UseMyServer ( string serverAddress, int serverPort, string application )
8.63.4 Member Data Documentation
8.63.4.1 string ServerSettings.AppID = ""
8.63.4.2 string ServerSettings.ChatAppID = ""
8.63.4.3 bool ServerSettings.DisableAutoOpenWizard
8.63.4.4 CloudRegionFlag ServerSettings.EnabledRegions = (CloudRegionFlag)(-1)
8.63.4.5 bool ServerSettings.EnableLobbyStatistics
8.63.4.6 HostingOption ServerSettings.HostType = HostingOption.NotSet
8.63.4.7 bool ServerSettings.JoinLobby
8.63.4.8 DebugLevel ServerSettings.NetworkLogging = DebugLevel.ERROR
8.63.4.9 CloudRegionCode ServerSettings.PreferredRegion
8.63.4.10 ConnectionProtocol ServerSettings.Protocol = ConnectionProtocol.Udp
8.63.4.11 PhotonLogLevel ServerSettings.PunLogging = PhotonLogLevel.ErrorsOnly
8.63.4.12 List<string> ServerSettings.RpcList = new List<string>()
8.63.4.13 bool ServerSettings.RunInBackground = true
8.63.4.14 string ServerSettings.ServerAddress = ""
8.63.4.15 int ServerSettings.ServerPort = 5055
8.63.4.16 string ServerSettings.VoiceAppID = ""
8.63.4.17 int ServerSettings.VoiceServerPort = 5055
8.63.5 Property Documentation
8.63.5.1 CloudRegionCode ServerSettings.BestRegionCodeInPreferences [static], [get]
```

Gets the best region code in preferences. This composes the PhotonHandler, since its Internal and can not be accessed by the custom inspector

The best region code in preferences.

8.64 PhotonAnimatorView.SynchronizedLayer Class Reference

Public Attributes

- SynchronizeType SynchronizeType
- int LayerIndex

- 8.64.1 Member Data Documentation
- 8.64.1.1 int PhotonAnimatorView.SynchronizedLayer.LayerIndex
- 8.64.1.2 SynchronizeType PhotonAnimatorView.SynchronizedLayer.SynchronizeType

8.65 PhotonAnimatorView.SynchronizedParameter Class Reference

Public Attributes

- · ParameterType Type
- SynchronizeType SynchronizeType
- string Name

8.65.1 Member Data Documentation

- 8.65.1.1 string PhotonAnimatorView.SynchronizedParameter.Name
- 8.65.1.2 SynchronizeType PhotonAnimatorView.SynchronizedParameter.SynchronizeType
- 8.65.1.3 ParameterType PhotonAnimatorView.SynchronizedParameter.Type

8.66 TypedLobby Class Reference

Refers to a specific lobby (and type) on the server.

Inherited by TypedLobbyInfo.

Public Member Functions

- TypedLobby ()
- TypedLobby (string name, LobbyType type)
- override string ToString ()

Public Attributes

• string Name

Name of the lobby this game gets added to. Default: null, attached to default lobby. Lobbies are unique per lobbyName plus lobbyType, so the same name can be used when several types are existing.

LobbyType Type

Type of the (named)lobby this game gets added to

Static Public Attributes

• static readonly TypedLobby Default = new TypedLobby()

Properties

bool IsDefault [get]

8.66.1 Detailed Description

Refers to a specific lobby (and type) on the server.

The name and type are the unique identifier for a lobby. Join a lobby via PhotonNetwork.JoinLobby(TypedLobby lobby). The current lobby is stored in PhotonNetwork.lobby.

8.66.2 Constructor & Destructor Documentation

```
8.66.2.1 TypedLobby.TypedLobby ( )
```

8.66.2.2 TypedLobby.TypedLobby (string name, LobbyType type)

8.66.3 Member Function Documentation

8.66.3.1 override string TypedLobby.ToString ()

8.66.4 Member Data Documentation

8.66.4.1 readonly TypedLobby TypedLobby.Default = new TypedLobby() [static]

8.66.4.2 string TypedLobby.Name

Name of the lobby this game gets added to. Default: null, attached to default lobby. Lobbies are unique per lobbyName plus lobbyType, so the same name can be used when several types are existing.

8.66.4.3 LobbyType TypedLobby.Type

Type of the (named)lobby this game gets added to

8.66.5 Property Documentation

8.66.5.1 bool TypedLobby.lsDefault [get]

8.67 TypedLobbyInfo Class Reference

Inherits TypedLobby.

Public Member Functions

• override string ToString ()

Public Attributes

- int PlayerCount
- int RoomCount

Additional Inherited Members

8.67.1 Member Function Documentation

```
8.67.1.1 override string TypedLobbyInfo.ToString ( )8.67.2 Member Data Documentation
```

8.67.2.1 int TypedLobbyInfo.PlayerCount

8.67.2.2 int TypedLobbyInfo.RoomCount

8.68 WebRpcResponse Class Reference

Reads an operation response of a WebRpc and provides convenient access to most common values.

Public Member Functions

• WebRpcResponse (OperationResponse response)

An OperationResponse for a WebRpc is needed to read it's values.

• string ToStringFull ()

Turns the response into an easier to read string.

Properties

• string Name [get, set]

Name of the WebRpc that was called.

• int ReturnCode [get, set]

ReturnCode of the WebService that answered the WebRpc.

• string DebugMessage [get, set]

Might be empty or null.

• Dictionary < string, object > Parameters [get, set]

Other key/values returned by the webservice that answered the WebRpc.

8.68.1 Detailed Description

Reads an operation response of a WebRpc and provides convenient access to most common values.

See method PhotonNetwork.WebRpc.

Create a WebRpcResponse to access common result values.

The operationResponse.OperationCode should be: OperationCode.WebRpc.

8.68.2 Constructor & Destructor Documentation

8.68.2.1 WebRpcResponse.WebRpcResponse (OperationResponse response)

An OperationResponse for a WebRpc is needed to read it's values.

8.68.3 Member Function Documentation

8.68.3.1 string WebRpcResponse.ToStringFull ()

Turns the response into an easier to read string.

Returns

String resembling the result.

8.68.4 Property Documentation

8.68.4.1 string WebRpcResponse.DebugMessage [get], [set]

Might be empty or null.

8.68.4.2 string WebRpcResponse.Name [get], [set]

Name of the WebRpc that was called.

8.68.4.3 Dictionary<string, object> WebRpcResponse.Parameters [get], [set]

Other key/values returned by the webservice that answered the WebRpc.

8.68.4.4 int WebRpcResponse.ReturnCode [get], [set]

ReturnCode of the WebService that answered the WebRpc.

0 is commonly used to signal success.

-1 tells you: Got no ReturnCode from WebRpc service.

Other ReturnCodes are defined by the individual WebRpc and service.

Chapter 9

File Documentation

- 9.1 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/general.md File Reference
- 9.2 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/main.md File Reference
- 9.3 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/optional
 Gui.md File Reference
- 9.4 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/photon
 StatsGui.md File Reference
- 9.5 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/_Doc/public

 Api.md File Reference
- 9.6 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/CustomTypes.cs File Reference

Sets up support for Unity-specific types. Can be a blueprint how to register your own Custom Types for sending.

Classes

class CustomTypes

Internally used class, containing de/serialization methods for various Unity-specific classes. Adding those to the Photon serialization protocol allows you to send them in events, etc.

9.6.1 Detailed Description

Sets up support for Unity-specific types. Can be a blueprint how to register your own Custom Types for sending.

210 File Documentation

9.7 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Enums.cs File Reference

Wraps up several of the commonly used enumerations.

Classes

• class EncryptionDataParameters

Enumerations

enum PhotonNetworkingMessage {

PhotonNetworkingMessage.OnConnectedToPhoton, PhotonNetworkingMessage.OnLeftRoom, Photon← NetworkingMessage.OnMasterClientSwitched, PhotonNetworkingMessage.OnPhotonCreateRoomFailed, PhotonNetworkingMessage.OnPhotonJoinRoomFailed, PhotonNetworkingMessage.OnCreatedRoom, PhotonNetworkingMessage.OnJoinedLobby, PhotonNetworkingMessage.OnLeftLobby, PhotonNetworkingMessage.OnDisconnectedFromPhoton, PhotonNetworkingMessage.OnConnectionFail, PhotonNetworkingMessage.OnFailedToConnectToPhoton, PhotonNetworkingMessage.OnReceivedRoom← ListUpdate.

PhotonNetworkingMessage.OnJoinedRoom, PhotonNetworkingMessage.OnPhotonPlayerConnected, PhotonNetworkingMessage.OnPhotonPlayerDisconnected, PhotonNetworkingMessage.OnPhoton← RandomJoinFailed.

PhotonNetworkingMessage.OnConnectedToMaster, PhotonNetworkingMessage.OnPhotonSerializeView, PhotonNetworkingMessage.OnPhotonInstantiate, PhotonNetworkingMessage.OnPhotonMaxCccuReached, PhotonNetworkingMessage.OnPhotonCustomRoomPropertiesChanged, PhotonNetworkingMessage.On← PhotonPlayerPropertiesChanged, PhotonNetworkingMessage.OnUpdatedFriendList, PhotonNetworking← Message.OnCustomAuthenticationFailed,

PhotonNetworkingMessage.OnCustomAuthenticationResponse, PhotonNetworkingMessage.OnWebRpc← Response, PhotonNetworkingMessage.OnOwnershipRequest, PhotonNetworkingMessage.OnLobby← StatisticsUpdate.

PhotonNetworkingMessage.OnPhotonPlayerActivityChanged, PhotonNetworkingMessage.OnOwnership ← Transfered }

This enum defines the set of MonoMessages Photon Unity Networking is using as callbacks. Implemented by Pun⇔

- enum PhotonLogLevel { PhotonLogLevel.ErrorsOnly, PhotonLogLevel.Informational, PhotonLogLevel.Full }

 Used to define the level of logging output created by the PUN classes. Either log errors, info (some more) or full.
- enum PhotonTargets {
 PhotonTargets.All, PhotonTargets.Others, PhotonTargets.MasterClient, PhotonTargets.AllBuffered,
 PhotonTargets.OthersBuffered, PhotonTargets.AllViaServer, PhotonTargets.AllBufferedViaServer }

Enum of "target" options for RPCs. These define which remote clients get your RPC call.

enum CloudRegionCode {
 CloudRegionCode.eu = 0, CloudRegionCode.us = 1, CloudRegionCode.asia = 2, CloudRegionCode.jp = 3,
 CloudRegionCode.au = 5, CloudRegionCode.usw = 6, CloudRegionCode.sa = 7, CloudRegionCode.cae = 8,
 CloudRegionCode.kr = 9, CloudRegionCode.in = 10, CloudRegionCode.ru = 11, CloudRegionCode.rue = 12,
 CloudRegionCode.none = 4 }

Currently available Photon Cloud regions as enum.

enum CloudRegionFlag {
 CloudRegionFlag.eu = 1 << 0, CloudRegionFlag.us = 1 << 1, CloudRegionFlag.asia = 1 << 2, Cloud
 RegionFlag.jp = 1 << 3,
 CloudRegionFlag.au = 1 << 4, CloudRegionFlag.usw = 1 << 5, CloudRegionFlag.sa = 1 << 6, Cloud
 RegionFlag.cae = 1 << 7,
 CloudRegionFlag.kr = 1 << 8, CloudRegionFlag.in = 1 << 9, CloudRegionFlag.ru = 1 << 10, Cloud
 RegionFlag.rue = 1 << 11 }

Available regions as enum of flags. To be used as "enabled" flags for Best Region pinging.

enum ConnectionState {
 ConnectionState.Disconnected, ConnectionState.Connection, ConnectionState.Connection,
 State.Disconnecting,
 ConnectionState.InitializingApplication }

High level connection state of the client. Better use the more detailed ClientState.

enum EncryptionMode { EncryptionMode.PayloadEncryption, EncryptionMode.DatagramEncryption = 10 }
 Defines how the communication gets encrypted.

9.7.1 Detailed Description

Wraps up several of the commonly used enumerations.

9.7.2 Enumeration Type Documentation

9.7.2.1 enum CloudRegionCode

Currently available Photon Cloud regions as enum.

This is used in PhotonNetwork.ConnectToRegion.

Enumerator

```
eu European servers in Amsterdam.
us US servers (East Coast).
asia Asian servers in Singapore.
jp Japanese servers in Tokyo.
au Australian servers in Melbourne.summary>USA West, San José, usw
usw summary>South America, Sao Paulo, sa
sa summary>Canada East, Montreal, cae
cae summary>South Korea, Seoul, kr
kr summary>India, Chennai, in
in
ru Russia, ru
rue Russia East, rue
none No region selected.
```

9.7.2.2 enum CloudRegionFlag

Available regions as enum of flags. To be used as "enabled" flags for Best Region pinging.

Note that these enum values skip CloudRegionCode.none and their values are in strict order (power of 2).

Enumerator

eu us asia jp au usw

sa

212 File Documentation

cae

kr

in

ru

rue

9.7.2.3 enum ConnectionState

High level connection state of the client. Better use the more detailed ClientState.

Enumerator

Disconnected

Connecting

Connected

Disconnecting

InitializingApplication

9.7.2.4 enum EncryptionMode

Defines how the communication gets encrypted.

Enumerator

PayloadEncryption This is the default encryption mode: Messages get encrypted only on demand (when you send operations with the "encrypt" parameter set to true).

DatagramEncryption With this encryption mode for UDP, the connection gets setup and all further datagrams get encrypted almost entirely. On-demand message encryption (like in PayloadEncryption) is skipped. This mode requires AuthOnce or AuthOnceWss as AuthMode!

9.8 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Extensions.cs File Reference

Classes

· class Extensions

This static class defines some useful extension methods for several existing classes (e.g. Vector3, float and others).

class GameObjectExtensions

Small number of extension methods that make it easier for PUN to work cross-Unity-versions.

Typedefs

- using Hashtable = ExitGames.Client.Photon.Hashtable
- using SupportClassPun = ExitGames.Client.Photon.SupportClass

- 9.8.1 Typedef Documentation
- 9.8.1.1 using Hashtable = ExitGames.Client.Photon.Hashtable
- 9.8.1.2 using SupportClassPun = ExitGames.Client.Photon.SupportClass
- 9.9 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/FriendInfo.cs File Reference

Classes

· class FriendInfo

Used to store info about a friend's online state and in which room he/she is.

9.10 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/GizmoType.cs File Reference

Classes

· class ExitGames.Client.GUI.GizmoTypeDrawer

Namespaces

package ExitGames.Client.GUI

Enumerations

- enum ExitGames.Client.GUI.GizmoType { ExitGames.Client.GUI.GizmoType.WireSphere, ExitGames.←
 Client.GUI.GizmoType.Sphere, ExitGames.Client.GUI.GizmoType.WireCube, ExitGames.Client.GUI.←
 GizmoType.Cube }
- 9.11 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/LoadbalancingPeer.cs File Reference

Classes

class LoadBalancingPeer

A LoadbalancingPeer provides the operations and enum definitions needed to use the loadbalancing server application which is also used in Photon Cloud.

- class OpJoinRandomRoomParams
- class EnterRoomParams
- class ErrorCode

ErrorCode defines the default codes associated with Photon client/server communication.

class ActorProperties

Class for constants. These (byte) values define "well known" properties for an Actor / Player.

class GamePropertyKey

Class for constants. These (byte) values are for "well known" room/game properties used in Photon Loadbalancing.

class EventCode

Class for constants. These values are for events defined by Photon Loadbalancing.

214 File Documentation

· class ParameterCode

Class for constants. Codes for parameters of Operations and Events.

· class OperationCode

Class for constants. Contains operation codes. Pun uses these constants internally.

class RoomOptions

Wraps up common room properties needed when you create rooms. Read the individual entries for more details.

class RaiseEventOptions

Aggregates several less-often used options for operation RaiseEvent. See field descriptions for usage details.

class TypedLobby

Refers to a specific lobby (and type) on the server.

- · class TypedLobbyInfo
- · class Authentication Values

Container for user authentication in Photon. Set AuthValues before you connect - all else is handled.

· class FindFriendsOptions

Options for OpFindFriends can be combined to filter which rooms of friends are returned.

Enumerations

enum JoinMode: byte { JoinMode.Default = 0, JoinMode.CreatelfNotExists = 1, JoinMode.JoinOrRejoin = 2, JoinMode.RejoinOnly = 3 }

Defines possible values for OpJoinRoom and OpJoinOrCreate. It tells the server if the room can be only be joined normally, created implicitly or found on a web-service for Turnbased games.

 enum MatchmakingMode: byte { MatchmakingMode.FillRoom = 0, MatchmakingMode.SerialMatching = 1, MatchmakingMode.RandomMatching = 2 }

Options for matchmaking rules for OpJoinRandom.

enum ReceiverGroup: byte { ReceiverGroup.Others = 0, ReceiverGroup.All = 1, ReceiverGroup.MasterClient = 2 }

Lite - OpRaiseEvent lets you chose which actors in the room should receive events. By default, events are sent to "Others" but you can overrule this.

• enum EventCaching : byte {

EventCaching.DoNotCache = 0, EventCaching.MergeCache = 1, EventCaching.ReplaceCache = 2, Event ← Caching.RemoveCache = 3,

EventCaching.AddToRoomCache = 4, EventCaching.AddToRoomCacheGlobal = 5, EventCaching.Remove FromRoomCache = 6, EventCaching.RemoveFromRoomCacheForActorsLeft = 7,

EventCaching.SliceIncreaseIndex = 10, EventCaching.SliceSetIndex = 11, EventCaching.SlicePurgeIndex = 12, EventCaching.SlicePurgeUpToIndex = 13 }

Lite - OpRaiseEvent allows you to cache events and automatically send them to joining players in a room. Events are cached per event code and player: Event 100 (example!) can be stored once per player. Cached events can be modified, replaced and removed.

enum PropertyTypeFlag: byte { PropertyTypeFlag.None = 0x00, PropertyTypeFlag.Game = 0x01, Property
 — TypeFlag.Actor = 0x02, PropertyTypeFlag.GameAndActor = Game | Actor }

Flags for "types of properties", being used as filter in OpGetProperties.

enum LobbyType: byte { LobbyType.Default = 0, LobbyType.SqlLobby = 2, LobbyType.AsyncRandomLobby = 3 }

Options of lobby types available. Lobby types might be implemented in certain Photon versions and won't be available on older servers.

enum AuthModeOption { AuthModeOption.Auth, AuthModeOption.AuthOnce, AuthModeOption.AuthOnce, Wss }

Options for authentication modes. From "classic" auth on each server to AuthOnce (on NameServer).

• enum CustomAuthenticationType : byte {

CustomAuthenticationType.Custom = 0, CustomAuthenticationType.Steam = 1, CustomAuthenticationType. ← Facebook = 2, CustomAuthenticationType.Oculus = 3,

CustomAuthenticationType.PlayStation = 4, CustomAuthenticationType.Xbox = 5, CustomAuthentication← Type.Viveport = 10, CustomAuthenticationType.NintendoSwitch = 11,

CustomAuthenticationType.None = byte.MaxValue }

Options for optional "Custom Authentication" services used with Photon. Used by OpAuthenticate after connecting to Photon.

9.11.1 Enumeration Type Documentation

9.11.1.1 enum AuthModeOption

Options for authentication modes. From "classic" auth on each server to AuthOnce (on NameServer).

Enumerator

Auth

AuthOnce

AuthOnceWss

9.11.1.2 enum CustomAuthenticationType : byte

Options for optional "Custom Authentication" services used with Photon. Used by OpAuthenticate after connecting to Photon.

Enumerator

Custom Use a custom authentification service. Currently the only implemented option.

Steam Authenticates users by their Steam Account. Set auth values accordingly!

Facebook Authenticates users by their Facebook Account. Set auth values accordingly!

Oculus Authenticates users by their Oculus Account and token.

PlayStation Authenticates users by their PSN Account and token.

Xbox Authenticates users by their Xbox Account and XSTS token.

Viveport Authenticates users by their HTC VIVEPORT Account and user token. Set AuthGetParameters to "userToken=[userToken]"

NintendoSwitch Authenticates users by their NSA ID.

None Disables custom authentification. Same as not providing any Authentication Values for connect (more precisely for: OpAuthenticate).

9.11.1.3 enum EventCaching: byte

Lite - OpRaiseEvent allows you to cache events and automatically send them to joining players in a room. Events are cached per event code and player: Event 100 (example!) can be stored once per player. Cached events can be modified, replaced and removed.

Caching works only combination with ReceiverGroup options Others and All.

Enumerator

DoNotCache Default value (not sent).

MergeCache Will merge this event's keys with those already cached.

ReplaceCache Replaces the event cache for this eventCode with this event's content.

RemoveCache Removes this event (by eventCode) from the cache.

AddToRoomCache Adds an event to the room's cache

AddToRoomCacheGlobal Adds this event to the cache for actor 0 (becoming a "globally owned" event in the cache).

RemoveFromRoomCache Remove fitting event from the room's cache.

216 File Documentation

RemoveFromRoomCacheForActorsLeft Removes events of players who already left the room (cleaning up).

SliceIncreaseIndex Increase the index of the sliced cache.

SliceSetIndex Set the index of the sliced cache. You must set RaiseEventOptions.CacheSliceIndex for this.

SlicePurgeIndex Purge cache slice with index. Exactly one slice is removed from cache. You must set RaiseEventOptions.CacheSliceIndex for this.

SlicePurgeUpToIndex Purge cache slices with specified index and anything lower than that. You must set RaiseEventOptions.CacheSliceIndex for this.

9.11.1.4 enum JoinMode : byte

Defines possible values for OpJoinRoom and OpJoinOrCreate. It tells the server if the room can be only be joined normally, created implicitly or found on a web-service for Turnbased games.

These values are not directly used by a game but implicitly set.

Enumerator

Default Regular join. The room must exist.

CreatelfNotExists Join or create the room if it's not existing. Used for OpJoinOrCreate for example.

JoinOrRejoin The room might be out of memory and should be loaded (if possible) from a Turnbased webservice.

RejoinOnly Only re-join will be allowed. If the user is not yet in the room, this will fail.

9.11.1.5 enum LobbyType: byte

Options of lobby types available. Lobby types might be implemented in certain Photon versions and won't be available on older servers.

Enumerator

Default This lobby is used unless another is defined by game or JoinRandom. Room-lists will be sent and JoinRandomRoom can filter by matching properties.

SqlLobby This lobby type lists rooms like Default but JoinRandom has a parameter for SQL-like "where" clauses for filtering. This allows bigger, less, or and and combinations.

AsyncRandomLobby This lobby does not send lists of games. It is only used for OpJoinRandomRoom. It keeps rooms available for a while when there are only inactive users left.

9.11.1.6 enum MatchmakingMode: byte

Options for matchmaking rules for OpJoinRandom.

Enumerator

FillRoom Fills up rooms (oldest first) to get players together as fast as possible. Default.Makes most sense with MaxPlayers > 0 and games that can only start with more players.

SerialMatching Distributes players across available rooms sequentially but takes filter into account. Without filter, rooms get players evenly distributed.

RandomMatching Joins a (fully) random room. Expected properties must match but aside from this, any available room might be selected.

9.11.1.7 enum PropertyTypeFlag: byte

Flags for "types of properties", being used as filter in OpGetProperties.

Enumerator

None (0x00) Flag type for no property type.

Game (0x01) Flag type for game-attached properties.

Actor (0x02) Flag type for actor related propeties.

GameAndActor (0x01) Flag type for game AND actor properties. Equal to 'Game'

9.11.1.8 enum ReceiverGroup: byte

Lite - OpRaiseEvent lets you chose which actors in the room should receive events. By default, events are sent to "Others" but you can overrule this.

Enumerator

Others Default value (not sent). Anyone else gets my event.

All Everyone in the current room (including this peer) will get this event.

MasterClient The server sends this event only to the actor with the lowest actorNumber. The "master client" does not have special rights but is the one who is in this room the longest time.

9.12 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/NetworkingPeer.cs File Reference

Classes

· class NetworkingPeer

Implements Photon LoadBalancing used in PUN. This class is used internally by PhotonNetwork and not intended as public API.

Typedefs

- using Hashtable = ExitGames.Client.Photon.Hashtable
- using SupportClassPun = ExitGames.Client.Photon.SupportClass

Enumerations

enum ClientState {

ClientState.Uninitialized, ClientState.PeerCreated, ClientState.Queued, ClientState.Authenticated, ClientState.JoinedLobby, ClientState.DisconnectingFromMasterserver, ClientState.ConnectingToGameserver, ClientState.ConnectedToGameserver,

ClientState.Joining, ClientState.Joined, ClientState.Leaving, ClientState.DisconnectingFromGameserver, ClientState.ConnectingToMasterserver, ClientState.QueuedComingFromGameserver, ClientState.Disconnecting, ClientState.Disconnected,

 $\label{lem:connectedToName} ClientState. Connected ToName Server, \ ClientState. Connected ToName \\ \ Server, \ ClientState. Disconnecting From Name Server, \\ \ ClientState. Disconne$

ClientState.Authenticating }

Detailed connection / networking peer state. PUN implements a loadbalancing and authentication workflow "behind the scenes", so some states will automatically advance to some follow up state. Those states are commented with "(will-change)".

• enum DisconnectCause {

DisconnectCause.DisconnectByServerUserLimit = StatusCode.DisconnectByServerUserLimit, Disconnect← Cause.ExceptionOnConnect = StatusCode.ExceptionOnConnect, DisconnectCause.DisconnectByServer← Timeout = StatusCode.DisconnectByServerTimeout, DisconnectCause.DisconnectByServerLogic = Status← Code.DisconnectByServerLogic,

DisconnectCause.Exception = StatusCode.Exception, DisconnectCause.InvalidAuthentication = Error ← Code.InvalidAuthentication, DisconnectCause.MaxCcuReached = ErrorCode.MaxCcuReached, Disconnect ← Cause.InvalidRegion = ErrorCode.InvalidRegion,

DisconnectCause.SecurityExceptionOnConnect = StatusCode.SecurityExceptionOnConnect, Disconnect← Cause.DisconnectByClientTimeout = StatusCode.TimeoutDisconnect, DisconnectCause.InternalReceive← Exception = StatusCode.ExceptionOnReceive, DisconnectCause.AuthenticationTicketExpired = 32753 }

Summarizes the cause for a disconnect. Used in: OnConnectionFail and OnFailedToConnectToPhoton.

enum ServerConnection { ServerConnection.MasterServer, ServerConnection.GameServer, Server
 — Connection.NameServer }

Available server (types) for internally used field: server.

9.12.1 Typedef Documentation

- 9.12.1.1 using Hashtable = ExitGames.Client.Photon.Hashtable
- 9.12.1.2 using SupportClassPun = ExitGames.Client.Photon.SupportClass

9.12.2 Enumeration Type Documentation

9.12.2.1 enum ServerConnection

Available server (types) for internally used field: server.

Photon uses 3 different roles of servers: Name Server, Master Server and Game Server.

Enumerator

MasterServer This server is where matchmaking gets done and where clients can get lists of rooms in lobbies.

GameServer This server handles a number of rooms to execute and relay the messages between players (in a room).

NameServer This server is used initially to get the address (IP) of a Master Server for a specific region. Not used for Photon OnPremise (self hosted).

9.13 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonClasses.cs File Reference

Wraps up smaller classes that don't need their own file.

Classes

• interface IPunObservable

Defines the OnPhotonSerializeView method to make it easy to implement correctly for observable scripts.

interface IPunCallbacks

This interface is used as definition of all callback methods of PUN, except OnPhotonSerializeView. Preferably, implement them individually.

• interface IPunPrefabPool

Defines all the methods that a Object Pool must implement, so that PUN can use it.

· class Photon.MonoBehaviour

This class adds the property photonView, while logging a warning when your game still uses the networkView.

class Photon.PunBehaviour

This class provides a .photonView and all callbacks/events that PUN can call. Override the events/methods you want to use.

· struct PhotonMessageInfo

Container class for info about a particular message, RPC or update.

class PunEvent

Defines Photon event-codes as used by PUN.

· class PhotonStream

This container is used in OnPhotonSerializeView() to either provide incoming data of a PhotonView or for you to provide it.

class HelpURL

Empty implementation of the upcoming HelpURL of Unity 5.1. This one is only for compatibility of attributes.

· class UnityEngine.SceneManagement.SceneManager

Minimal implementation of the SceneManager for older Unity, up to v5.2.

- · class SceneManagerHelper
- class WebRpcResponse

Reads an operation response of a WebRpc and provides convenient access to most common values.

Namespaces

- package Photon
- · package UnityEngine.SceneManagement

Typedefs

- using Hashtable = ExitGames.Client.Photon.Hashtable
- using SupportClassPun = ExitGames.Client.Photon.SupportClass
- using Photon.Hashtable = ExitGames.Client.Photon.Hashtable

Enumerations

9.13.1 Detailed Description

Wraps up smaller classes that don't need their own file.

9.13.2 Typedef Documentation

- 9.13.2.1 using Hashtable = ExitGames.Client.Photon.Hashtable
- 9.13.2.2 using SupportClassPun = ExitGames.Client.Photon.SupportClass

9.14 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonHandler.cs File Reference

Classes

· class PhotonHandler

Internal Monobehaviour that allows Photon to run an Update loop.

Typedefs

- using Debug = UnityEngine.Debug
- using Hashtable = ExitGames.Client.Photon.Hashtable
- using SupportClassPun = ExitGames.Client.Photon.SupportClass

9.14.1 Typedef Documentation

- 9.14.1.1 using Debug = UnityEngine.Debug
- 9.14.1.2 using Hashtable = ExitGames.Client.Photon.Hashtable
- 9.14.1.3 using SupportClassPun = ExitGames.Client.Photon.SupportClass

9.15 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonLagSimulationGui.cs File Reference

Part of the Optional GUI.

Classes

· class PhotonLagSimulationGui

This MonoBehaviour is a basic GUI for the Photon client's network-simulation feature. It can modify lag (fixed delay), jitter (random lag) and packet loss.

9.15.1 Detailed Description

Part of the Optional GUI.

9.16 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonNetwork.cs File Reference

Classes

· class PhotonNetwork

The main class to use the PhotonNetwork plugin. This class is static.

Typedefs

- using Debug = UnityEngine.Debug
- using Hashtable = ExitGames.Client.Photon.Hashtable

9.16.1 Typedef Documentation

- 9.16.1.1 using Debug = UnityEngine.Debug
- 9.16.1.2 using Hashtable = ExitGames.Client.Photon.Hashtable

9.17 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Networking/Plugins/PhotonNetwork/PhotonPing.cs File Reference

Unity

Classes

- · class Photon.Realtime.PhotonPing
- · class Photon.Realtime.PingMono

Uses C# Socket class from System.Net.Sockets (as Unity usually does).

Namespaces

· package Photon.Realtime

9.18 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonPlayer.cs File Reference

Classes

· class PhotonPlayer

Summarizes a "player" within a room, identified (in that room) by actorID.

Typedefs

- using Hashtable = ExitGames.Client.Photon.Hashtable
- 9.18.1 Typedef Documentation
- 9.18.1.1 using Hashtable = ExitGames.Client.Photon.Hashtable
- 9.19 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonStatsGui.cs File Reference

Part of the Optional GUI.

Classes

· class PhotonStatsGui

Basic GUI to show traffic and health statistics of the connection to Photon, toggled by shift+tab.

9.19.1 Detailed Description

Part of the Optional GUI.

9.20 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonStreamQueue.cs File Reference

Classes

· class PhotonStreamQueue

The PhotonStreamQueue helps you poll object states at higher frequencies then what PhotonNetwork.sendRate dictates and then sends all those states at once when Serialize() is called. On the receiving end you can call Deserialize() and then the stream will roll out the received object states in the same order and timeStep they were recorded in.

9.21 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PhotonView.cs File Reference

Classes

· class PhotonView

PUN's NetworkView replacement class for networking. Use it like a NetworkView.

Enumerations

- enum ViewSynchronization { ViewSynchronization.Off, ViewSynchronization.ReliableDeltaCompressed, ViewSynchronization.Unreliable, ViewSynchronization.UnreliableOnChange }
- enum OnSerializeTransform {
 OnSerializeTransform.OnlyPosition, OnSerializeTransform.OnlyRotation, OnSerializeTransform.PositionAndRotation,
 OnSerializeTransform.All }
- enum OwnershipOption { OwnershipOption.Fixed, OwnershipOption.Takeover, OwnershipOption.Request } Options to define how Ownership Transfer is handled per PhotonView.

9.21.1 Enumeration Type Documentation

9.21.1.1 enum OnSerializeRigidBody

Enumerator

OnlyVelocity OnlyAngularVelocity All

9.21.1.2 enum OnSerializeTransform

Enumerator

OnlyPosition
OnlyRotation
OnlyScale
PositionAndRotation
All

9.21.1.3 enum OwnershipOption

Options to define how Ownership Transfer is handled per PhotonView.

This setting affects how RequestOwnership and TransferOwnership work at runtime.

Enumerator

Fixed Ownership is fixed. Instantiated objects stick with their creator, scene objects always belong to the Master Client.

Takeover Ownership can be taken away from the current owner who can't object.

Request Ownership can be requested with PhotonView.RequestOwnership but the current owner has to agree to give up ownership. The current owner has to implement IPunCallbacks.OnOwnershipRequest to react to the ownership request.

9.21.1.4 enum ViewSynchronization

Enumerator

Off

ReliableDeltaCompressed

Unreliable

UnreliableOnChange

9.22 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/PingCloudRegions.cs File Reference

Classes

· class PingMonoEditor

Uses C# Socket class from System.Net.Sockets (as Unity usually does).

· class PhotonPingManager

Typedefs

- using Debug = UnityEngine.Debug
- using SupportClassPun = ExitGames.Client.Photon.SupportClass

9.22.1 Typedef Documentation

9.22.1.1 using Debug = UnityEngine.Debug

9.22.1.2 using SupportClassPun = ExitGames.Client.Photon.SupportClass

9.23 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Room.cs File Reference

Classes

• class Room

This class resembles a room that PUN joins (or joined). The properties are settable as opposed to those of a Room⊷ Info and you can close or hide "your" room.

9.24 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/RoomInfo.cs File Reference

Classes

· class RoomInfo

A simplified room with just the info required to list and join, used for the room listing in the lobby. The properties are not settable (open, MaxPlayers, etc).

9.25 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/RPC.cs File Reference

Reimplements a RPC Attribute, as it's no longer in all versions of the UnityEngine assembly.

Classes

class PunRPC

Replacement for RPC attribute with different name. Used to flag methods as remote-callable.

9.25.1 Detailed Description

Reimplements a RPC Attribute, as it's no longer in all versions of the UnityEngine assembly.

9.26 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/ServerSettings.cs File Reference

ScriptableObject defining a server setup. An instance is created as **PhotonServerSettings**.

Classes

- · class Region
- · class ServerSettings

Collection of connection-relevant settings, used internally by PhotonNetwork.ConnectUsingSettings.

9.26.1 Detailed Description

ScriptableObject defining a server setup. An instance is created as **PhotonServerSettings**.

9.27 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonAnimatorView.cs File Reference

Classes

· class PhotonAnimatorView

This class helps you to synchronize Mecanim animations Simply add the component to your GameObject and make sure that the PhotonAnimatorView is added to the list of observed components

- · class PhotonAnimatorView.SynchronizedParameter
- · class PhotonAnimatorView.SynchronizedLayer

9.28 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonRigidbody2DView.cs File Reference

Classes

· class PhotonRigidbody2DView

This class helps you to synchronize the velocities of a 2d physics RigidBody. Note that only the velocities are synchronized and because Unitys physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a PhotonTransformView to synchronize the position. Simply add the component to your GameObject and make sure that the PhotonRigidbody2DView is added to the list of observed components

9.29 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonRigidbodyView.cs File Reference

Classes

· class PhotonRigidbodyView

This class helps you to synchronize the velocities of a physics RigidBody. Note that only the velocities are synchronized and because Unitys physics engine is not deterministic (ie. the results aren't always the same on all computers) - the actual positions of the objects may go out of sync. If you want to have the position of this object the same on all clients, you should also add a PhotonTransformView to synchronize the position. Simply add the component to your GameObject and make sure that the PhotonRigidbodyView is added to the list of observed components

9.30 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformView.cs File Reference

Classes

· class PhotonTransformView

This class helps you to synchronize position, rotation and scale of a GameObject. It also gives you many different options to make the synchronized values appear smooth, even when the data is only send a couple of times per second. Simply add the component to your GameObject and make sure that the PhotonTransformView is added to the list of observed components

9.31 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewPositionControl.cs File Reference

Classes

• class PhotonTransformViewPositionControl

9.32 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewPositionModel.cs File Reference

Classes

- · class PhotonTransformViewPositionModel
- 9.33 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewRotationControl.cs File Reference

Classes

- class PhotonTransformViewRotationControl
- 9.34 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewRotationModel.cs File Reference

Classes

- · class PhotonTransformViewRotationModel
- 9.35 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewScaleControl.cs File Reference

Classes

- · class PhotonTransformViewScaleControl
- 9.36 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/Photon Unity Networking/Plugins/PhotonNetwork/Views/PhotonTransformViewScaleModel.cs File Reference

Classes

- class PhotonTransformViewScaleModel
- 9.37 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat

 Api/ChannelCreationOptions.cs File Reference

Reference 227

Classes

· class Photon.Chat.ChannelCreationOptions

Namespaces

- · package Photon.Chat
- 9.38 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat

 Api/ChannelWellKnownProperties.cs File Reference

Classes

· class Photon.Chat.ChannelWellKnownProperties

Namespaces

- · package Photon.Chat
- 9.39 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat

 Api/ChatChannel.cs File Reference

Classes

· class Photon.Chat.ChatChannel

A channel of communication in Photon Chat, updated by ChatClient and provided as READ ONLY.

Namespaces

- · package Photon.Chat
- 9.40 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat

 Api/ChatClient.cs File Reference

Classes

· class Photon.Chat.ChatClient

Central class of the Photon Chat API to connect, handle channels and messages.

Namespaces

package Photon.Chat

9.41 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat Api/ChatDisconnectCause.cs File Reference

Namespaces

· package Photon.Chat

Enumerations

enum Photon.Chat.ChatDisconnectCause {
 Photon.Chat.ChatDisconnectCause.None, Photon.Chat.ChatDisconnectCause.DisconnectCause.DisconnectCause.ExceptionOnConnect, Photon.Chat.ChatDisconnectCause.
 DisconnectByServer,

Photon.Chat.ChatDisconnectCause.TimeoutDisconnect,
Photon.Chat.ChatDisconnectCause.InvalidAuthentication,
Reached.

Photon.Chat.ChatDisconnectCause.Exception,
Photon.Chat.ChatDisconnectCause.MaxCcu←
Photon.Chat.ChatDisconnectCause.MaxCcu←

Photon.Chat.ChatDisconnectCause.InvalidRegion, Photon.Chat.ChatDisconnectCause.OperationNot← AllowedInCurrentState, Photon.Chat.ChatDisconnectCause.CustomAuthenticationFailed }

Enumeration of causes for Disconnects (used in ChatClient.DisconnectedCause).

9.42 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat Api/ChatEventCode.cs File Reference

Classes

· class Photon.Chat.ChatEventCode

Wraps up internally used constants in Photon Chat events. You don't have to use them directly usually.

Namespaces

· package Photon.Chat

9.43 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat Api/ChatOperationCode.cs File Reference

Classes

• class Photon.Chat.ChatOperationCode

Wraps up codes for operations used internally in Photon Chat. You don't have to use them directly usually.

Namespaces

· package Photon.Chat

9.44 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat Api/ChatParameterCode.cs File Reference

Classes

· class Photon.Chat.ChatParameterCode

Wraps up codes for parameters (in operations and events) used internally in Photon Chat. You don't have to use them directly usually.

Namespaces

· package Photon.Chat

9.45 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat Api/ChatPeer.cs File Reference

Classes

· class Photon.Chat.ChatPeer

Provides basic operations of the Photon Chat server. This internal class is used by public ChatClient.

· class Photon.Chat.AuthenticationValues

Container for user authentication in Photon. Set AuthValues before you connect - all else is handled.

· class Photon.Chat.ParameterCode

Class for constants. Codes for parameters of Operations and Events.

· class Photon.Chat.ErrorCode

ErrorCode defines the default codes associated with Photon client/server communication.

Namespaces

package Photon.Chat

Enumerations

enum Photon.Chat.CustomAuthenticationType: byte {
 Photon.Chat.CustomAuthenticationType.Custom = 0, Photon.Chat.CustomAuthenticationType.Steam = 1,
 Photon.Chat.CustomAuthenticationType.Facebook = 2, Photon.Chat.CustomAuthenticationType.Oculus = 3,
 Photon.Chat.CustomAuthenticationType.PlayStation = 4, Photon.Chat.CustomAuthenticationType.Xbox =
 5, Photon.Chat.CustomAuthenticationType.Viveport = 10, Photon.Chat.CustomAuthenticationType.None =
 byte.MaxValue }

Options for optional "Custom Authentication" services used with Photon. Used by OpAuthenticate after connecting to Photon.

9.46 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat Api/ChatState.cs File Reference

Namespaces

package Photon.Chat

Enumerations

enum Photon.Chat.ChatState {
 Photon.Chat.ChatState.Uninitialized, Photon.Chat.ChatState.ConnectingToNameServer, Photon.Chat.
 ChatState.ConnectedToNameServer, Photon.Chat.ChatState.Authenticating,
 Photon.Chat.ChatState.Authenticated, Photon.Chat.ChatState.DisconnectingFromNameServer, Photon.
 Chat.ChatState.ConnectingToFrontEnd, Photon.Chat.ChatState.ConnectedToFrontEnd,
 Photon.Chat.ChatState.DisconnectingFromFrontEnd, Photon.Chat.ChatState.QueuedComingFromFront
 End, Photon.Chat.ChatState.Disconnecting, Photon.Chat.ChatState.Disconnected }

Possible states for a Chat Client.

9.47 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat Api/ChatUserStatus.cs File Reference

Classes

· class Photon.Chat.ChatUserStatus

Contains commonly used status values for SetOnlineStatus. You can define your own.

Namespaces

· package Photon.Chat

9.48 C:/Dev/photon-sdk-dotnet/Unity/PhotonNetworking-Classic/Assets/PhotonChat Api/IChatClientListener.cs File Reference

Classes

· interface Photon.Chat.IChatClientListener

Callback interface for Chat client side. Contains callback methods to notify your app about updates. Must be provided to new ChatClient in constructor

Namespaces

· package Photon.Chat

Index

Actor	Connected
LoadbalancingPeer.cs, 217	Enums.cs, 212
AddToRoomCache	ConnectedToFrontEnd
LoadbalancingPeer.cs, 215	Photon::Chat, 32
AddToRoomCacheGlobal	ConnectedToGameserver
LoadbalancingPeer.cs, 215	Public API, 21
Additive	ConnectedToMaster
UnityEngine::SceneManagement, 33	Public API, 21
All	ConnectedToNameServer
LoadbalancingPeer.cs, 217	Photon::Chat, 32
PhotonView.cs, 222	Public API, 21
Public API, 26	Connecting
AllBuffered	Enums.cs, 212
Public API, 26	ConnectingToFrontEnd
AllBufferedViaServer	Photon::Chat, 32
Public API, 26	ConnectingToGameserver
AllViaServer	Public API, 21
Public API, 26	ConnectingToMasterserver
asia	Public API, 21
Enums.cs, 211	ConnectingToNameServer
AsyncRandomLobby	Photon::Chat, 32
LoadbalancingPeer.cs, 216	Public API, 21
au	Contains
Enums.cs, 211	Extensions, 76
Auth	Continuous
LoadbalancingPeer.cs, 215	PhotonAnimatorView, 110
AuthOnce	CreatelfNotExists
LoadbalancingPeer.cs, 215	LoadbalancingPeer.cs, 216
AuthOnceWss	Cube
LoadbalancingPeer.cs, 215	ExitGames::Client::GUI, 29
Authenticated	Custom
Photon::Chat, 32	LoadbalancingPeer.cs, 215
•	Photon::Chat, 32
Public API, 21	CustomAuthenticationFailed
Authenticating	Photon::Chat, 31
Photon::Chat, 32	i notononat, or
Public API, 21	DatagramEncryption
AuthenticationTicketExpired	Enums.cs, 212
Public API, 22	Default
PostPogion	LoadbalancingPeer.cs, 216
BestRegion	Disabled
ServerSettings, 203	PhotonAnimatorView, 110
Bool	PhotonTransformViewPositionModel, 168, 169
PhotonAnimatorView, 110	PhotonTransformViewRotationModel, 170 PhotonTransformViewRotationModel, 170
000	PhotonTransformViewScaleModel, 172
Cae	
Enums.cs, 211	DisconnectByClientTimeout
Cluster	Public API, 22
Region, 189	DisconnectByServer
Code Parier 400	Photon::Chat, 31
Region, 189	DisconnectByServerLogic

Public API, 22	Public API, 22
DisconnectByServerTimeout	ExceptionOnConnect
Public API, 22	Photon::Chat, 31
DisconnectByServerUserLimit	Public API, 22
Photon::Chat, 31	ExitGames::Client::GUI
Public API, 22	Cube, 29
Disconnected	
	Sphere, 29
Enums.cs, 212	WireCube, 29
Photon::Chat, 32	WireSphere, 29
Public API, 21	Extensions, 75
Disconnecting	Contains, 76
Enums.cs, 212	Merge, 76
Photon::Chat, 32	
Public API, 21	Facebook
DisconnectingFromFrontEnd	LoadbalancingPeer.cs, 215
Photon::Chat, 32	Photon::Chat, 32
DisconnectingFromGameserver	FillRoom
Public API, 21	LoadbalancingPeer.cs, 216
DisconnectingFromMasterserver	Fixed
Public API, 21	PhotonView.cs, 223
DisconnectingFromNameServer	FixedSpeed
Photon::Chat, 32	PhotonTransformViewPositionModel, 168, 169
Public API, 21	Float
Discrete	PhotonAnimatorView, 110
PhotonAnimatorView, 110	Full
DoNotCache	Public API, 22
LoadbalancingPeer.cs, 215	
	Game
Enums.cs	LoadbalancingPeer.cs, 217
asia, 211	GameAndActor
au, <mark>211</mark>	LoadbalancingPeer.cs, 217
cae, 211	GameServer
Connected, 212	NetworkingPeer.cs, 218
Connecting, 212	Networkingi eer.cs, 210
DatagramEncryption, 212	Hashtable
Disconnected, 212	Photon, 30
Disconnecting, 212	1 1101011, 30
eu, 211	in
in, 211, 212	Enums.cs, 211, 212
InitializingApplication, 212	Informational
jp, 211	Public API, 22
kr, 211, 212	InitializingApplication
none, 211	Enums.cs, 212
PayloadEncryption, 212	Int
ru, 211, 212	PhotonAnimatorView, 110
rue, 211, 212	InternalReceiveException
sa, 211	Public API, 22
us, 211	InvalidAuthentication
usw, 211	Photon::Chat, 31
ErrorsOnly	Public API, 22
Public API, 22	InvalidRegion
EstimateSpeedAndTurn	Photon::Chat, 31
PhotonTransformViewPositionModel, 168	Public API, 22
EstimatedSpeed	
PhotonTransformViewPositionModel, 169	JoinOrRejoin
eu	LoadbalancingPeer.cs, 216
Enums.cs, 211	Joined
Exception	Public API, 21
Photon::Chat, 31	JoinedLobby

Public API, 21	MasterServer
Joining	NetworkingPeer.cs, 218
Public API, 21	MaxCcuReached
jp	Photon::Chat, 31
Enums.cs, 211	Public API, 22
	Merge
kr	Extensions, 76
Enums.cs, 211, 212	MergeCache
	LoadbalancingPeer.cs, 215
Leaving	MoveTowards
Public API, 21	PhotonTransformViewScaleModel, 172
Lerp	, , , , , , , , , , , , , , , , , , , ,
PhotonTransformViewPositionModel, 169	Name
PhotonTransformViewRotationModel, 170	Room, 193
PhotonTransformViewScaleModel, 172	name
LoadbalancingPeer.cs	Room, 193
Actor, 217	NameServer
AddToRoomCache, 215	NetworkingPeer.cs, 218
AddToRoomCacheGlobal, 215	NetworkingPeer.cs
All, 217	GameServer, 218
AsyncRandomLobby, 216	MasterServer, 218
Auth, 215	NameServer, 218
AuthOnce, 215	NintendoSwitch
AuthOnceWss, 215	LoadbalancingPeer.cs, 215
CreatelfNotExists, 216	None
Custom, 215	LoadbalancingPeer.cs, 215, 217
Default, 216	Photon::Chat, 31, 32
DoNotCache, 215	none
Facebook, 215	Enums.cs, 211
FillRoom, 216	NotSet
Game, 217	ServerSettings, 203
GameAndActor, 217	
JoinOrRejoin, 216	Oculus
MasterClient, 217	LoadbalancingPeer.cs, 215
MergeCache, 215	Photon::Chat, 32
NintendoSwitch, 215	Off
None, 215, 217	PhotonView.cs, 223
Oculus, 215	OfflineMode
Others, 217	ServerSettings, 203
PlayStation, 215	OnConnectedToMaster
RandomMatching, 216	Public API, 24
RejoinOnly, 216	OnConnectedToPhoton
RemoveCache, 215	Public API, 23
RemoveFromRoomCache, 215	OnConnectionFail
RemoveFromRoomCacheForActorsLeft, 215	Public API, 23
ReplaceCache, 215	OnCreatedRoom
SerialMatching, 216	Public API, 23
SliceIncreaseIndex, 216	OnCustomAuthenticationFailed
SlicePurgeIndex, 216	Public API, 25
<u> </u>	OnCustomAuthenticationResponse
SlicePurgeUpToIndex, 216	Public API, 25
SliceSetIndex, 216	OnDisconnectedFromPhoton
SqlLobby, 216	
Steam, 215	Public API, 23
Viveport, 215	OnFailedToConnectToPhoton
Xbox, 215	Public API, 23
	OnJoinedLobby
MasterClient	Public API, 23
LoadbalancingPeer.cs, 217	OnJoinedRoom
Public API, 26	Public API, 24

OnLeftLobby	OthersBuffered
Public API, 23	Public API, 26
OnLeftRoom	1 ublic At 1, 20
	Parse
Public API, 23 OnLobbyStatisticsUpdate	Region, 189
·	PayloadEncryption
Public API, 26	Enums.cs, 212
OnMasterClientSwitched	PeerCreated
Public API, 23	Public API, 21
OnOwnershipRequest	Photon, 30
Public API, 26	Hashtable, 30
OnOwnershipTransfered	Photon::Chat
Public API, 26	Authenticated, 32
OnPhotonCreateRoomFailed	Authenticating, 32
Public API, 23	ConnectedToFrontEnd, 32
OnPhotonCustomRoomPropertiesChanged	ConnectedToNameServer, 32
Public API, 25	ConnectingToFrontEnd, 32
OnPhotonInstantiate	Connecting To Name Server, 32
Public API, 25	Custom, 32
OnPhotonJoinRoomFailed	CustomAuthenticationFailed, 31
Public API, 23	DisconnectByServer, 31
OnPhotonMaxCccuReached	DisconnectByServerUserLimit, 31
Public API, 25	Disconnected, 32
OnPhotonPlayerActivityChanged	Disconnecting, 32
Public API, 26	DisconnectingFromFrontEnd, 32
OnPhotonPlayerConnected	DisconnectingFromNameServer, 32
Public API, 24	Exception, 31
OnPhotonPlayerDisconnected	ExceptionOnConnect, 31
Public API, 24	Facebook, 32
OnPhotonPlayerPropertiesChanged	InvalidAuthentication, 31
Public API, 25	InvalidRegion, 31
OnPhotonRandomJoinFailed	-
Public API, 24	MaxCcuReached, 31
OnPhotonSerializeView	None, 31, 32
Public API, 24	Oculus, 32 OperationNotAllowedInCurrentState, 31
OnReceivedRoomListUpdate	PlayStation, 32
Public API, 24	QueuedComingFromFrontEnd, 32
OnUpdatedFriendList	
Public API, 25	Steam, 32 TimeoutDisconnect, 31
OnWebRpcResponse	Uninitialized, 32
Public API, 25	Viveport, 32
OnlyAngularVelocity	•
PhotonView.cs, 222	Xbox, 32
OnlyPosition	PhotonAnimatorView
PhotonView.cs, 222	Bool, 110
OnlyRotation	Continuous, 110
PhotonView.cs, 222	Disabled, 110
OnlyScale	Discrete, 110
PhotonView.cs, 222	Float, 110
Only Velocity	Int, 110
PhotonView.cs, 222	Trigger, 110
	PhotonCloud
open	ServerSettings, 203
Room, 194	PhotonTransformViewPositionModel
OperationNotAllowedInCurrentState	Disabled, 168, 169
Photon::Chat, 31	EstimateSpeedAndTurn, 168
Optional Gui Elements, 28	EstimatedSpeed, 169
Others	FixedSpeed, 168, 169
LoadbalancingPeer.cs, 217	Lerp, 169
Public API, 26	SynchronizeValues, 168, 169

PhotonTransformViewRotationModel	InternalReceiveException, 22
Disabled, 170	InvalidAuthentication, 22
Lerp, 170	InvalidRegion, 22
RotateTowards, 170	Joined, 21
PhotonTransformViewScaleModel	JoinedLobby, 21
Disabled, 172	Joining, 21
Lerp, 172	Leaving, 21
MoveTowards, 172	MasterClient, 26
PhotonView.cs	MaxCcuReached, 22
All, 222	OnConnectedToMaster, 24
Fixed, 223	OnConnectedToPhoton, 23
Off, 223	OnConnectionFail, 23
OnlyAngularVelocity, 222	OnCreatedRoom, 23
OnlyPosition, 222	OnCustomAuthenticationFailed, 25
OnlyRotation, 222	OnCustomAuthenticationResponse, 25
OnlyScale, 222	OnDisconnectedFromPhoton, 23
OnlyVelocity, 222	OnFailedToConnectToPhoton, 23
PositionAndRotation, 222	OnJoinedLobby, 23
ReliableDeltaCompressed, 223	OnJoinedRoom, 24
Request, 223	OnLeftLobby, 23
Takeover, 223	OnLeftRoom, 23
Unreliable, 223	OnLobbyStatisticsUpdate, 26
UnreliableOnChange, 223	OnMasterClientSwitched, 23
Ping	OnOwnershipRequest, 26
Region, 190	OnOwnershipTransfered, 26
PlayStation	OnPhotonCreateRoomFailed, 23
LoadbalancingPeer.cs, 215	OnPhotonCustomRoomPropertiesChanged, 25
Photon::Chat, 32	OnPhotonInstantiate, 25
PositionAndRotation	OnPhotonJoinRoomFailed, 23
PhotonView.cs, 222	OnPhotonMaxCccuReached, 25
Public API	OnPhotonPlayerActivityChanged, 26
All, 26	OnPhotonPlayerConnected, 24
AllBuffered, 26	OnPhotonPlayerDisconnected, 24
AllBufferedViaServer, 26	OnPhotonPlayerPropertiesChanged, 25
AllViaServer, 26	OnPhotonRandomJoinFailed, 24
Authenticated, 21	OnPhotonSerializeView, 24
Authenticating, 21	OnReceivedRoomListUpdate, 24
AuthenticationTicketExpired, 22	OnUpdatedFriendList, 25
ConnectedToGameserver, 21	OnWebRpcResponse, 25
ConnectedToMaster, 21	Others, 26
ConnectedToNameServer, 21	OthersBuffered, 26
ConnectingToGameserver, 21	PeerCreated, 21
ConnectingToMasterserver, 21	Queued, 21
ConnectingToNameServer, 21	QueuedComingFromGameserver, 21
DisconnectByClientTimeout, 22	SecurityExceptionOnConnect, 22
DisconnectByServerLogic, 22	Uninitialized, 21
DisconnectByServerTimeout, 22	Queued
DisconnectByServerUserLimit, 22	Public API, 21
Disconnected, 21	QueuedComingFromFrontEnd
Disconnecting, 21	Photon::Chat, 32
DisconnectingFromGameserver, 21	QueuedComingFromGameserver
DisconnectingFromMasterserver, 21	Public API, 21
DisconnectingFromNameServer, 21	1 UDIIO / 11 1, 2 1
ErrorsOnly, 22	RandomMatching
Exception, 22	LoadbalancingPeer.cs, 216
ExceptionOnConnect, 22	Region, 189
Full, 22	Cluster, 189
Informational, 22	Code, 189
•	-

Parse, 189	Photon::Chat, 32
Ping, 190	SynchronizeValues
Region, 189	PhotonTransformViewPositionModel, 168, 169
RejoinOnly	
LoadbalancingPeer.cs, 216	Takeover
ReliableDeltaCompressed	PhotonView.cs, 223
PhotonView.cs, 223	TimeoutDisconnect
RemoveCache	Photon::Chat, 31
LoadbalancingPeer.cs, 215	Trigger
RemoveFromRoomCache	PhotonAnimatorView, 110
LoadbalancingPeer.cs, 215	
RemoveFromRoomCacheForActorsLeft	Uninitialized
LoadbalancingPeer.cs, 215	Photon::Chat, 32
ReplaceCache	Public API, 21
LoadbalancingPeer.cs, 215	UnityEngine::SceneManagement
Request	Additive, 33
PhotonView.cs, 223	Single, 33
Room, 190	Unreliable
Name, 193	PhotonView.cs, 223
name, 193	UnreliableOnChange
open, 194	PhotonView.cs, 223
visible, 194	us
•	Enums.cs, 211
RotateTowards	usw
PhotonTransformViewRotationModel, 170	Enums.cs, 211
ru	
Enums.cs, 211, 212	visible
rue	Room, 194
Enums.cs, 211, 212	Viveport
	LoadbalancingPeer.cs, 215
sa	Photon::Chat, 32
Enums.cs, 211	1 Hotorn. Onat, 32
SecurityExceptionOnConnect	WireCube
Public API, 22	ExitGames::Client::GUI, 29
SelfHosted	WireSphere
ServerSettings, 203	·
SerialMatching	ExitGames::Client::GUI, 29
LoadbalancingPeer.cs, 216	Xbox
ServerSettings	LoadbalancingPeer.cs, 215
BestRegion, 203	Photon::Chat, 32
NotSet, 203	FilotonGhat, 32
OfflineMode, 203	
PhotonCloud, 203	
SelfHosted, 203	
Single	
UnityEngine::SceneManagement, 33	
SliceIncreaseIndex	
LoadbalancingPeer.cs, 216	
SlicePurgeIndex	
LoadbalancingPeer.cs, 216	
SlicePurgeUpToIndex	
- ·	
LoadbalancingPeer.cs, 216	
SliceSetIndex	
LoadbalancingPeer.cs, 216	
Sphere	
ExitGames::Client::GUI, 29	
SqlLobby	
LoadbalancingPeer.cs, 216	
Steam	
LoadbalancingPeer.cs, 215	