




F1 — Dot cueing

Did the onset dot mark the translating field?
F1=1 (CUED): dot marks translator · F1=0 (UNCUED): dot marks non-translator






Left → Middle: same data, two scales. Middle → Right: GLM adjusts for all other factors simultaneously.



F2 — Depth-field cueing



Did the translating field remain in the depth plane established during the cue interval?
F2=1: translator stays in cued depth plane · F2=0: translator changes depth plane at tStart
F2=1 conditions: CUED+N, CUED+C, UNCUE+Z, UNCUE+CZ




Left → Middle: same data, two scales. Middle → Right: GLM adjusts for all other factors simultaneously.

F3 — Color-field cueing (null)

Did the translating field retain the color associated with its cued identity?
F3=1: translator keeps cued color · F3=0: translator changes color at tStart
F3=1 conditions: CUED+N, CUED+Z, UNCUEDED+C, UNCUEDED+CZ






Left → Middle: same data, two scales. Middle → Right: GLM adjusts for all other factors simultaneously.



F4 — Translator depth plane (Near vs Far)


Which depth plane does the translating field occupy?
F4=1 (Near): translator is closer · F4=0 (Far): translator is farther
Near < Far is a robust asymmetry (stereoscopic origin — absent monocularly)



Left → Middle: same data, two scales. Middle → Right: GLM adjusts for all other factors simultaneously.

F1 × F2 — Dot cueing × Depth-field cueing (the key interaction)

Performance is high only when BOTH the onset dot cue AND depth-plane continuity point to the same field.
Neither factor alone drives selection — the conjunction is necessary.



F1×F2 interaction coefficient: $\beta = +1.785$ 95% CI [+1.363, +2.206] ***
Average Marginal Effect of F1×F2: +32.7 pp ***

Interpretation: being dot-cued AND depth-cued (F1=1, F2=1) is 1.78 log-odds units MORE effective than the additive sum of their separate effects. In plain terms: dot cueing only helps when the translator stays in its pre-cue depth plane.