- Why do we save and restore registers?
- Who saves the registers of whom?

g253wang

CS 241 Lecture 5

Assembler and Formal Languages
With thanks to Brad Lushman, Troy Vasiga, Kevin Lanctot,
and Carmen Bruni



Unresolved Questions

Most of our original questions have been resolved except for one: **How do we pass parameters?**

- Typically, we'll just use registers. If we have too many, we could push parameters to the stack and then pop them from the stack.
 Documentation is vitally important here!
- If we can do this correctly, then everything, including recursion, should just work properly.

Sum Evens 1 to N Slide 1 of 2

|253wang||g253wang||g253wang

```
: sumEvens1ToN adds all even numbers from 1 to N
; Registers:
; $1 Scratch Register (Should Save!)
 $2 Input Register (Should Save!)
 $3 Output Register (Do NOT Save!)
sumEvens1ToN:
    sw $1, -4($30); Save $1 and $2
    sw $2. -8($30)
   lis $1
  .word 8
    sub $30, $30, $1; Decrement stack pointer
    add $3, $0, $0; Don't forget to initialize $3!
    lis $1
    .word 2
   ; ....continued on next slide!
```

Sum Evens 1 to N Slide 2 of 2

g253wang g253wang g253wang

SUBARR

```
div $2, $1 ; Is N even?
    mfhi $1
    sub $2, $2, $1; Sub 1 if not
    lis $1
    .word 2 ; Restore 2
    top:
    add $3, $3, $2
    sub $2, $2, $1
    bne $2, $0, top
    lis $1
     .word 8
    add $30, $30, $1
    lw $2, -8($30)
    lw $1, -4($30); Reload $1 and $2
    jr $31 ; Back to caller
; End sumEvens1ToN
```

g253wang

Another outstanding problem: How to we print to the screen or read input?

SUBMESS S

Input and Output

Another outstanding problem: How to we print to the screen or read input?

g253wang g253wang g253wang

We do this one byte at a time!

SWan

- Output: Use sw to store words in location 0xffff000c. Least significant byte will be printed.
- Input: Use lw to load words in location 0xffff0004. Least significant byte will be the next character from stdin.

Example 9253 wang 9253 wang

Printing CS241 to the screen followed by a newline character:

```
lis $1
.word 0xffff000c
lis $2
.word 67 ; C
sw $2, 0($1)
lis $2
.word 83 ; S
sw $2, 0($1)
                                : Continued from left
                                .word 52 : 4
                                sw $2, 0($1)
                               lis $2
                                .word 49 ; 1
                                                            SUE/
                                sw $2, 0($1)
                               lis $2
1 is $2
                                .word 10 ; \n
                                sw $2, 0($1)
     .word 50 ; 2
    sw $2, 0($1)
                                ir $31
    lis $2
```

The Assembler

Recall: part of our long-term goal is to convert assembly code (our MIPS language) into machine code (bits).

253 wang g253 wang g253 wang

- Input: Assembly code
- · Output: Machine code

Any such translation process involves two phases: **Analysis** and **Synthesis**.

- Analysis: Understand what is meant by the input source
- Synthesis: Output the equivalent target code in the new format

Assembly File

- Think of it as a string of characters (because that's what it is).
- We want to first break it down into meaningful tokens such as labels, numbers, .word, MIPS instructions and so on.
- This is done for you in asm.rkt and asm.cc.

Your job:

SWar

- Analysis: Group tokens into instructions if possible
- Synthesis: Output equivalent machine code.
- If the tokens are not valid instructions, output ERROR to stderr.

Assignment Advice

SWan

• There are many more incorrect tokens than correct ones.

- Focus on finding correct ones! (More on this in upcoming weeks)
- Later we will discuss parsing, a formal way of grouping tokens.

The Biggest Assembler Problem

- How do we assemble this code:
- beq \$0, \$1, myLabel
- myLabel:

g253wan

- add \$1, \$1, \$1
- The problem is that myLabel is used before it's defined: we don't know the address when it's used!

g253wang g253wang g253wang

What is the best fix to this?

Standard Solution:

Perform two passes:

SWEIN

 Pass 1: Group tokens into instructions and record addresses of labels (data structure?).

- Note: multiple labels are possible for the same line! For example, f: g: add \$1, \$1. \$1.
- Pass 2: translate each instructions into machine code. If it refers to a label, look up the associated address compute the value.

Your Assembler

SWarn

When writing your assembler, you will do one things:

- Output the machine code coming from the assembled MIPS code to stdout.
- NOT THIS: Output the symbol table to stderr.

Symbol Table Example

Note: A label at the end of code is allowed (it would be the address of the first line after your program).

7				(()
0x00	main:	lis \$2	label	addr
0x04		.word beyond	main	0x00
0x08		lis \$1	top	0x14
0x0c		.word 2	beyond	0x24
9	; Ignore			_ =
0x10		add \$3, \$0, \$0		(3)
0x14	top:			
7)		add \$3, \$3, \$2		(()
0x18		sub \$2, \$2, \$1		
0x1c		bne \$2, \$0, to	p	
0x20		jr \$31	•	
0x24	beyond:	•		

g253wang g253wang g253wang

Summary of Passes

Pass 1:

- Group tokens into instructions
- Build Symbol Table one label at a time
- At the end of code, table is complete.

Pass 2:

- Translate each instructions to machine code
- For each label in an instruction, look up in symbol table and process accordingly

Creating Binary In C++

How do we write the binary output 0001 0100 0100 0000 1111 1111 for bne \$2, \$0, -3?

We've done a lot of the heavy lifting for this problem (figuring out the actual binary), but let's generalize the above and do it completely in C++.

g253wang g253wang g253wang

Bit-wise Operations

Our instruction (bne) can be broken down as follows:

```
Opcode Register's Register't Offset
(6 bits) (5 bits) (5 bits) (16 bits)
```

In this case,

- bne has opcode 000101 = 5
- Register s is 00010 = 2
- Register t is 00000 = 0
- Offset is 111111111111111 = -

253 wang g253 wang g253 wang

Bit Shifting!

We can use bit shifting to put information into the correct position, and use a bitwise or to join them:

```
int instr = (5 << 26) | (2 << 21) | (0 << 16) | offset
```

• We need to be careful with the offset. Why? Recall in C++, ints are 4 bytes. We only want the last two bytes. First, we need to apply a "mask" to only get the last 16 bits:

offset = -3 & 0xffff and then use this in the formula above. Thus, instr is 339804157.

Explanation of Offset Masking

Without Masking (Notice the leading ones ruin our work!):

With Masking:

Are We Done?

Finally, presumably, we just need to cout << instr right?

No! This would output **9 bytes** corresponding to the **ASCII code** for each digit of the instruction as interpreted in decimal! We want to output the four bytes that correspond to this number!

253 wang g253 wang g253 wang

Finally, let's print out the bytes of the instruction:

53พลก

```
int instr = (5 << 26) | (2 << 21) | (0 << 16) | (-3 & 0xffff);
unsigned char c = instr >> 24;
cout << c;
c = instr >> 16; cout << c;
c = instr >> 8; cout << c;
c = instr; cout << c;</pre>
```

Note: You can also mask here to get the 'last byte' by doing & 0xff if you're worried about which byte will get copied over.

End of MIPS

SWan

 We will now transition to something that looks completely different and is much more theoretical.

g253wang g253wang g253wang

- Our goal, remember, is to translate our high-level language into assembly language.
- Assembly language has a simple and universal way to be translated to machine code for a specific architecture.

End of MIPS

g253wang

- Higher level languages, however, could have multiple different translations to machine language. These usually have a more complex structure than assembly language code.
- What we need is to formalize our notion of a language and then figure out from this formalized notion how we are to parse and translate strings of text.