Module 3F2: Systems and Control

LECTURE NOTES 1: STATE-SPACE SYSTEMS


Contents

1	Sta	te Space Descriptions Of Dynamical Systems	3	
	1.1	States	3	
	1.2	General Guidelines For State-Space Modelling	8	
	1.3	Ideal Operational Amplifier Circuits	10	
	1.4	Velocity Fields In The State-Space	11	
			15	
2	Linearizing Nonlinear Dynamical Systems			
	2.1	Linearizing the standard form	15	
	2.2	Linearizing when the State Equations are Implicit	18	
	2.3	Behaviour of Nonlinear Systems	19	
3	Soli	itions of Linear State Equations	21	
J	Suit	itions of Diffeat State Equations	21	
	2.1		21	
	3.1	Using Laplace Transforms	21	
	3.2	Transfer function poles	23	
	3.3	Initial Condition Response of the State	26	
	3.4	Example: Rotating Rigid Body	34	
	3.5	Convolution Integral	40	
	3.6	Frequency Response	42	
	3.7	Stability of $\underline{\dot{x}} = A\underline{x}$	43	
4	State Space Equations for Composite Systems			
	4.1	Cascade of Two Systems	47	
	4.2	Parallel combination of two systems	49	
K.	Glove	Revised by J Maciejov	wski	
No	ovemb	er 2001 January 2		
Revised by G.V				
		January 2015. 2	2019	

1 State Space Descriptions Of Dynamical Systems

1.1 States

The essence of a dynamical system is its memory, i.e. the present output, y(t) depends on past inputs,



Three sets of variables define a dynamical system -

- 1. The inputs, $u_1(t)$, $u_2(t)$, ... $u_m(t)$ (input vector $\underline{u}(t)$)
- 2. The state variables, $x_1(t), ... x_n(t)$ (state vector $\underline{x}(t)$)
- 3. The outputs, $y_1(t)$, $y_2(t)$, ... $y_p(t)$, (output vector y(t))

The states are a subset of the system variables which satisfy the following two properties

- STATE PROPERT 1. for any $t_o < t_1, \underline{x}(t_1)$ can always be determined from $\underline{x}(t_o)$ and $\underline{u}(\tau), t_o \le \tau \le t_1$.
- 2. The outputs y at time t, is a memoryless function of $\underline{x}(t)$ and $\underline{u}(t)$ (that is, $\underline{y}(t)$ depends only on $\underline{x}(t)$ and u(t)).

That is completely $\underline{x}(t_o)$ summarizes the effect on the future of inputs and states prior to t_o .

eg Integrator

Let
$$x(t) = 3y(t)$$

$$\Rightarrow x(t) = 3y(t) = 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

$$= 3$$

= 3 y(0) + 3 (b) dk = >((to)) + 3 (b) dk => STATE PROPERTY is Saissied outh = y(t)

outh = 5y(t) equally valid

The most general class of dynamical system that we will consider is described by the set of first order ordinary differential equations -

$$S \begin{cases} \frac{dx_i}{dt} = f_i(x_1(t), x_2(t), ...x_n(t), u_1(t), ...u_m(t), t), & i = 1, 2, ...n. \\ y_j(t) = g_j(x_1(t), ...x_n(t), u_1(t), ...u_m(t), t) & j = 1, 2, ...p. \end{cases}$$

S is the standard form for a state-space dynamical system model. Or a vector form -

$$S \begin{cases} \underline{\dot{x}}(t) = \underline{f}(\underline{x}(t), \underline{u}(t), t) \\ \underline{y}(t) = \underline{g}(\underline{x}(t), \underline{u}(t), t) \end{cases}$$

Note that S has only first order ode's, but we can use a standard technique to convert high order o.d.e's to first order vector o.d.e.'s, by the use of auxiliary variables.

<u>Ex</u>:

$$\ddot{y} + 6y\ddot{y} + 5(\dot{y})^3 + 12\sin(y) = \cos(t)$$

a state variable is given by: $x_1 = y$, $x_2 = \dot{y}$, $x_3 = \ddot{y}$, when,

$$\begin{cases} \dot{x}_1 = x_2 \\ \dot{x}_2 = x_3 \\ \dot{x}_3 = -6x_1x_3 - 5x_2^3 - 12\sin(x_1) + \cos(t) \end{cases}$$

which is in the form

$$\underline{\dot{x}}(t) = \underline{f}(\underline{x}(t), t)$$

where \underline{f} is a vector valued function of a vector, i.e.

$$\underline{f}(\underline{x},t) = \begin{bmatrix} x_2 \\ x_3 \\ -6x_1x_3 - 5x_2^3 - 12\sin(x_1) + \cos(t) \end{bmatrix}$$

For linear time-invariant dynamical systems we use the standard form:

$$S \begin{cases} \frac{\dot{x}(t)}{y} = \frac{Ax(t) + B\underline{u}(t)}{Ax(t) + D\underline{u}(t)} \\ \frac{\dot{y}(t)}{y} = \frac{Cx(t) + D\underline{u}(t)}{Ax(t) + Dx(t)} \end{cases}$$

$$P \times M$$

$$P$$

1.2 **General Guidelines For State-Space Modelling**

Method 1: Choose system states, $x_1, x_2, ...x_n$ by considering the independent 'energy storage devices' or 'memory elements',

e.g.

$$E = \frac{1}{2}LL^{2}$$
 $C = \frac{1}{2}CV^{2}$

and in Lor voltage on C

electrical circuits - current in L or voltage on

mechanics - positions and velocities of masses (linear and angular).

chemical engineering - temperature, pressure, volume, concentration.

Then use the basic physical laws derive expressions involving \dot{x}_i , e.g.

•
$$V = Ldi/dt, i = Cdv/dt$$

•
$$m \times acc^n = force;$$
 $\frac{d(pos^n)}{dt} = velocity.$

•
$$\frac{d(\text{volume})}{dt}$$
 = flow = function of pressure.

E= 1/2 Word

Solve for $\underline{\dot{x}} = f(\underline{x}, \underline{u}, t)$.

Method 2: Choose state variables as successive time derivatives.

Example: Original ODE: $J\ddot{\theta} + B\dot{\theta} = M$.

Let $x_1 = \theta$, $x_2 = \dot{\theta}$. Then

$$3c_1 = 3c_2 \quad 3c_2 = -\frac{8}{5}3c_1 + \frac{1}{5}M$$

$$3c_1 = 3c_2 \quad 3c_2 = -\frac{8}{5}3c_1 + \frac{1}{5}M$$

$$3c_2 = \left[\frac{3c_1}{3c_2}\right] = \left[\frac{3}{3}c_1 - \frac{1}{3}\right] \left[\frac{3c_1}{3c_2}\right] + \left[\frac{3}{3}\right]M$$


$$3c_1 = 3c_2 \quad 3c_2 = -\frac{8}{5}3c_1 + \frac{1}{5}M$$

$$3c_2 = \left[\frac{3c_1}{3c_2}\right] = \left[\frac{3}{3}c_1 - \frac{1}{3}\right] \left[\frac{3c_1}{3}\right] + \left[\frac{3}{3}\right]M$$

In general for n'th-order ODE in θ define

$$x_1 = \theta$$
, $x_2 = \frac{d\theta}{dt}$, ..., $x_n = \frac{d^{n-1}\theta}{dt^{n-1}}$
 $2C_1 = 2C_2$
 $2C_2 = 2C_3$
 $2C_{n-1} = 2C_n$
 $2C_{n-1} = 2C_n$

1.3 Ideal Operational Amplifier Circuits



$$\begin{cases} C_1 \dot{x}_1 &= (V_i - x_1)/R_1; \quad C_2 \dot{x}_2 = x_1/R_2 \\ V_o &= x_1 + x_2 \end{cases}$$

Linear operation until the amplifier saturates when quite different equations may hold.

If the amplifier output saturates at $\pm V_s$, then for $|x_1 + x_2| \ge V_s$

we will have: $C_2\dot{x}_2 = (\pm V_s - x_2)/R_2$.

1.4 Velocity Fields In The State-Space


Consider the free motion of the time invariant dynamical system -

$$\underline{\dot{x}} = \underline{f}(\underline{x}) \implies \underline{x}(t + \delta t) \cong \underline{x}(t) + \underline{f}(\underline{x}(t))\delta t \qquad \qquad (\underline{\omega} = 0)$$

This implies a velocity field in the state space which can give a good qualitative idea of the system's behaviour in simple cases.

Ex n=2

The velocity field can be sketched by drawing an arrow in the direction $\underline{f}(\underline{x})$ for many values of \underline{x} . Equilibrium points (or *singular* points) where $\underline{f}(\underline{x}_e) = \underline{0}$, may be stable or unstable.



i) Let R = 1/2, L = 1, C = 1 (in consistent units) then

$$A = \begin{bmatrix} -\frac{1}{2} & -1 \\ 1 & 0 \end{bmatrix}$$




Figure 1: State space trajectories: underdamped RLC network




Figure 2: State space trajectories: overdamped RLC network

Note: Changing sign of A => 1, ->-1, & Arrows change direction

Suppose
$$A \omega_1 = \lambda_1 \omega_1$$

 $2 \omega_2(0) = \omega_1$
THEN $2 \omega_1 = \lambda_1 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$
 $2 \omega_2 = \lambda_1 \omega_2$
 $2 \omega_1 = \lambda_1 \omega_2$

$$\det \begin{pmatrix} \lambda + 4 \\ -1 \end{pmatrix}$$
= $\lambda^{2} + 4\lambda + 1 = 0$
= $(\lambda + 2)^{2} - 3 = 0$

$$\lambda = -2 \pm \sqrt{3} \cdot \frac{4}{3} \cdot 2 - 3.73, -0.27$$

2 Linearizing Nonlinear Dynamical Systems

2.1 Linearizing the standard form

Suppose we have a nonlinear (time invariant) dynamical system in state space form -

$$S \begin{cases} \underline{\dot{x}} = \underline{f}(\underline{x}, \underline{u}) \\ \underline{y} = \underline{g}(\underline{x}) \end{cases}$$

Let \underline{x}_e be an equilibrium state for the system when $\underline{u}(t) = \underline{u}_e$ (constant)

i.e.
$$\underline{f}(\underline{x}_e, \underline{u}_e) = \underline{0}$$
 and also let $\underline{y}_e = \underline{g}(\underline{x}_e)$.

Now consider small perturbations from this equilibrium, let

$$\underline{x}(t) = \underline{x}_e + \underline{\delta x}(t), \ \underline{u}(t) = \underline{u}_e + \underline{\delta u}(t), \ y(t) = y_a + \delta y(t)$$

A Taylor Series expansion of the i-th equation of $\underline{\dot{x}} = f(\underline{x}, \underline{u})$ gives

$$\dot{x}_{i} = \dot{x}_{i} + \delta \dot{x}_{i} = \frac{1}{2} \left[\frac{1}{2} \left(\frac{1}{2} + \frac{1}{2} \frac{1}{2} \frac{1}{2} + \frac{1}{2} \frac{1}{2} \frac{1}{2} \frac{1}{2} + \frac{1}{2} \frac{1}{$$

Thus for small $\underline{\delta x}$ and $\underline{\delta u}$ (\Rightarrow v. small remainder) we get

where
$$\begin{cases}
\frac{\partial x}{\partial t} = [-A_{t} -] \delta_{2t} + [-B_{t} -] \delta_{2t} \\
\frac{\partial x}{\partial t} \cong A \delta_{x} + B \delta_{tt}
\end{cases}$$

$$A = \begin{bmatrix} A_{t} \\ A_{t} \end{bmatrix}, B = \begin{bmatrix} B_{t} \\ B_{2} \end{bmatrix}$$

$$A = \frac{\partial \underline{f}}{\partial \underline{x}}(\underline{x}_e, \underline{u}_e) = \begin{bmatrix} \frac{\partial f_1}{\partial x_1} & \frac{\partial f_1}{\partial x_2} & \cdots & \frac{\partial f_1}{\partial x_n} \\ \frac{\partial f_2}{\partial x_1} & \cdots & & \frac{\partial f_2}{\partial x_n} \\ \vdots & & & \vdots \\ \frac{\partial f_n}{\partial x_1} & \cdots & & \frac{\partial f_n}{\partial x_n} \end{bmatrix}_{\underline{x} = \underline{x}_e, \underline{u} = \underline{u}_e}$$

$$B = \frac{\partial f}{\partial \underline{u}}(\underline{x}_e, \underline{u}_e) = \begin{bmatrix} \frac{\partial f_1}{\partial u_1} & \frac{\partial f_1}{\partial u_2} & \cdots & \frac{\partial f_1}{\partial u_m} \\ \vdots & & \vdots \\ \frac{\partial f_n}{\partial u_1} & \cdots & & \frac{\partial f_n}{\partial u_m} \end{bmatrix}_{\underline{x} = \underline{x}_e, \underline{u} = \underline{u}_e}$$

Similarly $\underline{\delta y} = C\underline{\delta x}$ where $C = \frac{\partial \underline{g}(\underline{x}_c)}{\partial x}$.

The linearized system equations are thus

$$\begin{cases} \underline{\delta x} = A\underline{\delta x} + B\underline{\delta u} \\ \underline{\delta y} = C\underline{\delta x} \end{cases}$$

which will accurately predict the system behaviour for \underline{x} and \underline{u} close to $\underline{x_e}$ and $\underline{u_e}$ respectively.

2.2 Linearizing when the State Equations are Implicit

Quite often a system's equations cannot easily be written as $\underline{\dot{x}} = \underline{f}(\underline{x}, \underline{u})$ but can be written as

$$\underline{F}(\underline{\dot{x}}, \underline{x}, \underline{u}) = \underline{0}$$
 (*n* equations in the *n* unknowns $\dot{x}_1 ... \dot{x}_n$.)

The linearized model can be derived without solving for $\underline{\dot{x}}$ as follows. Since $(\underline{x}_e, \underline{u}_e)$ gives an equilibrium we have,

$$\underline{F(0, x_{\rho}, u_{\rho})} = \underline{0}$$

Now linearize \underline{F} about $(\underline{0}, \underline{x}_e, \underline{u}_e)$ to get

$$\underbrace{\frac{\partial \underline{F}}{\partial \underline{\dot{x}}}\bigg|_{\underbrace{(\underline{0},\underline{x}_e,\underline{u}_e)}_{L}} \delta \underline{\dot{x}} + \underbrace{\frac{\partial \underline{F}}{\partial \underline{x}}\bigg|_{\underbrace{(\underline{0},\underline{x}_e,\underline{u}_e)}_{M}} \delta \underline{x} + \underbrace{\frac{\partial \underline{F}}{\partial \underline{u}}\bigg|_{\underbrace{(\underline{0},\underline{x}_e,\underline{u}_e)}_{N}} \delta \underline{u} \simeq \underline{0}}_{N}$$

$$L\underline{\delta x} + M\underline{\delta x} + N\underline{\delta u} \simeq \underline{0} \implies \underline{\delta x} \simeq -L^{-1}M\underline{\delta x} - L^{-1}N\underline{\delta u} \qquad (y \quad L \text{ is invertible})$$

(N.B. no nonlinear equations to solve except to obtain the equilibrium point)

2.3 Behaviour of Nonlinear Systems

As mentioned above the linearized equations will accurately predict the behaviour of the nonlinear system for \underline{x} and \underline{u} close to their equilibrium values. When the states and inputs are far away from the equilibrium values then the behaviour can be quite different, e.g.

- many equilibria with some stable and some unstable (e.g. inverted pendulum).
- · limit cycles.
- divergence.

This has a stable *Limit Cycle* and an unstable equilibrium at $\underline{x} = \underline{0}$.




Figure 3: State space trajectories for Van der Pol Oscillator

Note that if we were to change the signs on the \dot{x}_1 and \dot{x}_2 terms then this will just change the directions of the arrows in the state space. Hence the origin would then be a stable equilibrium and the limit cycle would be unstable (i.e. if perturbed from the limit cycle then it would either decay to the origin or diverge to infinity).

3 **Solutions of Linear State Equations**

3.1 **Using Laplace Transforms**

Taking Laplace Transforms of

$$\underline{\dot{x}}(t) = A\underline{x}(t) + B\underline{u}(t); \quad \underline{x}(0) = \underline{x}_0$$

$$\underline{y}(t) = C\underline{x}(t) + D\underline{u}(t)$$

$$\underline{\dot{x}}(t) = \underline{x}_0$$

$$\underline{\dot{x}}(t) = \underline{x}_0$$

$$\underline{\dot{x}}(t) = \underline{\dot{x}}(t) + \underline{\dot{x}}(t)$$

gives

and

$$SX(s) - x_0 = AX(s) + BU(s)$$

$$(sI - A)X(s) = x_0 + BU(s)$$

$$X(s) = (sI - A)^{-1}x_0 + (sI - A)^{-1}BU(s)$$

$$Y(s) = C(sI - A)^{-1}x_0 + (D + C(sI - A)^{-1}B)U(s)$$
initial condition response
$$input response$$

$$7C_1(s)$$

$$7C_2(s)$$

$$C(x_1(s))$$

For
$$\underline{x}_0 = \underline{0}$$
, $\underline{Y}(s) = \underbrace{(D + C(sI - A)^{-1}B)}_{G(s)} \underline{U}(s)$ and
$$\underbrace{(D + C(sI - A)^{-1}B)}_{G(s)} \underline{U}(s)$$
 is called the **transfer function matrix**.

The *i*, j^{th} entry of G(s) gives the transfer function from u_i to y_i .

3.2 Transfer function poles

Poles are values of s at which the transfer function becomes infinite:

$$||G(p)|| = \infty \Rightarrow p$$
 is a pole of $G(s)$

This can only happen when the matrix (sI - A) becomes singular, ie when

$$\det(sI - A) = 0$$

namely at the eigenvalues of A.

Later we will see that eigenvalues of A are not always poles of G(s).

Hence we have the important result:

Poles of $G(s) \subset$ eigenvalues of A

Analytical expression for transfer function matrix

It can be shown that, for any matrix M,

$$M^{-1} = \frac{1}{\det M} \begin{bmatrix} M_{11} & M_{21} & \dots & M_{n1} \\ M_{12} & & & \\ \vdots & & & \\ M_{1n} & \dots & & M_{nn} \end{bmatrix} = \frac{\text{adj}(M)}{\det(A)} - \frac{\text{'ADJUGATE'}}{\det(A)}$$

where M_{ij} is called the cofactor of m_{ij} given by

Hence
$$(sI - A)^{-1} = \frac{1}{\alpha(s)} \widetilde{N(s)}$$
 where $\alpha(s) = \det(sI - A)$

$$= s^{n} + \alpha_{1}s^{n-1} + \cdots + \alpha_{n-1}s + \alpha_{n}$$
and $N(s) = N_{1}s^{n-1} + N_{2}s^{n-2} + \cdots + N_{n-1}s + N_$

and
$$N(s) = N_1 s^{n-1} + N_2 s^{n-2} + \cdots + N_{n-1} s + N_n$$

The transfer function can therefore be written as $G(s) = \frac{1}{2\pi} (CN(s)R + D\alpha(s))$ with

Hence $(sI - A)^{-1} = \frac{1}{\alpha(s)} \widetilde{N(s)}$ where $\alpha(s) = \det(sI - A)$ $= s^n + \alpha_1 s^{n-1} + \cdots + \alpha_{n-1} s + \alpha_n$ and $N(s) = N_1 s^{n-1} + N_2 s^{n-2} + \cdots + N_{n-1} s + N_n$ $(CN(s)B + D\alpha(s))$ being a matrix of polynomials in s. $(CN(s)B + D\alpha(s))$ being a matrix of polynomials in s. (N - 3) (N -

Cayley-Hamilton Theorem

A square matrix Satisfies its

own characteristic polynomial

$$A^n + \alpha_1 A^{n-1} + \cdots + \alpha_n I = 0$$

since

$$\alpha(s)I = (sI - A)\left(N_1s^{n-1} + N_2s^{n-2} + \cdots + N_n\right)$$

Equating coefficients of s^k and premultiplying by A^k for k = n, ..., 1, 0 gives

Adding these equalities gives the result.

Hence any power of A is a linear combination of
$$I, A, A^2, ..., A^{n-1} - \text{only}!$$

$$A \cdot = -d_1 A^{n-1} - d_2 A^{n-1} - d_n I$$

$$A \cdot = -d_1 A^{n-1} - d_2 A^{n-1} - d_n I$$

Initial Condition Response of the State

For $\underline{u}(t) = 0$ we have $\dot{x}(t) = Ax(t)$ and hence,

$$\underline{X}(s) = (sI - A)^{-1} \underline{x}_0$$

$$\underline{x}(t) = \mathcal{L}^{-1}\left((sI-A)^{-1}\right)\underline{x}_0 = \Phi(t)\underline{x}_0$$

where
$$\Phi(t) = \mathcal{L}^{-1} \left\{ (sI - A)^{-1} \right\} = \int_{k \ge 0}^{-1} \left\{ \sum_{k \ge 0} A^k s^{-(k+1)} \right\}$$

$$= I + At + A^2 t^2 / 2! + \dots + A^k t^k / k! + \dots$$

$$\frac{def}{def} e^{At}$$

"Proof" (SI-A) (IS" +AS"+...) = I + (AS"-AS") + (S)

Note that

$$\frac{d}{dt}\Phi(t) = Ae^{At} = e^{At}A$$

(check by differentiating series expansion of $\Phi(t)$).

Hence with $\underline{x}(t) = \Phi(t)\underline{x}_0$,

Sinα & (I+At +(At)+...)

of Φ(1)).

- A(I+AL+...)

$$\frac{d}{dt}\underline{x}(t) = \frac{d}{dt} \left\{ \Phi(t)\underline{x}_0 \right\} = Ae^{At}\underline{x}_0 = A \left\{ \Phi(t)\underline{x}_0 \right\} = A\underline{x}(t)$$

$$\Phi(0) = I$$

$$\underline{x}(0) = \underline{x}_0$$

and the differential equation and initial condition are satisfied as required.

 $\Phi(t)$ is called the **state transition matrix**.

Properties of e^{At}

(1) Change of state coordinates

If

then
$$A^2 = T^{-1}\bar{A}T$$
 $\longrightarrow \sum_{k=0}^{\infty} A^k t^k/k!$

$$= T^{-1}\left(\sum_{k=0}^{\infty} \bar{A}^k t^k/k!\right)T$$

$$\Rightarrow e^{At} = T^{-1}e^{\bar{A}t}T$$

Why is this 'change of coordinates'?

If
$$\underline{\dot{x}}(t) = A\underline{x}(t)$$
 and $\underline{z} = T\underline{x}$, then

$$\underline{\dot{z}}(t) = T\underline{\dot{x}}(t)
= TA\underline{x}(t)
= TAT^{-1}\underline{z}(t)
= \overline{A}\underline{z}(t)
\underline{z}(t) = e^{\overline{A}t}\underline{z}(0)
\underline{x}(t) = T^{-1}e^{\overline{A}t}T\underline{x}(0)$$

Special case: Eigenvectors as coordinate axes

Recall that for W the matrix of eigenvectors of A, then the defining relations,

$$A\underline{w}_1 = \underline{w}_1 \lambda_1$$

$$A\underline{w}_2 = \underline{w}_2 \lambda_2$$

$$\vdots$$

$$Aw_n = w_n \lambda_n$$

can be written as:
$$A \underbrace{\left[\underline{w}_{1}, \underline{w}_{2}, ..., \underline{w}_{n} \right]}_{W} = \underbrace{\left[\underline{w}_{1}, \underline{w}_{2}, ..., \underline{w}_{n} \right]}_{W} \underbrace{\left[\begin{array}{cccc} \lambda_{1} & 0 & ... & 0 \\ 0 & \lambda_{2} & ... \\ \vdots & & \ddots & \\ 0 & & ... & \lambda_{n} \end{array} \right]}_{\Lambda}$$

Hence for *non-defective A* we have the eigenvalue/eigenvector decomposition:

$$A = W \Lambda W^{-1}$$

So that for $T = W^{-1}$ we have,

$$\bar{A} = TAT^{-1} = W^{-1}AW = \Lambda = \begin{bmatrix} \lambda_1 & & & \\ & \lambda_2 & & \\ & & \ddots & \\ & & & \lambda_n \end{bmatrix} = \operatorname{diag} \left\{ \lambda_i \right\}$$

$$e^{\Lambda t} = \sum_{k=0}^{\infty} \Lambda^k t^k / k! = \text{diag} \{ \sum_{k=0}^{\infty} \lambda_i^k t^k / k! \}$$

= diag $\{ e^{A_i t} \}$.

This gives one way of evaluating e^{At} .

(Another way is to evaluate $\mathcal{L}^{-1}(sI - A)^{-1}$.)

2) **Semigroup property** — Don't worry about the fancy name.

$$e^{A(t_1+t_2)} = e^{At_1}e^{At_2} = e^{At_2}e^{At_1}$$
since $\underline{x}(t_1+t_2) = \Phi(t_1+t_2)\underline{x}(0)$

$$= \Phi(t_2)\underline{x}(t_1)$$

$$= \Phi(t_2)\Phi(t_1)\underline{x}(0) \text{ for all } \underline{x}(0)$$

NB: This only works because $(At_1)(At_2) = (At_2)(At_1)$. For arbitrary matrices A and B, $e^{A+B} \neq e^A e^B$.

3) Inverse

$$I = e^{A.0} = e^{A(t-t)} = e^{At}e^{-At} \implies \boxed{(e^{At})^{-1} = e^{-At}}$$

4) Derivative — Repeated here for completeness.

$$\frac{d}{dt}e^{At} = Ae^{At} = e^{At}A$$

5) Integral

$$\int_{0}^{t} e^{A\tau} d\tau = \int_{0}^{t} \sum_{k=0}^{\infty} A^{k} \tau^{k} / k! d\tau$$

$$= \sum_{k=0}^{\infty} \left[A^{k} \tau^{k+1} / (k+1)! \right]_{0}^{t}$$

$$= A^{-1} \left\{ \sum_{k=0}^{\infty} A^{k+1} t^{k+1} / (k+1)! - 0 \right\}$$

$$= A^{-1} e^{At} - A^{-1} \quad \text{if} \quad \det(A) \neq 0.$$

If det(A) = 0 then the above formula is not valid and the integration needs to be done directly. e.g. A = 0.

3.4 Example: Rotating Rigid Body

Let I_1 , I_2 , I_3 be the moments of inertia of a rigid body rotating in free space, about its 3 principal axes, and w_1 , w_2 , w_3 the corresponding angular velocities. Then in the absence of externally applied torques EULER'S EQUATIONS OF MOTION are:-

$$I_1 \dot{w}_1 = (I_2 - I_3) w_2 w_3$$
 $I_2 \dot{w}_2 = (I_3 - I_1) w_3 w_1$
 $I_3 \dot{w}_3 = (I_1 - I_2) w_1 w_2$ nonlinear state space equations

This is a lossless system since the Kinetic Energy,

$$V(w_1, w_2, w_3) = \frac{1}{2}I_1w_1^2 + \frac{1}{2}I_2w_2^2 + \frac{1}{2}I_3w_3^2$$

$$\frac{dV}{dt} = I_1w_1\dot{w}_1 + I_2w_2\dot{w}_2 + I_3w_3\dot{w}_3$$

$$= w_1w_2w_3\left[(I_2 - I_3) + (I_3 - I_1) + (I_1 - I_2)\right]$$

$$= 0$$

 \Rightarrow if the trajectory starts on an ellipsoid $V(w_1, w_2, w_3) = \text{constant}$, it stays on it.

In addition conservation of angular momentum implies that,

$$\frac{d}{dt} \left\{ I_1^2 w_1^2 + I_2^2 w_2^2 + I_3^2 w_3^2 \right\} = 2w_1 w_2 w_3 \left[I_1 (I_2 - I_3) + I_2 (I_3 - I_1) + I_3 (I_1 - I_2) \right] = 0$$

Suppose $I_1 = 6$, $I_2 = 2$, $I_3 = 5$ then

$$\dot{w}_1 = -\frac{1}{2}w_2w_3
\dot{w}_2 = -\frac{1}{2}w_3w_1
\dot{w}_3 = \frac{4}{5}w_1w_2$$

Equilibrium Solutions satisfy: $\dot{w}_1 = \dot{w}_2 = \dot{w}_3 = 0 \implies w_2w_3 = w_1w_3 = w_1w_2 = 0 \implies$

either (a)
$$w_2 = w_3 = 0$$
 & $w_1 = \bar{w}_1$
or (b) $w_3 = w_1 = 0$ & $w_2 = \bar{w}_2$
or (c) $w_1 = w_2 = 0$ & $w_3 = \bar{w}_3$
or (d) $w_1 = w_2 = w_3 = 0$.

The linearized equations are

$$\frac{\dot{\delta}w}{\dot{\delta}w} \approx \frac{\partial f}{\partial \underline{w}} \underline{\delta w} = \begin{bmatrix} 0 & -\frac{1}{2}w_3 & -\frac{1}{2}w_2 \\ -\frac{1}{2}w_3 & 0 & -\frac{1}{2}w_1 \\ \frac{4}{5}w_2 & \frac{4}{5}w_1 & 0 \end{bmatrix} \underline{\delta w}.$$

$$\frac{\text{case (a)}}{\Rightarrow \underline{\delta i w}} \cong \begin{bmatrix} 0 & 0 & 0 \\ 0 & 1 & 0 & -\frac{1}{2} \overline{w_1} \\ 0 & \frac{14}{5} \overline{w_1} & 0 \end{bmatrix} \underline{\delta w}.$$

$$\Rightarrow \delta w_1(t) \simeq \delta w_1(0) \& \frac{d}{dt} \begin{bmatrix} \delta w_2 \\ \delta w_3 \end{bmatrix} \cong \begin{bmatrix} 0 & -\frac{1}{2} \bar{w}_1 \\ \frac{4}{5} \bar{w}_1 & 0 \end{bmatrix} \begin{bmatrix} \delta w_2 \\ \delta w_3 \end{bmatrix}$$

and the state trajectories are ellipses (with the ratio of the principal axes = $\sqrt{8/5} \simeq 1.26$.

$$\underline{\delta w} \simeq \begin{bmatrix}
0 & 0 & -\frac{1}{2}\bar{w}_2 \\
0 & 0 & 0 \\
\frac{4}{5}\bar{w}_2 & 0 & 0
\end{bmatrix} \underline{\delta w}$$

case (c)

$$\underline{\underline{\delta w}} \simeq \begin{bmatrix} 0 & -\frac{1}{2}\overline{w_3} & 0 \\ -\frac{1}{2}\overline{w_3} & 0 & 0 \\ 0 & 0 & 0 \end{bmatrix} \underline{\delta w}$$


 $\underline{\delta \dot{w}} \simeq \begin{bmatrix}
0 & -\frac{1}{2}\bar{w}_3 & 0 \\
-\frac{1}{2}\bar{w}_3 & 0 & 0 \\
0 & 0 & 0
\end{bmatrix}
\underline{\delta w}$ $\times = \pm \frac{\overline{\omega}_3}{2}$ $\times |\mathcal{K}_0(s)|$

$$\delta w_3(t) \simeq \delta w_3(0), \frac{d}{dt} \begin{bmatrix} \delta w_1 \\ \delta w_2 \end{bmatrix} = -\frac{1}{2} \bar{w}_3 \begin{bmatrix} 0 & 1 \\ 1 & 0 \end{bmatrix} \begin{bmatrix} \delta w_1 \\ \delta w_2 \end{bmatrix}$$

and

$$\begin{bmatrix} \delta w_1 \\ \delta w_2 \end{bmatrix} = \begin{bmatrix} 1 \\ 1 \end{bmatrix} e^{-\frac{1}{2}\tilde{w}_3t} \left(\frac{\delta w_1(0) + \delta w_2(0)}{2} \right) \\ + \begin{bmatrix} 1 \\ -1 \end{bmatrix} e^{\frac{1}{2}\tilde{w}_3t} \left(\frac{\delta w_1(0) - \delta w_2(0)}{2} \right)$$

UNSTABLE (A=WAW)



The trajectories in the 3-dimensional state space can thus be sketched as follows on a particular ellipsoid $V(w_1, w_2, w_3) = \text{const.}$




Figure 4: State space trajectories of a rotating rigid body

3.5 Convolution Integral

Consider

$$\dot{x} - A\underline{x} = B\underline{u} \tag{*}$$

Comparing with the scalar case note

$$\frac{d}{dt} \left\{ e^{-At} \underline{x}(t) \right\} = \frac{d}{dt} \left\{ e^{-At} \right\} \underline{x}(t) + e^{-At} \frac{d\underline{x}}{dt}$$
$$= -e^{-At} A\underline{x}(t) + e^{-At} \frac{d\underline{x}}{dt}$$

now premultiply (*) by e^{-At} to give

$$e^{-At} \frac{d\underline{x}}{dt} - e^{-At} A\underline{x} = e^{-At} B\underline{u}$$

$$\Rightarrow \frac{d}{dt} \left\{ e^{-At} \underline{x}(t) \right\} = e^{-At} B\underline{u}(t)$$

$$\Rightarrow e^{-At} \underline{x}(t) - \underline{x}_0 = \int_0^t e^{-A\tau} B\underline{u}(\tau) d\tau$$

$$\Rightarrow \underline{x}(t) = e^{At} \underline{x}_0 + e^{At} \int_0^t e^{-A\tau} B\underline{u}(\tau) d\tau$$

$$\Rightarrow \underline{x}(t) = e^{At} \underline{x}_0 + \int_0^t e^{A(t-\tau)} B\underline{u}(\tau) d\tau$$

and

$$\underline{\underline{y}(t)} = \underbrace{Ce^{At}\underline{x}_0}_{\text{initial condition response}} + \underbrace{D\underline{u}(t) + \int_0^t Ce^{A(t-\tau)}B\underline{u}(\tau) d\tau}_{\text{input response}}$$

Let
$$H(t) = \begin{cases} D\delta(t) + Ce^{At}B & t \ge 0 \\ 0 & t < 0 \end{cases}$$

then if $\underline{x}_0 = \underline{0}$,
$$\underline{y}(t) = \int_0^t H(t - \tau)\underline{u}(\tau)d\tau = H(t) * \underline{u}(t)$$

H(t) is called the **impulse response matrix**, since for multiple-input/multiple-output systems, if an impulse is applied at time 0^+ to the j-th input, with the other inputs at zero, then the i-th output will be

$$y_i(t) = \int_0^t h_{ij}(t-\tau)u_j(\tau)d\tau = h_{ij}(t)$$

Note that the transfer function, $G(s) = \mathcal{L}(H(t))$.

3.6 Frequency Response

Consider a linear time-invariant system that is asymptotically stable. What is the response due to sinusoidal input at each of the inputs? Let

$$u_i(t) = A_i \cos(\omega_0 t + \theta_i), j = 1, 2, \dots, m$$

then

$$y_i(t) \rightarrow B_i \cos(\omega_0 t + \phi_i)$$
 as $t \rightarrow \infty$

where

$$B_i e^{j\phi_i} = g_{i1}(j\omega_o) A_1 e^{j\theta_1} + g_{i2}(j\omega_o) A_2 e^{j\theta_2} + \dots + g_{im}(j\omega_o) A_m e^{j\theta_m}$$

i.e. the sum of the sinusoidal responses from each input. The rate at which the steady state is achieved depends on how quickly the impulse response tends to zero, which in turn depends on the pole positions.

3.7 Stability of $\dot{x} = Ax$

Stability of systems is concerned with whether as $t \to \infty$,

$$\underline{x}(t) \rightarrow 0$$
 $\rightarrow \infty$
or remains bounded?

but since $\underline{x}(t) = e^{At}\underline{x}_0$ the question becomes whether the elements of $e^{At} \to 0, \to \pm \infty$ or remain bounded as $t \to \infty$?

Consider

$$(sI - A)^{-1} = N(s)/\alpha(s)$$

where $\alpha(s)$ is the characteristic polynomial of A,

$$\alpha(s) = \det(sI - A) = s^n + \alpha_1 s^{n-1} + ... + \alpha_n$$

and

$$N(s) = N_1 s^{n-1} + N_2 s^{n-2} + ... + N_n$$

where N_i are $n \times n$ constant matrices. (Recall section 3.2.)

If we factor $\alpha(s)$ as

$$\alpha(s) = (s - \lambda_1)^{n_1} (s - \lambda_2)^{n_2} ... (s - \lambda_r)^{n_r}$$

where λ_i will be the eigenvalues of A and $n_1 + n_2 + ... + n_r = n = \dim(A)$, then the partial fraction expansion gives

$$(sI - A)^{-1} = \sum_{i=1}^{r} \sum_{k=1}^{n_i} \frac{C_{i,k}}{(s - \lambda_i)^k}$$

for suitable constant matrices $C_{i,j}$.

The inverse transform then gives

$$e^{At} = \sum_{i=1}^{r} \sum_{k=1}^{n_i} \frac{C_{i,k} t^{k-1} e^{\lambda_i t}}{(k-1)!}$$

Let $\lambda_i = \sigma_i + j\omega_i$ then $\left| e^{\lambda_i t} \right| = e^{\sigma_i t} \left| e^{j\omega_i t} \right| = e^{\sigma_i t}$

3 cases

(i)
$$\sigma_i < 0, \left| t^{k-1} e^{A_i t} \right| \to 0, k = 1, 2, 3, ...$$

(ii)
$$\sigma_i > 0, \left| t^{k-1} e^{\lambda_i t} \right| \rightarrow \infty, k = 1, 2, 3, \dots$$

(iii)
$$\sigma_i = 0$$

(a)
$$|t^{k-1}e^{\lambda_i t}| = 1$$
 $k = 1$


(b)
$$\left|t^{k-1}e^{\lambda_i t}\right| \to \infty$$
 $k = 2, 3,.$

Hence $\underline{x}(t) \to \underline{0}$ as $t \to \infty$ for all \underline{x}_0 if and only if all λ_i satisfy $Re(\lambda_i) < 0$. (i.e. case i)).

Also $\underline{x}(t)$ remains bounded as $t \to \infty$ for all \underline{x}_0 if and only if $Re(\lambda_i) \le 0$ and in partial fraction expansion of $(sI - A)^{-1}$ there are <u>no</u> terms of the form $C_{i,k}/(s - j\omega_i)^k$ with $k \ge 2$. (i.e. case (i) or (iii)(a).).

4 State Space Equations for Composite Systems

4.1 Cascade of Two Systems



Let $G_1(s)$ be realized by the state equation:

$$\begin{cases} \dot{\underline{x}}_1(t) &= A_1\underline{x}_1(t) + B_1\underline{u}(t) \\ \underline{w}(t) &= C_1\underline{x}_1(t) + D_1\underline{u}(t) \end{cases}$$

and $G_2(s)$ be realized by, (input \underline{w} , output \underline{y})

$$\begin{cases} \underline{\dot{x}}_{2}(t) = A_{2}\underline{x}_{2}(t) + B_{2}\underline{w}(t) \\ \underline{y}(t) = C_{2}\underline{x}_{2}(t) + D_{2}\underline{w}(t) \end{cases} = A_{2} \mathcal{L}_{1} + B_{2} \left(C_{1} \mathcal{L}_{1} + D_{1} C_{1} \right)$$

put 26 = | 261

then
$$\underline{Y}(s) = G_2(s)G_1(s)\underline{U}(s)$$
 is realized by

$$\underbrace{\frac{d}{dt} \begin{bmatrix} \underline{x}_{1}(t) \\ \underline{x}_{2}(t) \end{bmatrix}}_{\underline{\underline{x}}(t)} = \underbrace{\begin{bmatrix} A_{1} & 0 \\ B_{2}C_{1} & A_{2} \end{bmatrix}}_{A} \underbrace{\begin{bmatrix} \underline{x}_{1}(t) \\ \underline{x}_{2}(t) \end{bmatrix}}_{\underline{X}(t)} + \underbrace{\begin{bmatrix} B_{1} \\ B_{2}D_{1} \end{bmatrix}}_{B} \underline{\underline{u}}(t)$$


$$\underline{\underline{y}}(t) = \underbrace{\left[\begin{array}{cc} D_2C_1 & C_2 \end{array}\right]}_{C} \underline{\underline{x}}(t) + \underbrace{D_2D_1}_{D} \underline{\underline{u}}(t)$$

The cascade realization of a single-input single-output system can hence be obtained if G(s) is factored into second order factors such as

$$G(s) = A \frac{(s^2 + c_1 s + d_1)}{(s^2 + a_1 s + b_1)} \frac{(s^2 + c_2 s + d_2) \dots}{(s^2 + a_2 s + b_2) \dots}$$

then the overall system can be realized as the cascade of these factors.

4.2 Parallel combination of two systems



Let $G_1(s)$ be realized by the state equation:

$$\begin{cases} \underline{\dot{x}}_1(t) &= A_1\underline{x}_1(t) + B_1\underline{u}(t) \\ \underline{y}_1(t) &= C_1\underline{x}_1(t) + D_1\underline{u}(t) \end{cases}$$

and $G_2(s)$ be realized by, (input \underline{u} , output \underline{y}_2)

$$\begin{cases} \dot{\underline{x}}_2(t) = A_2\underline{x}_2(t) + B_2\underline{u}(t) \\ \underline{y}_2(t) = C_2\underline{x}_2(t) + D_2\underline{u}(t) \end{cases}$$

then $\underline{Y}(s) = (G_1(s) + G_2(s))\underline{U}(s)$ is realized by

$$\underbrace{\frac{d}{dt} \left[\begin{array}{c} \underline{x}_{1}(t) \\ \underline{x}_{2}(t) \end{array} \right]}_{\dot{x}(t)} = \underbrace{\left[\begin{array}{c} A_{1} & 0 \\ 0 & A_{2} \end{array} \right]}_{A} \underbrace{\left[\begin{array}{c} \underline{x}_{1}(t) \\ \underline{x}_{2}(t) \end{array} \right]}_{X(t)} + \underbrace{\left[\begin{array}{c} B_{1} \\ B_{2} \end{array} \right]}_{B} \underline{u}(t)$$

$$\underline{\underline{y}}(t) = \underbrace{\left[\begin{array}{cc} C_1 & C_2 \end{array}\right]}_{C} \underline{\underline{x}}(t) + \underbrace{(D_1 + D_2)}_{D} \underline{\underline{u}}(t)$$

IN GENERAL

- 1) WRITE DOWN STATE-SPACE EQUATIONS FOR ALL SUB-SYSTEMS
- 2) ASSEMBLE STATES INTO NEW STATE VECTOR
- 3) ELIMENATE ALL OTHER INTERNAL VARIABLES
 (e.g w, g, y, yz...)

Module 3F2: Systems and Control

LECTURE NOTES 2: 'CLASSICAL' METHODS

1	Revi	Revision of Feedback Control			
	1.1	Why use Feedback?	2		
	1.2	The Standard Feedback Loop	2		
	1.3	Sensitivity and Complementary Sensitivity	3		
	1.4	Steady-state Error	4		
	1.5	The Nyquist Stability Theorem	4		
2	The	Root-Locus Method	5		
	2.1	An Example	5		
	2.2	The Angle Condition	6		
	2.3	Finding Gain from the Root-Locus Plot	6		
	2.4	Constructing the Root-Locus Plot	7		
	2.5	Root-locus for negative k (or negative c)	9		
	2.6	Studying Parameter Variations	0		
3	The	Routh-Hurwitz Criterion 1	2		
J.N	J.M. Maciejowski February 2				
G. Vinnicombe February 201					

1 Revision of Feedback Control

1.1 Why use Feedback?

• To reduce effects of uncertainty:

- Disturbances

Wind/waves, Friction, Impurities, . . .

Approximations, Tolerances, Ageing, . . .

- Model errors

• To stabilise unstable system:

- Inverted pendulum, Bicycle

- High-performance fighter aircraft (Fly-by-wire)

- Helicopter, Sul

Submarine (depth)


- Exothermic chemical reactor,

Nuclear reactor

Problems with feedback:

- · May destabilise system
- · Sensors introduce noise

1.2 The Standard Feedback Loop



ONDER OF MULTIPLICATION MATTERS

1.3 Sensitivity and Complementary Sensitivity

Let L(s) be the (open) loop transfer function: L(s) = G(s)K(s)

"Return-ratio"

Complementary Sensitivity: $T(s) = \frac{L(s)}{1+L(s)}$

(Multivariable: $T(s) = L(s)[I + L(s)]^{-1}$

$$\bar{y} = T\bar{r} = -T\bar{n}$$
 (\bar{n} = sensor noise)

(= # (I+L)"L)

 $T \approx 1 \Rightarrow \text{good "tracking" but no noise filtering.}$

Sensitivity:
$$S(s) = \frac{1}{1 + L(s)}$$

(Multivariable: $S(s) = [I + L(s)]^{-1}$)

$$\bar{e} = S\bar{r}, \quad S = \frac{dT/T}{dG/G}, \qquad \qquad \bar{y} = GS\tilde{d}$$

Small $|S| \Rightarrow$ feedback is beneficial.

Fact:

$$S(s) + T(s) = 1$$

(Multivariable: S(s) + T(s) = I)

Hence trade-off:

- Small $|S(j\omega)|$ at low frequencies
- Small $|T(j\omega)|$ at high frequencies.




Figure 1.1: Sensitivity (S) and Complementary Sensitivity (T)

1.4 Steady-state Error

Constant reference:
$$r(t) = \alpha$$
,

$$\bar{r}(s) = \frac{\alpha}{s}$$
.

Assume closed-loop is asymptotically stable.

$$\lim_{t\to\infty} e(t) = S(0)\alpha = \frac{1}{1+L(0)}\alpha$$

(Final Value Theorem or $S(j\omega)$ with $\omega = 0$)

$$\lim_{t\to\infty} e(t) = 0$$
 if $|G(0)K(0)| = \infty \iff G(s)K(s)$ has pole at $s = 0$ — integral action

Constant disturbance: $d(t) = \beta$, $\bar{d}(s) = \frac{\beta}{s}$.

$$=\beta, \qquad \bar{d}(s)=\frac{b}{2}$$

 $\frac{\partial}{\partial t} = -GS$. Zero steady-state error $\Leftarrow K(s)$ has pole at s = 0.

Ramp reference: $r(t) = \alpha t$,

$$\bar{r}(s) = \frac{\alpha}{s^2}.$$

$$\lim_{t\to\infty} e(t) = \lim_{s\to 0} s\bar{e}(s) = \lim_{s\to 0} \frac{\alpha}{s} S(s).$$

(Final Value Theorem)

Hence:

- Finite steady-state error $\Leftarrow G(s)K(s)$ has a pole at s=0.
- Zero steady-state error $\Leftarrow G(s)K(s)$ has two poles at s=0.

Small steady-state error requires high gain at "DC



1.5 The Nyquist Stability Theorem

Motivation:

- The frequency response can be determined experimentally.
- Or from transfer function or state-space model.
- Want a test for closed-loop stability that uses *open-loop* information.

Theorem:

- Plot $L(j\omega) = G(j\omega)K(j\omega)$ on the Argand diagram, for $-\infty < \omega < +\infty$ — the Nyquist plot.
- The closed loop is stable if and only if the Nyquist plot encircles the point $-1 + j0 p_u$ times counterclockwise, where p_u is the number of *unstable poles* of G(s) and K(s).

2 The Root-Locus Method




Figure 2.1:

Root-locus diagram for

'rlocus' in Matlab

$$L(s) = \frac{s+5}{s(s^2+6s+10)}$$

This shows the locations of the roots of 1 + kL(s) = 0 for k > 0.

In this case $0 \le k \le 2 \times 10^4$.

Useful when the loop dynamics are fixed, and only the gain varies.

2.2 The Angle Condition

$$L(s) = \frac{n(s)}{d(s)} = \frac{c(s-z_1)(s-z_2)\dots(s-z_m)}{(s-p_1)(s-p_2)\dots(s-p_n)}$$

$$coles occur in conjugate pairs and $m \le n$.$$

where any complex zeros or poles occur in conjugate pairs and $m \le n$

We assume for the moment that c > 0.

Suppose that s_0 is on the root-locus:

Hence angle condition for
$$s_0$$
 to be on the root-locus:

$$1 + kL(s_0) = 0 \Rightarrow L(s_0) = -\frac{1}{k}$$
real and negative
$$(2.1)$$

$$\angle L(s_0) = (2\ell+1)\pi \tag{2.2}$$


$$\sum_{i=1}^{m} \angle(s_0 - z_i) - \sum_{i=1}^{n} \angle(s_0 - p_i) = (2\ell + 1)\pi$$
 (2.3)

Finding Gain from the Root-Locus Plot

Once a root-locus plot has been obtained, it can be calibrated with k values. From (2.1) we have, at a point s_0 on the root-locus:

$$k = \frac{1}{|L(s_0)|}$$

$$= \frac{1}{c} \times \frac{|s_0 - p_1| \times |s_0 - p_2| \times \dots \times |s_0 - p_n|}{|s_0 - z_1| \times |s_0 - z_2| \times \dots \times |s_0 - z_m|}$$



$$L = \frac{5+5}{5(5+3+j)(5+3-j)}$$

$$L(50) = 47^{\circ} - 100^{\circ} - 59^{\circ} - 68^{\circ}$$

$$= -180^{\circ} (!)$$

2.4 Constructing the Root-Locus Plot

Nowadays we can use software to draw root-locus diagrams (eg rlocus in Matlab).

But it is useful to have some understanding of how the form of the locus is determined. A set of about 15 'construction rules' has been developed. The 5 most important ones are given here. They are all consequences of (2.3) and properties of polynomials.

- Rule 1. The root-locus diagram is symmetric with respect to the real axis and consists of n branches.
- Rule 2. For k = 0 the *n* branches start at the open loop poles p_i . As $k \to \infty$, *m* branches tend to the zeros z_i and n m branches tend to infinity.
- Rule 3. Points on the real axis which lie to the left of an odd number of poles and zeros are on the root-locus.
- Rule 4. The breakaway points are those points on the root-locus for which $\frac{d}{ds}L(s) = 0$ (same as dk/ds = 0).
- Rule 5. As $k \to \infty$, the n-m branches which tend to infinity do so along straight line asymptotes at angles $(2\ell+1)\pi/(n-m)$ to the +ve real axis $(\ell=0,\ldots,n-m-1)$, and emanate from the point ('centre of gravity' pole +ve mass, zero -ve mass):

$$\frac{\sum_{i=1}^{n} p_i - \sum_{i=1}^{m} z_i}{n - m}.$$

Proof of Rule 3:

Consider a point s_0 , a pole p_i , and a zero z_i , all on the real axis.

$$\angle(s_0 - p_i) = \begin{cases} 0 \text{ if } s_0 > p_i \\ \pi \text{ if } s_0 < p_i \end{cases}$$

The same holds for $\angle(s_0 - z_i)$. Rule 3 follows from (2.3).

Example of use of Rule 3:

Suppose that G(s) has one pole and one zero in the right half-plane, eg $p_1 = +5$, $z_1 = +2$. Rule 3 shows that K(s) must have at least one pole to the right of +2.

— the controller must be unstable!

(Figuring out the details is often easier from Bode plots etc.)

IIn(5)

Re(s)

POLE

Proof of Rule 2:

$$d(s_0) + kn(s_0) = 0$$
 from (2.1)

So if k = 0 then $d(s_0) = 0 \Rightarrow$ Branches start at poles.

Also, for any fixed k,

(2.1)
$$\iff \frac{1}{k}d(s_0) + n(s_0) = 0$$

So, as $k \to \infty$ the finite roots tend to zeros (i.e. finite branches end at zeros). There can be at most m of them.

(to see this, put $n(s) = (s - s_0)n'(s)$, then for s close to s_0 we have $s = s_0 - \frac{1}{k} \frac{d(s_0)}{n'(s_0)} \rightarrow s_0$.)

$$-K = \frac{1}{L(s)} = \frac{(s-P_1)(s-P_2)...}{c(s-z_1)(s-z_2)...}$$

$$-Kc = \frac{s-2P_1s^{n-1}+...}{s^{n}-zz_0s^{n-1}+...}$$

The remaining
$$n-m$$
 branches go to ∞ , but how?

Proof of Rule 5:

$$-\mathcal{K} = \frac{1}{L(s)} = \frac{(s-P_1)(s-P_2)}{c(s-P_2)(s-P_2)}...$$

$$-\mathcal{K} c = \frac{s-P_1(s-P_2)}{s}...$$

$$-\mathcal{K} c = \frac{s-P_1(s-P_2)}{s}...$$
Application to previous example:
$$n = 3, m = 1, \text{ so } n - m = 2. \text{ Two asymptotes at angles } \pi/2 \text{ and } 3\pi/2.$$
Asymptotes emanate from (Rule 5):
$$\frac{(s-P_1)(s-P_2)}{s}...$$

$$-\mathcal{K} c = \frac{s-P_1(s-P_2)}{s}...$$

$$-\mathcal{K$$

$$\frac{(0-3-3)-(-5)}{3-1} = -\frac{1}{2}$$
 = $\frac{1}{2}$ = $\frac{\sum P_{i}-\sum Z_{i}}{N-N}$

Proof of Rule 4: Repeated was as 5=50

Application of Rule 4 to example of Fig.2.1:

$$\frac{d}{ds} \left(\frac{s+5}{s^3 + 6s^2 + 10s} \right) = 0$$

$$\Rightarrow \frac{1(s^3 + 6s^2 + 10s) - (s+5)(3s^2 + 12s + 10)}{(s^3 + 6s^2 + 10s)^2} = 0$$

$$\Rightarrow \frac{-2s^3 - 21s^2 - 60s - 50}{(s^3 + 6s^2 + 10s)^2} = 0$$


$$\Rightarrow \frac{-2(s+1.5505)(s+2.5)(s+6.4495)}{(s^3 + 6s^2 + 10s)^2} = 0$$


From Fig. 2.1 it is seen that the root at -6.4495 is not on the root-locus. The other two roots give the breakaway points (ie repeated roots).


2.5 Root-locus for negative k (or negative c)

$$1 + kG(s_0) = 0 \implies G(s_0) = -\frac{1}{k} > 0$$
$$\implies \angle G(s_0) = 2\ell\pi$$

- Rules 1,2,4 remain unchanged.
- Rule 3: Replace 'odd' by 'even'.
- Angles of asymptotes become $2\ell\pi/(n-m)$. (Points from which asymptotes emanate remain unchanged.)







Root-locus diagram for negative gain when

$$L(s) = \frac{s+5}{s(s^2+6s+10)}$$

Studying Parameter Variations

Root-locus diagrams can be used to study the variation of closed-loop poles as other parameters vary not just the loop-gain k.

All that is needed is to put the closed-loop characteristic equation into the form

$$1 + \lambda H(s) = 0 \tag{2.4}$$

where λ is the parameter that is varying, and H(s) is a transfer function.

Example: Robot placing objects of varying mass

The 1-D equation of motion of a robot moving a mass m with viscous friction c and elastic tether is $m\ddot{x} = u - c\dot{x} - \alpha x$ where x is the mass position and u is the applied force. The use of a PI controller is proposed, with a transfer function k(s+z)/s.

With m = 0.1 kg, c = 0.6 N/(m/sec), $\alpha = 1$ N/m and z = 5 we have

$$G(s) = \frac{1}{0.1s^2 + 0.6s + 1} = \frac{10}{s^2 + 6s + 10}$$
 and $K(s) = k\frac{s + 5}{s}$

Letting L(s) = G(s)K(s)/k the closed-loop characteristic equation is 1 + kL(s) = 0.

Using Fig.2.1, 10k = 1.395 places two closed-loop poles at -1.55 (one of the breakaway points) and the ch = TT [5-P] (gain condition) third pole at -2.9.

What if the mass varies?

The closed-loop characteristic equation is

$$1 + k \frac{(s+5)}{s(ms^2 + 0.6s + 1)} = 0$$

which has the same roots as

or
$$(ms^{3} + 0.6s^{2} + s) + k(s + 5) = 0$$

$$1 + (m) \frac{(0.6s^{2} + [1 + k]s + 5k)}{s^{3}} = 0$$

which is in the form of (2.4) with $\lambda = 1/m$. The root-locus plot for this, with k = 1.395/10, is shown in Fig.2.2. The roots with m = 0.1 are marked.

Variations of closed-loop poles as 1/m varies can be clearly seen.




Figure 2.2: Root-locus diagram for variation of mass in robot problem.

3 The Routh-Hurwitz Criterion

The closed-loop characteristic equation

$$1 + G(s)K(s) = 0$$

has the same roots as

$$d_G(s)d_K(s) + n_G(s)n_K(s) = 0$$
 polynomial

The Routh-Hurwitz criterion tests whether a polynomial has any roots with nonnegative real parts. So it tests for asymptotic stability.

Sometimes useful for finding value of k at which root-locus crosses imaginary axis.

Consider the polynomial (assume $a_0 > 0$):

$$a_0s^n + a_1s^{n-1} + a_2s^{n-2} + \dots + a_{n-1}s + a_n$$
 (3.5)

Easy to check that all roots have negative real parts only if $a_i > 0$ for each i.

A Routh array can be constructed for arbitrary n

- see Franklin, Powell and Emami-Naeini, 3rd edition, sec.4.4.3 (for example) for details.

For n = 2, 3, 4 simplifies as follows:

These are in Electrical and Information Data Book

All the roots of (3.5) have negative real parts if and only if:

n=2: $a_i > 0$, No other conditions

n = 3 : $a_i > 0$, $a_1 a_2 > a_0 a_3$

n=4 : $a_i > 0$, $a_1 a_2 a_3 > a_0 a_3^2 + a_4 a_1^2$