26-Docker安装nginx以及部署

整理:参码踪田不平

时间: 2020-03-18

联系: 3350996729 (QQ)

官网: http://www.shenmazong.com

1、nginx简介

1)、来源

Nginx (engine x) 是一个高性能的HTTP和反向代理web服务器,同时也提供了IMAP/POP3/SMTP服务。Nginx是由伊戈尔·赛索耶夫为俄罗斯访问量第二的Rambler.ru站点(俄文: Рамблер)开发的,第一个公开版本0.1.0发布于2004年10月4日。

其将源代码以类BSD许可证的形式发布,因它的稳定性、丰富的功能集、示例配置文件和低系统资源的消耗而闻名。2011年6月1日,nginx 1.0.4发布。

Nginx是一款轻量级的Web 服务器/反向代理服务器及电子邮件(IMAP/POP3)代理服务器,在BSD-like 协议下发行。其特点是占有内存少,并发能力强,事实上nginx的并发能力在同类型的网页服务器中表现较好,中国大陆使用nginx网站用户有:百度、京东、新浪、网易、腾讯、淘宝等。



2) 、源代码

Nginx代码完全用C语言从头写成,已经移植到许多体系结构和操作系统,包括: Linux、FreeBSD、Solaris、Mac OS X、AlX以及Microsoft Windows。Nginx有自己的函数库,并且除了zlib、PCRE和OpenSSL之外,标准模块只使用系统C库函数。而且,如果不需要或者考虑到潜在的授权冲突,可以不使用这些第三方库。

3) 、服务器

Tomcat

IIS(Window)

Apache

Nginx

Nginx作为负载均衡服务: Nginx 既可以在内部直接支持 Rails 和 PHP 程序对外进行服务,也可以支持作为 HTTP代理服务对外进行服务。Nginx采用C进行编写,不论是系统资源开销还是CPU使用效率都比 Perlbal 要好很多。

处理静态文件,索引文件以及自动索引;打开文件描述符缓冲。

无缓存的反向代理加速,简单的负载均衡和容错。

FastCGI,简单的负载均衡和容错。

模块化的结构。包括 gzipping, byte ranges, chunked responses,以及 SSI-filter 等 filter。如果由 FastCG或其它代理服务器处理单页中存在的多个 SSI,则这项处理可以并行运行,而不需要相互等待。 支持 SSL 和 TLSSNI。

4) 、优点

Nginx 可以在大多数 Unix/Linux OS 上编译运行,并有 Windows 移植版。 Nginx 的1.4.0稳定版已经于 2013年4月24日发布,一般情况下,对于新建站点,建议使用最新稳定版作为生产版本,已有站点的升级急迫性不高。

Nginx 是一个很强大的高性能Web和反向代理服务,它具有很多非常优越的特性:

在连接高并发的情况下,Nginx是Apache服务不错的替代品:Nginx在美国是做虚拟主机生意的老板们经常选择的软件平台之一。能够支持高达 50,000 个并发连接数的响应,感谢Nginx为我们选择了 epoll and kqueue作为开发模型。

5) 、代理

作为邮件代理服务: Nginx 同时也是一个非常优秀的邮件代理服务(最早开发这个产品的目的之一也是作为邮件代理服务器),Last.fm 描述了成功并且美妙的使用经验。

Nginx 是一个安装非常的简单、配置文件非常简洁(还能够支持perl语法)、Bug非常少的服务。Nginx 启动特别容易,并且几乎可以做到7*24不间断运行,即使运行数个月也不需要重新启动。你还能够不间断服务的情况下进行软件版本的升级。

2、nginx的安装

1) 、下载镜像

docker pull nginx:1.17.8

```
[root@iZlwo3fsqciqqbZ ~]# docker pull nginx:1.17.8

1.17.8: Pulling from library/nginx

68ced04f60ab: Pull complete

c4039fd85dcc: Pull complete

c16ce02d3d61: Pull complete

Digest: sha256:380eb808e2a3b0dd954f92c1cae2f845e6558a15037efefcabc5b4e03d666d03

Status: Downloaded newer image for nginx:1.17.8

docker.io/library/nginx:1.17.8

[root@iZlwo3fsqciqqbZ ~]# [
```

2)、查看镜像

docker images

```
[root@iZlwo3fsqciqqbZ ~]# docker images
REPOSITORY TAG IMAGE ID CREATED SIZE
nginx 1.17.8 a1523e859360 41 hours ago 127MB
[root@iZlwo3fsqciqqbZ ~]# □
```

3)、测试镜像

```
sudo docker run --name nginx -p 9091:80 -d nginx:1.17.8
 docker ps
 http://39.105.82.148:9091
root@iZlwo3fsqciqqbZ nginx]# sudo docker run --name nginx -p 9091:80 -d nginx:1.17.8
47b68e53c58edafdb55bb7c3ed4ed3b67fc8b7a0c5e757450740cff2421f4a54
[root@iZlwo3fsqciqqbZ nginx]# docker ps
                                 COMMAND
CONTAINER ID
                IMAGE
                                                      CREATED
                                                                       STATUS
                                                                                         PORTS
                                                                                                            NAMES
47b68e53c58e
                nginx:1.17.8
                                 "nginx -g 'daemon of..." 11 seconds ago
                                                                       Up 10 seconds
                                                                                         0.0.0.0:9091->80/tcp
                                                                                                            nginx
[root@iZlwo3fsqciqqbZ nginx]# [
 \leftarrow \rightarrow C \triangle

    不安全

 应用 🗀 在线工具 🗀 项目

◆ 承诺 - JavaScript |...
```

Welcome to nginx!

If you see this page, the nginx web server is successfully installed and working. Further configuration is required.

For online documentation and support please refer to <u>nginx.org</u>. Commercial support is available at <u>nginx.com</u>.

Thank you for using nginx.

4) 、容器部署

```
# 创建www目录
mkdir -p /server/nginx/html
# 创建日志目录
mkdir -p /server/nginx/logs
# 创建配置目录
mkdir -p /server/nginx/conf
```

拷贝容器内 Nginx 默认配置文件到本地当前目录下的 conf 目录,容器 ID 可以查看 docker ps 命令输入中的第一列:

```
## 拷贝配置文件
docker cp f77f78d2228d:/etc/nginx/nginx.conf ~/nginx/conf
## 映射容器目录
```

```
docker run -d -p 9091:80 --name nginx -v
/server/nginx/html:/usr/share/nginx/html -v
/server/nginx/conf/nginx.conf:/etc/nginx/nginx.conf -v
/server/nginx/logs:/var/log/nginx --privileged=true nginx:1.17.8
docker run -d -p 9091:80 --name nginx -v
/server/nginx/html:/usr/share/nginx/html nginx:1.17.8
##
sudo docker run -d -p 9091:443 --name nginx \
-v /home/centos/server/nginx/html:/usr/share/nginx/html \
-v /home/centos/server/nginx/conf/nginx.conf:/etc/nginx/nginx.conf \
-v /home/centos/server/nginx/logs:/var/log/nginx \
nginx:1.17.8
## 查看运行容器
docker ps
## 如果因为权限问题,需要加上--privileged=true这个参数
docker run -d -p 9091:80 --name nginx -v
/server/nginx/html:/usr/share/nginx/html --privileged=true nginx:1.17.8
[root@localhost nginx]# docker run -d -p 9091:80 --name nginx -v
/server/nginx/html:/usr/share/nginx/html -v
/server/nginx/conf/nginx.conf:/etc/nginx/nginx.conf -v
/server/nginx/logs:/var/log/nginx nginx:1.17.8
949f5d7cdebff5de5edc4d204f73d88da9e663eae75059295ea80c39138df0b0
docker: Error response from daemon: OCI runtime create failed:
container_linux.go:346: starting container process caused
"process_linux.go:449: container init caused \"rootfs_linux.go:58: mounting
\\\"/server/nginx/conf/nginx.conf\\\" to rootfs
\\"/var/lib/docker/overlay2/7c94763f88d871bb4d80d41fecbac8d6595b17cfc6e636c81
744ddcb21a42270/merged\\\" at
\\"/var/lib/docker/overlay2/7c94763f88d871bb4d80d41fecbac8d6595b17cfc6e636c81
744ddcb21a42270/merged/etc/nginx/nginx.conf\\\" caused \\\"not a
directory\\"\"": unknown: Are you trying to mount a directory onto a file (or
vice-versa)? Check if the specified host path exists and is the expected type.
```

5) 、检查配置

为了验证配置文件是否正确,可以通过如下命令:

```
# 进入容器
docker exec -it nginx /bin/bash
# 检查配置文件
nginx -t
```

```
[root@iZlwo3fsqciqqbZ ~]# docker exec -it nginx /bin/bash root@804b395f0864:/# nginx -t nginx: the configuration file /etc/nginx/nginx.conf syntax is ok nginx: configuration file /etc/nginx/nginx.conf test is successful root@804b395f0864:/# []
```

6) 、启动服务

```
# 重新载入配置文件
nginx -s reload
# 重启 Nginx
nginx -s reopen
# 停止 Nginx
nginx -s stop
```

3、web服务器

1) 默认配置

```
user nginx;
worker_processes 1;
error_log /var/log/nginx/error.log warn;
pid
     /var/run/nginx.pid;
events {
   worker connections 1024;
http {
    include /etc/nginx/mime.types;
    default_type application/octet-stream;
    log_format main '$remote_addr - $remote_user [$time_local] "$request" '
                     '$status $body_bytes_sent "$http_referer" '
                     '"$http_user_agent" "$http_x_forwarded_for"';
    access_log /var/log/nginx/access.log main;
    sendfile
                   on;
    #tcp_nopush
                  on;
    keepalive timeout 65;
    #gzip on;
```

```
include /etc/nginx/conf.d/*.conf;
}
```

2) server_name

(1) 准确匹配

```
server {
  listen 80;
  server_name www.shenmazong.com;
  #...
}
```

(2) 通配符开始

```
server {
  listen 80;
  server_name *.shenmazong.com;
  #...
}
```

(3) 通配符结束

```
server {
  listen 80;
  server_name www.shenmazong.*;
  #...
}
```

(4) 正则表达式

```
server {
  listen 80;
  server_name ~^(?.+)\.shenmazong\.org$;
  #...
}
```

3)、普通配置

- (1) 创建html 文件
- (2) 修改hosts文件
- (3) 修改nginx.conf文件
- (4) 重启docker

```
# For more information on configuration, see:
# * Official English Documentation: http://nginx.org/en/docs/
  * Official Russian Documentation: http://nginx.org/ru/docs/
user nginx;
worker_processes auto;
error log /var/log/nginx/error.log;
pid /run/nginx.pid;
# Load dynamic modules. See /usr/share/nginx/README.dynamic.
# include /usr/share/nginx/modules/*.conf;
events {
   worker connections 1024;
}
http {
    log format main '$remote addr - $remote user [$time local] "$request" '
                      '$status $body_bytes_sent "$http_referer" '
                      '"$http_user_agent" "$http_x_forwarded_for"';
    access_log /var/log/nginx/access.log main;
    sendfile
                        on;
    tcp_nopush
                        on;
    tcp_nodelay
                        on;
    keepalive_timeout
                        65;
    types hash max size 2048;
    include
                        /etc/nginx/mime.types;
    default type
                        application/octet-stream;
    # Load modular configuration files from the /etc/nginx/conf.d directory.
    # See http://nginx.org/en/docs/ngx_core_module.html#include
    # for more information.
    # include /etc/nginx/conf.d/*.conf;
  # www.shenmazong.com
    server {
        listen
                    80;
        listen
                    [::]:80;
        server_name www.shenmazong.com;
                    /usr/share/nginx/html/www.shenmazong.com;
        root
        # Load configuration files for the default server block.
        # include /etc/nginx/default.d/*.conf;
        location / {
                 /usr/share/nginx/html/www.shenmazong.com;
```


```
index index.html index.htm;
        }
        error_page 404 /404.html;
           location = /40x.html {
        }
        error_page 500 502 503 504 /50x.html;
           location = /50x.html {
        }
    }
  # blog.shenmazong.com
    server {
       listen
                    80;
       listen
                    [::]:80;
       server_name blog.shenmazong.com;
                    /usr/share/nginx/html/blog.shenmazong.com;
        # Load configuration files for the default server block.
        # include /etc/nginx/default.d/*.conf;
       location / {
         root /usr/share/nginx/html/blog.shenmazong.com;
         index index.html index.htm;
        }
        error_page 404 /404.html;
           location = /40x.html {
        }
        error_page 500 502 503 504 /50x.html;
           location = /50x.html {
        }
    }
# Settings for a TLS enabled server.
    server {
        listen
                    443 ssl http2 default server;
                    [::]:443 ssl http2 default server;
        listen
        server_name _;
#
        root
                    /usr/share/nginx/html;
        ssl_certificate "/etc/pki/nginx/server.crt";
        ssl_certificate_key "/etc/pki/nginx/private/server.key";
        ssl_session_cache shared:SSL:1m;
         ssl session timeout 10m;
        ssl_ciphers HIGH:!aNULL:!MD5;
```

```
ssl_prefer_server_ciphers on;
#
         # Load configuration files for the default server block.
#
         include /etc/nginx/default.d/*.conf;
#
         location / {
         }
         error_page 404 /404.html;
             location = /40x.html {
         }
#
         error page 500 502 503 504 /50x.html;
             location = /50x.html {
#
#
     }
```

4、反向代理


1) 、什么是代理

代理服务器,客户机在发送请求时,不会直接发送给目的主机,而是先发送给代理服务器,代理服务接 受客户机请求之后,再向主机发出,并接收目的主机返回的数据,存放在代理服务器的硬盘中,再发送 给客户机。




2) 、没有代理

在没有代理的情况下,客户端和nginx服务端,都是客户端,都是客户端之间请求服务端,服务端则直接响应客户端。



3)、企业场景

在互联网请求里面,客户端往往无法直接向服务端发起请求,那么就需要实现客户端和服务通信。



4) 、代理模式

nginx 作为代理服务,按照应用场景进行总结,代理分为正向代理,反向代理

(1) 正向代理

正向代理:客户端 <一> 代理 一>服务端:

正向代理简单地打个租房的比方:

A(租客)B(中介)C(房东)

A(客户端)想租C(服务端)的房子,但是A(客户端)并不认识C(服务端)租不到。 B(代理)认识C(服务端)能租这个房子所以你找了B(代理)帮忙租到了这个房子。

在这个过程中:

C(服务端)不认识A(客户端)只认识B(代理) C(服务端)并不知道A(客户端)租了房子,只知道房子租给了B(代理)。而A(租客)是知道自己租的是C(房东)的房子

正向代理,架设在客户机与目标主机之间,只用于代理内部网络对Internet的连接请求,客户机必须指定代理服务器,并将本来要直接发送到Web服务器上的http请求发送到代理服务器中。

(2) 反向代理

反向代理:客户端 一>代理 <一> 服务端

反向代理也用一个租房的例子:

A(客户端)想租一个房子,B(代理)就把这个房子租给了他。 这时候实际上C(服务端)才是房东。 B(代理)是中介把这个房子租给了A(客户端)。这个过程中A(客户端)并不知道这个房子到底谁才是房东 他都有可能认为这个房子就是B(代理)的。

反向代理服务器架设在服务器端,通过缓冲经常被请求的页面来缓解服务器的工作量,将客户机请求转发给内部网络上的目标服务器;并将从服务器上得到的结果返回给Internet上请求连接的客户端,此时代理服务器与目标主机一起对外表现为一个服务器。

5、反向代理的作用

现在许多大型web网站都用到反向代理。除了可以防止外网对内网服务器的恶性攻击、缓存以减少服务器的压力和访问安全控制之外,还可以进行负载均衡,将用户请求分配给多个服务器。

- 1) 提高访问速度 由于目标主机返回的数据会存放在代理服务器的硬盘中,因此下一次客户再访问相同的站点数据时,会直接从代理服务器的硬盘中读取,起到了缓存的作用,尤其对于热门站点能明显提高请求速度。
- 2) 防火墙作用 由于所有的客户机请求都必须通过代理服务器访问远程站点,因此可在代理服务器上设限,过滤某些不安全信息。
- 3) 通过代理服务器访问不能访问的目标站点 互联网上有许多开发的代理服务器,客户机在访问受限时,可通过不受限的代理服务器访问目标站点,通俗说,我们使用的翻墙浏览器就是利用了代理服务器,虽然不能出国,但也可直接访问外网。

6、支持的代理协议

http 属于七层的应用层 代理 超文本传输协议

https 代理 http/https协议

TCP 属于四层传输层 代理tcp/dupxiey

websocket 用于开发代理http1.1长链接通讯协议

GRPC 代理go语言远程调用

POP/IMAP 代理邮件收发协议 RTMP 代理 流媒体,直播

7、配置反向代理

```
'"$http_user_agent" "$http_x_forwarded_for"';
 access_log /var/log/nginx/access.log main;
 sendfile
               on;
 #tcp_nopush
                on;
 keepalive_timeout 65;
 #gzip on;
 include /etc/nginx/conf.d/*.conf;
 # www.91souyun.com
 server {
listen
          80;
     listen [::]:80;
     server_name www.91souyun.com;
     root /usr/share/nginx/html/www.91souyun.com;
     location / {
         root /usr/share/nginx/html/www.91souyun.com;
         index index.html index.htm;
     }
  }
 # blog.91souyun.com
  server {
     listen
                80;
     listen [::]:80;
     server_name blog.91souyun.com;
                /usr/share/nginx/html/blog.91souyun.com;
     root
     location / {
               /usr/share/nginx/html/blog.91souyun.com;
         root
         index index.html index.htm;
     }
  }
 server {
     listen 80;
     server_name bw.91souyun.com;
     #index index.html index.htm index.php;
     location / {
             proxy_pass http://www.homosafe.com;
             root html;
             index index.html index.htm index.php;
```

```
expires -1;
    proxy_set_header HOST $http_host;
    proxy_set_header X-Forwarded-For $proxy_add_x_forwarded_for;

    proxy_http_version 1.1;
    proxy_connect_timeout 60s;
    proxy_read_timeout 60s;
    proxy_send_timeout 60s;
    proxy_buffering on;
    proxy_buffer_size 8k;
    proxy_buffers 8 8k;
}
```

2) 、设置发往后端服务器的请求头信息

```
# 用户请求的时候HOST的值是www.oldboy.com, 那么代理服务会像后端传递请求的还是
www.oldboy.com
proxy_set_header Host $http_host;
# 将$remote_addr的值放进变量X-Real-IP中, $remote_addr的值为客户端的ip
proxy_set_header X-Real-IP $remote_addr;
# 客户端通过代理服务访问后端服务,后端服务通过该变量会记录真实客户端地址
proxy_set_header X-Forwarded-For $proxy_add_x_forwarded_for;
```

3) 、代理到后端的设置

```
# nginx代理与后端服务器连接超时时间(代理连接超时)
Syntax: proxy_connect_timeout time;
Default: proxy_connect_timeout 60s;
Context: http, server, location

# nginx代理等待后端服务器的响应时间
Syntax: proxy_read_timeout time;
Default: proxy_read_timeout 60s;
Context: http, server, location

# 后端服务器数据回传给nginx代理超时时间
Syntax: proxy_send_timeout time;
Default: proxy_send_timeout time;
Default: proxy_send_timeout 60s;
Context: http, server, location
```

8、负载均衡

1) 、负载均衡的目的

提升吞吐率, 提升请求性能, 提高高容灾。

2) 、负载均衡的实现

Nginx 实现负载均衡用到了 proxy_pass 代理模块核心配置, 将客户端请求代理转发至一组 upstream 虚拟服务池。

3) 、与反向代理的区别

负载均衡和反向代理的区别是,反向代理由代理服务器指定特定的服务器去请求资源,而负载均衡中的代理服务器将请求转发给虚拟服务池,具体由那个服务器处理根据相应的算法来定。

4) 、负载均衡的配置

(1) 配置web服务

```
## server.conf
server {
 listen 8081;
 root /soft/code1;
 index index.html;
}
server {
 listen 8082;
 root /soft/code2;
 index index.html;
}
server {
 listen 8083;
 root /soft/code3;
 index index.html;
}
```

(2) 、配置负载均衡

```
## proxy.conf

upstream node {
    server 你的IP:8081;
    server 你的IP:8082;
    server 你的IP:8083;
}

server {
    server_name localhost;
    listen 80;
    location / {
        proxy_pass http://node;
        proxy_set_header Host $http_host;
        proxy_set_header X_Real_IP $remote_addr;
        proxy_set_header X_Forwarded_For $proxy_add_x_forwarded_for;
}
```

9、ngin配置https

1) 自定义证书

```
# 生成证书
openssl req -new -x509 -nodes -out shenmav.crt -keyout shenmav.key
```

```
[centos@ip-172-26-10-74 html]$ openssl req -new -x509 -nodes -out shenmav.crt -keyout shenmav.key
Generating a 2048 bit RSA private key
writing new private key to 'shenmav.key'
You are about to be asked to enter information that will be incorporated
into your certificate request.
What you are about to enter is what is called a Distinguished Name or a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
Country Name (2 letter code) [XX]:CH
State or Province Name (full name) []:BJ
Locality Name (eg, city) [Default City]:BJ
Organization Name (eg, company) [Default Company Ltd]:personal
Organizational Unit Name (eg, section) []:david
Common Name (eg, your name or your server's hostname) □:v.shenmazong.com
Email Address []:admin@test.com
[centos@ip-172-26-10-74 html]$ ll
总用量 8
-rw-rw-r--. 1 centos centos 1399 3月 18 12:59 shenmav.crt
-rw-rw-r--. 1 centos centos 1704 3月 18 12:59 shenmav.key
drwxrwxr-x. 2 centos centos 63 3月 18 12:53
[centos@ip-172-26-10-74 html]$ sudo docker start 3c557952c6eD
```

2) 、nginx配置

```
## nginx PT
user nginx;
worker_processes 1;

error_log /var/log/nginx/error.log warn;
pid /var/run/nginx.pid;

events {
   worker_connections 1024;
}

http {
   include /etc/nginx/mime.types;
```

```
default_type application/octet-stream;
log format main '$remote addr - $remote user [$time local] "$request" '
                  '$status $body_bytes_sent "$http_referer" '
                  '"$http_user_agent" "$http_x_forwarded_for"';
access log /var/log/nginx/access.log main;
sendfile
                on;
#tcp nopush
                on;
keepalive_timeout 65;
#gzip on;
include /etc/nginx/conf.d/*.conf;
# v.shenmazong.com
server {
               443 default ssl;
    server_name v.shenmazong.com;
    ssl certificate /usr/share/nginx/html/shenmav.crt;
    ssl_certificate_key /usr/share/nginx/html/shenmav.key;
    ssl_session_cache shared:SSL:1m;
    ssl session timeout 5m;
    server_tokens off;
    keepalive_timeout 70;
    ssl_ciphers HIGH:!aNULL:!MD5;
    ssl_prefer_server_ciphers on;
    location / {
        proxy_pass https://www.google.com;
        root html;
        index index.html index.htm;
        expires -1;
        #proxy set header HOST $http host;
        proxy_set_header X-Forwarded-For $proxy_add_x_forwarded_for;
        proxy_http_version 1.1;
        proxy_connect_timeout 60s;
        proxy_read_timeout 60s;
        proxy_send_timeout 60s;
        proxy buffering on;
        proxy_buffer_size 8k;
```

```
proxy_buffers 8 8k;
}
}
```