

[illegible]

User Interface

event_properties

cyboi	unix_terminal	win32_console	x_window_system	win32_display	java_script	java	description
key_pressed		bKeyDown is true					
key_released		bKeyDown is false					
repeat_count		wRepeatCount					indicates that a key is being held down
key_code_virtual		wVirtualKeyCode	[still missing in xcb tutorial]				identifies key in a device-independent manner
key_code_device		wVirtualScanCode	detail (xcb_keycode_t)				physical key on the keyboard; device-dependent value generated by the keyboard hardware
character		uChar – UnicodeChar					translated Unicode character
mask		dwControlKeyState	state				mask of the buttons (or control keys) during the event
mode			mode				number of the mouse button that was clicked for enter/leave events
event_type			response_type				type of event
window_id			window				window identification
expose_x			x				x coordinate of the top-left part of the window that needs to be redrawn
expose_y			y				y coordinate of the top-left part of the window that needs to be redrawn
expose_width			width				width coordinate of the top-left part of the window that needs to be redrawn
expose_height			height				height coordinate of the top-left part of the window that needs to be redrawn
event_x			event_x				x coordinate where the mouse has been pressed in the window
event_y			event_y				y coordinate where the mouse has been pressed in the window

[illegible]

[illegible]

User Interface

key-button-mask

cyboi	unix_terminal	win32_console	x_window_system	win32_display	java_script	java	description
		ENHANCED_KEY 0x0100		-			The key is enhanced.
		LEFT_ALT_PRESSED 0x0002		-		ALT_DOWN_MASK	The left ALT key is pressed.
		NUMLOCK_ON 0x0020		-			The NUM LOCK light is on.
		RIGHT_ALT_PRESSED 0x0001		-		ALT_GRAPH_DOWN_MASK	The right ALT key is pressed.
		SCROLLLOCK_ON 0x0040		-			The SCROLL LOCK light is on.
		-		MK_LBUTTON 0x0001			The left mouse button is down.
		-		MK_RBUTTON 0x0002			The right mouse button is down.
		-		MK_MBUTTON 0x0010			The middle mouse button is down.
		-		MK_XBUTTONDOWN1 0x0020			The first X button is down.
		-		MK_XBUTTONDOWN2 0x0040			The second X button is down.
			XCB_BUTTON_MASK_1			BUTTON1_DOWN_MASK	
			XCB_BUTTON_MASK_2			BUTTON2_DOWN_MASK	
			XCB_BUTTON_MASK_3			BUTTON3_DOWN_MASK	
			XCB_BUTTON_MASK_4				
			XCB_BUTTON_MASK_5				
		SHIFT_PRESSED 0x0010	XCB_MOD_MASK_SHIFT	MK_SHIFT 0x0004		SHIFT_DOWN_MASK	The SHIFT key is pressed.
		CAPSLOCK_ON 0x0080	XCB_MOD_MASK_LOCK				The CAPS LOCK light is on.
		LEFT_CTRL_PRESSED 0x0008	XCB_MOD_MASK_CONTROL	MK_CONTROL 0x0008		CTRL_DOWN_MASK	The left CTRL key is pressed.
			XCB_MOD_MASK_1				Alt or Meta key, respectively
			XCB_MOD_MASK_2				
			XCB_MOD_MASK_3				
			XCB_MOD_MASK_4				
			XCB_MOD_MASK_5				
		RIGHT_CTRL_PRESSED 0x0004		MK_CONTROL 0x0008		CTRL_DOWN_MASK	The right CTRL key is pressed.
						META_DOWN_MASK	

cyboi	unix_terminal	win32_console	x_window_system	win32_display	java_script	java	description
				HTBORDER 18			In the border of a window that does not have a sizing border.
				HTBOTTOM 15			In the lower-horizontal border of a resizable window (the user can click the mouse to resize the window vertically).
				HTBOTTOMLEFT 16			In the lower-left corner of a border of a resizable window (the user can click the mouse to resize the window diagonally).
				HTBOTTOMRIGHT 17			In the lower-right corner of a border of a resizable window (the user can click the mouse to resize the window diagonally).
				HTCAPTION 2			In a title bar.
				HTCLIENT 1			In a client area.
				HTCLOSE 20			In a Close button.
				HTERROR -2			On the screen background or on a dividing line between windows (same as HTNOWHERE, except that the DefWindowProc function produces a system beep to indicate an error).
				HTGROWBOX 4			In a size box (same as HTSIZE).
				HTHELP 21			In a Help button.
				HTHSCROLL 6			In a horizontal scroll bar.
				HTLEFT 10			In the left border of a resizable window (the user can click the mouse to resize the window horizontally).
				HTMENU 5			In a menu.
				HTMAXBUTTON 9			In a Maximize button.
				HTMINBUTTON 8			In a Minimize button.
				HTNOWHERE 0			On the screen background or on a dividing line between windows.
				HTREDUCE 8			In a Minimize button.
				HTRIGHT 11			In the right border of a resizable window (the user can click the mouse to resize the window horizontally).
				HTSIZE 4			In a size box (same as HTGROWBOX).
				HTSYSTEMMENU 3			In a window menu or in a Close button in a child window.
				HTTOP 12			In the upper-horizontal border of a window.
				HTTOPLEFT 13			In the upper-left corner of a window border.
				HTTOPRIGHT 14			In the upper-right corner of a window border.
				HTTRANSPARENT -1			In a window currently covered by another window in the same thread (the message will be sent to underlying windows in the same thread until one of them returns a code that is not HTTRANSPARENT).
				HTVSCROLL 7			In the vertical scroll bar.
				HTZOOM 9			In a Maximize button.