GEOSUPPORT SYSTEM

User Programming Guide (UPG)

SOFTWARE VERSION 18.4 Draft

Department of City Planning / City of New York
Information Technology Division
Citywide Geographic Application Services

184.A07

Table of Contents

Overview of the UPG	12
Chapter I: SYSTEM OVERVIEW	16
I.1 Introduction	17
I.2 System Functionality	18
I.3 Introduction to Geographic Retrieval Consistency	19
I.4 The Geosupport Function Suite	20
I.5 Overview of System Architecture	25
The Foreground Component	26
The Background Component	26
Foreground Component Updating: New File Releases	26
Foreground Component Updating: New Software Versions and Vestigial Features	27
Character-Only Work Areas (COWs)	28
User Feedback of Rejects	28
I.6 Technical References	30
Chapter II: INTRODUCTION TO THE GEOSUPPORT API	31
II.1 Introduction	32
II.2 Geosupport Return Codes and Reject Handling	34
II.3 Geosupport API User Programming Procedure	36
II.4 One-Work-Area and Two-Work-Area Calls	37
II.5 Coding Geosupport API Calls	39
II.6 The Work Area C/C++ Header Files and Visual Basic Typedef File	40
II.7 Coding API Calls When Using Geosupport C/C++	40
II.7.1 C/C++ Source Code Statement	40
II.8 Creating a Geosupport Desktop Edition Application	41
II.9 Sample Programs with Descriptions	41
II.9.1 C/C++ Sample Program with Descriptions	42
II.9.2 Visual Basic(VB/VBA) Sample Program with Descriptions	51
II.10 The Long Work-Area-2 Option	61
II.11 The Auxiliary Segment Option (COW Only)	62
II.12 The Extended Work Area 2 Option- via Mode Switch(COW Only)	62
Chapter III: STREET NAME PROCESSING	64
III.1 Introduction	65
III.2 Street Name Normalizing and the SNL Parameter	66
III.3 Street Name Sorting and Normalization Format Options	68

III.4 Partial Street Names	70
III.5 The Similar Names Feature	73
III.6 Unconventional Geographic Feature Names	77
Paper Streets	77
Non-Street Features	78
Addressable Place Names	78
Non-Addressable Place Names (NAPs)	78
Support of Non-Addressable Place Names (NAPs) with address numbers	79
Pseudo-Street Names	80
Duplicate Address Pseudo-Street Names (DAPSs)	80
Intersection Names	81
III.7 Street Name Browsing and Functions BB and BF	81
III.8 Selection of Output Street Names (COW only)	83
CHAPTER IV: STREET CODES	85
IV.1 Introduction: Street Codes and Geographic Retrieval Consistency	86
IV.2 Street Name Relationships: Aliases and Locally Valid Street Names	87
IV.3 Five-Digit and Ten-Digit Street Codes	88
IV.4 Resynchronization of Street Codes Stored in User Files	90
Resynchronization procedure using B5SCs	91
Resynchronization procedure using street names	91
Resynchronization procedure using B10SCs	92
Summary of Street Code Resynchronization	93
IV.5 Seven-Digit Street Codes: Local Street Name Validity, Local Group Codes	94
Local Group Codes (LGCs)	95
Street Name Codes (SNCs)	96
IV.6 Functions D, DG and DN; Primary, Principal and Preferred Street Names	97
Input Data	97
Output Data	98
Preferred Street Names	99
IV.7 Street Codes and Non-Addressable Place Names	101
IV.8 Street Code Input Feature	102
Functions 1, 1A, 1B, 1E, and AP and Street Code Input	103
NAPs and Street Code Input	103
IV.9 Summary of Street Codes	104
Table IV-1: Notation for Street Code Items	105
Table IV-2: Summary of Street Code Items	106
CHAPTER V: ADDRESS PROCESSING - FUNCTIONS 1, 1A, 1B, 1E, AP	107

V.1 Introduction	108
V.2 Address Numbers (‘House’ Numbers), Normalization and Formats: HNI, HNS and HND	108
Processing of HNIs or HNSs by the Display Functions	109
HNIs or HNSs as Input to the Address-Processing Functions	109
House Number Format Standards	109
V.3 Specifying Input Data to the Address-Processing Functions: NAPs, Parsed-Form Addresses, Free-Form Addresses and Unit Information	113
V.4 Input Address Acceptance/Rejection and its Validation Significance	115
Function 1E	116
Function 1A	116
Function AP	116
Function 1B Input Address Processing and Return Code Processing	117
V.5 Output Data Returned in Work Area 2 of Address Processing Functions	117
Function 1	117
Function 1E	120
Function 1A	120
Function AP (COW Only)	121
Function 1B (COW Only)	121
Work Area 2 for Function 1B	122
V.5.1 Mainframe GOAT Screen for Function 1B	123
V.6 Duplicate Addresses	124
V.7 Marble Hill/Rikers Island	128
V.8 Special Ruby Street Processing	129
V.9 Vanity Addresses	130
V.10 Out-of-Sequence Addresses	130
V.11 ZIP Code as Input Instead of Borough Code	131
V.12 Fuzzy Search for Address Functions 1, 1A, 1B, and 1E	131
V.13 Special Place Name Processing	132
V.14 ‘No Cross Street’ Segment Processing	133
V.15 UNIT Information Feature (COW Only)	134
CHAPTER VI: TAX LOT AND BUILDING PROCESSING - FUNCTIONS 1A, BL, BN / ADDRESS POINT PROCESSING - FUNCTION AP	138
VI.1 Introduction	139
VI.2 Tax Lots and BBLs	139
VI.3 Buildings and Building Identification Numbers (BINs)	141
VI.4 Condominiums and Billing BBLs	142
VI.5 Vacant Street Frontages and Pseudo-Addresses	143

VI.6 Function 1A	144
VI.7 Function BL	147
VI.8 Standard and Legacy Versions of Functions 1A and BL	148
VI.9 Function BN	148
VI.10 Function AP (COW Only)	148
VI.11 Transitional Property Address Directory (TPAD) Building Identification Number (BIN) and status information for Functions 1A, 1B, BL and BN (COW Only)	149
CHAPTER VII: STREET CONFIGURATION PROCESSING - FUNCTIONS 2, 3, 3C, 3S	155
VII.1 Introduction	156
VII.2 Intersections:Function 2 and Function 2W	158
Nodes	158
The Two-Node Case	161
Overview of Function 2 Node Enhancements	163
VII.3 Three-Street Configurations - Concepts and Terminology	174
Street Stretches and Street Segments	176
Logical Direction Assigned to Streets	177
Blockfaces	177
T-Intersections	178
VII.4 Street Segments and Related Configurations: Function 3	180
Input Data Examples for Function 3	180
Ambiguous Function 3 Input Data	182
Function 3 Output Data	183
Cross Street Reversal Flag	184
Segment Orientation	185
Consistent Retrieval of Application Data by ‘On’ Street and Two Cross Streets	186
Converting Address-Keyed Application Data to ‘On’ Street/Cross Streets	187
VII.5 Blockfaces: Function 3C	187
VII.6 Street Stretches: Function 3S	189
Locally Valid Street Name or Street Code processing	193
Roadbed Street Stretches: Function 3S Partial Implementation	193
Coincident Segments: Function 3S Processing	194
VII.7 Borough Boundary Processing (Functions 2, 3 and 3C)	195
VII.8 Fuzzy Name Search Processing for Functions 3, 3C, and 3S – Front-truncated street names	195
CHAPTER VIII: THE GEOSUPPORT API - USER PROGRAM CODING AND	

JCL	197
VIII.1 Introduction	198
VIII.2 Review of the Geosupport API	199
Important note for CICS applications written in NATURAL	199
VIII.3 Coding API Calls	200
VIII.4 The Geosupport COPY Files	201
Overview of COPY Files in General	201
The Geosupport COPY Libraries	202
VIII.5 Coding API Calls When Using Geosupport COPY Files	205
COBOL Source Code Statements	206
Assembler Source Code Statements	207
PL/1 Source Code Statements	208
IBM/C Source Code Statements	209
NATURAL Source Code Statements	210
VIII.6 JCL for the Compile Step	212
VIII.7 JCL for the Linkage Editor Step	214
VIII.8 JCL for the Execute Step (Batch Applications)	215
CHAPTER IX: GEOSUPPORT BATCH ADDRESS TRANSLATOR (GBAT)	217
IX.1 Introduction	218
IX.2 JCL Considerations	218
IX.3 GBAT Processing and Programmed Abnormal Terminations	220
IX.4 The Input Data File (DDNAME=INFILE or INVSAM)	223
IX.5 The Input Control File (DDNAME=CARDIN)	223
IX.6 The Input Alias File (DDNAME=ALIASES)	225
IX.7 The Output File of Accepted Records (DDNAME=OUTFILE)	227
IX.8 The Output Files of Rejected Records (DDNAME=ERRFILx)	230
IX.8.1 ERRFILE	231
IX.8.2 ERRFIL2 (for use by Function 1B only)	231
IX.8.3 ERRFIL3 (for use by Function2 with RELATEDNODES=YES)	232
IX.8.4 ERRFIL4 (for use with WORKAREA1=YES)	233
IX.8.5 ERRFIL5 (for use by Function 1B with WORKAREA1=YES)	234
IX.9 The Output Print File (DDNAME=SYSPRINT)	234
CHAPTER X: Desktop Edition GBAT	236
X.1 What is GBAT	237
X.2 Using GBAT	237
X.2.1 Before You Begin	237
X.2.2 Starting the Application	238

X.2.3 Selecting an ODBC Data Source	238
X.2.4 Configuring a New Text Data Source	239
X.2.5 Function Selection	244
X.2.6 Function-Specific Configuration	245
X.2.7 General Input Configuration	255
X.2.8 Output Configuration	257
X.2.9 Function Processing	258
CHAPTER XI: Desktop Edition GOAT	261
XI.1 Introduction	262
XI.2 How to Use GOAT	262
XI.3 Invoking Function 1 or Function 1E	263
XI.4 Invoking Function 1A	265
XI.5 Invoking Function 2	266
XI.6 Invoking Function 3 or Function 3C	268
XI.7 Invoking Function 3S	271
XI.8 Invoking Function B	273
XI.9 Invoking Function BL	273
XI.10 Invoking Function BN	274
XI.11 Invoking Function D	275
Appendices and Glossary	277
APPENDIX 1: GEOSUPPORT FUNCTIONS - QUICK REFERENCE	278
Introduction	278
Function 1	280
Function 1A	283
Function 1E	285
Function 1B	286
Function 1N	288
Function 2 (and 2W)	288
Function 3	291
Function 3C	294
Function 3S	296
Function AP	299
Functions BB and BF	301
Function BL	302
Function BN	303
Functions D, DG and DN	304
APPENDIX 2: MAINFRAME-SPECIFIC WORK AREA LAYOUTS (MSW)	308

Work Area 1 (MSW) All Functions	309
Regular Work Area 2 (MSW) Layout for Function 1	311
Long Work Area 2 (MSW) Layout for Function 1	312
Regular Work Area 2 (MSW) Layout for Functions 1A, BL, BN	312
Long Work Area 2 (MSW) Layout for Functions 1A and BL	314
Regular Work Area 2 (MSW) Layout for Function 1E	316
Long Work Area 2 (MSW) Layout for Function 1E	317
Work Area 2 (MSW) Layout for Function 2	317
Work Area 2 (MSW) Layout for Function 3	319
Long Work Area 2 (MSW) Layout for Function 3	320
Work Area 2 (MSW) Layout for Function 3	321
Work Area 2 (MSW) Layout for Function 3S	323
APPENDIX 3: DATA ITEM DICTIONARY	324
APPENDIX 4: GEOSUPPORT RETURN CODES, REASON CODES AND MESSAGES	384
TPAD WARNING MESSAGES and TPAD Conflict Flag / REASON CODE QUALIFIERS in( )	390
APPENDIX 5: GEOSUPPORT COPY FILES (MSW)	392
COBOL COPY Files (MSW)	392
ASSEMBLER COPY FILES (MSW)	412
PL/1 COPY Files (MSW)	428
C COPY File (MSW)	448
NATURAL LDAs (MSW)	463
APPENDIX 6: USER FEEDBACK PROCEDURES	485
APPENDIX 7: MAINFRAME DATA CENTERS WHERE GEOSUPPORT IS INSTALLED	487
APPENDIX 8: SAMPLE APPLICATION PROGRAMS AND JCL	488
COBOL SAMPLE PROGRAM #1	490
COBOL SAMPLE PROGRAM #2	507
ASSEMBLER SAMPLE PROGRAM #1	522
ASSEMBLER SAMPLE PROGRAM #2	562
PL/1 SAMPLE PROGRAM #1	582
PL/1 SAMPLE PROGRAM #2	593
C SAMPLE PROGRAM #1	599
C SAMPLE PROGRAM #2	611
NATURAL SAMPLE PROGRAM #1	623
NATURAL SAMPLE PROGRAM #2	633
APPENDIX 9: GBAT REFERENCE TABLES	644

Table A9-1: GBAT Control Entry Descriptions by Keyword	644
Table A9-2: Summary of GBAT Control Entries by Keyword	659
Table A9-3: Summary of GBAT Control Entry Usage by Function	663
Table A9-4: MSW Appended Items for GEOCODE=NO	667
Table A9-5: MSW Format- Length of GBAT−Appended Datad	668
APPENDIX 10: SAMPLE GBAT JOBS	670
SAMPLE GBAT JOB #1	670
SAMPLE GBAT JOB #2	680
APPENDIX 11: GUIDELINES FOR APPLICATION DESIGN	693
APPENDIX 12: CHARACTER-ONLY WORK AREAS (COW)	696
Introduction	696
Overview	696
Comparison of COWs and MSWs	697
Consideration When Using the COWs	699
Work Area Lengths (COWs and MSWs)	699
Specifying a Work Area Format (COW or MSW)	700
GBAT Considerations for COWs	700
COPY Files for COWs	706
APPENDIX 13: CHARACTER-ONLY WORK AREA LAYOUTS (COW)	709
Character-Only Work Area 1 (COW) – All Functions	711
Work Area 2 (COW) - Functions 1, 1E	715
Work Area 2 (COW) - Functions 1, 1E Extended	717
Work Area 2 (COW) - Functions 1A, BL, BN	720
Long Work Area 2 (COW) - Functions 1A, BL	723
TPAD Long Work Area 2 (COW) - Functions 1A, BL	724
Work Area 2 (COW) - Functions 1A, BL, BN Extended	724
Work Area 2 (COW) - Function 1B	725
Work Area 2 (COW) - Function AP	733
Work Area 2 (COW) - Function AP Extended	735
Work Area 2 (COW) - Function 2	736
Work Area 2 (COW) - Function 2W (Wide)	738
Work Area 2 (COW) - Function 3	739
Work Area 2 (COW) - Function 3 with Auxiliary Segment List	742
Work Area 2 (COW) - Function 3 Extended	742
Work Area 2 (COW) - Function 3 Extended with Auxiliary Segment List	745
Work Area 2 (COW) - Function 3C	745
Work Area 2 (COW) - Function 3C with Auxiliary Segment List	747

Work Area 2 (COW) - Function 3C Extended	747
Work Area 2 (COW) - Function 3C Extended with Auxiliary Segment List	749
Work Area 2 (COW) - Function 3S	749
APPENDIX 14: GEOSUPPORT COPY FILES (COW)	751
COBOL COPY Files (COW)	752
P1COB COPY File	752
P2COB COPY File	755
P2COB1A COPY File	773
P2COB1AL COPY File	775
P2COB3S COPY File	789
P2COBAP COPY File	789
ASSEMBLER COPY Files (COW)	792
P2BAL COPY File	792
P2BAL1A COPY File	813
P2BAL3S COPY File	827
P2BALAP COPY File	828
PL/1 COPY Files (COW)	832
P1PL1 COPY File	832
P2PL1 COPY File	835
P2PL11A COPY File	853
P2PL11AL COPY File	856
P2PL13S COPY FIle	871
P2PL1AP COPY File	871
C COPY File (COW)	874
PAC COPY File	874
NATURAL LDAs (COW)	900
GEOLP1 COPY File	900
GEOLP2 COPY File	902
GEOLP21A COPY File	937
GEOLP2AL COPY File	941
GEOLP23S COPY File	968
GEOL2AP COPY File	968
GEOL2APX COPY File	969
APPENDIX 15: 2010 CENSUS GEOGRAPHY – Functions 1, 1E, 2, 3, and 3C	972
APPENDIX 16: NEIGHBORHOOD TABULATION AREAS (NTAS) AND PUMAS	976
APPENDIX 17: TPAD - ADDITIONAL INFORMATION	977
APPENDIX 18: GeoExcel Application	982

APPENDIX 19: GEOSUPPORT COPY FILES (COW)	987
Character-Only Work Areas	987
Work Area 1 (COW) - All Functions	987
Work Area 2 (COW) - Functions 1 and 1E	989
Work Area 2 (COW) - Functions 1A, BL and BN	991
Long Work Area 2 (COW) - Functions 1A and BL	994
Work Area 2 (COW) - Function 2	994
Work Area 2 (COW) - Function 3	995
Work Area 2 (COW) - Function 3C	997
Work Area 2 (COW) - Function 3S	999
APPENDIX 20: Geosupport Header And Typedef Files	1001
C/C++ Header File	1001
Visual Basic Typedef File	1011
APPENDIX 21: Geosupport System And General Overview	1022
Geosupport System General Overview	1023
I Goals And Objectives of The Geosupport Systems	1023
II System requirements, Availability And Enhancements	1026
III Accessing Geosupport: The Application Programming Interface And Utility Programs	1026
IV Geosupport Update Cycles And User Feedback	1027
APPENDIX 22: GeoX Programming Guide	1030/td>
GeoX Overview	1030
Setup	1030
Using GeoX in a .NET Program	1030
Sample Code for Function 1E	1031
Sample Code for Function BL	1033
Selecting the Broker to Use	1035
Which Functions to Use	1036
Which Options to Use	1036
Selecting the Proper Work Area 2	1038
List of Classes and Overview	1039
Classes	1040
Supporting Classes for Work Areas	1041
Glossary of Term And Acronyms	1042
About Us	1054

Overview of the *User Programming Guide*

This document, the *Geosupport System User Programming Guide* (UPG), contains the detailed technical information necessary for users to design and develop their own application programs that access Geosupport, as well as to use GBAT. (The use of GOAT and the AIMZ transaction requires no programming skills and they are not documented herein.) The UPG serves as a comprehensive set of technical specifications for the Geosupport System, and can be incorporated into procurement documents issued by city agencies soliciting consulting services for application design and development.

The contents of the UPG are as follows

- Chapter I is a general overview of the system, its purposes, features, means of access and the broad outlines of its architecture.
- Chapter II is an introduction to the Geosupport API, describing in general terms its components and the user programming required to utilize it. (Chapter VIII discusses the usage of the API in greater detail.)
- Chapter III covers street name processing and in particular describes important user-controllable features of Geosupport's street name standardizing routine.
- Chapter IV discusses Geosupport's system of numeric street codes, a feature that is relevant principally for applications that must retrieve data from user files by geographic location.
- Chapters V through VII discuss in detail the types of geographic locations that Geosupport can process and the functions that process them:
    - Chapter V discusses address and non-addressable place name processing and Functions 1, 1A, 1B, 1E, and AP.
    - Chapter VI discusses tax lot and building processing and Functions 1A &1B (aspects not covered in Chapter V), BL and BN.
    - Chapter VII discusses street configuration processing and Functions 2, 3, 3C and 3S.
- Chapter VIII describes in detail the application program coding and JCL required to use the Geosupport API
- Chapter IX discusses GBAT, Geosupport's standalone batch utility program.
- Appendix 1 contains summary reference information for each Geosupport function, including a brief description of the function and reference to relevant sections of the UPG.
- Appendix 2 contains layouts of the Geosupport API Mainframe-Specific Work Areas (MSWs).

- Appendix 3 is a data item dictionary, containing descriptions of the formats and contents of all of the data items that appear in the work area.
- Appendix 4 is a comprehensive table of Geosupport Return Codes, Reason Codes and Messages.
- Appendix 5 contains listings of the MSW Geosupport COPY files for all of the programming languages supported by the Geosupport COPY feature. (This important feature is discussed in Chapter VIII.)
- Appendix 6 describes the procedures that users should follow to report Geosupport System problems and to provide feedback to GSS of rejected input data that the user is unable to resolve.
- Appendix 7 is a list of the data centers where Geosupport is installed.
- Appendix 8 contains sample user programs written in various programming languages together with sample JCL.
- Appendix 9 contains reference tables for setting up GBAT jobs.
- Appendix 10 contains sample GBAT jobs.
- Appendix 11 contains a set of guidelines for user application design.
- Appendix 12 contains a description of Character-Only Work Areas (COWs) and how to use them.
- Appendix 13 contains layouts of the Character-Only Work Areas (COWs).
- Appendix 14 contains listings of the COW Geosupport COPY files for all of the programming languages supported by the Geosupport COPY feature. (This important feature is discussed in Chapter VIII.)
- Appendix 15 describes where the 2010 Census Geography was incorporated into the Version 11.0 Geosupport System. The appendix includes tables describing the offsets of the data and the field names in the COPYLIBs
- Appendix 16 contains a description of the history and significance of the Neighborhood Tabulation Areas.
- Appendix 17 contains additional TPAD information, including error processing and error message handling.
- The Glossary contains definitions of special terms and acronyms

Appendices 1 through 5, together with Appendices 13 and 14 (for COW Work Areas), collectively can serve as a quick reference guide for experienced Geosupport users.

Note: Since the geography of New York City is constantly growing and changing, any examples mentioned in this document may, occasionally, function differently from the way they are described. The examples will, in any case, illustrate the concept being discussed.

Summary of Changes and New Features

The updates listed below indicate changes and new features since the last release of the *User Programming Guide* (written for Software Version 18.1). Some of the changes and features are described elsewhere in the UPG; other changes are mentioned only in this summary to make users aware of items such as general improvements or items displayed by GOAT.

Note: Entries in this summary which begin with **'(COW Only)'** describe changes and features which are available only for applications that use the Character-Only Work Areas (COWs). Character-Only Work Areas are described in Appendix 12. To take advantage of the full functionality of Geosupport, it is recommended that applications be written using the Character-Only Work Areas (COWs).

Character-Only Work Areas (COWs), as the name implies, contain character fields only. The Geosupport work areas that have long been in use are called the **Mainframe-Specific Work Areas (MSWs)**. Typically, MSWs contain some fields that are in a format which is unique to IBM mainframes. COWs were introduced as an essential part of a long-term effort to port the Geosupport System to other platforms, e.g. the Desktop, the Internet (web version of GOAT) and as a Microsoft Office VSTO add-in (GeoExcel). For a detailed description of the COWs, see Appendix 12.

Work Area 1 and Work Area 2 are often referred to, in this document, as **WA1** and **WA2**, respectively.

Version 18.4

- **(COW Only) System Enhancements Implemented**

    - **The numeric words 'ONE' through 'NINE' are now accepted as a house number in the Geosupport house number input field.**

An increasing number of New York City buildings with an address number less than 10 are opting to post their addresses using numeric words rather than numbers, such as ONE BRYANT PARK. The numeric words 'ONE' through 'NINE' are now accepted as a house number in the Geosupport house number input field. These words are processed as if they were the actual numbers '1' through '9'. The house numbers will appear in the output as '1' through '9'.

This feature will allow the user to input the address ONE BRYANT PARK, for example, by specifying the word ONE in the input house number field.

‘ONE’ through ‘NINE’ will be recognized in a free-form address when that address is also defined as a NAP (Non-Addressable Place Name); however for these cases, the numeric word will not be converted to a number and the free-form NAP name output will be returned as entered. (Note: A ‘ONE’ through ‘NINE’ free-form address will have a different street code from its standard parsed form address.)

(COW Functions 1, 1A, 1B, AP and their various forms, e.g. Function 1E Extended)

*** The numeric words ‘ONE’ through ‘NINE’ are now accepted as a house number in the Geosupport house number input field.**

An increasing number of New York City buildings with an address number less than 10 are opting to post their addresses using numeric words rather than numbers, such as ONE BRYANT PARK. The numeric

```
* **Two new house number suffixes are now supported:
```

o BA
o B GARAGE.**

```
  An increasing number of New York City buildings with an address number less than 10 are opting to
post their addresses using numeric words rather than numbers, such as ONE BRYANT PARK.  The numeric
```

Version 18.3

- **(COW Only) System Enhancement Implemented**

    - **Hi-Rise Buildings in the New York City Department of Sanitation (DSNY) Organics Recycling Program**
      Geosupport now allows more flexibility when adding high-rise buildings to the DSNY Organics Recycling Program. It is no longer necessary for DSNY to wait until the quarterly release of Geosupport files to add a hi-rise building to the program.

      This enhancement is transparent to the user and is available across all platforms and formats (e.g. Geosupport Desktop Edition™, Linux, etc.).

      No programming changes are necessary.

(COW Functions 1/1E, 1/1E Extended, 1B)

CHAPTER I

SYSTEM OVERVIEW

I.1 Introduction

The Geosupport System is an integrated system of software and data files that processes New York City geographic locations. Input locations can be accepted in various forms, including addresses, place names, street intersections, blockfaces, street stretches and property parcels (tax lots). Geosupport standardizes and validates the input location and provides related geographic information, such as the community district, census tract and census block, ZIP code, tax block and tax lot, police precinct, cross streets, City Council district and spatial coordinates. In addition, Geosupport provides user-written applications with the means to retrieve data from the user's own files by geographic location in a consistent manner.

The Geosupport System was developed and is maintained as a service to all agencies of the City of New York by the staff of the Geographic Systems Section (GSS) of the Department of City Planning's Information Technology Division. GSS has been enhancing the Geosupport software and updating the system's data files continually since the system's introduction in 1983.

This document, the *Geosupport System User Programming Guide* , is a comprehensive technical description of the system and how to access it. The document is intended to be read primarily by technical users such as computer application designers, software analysts and programmers. Knowledge of IBM mainframe application programming is assumed.

Geosupport is installed on IBM mainframes at the city computer centers listed in Appendix 7, where it is used by most city agencies as an integral component of many of their major data processing applications. An employee of each computer center's custodial agency, generally a systems programmer, has been designated as the Geosupport System Administrator (GSA) for that computer center. The GSA is responsible for installing or coordinating the installation of new Geosupport file releases and software versions received from GSS. At some computer centers, the GSA makes certain customizing modifications to Geosupport during installation, such as changing the data set names (DSNs) of Geosupport files to conform to local file naming conventions. The GSA is also the first responder for users encountering system-related Geosupport problems, and interacts with GSS staff as needed to resolve such problems. However, the GSA is not necessarily familiar with Geosupport from a user application perspective, and is not responsible for assisting users with application-related problems or design issues.

In general, Geosupport is accessible without restriction to anyone having a valid account at any of the computer centers where it is installed; no special passwords or security procedures are required beyond the normal data center logon procedures. In addition to running on IBM (and IBM-compatible) mainframes, GSS has developed Geosupport Desktop Edition for running in the Windows environment. There are also several methods by which Geosupport running on a city mainframe can be accessed by applications running on other hardware platforms, including 3270 emulation and access through the city's Intranet. Geosupport is also available via GeoX, Linux, .net and Java. This User Programming Guide can be used when programming in any of these environments.

For many user applications, only a subset of Geosupport's functions, features and data items are relevant. In addition, many Geosupport options have defaults which are appropriate for most applications. Thus, even though Geosupport is a large-scale, multi-feature system, the user effort required to design an application to access it is often relatively modest.

Geosupport has an Application Programming Interface (API) that enables it to be accessed directly from a user-written batch or CICS application program. (Geosupport cannot be run in the VM environment.) The Geosupport API supports application programs written in any programming language that can issue a standard IBM external program call. COBOL, PL/1, the various types of IBM mainframe assembler languages (hereafter referred to generically as 'Assembler'), NATURAL and C are five such languages. In addition, Geosupport has one batch and two interactive 'stand-alone' utility programs that enable users to satisfy many geographic processing needs without having to write custom application programs.

The ability of user-written applications to access Geosupport via its API enables users to avoid the burden of duplicating complex, specialized geographic processing routines within their own applications. The Geosupport API affords users total design control of their own applications, with their own input and output files, printed reports and screen formats; users develop those applications in their conventional data processing environments, using the programming languages they deem best suited to those applications.

The Geosupport batch utility program is called the Geosupport Batch Address Translator (GBAT). GBAT requires no user programming; to run GBAT, the user simply sets up a batch job containing JCL and GBAT control records. There are two Geosupport interactive utility programs, both of them CICS transactions. The principal interactive utility is called the Geographic Online Address Translator (GOAT), which provides general inquiry capabilities for almost all Geosupport functions. There is also a specialized interactive utility called Address / Intersection Map Zones (AIMZ), which displays a set of map identification numbers corresponding to an input address or intersection.

I.2 System Functionality

The output information that Geosupport provides consists of geographic information only. Geosupport does not provide, for example, population or crime statistics, housing data, building code violations, property ownership etc. Such data are available from the U.S. Bureau of the Census, city agencies and other sources. Geosupport can facilitate matching many such statistical and administrative databases with user data containing individual locations, by associating those locations with district identifiers needed for such matching, such as census tract, ZIP code or tax block.

Geosupport processes New York City geography only, and is highly customized for that geography. For example, Geosupport can recognize and process many alternative names, spelling variants and partial names of New York City streets; the various address number formats that occur in the city; both old and new addresses on streets that have been renumbered; unique addressing schemes that exist in certain neighborhoods; and many other idiosyncrasies of New York City's geography

Geosupport is organized into more than a dozen distinct functions that can be accessed by the user. Chapter I.4 contains a brief overview of Geosupport's suite of functions. The typical function accepts as input geographic locations of a particular type, such as addresses, street intersections or tax lots, and provides some or all of the following services, depending on the function and on calling options chosen:

- Geosupport standardizes and encodes components of the user input data. Specifically, it reformats input street names and input address numbers into standard formats, a process called 'normalizing', and it provides numeric street codes corresponding to input street names.

- Geosupport validates the input data. The nature of the validation performed depends on the function requested and the type of call made. Validation of geographic data is a particularly powerful tool in the interactive environment, where it can help applications to trap keying errors and street name misspellings at the point of initial data entry when such errors are most easily rectified.

- Geosupport geocodes the input data. That is, it outputs a predefined set of 'higher-level' geographic information associated with the input location, such as the community district, ZIP code, police precinct, cross streets.

- Geosupport enables consistent retrieval of user application data by geographic location. That is, it supports the ability of user applications to search (for inquiry or updating) or match their own data files by geographic location in a way that is independent of possible variations in referring to locations.

The nature of each application determines the combination of these services that is relevant. For example, some applications need only to validate geographic locations, not to obtain any of the output information that Geosupport provides. The fourth type of service, support for geographic retrieval consistency, is relevant only for applications that retrieve or match data from their own files by geographic location (as distinct from Geosupport's retrieval of data from its internal files). For those applications, geographic retrieval consistency is a critical issue. The next section of this chapter contains a discussion of geographic retrieval consistency in general terms. Later chapters of this document contain detailed discussions of this topic.

I.3 Introduction to Geographic Retrieval Consistency

In applications that retrieve data from an application file by geographic location or match two application files by geographic location, the consistency of that retrieval or matching is a critical consideration that arises when processing any type of location that can be specified in more than one way. For example, consistency is a consideration for any type of location involving streets (such as addresses, intersections and street segments), since many streets have alternative names and many street names have spelling variants. The goal is to enable applications to retrieve records independently of which street name spelling was used when the record was created and which one is used at retrieval time. Similarly, consistency is a consideration when retrieving building-level

data by address, since many buildings have more than one address. It is a consideration when retrieving data for street intersections, since many intersections (e.g., three-way intersections) can be specified using more than one pair of streets.

The achievement of retrieval consistency can greatly improve an application's 'hit' rate on geographic searches into the application's own files. Moreover, it enables applications to identify and consolidate multiple records for the same location effectively. These advantages can have a significant impact on the efficiency of a city operation. For example, an application can use this capability to generate a single work order for dispatching personnel to handle multiple repairs, inspections or other transactions for the same location.

Of the services that Geosupport provides, its use to achieve geographic retrieval consistency involves the most extensive integration of Geosupport in the design of the user application. Geosupport provides such support by returning certain data items which an application can store in its file during record creation and use as part of a geographic retrieval key. An example is an item called the <u">five-digit street code, which applications can use to achieve consistent retrieval of data by those types of geographic locations that are specified in terms of streets. This is briefly discussed below, and is explained in detail in later chapters.

Within Geosupport, a set of numeric street codes has been assigned to represent New York City's street names. A full street code is a ten-digit item that, together with a borough identifier, corresponds to a specific spelling of a specific name for a specific street in that borough. The first five digits of the ten-digit street code are collectively called the five-digit street code. Ten-digit street codes are assigned in such a way that alternative names and spelling variants of the same street have the same five-digit street code. As a result, applications can achieve consistent retrieval or matching of application data by any type of geographic location that involves streets by using five-digit street codes instead of street names as part of the retrieval key. For the convenience of users, for all functions that involve street input except Function 1N and the display functions (Functions D, DG and DN), applications have the option to provide input streets to Geosupport in the form of either street names or street codes. Street codes are discussed in greater detail in Chapter IV.

I.4 The Geosupport Function Suite

This section contains a brief introduction to the Geosupport function suite. Each Geosupport function is identified by a one- or two-character function code. The function suite consists of location-processing functions (Functions 1, 1A, 1B, 1E, 2, 3, 3C, 3S, AP[1],BL and BN), display functions (Functions D, DG and DN) and miscellaneous functions (Functions 1N, BB and BF). Table I-2 lists the currently implemented functions. Note that Functions 1B and AP are COW[2] functions only.

Each location-processing function processes input geographic locations of a particular type. For each type of location, there is an appropriate set of data items that collectively define such locations. Table I-1 lists the various types of geographic locations, the data items required to specify

them, and examples. The location-processing functions can be sub-classified into address-processing functions, street-configuration-processing functions and ID-processing functions:

- The address-processing functions are Functions 1, 1A, 1B, 1E and AP. There are also Extended versions of four of the functions, viz. Function 1 Extended, Function 1A Extended, Function 1E Extended, Function AP Extended . Function 1B is a combination of Function 1E Extended and Function 1A Extended. Except for Function AP, the address-processing functions process conventional addresses, Addressable Place Names (APs) and Non-Addressable Place Names (NAPs). Function AP processes conventional addresses only.

- The street-configuration-processing functions are Functions 2, 3, 3C and 3S. There are also Extended versions of two of the functions, viz. Function 3 Extended and Function 3C Extended. All these street-configuration-processing functions process geographic locations that are defined in terms of one, two or three streets, such as street intersections, intersection names, blockfaces and street stretches. Note that Function 2 is also an ID-processing function (see below).

- The ID-processing functions are Functions BL, BN, and COW Function 2. There are also Extended versions of these functions, viz. Function BL Extended and Function BN Extended and the Wide version of Function 2, viz. Function 2W. These functions process locations defined in terms of identifying numbers, namely, tax lot identifiers in the case of Function BL, Building Identification Numbers (BINs) in the case of Function BN and Node ID in the case of Function 2. Tax lot identifiers and BINs are discussed in detail in Chapter VI. Node IDs are discussed in Chapter VII. Note that Function 2 is also a street-configuration-processing function (see above).

In general, anything that applies to a basic Geosupport Function will also apply to the Extended Version of that function and other variations (e.g. Long Work Area or Auxiliary Segments) as well. For example, anything that is true of Function 1 will also be true of Function 1 Extended. In our discussion of the various functions, for simplicity, we will often refer only to the basic function, but the information will apply also to the Extended function and other variations.

The address-processing functions differ from each other with respect to the output data that they provide and the nature of the validation processing that they perform. In general, the type of validation processing a Geosupport function performs is related to the geographic level of the output data. Thus the processing for Functions 1, 1E (and the 1E portion of Function 1B, see below), validates only whether the input address falls within an address range for an entire blockface, but it does not validate whether the input address is itself specifically valid. Function AP and Function 1A (and the Function 1A portion of Function 1B, see below), on the other hand, do validate whether the input address is (or could be) a valid address for a specific building. The return of a Building Identification Number (BIN) from Function AP and Function 1A will verify the existence of a building at the given address.

There are some users of Geosupport who process addresses by making two Geosupport calls (one call to Function 1 or 1E and another call to Function 1A). In response to requests by users, Function 1B was developed in order to allow users to retrieve blockface information (which is available with Function 1 or 1E) and Property Level information (which is available with Function 1A) in one Geosupport call. Function 1B combines Function 1E Extended with Function 1A Extended. The input requires borough (or ZIP code), address number if needed, and street name or street code. Function 1B retrieves the tax lot and building information from the PAD (Property Address Directory; data is at the property parcel level) file based on the input (Function 1A-type processing). The blockface and political data are then retrieved from the GRID (Geographic Reference Integrated Dictionary; data is at the centerline level) and the Election files (Function 1E-type processing) for the address set by the building level information

The display functions do not themselves directly 'display' anything, but they provide street names and/or address numbers in formats suitable for applications to display on screens, reports, mailing labels etc.

In Table I-1, the word 'street' refers to either a street name or a street code. In the examples in Table I-1, street names rather than street codes are used. (Note: the examples are formatted for reader comprehension, and would not be accepted by Geosupport as shown. Specifically, they contain borough names rather than the borough codes that Geosupport requires, and they contain English words and phrases such as 'intersection of' and 'between' that Geosupport does not recognize.)

Table I-1: Types of Geographic Locations Processed

Types of Locations	**Input Items Required to Specify Location,** ***Example***
Address	Borough (or ZIP code) + address number + street: *Bronx, 307 East Tremont Avenue*
Non-Addressable Place Name	Borough (or ZIP code) + place name: *Manhattan, Carnegie Hall*
Addressable Place Name	Borough (or ZIP code) + address number + place name: *Manhattan, 2 Penn Plaza*
Street Intersection	Borough + two intersecting streets: *Brooklyn, intersection of Flatbush Avenue and Atlantic Avenue* *OR (if a pair of streets has two points of intersection), Borough + two intersecting streets + compass direction:* *Queens, east intersection of Alderton Street and Cromwell Crescent* OR Borough + Intersection Name: *Manhattan, Isaac Stern Place* OR Node ID: *0015376 (intersection of Broadway and Reade St, Manhattan)*

Street Segment	Borough + 'on' street + two consecutive cross streets: *Manhattan, Broadway between W 38th St and W 39th St*
Blockface	Borough + street segment + compass direction specifying side of street: *Manhattan, east side of Broadway between W 38th St and W 39th St*
Street Stretch	Borough + 'on' street + any two cross streets: *Manhattan, Broadway between W 38th St and W 54th St* OR (if either or both of the cross streets has two points of intersection with the 'on' street), Borough + 'on' street + two intersecting streets + compass direction(s): *Queens, Alderton Street between East intersection with Cromwell Crescent and intersection with 63rd Drive* OR Borough + 'on' street: *Manhattan, Broadway*
Tax Lot	Borough + tax block + tax lot: *Staten Island, Block 247 Lot 16*
Building	Building Identification Number (BIN): *5006708*

Table I-2 below lists all of the current Geosupport functions, indicating for each function the type of input geographic location processed, the geographic level of the output data, and a sample of output data items. The table does not include normalized street names, street codes and normalized address numbers among the sample output items listed; those items are always returned when the input involves street names and address numbers. Certain terms not defined until later have been included in Table I-2 for completeness.

Table I-2: List of Geosupport Functions

Function	Type of Input	Description of Output	Sample Output Items
1	Address or Non-Addressable Place Name	Blockface-related data	Cross streets, ZIP code, census tract and block, community district, police precinct, school district, health area, spatial coordinates; COW Only: NTA, Police Patrol Borough; COW Extended Only: PUMA Code
1A	Address or Non-Addressable Place Name	Property-related data	Tax block and lot identifiers, list of all buildings, addresses and street frontages of property, condo flag, spatial coords.
1B (COW Only)	Address or Non-Addressable Place Name	Combined Property and Blockface related data	See Function 1E below and Function 1A above (COW Only)
	Address or		

1E	Non-Addressable Place Name	Blockface-related data	Same as Function 1 + political districts: Election, State Assembly and Senate, City Council, Congressional and Municipal Court Districts
1N	Street Name or Place Name	Normalized name, street code	
2	Street Intersection or Named Intersection or Node ID	Intersection-related data	Additional streets at intersection (other than input streets), census tract, community district, spatial coordinates COW Only: Some Political Geography
3	Street Segment	Segment-related data + data related to left and right blockfaces	Cross streets, left and right ZIP code, left and right census tract and block, left and right community district, node ID
3C	Blockface	Blockface-related data	Cross streets, ZIP code, census tract and block, community district, node ID
3S	Street Stretch	Street stretch-related data order along the stretch, approximate	Number of and list of intersections in distance in feet between intersections
AP (COW only)	Address	Property-related data of CSCL Address Point	BBL, BIN, Spatial coordinates of CSCL Address Point, Address Point ID
BB, BF	Character String	See right-hand column	Set of ten normalized street names in alphabetical order
BL	Tax Lot	Property-related data Same as Function 1A	
BN	Building	Property- and building-related data	Tax block and lot identifiers, list of all addresses of building, condo flag, spatial coordinates
D	5-Digit Street Code	Normalized ‘primary’ name of street	
DG	7-Digit Street Code	Normalized ‘principal’ name of local group	
DN	10-Digit	Normalized	

	Street Code	street name	
HR	None – CICS GOAT	Geosupport Data Set Information	Creation date, Geosupport release cycle, number of records
N*	Street Name	Normalized street name	Name is normalized without a borough, therefore no consideration of validity.

As a mnemonic aid, Geosupport function codes have been chosen to be as descriptive as possible. For functions involving street input, the first character of the function code is numeric and indicates the number of input streets. (There is one exception, Function AP, which is described below). Thus, Functions 1, 1A, 1B and 1E process addresses and non-addressable place names, which are specified by a single input street or place; Function 2 processes intersections, which generally are specified by two input streets, a single intersection name, or a node ID. Functions 3, 3C and 3S process street segments, block faces and street stretches, respectively, all of which involve three input streets (an 'on' street and two cross streets), or, optionally, just an 'on 'street for Function 3S. The second character of the function code, if any, is often descriptive as well: the letter 'C' signifies that the function involves compass direction input; the letter 'S 'signifies street stretch input. Function AP is the one exception to the pattern described above: Function AP is a mnemonic for 'Address Point' and has one street address as input. The function codes of functions that do not involve street address input are abbreviations of descriptive terms for the functions: BB and BF are abbreviations for 'browse backward' and 'browse forward', BL for 'block/lot', BN for 'building number', and D, DG and DN for 'display', 'display group' and 'display name'.

---

[1] Note that 'AP' is the acronym for the function AP (Address Point). It is also the acronym for Addressable Place Name and Atomic Polygon. The acronym's meaning should be clear by its usage. It will be spelled out as needed.
[2] Character-Only Work Area (COW). See Appendix 12.

I.5 Overview of System Architecture

The Geosupport System consists of two major components called the foreground component and the background component,as well as the utility programs GBAT, GOAT and AIMZ. The relationships among the foreground component, the background component and the user application program are described in this section and are illustrated in Figure I-1 below.

Both the foreground component and the background component consist of both software and files. Users access the foreground component either directly from user-written programs via Geosupport API calls, or indirectly via the utility programs, which in turn access the foreground component via the Geosupport API. The foreground component and the utility programs are installed on IBM mainframes at the city computer centers listed in Appendix 7. Users do not access the background component, and it is not described in this document beyond the brief remarks in this section.

The Foreground Component

The files of the foreground component contain the geographic data that the foreground software requires to process user requests. User programs never read the foreground files directly; they are read only by the Geosupport foreground software.

The foreground software processes the input data passed to it by a calling user program. It performs such tasks as standardizing input street names and house numbers, reading foreground files, and returning information retrieved from those files, or appropriate error codes and messages, to the user program.

The Background Component

The background component contains a set of interrelated base files of the city's geography. The background files are continually updated and validated by the GSS staff. The background software includes software for updating and validating the background files and software for generating new foreground files from the background files.

The background work takes place partly on an IBM mainframe at the centralized data center operated by the City of New York Department of Information Technology and Telecommunications (DoITT) and on PCs located at the Department of City Planning, and partly in an enterprise Geographic Information System (GIS) software environment running on DoITT's servers..

The background component, including GSS's GIS environment, is not accessible to users. To a user application, Geosupport appears to consist only of conventional data processing technology, and does not appear to include computer mapping capabilities. However, Geosupport, through its geocoding functionality, particularly its provision of spatial coordinates for an address, tax lot, or intersection, can facilitate the use of separate computer mapping or GIS software to display geographically-related user data graphically. In addition, many of GSS's background files are available in ESRI format for free download as part of our BYTES of the BIG APPLE™ product line which can be used in conjunction with a user's Geosupport output.

Foreground Component Updating: New File Releases

All of the foreground files are read-only files. They remain in production, unchanged, until GSS requests that DoITT replace them with a new set containing updated data. The set of foreground files in production at a particular time constitutes a release,and is identified by a release designator such as Release15D. The first two characters of the release designator are the last two digits of the calendar year in which the release was deployed.

In the background component, GSS periodically performs a complex series of steps, called the Geosupport production cycle,to generate a new set of foreground files, quality assure those files, and deploy them for user access as a new Geosupport release.

Each new release is first implemented for user access on the DoITT mainframe. This is done in coordination with DoITT staff, who play an active role in migrating the files of the new release to all user-accessible CICS regions and the batch environment. After the new release is in production

at DoITT for a brief testing period, GSS staff disseminate the new release to the other computer centers where Geosupport is installed.The Desktop Edition also becomes available shortly after the new release is in production on the DoITT mainframe.

For many applications, no special user action is required when a new release of Geosupport files is implemented; the application will continue to run as before. Of course, under the new release, Geosupport may respond differently to a particular set of input data than it had under previous releases. For example, it may return different output information for a given set of input data, it may accept input data that had previously been rejected, and it may reject input data that had previously been accepted.

In some applications in which data items obtained from Geosupport are stored in an application file, it may be appropriate for the user to update those stored items to reflect changes in each new Geosupport release. This is referred to as resynchronizing the user file with respect to the new Geosupport release. Resynchronizing is particularly important for applications that use Geosupport-provided items, such as street codes, in geographic retrieval keys. For such applications, the user should develop a resynchronization procedure, and should run that procedure each time a new release of Geosupport is implemented. Resynchronization is discussed further in Chapter IV.

Foreground Component Updating: New Software Versions and Vestigial Features

From time to time, GSS makes changes to the foreground software, to enhance the system or correct errors. The foreground software in production is identified by a version number, such as Version13.1 etc. (Note that the foreground software is identified as a version while the foreground files are identified as a release.) On occasion, new foreground file releases and new foreground software versions are installed in production independently of one another, and therefore there is not a one-to-one correspondence between file releases and software versions. Typically, a file release and a software version are implemented simultaneously in what is referred to as a coordinated release.

Since the year 2013, the numbering scheme for a Software Version is yy.n, where ‘yy’ are the last two digits of the year and ‘n’ is the sequence number of the software version in that year, starting from ‘1’, e.g. Version 13.1. The numbering scheme for a Data Release is yy-x (or yyx), where ‘yy’ are the last two digits of the year and ‘x’ is the sequence letter of the data release in that year, starting from ‘A’, e.g. Release 15A).

It is a fundamental policy of GSS to strive to minimize the impact of Geosupport enhancements on existing applications. Whenever possible, enhancements are designed so that existing applications that do not require the new Geosupport feature need not be modified. In other words, enhancements are generally ‘transparent’ to existing applications. Although this is generally the policy of GSS, please see the SUMMARY OF CHANGES AND NEW FEATURES, at the beginning of this manual, for any item that could possibly affect your applications.

Over the years, numerous enhancements have been made to Geosupport, and virtually none of them have required existing applications to be modified or recompiled (except as necessary to take advantage of new features). As a consequence of this approach, Geosupport has a number of vestigial features. These are elements of the system, such as data items, work area formats, batch JCL, or entire functions that are still operational but are obsolete or have been superseded.

Vestigial features will continue to be supported for the most part, so that existing applications that use them will continue to run without modification. However, vestigial features will not be enhanced. Moreover, vestigial features have that status because of some shortcoming.Users are strongly encouraged to update their existing applications to eliminate all usage of vestigial features. All new applications should be designed to avoid any usage of vestigial features.

Vestigial features are mentioned in appropriate sections of this document, and are identified as such, but in many cases they are not documented in detail. An example of a vestigial feature is the erstwhile Function 2C (superseded by an enhancement to Function 2; discussed in Chapter VII.2).

Character-Only Work Areas (COWs)

COWs are an enhancement to Geosupport that was announced in Technical Bulletins in 2002. The Character-Only Work Areas are discussed, specifically, in Appendices 12, 13 and 14, and, in general, throughout the entire document.

User Feedback of Rejects

Typically, some of the geographic locations passed to Geosupport by a user application will be rejected as invalid. A reject could be caused by invalid user input data, such as a misspelled street name or an invalid address; or it could be caused by a Geosupport problem, such as an error or omission in Geosupport's internal data. Users should examine their rejects, and should report those rejects that cannot be attributed to user-caused errors to GSS staff by emailing GSS_Feedback@planning.nyc.gov (for more information, see Appendix 6). In addition, users should report cases where Geosupport has accepted the input data but has returned output information that the user believes to be incorrect (for example, a ZIP code that is believed to be incorrect for a particular input address). GSS relies on feedback from users as an essential source of information for quality-assuring Geosupport's data and keeping the data up-to-date and accurate.

GSS researches feedback received from users and updates the Geosupport background files as appropriate. Such corrections become visible to user applications only after a new release of the foreground files reflecting the corrections is deployed for user access. A time lag of as much as several months is possible between the reporting of a reject to GSS and the appearance of the correction in the foreground component.

Figure I-1 below illustrates the basic architecture of the Geosupport System.

Fig I-1 Geosupport architecture: components and Production Cycle

Please note the following elements depicted in Figure I-1:

• The interaction between the application program and the Geosupport foreground component via the Geosupport API

• The examination by the user of rejects and the feedback of unresolved rejects to GSS for research and possible background file updating

• The periodic generation (in the Background Component) of new releases of foreground files

I.6 Technical References

For detailed information refer to the *Geosupport System User Programming Guide*. This section will discuss those elements where the information on the mainframe is different than when you are using Geosupport Desktop Edition.

I.6.1 Street Names

Refer to Chapter III in the *Geosupport System User Programming Guide*. There is no difference for Street Names between Geosupport on the mainframe and Geosupport Desktop Edition.

I.6.2 Street Codes

Refer to Chapter IV in the *Geosupport System User Programming Guide*. Ignore any discussion of "PB5SC", which is a special form of the street codes used only on the mainframe.

I.6.3 Address Processing

Refer to Chapter V in the *Geosupport System User Programming Guide*. In Geosupport Desktop Edition, the House Number in Internal Format (HNI) is not used. In its place the House Number in Sort Format (HNS) is used. The HNI is a 6 byte field and may be used in mainframe applications. The HNS is an 11 byte field. When reading Chapter V in the *Geosupport System User Programming Guide*, substitute HNS whenever HNI is referenced.

I.6.4 Tax Lot and Building Processing

Refer to Chapter VI in the *Geosupport System User Programming Guide* for detailed information on this subject. However ignore Chapter VI.8, which discusses the Standard and Legacy version of Functions 1A and BL. The Legacy version is not available in Geosupport Desktop Edition.

I.6.5 Street Configuration Processing

Refer to Chapter VII in the *Geosupport System User Programming Guide* for detailed information on this subject.

CHAPTER II

INTRODUCTION TO THE GEOSUPPORT API

II.1 Introduction

This chapter presents an overview of the Geosupport Application Programming Interface (API), the mechanism through which a user-written application program interfaces directly with the Geosupport System. The basic architecture of the API, the user programming procedure required to utilize the API, and reject handling are described. The important distinction between one-work-area and two-work-area calls is discussed, and the long-work-area-2 option is described. The material in this chapter is general in nature. Chapter VIII discusses in detail the user programming statements and JCL required to utilize the API, and other chapters discuss application design issues specific to the various functions.

The Geosupport API consists of the following elements:

- A Geosupport load module called the driver that the user must link-edit into the application program. The driver serves as an intermediary between the user's application program and the Geosupport foreground software.
- One or two standard layout work areas that the user must include in the application program and that are used to pass data between the application program and Geosupport.
- Programming statements that the user codes in the application program utilizing the driver and work area(s) to interact with Geosupport.

With very few exceptions, the Geosupport API is identical in the batch and CICS environments. The principal exception is the name of the driver.

The driver has two principal purposes. It passes execution control from the user program to the Geosupport foreground software, which is external to the user program load module. The driver also passes addressability to the work areas (which are located within the user program) to the Geosupport foreground software, thereby enabling the foreground software to access those work areas.

User programs never read Geosupport's internal files directly. They are read only by the Geosupport foreground software, which returns data retrieved from those files to the calling user program in the work areas. In batch applications, the user JCL for the execute step must include DD statements for the load libraries that contain the Geosupport foreground software and data. Chapter VIII describes the JCL required for batch execution, and Appendix 8 contains examples.

Figure II-1, below, illustrates the elements of the Geosupport API as just described. The illustration assumes that the user program has a data file into which it writes information obtained from successful calls to Geosupport, and another file, printed report or screen display for handling rejects.

Fig II-1 The Geosupport API

When a user program issues a call to the driver, either one or two work areas are passed as parameters of the call. Work Area 1 (WA1) is always passed, and its length and layout are the same for all functions. Work Area 2 (WA2) may also be passed, depending on the Geosupport function being requested and the type of information needed by the user's application. The length and layout of WA2 are determined by the function and, for functions that have the 'long Work Area 2 option', by whether that option is specified. The distinction between one-work-area calls and two-work-area calls is discussed in Chapter II.4. The long Work Area 2 option is discussed in Chapter II.5. There is also the Auxiliary Segment option which is discussed in Chapter II.6 and the Extended Work Area 2 option which is discussed in Chapter II.7. The work areas may be Mainframe-Specific Work Areas (MSWs) or Character-Only Work areas (COWs). For a description of these formats see Appendix 12.

For the convenience of users whose programs are written in COBOL, IBM mainframe assembler, PL/1, C or NATURAL, Geosupport COPY libraries (copylibs) are maintained, containing source code layouts of each work area in each of those programming languages. The Geosupport COPY libraries are discussed in detail in Chapter VIII. The use of the Geosupport COPY libraries is optional but strongly recommended.

Note for CICS NATURAL Users: In order for Geosupport's CICS driver to pass control to the foreground component of Geosupport properly, it must know whether the calling user program is written in NATURAL. The driver determines this by examining a Geosupport table. This table contains a list of the transaction-IDs of CICS transactions that launch NATURAL programs that call Geosupport. If the transaction-ID of such a transaction is not in the table, the driver will mistakenly assume that the program calling Geosupport is not written in NATURAL, and the transaction will terminate abnormally when the program calls Geosupport.

At DoITT, the updating of the Geosupport NATURAL transaction-ID table is the responsibility of DoITT staff. Therefore, DoITT users who have new CICS applications written in NATURAL that are to access Geosupport must inform DoITT staff, who will enter the new transaction-ID into the table. CICS NATURAL users running at other computer centers should contact GSS.

II.2 Geosupport Return Codes and Reject Handling

Geosupport has an elaborate apparatus to support application problem-handling. There are three output fields in Work Area 1 that are used to inform calling applications of the outcome of each call to Geosupport. These fields are the Geosupport Return Code (GRC), the Reason Code and the Message. A comprehensive list of GRCs, Reason Codes and Messages is contained in Appendix 4.

The GRC is a two-byte character item into which Geosupport inserts a value before returning control to the calling application, as follows.

- A GRC value of '00' indicates unconditionally successful completion.
- A GRC value of '01' indicates a warning condition.
- A GRC value other than '00' or '01' signifies unsuccessful completion, or rejection, caused by either a system error or a user error.

Since Function 1B is a combination of two functions, viz. Functions 1A Extended and 1E Extended, a second set of GRC, Reason Code and Message field is defined in Work Area 1. This second set contains the GRC, Reason Code and Message for the Function 1A Extended portion of the Function 1B call. The original GRC, Reason Code and Message fields in Work Area 1 contain the GRC, Reason Code and Message from the Function 1E Extended portion of the Function 1B call. (It is entirely possible that Geosupport will find one set of information and not find the other. There can be an error code and message in the new GRC and Message fields indicating PAD data (Function 1A) has not been found, and a 00 or 01 GRC in the original Return Code field indicating Blockface (Function 1E) information has been found, or just the opposite.)

Warnings are conditionally successful completions. They alert the user to unusual aspects of the input or output data, or signify that Geosupport made an assumption about or modification to the input data. For example, Functions 1A, 1B and 1E issue a warning to alert the user that a required hyphen is missing from an input house number and that Geosupport has inserted the missing hyphen into the output normalized house number.

There are situations where user input data may result in multiple warning messages. In some cases, the warnings may be combined into a single message; however in other situations, it is not possible to combine the messages. When that happens, Geosupport attempts to select the warning message that would be most important. Based upon user feedback, the relative importance of the warning messages may be updated.

It is advisable for application designers to review the possible warnings that can be elicited by the functions their application will be calling (delineated in Appendix 4), and to determine whether there are types of warnings for which it would be appropriate to provide special handling routines. In some applications, it may be appropriate simply to display the messages that accompany warning returns, and otherwise to process warnings in the same fashion as unconditionally successful completions.

For all unconditionally successful completions, Geosupport returns values in the work area(s) for the full set of output data items that the given Geosupport function is designed to provide. (But see the note of caution regarding the return of values in work area output fields in Chapter II.4.) In the case of a warning, certain output fields may be 'empty' (blank, all zeros or otherwise devoid of information), depending on the nature of the warning. In the case of a rejection, almost all output fields are returned empty, but there will be values in the GRC and Message field.

Rejects can be caused either by a system error or a user error.

- System errors are problems that are not attributable to the user program or to the user input data, and therefore are beyond the user's control. Typical system errors are hardware errors, operating system errors and Geosupport software errors or data errors.

- User errors can occur when the user's program makes a call to Geosupport improperly, such as passing an invalid number of work areas; or when Geosupport considers the user's input data to be geographically or otherwise invalid, such as an invalid function code, an empty input field for which a value is mandatory, an invalid borough code, an invalid address.

For all warnings and rejects, the Message field contains an appropriate message. In addition, for all warnings and for some rejects, a value is returned in the Reason Code field, specifying more precisely the reason for the warning or rejection.

The user program should be designed so that, immediately upon receiving execution control back after a call to Geosupport, it examines the GRC (and the Reason Code, when relevant) to determine the outcome of the call, and takes appropriate action. (Note: the textual content of Geosupport messages is subject to revision without notice. Therefore, application developers should program rejection processing based on the value of the GRC and Reason Code rather than on the Message. Note also, that, in very rare instances a GRC may be retired and reused for a new message. If and when this happens, the Geosupport users will be notified of the change in advance so that appropriate adjustments can be made.)

In batch applications, appropriate actions for processing a warning or reject might include printing out the GRC, Reason Code and Message and/or writing the record to a reject file. In interactive applications, appropriate actions might include displaying the GRC, Reason Code and Message on the screen, and (for user errors, not system errors) giving the data entry operator an opportunity to correct the error and resubmit.

II.3 Geosupport API User Programming Procedure

A field in a Geosupport API work area into which the user program inserts a value to be passed to Geosupport is referred to as an input field of the work area (because it is an input datum to Geosupport). A field in a work area into which Geosupport inserts a value to be returned to the user program is called an output field. WA1 contains both input and output fields. WA2 contains output fields only.

The loading of values into WA1 input fields by the user program prior to issuing the call to the driver is referred to as priming WA1. The function being requested, determines which WA1 input fields must be primed, which are optional, and which are not used. One WA1 input field that is mandatory for all calls is the field for the function code. Combinations of other WA1 input fields, such as those for borough code, address number, street name and street code fields, collectively serve to specify a geographic location to be processed. Still other WA1 input fields are for specifying processing options, such as parameters that control how street names are normalized; most of those fields have default values and are optional.

It is essential that the user program clear WA1 to blanks before priming it, in order to eliminate any 'stray' data inadvertently lingering from a previous call. Various fields in the WA1 output area are initialized to blanks to help avoid extraneous data. If the call involves two work areas, however, WA2 need not be cleared by the user program before calling the driver, because Geosupport clears WA2 automatically.

After clearing WA1 to blanks, the user program primes WA1, and then issues a standard subroutine call to the driver, passing the work area(s) (more precisely, their memory addresses) as parameters of the call. (Note that a standard subroutine call is used to call the driver even in the CICS environment, rather than a CICS LINK.) The driver, in turn, passes execution control to Geosupport (more precisely, to the foreground component of Geosupport), which is external to the user program load module.

When Geosupport completes its processing for the given call, control is returned to the driver, which in turn returns control back to the user program. The user program can issue any number of calls to Geosupport during a single execution. Each call is an independent event, which Geosupport processes based entirely on the contents of WA1 passed in that call; Geosupport does not 'remember' previous calls.

The procedure that a user program would follow to call Geosupport via the API can be summarized as follows:

1. Clear WA1 to blanks

2. Prime WA1. That is, move values to the appropriate input fields in WA1. The function code is always required; other required and optional input fields depend on the function, and are listed in Appendix 1.

3. Issue a standard subroutine call to the driver, passing as calling parameter(s) either WA1 only or both WA1 and WA2. The required calling statements are described in Chapter VIII.3 and VIII.5. The distinction between one- and two-work-area calls is discussed in Chapter II.4.

4. Upon return of control to the user program, examine the GRC (and the Reason Code, if appropriate) in WA1, and take appropriate action. A list of the GRCs and Reason Codes that can be produced by each function is in Appendix 4.
   a. For Function 1B, examine both sets of GRC (and Reason Code, if appropriate) in WA1.

II.4 One-Work-Area and Two-Work-Area Calls

There are important distinctions between one-work-area and two-work-area calls. When a Geosupport function is called using one work area, Geosupport 'normalizes' certain input items, that is, it reformats them into a standard form. For each such input item that Geosupport successfully normalizes, there is a WA1 output field into which Geosupport inserts the item in normalized form. Normalizing includes such processing as right-justifying and zero-filling certain numeric input items (such as tax block and tax lot numbers), and providing fully spelled out borough names corresponding to input borough codes. Normalizing also encompasses performing complex algorithms to reformat street names and address numbers into standard formats.

After normalizing the appropriate input items, if the one-work-area call involves street name input items, Geosupport attempts to retrieve the street code corresponding to each input street name. If this is successful, each street code is returned in WA1. In summary, the processing Geosupport performs for a one-work-area call consists of normalization of the input data and the return of normalized values and street codes (if any) in WA1.

The processing performed for a two-work-area call includes all of the processing performed for a one-work-area call as well as certain additional processing. The nature of this additional processing depends on the Geosupport function. The additional processing generally consists of accessing Geosupport files in order to attempt to obtain certain geographic information associated with the input data. If the file access is successful, this geographic information is returned in WA2 (but see the cautionary note below). The process of associating higher level geographic information with an individual location is called geocoding, and the items of higher level information are called geocodes. Typical examples of geocodes returned by Geosupport in WA2 are community district, census tract, ZIP code and health area.

Caution: For a two-work-area call, a GRC of '00' or '01' signifies that Geosupport has accepted as valid the input geographic location specified by the user, but it does not guarantee that every item normally returned by the given function in WA2 contains a non-empty value. If a WA2 field is returned empty, this may or may not be erroneous. The field might be empty (blanks, zeros or otherwise devoid of information) because of an erroneous Geosupport data omission; this should be reported to GSS staff using the feedback procedures described in Appendix 6. However, the field might be empty intentionally and non-erroneously because the type of geographic area it represents does not completely cover the city. For example, there are certain non-residential areas of the city

where the Department of Sanitation has not defined Collection Scheduling districts. When a two-work-area call results in a GRC of '00' or '01', it is the responsibility of the user program to determine whether the particular WA2 fields being used by the application are non-empty.

Except for system errors, the outcome of a call to Geosupport, as signified by the GRC, Reason Code and Message, concomitantly has significance with respect to the geographic validity of the input data. The type of validation performed depends on the function and on whether a one- or two-work-area call has been made. The validations performed in a two−work−area call to a function are always more extensive than those performed in a one-work-area call to the same function. To illustrate this, consider Function 2, which processes an intersection specified in terms of two streets (note that Function 2 can also process intersections based on an intersection name or a node ID, but those inputs are not relevant to this example). In a one-work-area Function 2 call, if the two input streets were specified in the form of street names rather than street codes, Geosupport attempts to normalize the street names and obtain their street codes; success in doing so therefore validates that each input street name is recognizable to Geosupport as a valid name of a specific New York City street. However, the two input streets (names or codes) are processed independently of each other and are not treated as collectively defining a geographic location, in this case an intersection. In other words, when Function 2 is called using one work area, the existence of the intersection formed by the two input streets is not validated; the call will result in a GRC of '00' or '01' if both input street names are successfully normalized and recognized, regardless of whether the two streets intersect. In a two-work-area Function 2 call, on the other hand, Geosupport treats the two input streets as the intended specification of an intersection; an (unconditionally or conditionally) successful outcome validates the existence of this intersection, and if it is valid, Geosupport returns information about the intersection in WA2. For Geosupport functions in general, a one-work-area call validates only that the input items can be normalized and that input street names are recognizable to Geosupport, while a two-work-area call additionally provides some level of validation of the geographic location specified collectively by the input items. The specific validations performed in a two-work-area call to each Geosupport function are described in Chapters V through VII.

A two−work−area call causes Geosupport to access files additional to those accessed for a one−work−area call to the same function. Therefore, to maximize execution efficiency, when an application does not require the additional output data and/or validation processing that a two−work−area call provides, the application should issue a one-work-area call.

II.5 Coding Geosupport API Calls

The languages discussed in this section are C/C++ and Visual Basic/VBA. In general, the discussion assumes that the defaults were chosen during installation of Geosupport Desktop Edition.

This section describes the source code statements that the user must code in C/C++ and Visual Basic/VBA application programs to call the DLL. Also described are the statements required to declare the DLL.

As discussed in Chapter II.4, typically, the DLL can be called either with one or with two calling parameters. The first parameter passes the address of Work Area 1 to the DLL. If the application program is making a two-work-area call, the second parameter passes the address of Work Area 2 to the DLL.

The programming statements to declare and call the DLL are shown below.
Declaring the DLL

In a C/C++ program, the DLL is declared by including the `NYCgeo.h` header file that is distributed with Geosupport Desktop Edition, as shown below:

```
#include "NYCgeo.h"
```

In a Visual Basic/VBA program, the DLL must be declared to have two calling parameters for two-work-area calls and also two calling parameters for one-work area calls. This will not affect the processing. Examples of declaring NYCgeo for a two-work-area call (function 1E) and a one-work-area call (function D) appear below:

```
Declare Sub wgF1E Lib "NYCgeo.dll" Alias "NYCgeo" (x As C_WA1, y As C_WA2_F1E)
Declare Sub wgFD Lib "NYCgeo.dll" Alias "NYCgeo" (x As C_WA1, Optional y = NOTHING)
```

Calling the DLL
If 'WA1' and 'WA2' are the names that the user has given to the work areas within the application program source code, the statement calling the DLL would be coded as follows:

Language	One-Work-Area Call	Two-Work-Area Call
C/C++	`NYCgeo(&WA1);`	`NYCgeo(&WA1,&WA2);`
Visual Basic/VBA	`wgFD wa1`	`wgF1E wa1, wa2`

II.6 The Work Area C/C++ Header File and Visual Basic Typedef File

The source code layouts of all the Geosupport API work areas appear in a header file for C/C++ (`pac.h`) and a typedef file for Visual Basic (`vbwadef.bas`). These files may be found in `c:\program files\Geosupport Desktop Edition\include`

Use of these files is strongly recommended. A listing of the files appear in Appendix 5. A text description of the work area layouts is provided in Appendix 2.

For C/C++, Chapter II.7 describes the specific source code statements that users must code in their programs to utilize the Geosupport header file. See sample C/C++ program for what is required to compile a program that utilizes the Geosupport header file.

II.7 Coding API Calls When Using Geosupport C/C++ Header Files

This section describes the source code statements that users must code in application programs that use the Geosupport header file. The required statements consist of a declarative statement to reference the header file and statements calling the DLL.

In Chapter II.5, the forms of calls to the DLL were given using arbitrary data names for the work areas. In programs that do not use the Geosupport header file, those names are user-selectable. In the present section, the forms of the DLL calls are given again, this time with the specific data names that are required for compatibility with the header file. The C/C++ languages permit header file users to select their own names for the work areas (but not for the fields within the work areas). Prior to each call to the DLL, the program must prime Work Area 1 with the input data to be processed by Geosupport, as described in Chapter II.3.

II.7.1 C/C++ Source Code Statement

To reference the Geosupport C/C++ header file which contains the work area layouts, the C/C++ program must contain the following statement:

```
#include "pac.h"
```

The work area layouts must be declared using the typedefs in the Geosupport header file. For example:

C_WA1 anyname_wa1;	WA1, all functions
C_WA2_F1 anyname_wa2_f1;	WA2, Functions 1 & 1E
C_WA2_F1A anyname_wa2_f1a;	WA2, Functions 1A & BL (regular & long WA2), BN
C_WA2_F2 anyname_wa2_f2;	WA2, Function 2
C_WA2_F2 anyname_wa2_f3;	WA2, Function 3
C_WA2_F3C anyname_wa2_f3c;	WA2, Function 3C
C_WA2_F3S anyname_wa2_f3s;	WA2, Function 3S

For C/C++ programs that use the Geosupport header file, API calls may be coded as follows:

NYCgeo (&anyname_wa1);	One-work-area calls, all functions.
NYCgeo (&anyname_wa1,&anyname_wa2_f1);	Two-work-area calls, Functions 1 & 1E
NYCgeo (&anyname_wa1,&anyname_wa2_f1a);	Two-work-area calls, Functions 1A & BL (regular & long WA2), BN
NYCgeo (&anyname_wa1,&anyname_wa2_f2);	Two-work-area calls, Function 2
NYCgeo	

(&anyname_wa1,&anyname_wa2_f3);	Two-work-area calls, Function 3
NYCgeo (&anyname_wa1,&anyname_wa2_f3c);	Two-work-area calls, Function 3C
NYCgeo (&anyname_wa1,&anyname_wa2_f3s);	Two-work-area calls, Function 3S

An alternative method of calling NYCgeo from C/C++ appears in the sample program. Please see Chapter II.9.

II.8 Creating a Geosupport Desktop Edition Application

The Geosupport library (NYCgeo.lib) must be made available to the languages that require it, viz. C/C++.

The C/C++ header files (NYCgeo.h and pac.h) should be included in made available for C/C++ programs.

See sample programs in Chapter II.9 for more detail.

The internal Geosupport data files are automatically defined as environment variables during installation of Geosupport Desktop Edition. No action is required by the user.

II.9 Sample Programs with Descriptions

This section contains:

- A fully described sample C/C++ program
- A fully described sample Visual Basic program

Please note that the sample programs are not guaranteed to work and are provided as programming aides.

II.9.1 C/C++ Sample Program with Description

This section walks you through writing a C/C++ program that makes Geosupport Desktop Edition calls. It assumes that you are familiar with your Integrated Development Environment (IDE) and that you know how to code in C/C++. The complete program used here can be found at the end of this section in Listing II.8. Please note: The program in this section represents just one of many styles of coding in C/C++. It may be used as an example. It is not guaranteed.

There are six basic steps to making Geosupport Desktop Edition calls from a C/C++ program:

1. Set up your environment.
2. Include needed header files and other variable definitions.

3. Prepare Work Area 1.
4. Call NYCgeo.
5. Check the Geosupport Return Code.
6. Access the data in Work Area 1 and Work Area 2.

   optional step - convert house numbers in sort format or street codes with a function D call.

That's it. If you follow this list, in no time you should be writing C/C++ programs that take advantage of the power of Geosupport.

Set Up Your Environment

To begin, you need to tell your Integrated Development Environment (IDE) where to find several important Geosupport files. These can be found in Listing II.1 below. Your IDE should have a Setup Menu for changing project options. Navigate to this menu in your IDE and add Line 1 or Line 2 in Listing II.1 to the existing settings. Now add lines 3 and 4 in Listing II.1 to the settings for Include (or Header) File Locations.

Listing II.1 Library and Header Files Needed by Geosupport Desktop Edition

```
1: harddrive:\Program Files\Geosupport Desktop Edition\Include\BC++ Library\NYCgeo.lib
or <br>
2: harddrive:\Program Files\Geosupport Desktop Edition\Include\MSVC Library\NYCgeo.lib
3: harddrive:\Program Files\Geosupport Desktop Edition\Include\ NYCgeo.h
4: harddrive:\Program Files\Geosupport Desktop Edition\Include\pac.h
```

Include Header Files

In C/C++, you need to include a function prototype in order to successfully call a function. Line2 in Listing II.2 below shows you how to include the Geosupport Desktop Edition prototype in your program.

Geosupport uses several "work areas" to return data to the user. For your convenience we have included the layouts for these work areas in a header file "pac.h" (line 4 in Listing II.2). We strongly recommend that you use these layouts.

Lines 8 and 9 below are useful variables we recommend you use. These are the lengths of the work areas that you will be using. LEN_WA1 is particularly useful as you will see later.

The unions (lines 11 through 20 in Listing II.2) of the work area structures with character arrays are useful in several ways for making your calls. First, the structure (e.g."wa1" in line 11) makes it easy for you to access the individual fields in the work areas. Second, the character array (e.g."wa1c" in line 12) allows you to easily initialize Work Area 1. The second Work Area 1 (lines 18 through 20) was set up to enable you to make another Geosupport call (e.g. function D } without losing the Work Area 1 output data from your original function call.

Listing II.2 Include Header Files and Set Up Variables

```
// function prototype for NYCgeo
#include "NYCgeo.h"
// header file of workarea layouts
#include "pac.h"
#include <string.h>
#include <iostream.h>
// lengths of workareas
size_t const LEN_WA1 = sizeof(C_WA1);
size_t const LEN_WA2F1 = sizeof(C_WA2_F1);
// convenient way to handle workareas
union { C_WA1 wa1;
char wa1c[LEN_WA1];
} w1;
union { C_WA2_F1 wa21;
char wa21c[LEN_WA2F1];
} w21;
// this second WA1 is for Function D calls
union { C_WA1 wa1fd;
char wa1fdc[LEN_WA1];
} w1fd;
```

Set Up Work Area 1 for Function Call

There are two steps that must precede every call to Geosupport..

1. Work Area 1 must be initialized to spaces (see line 4 in Listing II.3 below).
2. The "platform indicator" field must be set to <C' (see line 5 in Listing II.3 below).

Other than the two steps above, there is only one other field that must contain a value on every call. That is the "function code" field. The remaining fields and their values that are set up will vary with the function call you want to make. Line 9 in Listing II.3 below shows you how to indicate you want to make a Function 1E call. Function 1E requires as input a borough code, a street name or street code, and a house number (see lines 10 through 12 in Listing II.3).

In addition to the required fields, there are optional fields that can be filled. Line 13 in Listing II.3 indicates that you want the Street Name normalized to a length of 32 characters.

Listing II.3 Set Up Work Area 1 for Function Call

```
1) ////////////////////////////////////////////////////////////////////
2) // these two lines of code must be executed for every NYCgeo call
3) ////////////////////////////////////////////////////////////////////
4) memset(w1.wa1c, ' ', LEN_WA1);
5) w1.wa1.input.platform_ind = 'C';
6) ////////////////////////////////////////////////////////////////////
7) // select the function you wish to call
8) ////////////////////////////////////////////////////////////////////
9) memcpy(w1.wa1.input.func_code, "1E", 2);
10) memcpy(w1.wa1.input.sti, in_boro_str, 1);
11) memcpy(w1.wa1.input.sti[0].Street_name, in_stname_str, 32);
12) memcpy(w1.wa1.input.hse_nbr_disp, in_housenum_str, 16);
13) memcpy(w1.wa1.input.snl, "32", 2);
```

Call NYCgeo

Now that we have set up Work Area 1 for the desired function we can now look at how to make the call. Earlier we set up unions of the structures of work areas with character arrays (see lines 11 through 16 in Listing II.2 above). The parameters to the NYCgeo call must be pointers to characters. The references w1.wa1c and w21.wa21c are just such pointers. Line 1 in Listing II.4 below shows the code to make the Geosupport call.

Listing II.4 Call NYCgeo

```
(A) NYCgeo(w1.wa1c, w21.wa21c);
```

Check the Geosupport Return Code

After you've made the Geosupport call, you need to check the Geosupport Return Code (GRC) in the Output section of Work Area 1 (lines 2 and 3 in Listing II.5 below). A return code of <00' indicates a successful call and a value of <01' indicates a successful call but there is a warning message you should check. Any other Geosupport Return Code value indicates that an error has taken place; you will want to have special processing to handle these situations. For a complete listing of the warning and error codes see "Geosupport Return Codes, Reason Codes and Messages" in Appendix 4 of this guide.

Listing II.5 Check the Return Code

```
1: // the function completed successfully
2: if ((memcmp(w1.wa1.output.ret_code, "00", 2) == 0) |
3: (memcmp(w1.wa1.output.ret_code, "01", 2) == 0))
4: {
5: // add code to process data returned (and warning, if ret_code == 01)
6: }
7: // there was an error in the function call
8: else
9: {
10: // add code to process errors
11: }
```

Access the Data from the Work Areas

Listing II.6 below gives several examples of accessing data in the work areas after a successful Geosupport Function 1E call. Remember that earlier we included the Work Area 2 structure in a union with a character array. That is the reason for the "w21" qualifier before each of the fields in lines 1 through 8 in Listing II.6). The "w1" qualifier in lines 9 through 12 in Listing II.6 reflects the union we created for Work Area 1.

Listing II.6 Access Data from Work Areas

```
1: // these fields are returned for both function 1 and 1E calls
2: memcpy(convstr, w21.wa21.zip_code, sizeof w21.wa21.zip_code);
3: convstr[sizeof w21.wa21.zip_code] = '\0';
4: printf("zip code = %s\n", convstr);
....
5: // these fields are returned for function 1E calls only
6: memcpy(convstr, w21.wa21.ad, sizeof w21.wa21.ad);
7: convstr[sizeof w21.wa21.ad] = '\0';
8: printf("Assembly District = %s\n", convstr);
....
9: // display grc message
10: memcpy(convstr, w1.wa1.output.msg, sizeof w1.wa1.output.msg);
11: convstr[80] = '\0';
12: printf(" : %s\n", convstr);
```

Convert House Numbers in Sort Format and Street Codes

Geosupport functions (e.g. function 1E) often return house numbers in sort format and street codes. To convert house numbers in sort format to house numbers in display format, or to convert street codes to street names, make a function D call. Function D calls (see Listing II.7 below) follow the same procedure as the other functions with one exception, only Work Area 1 is passed as a

parameter (see line 9 in Listing II.7 below). Also note: We've used a second copy of Work Area1 (see lines 18 through 20 in Listing II.2 above) so that the data in Work Area1 from the original function 1E call is not lost.

Listing II.7 Convert House numbers in Sort Format with Function D call

```
1: // set up workarea 1 defined for function D calls
2: memset(w1fd.wa1fdc, ' ', LEN_WA1);
3: w1fd.wa1fd.input.platform_ind = 'C';
4: memcpy(w1fd.wa1fd.input.func_code, "D ", 2);
5: memcpy(w1fd.wa1fd.input.hse_nbr_hns, w21.wa21.hi_hse_nbr,
6: sizeof w21.wa21.hi_hse_nbr);
7: memcpy(w1fd.wa1fd.input.sti, w1.wa1.output.sto, 1);
8: // make 1 work area call
9: NYCgeo(w1fd.wa1fdc);
10: // function D completed successfully
11: if ((memcmp(w1fd.wa1fd.output.ret_code, "00", 2) == 0) |
12: (memcmp(w1fd.wa1fd.output.ret_code, "01", 2) == 0))
13: {
14: ////////////////////////////////////////////////////////////////////
15: // prepare output fields from function D call
16: ////////////////////////////////////////////////////////////////////
17: memcpy(convstr, w1fd.wa1fd.output.hse_nbr_disp,
18: sizeof w1fd.wa1fd.output.hse_nbr_disp);
19: convstr[sizeof w1fd.wa1fd.output.hse_nbr_disp] = '\0';
20: printf("High House Number of Block Face = %s", convstr)
21: }
```

You've now seen how to write a C/C++program that makes Geosupport Desktop Edition calls. Of course, your style of coding may be different and your processing will probably be more involved. Nevertheless, if you follow these few simple steps you can easily harness the power of Geosupport in your C/C++programs.
Listing II.8 below contains the complete program used in this section.

Listing II.8 Complete C/C++ Sample Program

```
////////////////////////////////////////////////////////////////////////////////
// C sample program demonstrating how to use Geosupport Desktop Edition
// to make a function 1E call
////////////////////////////////////////////////////////////////////////////////
// function prototype for NYCgeo
#include "NYCgeo.h"
// header file of workarea layouts
#include "pac.h"
#include <string.h>
#include <iostream.h>
```

```
// lengths of workareas
size_t const LEN_WA1 = sizeof(C_WA1);
size_t const LEN_WA2F1 = sizeof(C_WA2_F1);
// convenient way to handle workareas
union { C_WA1 wa1;
char wa1c[LEN_WA1];
} w1;
union { C_WA2_F1 wa21;
  char wa21c[LEN_WA2F1];
} w21;
// this second WA1 is for Function D calls
union { C_WA1 wa1fd;
char wa1fdc[LEN_WA1];
} w1fd;
char *convstr;
convstr = (char*) malloc(81);

////////////////////////////////////////////////////////////////////////////
// input fields initialized to sample values
////////////////////////////////////////////////////////////////////////////
char in_boro_str[2] = '1';
char in_stname_str[32] = 'reade st';
char in_housenum_str[16] = '22';
char in_stcode_str[11] = '1061002010';
void main()
{
//////////////////////////////////////////////////////////////////////////
// get input data from user
//////////////////////////////////////////////////////////////////////////
printf("Input a Boro Code:");
gets(in_boro_str);
printf("Input a House Number:");
gets(in_housenum_str);
printf("Input a Street Name:");
gets(in_stname_str);
//////////////////////////////////////////////////////////////////////////
// set up workarea 1
//////////////////////////////////////////////////////////////////////////
//////////////////////////////////////////////////////////////////////////
// these two lines of code must be executed for every NYCgeo call
//////////////////////////////////////////////////////////////////////////
memset(w1.wa1c, ' ', LEN_WA1);
w1.wa1.input.platform_ind = 'C';
//////////////////////////////////////////////////////////////////////////
// select the function you wish to call
```

```
////////////////////////////////////////////////////////////////////////
memcpy(w1.wa1.input.func_code, "1E", 2);
memcpy(w1.wa1.input.sti, in_boro_str, 1);
memcpy(w1.wa1.input.sti[0].Street_name, in_stname_str, 32);
// can use street code instead of street name
// memcpy(w1.wa1.input.sti[0].SC10, in_stcode_str, 5);
memcpy(w1.wa1.input.hse_nbr_disp, in_housenum_str, 16);
memcpy(w1.wa1.input.snl, "32", 2);
NYCgeo(w1.wa1c, w21.wa21c);
////////////////////////////////////////////////////////////////////////
// check the return code: if successful, process data
// if not successful, display error message
////////////////////////////////////////////////////////////////////////
// the function completed successfully
if ((memcmp(w1.wa1.output.ret_code, "00", 2) == 0) |
(memcmp(w1.wa1.output.ret_code, "01", 2) == 0))
{
  // these fields are returned for both function 1 and 1E calls
  memcpy(convstr, w21.wa21.zip_code, sizeof w21.wa21.zip_code);
  convstr[sizeof w21.wa21.zip_code] = '\0';
  printf("zip code = %s\n", convstr);
  memcpy(convstr, w21.wa21.lo_hse_nbr, sizeof w21.wa21.lo_hse_nbr);
  convstr[sizeof w21.wa21.lo_hse_nbr] = '\0';
  printf("low house number = %s\n", convstr);
  memcpy(convstr, w21.wa21.hi_hse_nbr, sizeof w21.wa21.hi_hse_nbr);
  convstr[sizeof w21.wa21.hi_hse_nbr] = '\0';
  printf("high house number = %s\n", convstr);
  memcpy(convstr, w21.wa21.coord[0], sizeof w21.wa21.coord[0]);
  convstr[sizeof w21.wa21.coord[0]] = '\0';
  printf("X coordinate = %s\n", convstr);
  memcpy(convstr, w21.wa21.coord[1], sizeof w21.wa21.coord[1]);
  convstr[sizeof w21.wa21.coord[1]] = '\0';
  printf("Y coordinate = %s\n", convstr);
  // these fields are returned for function 1E calls only
  memcpy(convstr, w21.wa21.ad, sizeof w21.wa21.ad);
  convstr[sizeof w21.wa21.ad] = '\0';
  printf("Assembly District = %s\n", convstr);
  memcpy(convstr, w21.wa21.ed, sizeof w21.wa21.ed);
  convstr[sizeof w21.wa21.ed] = '\0';
  printf("Election District = %s\n", convstr);
  ////////////////////////////////////////////////////////////////////////
  // function D, a 1 workarea call to Geosupport, converts
  // housenumbers in sort format to housenumbers in display format and
  // street codes to street names
  ////////////////////////////////////////////////////////////////////////
```

```
// set up workarea 1 defined for function D calls
memset(w1fd.wa1fdc, ' ', LEN_WA1);
w1fd.wa1fd.input.platform_ind = 'C';
memcpy(w1fd.wa1fd.input.func_code, "D ", 2);
memcpy(w1fd.wa1fd.input.hse_nbr_hns, w21.wa21.hi_hse_nbr,
  sizeof w21.wa21.hi_hse_nbr);
memcpy(w1fd.wa1fd.input.lohse_nbr_hns, w21.wa21.lo_hse_nbr,
  sizeof w21.wa21.lo_hse_nbr);
memcpy(w1fd.wa1fd.input.sti, w1.wa1.output.sto, 1);
memcpy(w1fd.wa1fd.input.sti[0].SC10, w1.wa1.output.sto[0].SC10, 5);
// make 1 work area call
NYCgeo(w1fd.wa1fdc);
// function D completed successfully
if ((memcmp(w1fd.wa1fd.output.ret_code, "00", 2) == 0) |
(memcmp(w1fd.wa1fd.output.ret_code, "01", 2) == 0))
{
  ////////////////////////////////////////////////////////////////////
  // prepare output fields from function D call
  ////////////////////////////////////////////////////////////////////
  memcpy(convstr, w1fd.wa1fd.output.lo_hse_nbr_disp,
    sizeof w1fd.wa1fd.output.lo_hse_nbr_disp);
  convstr[sizeof w1fd.wa1fd.output.lo_hse_nbr_disp] = '\0';
  printf("Low House Number of Block Face = %s", convstr);
  memcpy(convstr, w1fd.wa1fd.output.hi_hse_nbr_disp,
    sizeof w1fd.wa1fd.output.hi_hse_nbr_disp);
  convstr[sizeof w1fd.wa1fd.output.hi_hse_nbr_disp] = '\0';
  printf("High House Number of Block Face = %s", convstr);
  memcpy(convstr, w1fd.wa1fd.output.sto[0].Street_name,
    sizeof w1fd.wa1fd.output.sto[0].Street_name);
  convstr[sizeof w1fd.wa1fd.output.sto[0].Street_name] = '\0';
  printf("Street Name from Function D = %s", convstr);
}
// there was an error in the function D call
else
{
  // display grc of function D call
  memcpy(convstr, w1fd.wa1fd.output.ret_code,
    sizeof w1fd.wa1fd.output.ret_code);
  convstr[sizeof w1fd.wa1fd.output.ret_code] = '\0';
  printf("Error on Function D call: %s\n", convstr);
  // display grc message of function D call
  memcpy(convstr, w1fd.wa1fd.output.msg, sizeof w1fd.wa1fd.output.msg);
  convstr[80] = '\0';
  printf(" : %s\n", convstr);
}
```

```
}
// there was an error in the function 1E call
else
{
  // display grc
  memcpy(convstr, w1.wa1.output.ret_code, sizeof w1.wa1.output.ret_code);
  convstr[sizeof w1.wa1.output.ret_code] = '\0';
  printf("Error on Function 1E call: %s\n", convstr);
  // display grc message
  memcpy(convstr, w1.wa1.output.msg, sizeof w1.wa1.output.msg);
  convstr[80] = '\0';
  printf(" : %s\n", convstr);
}
free (convstr);
} // end of main
```

II.9.2 Visual Basic (VB/VBA) Sample Program with Description

This section walks you through writing a Visual Basic (VB) or Visual Basic for Applications (VBA) program that makes Geosupport Desktop Edition calls. It assumes that you are familiar with your Integrated Development Environment (IDE) and that you know how to code in VB or VBA. This sample program is based on a simple form that provides input fields and output fields to display the returned data. The code is attached to a command button and responds to a "click" event. Please note: The program in this section represents just one of many styles of coding in Visual Basic. It may be used as a sample. It is not guaranteed.

There are six basic steps to making Geosupport Desktop Edition calls from a VB/VBA program:

1. declare the work area variable definitions.
2. declare the NYCgeo procedure.
3. prepare Work Area 1.
4. call NYCgeo.
5. check the Geosupport return code
6. access the data in Work Area 1 and Work Area 2
   optional step - convert house numbers in sort format or street codes with a function D call.

That's it. If you follow this list, in no time you should be writing VB programs that take advantage of the power of Geosupport.

Declare the Work Area Variables

VB/VBA users may use the tyepdef file found in

```
c:\program files\Geosupport Desktop Edition\include\vbwadef.bas
```

or they may choose to code their own typedefs using the character-only Work Area descriptions that can be found in Appendix 2 as the guide. It is recommended that you use the supplied typedef file.

The sample program in Listing II.16 does not use the typedef file, vbwadef.bas, but does create similar typedefs for Work Area 1 and Work Area 2 for Functions 1/1E. If the users choose to create their own typedefs, particular attention should be paid to setting up Work Area 1 as this is used in every function call. Listing II.9 shows a few examples of how to set up Work Area 1 as well as a second Work Area 1 to be used in making Function D calls (see Line 33 in Listing II.9).

If this code is part of a VBA application and is attached to a Form, you may have to declare the variables and types as Private. Because the code in Listing II.16 at the end is attached to a Form, the variables and types are declared as Private.

Listing II.9 Declare the Work Area Variables

```
1: Type STREET
2: boro As String * 1
3: sc10 As String * 10
4: Street_name As String * 32
5: End Type
6: Type INPUT_DEF
7: func_code As String * 2
8: house_num As String * 16
9: house_num_sort As String * 11
10: lo_house_num As String * 16
11: lo_house_num_sort As String * 11
12: sti(1 To 3) As STREET
13: filler01 As String * 175
14: End Type
15: Type OUTPUT_DEF
16: boro_name As String * 9
17: house_num As String * 16
18: house_num_sort As String * 11
19: sto(1 To 3) As STREET
20: filler02 As String * 11
21: lo_house_num As String * 16
22: lo_house_num_sort As String * 11
23: filler05 As String * 154
24: ret_code As String * 2
25: msg As String * 80
26: filler03 As String * 402
27: End Type
28: Type C_WA1
29: input1 As INPUT_DEF
30: output1 As OUTPUT_DEF
31: End Type
32: vbwa1 As C_WA1
33: fdwa1 As C_WA1
```

Declare the NYCgeo Procedure

Listing II.10 below shows one example of how you can declare a Sub procedure to call Geosupport Desktop Edition. If "NYCgeo.dll" is not in your Windows system directory (usually c:\winnt\system) or not in your include path, then you should give its fully qualified path name (e.g. "c:\myproj\files\NYCgeo.dll"). You may use whatever naming convention you wish for your Sub procedures, but the Alias must always be "NYCgeo".

Line 2 in Listing II.10 shows how to declare a Sub procedure to call Geosupport Desktop Edition for a one-work-area call. The first parameter is Work Area 1 but the second parameter must be defined as "Optional". Setting its default value to "Nothing" is not required but a safe programming

technique.

Listing II.10 Declare the NYCgeo Procedure

```
1: Declare Sub wgF1E Lib "NYCgeo.dll" Alias "NYCgeo" (x As C_WA1, _y As C_WA2_F1E)
2: Declare Sub wgFD Lib "NYCgeo.dll" Alias "NYCgeo" (x As C_WA1, _Optional y = Nothing)
```

Prepare Work Area 1

There are two steps that must precede every call to Geosupport. First, Work Area 1 must be initialized to spaces (see lines 1 - 7 in Listing II.11 below). Second, the "platform indicator" field must be set to 'C' (see line 8 in Listing II.11 below).

Other than the two steps above, there is only one other field that must contain a value on every call. That is the "function code" field. The remaining fields and their values that are set up will vary with the function call you want to make. Line 9 in Listing II.11 below shows you how to indicate you want to make a Function 1E call. Function 1E requires as input a borough code, a house number, and a street name or street code (see lines 10 through 12 in Listing II.11).

Listing II.11 Prepare Work Area

```
1: vbwa1.input1.house_num = " "
2: vbwa1.input1.house_num_sort = " "
3: vbwa1.input1.lo_house_num = " "
4: vbwa1.input1.lo_house_num_sort = " "
5: vbwa1.input1.sti(1).boro = " "
6: vbwa1.input1.sti(1).sc10 = " "
7: vbwa1.input1.sti(1).Street_name = " "
8: vbwa1.input1.platform_ind = "C"
9: vbwa1.input1.func_code = "1E"
10: vbwa1.input1.sti(1).boro = Form_Geodlg.txtboro
11: vbwa1.input1.house_num = Form_Geodlg.txthousenumber
12: vbwa1.input1.sti(1).Street_name = Form_Geodlg.txtstreetname
```

Call NYCgeo

Now that we have set up Work Area 1 for the desired function we can now look at how to make the call. Line 1 in Listing II.12 below shows the code to make the Geosupport Desktop Edition call.

Listing II.12 Call NYCgeo

```
1: wgF1E vbwa1, vbwa21e
```

Check the Return Code

After you've made the Geosupport call, you need to check the Return Code in the Output section of Work Area 1 (Listing II.13 below). A return code of <00' indicates a successful call and a value of <01' indicates a successful call but there is a warning message you should check. Any other Return Code value indicates that an error has taken place; you will want to have special processing to handle these situations. For a complete listing of the Warning and Error codes see "Geosupport Return Codes, Reason Codes, and Messages" in Appendix 4 of this guide.

Listing II.13 Check the Return Code

```
1:If vbwa1.output1.ret_code = "00" Then
2: 'code to process successful call goes here
3: Else
4: If vbwa1.output1.ret_code = "01" Then
5: 'code to process a successful call with a warning goes here
6: Else
7: 'code to process an unsuccessful call goes here
8: End
```

Access the Data from the Work Areas

Listing II.14 below gives several examples of accessing data in the work areas after a successful Geosupport Function 1E call. Of course, you may not want to display the data at this point. You may want to write the data to a file or do some other processing.

Listing II.14 Access the Data from the Work Areas

```
1: Form_Geodlg.txtB10SC = vbwa1.output1.sto(1).boro +
2: vbwa1.output1.sto(1).sc10
3: Form_Geodlg.txtzipcode = vbwa21e.zip_code
4: Form_Geodlg.txtlhns = vbwa21e.lo_house_num_sort
5: Form_Geodlg.txtlb5sc = vbwa21e.lo_xsts.B5SC_low1(1)
6: Form_Geodlg.txthhns = vbwa21e.hi_house_num_sort
7: Form_Geodlg.txthb5sc = vbwa21e.hi_xsts.B5SC_high
1(1)
```

Convert House Numbers in Sort Format and Street Codes

To convert house numbers in sort format to house numbers in display format or street codes to street names make a function D call. Function D calls (see Listing II.15 below) follow the same procedure as the other functions with one exception, only Work Area 1 is passed as a parameter (see line 16 in Listing II.15 below). Also note: We've used a second copy of Work Area 1 (see Line 33 in Listing II.9 above) so that the data in Work Area 1 from the original function 1E call is not lost.

Listing II.15 Convert House numbers in Sort Format with Function D call

```
1: // initialize work area 1 defined for Function D calls
2: fdwa1.input1.house_num = " "
3: fdwa1.input1.house_num_sort = " "
4: fdwa1.input1.lo_house_num = " "
5: fdwa1.input1.lo_house_num_sort = " "
6: fdwa1.input1.sti(1).boro = " "
7: fdwa1.input1.sti(1).sc10 = " "
8: fdwa1.input1.sti(1).Street_name = " "
9: // set up work area 1 defined for function D calls
10: fdwa1.input1.platform_ind = "C"
11: fdwa1.input1.func_code = "D "
12: fdwa1.input1.sti(1).boro = vbwa1.output1.sto(1).boro
13: fdwa1.input1.house_num_sort = vbwa21e.hi_house_num_sort
14: fdwa1.input1.lo_house_num_sort = vbwa21e.lo_house_num_sort
15: // make 1 work area function D call
16: wgFD fdwa1
17: // check the return code and access the converted house numbers
18: If vbwa1.output1.ret_code = "00" Or vbwa1.output1.ret_code = "01" Then
19: Form_Geodlg.txthhnd = fdwa1.output1.house_num
20: Form_Geodlg.txtlhnd = fdwa1.output1.lo_house_num
21: End If
```

You've now seen how to make Geosupport calls from your VB or VBA program. Of course, your style of coding may be different and your processing will probably be more involved. But if you follow these few simple steps you can easily harness the power of Geosupport Desktop Edition in your VB or VBA programs.
Listing II.16 below contains a VBA sample application with the complete variable declarations for Work Area 1 and Work Area 2 for Function 1E.

Listing II.16 Work Area 1 and Work Area 2 for Function 1E Variable Declarations with Sample Code

```
Option Explicit
'*****************************************************************************
'Some situations may requires these to be declared as Private
'*****************************************************************************
'define data types
Private Type STREET
  boro As String * 1
  sc10 As String * 10
  Street_name As String * 32
End Type

Private Type BBL
  boro As String * 1
```

```
  block As String * 5
  lot As String * 4
End Type

'typedef for input area of work area 1
Private Type INPUT_DEF
  func_code As String * 2
  house_num As String * 16
  house_num_sort As String * 11
  lo_house_num As String * 16
  lo_house_num_sort As String * 11
  sti(1 To 3) As STREET
  bbli As BBL
  filler01 As String * 1
  bin As String * 7
  compass_direction As String * 1
  compass_direction2 As String * 1
  filler02 As String * 7
  platform_ind As String * 1
  filler03 As String * 101
  long_WA2_flag As String * 1
  filler04 As String * 4
  snl As String * 2
  st_name_norm As String * 1
  expanded_format As String * 1
  filler05 As String * 37
End Type

'typedef for output area of work area 1
Private Type OUTPUT_DEF
  boro_name As String * 9
  house_num As String * 16
  house_num_sort As String * 11
  sto(1 To 3) As STREET
  bblo As BBL
  filler05 As String * 1
  lo_house_num As String * 16
  lo_house_num_sort As String * 11
  bin As String * 7
  attr_byte(1 to 3) As String * 1
  filler06 As String * 139
  reason_code As String * 1
  filler07 As String * 1
  warn_code As String * 2
  ret_code As String * 2
```

```
  msg As String * 80
  nbr_names As String * 2
  B7SC(1 to 10) As String * 8
  st_names(1 to 10) As String * 32
End Type

'typedef for work area 1
Private Type C_WA1
  input1 As INPUT_DEF
  output1 As OUTPUT_DEF
End Type

'typedefs used in work area 2
Private Type St_list
  nbr_sts As String * 1
  B5SC(1 To 5) As String * 6
End Type

Private Type St_list_high1
  nbr_sts_high1 As String * 1
  B5SC_high1(1 To 5) As String * 6
End Type

Private Type St_list_low1
  nbr_sts_low1 As String * 1
  B5SC_low1(1 To 5) As String * 6
End Type

'typedef for work area 2 for function 1
  Private Type C_WA2_F1E
  filler08 As String * 21
  cont_parity_ind As String * 1
  lo_house_num_sort As String * 11
  hi_house_num_sort As String * 11
  lgc As String * 2
  lo_xsts As St_list_low1
  hi_xsts As St_list_high1
  lion_key As String * 10
  sagr_flag As String * 1
  sos_ind As String * 1
  seg_len As String * 5
  Xcoord As String * 7
  Ycoord As String * 7
  Zcoord As String * 7
  iaei As String * 1
```

```
  mh_ri_flag As String * 1
  DOT_slca As String * 1
  com_dist As String * 3
  zip_code As String * 5
  ed As String * 3
  ad As String * 2
  sped_flag As String * 1
  congress_dist As String * 2
  state_sen_dist As String * 2
  civil_court as String * 2
  city_council As String * 2
  health_cent As String * 2
  health_area As String * 4
  sanit_dist As String * 3
  sanit_sub_sect As String * 2
  sanit_reg_pick_up As String * 5
  police_boro_com As String * 1
  police_pct As String * 3
  fire_div As String * 2
  fire_bat As String * 2
  fire_co_type As String * 1
  fire_co As String * 3
  scsd_flag As String * 1
  com_schl_dist As String * 3
  dynam_block As String * 3
  filler02 As String * 9
  cen_tract_90 As String * 6
  cen_tract_00 As String * 6
  cen_blk_00 As String * 4
  filler04 As String * 51
  true_B7SC As String * 8
  seg_id As String * 7
  curve_flag As String * 1
End Type

'define variables
  Private vbwa1 As C_WA1
  Private fdwa1 As C_WA1
  Private vbwa21e As C_WA2_F1E

'define NYCgeo function
  Private Declare Sub wgF1E Lib "NYCgeo.dll" Alias "NYCgeo" (x As C_WA1, _y As C_WA2_F1E)
  Private Declare Sub wgFD Lib "NYCgeo.dll" Alias "NYCgeo" (x As C_WA1, _Optional y = Nothing)

'*****************************************************************************
```

```
Private Sub Call_wgF1E_Click()
  'setup work area 1
  'need better way to initialize wa1 to spaces
  vbwa1.input1.house_num = " "
  vbwa1.input1.house_num_sort = " "
  vbwa1.input1.lo_house_num = " "
  vbwa1.input1.lo_house_num_sort = " "
  vbwa1.input1.sti(1).boro = " "
  vbwa1.input1.sti(1).sc10 = " "
  vbwa1.input1.sti(1).Street_name = " "
  vbwa1.input1.platform_ind = "C"
  vbwa1.input1.func_code = "1E"
  vbwa1.input1.sti(1).boro = Form_Geodlg.txtboro
  vbwa1.input1.house_num = Form_Geodlg.txthousenumber
  vbwa1.input1.sti(1).Street_name = Form_Geodlg.txtstreetname

  'call geosupport
  wgF1E vbwa1, vbwa21e

  'check the return code and process output
  'this program assumes the existence of a form called Geodlg
  If vbwa1.output1.ret_code = "00" Or vbwa1.output1.ret_code = "01" Then
    Form_Geodlg.txtB10SC = vbwa1.output1.sto(1).boro + vbwa1.output1.sto(1).sc10
    Form_Geodlg.txtzipcode = vbwa21e.zip_code
    Form_Geodlg.txtlhns = vbwa21e.lo_house_num_sort
    Form_Geodlg.txtlb5sc = vbwa21e.lo_xsts.B5SC_low1(1)
    Form_Geodlg.txthhns = vbwa21e.hi_house_num_sort
    Form_Geodlg.txthb5sc = vbwa21e.hi_xsts.B5SC_high1(1)

    'func d call to convert house numbers in sort format to
    'setup work area 1
    fdwa1.input1.house_num = " "
    fdwa1.input1.house_num_sort = " "
    fdwa1.input1.lo_house_num = " "
    fdwa1.input1.lo_house_num_sort = " "
    fdwa1.input1.sti(1).boro = " "
    fdwa1.input1.sti(1).sc10 = " "
    fdwa1.input1.sti(1).Street_name = " "

    fdwa1.input1.platform_ind = "C"
    fdwa1.input1.func_code = "D "
    fdwa1.input1.sti(1).boro = vbwa1.output1.sto(1).boro
    fdwa1.input1.house_num_sort = vbwa21e.hi_house_num_sort
    fdwa1.input1.lo_house_num_sort = vbwa21e.lo_house_num_sort wgFD fdwa1
```

```
    If vbwa1.output1.ret_code = "00" Or vbwa1.output1.ret_code = "01" Then
      Form_Geodlg.txthhnd = fdwa1.output1.house_num
      Form_Geodlg.txtlhnd = fdwa1.output1.lo_house_num
    End If
    Else
      Form_Geodlg.txtGRC = vbwa1.output1.ret_code
      Form_Geodlg.txtmessage = vbwa1.output1.msg
      End If
End Sub
```

II.10 The Long Work-Area-2 Option

From time to time, GSS adds new output fields to a function's WA2. For example, in 2011, the WA2s of several functions were enhanced to include fields for the 2010 census tract and block. In general, when new output fields are added to a Geosupport work area, GSS utilizes existing filler space in the work area for those fields, if available. In that way, the basic layout of the work area remains the same, and existing users of that function who do not need to make use of the new items are not compelled to modify their applications.

If there is not enough filler space available in a function's WA2 to accommodate new fields, GSS introduces a 'long WA2 option' for that function, as described below. This approach enables new data items to be made available to applications that need them, without affecting existing applications that do not need them. The MSW functions that currently have the long WA2 option are Functions 1, 1E, 1A, BL and 3. The COW functions that currently have the long WA2 option are functions 1A and BL. The long WA2 option may be implemented for other functions in the future.

When issuing a two-work-area call to a function that has the long WA2 option, the application has the option to use either the 'regular WA2' (the work area layout that had already been in existence before the long WA2 option was introduced for that function), or the 'long WA2'. The application informs Geosupport that the long WA2 is being used by inserting an 'L' in a WA1 input field called the Long Work Area 2 Flag. When the long WA2 option is specified, it is the application's responsibility to pass a WA2 of the proper length to the Geosupport driver. If the application passes a blank in the Long WA2 Flag, the regular WA2 is used. Both the regular and long WA2s are documented in Appendix 2.

The MSW Function 3 exemplifies the role of the long WA2 option. MSW Function 3's regular WA2 is 200 bytes long, almost all of which was long ago allocated to specific fields, leaving little filler space available for new fields. At some point in the past, the necessity to add new fields for which no space was available in Function 3's regular WA2 impelled the introduction of the long WA2 option for Function 3. Function 3's long WA2 is 300 bytes long, and consists of the same 200 bytes of information that are returned in the regular WA2, followed by 100 additional bytes containing fields for several additional items that the regular WA2 was not designed to include, as well as ample filler space for future enhancements. Applications that existed prior to the

introduction of the long WA2 option for Function 3, and that have no need of any of the fields returned in the last 100 bytes of the long WA2, are able to continue running properly without modification using the regular WA2.

II.11 The Auxiliary Segment Option (COW Only)

Similar to the 'long WA2 option', the 'auxiliary segment option' is available for COW Functions 3 and 3C. This option adds an additional 500 bytes to the COW WA2 output. This option allows the user to request that, in the special case of a record that actually encompasses more than one segment, Geosupport will return the Segment IDs of all the segments (up to 70).

II.12 The Extended Work Area 2 Option- via Mode Switch(COW Only)

To accommodate additional information from Geosupport, an Extended version of Work Area 2 has been defined for various functions. Users may request the Extended Work Area 2 by setting the Mode Switch in Work Area 1 to 'X'. This option is available only for COW Functions.

Users have expressed a desire to receive **Street Names along with Street Codes** when making Geosupport calls. In previous versions of Geosupport, Street Names (of cross streets, etc.) were not a part of Work Area 2. Users may request an Extended Work Area 2 for Functions 1, 1E, 1A, 3, 3C, BL and BN. These Extended Work Areas contain street names in addition to Street Codes. Users will no longer have to make separate D, DG, or DN Geosupport calls (or use the Cross Street Names Flag) to get the street names. In addition, new data will be returned (e.g. CSCL data) in the Extended Work Area 2, and space is reserved for additional new data as it becomes available. Users who think they may want to use this new data in the future should consider modifying their applications to request the Extended Work Area 2s with the Mode Switch. The street codes and street names that are returned by Extended functions typically are the Principal Street Name and 7-Digit Street Code. This typically gives the user the best name for the location being requested.

Users may request an Extended Work Area 2 for Functions 1, 1E, 1A, 3, 3C, BL and BN. The Extended Work Area 2 contains Street Names in addition to Street Codes. New data (e.g. CSCL data) is also contained in the Extended Work Area 2, and space is reserved for additional data as it becomes available. Users who want to use this new data should consider modifying their applications to request the Extended Work Area 2s with the Mode Switch. The street codes and street names that are returned by Extended functions typically are the Principal Street Name and 7-Digit Street Code. This usually gives the user the best name for the location being requested. Some other data that may be included in the Extended Work Areas are: Health Center District, NTA Name (Neighborhood Tabulation Area Name), PUMA Code (Public Use Microdata Area Code) and X-Y coordinates of 'From' Node and 'To' Node..

The Mode Switch is a one-byte field, in column 330 of the COW Work Area 1. The only valid values for the Mode Switch are "X" for Extended, and blank. The Extended Mode cannot be requested when the Long-Work-Area 2 option is requested. The Extended Mode can, however, be

requested when the Auxiliary Segments are also requested. The Extended Work Area layouts for the various functions and options may be found in Appendix 13.

Note that when the Mode Switch is set to ‘X”, for Functions 1, 1E, 1A, 3, 3C, BL, and BN the functions may be referred to as Function 1 Extended, 1E Extended, 1A Extended, 3 Extended, 3C Extended, BL Extended, and BN Extended, respectively. The functions may also be referred to as 1X, 1EX, 1AX, 3X, 3CX, BLX, and BNX respectively.

The Mode Switch is supported by GBAT.

The COPYLIBs include new Work Area definitions for the Extended versions of WA2. In general, names of existing individual fields remain the same, except for the prefix, e.g. the prefix for COBOL Function 3 is PIWA2-FN3 and the prefix for COBOL Function 3 Extended is PIWA2-3X.

CHAPTER III

STREET NAME PROCESSING

III.1 Introduction

This chapter discusses Geosupport's street name processing in detail. (In this chapter, unless otherwise noted, the term 'street name' is used generically to encompass not only names of city streets, but also a wide variety of other New York City geographic feature names that Geosupport recognizes, including the names of some tunnels, bridges, rail lines, shorelines and geographic place names of various kinds.) The street name normalizing algorithm is briefly outlined. Two aspects of street name normalizing that are under user control, the selection of a street name normalization format and the Street Name Normalization Length Limit (SNL) parameter, are described. Other street name processing features that are described are partial street names, similar names, street name browsing, and selection of output street names for Character-Only Work Area calls . Certain non-street feature names, place names and 'pseudo-street names' that are recognized by Geosupport are also discussed in this chapter. The related topic of street codes is discussed in detail in Chapter IV.

It is important to note that New York City geographic names are meaningful only when the borough is identified, since features in different boroughs can have the same name. For example, all five boroughs have a street named BROADWAY. In general, the borough is identified via a borough code. For Functions 1, 1A, 1B, 1E and AP, the borough may also be identified via a ZIP code.

Applications pass up to three input streets to Geosupport in a single call, depending on the function being called. For most of the functions that accept street input, input streets are passed either in the form of street names or in the form of street codes. The exceptions are that Function 1N accepts street name input only, and the display functions, Functions D, DG and DN, accept street code input only.

Input streets are passed to Geosupport using as many as necessary of WA1's three input street name fields or its three input street code fields. Each WA1 input street name field is 32 bytes long. If there is more than one input street in a call, they must all be of the same type, either all names or all codes, not a combination of both types. If both street names and street codes are specified in WA1, for all functions other than D, DG, and DN, Geosupport processes the street names and ignores the street codes. For functions D, DG, and DN, the street names are ignored.

When street input is in the form of street names, before attempting to identify which New York City street an input name refers to, Geosupport attempts to 'normalize' the name by executing a systematic algorithm intended to produce a version of the name in a standardized format. If normalization is successful, Geosupport returns the normalized street name(s) to the user in as many as necessary of WA1's three output normalized street name fields. Geosupport's normalizing algorithm is designed so that users have considerable leeway in spelling input street names. For example, input names may contain commonly used abbreviations for words like avenue, street, boulevard, east, etc.

When Geosupport is able to normalize an input street name successfully, it uses the normalized name to read an internal Geosupport file in order to obtain the street code. Successful normalization followed by successful street code retrieval constitutes Geosupport System validation of the input street name, i.e. its identification or 'recognition' as the name of a specific New York City street. Note that successful normalization alone does not constitute validation of the input street name.

Geosupport's street name normalizing algorithm is highly customized for New York City. The algorithm is complex and a complete description of it is beyond the scope of this document. In any event, the algorithm is performed automatically, and users need to be aware primarily of two aspects that they can control. These are a parameter for controlling the maximum length of normalized street names, called the SNL; and a choice of two formats for normalizing street names, called the compact and sort formats. These features are described in detail in this chapter. For completeness of the discussion, and because some familiarity with the normalizing algorithm may aid the user in understanding possible causes of rejection, a summary description of the normalizing algorithm is also given in this chapter.

Function 1N. Function 1N can be used to normalize a street name and retrieve its street code, without having to specify a particular geographic location. Function 1N requires the input only of a borough code and a street name. The SNL parameter and the selection of a street name normalization format can be specified in a Function 1N call. Function 1N is called using Work Area 1 only.

III.2 Street Name Normalizing and the SNL Parameter

Street name normalizing is governed by a user-controllable parameter called the Street Name Normalization Length Limit (SNL), which sets an upper limit to the lengths of output normalized street names. The SNL feature is particularly useful in applications that have a restricted amount of space for the display of street names, such as when addresses must be visible through transparent envelope windows, or when a screen display or printed report line is crowded.

The user specifies an SNL value using the two-byte WA1 input SNL field. The permissible range of SNL values is 4 through 32, inclusive. The setting of an SNL value is optional. If the user specifies no SNL value, the default value of 32 is in effect for that call to Geosupport. Every call to Geosupport is an independent event, even within a single execution of a user program, so if an SNL value other than 32 is desired in a particular call, it must be explicitly specified in that call; Geosupport does not 'remember' an SNL value specified in a previous call.

Geosupport attempts to normalize each input street name in such a way that the result has a length in bytes that does not exceed the SNL value in effect. The SNL also governs the length of the normalized street name output returned by the display functions (Functions D, DG and DN). However, the SNL does not limit the lengths of input street names. Regardless of the SNL value, the maximum length of an input street name is 32 bytes, which is the length of the WA1 street name input fields.

The smaller the SNL value that the user specifies is, the more difficult it is for Geosupport to normalize input street names within that length limit, and therefore the greater the proportion of input street names that are likely to be rejected as not normalizable. Consequently, users who must limit the lengths of normalized street names should specify the largest possible SNL value that can satisfy the needs of their application. An SNL value of 32 (the default) insures that virtually all New York City street names can be normalized. It is recommended that in the design of new applications, 32 bytes be allocated for street name fields in files, programs, screens, reports and manual forms whenever possible.

The following is a simplified description of the street name normalizing algorithm:

- Parsing the input name: The normalizing algorithm logically separates the input name into 'words' delimited by blanks. Any sequences of consecutive blanks are consolidated to single blanks. If any numeric characters (the digits '0' through '9') and non-numeric characters are adjacent to each other, they are separated by the insertion of blanks. For example, W2PLACE becomes W 2 PLACE.
  To improve readability, normalization processing deletes any blanks that appear before and/or after a slash (/) or a dash (-) in a street name. The normalization process also does not generate any such blanks. In the case where there is a numeric before or after the slash or dash, the numeric is treated as alphabetic. For example, 'I - 25' becomes 'I-25' and ABC / DEF becomes ABC/DEF. See Chapter III.3 for a discussion of Street Name Sorting and how a numeric is normalized in a street name.

- Deleting ordinal suffixes: Numeric words in input street names are often expressed as ordinal numbers (integers formatted to specify order, consisting of numeric digits followed by ordinal suffixes, such as '1st', '2nd', '3rd', '4th'). The normalizing algorithm deletes the ordinal suffixes (the endings 'st', 'nd', 'rd' and 'th') from such words. For example, WEST 3RD STREET is converted to WEST 3 STREET. Note, however, that numeric words that are expressed alphabetically (such as WEST THIRD STREET) are not modified.

- Handling special characters: The normalizing algorithm deletes any periods (the character '.') at the ends of words. For example, ST. MARKS PLACE becomes ST MARKS PLACE. Any periods not at the ends of words are replaced by blanks, which will usually cause rejection. Special characters other than periods are left unaltered, and will cause rejection unless those special character(s) are specifically valid for the given street name. (Currently, the only special characters that appear in specific street names accepted by Geosupport are: ' (apostrophe), ((open parenthesis) and) (closed parenthesis), & (ampersand), / (forward slash) and – (dash or hyphen). . Currently, the only special characters that appear in specific street names accepted by Geosupport are: apostrophes, open and closed parentheses, ampersands, forward slashes, dashes and hyphens, viz, ' ( ) & / -. In general, if Geosupport accepts a street name with a special character, it will also accept that street name without the special character. For example, in Manhattan, both SAINT MARK'S PLACE and SAINT MARKS PLACE are accepted. In the Bronx, O'BRIEN AVENUE, OBRIEN AVENUE and O BRIEN AVENUE are all accepted. In Manhattan, BEN-GURION PLACE, BEN GURION PLACE and BENGURION PLACE are all accepted.

- Expanding and abbreviating standard words under SNL constraint: There are certain standard words that appear frequently in street names, either fully spelled out, such as EAST, AVENUE and BOULEVARD, or in the form of standard abbreviations, such as E, AV or AVE, and BL or BLVD, respectively. If the input name is shorter than the SNL value in effect, then to the extent permitted by that SNL value, the normalizing algorithm expands standard abbreviations to their full spellings. Conversely, if the input name is longer than the SNL value in effect, then the normalizing algorithm attempts to shorten the name to the extent required by that SNL value, by replacing fully spelled out standard words with standard abbreviations.

- Suppressing expansion in special cases: The normalizing algorithm recognizes certain special cases in which a character string normally treated as a standard abbreviation is not to be so treated, that is, is not to be expanded under any circumstances. For example, ST is expanded to STREET only when it occurs as the last word of the input name; this prevents the conversion, for example, of ST MARKS PLACE into STREET MARKS PLACE. Certain character strings that are treated as standard abbreviations in most street names are not so treated in specific street names; for example, the 'S' in the Brooklyn street name AVENUE S and in the Bronx street name S STREET is not expanded into SOUTH; the 'E' in the Manhattan street name ABRAHAM E KAZAN STREET is not expanded into EAST; the 'DR' in the Manhattan street name DR MARTIN L KING JR BOULEVARD is not expanded into DRIVE.

III.3 Street Name Sorting and Normalization Format Options

Many applications display addresses or other types of geographic locations in their reports and online screens, including normalized street names obtained from Geosupport. Applications often sort their data by geographic location for display. However, street names that contain numeric characters do not sort appropriately when they have been normalized in the 'conventional' fashion. To solve this problem, Geosupport is able, at the user's option, to normalize street names either into the conventional format, which is called the compact format, or into a format that is more suitable for sorting, called the sort format. The compact and sort formats differ only for street names that contain numeric characters. Such a street name contains, in the sort format, a number of 'alignment' blanks in front of the numeric digits in the street name, which serve to align the numeric digits for proper sorting. In the compact format, no alignment blanks are present. The presence or absence of the alignment blanks is the sole difference between a name that contains numeric characters normalized in the sort format and the same name normalized in the compact format. We illustrate by displaying, side by side, two sorted lists of a sample of Manhattan street names normalized in the two formats:

SORTED LIST IN COMPACT FORMAT	SORTED LIST IN SORT FORMAT
EAST HOUSTON STREET	5 AVENUE
EAST 10 STREET	EAST 1 STREET

EAST 102 STREET	EAST 2 STREET
EAST 129 STREET	EAST 3 STREET
EAST 13 STREET	EAST 9 STREET
EAST 167 STREET	EAST 10 STREET
EAST 2 STREET	EAST 13 STREET
EAST 20 STREET	EAST 20 STREET
EAST 201 STREET	EAST 79 STREET
EAST 3 STREET	EAST 102 STREET
EAST 79 STREET	EAST 129 STREET
EAST 9 STREET	EAST 167 STREET
FULTON STREET	EAST 201 STREET
10 AVENUE	EAST HOUSTON STREET
5 AVENUE	FULTON STREET

As this example illustrates, in the compact format, normalized street names do not sort appropriately. For example, EAST 10 STREET sorts in front of EAST 9 STREET, and 10 AVENUE sorts in front of 5 Avenue. In contrast, in the sort format, the presence of the alignment blanks causes street names containing numeric characters to sort appropriately. Notice that the presence of the alignment blanks in the sort format, and their absence in the compact format, causes a change to the sort order of numeric street names not only relative to each other, but also relative to non-numeric street names. For example, in the compact format, FULTON STREET sorts in front of street names that begin with a numeric character, such as 10 AVENUE, while in the sort format it sorts behind them. Similarly, in the compact format, EAST HOUSTON STREET sorts in front of the street names that start with the word EAST followed by a numeric word, while in the sort format, it sorts behind those street names.

Note that for purposes of this discussion, all samples of sort output assume the EBCDIC collating sequence.

The sort format should always be used for street names that are to be sorted. However, the sort format is not as well-suited for display purposes as the compact format, since the alignment blanks give the sort format an awkward appearance. In applications that must display data sorted by geographic location, sorting should be done using street names in the sort format, while street names should be displayed in the compact format. (This would, of course, necessitate the application making a second call to Geosupport for each name, to obtain the alternative format. Function 1N could be used for that purpose.)

The sort format is the default format. That is, Geosupport will normalize input street names into the sort format unless the user program specifically requests the compact format by placing a ‘C’ in the Street Name Normalization Format Flag field in WA1. Note that every Geosupport API call is an independent event: Geosupport does not ‘remember’ previous calls. Therefore, if repeated calls are

being made within a single execution of an application program, and the user wishes all the input street names to be normalized into the compact format, a ‘C’ must be present in the flag during each call.

We now give a precise description of the sort format. First, note that New York City street names have numeric characters (the digits ‘0’ through ‘9’) in at most one word. If a street name has such a ‘numeric word’, that word consists only of a one-, two- or three-digit number, possibly followed by an ordinal suffix. (If there is an ordinal suffix, it is deleted during normalizing in either format.)

For street names that do not have a numeric word, the compact and sort formats are identical. For a street name that does have a numeric word, the two formats differ only in the fact that alignment blanks are present in the sort format and absent in the compact format. In forming the sort format, the normalizer inserts the required number of alignment blanks in front of the numeric characters, to form a four-byte field within which the numeric characters are right-justified and blank-filled. (The rationale for using four bytes for the normalized numeric word is explained below.) Thus, when normalizing street names that have a numeric word into the sort format, the normalizer inserts three blanks in front of a one-digit number, two blanks in front of a two-digit number and one blank in front of a three-digit number. The inserted alignment blanks are additional to the single word-separating blank between the numeric word and the preceding word in the street name, if any.

We illustrate with an example, using the dash character to represent blanks for clarity. The street name EAST--129 STREET is in sort format. The first blank between EAST and 129 (represented by the leftmost dash) is the word-separating blank always present (in either format) between any two consecutive words. The second blank is the alignment blank inserted only in the sort format to right-justify the three-digit number ‘129’ within the four-byte field for the numeric word. EAST-129 STREET is the same street name in compact format; it has the single word-separating blank between the two words, but no blank inserted for alignment.

Actual Sort Format With 4-Byte Numeric Word Field	**Hypothetical Sort Format With 3-Byte Numeric Word Field**
EAST ---7 STREET	EAST --7 STREET
EAST --23 STREET	EAST -23 STREET
EAST -129 STREET	EAST HOUSTON STREET
EAST -203 STREET	EAST 129 STREET
EAST HOUSTON STREET	EAST 203 STREET

In this example, all of the street names are identical in their first five positions, with the fifth position being a word-separating blank. In the four-byte list, all the numeric names have a blank in the sixth position (the first position of the four-byte numeric field), and therefore have sorted ahead of the one non-numeric name, which has an ‘H’ in that position. In the three-byte list, the numeric names containing fewer than three digits have a blank in the sixth position, the non-numeric name has an ‘H’ there, and the numeric names containing three digits have a numeric character (a ‘1’ or a ‘2’) in the sixth position. Since the sort sequence of these characters is blank, ‘H’, ‘1’, ‘2’, the result of sorting with a three-byte numeric field is the undesirable separation of the numeric names by the non-numeric name.

III.4 Partial Street Names

It is a common informal practice to refer to streets using partial versions of ‘full’ street names. For example, the intersection of Nassau Street and Broad Street in Manhattan might be specified as the intersection of “"Nassau Street and Broad”. To accommodate this practice, Geosupport is designed to accept such partial street names as input street names whenever feasible. In this section, a precise definition and some examples of partial street names are given, and the circumstances under which Geosupport accepts a partial street name as an input street name are described.

A partial street name is a character string that is not itself a valid ‘full’ street name, and that is formed from a valid full street name by deleting one or more entire words from the end of the full street name. Note that, according to this definition, forming a partial street name involves the deletion of words only from the end of a full street name, not from the beginning or middle, and the deletion only of entire words, not portions of words. The following examples illustrate the definition.

- READE is a Manhattan partial street name for the valid Manhattan full street name READE STREET. READE STRE and READ are not partial street names, since they are formed by deleting portions of words rather than entire words.

- Both KATHARINE and KATHARINE HEPBURN are Manhattan partial street names for the valid Manhattan full street name KATHARINE HEPBURN PLACE, which exists on East 49 Street between Second Avenue and Third Avenue

- PARK AVENUE is not considered a Manhattan partial street name, because it is a valid Manhattan full street name in its own right, even though it can be formed by deleting the last word from a valid Manhattan full street name, PARK AVENUE SOUTH.

- PARK is a Manhattan partial street name that can be formed from several valid Manhattan full street names, including PARK AVENUE, PARK AVENUE SOUTH, PARK ROW and PARK PLACE

Geosupport accepts a partial street name as an input street name only if it unambiguously represents (i.e., if it can be formed only from) a single valid full street name in the specified input borough. If a partial street name can be formed from more than one full street name in the given borough, it is ambiguous and Geosupport rejects it. A partial street name cannot also be a front-truncated street name. Consider the following examples:

- Several valid Manhattan full street names begin with the word PARK, as noted above. Therefore PARK is an ambiguous partial street name, and Geosupport does not accept it as an input street name for Manhattan. Similarly, two valid Manhattan full street names begin with the word YORK, namely YORK AVENUE and YORK STREET. Therefore, YORK is an ambiguous partial street name, and Geosupport does not accept it as an input street name for Manhattan.

- There is only one Manhattan street name that begins with the word READE, namely READE STREET. Therefore, Geosupport accepts the partial street name READE as a Manhattan input street name unambiguously representing the Manhattan full street name READE STREET.

- Geosupport accepts both KATHARINE and KATHARINE HEPBURN as Manhattan input street names, since they are unambiguous partial street names for the Manhattan full street name KATHARINE HEPBURN PLACE.

- A partial street name cannot also be a front-truncated street name. For example, 65 STREET in Manhattan would seem to be a partial street name of 65 STREET TRANSVERSE, but it is also a front-truncated street name of EAST 65 STREET and WEST 65 STREET. Geosupport accepts 65 STREET as a front-truncated street name, but not as a partial street name. If 65 STREET is not successful as a front-truncated street name, 65 STREET TRANSVERSE will appear in the list of Similar Names, e.g. Function 1, 80 65 STREET in Manhattan.

- Some partial street names are accepted as input street names in some boroughs but not in others. For example, Geosupport accepts BROAD as an unambiguous partial street name for BROAD STREET in Manhattan and in Staten Island. However, in Queens, BROAD is rejected as an ambiguous partial street name, since it can be formed from a number of different valid full Queens street names, including BROAD STREET and BROAD CHANNEL. In the Bronx and Brooklyn, BROAD is not a partial street name at all, and is rejected accordingly, since in those boroughs there are no full street names that begin with the word BROAD.

Note: Since street names may be added or deleted with each Geosupport release, the acceptability of partial street names may also change.

Partial Street names and SNL: If a partial street name is accepted as an input street name, Geosupport returns the normalized version of the corresponding full street name in the WA1 output street name field, provided that the length of the normalized full street name does not exceed the SNL value that is in effect. If the length of the normalized full street name does exceed the SNL value in effect, Geosupport attempts to normalize the partial street name to fit within the SNL value; if that is successful, the normalized partial street name is returned in WA1. If neither the normalized full street name nor the normalized partial street name fits, Geosupport rejects the input as a street name that cannot be normalized within the SNL value in effect. If the SNL value in effect is 32 (the default value), it is certain that the normalized full street name will fit.

The following example illustrates the effect that varying the SNL value can have on street name normalizing. Suppose the input street name is CHAMBERS and the borough is specified as Manhattan. In this borough, CHAMBERS is accepted as an unambiguous partial street name for the full street name CHAMBERS STREET. If the SNL value in effect is 15 or greater, the output normalized street name is returned as CHAMBERS STREET. If the SNL is between 11 and 14 inclusive, the output street name is returned as CHAMBERS ST (the result of normalizing the full

street name CHAMBERS STREET with an SNL of 11, 12, 13, or 14). If the SNL is between 8 and 10 inclusive, the partial street name CHAMBERS is returned. If the SNL is smaller than 8, the input is rejected as a street name that cannot be normalized within the current SNL value.

Optimizing the choice of partial street names: In order to allow users to have partial street names accepted as much as possible, Geosupport will not consider roadbed street names when processing generic calls. Roadbed street names will be considered only when processing roadbed calls. As an example, if a user inputs 1830 'A C P' for a generic call in Manhattan, 'A C P' will be accepted as a partial street name for A C P Boulevard. However, if the user inputs a Roadbed Request, 'A C P' will not be recognized because of similar roadbed names.

In addition, since Non-Addressable Place Names (NAPs) and Addressable Place Names (APs) are not valid for Function 2, 3, 3C or 3S calls, Geosupport does not consider them when attempting to resolve an input partial street name; this too allows more partial street names to be recognized.

III.5 The Similar Names Feature

Geosupport has a 'similar names' feature that applications can utilize when handling Geosupport rejection of input street names. The feature consists of returning to the application a list of up to ten valid street names from the specified input borough that Geosupport deems to be 'similar' to the rejected input street name. Similar names are always full (not partial) street names, normalized in sort format. Applications can be designed to display the similar names whenever there are any, to aid the data entry operator in correcting rejected input names.

Whenever an input street name is rejected, if there is at least one valid full street name in the specified input borough that Geosupport deems to be similar to the rejected name, Geosupport takes the following actions:

- A list of the similar names, up to a maximum of ten, is returned in the List of Street Names field in WA1.
- The Geosupport Return Code value is 'EE'. The Reason Code value is a number from 1 to 9 or the letter 'A', indicating the number of similar names that are in the List of Street Names. (The value 'A' indicates that there are 10 similar names.)
- An appropriate message is returned in the WA1 Message field.
- The number of similar names that are in the list is returned in the WA1 field Number of Street Names in List.

If there is exactly one similar name, the message explicitly indicates that name. For example, if the input is the invalid Manhattan name DUFFEY SQUARE, there is a single similar name, DUFFY SQUARE. The message in this case would be:

'DUFFEY SQUARE' NOT RECOGNIZED. IS IT 'DUFFY SQUARE'?

If there is more than one similar name, then the message indicates the number of similar names but does not contain the similar names themselves. For example, the invalid Staten Island name ABBNER ROAD has three similar names. The message in this case would be:

'ABBNER ROAD' NOT RECOGNIZED. THERE ARE 003 SIMILAR NAMES.

To utilize the similar names feature, the user might program the application as follows.

- Whenever a call to Geosupport generates the GRC value 'EE', indicating rejection of an input street name and the existence of similar names, the application displays the Geosupport message (and/or the application's own message) and the similar names. (When there is exactly one similar name, the Geosupport message already contains the similar name.)

- The application then offers the data entry operator an opportunity to correct the input name, either by selecting one of the similar names (for example, by allowing the operator to use the cursor and the Enter key to make the selection) or by keying in a new name. If the operator has selected a similar name, the application moves it to the WA1 input street name field, overlaying the original input name, while leaving the rest of the WA1 input fields unmodified. The application then issues a second Geosupport call.

Designing the application to allow the operator to select a similar name from the list lessens the need for the operator to handle street name rejects by key-entering new street name spellings, thus increasing the operator's productivity and eliminating the possibility of new key-stroke errors.

<u>Applications should never be designed to replace a rejected input name with a Geosupport-provided similar name in an automatic fashion, even when there is exactly one similar name</u>. The similar names that Geosupport provides are merely possibilities for the intended input street name, and it may well be that none of them is the intended input street name. Human judgment should always be exercised when deciding whether to use a similar name.

To optimize the contents of the similar names list that is returned to the user's application, Geosupport takes the following steps:

- Geosupport only returns names that could be used in the specified function call. For example, since Non-Addressable Place Names, Addressable Place Names and Business Improvement Districts (BID) are not valid for Functions 2, 3, 3C and 3S, they will not be included in the similar names list for those functions.

- Also, roadbed street names are valid only when the Roadbed Request Switch is turned on. Roadbed street names will therefore not be included in the similar names list unless the Roadbed Request Switch is on. For example, in Brooklyn, if the input street name is 'OCEAN PARTKAY' and the Roadbed Request Switch is on, names such as OCEAN PARKWAY NORTHBOUND ROADBED will be included in the similar names list; however, if the Roadbed Request Switch is off, the roadbed street name will not be included.

- The similar names list will include only one spelling variation per locally valid street name (or 7-digit street code). For example, in Manhattan, if the input street name is 'ADAM', the similar names list will include only 'ADAM C POWELL BOULEVARD' and not the four other valid variations of that street name. The spelling variation selected is the first one encountered based upon sort sequence, which means it may or may not be the principal street name.

Although users need not be concerned with the criteria that Geosupport uses to generate similar names, the general criteria are listed here. A valid full street name is deemed 'similar' to an invalid input street name if it is in the specified input borough and any of the following conditions holds:

(A) The valid full street name is at least as long as the input street name, and the two names are identical for the length of the input street name.

For example, in Manhattan, the valid full street names YORK AVENUE and YORK STREET would be deemed similar to the invalid name YORK. (YORK is invalid because it is an ambiguous partial street name.)

or

(B) There are no valid full street names in the specified borough that satisfy criterion (A), and the input street name begins with a compass direction word (NORTH, SOUTH, EAST or WEST) followed by a blank, and the input street name and the given valid full street name are identical up to and including the first three bytes following that blank.

For example, in Manhattan, consider the invalid input name EAST HOUSTIN STREET, which is 12 bytes long. For this name, there are no valid full Manhattan street names that satisfy criterion (A). That is, there are no valid full Manhattan street names that are longer than 12 bytes such that the first 12 bytes consist of the character string EAST HOUSTIN STREET. However, this input name begins with a compass direction word, EAST, and there is a valid full street name, EAST HOUSTON STREET, that is identical to EAST HOUSTIN STREET through the third byte following the blank after the word EAST (i.e., they are identical in their first eight bytes, consisting of the string 'EAST HOU'). Therefore, by criterion (B), EAST HOUSTON STREET is deemed similar to EAST HOUSTIN STREET.

or

(C) There are no valid full street names in the specified borough that satisfy criterion (A) or criterion

(B), and at least the initial three bytes of the input street name and the given valid full street name are identical. The overall process is to keep looking for a match while dropping off characters from the end of the input street name. The streets must match on at least the first three bytes of the input street name to be considered a similar name for this criterion. The actual algorithm is somewhat complex and a complete description of it is beyond the scope of this document.

As an example, in Manhattan, if the input street name is BROADWAY TERRACH, then BROADWAY TERRACE will appear first in the list of similar names. Other street names beginning with BROADWAY will also appear in the list. Since BROADWAY TERRACE matches the most letters in the input street name, it appears first. The algorithm will typically insert the name with more matches at the beginning of the list.

As another example, in Staten Island, each of the valid street names ABBEY ROAD, ABBOTT STREET and ABBY PLACE will be deemed similar to ABBNER ROAD since they all begin with the same three bytes, namely, ABB.

or

(D) The input street name contains numeric characters, and the input street name is identical to the valid street name up to and including the first numeric word.

For example, in Manhattan, the valid street name 8 AVENUE is deemed similar to the invalid name 8 PLACE. In Brooklyn, the valid street names BRIGHTON 6 COURT and BRIGHTON 6 STREET are both deemed similar to the invalid name BRIGHTON 6 AVENUE.

or

(E) In the boroughs of the Bronx and Manhattan only, the input street name is a <u>front-truncated street name</u>. A front-truncated street name is one for which all of the following are true:

(E1) The input street name can be transformed into the valid street name by adding the word EAST or WEST to the front of the input street name.

(E2) The input street name has at least two words.

(E3) The first word of the input street name is not END, RIVER, SIDE, ST or STREET.

(E4) The last word of the input street name is not EXTENSION.

The set of criteria in (E) is designed to reflect the common practice to specify street names of Bronx and Manhattan streets that begin with the word EAST or WEST without that first word. These street names are referred to as front-truncated street names. For example, the intersection of Broadway and West 42 Street in Manhattan is often expressed informally as "the intersection of Broadway and 42 Street"; pursuant to criteria (E), Geosupport generates EAST 42 STREET and WEST 42 STREET as similar names for the invalid Manhattan street name 42 STREET. Similarly, EAST HOUSTON STREET and WEST HOUSTON STREET are generated as similar names for the invalid Manhattan street name HOUSTON STREET. Criteria (E2) through (E4) filter out certain special cases where it is not customary to drop the first word EAST or WEST. For example, Criterion (E2) prevents the invalid Bronx input street name AVENUE from generating as similar names the valid Bronx street names EAST AVENUE and WEST AVENUE; Criterion (E3) prevents the invalid Manhattan street names END AVENUE, RIVER DRIVE and SIDE HIGHWAY from generating as similar names EAST END AVENUE and WEST END AVENUE, EAST RIVER DRIVE, and WEST SIDE HIGHWAY, respectively.

Note that, if the input street name is the invalid Manhattan name 7 STREET, then 7 AVENUE and 7 AVENUE SOUTH are similar names by virtue of criterion (D), and EAST 7 STREET is a similar name by virtue of (E), but WEST 7 STREET is not a similar name, since it is not itself a valid Manhattan street name.

The similar names are returned in the List of Street Names sorted in alphabetical order, except that any front-truncated street names (i.e. similar names that satisfy criteria (E)) are listed first.

III.6 Unconventional Geographic Feature Names

In addition to conventional street names, Geosupport recognizes the following other types of geographic names: the names of 'paper streets'; the names of some non-street features; addressable and non-addressable place names; pseudo-street names; and intersection names. 'Recognizing' a name means that a street code has been assigned to that name and Geosupport accepts the name as valid input. The various types of unconventional names are discussed below, and there are further details on their processing in subsequent chapters.

Paper Streets

A paper street is a street that is legally 'mapped' (designated as a street on the official City Map) but that does not exist physically. The city 'maps' paper streets with the intention of constructing them, but there is no certainty that a particular paper street will be built. Indeed, some paper streets have been mapped and then eventually de-mapped without ever having been built.

Geosupport recognizes the names of paper streets, but it does not recognize geographic locations (addresses, intersections etc.) along a paper street. In addition to streets that are paper streets in their entirety, there are some streets that have both portions that exist physically and portions that exist

only ‘on paper’; for such a street, Geosupport recognizes geographic locations only within the portion that exists physically.

Non-Street Features

In the category of non-street features, as of this writing, Geosupport recognizes only the names of some railroad tracks and shorelines. Eventually, Geosupport will be enhanced to recognize the names of other non-street geographic features in New York City, including all railroad tracks and shorelines. Non-street features do not have addresses, but names of non-street features that are recognizable to Geosupport can serve as street name input to describe geographic locations other than addresses, such as intersections, street segments and street stretches.

Addressable Place Names

Addressable place names are the names of ‘places’, generally major individual buildings or building complexes, that can be combined with address numbers to form valid New York City addresses. Such places are not streets but their names serve the same role as do ordinary street names in forming addresses that Geosupport will recognize. An example in Manhattan that Geosupport recognizes is PENN PLAZA, a cluster of commercial buildings in the vicinity of Pennsylvania Station. For example, 1 PENN PLAZA, 2 PENN PLAZA and 7 PENN PLAZA are all valid Manhattan addresses, recognized by the U.S. Postal Service and by Geosupport’s address processing functions. Other examples of addressable place names recognized by Geosupport are: in Manhattan, NEW YORK PLAZA, WASHINGTON SQUARE VILLAGE, GOVERNORS ISLAND and CONFUCIUS PLAZA; in Brooklyn, ALBEE SQUARE, METROTECH and FORT HAMILTON MANOR.

Non-Addressable Place Names (NAPs)

Non-Addressable Place names (NAPs) are names of buildings or other geographic features that typically are not combined with an address number to form a valid address. See discussion of Support of Non-Addressable Place Names (NAPs) with Address Numbers below) Note that a building that has a NAP may or may not also have a conventional street address; it is the place name that is non-addressable, not necessarily the place itself. For example, the EMPIRE STATE BUILDING can be identified both by its name, which is a NAP, and by its conventional street address (i.e. 350 Fifth Avenue). CITY HALL in Manhattan and YANKEE STADIUM in the Bronx are examples of NAPs referring to buildings that do not have conventional street addresses.

Typical geographic features that have NAPs include named buildings, stadiums, arenas, hospitals, housing projects, military complexes, museums, universities, theaters, airports, parks, zoos, marinas and islands. Geographic features that have NAPs are classified as either simplexes, complexes or constituent entities of a complex.

- A simplex is a "stand-alone" named geographic feature, that is, a feature that has a NAP and is not a complex or a constituent entity of a complex. Examples in Manhattan: EMPIRE STATE BUILDING, CARNEGIE HALL, BRYANT PARK

- A complex is a group of related geographically identifiable features at one site. A geographically identifiable feature is a feature that has an address, a NAP and/or a Building Identification Number (BIN). (BINs are discussed in detail in Chapter VI.3.) Examples of Manhattan complexes: LINCOLN CENTER, JEFFERSON HOUSES, CITY COLLEGE.

- A constituent entity of a complex is a building or other geographically identifiable feature that is part of a complex. A constituent entity may be identified by a NAP or by a conventional street address. Examples in Manhattan: AVERY FISHER HALL (a constituent entity of LINCOLN CENTER identified by NAP); CITY COLL SHEPARD HALL (a constituent entity of CITY COLLEGE identified by NAP); 259 CONVENT AVE (a conventional street address which identifies CITY COLL SHEPARD HALL).

NAPs are accepted as input data by Function 1N and by the address-processing functions (Functions 1, 1A, 1B and 1E, but not Function AP.). *Currently, these functions accept a limited set of NAPs (including only some of the examples in this section). Additional NAPs are being added over time.* Support of NAPs that have address numbers is described below. For further details on NAPs, see Chapter IV.7.

Support of Non-Addressable Place Names (NAPs) with address numbers

Warning: Some users may need to modify their input NAP data to get expected results (see below).

There are some Non-Addressable Place Names (NAPs) in New York City that either actually have addresses associated with them – often in a location that differs from the NAP itself – or are commonly treated as addressable. An example in Manhattan is the NAP called '**Bryant Park**'. A building exists near Bryant Park with its own NAP of One Bryant Park which is often treated by users as if it had the address '**1 Bryant Park**'. Another example, in Brooklyn, is the NAP called '**Grand Army Plaza**'. A cooperative now exists near Grand Army Plaza, and its address is '**1 Grand Army Plaza**'. Geosupport supports as input the special case of a NAP that has an address number. (Releases of Geosupport prior to Version 13.2 ignored any address number that was entered as input with a NAP.)

In order to support this type of address (i.e. a NAP with an address number), Geosupport does not automatically ignore an address number that is submitted as input with a NAP. Geosupport ignores the input address number only if the address does not exist. In general, this does not affect the user's output since users typically do not enter an address number with a NAP. Note, however, if a user submits an address number (by accident or intentionally), the resulting output may be different from submitting the NAP without the address number, because, for example, '**1 Bryant Park**' will be recognized as a specific building, not as the park called '**Bryant Park**'. The results will be

identical to a NAP without an address number if the address number submitted does not exist. For example, '**34 Bryant Park**' does not exist; the address number (viz. '34') will be ignored in that situation and the information for '**Bryant Park**' will be returned. Geosupport issues a warning to users that the input address number is ignored.(Though this will not be apparent in GBAT if the option to treat warning messages as rejects is not selected).

Note to users who enter a 'dummy' address number with a NAP intentionally:
It may be necessary for these users to modify their input data. These users typically run applications that do not allow the data to have a blank address number, even for a NAP. The input is submitted with a 'dummy' address number. To ensure that Geosupport returns information about the NAP (and not a specific building that is now being supported), the users should ***use '9999' as the dummy address number***. In all probability, the '9999' address will not exist. When the '9999' address does not exist, Geosupport will ignore the '9999' and treat it as blanks. Geosupport will then give results as if the NAP was entered without the address number.

Pseudo-Street Names

Pseudo-street names are special 'invented' names that in certain circumstances Geosupport accepts as valid input street names, as described in Chapters V.2, VII.2 and VII.3. Three sets of pseudo-street names are:

> DEAD END and its aliases DEADEND, DEAD END STREET, CUL DE SAC and CULDESAC
>
> CITY LIMIT and its aliases CITY LIMITS and CITY LINE
>
> BEND and its alias BENDING POINT

DEAD END and BEND, and their aliases, are valid in all five boroughs. CITY LIMIT and its aliases are valid in all boroughs except Brooklyn. These pseudo-street names may not be used to specify addresses, but they may be used to specify street intersections, and to specify the cross streets (but not the 'on' street) in other types of street configurations.

Duplicate Address Pseudo-Street Names (DAPSs):

Another type of pseudo-street name that Geosupport recognizes, for certain addresses only, is Duplicate Address Pseudo-Street Names (DAPSs). DAPSs are used with Geosupport's duplicate address processing feature (discussed in detail in Chapter V.6). New York City has a small number of duplicate addresses, which are not data errors in Geosupport files, but are situations where an address is valid in reality at two different locations on the same street. DAPSs provide a means for a user to specify unambiguously a particular instance of a duplicate address. The user may also provide ZIP Code input to enable Geosupport to recognize which duplicate street name should be used.

An example of a street that has duplicate addresses is Hillside Avenue in Queens. A portion of Hillside Avenue in the Bellerose neighborhood has some of the same addresses as does another portion of Hillside Avenue in the Douglaston neighborhood. To make it possible to process these addresses, the DAPSs HILLSIDE AVENUE BELLEROSE and HILLSIDE AVENUE DOUGLASTON have been created. Similar DAPSs have been created for each city street that has duplicate addresses. In general, DAPSs are formed by augmenting the conventional name of the street with a neighborhood name.

An example of using ZIP Code input in a duplicate address situation follows. If 239-02 Hillside Avenue in Queens, with a ZIP Code set to 11426 is provided as input to Function 1, 1A, 1B, 1E or AP, Geosupport will determine that Hillside Avenue Bellerose should be used. If the ZIP Code provided had been 11363, Geosupport would determine that Hillside Avenue Douglaston should be used. This processing will occur even if the borough code has been provided as well.

Geosupport accepts DAPSs as valid input only for certain addresses on streets that have duplicate addresses, as explained in Chapter V.6.

If a DAPS is supplied as input to a Function 2, 3, 3C or 3S call, the associated neighborhood name (a.k.a. town name in Queens) will be stripped off to provide a valid street name for these calls. A warning message (Reason Code W) will be issued. For example, if the input to a Function 2 call is “Hillside Avenue Douglaston”, the word “Douglaston” will be removed and the street name “Hillside Avenue” will be used.

Intersection Names

Certain street intersections in New York City have intersection names which can serve as an alternative way to identify such locations in addition to the conventional means of reference using the names of two intersecting streets. For example, ISAAC STERN PLACE is an intersection name for the intersection of West 57 Street and 7 Avenue in Manhattan. On the other hand, TIMES SQUARE is not an intersection name, because it refers to an area encompassing several intersections rather than a single street intersection. Official intersection names are designated by the City Council, and informal intersection names develop over time through local customary usage.

Geosupport accepts the input of a limited set of intersection names. Intersection names may not be used to specify addresses (Functions 1, 1A, 1B, 1E, or AP), but they may be used to specify street intersections (Function 2), and to specify a cross street (but not the ‘on’ street) in other types of street configurations (Functions 3, 3C or 3S).

III.7 Street Name Browsing and Functions BB and BF

Functions BB ("browse backward") and BF ("browse forward") enable users to include interactive street name browsing functionality in their CICS applications. These functions may be used to assist data entry staff in determining valid spellings of street names that were rejected or the spelling of

which is unknown to the staff. Functions BB and BF are supported in both the CICS and batch environments and are called using one work area.

A sequence of repeated calls to Functions BB and/or BF will browse backwards and/or forwards in alphabetical order through a list of all the valid normalized street names in a given borough. Each call to one of these functions returns up to ten names in alphabetical order. A call returns fewer than ten names if there are fewer than ten names remaining in the given borough in the given browse direction. When fewer than ten names are returned, a warning is issued. The starting point of the browse is determined by the value of the input character string.

Both Function BB and Function BF process an input borough code and character string, which are passed in the WA1 input Borough Code 1 and Street Name 1 fields, respectively. The input character string can be from one to 32 bytes long.

In addition, when issuing a **COW** Function BB or BF call, a user may request that either all street names, only primary street names, or only principal street names be returned. The request is made via the **Browse Flag**. If this flag is set to **P**, then only primary street names are returned. If this flag is set to F, then only principal street names are returned. Any other value causes an error message to be generated. When the principal street names are requested, the primary street names will also be returned since all primary street names are also principal street names. For more information on Primary (P) and Principal (F) street names, please refer to Chapters IV.5 and IV.6.

The list of output normalized street names in alphabetical order is returned in the WA1 output field List of Street Names. The number of names returned is returned in packed decimal format in the MSW WA1 output field Number of Street Names in List. In COW WA1 output, the Number of Street Codes and Street Names in List is returned in character format.

The List of Street Names is a 320−byte WA1 output field containing ten 32−byte sub-fields or ‘slots’ for normalized street names. Let us call these sub-fields Namefield1 through Namefield10. (Do not confuse Namefield1 with the WA1 input street name field called Street Name 1.) Each output normalized street name is returned left-justified and blank-filled within its sub-field. When fewer than ten names are returned, the unused slots are left blank.

Function BF returns up to ten names for the given input borough, in alphabetical order, starting with the alphabetically first normalized name that is equal to or greater than the input character string. If the input string itself is a normalized name, it is returned in Namefield1, followed by the other returned names in Namefield2, Namefield3 etc., if any. Otherwise, the first name alphabetically greater than the input string for the given borough, if any, is returned in Namefield1, followed by the other returned names, if any.

Function BB works similarly but the list of up to ten names it returns ends with the alphabetically first name greater than or equal to the input string. Notice that, for a given input character string, there is an overlap of one name between the sets of names returned by Functions BB and BF.

If Function BB or BF returns ten names (in sub-fields Namefield1 through Namefield10) and the user wishes to continue the browse, additional browse function calls may be issued. For Function BF, prior to the subsequent call, the user primes the WA1 input field called Street Name 1 with the

street name that was returned in Namefield10. For Function BB, prior to the subsequent call, the user primes the WA1 input field called Street Name 1 with the street name that was returned in Namefield1.

III.8 Selection of Output Street Names (COW only)

For COW Function calls, the Browse Flag allows users to request the return of **primary** or **principal** output street names and street codes (for Functions 1, 1A, 1B, 1E, 1N, 2, 3, 3C and AP). The Browse Flag also allows users to request the return of **preferred** output street names and street codes (for Functions 1, 1A, 1B. 1E, 2, 3, 3C and AP).

Setting the Browse Flag to **P** will cause the output street name(s) and code(s) that are returned to the user to be the **primary** name of the input street names or codes.

Setting the flag to **F** will cause the **principal** name and street code of the input street name to be returned to the user.

For Functions 1, 1A, 1B, 1E, 2, 3, 3C and AP when the Geosupport call involves two work areas, the Browse Flag may also be set to **R**. Setting the flag to **R** will cause the **preferred** name and street code of the input street name to be returned to the user. For all of these functions except Functions 1E, the principal Department of City Planning (DCP) preferred street name and code will be returned in the output section of Work Area 1. For Function 1E, the principal Board of Elections (BOE) preferred street name and code will be returned to the user. If the user supplies a value of **R** for Function 1N, it is rejected with a GRC of 79. Preferred Street Names are described in more detail in Chapter IV.6.

Below is a sample where the Browse Flag causes Geosupport to return different street names.
The example is in Manhattan, in the portion of 7 AVENUE (north of Central Park) where ADAM C POWELL BOULEVARD is the Principal Street Name.
The input address is: 2019 A C POWELL BLVD

Function	**Browse**	**Output**
	Flag	Street Name
1 (or 1A or 1B)	Blank	A C POWELL BOULEVARD
1 (or 1A or 1B)	P	7 AVENUE
1 (or 1A or 1B)	F	ADAM CLAYTON POWELL JR BOULEVARD
1 (or 1A or 1B)	R	ADAM CLAYTON POWELL JR BOULEVARD
1E	BLANK	A C POWELL BOULEVARD
1E	P	7 AVENUE
1E	F	ADAM CLAYTON POWELL JR BOULEVARD
1E	R	7 AVENUE

Note that the Board of Elections (Function 1E) prefers a different street name from the Department of City Planning.

The Selection of Output Street Names feature is available only with the Character-Only Work Areas (COWs). For more information on Primary (P) and Principal (F) street names, please refer to Chapters IV.5 and IV.6.

CHAPTER IV

STREET CODES

IV.1 Introduction: Street Codes and Geographic Retrieval Consistency

This chapter discusses street codes, a set of numeric codes assigned in the Geosupport System to the city's street names and the names of certain non-street geographic features, place names, pseudo-street names and intersection names (see Chapter III.6). (In this chapter, except where otherwise stated, the terms 'street' and 'street name' refer to any geographic feature or feature name that has a Geosupport street code assigned to it.) Geosupport's street code feature provides critical support for many types of applications.

The primary purposes of the street code feature are:

• To enable applications to retrieve or match data from their own files by geographic location in a consistent manner: (See Chapter I.3 for a general discussion of the concept of geographic retrieval consistency.) Some streets have more than one name, and some street names have alternative spellings. Therefore, for applications that must retrieve data by types of geographic locations that are defined in terms of streets, such as addresses and intersections, the consistency of the retrieval is an important design consideration. For example, suppose a record is created in an application file for the Manhattan address 1204 SIXTH AVENUE. It is desirable that the application be able later to retrieve this record whether the user specifies the input address at retrieval time as 1204 SIXTH AVENUE, 1204 6 AVENUE or 1204 AVENUE OF THE AMERICAS. To achieve such consistency, Geosupport five-digit street codes rather than street names should be used in the retrieval key, as explained in this chapter.

• To obtain 'preferred' street names: For streets that have more than one name, the street name that is most appropriate to use for display purposes (such as on application screens, reports and mailing labels) may vary along the street. Street codes can be used to obtain location-specific 'preferred' street names for display, as explained in Chapter IV.6.

Secondary purposes of the street code feature are:

• To improve execution efficiency via street code input : There is an optional feature in which applications can pass input streets to Geosupport in the form of street codes rather than street names. This feature is useful when processing an application file that already contains street codes retained from a previous pass through Geosupport. The use of this feature can increase the execution efficiency of batch applications by sometimes allowing Geosupport to circumvent street name normalization and street code retrieval processing.

• To save application disk storage space: Storing street codes, instead of street names, in an application file saves application disk storage space. In many applications, however, doing so would necessitate increased programming and increased execution time overhead to make

additional Geosupport calls to obtain street names for display. Note, however, that with Extended Work Areas, many of the functions return both street codes and street names, thus additional programming is not needed.

The use of Geosupport street codes in an application does complicate the design and development of the application. It also adds a maintenance burden to the application, since street codes stored in an application file must be periodically resynchronized to reflect street code assignment changes effectuated in new Geosupport releases. In view of this overhead, the secondary purposes listed above are not likely by themselves to justify incorporating the use of street codes in an application.

IV.2 Street Name Relationships: Aliases and Locally Valid Street Names

GSS assigns street codes in a way that encodes certain information about street names. Specifically, a portion of the street code signifies whether an alias relationship exists between two street names; and a portion of the street code signifies whether a street name is only locally valid. These aspects of street code assignment can have implications for application design.

Two normalized street names are called aliases of each other if they are either alternative names of the same street (such as SIXTH AVENUE and AVENUE OF THE AMERICAS in Manhattan) or any portion thereof, or are spelling variants of the same street name (such as SIXTH AVENUE and 6 AVENUE, or MAC DOUGAL STREET, MACDOUGAL STREET and MCDOUGAL STREET).

Geosupport is designed to recognize all commonly accepted street name aliases, and through the structure of its street code assignments, to identify whether two street names are aliases for the same street.

Locally valid street names are street names that are only valid ‘locally’, that is, for a portion of a street. Almost all streets that have locally valid street names also have at least one name that is valid for the entire street. An example is Seventh Avenue in Manhattan, which has the following names:

• The names 7 AVENUE and SEVENTH AVENUE are valid for the entire street.

• POWELL BOULEVARD and various aliases (ADAM CLAYTON POWELL JR BOULEVARD, A C POWELL BOULEVARD etc.) are valid only for the portion of the street north of Central Park.

• FASHION AVENUE is valid only for a portion of the street in the Garment District.

• SAINT VINCENTS SQUARE and ST VINCENTS SQUARE are valid only for a small stretch of the street in the vicinity of the former Saint Vincent’s Hospital.

All of the above names are aliases of each other, since they are all names for the same street or a portion thereof. The names in the first set are valid for the entire length of the street; the other names are only valid locally. Notice that two street names can be considered aliases of each other

even if there are no locations at which both names are valid. For example, FASHION AVENUE and SAINT VINCENTS SQUARE are aliases, even though there is no location where both names are valid.

IV.3 Five-Digit and Ten-Digit Street Codes

To each normalized spelling of a full street name within a borough, a ten-digit number called the ten-digit street code (10SC) is assigned.Partial street names (see Chapter III.4) are assigned the same 10SC values as the full streets names from which they were generated.

A 10SC value is meaningful only within a borough, and is generally preceded by a borough code to form an eleven-digit item called the borough and ten-digit street code (B10SC).If two street names in different boroughs happen to have the same 10SC value, that does not signify any relationship between those streets. **Streets in two different boroughs are always considered to be different streets**, even if the two streets have the same name, and even if they form a single physically continuous street running across the borough boundary. For example, Atlantic Avenue crosses the Brooklyn-Queens border. Geosupport treats the Brooklyn and Queens portions of Atlantic Avenue as two different streets, each with its own B10SC value ('31343001010' and '42889001010', respectively).

The first five digits of the 10SC are called the five-digit street code (5SC). The 5SC has a fundamental significance: **the 5SC values of two street names in a borough are identical if and only if those names are aliases for the same street** . Positions six through ten of the 10SC are discussed in Chapter IV.5.

Like the 10SC, the 5SC is meaningful only when accompanied by a borough code; when concatenated, the borough code and 5SC form a six-byte item called the borough and five-digit street code (B5SC). The B5SC simply consists of the first six bytes of the B10SC. For MSWs only, Geosupport sometimes represents the B5SC as a four-byte packed decimal item, referred to as the packed borough and five-digit street code (PB5SC).

Conceptually, a B10SC value represents a particular (normalized) spelling of a particular name for a street within a borough, while a B5SC value represents the street itself and is shared by all the street's aliases. Consider the following examples of Manhattan street names, grouped by street, i.e. by five-digit street code. (Note: '1' is the borough code for Manhattan.)

(Normalized) Street Name	B10SC =	B +	5SC +	Remainder of 10SC
5 AVENUE	11041001010	1	10410	01010
FIFTH AVENUE	11041001010	1	10410	01020
MUSEUM MILE	11041001020	1	10410	02010
6 AVENUE	11051001010	1	10510	01010
SIXTH AVENUE	11051001040	1	10510	01040
AVENUE OF THE AMERICAS	11051001030	1	10510	01030
7 AVENUE	11061004010	1	10610	04010

SEVENTH AVENUE	11061004020	1	10610	04020
FASHION AVENUE	11061002010	1	10610	02010
POWELL BOULEVARD	11061001080	1	10610	01080
A C POWELL BOULEVARD	11061001010	1	10610	01010
7 AVENUE SOUTH	11071001010	1	10710	01010
SEVENTH AVENUE SOUTH	11071001020	1	10710	01020
EAST 21 STREET	11741001010	1	17410	01010
EAST 21	11741001010	1	17410	01010
WEST 21 STREET	13419001010	1	34190	01010
WEST 21	13419001010	1	34190	01010

The above example illustrates several aspects of street code assignment. Notice that alias names of the same street have the same B5SC value. Notice that EAST 21 STREET and WEST 21 STREET have different B5SC values, which amounts to treating them as names of two different streets (as indeed they must be treated, since they have address numbers in common). Similarly, 7 AVENUE and 7 AVENUE SOUTH are treated as two different streets. Notice that partial street names have the same B10SC's as the full names from which they were generated, such as EAST 21 and EAST 21 STREET.

By using B5SC's in the retrieval key instead of street names, applications can achieve consistent retrieval or matching of application data by types of locations involving streets. We outline below how an application might be designed for consistent retrieval or matching by address, which requires a retrieval key consisting of a B5SC and a normalized address number (discussed in Chapter V.2). When the type of location being retrieved involves more than one street, such as intersections, the key would be designed to contain a B5SC field for each street.

• At record creation time: During the initial creation of a record in the application file, the application calls Geosupport to obtain the B5SC corresponding to the input street name, as well as the normalized form of the input address number. The application uses these items to form a geographic retrieval key, which it stores in the new application record. Two files that contain such a key can be matched directly on the key, resulting in a match that will be consistent, i.e. independent of the use of street name aliases.

• At retrieval time: When retrieving data from the application file by address, the application again calls Geosupport, obtaining the B5SC and normalized address number corresponding to the input street name and address number. The application formats these items into a search key, and reads the application file using this key. The use of the B5SC in the key instead of the street name allows the retrieval to be consistent, i.e. independent of which alias for the street is passed as input.

Geosupport has three display functions, Functions D, DG and DN, which can be used to obtain street names for display in application screens, reports, mailing labels etc. These functions process five-, seven- and ten-digit street code input, respectively . (Note: seven-digit street codes are discussed in Chapter IV.5). Chapter IV.6 discusses the display functions.

IV.4 Resynchronization of Street Codes Stored in User Files

When designing an application in which street codes, either B5SCs or Bl0SCs, are stored in an application file, the user must consider the important issue of resynchronizing those street codes with respect to new Geosupport releases. This issue arises because it is sometimes necessary for the GSS staff to change the B5SC value (and therefore also the Bl0SC value) that is assigned to a street name. This would be necessary if they determine that two street names that currently have different B5SC values (signifying that they are names of two different streets) are in reality aliases for the same street and therefore must be made to have the same B5SC value. Conversely, the GSS staff might determine that two names that currently have the same B5SC value are actually names of two different streets, and therefore must be made to have different B5SC values. Both of these types of problems can be rectified only if the B5SC value, and therefore the B10SC value, assigned to one or more street names is changed.

Whenever a new Geosupport release is implemented that includes any changes to street codes assigned to street names, it is essential for users to make the corresponding changes to all occurrences of those street codes stored in application files. This street code 'resynchronization' should be timed to be as simultaneous as possible with the implementation of the new Geosupport release. User failure to resynchronize the street codes stored in an application file for each new Geosupport release could have serious negative consequences for the application. Geographic searches in the application file in which the street code is used as part of the retrieval key might fail to retrieve some application records or might retrieve inappropriate ones. Matching of records within an application file or between files by geographic location could fail, or could result in an erroneous match. Also, the display functions D, DG and DN could return inappropriate street names for some street code values.

Prior to the implementation of each new Geosupport release, a Street Name/Street Code Change Bulletin is sent to known Geosupport users[3] listing the street code changes being made in the new release. Also, as part of each release, a Geosupport file called the Street Code Change File (SCCF) is created and made accessible to users. If an application file contains B10SCs, the user can utilize the SCCF to develop an automated batch resynchronization procedure. Of course, when the stored B10SCs are updated, that also updates the B5SCs that comprise the first six bytes of the B10SCs. (If for some reason there is a separate B5SC field in the application file in addition to a B10SC field, the B5SC field must be overlaid with the new value using the first six bytes of the new B10SC value.) Resynchronizing stored B10SCs using the SCCF is the optimal resynchronization method. Users are strongly urged, when designing new applications in which street codes are to be stored in application files, to design those files so they contain B10SCs, either in addition to or instead of street names, and to write a batch street code resynchronization program that uses the SCCF.

In existing applications in which B10SCs are not currently stored in the application file, we recommend that the file be enhanced to contain B10SCs, enabling a resynchronization procedure that uses the SCCF to be developed. If the file currently contains street names, B10SCs can be inserted into it easily using Function 1N (discussed in Chapter III.2). If only B5SCs are currently stored in the file, not street names, a more difficult one-time effort would be required to insert

B10SCs into the file; the methodology for doing this would be similar to the resynchronization procedure using B5SCs described below. For application files that do not currently contain B10SCs and cannot be enhanced to contain them, the SCCF cannot be used to resynchronize the B5SCs, and other resynchronization methods must be used.

The various methods for resynchronization are discussed below.It is the user's responsibility to develop a street code resynchronization procedure for each application file in which street codes are stored, and to run that procedure as soon as possible after each new Geosupport release is placed into production.

Resynchronization procedure using B5SCs

When only B5SCs are stored in the application file, not the original input street names nor B10SCs, it is not possible to develop a fully automated procedure to resynchronize those B5SCs. Instead, records in the application file that are affected by street code changes (as listed in the Street Name/Street Code Change Bulletin) must be found and individually examined and updated. This is because of the inherent ambiguity of a B5SC value, which can be associated with more than one street name. Specifically, it is possible that two or more street names that had the same B5SC value prior to the new Geosupport release no longer have the same value in the new release. When this occurs, the user cannot resynchronize the old B5SC value mechanically, but must determine, for each occurrence of the old B5SC value in the application file, which street name that occurrence represents in order to determine what the new B5SC value should be for that occurrence. In order to make that determination, the user would have to individually research each record containing such a B5SC value, using any information that could help to pinpoint the location and thus to determine whether the B5SC value should be changed and what the new value should be. Such information as an address, cross streets, a ZIP code, a community district or other district identifier, or tax block and tax lot identifiers could be helpful for this purpose. Because this procedure is not automatic, it is the least desirable method.

Resynchronization procedure using street names

If the application file contains the original input street names in addition to B5SCs, then the user can develop a fully automated batch procedure for resynchronizing the B5SCs, albeit a less than optimal one, as follows. The user can write a batch program that calls Function 1N to obtain, for each original input street name, the B5SC value currently (in the new Geosupport release) assigned to that name. The program would process every record in the application file, automatically replacing the B5SC value already stored in each record with the current B5SC value obtained from Function 1N. The program would have to provide for handling any Function 1N rejects, that is, street names that are no longer valid in the new Geosupport release.

Resynchronization procedure using B10SCs

Using stored street names to resynchronize B5SCs is preferable to using just the B5SCs themselves, because the former method can be automated while the latter cannot. Nevertheless, the former method is highly inefficient, because it necessitates processing every record in the application file, even though in each Geosupport release only a tiny portion (if any) of the city's street names have street code assignment changes.

Storing B10SCs in the application file, and using the SCCF to resynchronize them, is the optimal approach to street code resynchronization. The ambiguity intrinsic to B5SCs does not exist for B10SCs. Since every B10SC value is assigned to a single street name only, stored B10SCs can be resynchronized by automatically replacing every occurrence of each changed B10SC value with the proper new value, with no research required to determine the latter.

GSS creates a new release of the SCCF as part of each new Geosupport release. The following DD statement gives users batch access to the SCCF:

//ANYDDNM DD DSN=A030.STREET.SCCF,DISP=SHR

The SCCF is a sequential file with 80-byte records. The SCCF has a single header record containing file identification information, followed by a set of data records. The layouts of the header and data records are as follows:

Street Code Change File (SCCF) Record Layouts

SCCF Header Record

Field	Size	Positions	Comments
Header constant	42	1 - 42	**Literal constant:** 'GEOSUPPORT SYSTEM FOREGROUND HEADER RECORD'
DDNAME of File	8	43 - 50	**Literal constant:** 'SCCF '
Geosupport Release Identifier	4	51 - 54	e.g. '15B **' (4th byte is generally blank) **
Date of File Creation	6	55 - 60	yymmdd format
Filler	20	61 - 80	

(The fields Borough Code and Street Name are in the SCCF records for informational purposes only and are not needed for synchronization.)

In an application file containing stored B10SCs, the first six bytes of the B10SC field (or fields, if the geographic location represented in the record involves more than one street, such as records for intersections) constitute the B5SC field, which could be defined as

SCCF Data Records

Field	Size	Positions
Old B10SC	11	1 - 11
Filler	5	12 - 16
New B10SC	11	17 - 27

part of a key for consistent geographic retrieval; therefore, a separate B5SC field would not be needed for that purpose. The full B10SC field could also itself be defined as a direct access key, for use by the resynchronization program.

Filler	5	28 - 32
Borough Code	1	33
Filler	1	34
Street Name	32	35 - 66
Filler	14	67 - 80

The resynchronization program would read the SCCF sequentially. For each SCCF record, the program would read the application file directly using the old B10SC value in the SCCF record as the search key. All occurrences of this B10SC value found in the application file would be replaced by the new B10SC value from the SCCF record. (Note: most application files contain multiple records for the same street. Hence, if the application file is a VSAM file, in most applications, the B10SC field(s) must be defined as an alternate key(s), not as the primary key, since several records could have the same key values. In addition, since the resynchronization program modifies a key value, the UPGRADE option should be specified in the DEFINE ALTERNATE INDEX component of the IDCAMS control file. Similar considerations might apply for other types of direct access files.)

Summary of Street Code Resynchronization

The resynchronization of street codes stored in an application file is an important issue for application design. If the application must retrieve records by geographic location, it is necessary to use B5SCs in the retrieval key in order to make the retrieval geographically consistent, and therefore B5SCs must be stored in the application file. Since the street codes that are assigned to some street names can be changed in new Geosupport releases, these stored B5SCs (and/or stored B10SCs, if any) must be synchronized to reflect these changes. However, as we have seen, the synchronization of B5SCs cannot be fully automated unless either the originally entered street names or the B10SCs corresponding to those names are stored in the record.

Resynchronization using street names is inefficient, since every street name in the application file would have to be processed. The best alternative to achieve resynchronization efficiency is to store B10SCs in the application file. In that case, the first six bytes of the B10SC field, which is the B5SC, could be defined as part of a geographic retrieval key. For resynchronization, the full B10SC could be used in conjunction with the Street Code Change File (SCCF). The user could develop a highly efficient procedure in which only those application records containing B10SC values that are in SCCF records, i.e., that have been changed in the new Geosupport release, would be accessed and updated.

In view of the above considerations, the following design guidelines are strongly recommended with respect to resynchronizing street codes stored in application files:

• When an application is being designed in which there will be a file to which consistent street-related geographic access is required, then the file should be designed to contain B10SCs obtained from Geosupport.

• Application programs that access the file geographically should be written to use the first six bytes of the B10SC field, which constitute the B5SC, in the geographic retrieval key. In existing application files that contain B5SCs but not B10SCs, the B5SC field should be enhanced into a B10SC field. The B5SC portion of the B10SC should continue to be used for geographic retrieval. The entire B10SC field should be defined as a direct access key, to support efficient automated street code resynchronization.

• The user should develop a batch procedure to resynchronize the B10SCs stored in the file, using the SCCF. An optimal procedure would access directly those records in the application file that contain B10SCs for which there are changes in the new Geosupport release (i.e., for which SCCF records exist). The user should run this procedure routinely whenever a new Geosupport release is implemented.

---

[3] To be added to this list, please send a request to GSS_Feedback.nyc.gov

IV.5 Seven-Digit Street Codes: Local Street Name Validity, Local Group Codes

This section discusses local street name validity, the phenomenon that some street names are valid for only a portion of the street. (In fact, there are even a few New York City streets that do not have a single street name that is valid for the street's full length.) A street that illustrates the phenomenon of local street name validity is Seventh Avenue in Manhattan. The names 7 AVENUE and SEVENTH AVENUE are valid for the full length of the street. The name ADAM C POWELL BOULEVARD and its various spelling variants (POWELL BOULEVARD, A C POWELL BOULEVARD etc.) are valid only for the portion of the street north of Central Park. The name FASHION AVENUE is valid in the Garment District. The names SAINT VINCENTS SQUARE and ST VINCENTS SQUARE are valid for a portion of the street in the vicinity of the former Saint Vincent's Hospital.

All of the Geosupport functions that accept street name input, except for Function 1N, perform local street name validation, which verifies whether the input street name is specifically valid for the input location, and if it is not valid, returns up to four aliases of the invalid name that are valid for the given location. Local street name validation is performed automatically when a two-work-area call is made, with no special user action required to invoke it.

If, in a two-work-area call, the input street name is not valid for the given input location, Geosupport takes the following actions:

• The call is rejected with a Geosupport Return Code of '50' and an appropriate Message.

• Up to four locally valid street name aliases of the invalid street name are returned in the WA1 List of Street Names field. (Specifically, the names that are returned are the principal street name of each local street name group that is valid for the given location. The concepts of 'principal street

name' and 'local street name group' are discussed below and in the next Chapter.)

• The Reason Code contains the number of names returned in the List of Street Names.

• For MSW: the WA1 Number of Street Names Field contains the number of names returned in the List of Street Names, in packed decimal format. For COW: the WA1 Number of Street Codes and Names Field contains the number of names returned in character decimal format.

For example, the address 375 7 AVENUE in Manhattan is located south of Central Park, so the street name ADAM C POWELL BOULEVARD is invalid for this address. Therefore, a two-work-area call to Function 1E (for example) with the input address as 375 ADAM C POWELL BOULEVARD would result in a GRC '50' rejection and the return of the locally valid alias street name 7 AVENUE in the List of Street Names. On the other hand, 2019 7 AVENUE is north of Central Park, so 2019 ADAM C POWELL BOULEVARD is a valid address, and is accepted by Function 1E. Similarly, a two-work-area call to Function 2 would reject the intersection of ADAM C POWELL BOULEVARD and WEST 56 STREET with a GRC of '50' and the return of the locally valid alias street name 7 AVENUE in the List of Street Names.

Local Group Codes (LGCs)

Local street name validity is reflected in the sixth and seventh digits of the 10SC, which constitute the Local Group Code (LGC). Street codes are assigned in such a way that two names for a street have the same LGC value if and only if those names are valid for the same portion (possibly all) of the street. Note that if two names are valid for overlapping portions of a street, or one is valid for a subset of the portion where the other is valid, then those names are in different local groups. In order to be in the same local group, names must be valid for exactly the same portion of the street.

Conceptually, the set of all street names for a given street can be viewed as being partitioned into subsets called 'local street name group' each group identified by its LGC value and consisting of all the names that are valid for a particular portion (possibly all) of the street. (Most New York City streets only have one local street name group.)

A LGC value is meaningful only relative to its B5SC value. The B5SC identifies the street, and the LGC identifies a local street name group for the given street, that is, the group of all names for the given street that are valid for a particular portion (possibly all) of the street. The B5SC concatenated with the LGC, that is, the first eight bytes of the B10SC, constitute the Borough and Seven-Digit Street Code (B7SC). Two street names have the same B7SC value if and only if they are names for the same street (same B5SC value) and are valid for the same portion of the street (same LGC value relative to the given B5SC value).

Street Name Codes (SNCs)

The final three digits of the B10SC are called the Street Name Code (SNC). Thus, the B10SC consists of the concatenation of the borough code, 5SC, LGC and SNC. The SNC serves simply to serialize the street names within a local group, so that the full B10SC is unique to a specific spelling

of a specific street name.

Consider the example of Seventh Avenue in Manhattan. The following is a list of many of Geosupport's normalized aliases for this street, sorted by B10SC. The dashed lines highlight the four local street name groups.

STREET NAME	B10SC =	BORO+	5SC +	5SC +	5SC +
A C POWELL BOULEVARD	11061001010	1	10610	01	010
AC POWELL BOULEVARD	11061001020	1	10610	01	020
ADAM C POWELL BOULEVARD	11061001030	1	10610	01	030
ADAM POWELL BOULEVARD	11061001040	1	10610	01	040
ADAM POWELL JR BOULEVARD	11061001050	1	10610	01	050
ACP BOULEVARD	11061001060	1	10610	01	060
A C P BOULEVARD	11061001070	1	10610	01	070
POWELL BOULEVARD	11061001080	1	10610	01	080
ADAM CLAYTON POWELL BOULEVARD	11061001090	1	10610	01	090
ADAM CLAYTON POWELL JR BOULEVARD	11061001100	1	10610	01	100
FASHION AVENUE	11061002010	1	10610	02	010
SAINT VINCENTS SQUARE	11061003010	1	10610	03	010
ST VINCENTS SQUARE	11061003020	1	10610	03	020
7 AVENUE	11061004010	1	10610	04	010
SEVENTH AVENUE	11061004020	1	10610	04	020

All of the names in the above list are aliases of each other, and therefore their B10SCs have the same B5SC value, '110610'. The first ten names in the list, A C POWELL BOULEVARD and its nine spelling variants, constitute the group of names valid only for the part of the street north of Central Park; this local group is identified by LGC value '01' and B7SC value '11061001'. The name FASHION AVENUE is valid only for the portion of the street in the Garment District, and constitutes the sole member of local group '02'. Local group '03' consists of the names SAINT VINCENTS SQUARE and ST VINCENTS SQUARE, which are valid only for a small portion of the street in the vicinity of the former Saint Vincent's hospital. Finally, the names 7 AVENUE and SEVENTH AVENUE are valid for the entire street and constitute local group '04'.

IV.6 Functions D, DG and DN; Primary, Principal and Preferred Street Names

This section discusses Functions D, DG and DN. These functions are referred to as the Geosupport 'display functions' because, although they do not actually display anything themselves, they return street names that applications can use to format geographic locations for display on reports, screens,

mailing labels, work orders for field work, etc. Functions D, DG and DN process input five-, seven- and ten-digit street codes (accompanied by borough codes), respectively. (The display functions can also be used to obtain address numbers in display format. This is discussed in Chapter V.2)

The selection of street names for display is a significant consideration for any street that has more than one local street name group. Given a specific location (i.e., an address, intersection, street segment or blockface) on a street, applications can use a simple procedure involving a call to Function DG to obtain a street name that is considered 'optimal' to display for that location, called the 'preferred street name'. Functions D and DN return street names that are of more specialized and limited use.

The display functions do not have a Work Area 2, and are accessed via one-work-area calls only. (If a second work area is mistakenly supplied, it is ignored.) Work Area 1 contains fields for the input street codes and for the output street names. The street names that the display functions return are full street names (never partial street names), normalized in accordance with the SNL and Street Name Normalization Format Flag values that are in effect for the given call.

Input Data

For the convenience of applications, each of the display functions can process up to three input street codes in a single call. If there are multiple input street codes, they are processed independently of each other and are not treated as though they were specifying a geographic location such as an intersection. (Similarly, if there is both an input street code and an input address number, they are not treated as though they were specifying an address.) In particular, a successful call to a display function does not imply the validation of the input data as a geographic location. Furthermore, the output street names returned by the display functions are not by themselves customized to be location-specific. Function DG must be used in conjunction with a call to another function to obtain a location-customized preferred street name.

For Function D, there are two different sets of fields in Work Area 1 that applications can use to pass input street code values, as follows.

• For MSW calls, if the input street codes are in the form of PB5SCs, the 4-byte input fields that are labeled PB5SC-1, PB5SC-2 and PB5SC-3 in the Work Area 1 layout in Appendix 2 are used.

• For MSW or COW calls, if the input street codes are in the form of B5SCs, the 11-byte input fields labeled B10SC-1, B10SC-2 and B10SC-3 are used. The input B5SC values, which are 6 bytes long, must be passed in these fields left-justified, and the contents of these fields beyond the first six bytes are ignored.

If an MSW application passes values to Function D in both sets of input street code fields (presumably inadvertently), the PB5SC fields are processed, and the B10SC fields are ignored.

For Function DG and DN, only the fields B10SC-1, B10SC-2 and B10SC-3 are used. In the case of Function DG, input 8-byte B7SC values must be passed in these fields left-justified, and the contents of these fields beyond the first eight bytes are ignored.

In a call to any of the display functions, Geosupport will process all three of the input street code fields, even if some of the fields are blank. If a street code field is blank, Geosupport will simply skip it and process the next field. For example. if B10SC-1 is blank, but B10SC-2 and B10SC-3 are not blank, they will be processed. The output street names will appear in the corresponding street names fields, viz. Street Name-2 and Street Name-3. Similarly, if B10SC-1 is not blank but B10SC-2 is blank, B10SC-3 will still be processed and the output street names will appear in Street Name-1 and Street Name-3. An error message is generated only if all the input street code fields are blank. Similar conditions hold for the PB5SC fields.

Output Data

The output street names that the display functions return are as follows:

• Function D is used to obtain, for an input B5SC value, or PB5SC value (MSW only), the primary street name for the given street. The primary street name is one alias, that is, one spelling of one street name, that GSS has designated, from among all the aliases for the street, as 'best' representing the street as a whole. (Note: The designation of primary street names has no 'official' status, and of necessity sometimes involves an element of arbitrariness.) The primary street name is not customized to be the 'best' name for any particular location along the street; it is simply the street name deemed most suitable to display if a single street name must be used to represent the entire street. Most applications do not require the services of Function D. However, some applications may, for example, have a requirement to display a consistent street name for all locations that are on the same street, so that it will be clear to users that all the displayed locations do refer to the same street. When possible, GSS designates as primary a street name that is valid for the entire length of the street. However, it is important to note that there are a few streets that do not have any such names. On such streets, there are locations where the street's primary street name is invalid. An example exists in Queens. 103 Street and William Clarke Place share the same B5SC viz.419690, and 103 Street is the primary street name. However, 700 William Clarke Place is a valid address and 700 103 Street is invalid because 103 Street is not valid at that location.

• Function DG is used to obtain, for an input B7SC value, the principal street name of the corresponding local street name group. This is a street name belonging to the given local street name group that GSS has designated as 'best' representing that group of street names, that is, the name that has been deemed to have the most 'standard' spelling. (As with primary street names, the designation of principal street names has no 'official' status, and of necessity sometimes involves an element of arbitrariness.) The most important use of Function DG is to retrieve preferred street names, as discussed below.

• Function DG is used to obtain, for an input B10SC value, the full street name spelling to which that B10SC value uniquely corresponds. Function DN is useful mainly in certain atypical applications that store ten-digit street codes in an application file, but do not store the input street names from which the street codes were originally obtained, and the application has a requirement (for legal purposes, for example) to display those originally-entered street names. Such applications can use Function DN to obtain the original name from the corresponding stored B10SC value

(although the name will be provided in normalized form.) Application designers can obviate the need to make Function DN calls by retaining in the application file either the original input street name or that name in normalized form.

The display functions return one output street name for each valid input street code. For each input street code that is invalid, the display functions return all question marks (the character '?') in the corresponding output street name field. In addition, if at least one input street code is invalid, the GRC value '64' is issued along with an appropriate Message.

Preferred Street Names

As explained above, the primary street name is not necessarily the 'best' name to use to express any particular location along a street. Furthermore, although each principal street name is the 'best' representative of its local group of street names, there may be more than one local group valid at a particular location.

COW applications can retrieve preferred street names easily. Given a specific address, street intersection, street segment or blockface along a street, COW applications can use Function 1, 1A, 1B, 2, 3 or 3C, respectively, with the Work Area 1 Browse Flag set to 'R' to obtain the DCP-preferred street name(s) specific to that location. For a description of the Browse Flag, see Section III.8 Selection of Output Street Names (COW only).

Note: In support of the unique requirements of the New York City Board of Elections' voter registration application, COW Function 1E with Browse Flag set to 'R' will return the BOE-preferred street. For most addresses, the DCP-preferred LGC and the BOE-preferred LGC are identical.

MSW application may also obtain preferred street names corresponding to the input. Given a specific address, street intersection, street segment or blockface along a street, MSW applications can use Function 1, 1A, 1B, 2, 3 or 3C, respectively, in conjunction with Function DG, to obtain the DCP preferred street name specific to that location, as follows:

1. Issue a two-work-area call to the appropriate location-processing function (Function 1, 2, 3 or 3C), to obtain an item called the 'DCP-preferred LGC', which all of these functions return in WA2. The DCP-preferred LGC represents the blockface-specific local street name group that GSS has designated from among those local groups that are valid for the given blockface as being the 'best' group of street names to display for that blockface. (Note: In support of unique requirements of the New York City Board of Elections' voter registration application, Function 1E returns an item called the BOE-preferred LGC in place of the DCP-preferred LGC. For most addresses, the DCP-preferred LGC and the BOE-preferred LGC are identical.)

2. Concatenate the DCP-preferred LGC to the B5SC to form a B7SC.

3. Call Function DG with the above B7SC as input to obtain the preferred street name. The principal street name of the DCP-preferred local group is the preferred street name for the given location.

For example, suppose the original user input address to an application is 2019 SEVENTH AVENUE in Manhattan. This address is within the portion of the street north of Central Park, where two local groups are valid: local group 1 (LGC = '01'), which consists of the name POWELL BOULEVARD and its spelling variants, and local group 4 (LGC = '04'), which consists of the names 7 AVENUE and SEVENTH AVENUE. GSS has designated local group 1 as the DCP-preferred LGC for the portion of the street north of Central Park, and has also designated ADAM C POWELL BOULEVARD as the principal name of this local group.

A COW application obtains the preferred street name for the address 2019 SEVENTH AVENUE in Manhattan by issuing a Function 1 call with the Work Area 1 Browse Flag set to 'R'. Geosupport returns the DCP-preferred street name, ADAM CLAYTON POWELL JR BOULEVARD. The associated B10SC, 11061001100, will also be returned. (Function 1E will return 7 AVENUE and 11061004010 correspondingly, since BOE chose 7 Avenue as the preferred street name.).

An MSW application can obtain the preferred street name for the address 2019 SEVENTH AVENUE in Manhattan, by performing the procedure outlined above, as follows:

• Function 1 is called with the input address 2019 SEVENTH AVENUE. Function 1 returns in WA1 the B10SC value of the input street name, SEVENTH AVENUE, namely, the value '11061004020'. The first six positions, '110610', constitute the street's B5SC value. Function 1 also returns, in WA2, the DCP-preferred LGC value for this address, which is '01'.

• The application concatenates the B5SC value with the DCP-preferred LGC value, forming the B7SC value '11061001'.

• The application calls Function DG using this B7SC value as input, obtaining ADAM C POWELL BOULEVARD as the preferred street name corresponding to the address 2019 SEVENTH AVENUE. The application may now display the address as 2019 ADAM C POWELL BOULEVARD.

In summary, the MSW application began with the address 2019 SEVENTH AVENUE, and by following the outlined procedure, in which first Function 1 and then Function DG was called, the application formed the 'preferred' address 2109 ADAM C POWELL BOULEVARD for display.

If either the COW or MSW application had started with the address 375 SEVENTH AVENUE, which is located south of Central Park, then either procedure would have resulted in the address 375 7 AVENUE, since 7 AVENUE is the principal name of the DCP-preferred local group for all locations on Seventh Avenue south of Central Park.

** Please note: ** There is a new switch defined in COW Work Area 1 that will allow a user to call Geosupport and get a new, extended Work Area 2 for various functions. Functions 1, 1E, 1A, 3, 3C, BL and BN have extended work areas. These extended Work Areas contain Street Names of cross

streets, etc. in addition to Street Codes. Users will rarely have to make separate D, DG, or DN calls (as explained above) to get the street names.

IV.7 Street Codes and Non-Addressable Place Names

This section discusses the manner in which street codes are assigned to Non-Addressable Place names (NAPs). Every NAP is a name of a simplex, a complex or a constituent entity of a complex (see Chapter III.6). By definition, every simplex and every complex has a NAP. A constituent entity of a complex may or may not have a NAP, and may or may not have one or more addresses. (A building that has neither an address nor a NAP is called a Non-Addressable Un-named Building (NAUB). NAUBs can be identified only by their Building Identification Numbers (BINs). NAUBs and BINs are discussed in detail in Chapter VI.)

Like conventional street names, some NAPs have aliases (alternative names and spelling variants). For example, CABRINI MEDICAL CENTER and CABRINI MED CENTER are spelling variants of the same name; AVERY FISHER HALL and PHILHARMONIC HALL are alternative names of the same geographic feature. As with conventional street names, the B10SC values assigned to NAP aliases have the same B5SC value.

In the case of a complex and its constituent entities, the assignment of street codes is analogous to the methodology used for streets. In general (the exceptional case is described below), the names of the entire complex and the names of its constituent entities are all treated as aliases of each other (that is, their B10SCs have the same B5SC value), since they are all names of the same geographic feature (the entire complex) or parts thereof (the constituent entities of the complex). Within the umbrella of this B5SC value, the NAPs that are valid for each portion of the complex, namely, either the entire complex or a particular constituent entity, are assigned to a different local group. Thus, the entire complex has its own distinct B7SC value, and each constituent entity has its own distinct B7SC value.

The following NAPs associated with Manhattan's Lincoln Center complex illustrate the assignment of street codes to NAPs associated with a complex.

NAP	B	10SC
LINCOLN CENTER	1	25006 01 010
LINCOLN CTR FOR THE PERFRMG ARTS	1	25006 01 030
NY STATE THEATER	1	25006 02 020
NEW YORK STATE THEATER	1	25006 02 040
N Y STATE THEATER	1	25006 02 060
AVERY FISHER HALL	1	25006 03 010
PHILHARMONIC HALL	1	25006 03 030

All of the NAPs associated with Lincoln Center (of which only a sample is listed above) have the same B5SC value, 125006. Within this B5SC value, the LGC value 01 is assigned to the NAPs of the complex as a whole, LINCOLN CENTER and LINCOLN CTR FOR THE PERFRMG ARTS

(and other variants not listed). The LGC value 02 is assigned to NY STATE THEATER and variants thereof, and so on. An application can use the B5SC value, 125006, as the retrieval key to retrieve all the records in an application file for the NAPs associated with Lincoln Center, both records for the complex as a whole and records for its constituent entities. If only the records for the complex as a whole are to be retrieved, the application would use the B7SC value 12500601. If only the records for the New York State Theater are to be retrieved, the application would use the B7SC value 12500602, and so on. (Note that none of these retrievals would retrieve any records stored by address, since the street name or addressable place name in an address would have a different B5SC value than the one assigned to the NAPs.)

IV.8 Street Code Input Feature

For most functions involving street input, applications have the option to pass the input streets to Geosupport in the form of either street names or street codes. The exceptions are Function 1N and the display functions. Function 1N requires input streets to be passed in the form of street names, since that function's sole purpose is to normalize input street names and provide their street codes. The display functions require input streets to be passed in the form of street codes, since those functions are designed to provide street names corresponding to input street codes.

The street code input feature is useful in an application that stores street codes but not street names in an application file (presumably to save disk storage space), since it enables the application to process records from that file directly through a Geosupport location-processing function, without first having to call a display function to obtain street names.

Applications can provide input street codes to any of the functions that can accept them in any of the following forms (the field names used below are the same as those used in the WA1 layouts in Appendix 2 for MSWs and Appendix 13 for COWs.):

- PB5SCs (MSW only), passed in as many as necessary of the WA1 input fields PB5SC-1, PB5SC-2 and PB5SC-3.
- B5SCs, passed left-justified and space-filled in as many as necessary of the WA1 input fields B10SC-1, B10SC-2 and B10SC-3.

• B7SCs, passed left-justified and space-filled in as many as necessary of the WA1 input fields B10SC-1, B10SC-2 and B10SC-3.

• B10SCs, passed in as many as necessary of the WA1 input fields B10SC-1, B10SC-2 and B10SC-3.

For functions that involve multiple input streets, the input streets specified in a call must all be in the same form, either all street names, or all PB5SCs (MSW only), or all B5SCs, or all B7SCs, or all B10SCs. Note that the first byte of all input street code fields is a borough code. When input streets are specified using street code input, the contents of the separate WA1 input borough code field (MSW only) is ignored.

Local street name validation (see Chapter IV.5) is not performed when the street input is in the form of five-digit street codes, but it is performed with seven-digit and ten-digit street code input.

Functions 1, 1A, 1B, 1E, and AP and Street Code Input

When a user supplies a borough and 5-digit street code as input to Functions 1, 1A, 1B and AP, Geosupport returns the DCP-preferred street name and its corresponding B10SC. For Function 1E, Geosupport returns the BOE-preferred street name and its corresponding B10SC. Primary street names are not returned, because primary street names do not always apply to the entire street stretch, and may produce an error when used as input for a subsequent call for that location. Preferred street names are also often the more widely used name and therefore a better choice.

The street names returned by Functions 1, 1A, 1B, AP and Function 1E are usually the same. An example where the street names are not the same is for Functions 1 and 1A calls for address numbers (e.g. 2019) on 7 Avenue in Manhattan north of West 110th Street. If the user supplies the B5SC of 110610, the street name ADAM C. POWELL BOULEVARD, the DCP-preferred name, will be returned. Since ADAM C. POWELL BOULEVARD is the street name most commonly used in this location, it is a better choice than the primary street name (7 AVENUE). However, Function 1E will return 7 AVENUE since this is the BOE-preferred street name.

The technique of returning the preferred street name instead of the primary street name helps to insure that if the street name is used as input to Geosupport with the address number, it will be a successful call.

NAPs and Street Code Input

With respect to a NAP of a simplex, as with conventional street input, the user has the option to specify the input datum either in the form of the name (in this case, the NAP) or its B5SC. However, five-digit street code input is prohibited for a NAP of a complex or a constituent entity of a complex (it is rejected with a GRC value of '07'); instead, 7-digit or 10-digit street code input (B7SC or B10SC) is accepted. The reason for this restriction is that different entities of the same complex may be located within different blockfaces, tax lots, census blocks, administrative or political districts etc., so that the B5SC may not be specific enough to enable Geosupport to determine the proper set of output data to return.

IV.9 Summary of Street Codes

This section recapitulates the discussion of street codes. A B5SC value represents a New York City street (or a pseudo-street, non-street feature, place name or intersection name) and is assigned to all of the street's aliases, that is, to all of the names by which that street, or any part of it, is known to Geosupport. Therefore, the B5SC is a suitable item to use as an access key for street-related geographic retrieval, since then retrieval will be consistent with respect to street name aliases. That is, retrieval will succeed regardless of which alias is used at the time of record creation and which is used at retrieval time.

A B10SC value represents a particular spelling of a particular name for a street (along with all of that name's partial street names, if any). Two B10SC values are identical in their first six bytes (the B5SC values) if and only if the street names to which those B10SC values correspond are aliases (names for the same street). Since B10SC values correspond uniquely to a single spelling of a single name for a street, they can be used to automatically resynchronize the B5SCs stored in an application file to reflect street code assignment changes made in new Geosupport releases. Such resynchronization is essential, and is the user's responsibility. A Street Name/Street Code Change Bulletin and a Geosupport file called the Street Code Change File (SCCF) are made available in each new Geosupport release to facilitate user-developed procedures for street code resynchronization. If an application file contains stored B10SCs, the SCCF can be used to develop a fully automated street code resynchronization procedure that directly accesses only those records in the application file containing B10SC values that must be updated, and that updates those B10SCs; this is the optimal resynchronization method. If street names and B5SCs are stored in the file, but not B10SCs, then the B5SCs can be resynchronized by using Function 1N and processing every record in the file. If only B5SCs are stored in the file, then the change bulletin must be used, and records containing B5SCs involved in changes must be individually researched.

Some streets in the city have certain names that are only locally valid, that is, valid only for a portion of the street. The set of all names for a given street is partitioned into 'local street name groups' corresponding to portions of the street where various street names are valid. Two names for a street are in the same local group if and only if they are valid for exactly the same portion of the street. Each local group is assigned a Local Group Code (LGC) value, which is a number from '01' to '99' that labels the group relative to all of the local groups for that street. The B5SC value and LGC value are concatenated to form the B7SC value, which is assigned to every name belonging to the corresponding local group, and only to those names. Each local group has a single member designated as the principal street name for that group. Each portion of a street has one local group designated as the preferred local group for that portion. The principal name of the preferred local group is called the preferred street name for that portion of the street. The preferred street name is obtainable for any specific location on a street. For example, for an address, the preferred street name is obtained by calling Function 1 to obtain both the B5SC and the preferred LGC, concatenating these to form a B7SC, and using the latter as input to a call to Function DG. For an intersection, street segment or blockface, Function 2, 3 or 3C is called, respectively, instead of Function 1.

The B5SC, B7SC and B10SC can be viewed as forming a hierarchy in which the greater the length of the item, the more the more restricted the set of street names represented. The B5SC represents all the names for the street. The B7SC represents all the names that are valid for a particular portion (possibly all) of the street. The B10SC represents a particular name (and any unambiguous partial street names generated from it).

The methodology that is used to assign street codes to the Non-addressable Place Names (NAPs) of a complex and its constituent entities is analogous to the methodology used with street names. The B5SC represents all the NAPs of both the complex as a whole and all of its constituent entities. A distinct B7SC represents all the NAPs that are valid for a particular portion (possibly all) of the

complex, that is, all the NAPs that are valid either for the complex as a whole or for a particular constituent entity. A distinct B10SC represents each individual normalized spelling of a specific NAP (and any unambiguous partial names generated from it).

For the reader's convenience, two reference tables summarizing street codes are below. Table IV-1 is a summary of the various street code items used by Geosupport, conventional abbreviations for them, and their lengths in bytes. The abbreviations listed in Table IV-1 are used throughout the remainder of the UPG. In these abbreviations, 'B' represents the standard Geosupport one-byte Borough Code, as described in Appendix 3, and 'P' means that the item is packed. (Note: Packed applies to MSW only.) Table IV-2 is a summary of the three main types of street code items, indicating the display function that accepts each as input, and what street name that display function returns as output. Table IV-2 is written to describe the assignment of street codes to street names, but it applies analogously as well to the NAPs of a complex and its constituent entities.

Table IV-1: Notation for Street Code Items

Item Abbreviation	Item Name	Length (Bytes)
5SC	Five-digit Street Code	5
P5SC (MSW only)	Packed Five−digit Street Code	3
B5SC	Borough and Five−digit Street Code	6
PB5SC (MSW only)	Packed Borough and Five−digit Street Code	4
7SC	Seven−digit Street Code	7
B7SC	Borough and Seven−digit Street Code	8
10SC	Ten−digit Street Code	10
B10SC	Borough and Ten−digit Street Code	11
LGC	Local Group Code (6th and 7th digits of 10SC)	2
SNC	Street Name Code (8th, 9th and 10th digits of 10SC)	3

5SC + LGC = 7SC
B5SC + LGC = B7SC
B5SC + LGC + SNC = B7SC + SNC = B10SC

Table IV-2: Summary of Street Code Items

Type of Street Code	Geography Represented	Corresponding Street Name(s)	Applicable Display Function and Its Output Datum
B5SC	A street for all or any portion of the given street	All names valid	D - returns primary name
B7SC	The portion (possibly all)	All the names in the given local	DG - returns principal name

B7SC	of a street where a group of names is valid	street name group	of local group
B10SC	The portion (possibly all) of a street where a specific name is valid	One spelling of one name (and any unambiguous partial names generated from it)	DN - returns the unique name to which the given B10SC corresponds

CHAPTER V

ADDRESS PROCESSING - FUNCTIONS 1, 1A, 1B, 1E, AP

V.1 Introduction

This chapter and the following two chapters discuss in detail the various types of geographic locations that Geosupport can accept as input, and the Geosupport functions that process them. This chapter, Chapter V, discusses addresses and Functions 1, 1A, 1B, 1E, and AP . Chapter VI discusses properties (tax lots) and buildings and Functions 1A (covering aspects not discussed in Chapter V), BL and BN. Chapter VII discusses 'street configurations' (geographic locations that are specified in terms of combinations of streets) and Functions 2, 3, 3C and 3S.

V.2 Address Numbers ('House' Numbers), Normalization and Formats: HNI, HNS and HND

Address numbers identify buildings, and are combined with street names and addressable place names (see Chapter III.6) or with street codes (as surrogates of street names or place names) to form addresses. Address numbers are commonly called 'house' numbers (although this term is a misnomer, since many addresses refer to buildings other than houses). To be consistent with common parlance and with other Geosupport documentation, the term 'house number' will be used instead of 'address number' in the remainder of this document, except in literal citations of Geosupport reject messages, since those messages use the term 'address number'.

Applications can pass a house number to any of the address-processing functions in character form, in the 12-byte WA1 input House Number field for MSW and the 16-byte WA1 input House Number field for COW. A house number passed in this manner need not be in any particular format, but could be a 'raw', un-formatted house number. Alternatively, house numbers can be passed in a 6-byte WA1 input field in a special Geosupport format called the House Number in Internal format (HNI), which presumes, the application will have obtained the HNI from a previous Geosupport call. HNIs are only used with MSW. A newer Geosupport format called House Number in Sort Format (HNS) is used for COWs.

When a house number is passed to Geosupport in the 12-byte WA1 for MSW or the 16-byte WA1 for COW input House Number field, Geosupport normalizes it. The house number normalization algorithm is complex, and a full description of it is beyond the scope of this document, but some aspects are discussed below. If normalization is successful, an output normalized house number is produced in two standard formats, the 12-byte or 16-byte output House Number in Display format (HND) and the 6-byte output House Number in Internal format (HNI) or the 11-byte House Number in Sort format (HNS), and both of these are returned to the application in WA1. The HND is in character form and is suitable for display, for example, on application screens, reports and mailing labels. While the HNS format contains character data, it is intended for Geosupport internal use. To conserve space, users may store this value in their files.

The HNI format contains packed decimal data, and is the format that Geosupport uses internally to perform its address-matching routines. The HNI is not documented in detail herein, and is of little direct relevance to most users. However, to conserve disk space in application files in which house numbers must be stored in some form, users can store the 6-byte HNI in their files rather than the 12-byte HND for MSW or the 11-byte HNS in their files rather than the 16-byte HND for COW, and then use any of the display functions, Functions D, DG and DN, to obtain the house number in HND format for display, as described below.

Processing of HNIs or HNSs by the Display Functions

The processing of an input HNI or HNS by a display function consists only of forming and outputting the HND. The successful processing of an input HNI or HNS by a display function implies that the HNI or HNS conforms to Geosupport's format requirements for HNIs or HNSs, but does not imply that the HNI or the HNS forms part of a valid address.

The display functions can process up to two input HNI or HNS values in a single call, using the two input HNI or HNS fields and two output HND fields in WA1. If two input HNIs or HNSs are supplied, they are processed independently of each other and are not treated as forming an address range. If only one input HNI or HNS is supplied, it may be passed in either of the input HNI or HNS fields.

The display functions return one output HND for each validly formatted input HNI or HNS. For each input HNI or HNS that is invalid, the display functions return all question marks (the character '?') in the corresponding output HND field. In addition, if at least one input HNI or HNS is invalid, the GRC value '13', Reason Code value '9' and corresponding Message are issued.

The display functions can also be used to obtain street names corresponding to input street codes. (The processing of street codes by the display functions is discussed in detail in Chapter IV.6.) In a single call, the display functions can process input HNIs or HNSs without input street codes, input street codes without HNIs or HNSs or both types of input. If both HNIs or HNSs and street codes are provided as input data to a display function call, they are processed independently of each other and are not treated as forming an address. In particular, the display functions perform no address validation.

HNIs or HNSs as Input to the Address-Processing Functions

The user has the option of providing input house numbers to the address-processing functions in the form of an HNI or HNS instead of a 'raw' unprocessed house number. This feature is useful for processing an application file that already contains house numbers in HNI or HNS format from a previous pass through Geosupport. The use of this feature slightly improves execution efficiency by allowing Geosupport to circumvent the house number normalization routine.

House Number Format Standards

'Raw' (un-normalized) input house numbers must conform to certain Geosupport standards, which are based on the characteristics of New York City's addresses. If an input house number does not satisfy these standards, Geosupport is unable to normalize it and rejects the call. The house number standards include the following, among others:

• Conformance to a set of allowable characters

• A limitation on the total length of the 'basic house number' (this term and the term 'house number suffix' are defined below)

• Limitations on the number of digits and maximum numeric values of the basic house number, if it does not contain a hyphen; or such limitations on the portions of the basic house number preceding and following the hyphen, if a hyphen is present

• Validity of the house number suffix (discussed below), if one is present

Every valid New York City house number conforms to the above standards.

The ability of Geosupport to normalize an input house number does not by itself signify that that house number, together with the input borough and street, form in combination a valid New York City address. Successful normalization signifies only that the input house number conforms to Geosupport's house number format criteria. Only the successful completion of a two-work-area call to one of the address-processing functions has significance with respect to the geographic validity of the input address. (See Chapter II.4 for a discussion of the distinction between the validations performed by one- and two-work-area calls.)

New York City house numbers consist of a 'basic house number', possibly followed by a 'house number suffix'. (Note: the basic house number and house number suffix are not to be confused with the digits to the left and right of the hyphen in a hyphenated house number. For example, in the Queens address '240-55 1/3 DEPEW AVENUE', '240-55' is the basic house number, and is hyphenated; '1/3' is the house number suffix.) A dash character may appear in the input house number field between the basic house number and the house number suffix, e.g. 22-GARAGE. Geosupport replaces the dash with a blank and processing continues. No message is generated for this situation.

Only a small percentage of New York City addresses have house number suffixes. The following are some examples of valid New York City addresses containing house number suffixes (highlighted in bold type):

```
519 Front  East 12th Street   (Manhattan)
625 Rear  Smith Street   (Brooklyn)
120 1/2  First Avenue   (Manhattan)
240-55 1/3  Depew Avenue   (Queens)
469 1/4  Father Capodanno Boulevard   (Staten Island)
470 A  West 43rd Street   (Manhattan)
171C  Auburn Avenue   (Staten Island)
20-29 Garage  120th Street   (Queens)
```

Input basic house numbers may contain a dash(the character '-'), which can serve either as a hyphen, as with most house numbers in Queens and some house numbers in other boroughs, or as a range separator.

• House Number Ranges: Addresses in New York City are often expressed in ranges, using a dash to separate the low and high house numbers of the range. For example, 22-28 Reade Street in Manhattan represents the range of even addresses consisting of 22 Reade Street, 24 Reade Street, 26 Reade Street and 28 Reade Street, all of which are valid individual addresses for the same building. In other words, in this example, the character string '22-28' is not an individual house number, but represents a range of house numbers, in which the dash serves as a range separator, and the number to the left of the dash, 22, as well as that to the right of the dash, 28, constitute by themselves valid individual house numbers for Reade Street.

• Hyphenated House Numbers: Consider the Queens address 22-28 36th Street. The house number portion of the address, 22-28, consists of the same character string as the above Reade Street example, but it has a very different meaning in the two cases. In the Reade Street case, 22-28 represents a range of even house numbers; in the 36th Street case, 22-28 is a single hyphenated house number, not a range of several unhyphenated house numbers. In a hyphenated house number, the digits to the left and to the right of the hyphen in combination form a single house number; the digits on one side of the hyphen are not by themselves geographically meaningful. For example, 22 36th Street and 28 36th Street are not valid Queens addresses. In addition, the position of the hyphen within a hyphenated house number is significant. For example, consider the addresses 13-103 41st Avenue and 131-03 41st Avenue. These are two distinct addresses on the same Queens street, even though the house numbers consist of the same sequence of digits and differ only in the position of the hyphen.

Geosupport's house number normalization algorithm interprets a dash encountered in an input house number either as a hyphen or as a range separation character, depending on the borough, the street (some streets do not conform to the norm for their borough with respect to house number hyphenation) and other criteria.

• When Geosupport interprets the dash as a range separation character: In normalizing the input house number, both the dash itself and the portion of the basic house number to the right of the dash are deleted. As one consequence of this, when the input to a two-work-area call is an address range, only the address formed from the house number to the left of the dash is validated; the house number to the right of the dash is ignored and no conclusion can be drawn about its validity from the success or failure of the call. For example, 22-28 Reade St in Manhattan is normalized as 22 READE STREET; the '28' is ignored during normalization, and is not validated as an individual house number in a two-work-area call.

• When Geosupport interprets the dash as a hyphen: In normalizing the input house number, the digits on both sides of the hyphen are retained, as is the hyphen itself.

If Geosupport determines that an input house number in character form has a missing or inappropriately present dash, then whenever it is feasible, Geosupport modifies the house number to correct the error before normalizing it. (Geosupport never modifies input HNIs or HNSs.)

Geosupport will make such a modification automatically (without user request), but only if the intended address is clear and unambiguous and is valid for the function being called, and a valid address could not be formed by normalizing the input house number in a different fashion. Two types of such dash-related modifications are as follows:

• When an input house number does not contain a dash, but Geosupport determines that the house number should be hyphenated: Geosupport inserts a hyphen, provided it can determine the proper position of the hyphen unambiguously so that a valid address results. For example, the input address 6603 Booth Street in Queens is normalized as 66-03 BOOTH STREET; the input address 63101 Alderton Street in Queens is normalized as 63-101 ALDERTON STREET.

• When an input house number contains a dash, but Geosupport determines that the presence of the dash is erroneous (i.e., the house number is invalid whether the dash is interpreted as a hyphen or as a range separator): Geosupport concatenates the digits to the left and right of the dash without retaining the dash itself, provided that this results in a valid address. For example, 10-22 38th Street in Brooklyn is normalized as 1022 38 STREET.

Whenever the house number normalizer makes an assumption about, or a dash-related modification to, an input house number, Geosupport informs the calling application by issuing a warning condition. A warning is issued, for example, when Geosupport assumes that an input dash is a range separator and then normalizes the house number by deleting the dash and digits following it, or when it assumes that a required hyphen is missing and inserts one.

When Geosupport is unable to normalize an input house number without making a dash-related modification so that a valid address results, and there is more than one type of dash-related modification that would result in a valid address, the input is considered ambiguous. For such a rejection, the Message would list the possible valid forms of the input address. This assists the user to determine how the input house number should be modified to make it valid. For example, consider the input 10-14 Lexington Avenue in Manhattan. Lexington Avenue has unhyphenated addresses only. There are two reasonable interpretations of the user's intended input in this example. These are 10 Lexington Avenue, which assumes the input is an address range, and 1014 Lexington Avenue, which assumes the dash is an inappropriately present hyphen. All of the address-processing functions consider both of these to be valid addresses. Initially, 10-14 Lexington Avenue in Manhattan was rejected as ambiguous, but, at user request, the first successful house number is accepted; i.e. 10 Lexington Avenue in Manhattan.

In the borough of Queens, the great majority of streets have hyphenated house numbers only; a few streets have unhyphenated house numbers only, and a few streets have 'mixed hyphenation'(i.e., both hyphenated and unhyphenated house numbers). In the other four boroughs, all but a few streets have unhyphenated house numbers only, a few streets have hyphenated house numbers only, and a few streets have mixed hyphenation. Riverside Drive in Manhattan is an example of a mixed-hyphenation street. A small stretch of Riverside Drive running north from West 156th Street has hyphenated even addresses ranging from 156-00 to 159- 34 (with some gaps). The remainder of Riverside Drive has unhyphenated addresses only.

Information on the address hyphenation status of each of the city's streets is maintained internally within Geosupport. The house number normalizer makes use of this information when analyzing an input house number that contains a dash character. Dash analysis is particularly complex for mixed-hyphenation streets, for which a dash could be either a hyphen or a range separator. For example, 156-158 Riverside Drive is a valid range of unhyphenated addresses assigned to a building located near West 88th Street, while 156-10 Riverside Drive is a valid single hyphenated address assigned to a building located near West 156th Street.

When there are more than 3 digits following the dash in an input address number on a street having unhyphenated or mixed hyphenated house numbers, Geosupport treats the dash as a range separation character and issues a warning message that the address number has been altered (GRC 01 / Reason 1). When this input occurs on a street having only hyphenated house numbers, the call is rejected and Geosupport issues an error message (GRC 13 / Reason 2).

V.3 Specifying Input Data to the Address-Processing Functions: NAPs, Parsed-Form Addresses, Free-Form Addresses and Unit Information

Functions 1, 1A, 1B, 1E and AP are Geosupport's address-processing functions. In general, they accept as input conventional street addresses, Addressable Place names, and certain Non-Addressable Place names (NAPs) (described in Chapter III.6 and further discussed in Chapter IV.7). Note, however, that Function AP does not accept Non-Addressable Place names as input.

- Addresses can be specified in parsed form, that is, with the house number and street specified in separate WA1 input fields. The street can be specified either as a street name or a street code. Non-street feature names, pseudo-street names and intersection names may not be used. There are two options for specifying an address in parsed form:
    - Parsed-form addresses using street name Specify a borough code (or ZIP code), street name and house number (using the WA1 input borough code (or ZIP code) and street name-1 field and either the MSW 12-byte or COW 16-byte WA1 input house number field or the MSW 6-byte WA1 input HNI field or the COW 11-byte HNS field).
    - Parsed-form addresses using street code: Specify a borough code (or ZIP code), street code and house number. The borough code and street code may be specified using any of the WA1 input combined borough code and street code fields (the B5SC, PB5SC, B7SC or B10SC) for MSW. For COW, there is only one borough code/street code field. The house number may be specified using either the MSW 12-byte or COW 16-byte WA1 input house number field or the MSW 6-byte WA1 input HNI field or the COW 11-byte HNS field.
- Alternatively, addresses can be specified in free-form, that is, with the house number specified together with the street name in the WA1 input Street Name field, as described below. Non-street feature names, pseudo-street names, intersection names and partial street

names (see Chapter III.4) may not be used. When addresses are specified in free-form, the input house number and HNI or HNS fields are not used.

- NAPs are specified in the same fashion as addresses, as described above, except that typically no house number is supplied. If a house number is supplied with a NAP, Geosupport typically ignores the house number and issues a warning. If the NAP is one that actually has house numbers associated with it, then if the address exists the house number will not be ignored. (See Chapter III.6 for more information.)

Free-form addresses are addresses in which the house number and street name are stored together in a single field, as they might appear in the address line of a mailing address. When an application passes all blanks in the WA1 input house number, HNI and HNS fields, and Geosupport determines that the WA1 input Street Name field does not contain a NAP, Geosupport assumes that the latter contains a free−form address, and attempts to parse the contents into a house number followed by a street name.

Since both house numbers and street names vary in length, and may be separated by a varying number of blanks, these items will not be in predictable positions within a free-form address. Therefore, when processing a free-form address, Geosupport must parse the contents of the input street name field to attempt to identify and logically separate the house number and the street name. If this is successful, the processing proceeds as with parsed-form address input. If an input free−form address contains any extraneous data following the house number and street name, such as an apartment number, neighborhood name, borough name or ZIP code, Geosupport attempts to recognize those data as extraneous information, in which case it ignores them, or in the case of COW function calls, Geosupport will also attempt to process the extraneous data as Unit input. (See Chapter V.15 for more discussion of the UNIT feature.)

Geosupport's processing of free-form addresses is complex and is not as reliable as that for parsed-form address input. It is strongly recommended that, whenever possible, applications be designed to pass input addresses to Geosupport in parsed form, that is, to pass input house numbers and input street names in separate fields.

In order to give users the ability to describe addresses in more detail, Geosupport now allows users to specify UNIT information, e.g. APT 5, on address-processing functions. This feature is described more fully in Chapter V.15.

V.4 Input Address Acceptance/Rejection and its Validation Significance

The address-processing functions differ significantly among themselves with respect to which input addresses they accept and reject, and with respect to the significance of the validation of an input address implied by acceptance or rejection. These distinctions are discussed below.

** Function 1.** Function 1 accepts an input address if and only if it falls within the administrative address range allocated to some blockface (described below). Thus, Function 1's acceptance of an input address does not by itself validate whether the input address is the actual address of a building, but only whether it falls within an administrative address range.

The administrative address range allocated to a blockface is the set of addresses that actually are, or potentially may be, assigned to buildings on that blockface. Administrative address ranges are allocated to blockfaces by the offices of the Borough Presidents. In many cases, the administrative address range allocated to a blockface is broader than its current 'actual' address range (i.e., the range encompassed by the lowest and highest actual addresses of existing buildings on the blockface). This reserves addresses for new buildings that might be built on that blockface in the future. (To 'shoehorn' new buildings between existing buildings, it is sometimes necessary to assign house numbers with suffixes like A, B, 1/2 and 1/3.)

In theory, an administrative address range encompasses all of the actual addresses of existing buildings on the blockface. However, there are discrepancies from this in reality for a relatively small number of blockfaces, as well as temporary discrepancies caused by Geosupport data errors.

An administrative address range may also encompass nonexistent addresses, either between the low and high actual addresses of the blockface or beyond them. For example, consider the blockface on the east side of East 28 Street between Avenues I and J in Brooklyn. The administrative address range allocated to this blockface is 901-999. Function 1 would accept any odd address between 901 and 999 on E 28 Street in Brooklyn as input, whether or not that input address is a valid address of an existing building. In reality, the lowest and highest actual house numbers of existing buildings on this blockface (as of the writing of this document) are 901 and 985, and within this range there are gaps in actual addresses. For example, there are buildings on East 28 Street with the house numbers 925 and 929, but there is not currently a building with the house number 927, nor are there buildings with any of the odd house numbers from 987 through 999. Nevertheless, all of these house numbers will result in successful Function 1 calls, since they all fall within the administrative address range.

Function 1E

With the exception of a rare case discussed below, Functions 1 and 1E accept the same addresses and reject the same addresses, and the validation significance of acceptance and rejection is the same for both functions.

The exceptional case is that of an address that is split among more than one Election District (ED). As of this writing, there is only one instance of this case, 3333 Broadway in Manhattan; it is split among three EDs. Therefore, for this address, Function 1E is unable to determine an ED (or any of the higher-level political districts). Since the primary purpose of Function 1E is to provide the political geography for an address, Function 1E rejects this address with a GRC value of '56'. However, portions of this building in specific EDs can be identified using house number suffixes, 'A' through 'E': 3333A through 3333C Broadway are in ED 94 of Assembly District (AD) 70;

3333D Broadway is in ED 82 of AD 70; and 3333E Broadway is in ED 83 of AD 70. Function 1E accepts these addresses as input, and returns the political districts specific to the input. Functions 1 and 1A accept both the un-suffixed and suffixed addresses.

Function 1A

Function 1A accepts an input address if and only if the address falls within one of the following two cases:

- Valid actual address. If the input address is a valid address of an existing building on a property, there is a normal completion (Geosupport Return Code = '00').
- Pseudo-address. If the input address is a 'pseudo-address' , a warning is issued (GRC = '01', Reason Code = '8' or '9'). Pseudo-addresses (not to be confused with pseudo-street names) are discussed in Chapter VI.5.

If the input address is neither a valid address of an existing building nor a pseudo-address, Function 1A rejects that input address. This is true even if the input address falls within an administrative address range allocated to a blockface and is therefore accepted by Functions 1 and 1E. Thus, Function 1A's criterion for accepting an input address is typically more stringent than those of Functions 1 and 1E, and the validation significance of acceptance differs accordingly.

Function AP

Function AP accepts an input address if and only if the address falls within the following case:

- Valid actual address. If the input address is a valid address of an existing building on a property, there is a normal completion (Geosupport Return Code = '00').

Function AP's criterion is very similar to Function 1A's. If the input address is not a valid address of an existing building, Function AP rejects that input address. This is true even if the input address falls within an administrative address range allocated to a blockface and is therefore accepted by Functions 1 and 1E. Thus, Function AP's criterion for accepting an input address is typically more stringent than those of Functions 1 and 1E, and the validation significance of acceptance differs accordingly.

Function 1B Input Address Processing and Return Code Processing

Function 1B makes an internal combined call to Extended Function 1A and Extended Function 1E (see descriptions of 1E and 1A above). Extended Functions 1A and 1E return more information than the regular Functions 1A and 1E. This is described in Chapter V.5 (Output Data Returned) below.

Function 1B invokes Function 1A Extended processing first. If the input address number is altered by the Function 1A Extended processing (e.g. deleting a hyphen) the altered version of the address number is passed as input to the Function 1E Extended processing.

Also, since Function 1A is more stringent than Function 1E, it is possible that the address will be rejected by the Function 1A portion of 1B and then successfully processed by the Function 1E portion of 1B. There can be rare cases where the input address is processed successfully by the Function 1A portion and rejected by the Function 1E portion. In Work Area 1, there are two sets of GRC, Reason Code and Message fields to accommodate the Function 1E and Function 1A processing included in Function 1B.

The original set of GRC, Reason Code and Message fields in Work Area 1 contain the GRC, Reason Code and Message from the Function 1E Extended portion of the Function 1B call. This second set contains the GRC, Reason Code and Message for the Function 1A Extended portion of the Function 1B call. (As described above, it is entirely possible that Geosupport will find one set of information and not find the other. There can be an error code and message in the new GRC and Message fields indicating property data (Function 1A) has not been found, and a 00 or 01 GRC in the original Return Code field indicating Blockface (Function 1E) information has been found, or just the opposite.)

V.5 Output Data Returned in Work Area 2 of Address Processing Functions

The address-processing functions differ significantly with respect to the output data they return.

Function 1

Function 1, when called using two work areas, performs blockface-level processing. Almost all of the items that Function 1 returns in WA2 are associated with the entire blockface, and do not vary with the specific input address within that blockface. Among these items is a set of geographic district identifiers, such as Census Tract and Block, Police Precinct and Community District.

One piece of information returned by Function 1 that does vary with the specific input address is a pair of spatial coordinates. This identifies the approximate location of the given address on the earth's surface.

School District (SD) boundaries split some blockfaces, and in those cases, Function 1 returns the SD value that is appropriate for the specific input address. However, the high and low house numbers returned in WA2 always correspond to the entire blockface, not to the portion of the blockface within the given SD. When the blockface is split by a SD boundary, no indication is provided that the blockface is split.

An example of a blockface that is split by a SD boundary is the odd-address side of FARRAGUT ROAD in Brooklyn between EAST 105 STREET and EAST 108 STREET. The address range for the entire blockface is 10501 to 10799. The subrange from 10501 to 10599 is in SD 18; and the

subrange from 10601 to 10799 is in SD 19. If the input to a Function 1 call is 10559 FARRAGUT ROAD, '18' is returned in the WA2 SD field, but 10501 and 10799 are returned as the address range for the blockface. If the input to a Function 1 call is 10611 FARRAGUT ROAD, '19' is returned in the WA2 SD field, but, again, 10501 and 10799 are returned as the address range for the blockface.

The information that regular Function 1 returns in WA2 also includes two lists of street codes for the cross streets at both ends of the blockface. These cross street codes are B5SCs thus reflecting the primary street names. The Extended WA2 (MODE=X) also returns B7SC lists of cross streets and their street names thus reflecting the principal street names. Applications can use these cross streets to identify address-based data to blockfaces or street segments. In many applications, the consolidation of data for individual locations to the level of the blockface or street segment can significantly improve the efficiency of a municipal operation. The conversion of address-based data to segment-based data is further discussed in Chapter VII.3.

If a COW application has a need to display the street names of the cross streets,aside from calling Function D or DG, the user can employ one of the following options:

a. The Mode Switch in WA1 can be set to 'X' and the Extended function will return cross street codes as B7SCs and their corresponding principal street names in the extended portion of WA2. This is done with no processing overhead. This can be helpful to the user since the Primary Name is not always the best name for a particular cross street. See description of Extended Mode in Chapter II.7)

b. The Cross Street Names Flag in WA1 can be set to 'E' and the cross street names will be returned in the List of Street Names in WA1 (see entries for Cross Street Names Flag and List of Street Names in Appendix 3). The Cross Street Names will be the primary street names since they are based on B5SCs. Note that the cross street names feature incurs processing overhead, and should only be used when necessary,. It is recommended that the Extended Mode option, mentioned above, be used.

** NOTE: There is no longer a need to set the Cross Street Names Flag to "E" when using Function 1 and 1E with Mode Switch of "X", since the Cross Street Names are in the Extended part of the work area, ** although this will not create an error if the Cross Street Names flag is set to "E". However, the Street Names returned in Work Area 1 with the Cross Street Name flag are based on the B5SCs and not the updated B7SCs.

Function 1 and 1E Extended Work Areas - MODE=X (COW Only)

In the Extended Function 1 and 1E work area 2, the BOE Preferred LGC and associated street name will be returned in new fields that are defined in the "Extended" portion of Work Area 2.

The Extended Function 1 and 1E work area 2 includes additional fields such as USPS Preferred City Name, Latitude and Longitude, Neighborhood Tabulation Area (NTA) Name, PUMA Code, Bike Lane 2, Bike Traffic Direction, Street Width, Street Width Maximum, Speed Limit, etc. For a complete list, see the Work Area layout in Appendix 13.

** Underlying Street Name or Street Address **

For NAPs and Addressable Place Names, the underlying street name or street address is returned as part of a warning message (reason code V). The street code of the underlying true street is not included in the list of cross streets. For example, Fifth Avenue is an underlying street of the Empire State Building; it will not be included in the list of cross streets for the Empire State Building. Information on the underlying true street appears in COW WA2 and MSW Long WA2.

** Additional data in COW regular WA2 and in long WA2 for MSW Functions 1 and 1E **

The long WA2 option is available for the MSW Functions 1 and 1E. Since all the additional data in the long WA2 for MSW Functions 1 and 1E are included in the regular WA2 for COW Functions 1 and 1E, there is no long WA2 option for COW. (There are extended work areas for COW Function 1/1E which are discussed below.) The additional data in COW regular WA2 and long MSW WA2 includes the following:

- Segment ID
- Borough and 7-digit street code for the underlying true street of a NAP or Addressable Place Name
- Underlying house number
- 2000 Census tract, block, and block suffix. (The 2010 fields are in the regular portion of the work area.)
- (COW only) Hurricane Evacuation Zone
- (COW Only) Organics Recycling Schedule
- (COW Only) Bulk Items Pickup Schedule

Functions 1, 1B, and 1E allow a user to receive roadbed-specific information in place of information based upon the generic center line of a multi-roadbed street. A user requests roadbed-specific information via the 'Roadbed Request Switch'. This means that a Function 1, 1B, or 1E call with this switch set will return the roadbed-specific geocodes, assuming that the input street has multiple roadbeds. Examples of geocodes that would be different include Segment ID, Segment Type Code, X-Y coordinates, LION Key and possibly cross streets and Census Tracts / Blocks. An additional file has been added to the Geosupport system to handle this data. Users who prefer non-roadbed-specific information, which assumes a single roadbed for all roads, are not required to make any changes.

Function 1E

Function 1E, when called using two work areas, returns all of the WA2 data items that Function 1 returns. In addition, Function 1E returns the following political district identifiers in WA2: Election District, State Assembly and Senate Districts, City Council District, Congressional District and Municipal Court District.

Function 1E handles cases where a School District boundary splits a blockface in the same manner as Function 1 does. In addition, Election District boundaries can also split blockfaces, and Function 1E handles those cases similarly. This includes the special case of the addresses 3333A through

3333E Broadway discussed in Chapter V.6.

As indicated above, Function 1E permits roadbed-specific information to be returned to the user. For more information, refer to the description as part of Function 1.

COW Function 1/1E Extended Mode - Mode Switch set to "X". Geosupport has an Extended Work Area 2 for COW Functions 1 and 1E called Function 1 and 1E Extended. The first 300 bytes of Function 1 and 1E with the Mode Switch set to "X" will be the same as regular Function 1 and 1E calls. Note: Please see Appendix 13 for the Extended Work Area 2 layout. Some of the fields in the extended portion of the Function 1/1E Work Areas include: USPS Preferred City Name, NTA Name, PUMA Code, Latitude, and Longitude.

Note: There is no longer a need to set the Cross Street Names Flag to "E" when using Function 1 and 1E with Mode Switch "X", since the Cross Street Names are in the Extended part of Work Area 2, although this will not create an error if the field is set to "E". However, the Street Names returned in Work Area 1 with the Cross Street Names flag are based on the B5SCs (thus returning the primary street names) and not based on the updated B7SCs which allow the Extended Work Area 2 to return the principal street names.

Function 1A

Function 1A, when called using two work areas, performs property (i.e., tax lot) and building-level processing. Function 1A returns information in WA2 associated with the specific property and building (if any) containing the input address. This information includes the property identifiers (tax block and tax lot numbers), and a list of all addresses of all buildings on the property (or as many as will fit in WA2) as well as the Building Identification Numbers (BINs) if any. Function 1A's output information is discussed in detail in Chapter VI.6.

** Function 1A Extended Work Area 2 (Mode Switch set to 'X') – COW Only. ** The first 246 bytes of the Extended Work Area 2 for Function 1A, up to the "Number of Entries in List of Geographic Identifiers" field, are the same as with regular Work Area 2. Aside from adding the new Function 1A Reason Code, Warning Code, GRC and filler to the work area for Function 1A Extended, the only change is in the address list. **The Principal Street Name (based on the B7SC in the address list) has been added to each element in the address list for the user's convenience.** Note that Mode Switch of 'X' is not valid with the Long Work Area 2 Flag set to Y, since the Function 1A Long Work Area 2 primarily returns BINs, not street codes.

Function AP (COW Only)

Function AP, when called using two work areas, performs Address Point processing and some property-level and building-level processing. Function AP returns the Address Point ID and the X,Y spatial coordinates of the Address Point. In addition, Function AP returns the Borough-Block-Lot of the Address Point and its BIN. The tax-lot information in WA2 lists only one address in the

lot, namely, the input address with the BIN number (if an) of the building at that address. Function AP's property output information is very similar to Function 1A's output. Function AP and Function 1A's output information is discussed in detail in Chapter VI.10 and Chapter VI.6.

** Function AP Extended Work Area 2 (Mode Switch set to 'X') – COW Only. ** The first 246 bytes of the Extended Work Area 2 for Function AP, up to the "Number of Entries in List of Geographic Identifiers" field, are the same as with regular Work Area 2. Aside from adding Function AP Reason Code, Warning Code, GRC and filler to the work area 2 for Function AP Extended, the only change is in the address list. **The Principal Street Name (based on the B7SC in the address list) has been added to each element in the address list for the user's convenience.**

Function 1B (COW Only)

Function 1B returns Blockface-level information and political geography, followed by property-level information for a given input. Work Area 2 consists of the output of a Function 1E call with Mode Switch = "X" followed by the output of a Function 1A call with Mode Switch = "X". The input requires borough or zip code, address number if needed, and street name or street code. Function 1B processing first retrieves the property-level information (Function 1A Extended- tax lot and building) based on the input. The Function 1A Extended processing may modify the input address (e.g. a hyphen is inserted into the address number). In any case, the input address used by Function 1A Extended is then used to retrieve the blockface and political data (Function 1E Extended).

Function 1B (combined Function 1E Extended and 1A Extended) returns a total of 4300 bytes in Work Area 2. The first 1500 are for the Blockface portion (Function 1E, see description above) of the call. The next 2800 bytes are for the Property Level portion (Function 1A, see description above and Chapter VI.6) of the call.

A second set of Geosupport Return Code (GRC), Reason Code and Error/Warning Message fields is defined in Work Area 1 to be used for Function 1B. This new set contains the GRC, Reason Code and Error or Warning Message for the Function 1A Extended portion of the Function 1B call. The original GRC, Reason Code and Message fields in Work Area 1 contain the Return Code, Reason Code and Error or Warning Message from the Function 1E Extended portion of the Function 1B call. It is entirely possible that Geosupport will find one set of information and not find the other. There can be an error code and message in the new GRC and Message fields indicating property data (Function 1A) has not been found, and a 00 or 01 GRC in the original Return Code field indicating Blockface (Function 1E) information has been found or just the opposite.

Work Area 2 for Function 1B

Function 1B returns a total of 4300 bytes in Work Area 2. The first 1500 are for the Blockface (Function 1E Extended) portion of the call. The next 2800 bytes are for the Property Level (1A Extended) portion of the call.

In the Function 1B Work Area 2, the Function 1E Extended WA2 output portion includes all the Function 1E Extended fields. There is one difference, namely that the preferred LGC that is returned in the Function 1B Work Area 2 is the DCP preferred LGC, not the Board of Elections preferred LGC.

A new Return Code and Reason Code field are defined in Work Area 2 for each of the 1E Extended and 1A Extended portions of the 1B call. This information duplicates the original and secondary Return Code and Reason Codes in Work Area 1. **GBAT does not return a Work Area 1 and therefore does not return both Return Code fields. In order to make it easier for the GBAT user to see the results for both components of the 1B call, Work Area 2 contains a Return Code and Reason Code for each portion (1E and 1A).** If data is found, either in the Blockface (Function 1E) call or the Property Level (Function 1A) call, that data will be returned to the user along with both Return Codes and Reason Codes.

If data has been found for the Blockface (1E) portion of the call, there will be data in columns 1 through 1500 of Work Area 2 returned to the user. Columns 1005-1006 will contain the GRC for the 1E portion of the call (which will be either a “00” or “01” indicating a warning) and column 1001 will contain the Reason Code if there is a warning. If data has not been found for the Blockface (1E) portion of the call, columns 1 through 1500 will be blank aside from the Error GRC in column 1005-1006 and the Error Reason Code, if any, in column 1001.

If data has been found for the Property Level (1A) portion of the call, there will be data in columns 1501-4300 of Work Area 2. Columns 1751-1752 will contain the GRC for the 1A portion of the call (which will be either a “00” or a “01” indicating a warning) and column 1747 will contain the Reason Code if there is a warning. If data has not been found for the Property Level (1A) portion of the call, columns 1501-4300 will be blank aside from the Error GRC in column 1751-1752 and the Error Reason Code, if any, in column 1747.

If data has not been found for either the Blockface or Property Level request, Function 1B’s Work Area 2 will be returned to the user with all fields blank aside from the two GRC and Reason Code fields mentioned above.

V.5.1 Mainframe GOAT Screen for Function 1B

In order to make room for more information, the Function 1B GOAT screen is formatted somewhat differently from the other GOAT screens. Since this new screen has many changes we are making an exception and describing it in the UPG.

a.There is only one field for the address number (Adr #:) and street name (Strt:). The same field is now used for the user’s input and the normalized output.

b. The screen is basically divided into two halves – with the top half giving Blockface Level Information (Function 1E) and the bottom half giving Property Level Information (Function 1A).

c. Two Return Code and Message Areas are displayed at the bottom of the screen. The first message area will reflect the Property Level portion and the second message area will reflect the Blockface and Political Level portion.

d. The Function Code input field is at the very top of the screen (Function Code:). The same field is used to display '1B' and to allow the user to transfer to another function.

e. The Unit input field is at the very top of the screen (Unit:). The same field is used to return the normalized unit display format output.

```
Function Code: 1B   *****  GOAT  (Geographic Online Address Translator)  ****
 Adr#: 1            Strt: PENN PLAZA                        Unit:
 Boro: 1 MANHATTAN 10SC: 4560201010     Browse(P/F/R):   Roadbed Req: N TPAD: N
 -------------------- Block Face Level Information ----------------------------
 Segm Id: 0297867 Physical Id:  0174203  Feature Type:                CD ELG: N
 ED/AD: 060/75    DSNY Dist/Sec: 105/051 DSNY Sub/Sched:    1H/MWF/EF SOS: R
 City Council: 03 NYPD PB/PCT: MS/014   2010 CT/CB  101.00/1002  Cont Parity:
 Fire Div/Batt: 01/07 Fire Comp/Insp Area:  L024 ZIP Code: 10119 Com Dist: 105
 Low Addr Nbr: 1            Low Cross St: 11061004    7 AVENUE
 Hi  Addr Nbr: 1            Hi  Cross St: 11081002    8 AVENUE
 -------------------- Property Level Information-------------------------------
 Block/Lot:   783/0070 BIN:         BIN Stat:   TBIN/Stat:        /  Vacant: N
 Structures: 0003      BD Class: O4 RPAD SCC: 4 X,Y Coords: 0986363,0212982
 BID:   34 STREET PARTNERSHIP   Condo#:      Condo Low-Hi Lot:
 Type of Item    Low Adr #   High Adr #  Street Name              Bldg ID Number
 Addr Range              1            1 PENN PLAZA                     1014387
 Addr Range            265          265 WEST   33 STREET             1014387
 Addr Range            206          268 WEST   34 STREET             1014387
 ---------------------------------------------------------------------------
 Function 1A Extended: Return Code = 00
 PRESS F7 TO SCROLL BACKWARD, F8 TO SCROLL FORWARD
 Function 1E Extended: Return Code = 01 Reason Code = V
 1 PENN PLAZA IS ON RIGHT SIDE OF WEST 33 STREET
```

Sample Mainframe GOAT Function 1B Screen

V.6 Duplicate Addresses

New York City has a small number of duplicate addresses, which are not data errors in Geosupport files, but real duplicates in the assignment of house numbers to buildings or in the allocation of administrative address ranges to blockfaces. Some duplicate addresses were created when formerly independent towns were consolidated into one of the city's boroughs. Other duplicates involve situations in which a developer or other entity has given the same name to a private street that the city has given to a public street in the same borough. When two streets in the same borough have the same name, Geosupport treats them as portions of a single street, regardless of how far apart they are geographically.

Geosupport's address-processing functions, Functions 1, 1A, 1B and 1E, when called using two work areas, have a special feature to process duplicate addresses. This feature involves the use of Duplicate Address Pseudo-Street Names (DAPSs), described in Chapter III.6. DAPSs are assigned to every street that has duplicate addresses, providing a means for users to specify unambiguously a particular instance of such an address. The user may alternatively specify the unique ZIP Code for the address. See Chapter III.6 for more detail.

Whether a given input address is processed as a duplicate address depends on the function. Functions 1 and 1E behave identically with respect to duplicate address processing, both in the set of addresses they consider to be duplicates, and in the way addresses are processed. However, Function 1A differs from Functions 11E in both of these respects.

Note, that **Function 1B** is a combination of Function 1A Extended and Function 1E Extended.

Function 1B first calls Function 1A Extended to process the input address. During its processing, Function 1A Extended may modify the input address, (e.g. if it assumes a range). Function 1B then calls Function 1E Extended with the input address as it was modified by Function 1A Extended. Separate error messages are issued by the Function 1A Extended and the Function 1E Extended processing. Both messages are returned to the user.

There are two cases of duplicate address situations:

- Case 1: Overlap of Administrative Address Ranges Allocated to Two Blockfaces: The same administrative address range (discussed in Chapter V.4) or portion thereof is allocated to two different blockfaces on the same street in the same borough. That is, an administrative address range allocated to one blockface along a street contains, coincides with, or otherwise overlaps with, that allocated to another blockface along the same street. Any input address that is within such an overlap is processed as a duplicate address by Functions 1 and 1E.

- Case 2: Duplication of an Address or Address Range Assigned to Two Buildings: The same address or range of addresses is assigned to two different buildings on the same street in the same borough. Any such input address is processed as a duplicate address by Function 1A.

In general, an address that is an instance of Case 2 is also an instance of Case 1, but the reverse is not necessarily true. That is, almost all addresses that are processed as duplicates by Function 1A are also processed as duplicates by Functions 1/1E, but there are many addresses that are processed as duplicates by Functions 1/1E but are not processed as duplicates by Function 1A.

Hillside Avenue in Queens has addresses that exemplify both of the above cases. A Case 1 example is the following: There is a blockface of Hillside Avenue in the Bellerose neighborhood of Queens to which the administrative address range 239-02 to 239-10 is allocated. There is another blockface of Hillside Avenue, in the Douglaston neighborhood of Queens, to which the administrative address range 239-02 to 239-20 is allocated. Since the Bellerose range is entirely contained within the Douglaston range, Functions 1 and 1E process every house number in the Bellerose range (all the even house numbers on Hillside Avenue from 239-02 to 239-10) as a duplicate address.

Despite the administrative address range duplication, not every individual even house number on Hillside Avenue between 239-02 and 239-10 is a valid actual building address in both Bellerose and Douglaston, i.e., is an instance of Case 2. Function 1A does not process an address as a duplicate unless it is assigned to two different buildings, even if Functions 1 and 1E process that address as a duplicate

Function 1A faces three possibilities when processing an address that Functions 1/1E consider to be a duplicate, as illustrated by the following Hillside Avenue examples:

- 239-02 Hillside Avenue is assigned to buildings in both Bellerose and Douglaston. Therefore, this address is processed as a duplicate address by Function 1A, as well as by Functions 1/1E.

- 239-06 Hillside Avenue is assigned to only one building, in Bellerose. Therefore, this address is processed normally, not as a duplicate address, by Function 1A, even though it is processed as a duplicate address by Functions 1/1E.

- There are no buildings to which 239-04 Hillside Avenue is assigned. Therefore, this address is rejected as entirely invalid by Function 1A, even though it is processed as a duplicate address by Functions 1/1E.

Processing of a duplicate address. When an address-processing function considers an input address to be a duplicate, it processes that address as follows.

- If the street in the input address is specified using the conventional street name (and no ZIP code is specified or an invalid ZIP code is specified), the call is rejected with a Geosupport Return Code of '75'. The accompanying Message informs the user that the function considers this input address to be a duplicate address, and indicates the two DAPSs that could be used to specify this address unambiguously. For example, 239-02 Hillside Avenue is considered a duplicate address by all of the address-processing functions, so all of them would reject the input 239-02 HILLSIDE AVENUE and would return a GRC of '75' and the Message:

```
DUPLICATE ADDRESS-USE HILLSIDE AVENUE BELLEROSE OR HILLSIDE AVENUE DOUGLASTON
```

- If the user specifies the input address using one of the DAPSs instead of the conventional street name, it is accepted. For example, 239-02 HILLSIDE AVENUE BELLEROSE is accepted by all of the address-processing functions, as is 239-02 HILLSIDE AVENUE DOUGLASTON. These functions return output information that is specific to the blockface (Functions 1/1E) or the tax lot and building (Function 1A) pinpointed by the DAPS.

- If the user specifies the input address using the conventional street name and a valid ZIP code then it is accepted. For example, 239-02 HILLSIDE AVENUE with ZIP code 11426 (in Bellerose) is accepted by all of the address-processing functions, as is 239-02 HILLSIDE AVENUE with ZIP code 11363 (in Douglaston). These functions use the corresponding DAPS information for the output street name and street code. These functions return output information that is specific to the blockface (Functions 1/1E, 1B) and/or the tax lot and building (Function 1A, 1B) pinpointed by the DAPS.

To summarize, for an address that the function being called considers to be a duplicate, the conventional street name, without a ZIP code, is rejected; only a DAPS or a conventional street name, with a ZIP code, is accepted as an input street name for such addresses.

Processing of a non-duplicate address on a street that has DAPSs. Now suppose that a particular address-processing function considers a given input address to be a valid non-duplicate. If the street does not have DAPSs (i.e., if the street does not have any addresses that are considered to be duplicates by any of the address-processing functions), then the processing does not involve the duplicate address processing feature. If the street does have DAPSs, then the address is processed as follows.

- If the address is specified using the conventional street name, it is accepted. For example, 239-20 Hillside Avenue is considered a non-duplicate address by all of the address-processing functions. Therefore, they all accept 239-20 HILLSIDE AVENUE as input. 239-06 Hillside Avenue is considered a non-duplicate address by Function 1A (it is valid for one building only, which happens to be in Bellerose), but it is considered a duplicate address by Functions 1/1E. Therefore, Function 1A accepts 239-06 HILLSIDE AVENUE as input, but Functions 1/1E reject this as a duplicate address for which DAPS input, or a ZIP code, is required.

- If the address is specified using DAPSs, the processing depends on the function:

    - Functions 1/1E reject the address. For example, Functions 1/1E reject 239-20 HILLSIDE AVENUE BELLEROSE, as well as 239-20 HILLSIDE AVENUE DOUGLASTON. Functions 1/1E treat DAPSs as valid only for addresses they consider to be duplicates, and reject DAPSs for addresses that these functions do not consider to be duplicates.

    - Function 1A's processing depends on whether Functions 1/1E consider the address to be a duplicate:

        - If Functions 1/1E consider the address to be a non-duplicate, Function 1A rejects the address. For example, Function 1A rejects the input 239-20 HILLSIDE AVENUE BELLEROSE, as well as 239-20 HILLSIDE AVENUE DOUGLASTON.

        - If Functions 1/1E consider the address to be a duplicate, Function 1A accepts the address when it is specified using the DAPS corresponding to the neighborhood where the address is valid, and rejects the address when it is specified using the other DAPS. For example, as mentioned above, 239-06 Hillside Avenue is valid only for a building in Bellerose. Therefore, Function 1A accepts 239-06 HILLSIDE AVENUE BELLEROSE, but it rejects 239-06 HILLSIDE AVENUE DOUGLASTON. Note that this contrasts with the behavior of Functions 1/1E, which reject both DAPSs when they consider an address to be a non-duplicate.

We now summarize the duplicate address processing feature. Functions 1 and 1E behave identically with respect to duplicate address processing: they consider the same addresses to be duplicates, and they process all addresses in exactly the same way, both those they consider to be duplicates and those they do not. However, Functions 1/1E differ from Function 1A in certain respects.

- Functions 1/1E differ from Function 1A in which addresses they consider to be duplicates. Almost all addresses that Function 1A considers to be duplicates are also considered duplicates by Functions 1/1E. However, there are many addresses that Functions 1/1E consider to be duplicates that Function 1A does not.

- If an address-processing function considers an input address to be a duplicate, the function rejects the conventional street name, and accepts DAPSs, or conventional street names with ZIP codes.
- If an address-processing function considers an input address to be a valid non-duplicate, it accepts the conventional street name.
- If an address-processing function considers an input address to be a valid non-duplicate, and the street is specified using a DAPS, the action taken depends on the function. Functions 1/1E reject both DAPSs, regardless of whether Function 1A considers the address to be a duplicate. Function 1A's action depends on whether Functions 1/1E consider the address to be a duplicate. If Functions 1/1E consider the address to be a non-duplicate, Function 1A rejects both DAPSs. If Functions 1/1E consider the address to be a duplicate, Function 1A accepts the DAPS that corresponds to the location where the input address is a valid address of a building, and rejects the other DAPS.
- As mentioned earlier, Function 1B is a combination of Function 1A Extended and Function 1E Extended. Function 1B first performs Function 1A Extended processing of the input address. Function 1B then performs Function 1E Extended processing of the input address (as it was modified by Function 1A Extended). Separate error messages are issued by the Function 1A Extended and the Function 1E Extended processing. Both messages are returned to the user.
    - If Function 1A Extended accepts the input, e.g. 239-06 Hillside Avenue, but Function 1E Extended does not, then the Function 1A portion of the Function 1B Work Area 2 will contain valid output, but the Function 1E Extended portion will show an error message rejecting the input (GRC 75) and no valid output will appear in the Function 1E Extended portion.

V.7 Marble Hill/Rikers Island

There are two New York City areas, Marble Hill and Rikers Island, that have the following idiosyncrasy: each is more closely identified geographically with a borough other than the borough to which the area legally belongs. The former is referred to as the 'alternative borough'.

- Marble Hill: The legal borough is Manhattan, and the alternative borough is the Bronx. Marble Hill is located on the Bronx side (the north side) of a body of water separating Manhattan Island from the Bronx, and it has a land boundary with the Bronx but it is connected to Manhattan Island only by a bridge.
- Rikers Island: The legal borough is the Bronx, and the alternative borough is Queens. Rikers Island is physically connected to Queens via a bridge but is not connected to the Bronx.

Because of their locations, Marble Hill and Rikers Island receive many of their government services from their alternative borough, and therefore they are included in many operational and administrative districts of the alternative borough. For example, most of Marble Hill is in Bronx Community District (CD) 8, and the remainder of it is in Bronx CD 7. Marble Hill also has a Bronx ZIP code (10463). Rikers Island is assigned to Queens CD1.

In practice, both the legal borough and the alternative borough are used when specifying Marble Hill and Rikers Island locations. To accommodate this practice, Geosupport's address-processing and street configuration-processing functions have been designed to accept either the legal borough or the alternative borough as the input borough for Marble Hill and Rikers Island locations. For example, the Marble Hill address 150 WEST 225 STREET is accepted by the address-processing functions whether Manhattan or the Bronx is specified. The Rikers Island address 18-99 HAZEN STREET is accepted whether the Bronx or Queens is specified.

When an application makes a two-work-area call to any of the address-processing or street configuration-processing functions other than Function 3S, and specifies the alternative borough for a Marble Hill or Rikers Island location, Geosupport issues a warning with a Reason Code value of 'C' and an appropriate Message.

Except for the LION Key (viz. Borough Code, Face Code and Sequence Number) the information returned to the application in WA2 is the same regardless of which borough is specified as the input borough. Note, however, that the output borough name and street code(s) returned to the application in WA1 do depend on which borough is specified as the input borough. Each street in Marble Hill and Rikers Island has two street codes assigned to it, one for the legal borough and one for the alternative borough. The street code(s) and borough name that are returned in WA1 correspond to the input borough.

V.8 Special Ruby Street Processing

The address processing functions have a special feature to handle an anomaly involving a stretch of a street that lies along the Brooklyn−Queens border. On the Brooklyn side, this street is called Ruby Street; on the Queens side of the same physical street, it is called 75 Street. Many residents of the Brooklyn side of this street customarily specify Brooklyn as the borough but they specify the Queens street name, 75 Street, rather than the 'legal' Brooklyn street name, Ruby Street. A further complication is that there is a different Brooklyn street (in Bay Ridge, far from the Queens border) that is also called 75 Street. Geosupport handles these anomalies automatically, as follows:

When an address-processing function is called, and Brooklyn is specified as the input borough, and 75 STREET is specified as the input street name, Geosupport is able to determine from the input house number (assuming it is a valid house number) whether the address is on 75 Street in Bay Ridge or is actually on Ruby Street. If it is in Bay Ridge, it is processed normally. If the address is on Ruby Street, then Geosupport takes the following actions:

- The street name RUBY STREET and the street code for Ruby Street are returned in WA1 instead of the normalized input street name, 75 STREET, and the latter's Brooklyn street code.

- WA2 is returned with a full complement of data.
- Geosupport issues a warning with a Reason Code value of either '6' or '7'. (Reason Code '6' indicates simply that the output street name and street code differ from the corresponding input values. Reason Code '7' indicates in addition that the input and output house numbers differ from each other in some way, as per Chapter V.2. See Appendix 4.)

V.9 Vanity Addresses

Vanity addresses are a type of geographically 'dislocated' address in which the street name is that of a different street from the one on which the building entrance is actually located. Developers sometimes use such addresses in the belief that a prestigious street name enhances the market value of a property.

1049 FIFTH AVENUE in Manhattan is an example of a vanity address. Although this is ostensibly a Fifth Avenue address, the building entrance to which this address is assigned is actually located on the south side of East 86th Street between Fifth and Madison Avenues. (In this case, the building has no frontages at all on the named street, although that is not a prerequisite to being a vanity address.)

Functions 1 and 1E process vanity addresses as follows.

- A warning with Reason Code 'V' is issued, along with a message that indicates the 'true' street name (the name of the street on which the building entrance is actually located).
- The output data returned, including cross streets and geographic district identifiers, pertain to the true blockface. For example, the information returned for 1049 FIFTH AVENUE corresponds to the blockface on the right (south) side of East 86th Street between Fifth and Madison Avenues, not to a blockface of Fifth Avenue. In particular, East 86th Street is not returned as a cross street, since it is the true 'on' street; and Fifth Avenue is returned as the cross street at the low-address end of the segment.
- The source for the Spatial Coordinates (a.k.a. X-Y coordinates) returned for Vanity Addresses (and NAPs) is the **Citywide Street Centerline file (CSCL).** The CSCL information guarantees that the X-Y coordinates fall within the actual location (e.g. building footprint) of the Vanity Address.

Function 1A processes vanity addresses as follows:

- A warning with Reason Code 'V' is <u>not</u> issued.
- The output data returned pertain to the actual building associated with the vanity address.

- In the list of geographic identifiers at least two entries will appear: one (type V entry) for the vanity address and one for the real street (a.k.a. true street or underlying street). The second entry will be either a regular address entry with house numbers and street information or a type R entry indicating the street that the entrance to the vanity address is on.

V.10 Out-of-Sequence Addresses

In addition to vanity addresses, there is another type of geographically dislocated address called out-of-sequence addresses. In such an address, the street name does refer to the street where the referenced building entrance is actually located, but the house number is out of sequence with those of the adjacent buildings. An out-of-sequence address may or may not be so dislocated that the building entrance is on a blockface other than the one that is consistent with the normal addressing pattern of the given street. Developers sometimes request such addresses because they feel they are euphonious or easy to remember.

An example of an out-of-sequence address is 62 WEST 62 STREET in Manhattan. This address refers to a building entrance located on the south side of West 62nd Street between Broadway and Columbus Avenue. In this case, the out-of-sequence address is indeed on the blockface that is consistent with the normal addressing pattern for West 62nd Street. However, the building in question is directly to the east of a building with the address range 42-44 WEST 62 STREET. This violates the normal addressing pattern for West 62nd Street, and for east-west streets on the west side of Manhattan in general, in which the house numbers consistently increase going from east to west.

Functions 1 and 1E process out-of-sequence addresses as follows. A warning with Reason Code ‘O’ is issued for any address on a blockface containing an out-of-sequence address. The output data returned, including cross streets and geographic district identifiers, pertain to the blockface on which the building entrance is actually located. The Spatial Coordinates returned are those of a point calculated under the assumption that the building entrance is located at the midpoint of the blockface.

An opposite-parity address contains a house number that is of the opposite parity to the predominant parity on the blockface. Opposite-parity addresses are processed in the same manner as out-of-sequence addresses.

V.11 ZIP Code as Input Instead of Borough Code

For Functions 1, 1A, 1B, and 1E, the user may supply the five-digit ZIP code in place of the borough code. Geosupport will determine the borough based on the ZIP code. If both a ZIP code and a borough code are supplied, the borough code will be used and, in general, the ZIP code will be ignored.

Please note that the ZIP code is not validated. It is mainly used to determine the borough. For example, if you supply a ZIP code that is valid for the borough, but not for that particular location, the specified function will execute successfully. In addition, the ZIP code returned in Work Area 2 may be different than the ZIP code you have supplied.

In general the ZIP codes returned in Work Area 2 are usually accurate for residential areas since these ZIP codes are validated by the Board of Elections. If you believe that the ZIP code returned by Geosupport is incorrect, please forward the address in question with the ZIP code you believe is correct to GSS_Feedback@planning.nyc.gov. See Appendix 6 for more information.

V.12 Fuzzy Search for Address Functions 1, 1A, 1B, and 1E

Geosupport processes situations where there is only one possible valid similar name and that valid similar name is created by adding the word EAST or WEST to the front of the input street name (in other words, the input street name is a front-truncated street name). For example, if a user supplies 212 146 STREET in Manhattan as the input to a Function 1, 1A, 1B or 1E call, Geosupport recognizes that 146 Street does not exist in Manhattan. Since only WEST 146 STREET exists (there is no East 146 Street), Geosupport will accept the call with a warning message indicating that West 146 Street is assumed.

V.13 Special Place Name Processing

Functions 1 and 1E return the underlying street name of an addressable place name, and the street address of a non-addressable place name, as part of a warning message with reason code V. In addition, the underlying information is returned in code format in the COW Work Area 2 and the MSW Long Work Area 2.

V.14 'No Cross Street' Segment Processing

When there are no cross streets at the end of a segment, Functions 1, 1E and B return the cross streets from preceding or subsequent segments. The High and Low Addresses at those cross streets are also returned. In Function 1 and 1E Extended and Function 1B, the Node ID and X-Y coordinates (spatial coordinates) at those cross streets are returned as well.

If the user wishes to see the original values of the Node ID and X-Y coordinates of the original segment (which may have no cross street) those values appear in special 'segment' fields in Functions 1/1E Extended and Function 1B.Work Area 2.

V.15 UNIT Information Feature (COW Only)

Users have requested the ability to describe addresses more in more detail. Geosupport now allows users to specify UNIT information, e.g. APT 5, on COW address-processing functions

The UNIT feature enables users to keep better track of information specific to units within a building. For example, it will be useful for PECO (Post Emergency Canvassing Operations) to record which units in a building were canvassed, and which units required assistance. By allowing users to input apartment numbers it will help the users keep track of whom they saw when going into the field. They can print lists with apartment numbers and keep track of which apartments were seen and which still remain to be seen. The Unit information can also be used on mailing labels, etc.

- Unit information may appear at the end of an input free-form address,
  e.g. 120 BROADWAY STE 3102

- Alternatively, unit information may also appear in the Unit Input field in Work Area 1,
  e.g. STE 3102

** Unit ** information consists of a ** Type ** and an ** Identifier ** . For example, 'APT 5' consists of a Unit Type of 'APT' (apartment) and a Unit Identifier of '5'. (Unit Type and Unit Identifier are similar to NENA (National Emergency Number Association) terminology.) NENA and USPS (US Postal Service) have defined Preferred Types with a length of up to 4 characters. Geosupport converts the input Type to the Preferred Type. See Table of Preferred Types later in this section. If the unit information does not have a recognized type, the Type will be set to a pound sign, viz. #, and the data will be considered as the Identifier. If the data is longer than the space available in the Unit fields, the identifier will be truncated and a warning message (Reason Code $) will be issued.

Unit information is supplied by the user in the Work Area 1 (WA1) Unit Input field for a length of 14, or at the end of a free-form address. In either case, the unit information is normalized and returned in the Output Area of WA1 in two formats – Display format and Sort format.

- Display format for a length of 14, with Type and Identifier concatenated with one blank in between them.

- Sort format for a length of 14, which is broken down into two consecutive fields

  - Unit Type for a length of 4
  - Unit Identifier for a length of 10

The following table indicates the size and location of the UNIT fields in the COW Work Area 1. These fields are defined in the Geosupport COPY library.

UNIT Fields Work Area 1 (COW only)				
Field name	**Size**	**From**	**To**	**Functions**
---- The following Unit field is in the Input portion of Work Area 1 ----				
Unit Input	14	219	232	1*
---- The following Unit fields are in the Output portion of Work Area 1 ----				
UNIT - SORT FORMAT	14	667	680	1*
Unit – Type	4	667	670	1*
Unit – Identifier	10	671	680	1*

Unit – Display Format	14	681	694	1*

The normalization of Unit input includes recognizing the Unit Type and Identifier and converting all Unit Types to the Preferred Unit Types. In addition, the first instance of a Type is moved to the front of the Display Unit field. Some of the basics of normalization are mentioned here.

- All ordinals are removed
- All characters aside from A-Z, 0-9, -, / are removed
- All extraneous blanks and all blanks before and after / or – are removed
- The first instance of a Type is moved to the front of the unit field with the rest of the identifier following, e.g. 1st Floor will be output as FL 1.
- All instances of a Type are replaced by the Preferred Type
- In the absence of a Type, the software will return a pound sign (#).
- In Display format there will always be a blank between the Type and the Identifier, e.g.`MEZZA` will appear as `MEZZ A` in a Unit output field. (`MEZZ` is the preferred Type for Mezzanine.)

Note: In the following discussions, blanks appear as hyphens.

- Consider an example where the Unit Input is '

  `4TH-FLOOR`'. It will be normalized to: '`FL-4`' in the Display format. The ordinal `'TH'` was removed; `'FLOOR'` was replaced by the Preferred Type `'FL'` ; and `'FL'` was moved to the front of the Display Unit field.

- The Sort format is similar except that it is composed of two fields. The Type is always 4 characters. The first instance of a Type is put into the Type field of the Sort format. The Identifier has 10 characters and any numeric may have extra spaces around them to ensure that they sort properly. In this case,

  `'4th-FLOOR'` would be appear as `'FL--'` in the Sort Type field and '---4------' in the Sort Identifier field. The extra blanks before the '4' in the Sort Identifier field will ensure that if they are sorted, the sort version of `'10TH-FLOOR'` ('--10------') will appear after the sort version of `'4TH-FLOOR'`

- If no Type at all is recognized in the input, then a pound sign '#' is used as the Type in the Display and the Sort format. For example, if the Unit Input just had a '5', Then the Display format would contain

  `'#-5'` ; the Sort format would contain Type: '#---' and Identifier:'---5------'.

- If Unit Input is specified in the WA1 Unit Input field, and additional information also appears after the Street Name in a free-form call, then the WA1 Unit Input field is processed and the information appearing after the free-form address is ignored.

- When the Unit information is supplied as part of the free-form address, Geosupport continues to give the Reason Code 'W' warning message
  INPUT STREET NAME HAS BEEN MODIFIED

- In rare instances, a Unit Identifier may be truncated in an output field. In that case, if the Unit Input was specified in the WA1 Unit Input field, then a warning message is issued. The warning message is:

GRC	Reason Code	Functions	Message
01	$	1*	UNIT IDENTIFIER HAS BEEN TRUNCATED

When this situation occurs with a free-form address, the original warning message with Reason Code ‘W’: INPUT STREET NAME HAS BEEN MODIFIED is still given.

The following is a table of the Preferred Unit Types and the Alternate Types that are recognized as input. The Preferred Type will appear in the Unit Output fields.

Table of PREFERRED UNIT TYPEs				
Preferred Unit Type	**Alternate Input 1**	**Alternate Input 2**	**Alternate Input 3**	**Alternate Input 4**
APT	APARTMENT	APART	APT	
BSMT	BASEMENT	BSMT	BSM	
BSMBLDGT	BUILDING	BLDG	BLD	
CLR	CELLAR	CELAR	CELL	CLR
COMM	COMMONS	COMMON	COMM	COM
CONC	COMCONCOURSEMONS	CONCOURS	CONC	
CORR	CORRIDOR	CORRID	CORR	COR
DEPT	DEPARTMENT	DEPT	DEP	
FL	FLOOR	FLR	FL	
FRNT	FRONT	FRNT	FRT	
HNGR	HANGER	HNGR		
KEY	KEY			
LBBY	LOBBY	LBBY	LBY	
LOT	LOT			
LVL	LEVEL	LEVL	LVL	LEV
LOWR	LOWER	LOWR	LOW	
MEZZ	MEZZANINE	MEZZ	MEZ	
OFC	OFFICE	OFFIC	OFF	
PH	PENTHOUSE	PNTHSE	PH	
PIER	PIER			
REAR	REAR			

RM	ROOM	RM		
SIDE	SIDE			
SLIP	SLIP	SLP		
SPC	SPACE	SPAC	SPC	
STG	STORAGE	STORAG	STRG	STG
STOP	STOP	STP		
STE	SUITE	SUIT	STE	
TRML	TERMINAL	TRMNL	TRML	
UNIT	UNIT	UNT		
RM	ROOM	RM		
UPPR	UPPER	UPPR	UPR	
WING	WING	WNG		

** Mainframe GOAT (CICS) Support of Unit - Functions 1A and 1B **

- Function:1A
- Input: Field labeled

  `'Unit'` is available for input data.

- Output: Field labeled

  `'Norm Unit Disp' displays the Normalized Display Format`

  `Unit Output field.`

- Function:1B
- Input: Field labeled 'Unit' is available for input data.
- Output: To save screen space, the Field labeled

  `'Unit'` that was used for input is also used for output and displays the Normalized Display Format Unit Output field.

** Mainframe GBAT Support - Functions 1A and 1B **

- ** Required ** GBAT Control Entries
  WORKAREA=COW
  RECTYPE=1A or 1B

- ** Optional ** GBAT Control Entries

UNIT=S,L	defines location of Unit input field(not required if input data is free-form only)

GEOUNIT=YES or NO	specifies if GBAT returns the Normalized Display Format Unit output field.
GEOCODE=NO or ALL	required if GEOUNIT=YES

- ** Optional LRECL ** change
  If GEOUNIT=YES is in effect, the LRECL of OUTFILE must be increased by 70.
- For more detail on GBAT Unit processing, see Chapter IX, Appendix 9, and Appendix 12.

** Summary of Geosupport support of Unit processing **

- As of this writing, Unit Processing is supported by:
  - Mainframe Batch and CICS
  - Desktop Edition
  - Linux Edition
  - .net and Java classes
  - Mainframe GBAT Batch (Functions 1A and 1B)
  - Mainframe GOAT CICS (Functions 1A and 1B)
  - Desktop Edition GBAT (Functions 1A and 1B)!
  - GeoExcel 2013
  - Web GOAT
- As of this writing, Unit fields are not processed by:
  - Mainframe GBAT Batch (Functions 1 and 1E)
  - Desktop Edition GBAT (Functions 1 and 1E)
  - Desktop Edition GOAT

CHAPTER VI

TAX LOT AND BUILDING PROCESSING - FUNCTIONS 1A, BL, BN / ADDRESS POINT PROCESSING - FUNCTION AP

VI.1 Introduction

New York City has approximately one million parcels of privately and publicly owned real property, called tax lots, containing more than 800,000 buildings. This chapter describes the Geosupport functions that process tax lots and buildings, Functions 1A, BL and BN. It also describes the Geosupport function that provides the Address Point information for addresses in New York City, Function AP.

Two data items discussed in detail in this chapter, the Borough-Block-and-Lot (BBL) and the Building Identification Number (BIN), serve as unique identifiers for tax lots and buildings, respectively. (Addresses are non-unique building identifiers, since many buildings have more than one address.) Function 1A accepts address input, Function BL accepts BBL input, and Function BN accepts BIN input.

Address Point IDs which relate to a 'real' posted address, and BBL and BIN information can be retrieved via Function AP. Function AP accepts address input. For more information on Function AP and Address Points, see Chapter VI.10.

Functions 1A, 1B, BL, and BN return property information that is updated on a weekly basis. (Prior to Version 17.1/Release 17A, the property information was updated on a quarterly basis. For Function 1B, only the property level data will be updated weekly[4].) COW users may request more up-to-date information relating to new buildings and demolitions via the TPAD Request Flag for Functions 1A, 1B, BL and BN. (Note that TPAD information is not available for Function AP. Also, for Function AP, the property information continues to be updated on a quarterly basis.) For more information on the TPAD feature see Chapter VI.11 which discusses TPAD[5] BIN and Status Information (COW only). See also Appendix 17 which discusses TPAD error processing and work area field names.

---

[4] The weekly updates are typically available to users on the DoITT mainframe. For other users, discuss availability with the Geosupport Staff. [5] TPAD – Transitional Property Address Directory

VI.2 Tax Lots and BBLs

The city's tax geography is designated and modified by the New York City Department of Finance (DOF). The tax geography consists of the subdivision of the territory of the city (excluding city-owned land that is mapped for streets) into tax blocks, each of which is further subdivided into one or more tax lots.

- Each tax block is identified, uniquely within its borough, by a tax block number assigned by DOF. Each tax block can consist of one, more than one, or a portion of one physical city block.

- Each tax lot is identified, uniquely within its tax block, by a tax lot number assigned by DOF.

Thus, each of the city's tax lots is identified, uniquely within the entire city, by the combination of three items, the borough code, tax block number and tax lot number. These items are often concatenated to form a single data item called the Borough-Block-and-Lot (BBL).

DOF strives to keep the tax block numbering as stable as possible over time, to facilitate property title searches and other historical record-keeping. For example, when a new stretch of street divides what was a single physical block into two physical blocks, DOF generally retains the old tax block number for both of the new physical blocks. As a result, there are many tax blocks that consist of more than one physical block. Occasionally, DOF does subdivide a tax block into two or more new tax blocks, assigning new tax block numbers to them. This may be done when a large area of land is being developed, often in conjunction with the mapping of a new pattern of streets. In recent years, this has most commonly occurred in Staten Island.

In contrast to the relatively stable tax block geography, the tax lot geography is quite volatile. DOF constantly merges and 'apportions' (subdivides) tax lots, generally assigning new tax lot numbers to the newly created tax lots. However, DOF sometimes reassigns the tax lot number of a 'predecessor' lot (one of the lots that is being merged or apportioned out of existence) to a 'successor' lot. As a result, it is possible for the same BBL value to refer simultaneously to an existing tax lot and to one or more tax lots that no longer exist.

Figure VI-1, below, illustrates the tax geography for a portion of Manhattan in the vicinity of City Hall.

Figure VI-1: Tax Geography for a Portion of Manhattan

The large numbers in Figure VI-1 are tax block numbers, and the small numbers are tax lot numbers. Notice that tax block 153 is a case of a tax block consisting of two physical blocks. Also notice that tax blocks 154 and 155 both have a tax lot 1, exemplifying that tax lot numbers are unique only **within a tax block**. (Similarly, tax block numbers are unique only within a borough.)

VI.3 Buildings and Building Identification Numbers (BINs)

Many city agencies must maintain and process building-related data rather than, or in addition to, tax lot-related data. These two levels of processing are distinct, since a single tax lot can contain more than one building or no buildings.

A critical issue for building-level processing is to be able to identify buildings consistently. Neither addresses nor BBLs are suitable to serve as consistent identifiers for buildings. Some shortcomings of using addresses as building identifiers are as follows:

- Many buildings have more than one address.
- Some buildings have no addresses.
- The same address can identify both an existing building and a demolished one.
- New York City has a small number of instances in which two different existing buildings have the same address (see Chapter V.6).

Some shortcomings of using BBLs as building identifiers are as follows:

- Some tax lots contain more than one building.
- The relationship of buildings to tax lots is volatile, since tax lots are often subdivided and merged over time.

In order to provide a unique, immutable, citywide standard for building identification that can support consistent building-level processing, GSS has developed a set of Building Identification Numbers (BINs) that are assigned to every known building in the city. (BINs are distinct from, and should not be confused with, house numbers.) A BIN is a seven−byte numeric item, the first digit of which is the borough code. If a BIN field in a Geosupport work area is ‘empty’ (devoid of information), it contains the borough code followed by all zeros (in contrast to most Geosupport fields, which contain all blanks when ‘empty’). These are often referred to as zero BINs or ‘million’ BINs (e.g. 1000000, 2000000, etc.).

By using BINs as the building identifier, city agencies can process and match building-related data easily and in a consistent manner. Indeed, there are buildings that do not have either an address or a Non-Addressable Place Name (NAP) and can be identified only by their BIN. In this document, such buildings are called Non-Addressable Un-named Buildings (NAUBs). Typical examples of NAUBs are some storage sheds on industrial lots and some comfort stations in parks.

The proliferation of the use of BINs among city agencies facilitates matching data by building across applications and across agencies. The Department of Buildings, which is particularly involved with building-level processing, uses BINs to identify buildings in its major computer applications.

The BIN that is assigned to a building is never changed (except to correct assignment errors); it remains assigned to that building permanently, even if the building is subsequently demolished or its BBL changes as a result of a tax lot merger or apportionment. If a building is demolished, and a new building is subsequently built and given the same address as that of the demolished building,

GSS assigns to the new building a new BIN, different from that of the demolished building. In this case, the same address ambiguously identifies two distinct buildings (the new one and the demolished one), but each building is unambiguously identified by its own unique BIN. However, only the 'active' BIN for an address is returned in the Geosupport System at one time, unless the user sets the TPAD request switch in which case a Transitional BIN may also be returned for a given address (see Chapter VI.11 for more information). That is, only one BIN per address is accepted as Function BN input and returned as Function 1A, 1B and BL output. Generally, the active BIN of an address is the BIN assigned to the most recent building at the given address. Function BN also accepts as input the BINs assigned to buildings that have no addresses, such as NAUBs.

VI.4 Condominiums and Billing BBLs

Condominiums are a class of properties with unique characteristics. A condominium consists of condominium units, each of which constitutes a separate tax lot that has its own BBL. In a residential condominium, the condominium units are generally the individual apartments. In a commercial condominium, the units might be retail shops or blocks of space in an office building. There are also mixed-use condominiums that have both commercial and residential units. A condominium can encompass all or part of a building or more than one building, possibly on more than one tax block.

The individual units in a condominium (but not the condominium itself) are parcels of real property. For example, title to an individual unit can be conveyed via a deed; unit owners are responsible for paying real estate taxes directly to the city; and liens can be placed against units.

Many municipal operations relate to condominiums as a whole rather than to specific condominium units. Examples are collecting sanitation fines, issuing code violations and inspecting and licensing building-wide systems such as boilers and elevators.

To distinguish condominiums from their constituent units, DOF has assigned to each condominium a set of special tax lot identifiers called the billing BBL. (Condominiums are also identified by a Condominium Identification Number, also assigned by DOF.) If a condominium occupies land on more than one tax block, DOF assigns a billing BBL to each portion of the condominium on a separate tax block. Function BL accepts billing BBLs as valid input data, and Functions 1A and BN return them as output data.

DOF assigns billing BBLs only to condominiums, not to condominium units or non-condominium properties. Billing BBLs do not represent actual tax lots, and are not lienable. However, billing BBLs do provide a mechanism to obtain the name and address of a more appropriate party than a unit owner to communicate with concerning condominium-wide matters. DOF maintains files keyed to BBL which, for conventional BBLs, contain the names and addresses of parties registered to receive bills for real property taxes, often the property owner, but possibly a property manager, attorney or mortgagee. For a condominium billing BBL, the party listed might be an officer of the condominium, a property manager or an attorney. (Note: Geosupport does not provide direct access to DOF's files; to arrange such access, contact DOF.) In some instances there may be a

condominium that has not yet been assigned a Billing BBL by DOF (or the Billing BBL was not yet available when the Geosupport files were generated); in these cases the BBL that is returned by Geosupport is set to zero and a warning message is issued.

VI.5 Vacant Street Frontages and Pseudo-Addresses

'Real' addresses are officially assigned to new buildings by the topographic bureaus at each of the five borough president's offices. In addition, GSS assigns addresses called pseudo-addresses to some vacant street frontages of tax lots, that is, to street frontages that do not have 'real' building addresses. Pseudo-addresses have no 'official' status; they are not meaningful outside of the Geosupport System and should not be used for any operational purpose. In particular, mail sent to a pseudo-address is likely to be undeliverable. Since pseudo-addresses are not associated with buildings, they do not have associated BINs. Note: Pseudo-addresses are not to be confused with the unrelated concept of pseudo-street names (discussed in Chapter III.6).

When assigning a pseudo-address, GSS attempts to anticipate what 'real' address might someday be assigned to a building if one were to be built at that location. However, the assignment of pseudo-addresses can sometimes involve an element of arbitrariness, especially where there is a wide gap between the two real addresses that 'sandwich' a vacant frontage, or where there is a row of several adjacent vacant frontages. When assigning a pseudo-address, at a minimum, GSS uses a house number that is not already in service on the given street and that is in proper sequence with nearby real house numbers and with any previously assigned pseudo-addresses. If no such house number is available, no pseudo-address is assigned to that vacant street frontage.
Function 1A is designed to accept as input both real addresses and pseudo-addresses. Also, both Function 1A and Function BL include pseudo-addresses in the list of geographic identifiers that they return for a tax lot Pseudo-addresses serve the following purpose: Certain information is obtainable from Geosupport by address but not by BBL, such as many political and administrative district identifiers that Functions 1 and 1E return. For vacant tax lots, which have no buildings at all and therefore no real addresses, pseudo-addresses provide the only means to obtain such information from Geosupport. Of course, for those vacant tax lots that have no pseudo-addresses assigned to them, it is not possible to obtain such information from Geosupport.

If a pseudo-address comes to be assigned as a real address of a newly constructed building, GSS changes that address's classification in the Geosupport System from pseudo-address to real address. At the same time, the address's tax lot might also change, if the new building happens to be on a different tax lot than the lot to which the address had been assigned as a pseudo-address. Real addresses can also change status and become either Geosupport rejects or pseudo-addresses, as the result of building demolitions. Geosupport is updated to reflect such changes, but time lags are possible.

VI.6 Function 1A

Function 1A processes input addresses and NAPs. When Function 1A is called using two work areas, it returns information in WA2 related to the tax lot and the building (if any) identified by the input data (see work area layouts in Appendix 2(MSW) and Appendix 13 (COW) . If the input address is a pseudo-address, a warning is issued with Reason Code ‘8’ or ‘9’.

See Chapter V for a general discussion of Geosupport address processing, much of which is applicable to Function 1A. In particular, the various combinations of data items that can be used to specify an input address are described in Chapter V.3. Chapter V.4 discusses how Function 1A differs from the other address-processing functions with respect to the validation significance of input address acceptance and rejection, and explains why Function 1A is the best address-processing function to use to validate addresses. Special address processing features discussed in Chapter V are also available with Function 1A, including duplicate address processing, the special Marble Hill/Rikers Island feature, and the special Ruby Street feature.

An important purpose of Function 1A is to provide the BBLs for which addresses are known. The BBLs can then be used (outside of the Geosupport System) to retrieve information from various city files that are keyed to BBL, including DOF’s billing address files, from which the name and mailing address of the party registered to receive real estate tax bills can be retrieved. This same party might also be an appropriate recipient for many other property-related city mailings, such as notices of inspections, violations, summonses, fines, hearing notifications and licenses.

If the property is part of a Business Improvement District (BID), the BID is returned in Work Area 2 as a borough and five-digit street code (B5SC). Function D may be used to obtain the name of the BID.

The latitude and longitude of the location are also returned by COW Function 1A. In addition, COW Function 1A returns the DCP Zoning Map number.

The long WA2 option (COW and MSW) as well as the Extended WA2 option (COW only) are available for Function 1A. Note that Extended WA2 is not valid if Long Work Area 2 is in effect. All three WA2s (viz. regular, long, and extended) for Function 1A contain a set of data organized into a list. The list in the regular WA2 and the Extended WA2 is a List of Geographic Identifiers (LGI). The LGI is intended to provide a comprehensive geographic profile of the tax lot by listing, so far as the information is known and space allows, all of the buildings the lot contains; all of the street addresses and non-addressable street frontages of each of those buildings; all of the vacant street frontages of the lot; and all NAPs associated with the lot. See the entry for the List of Geographic Identifiers in Appendix 3 for a detailed discussion of the contents of the LGI.

The LGI’s entries are ordered so that entries with non-empty BINs are listed first, grouped by BIN. If the input address is a real address, the first group of entries in the LGI consists of the entries for the BIN corresponding to the input address, and (except for certain special cases) the very first entry is an address range encompassing the input address. (The special cases are when the input information contains the alternative borough for a Marble Hill or Rikers Island location or the alternative street name or street code for a Ruby Street address -- see Chapters V.7 and V.8.) Any entries with empty BINs (a.k.a. zero BINs), such as entries for pseudo-address ranges, are listed

after the entries with non-empty BINs as space in the LGI allows. If the input address is a pseudo-address, an address range encompassing it may or may not appear in the LGI, depending on the availability of space in the LGI and on the order in which the non-BIN entries happen to be listed.

The LGI has a maximum capacity of 21 entries, which for almost all tax lots is sufficient to contain all of the lot's geographic identifiers. A tax lot that does have more than 21 geographic identifiers is said to have the 'LGI overflow condition'. The LGI overflow condition is indicated by a value in the LGI Overflow Flag in Function 1A's regular WA2, as well as by the issuance of a warning (Reason Code 'A').

By definition, when a tax lot has the LGI overflow condition, some of the lot's geographic identifiers are not included in the LGI. In particular, it is possible that the BINs of some of the lot's buildings do not appear in the LGI. The purpose of the long WA2 option for Function 1A is to provide a means for applications to retrieve a complete list of BINs for all the buildings on a tax lot, even for lots that have the LGI overflow condition. The long WA2 contains a List of Buildings on the Tax Lot. Each entry in this list consists only of a BIN; the list includes no address, street frontage or NAP information. (Such information can be obtained for each of the lot's buildings by making Function BN calls.) The maximum capacity of the List of Buildings is 2,500, which is sufficient to list the BINs of all of the buildings on any tax lot in New York City.

Applications can use the long WA2 option for all tax lots, even for those that do not have the LGI overflow condition. Using the long WA2 option for every Function 1A call, rather than only for tax lots that have the LGI overflow condition, may be advantageous in applications that require a list of BINs but do not require the other information returned in the LGI. Doing so simplifies application design: only a single Function 1A call would be required for each input address, and the List of BINs, unlike the LGI, contains every BIN for the lot without repetition. However, users should be aware that, for tax lots that have the LGI overflow condition, a long WA2 call causes Function 1A to perform more I/O operations than a regular WA2 call.

If the input address to a Function 1A call (using the regular WA2, the long WA2, or the Extended WA2), is that of a condominium, Geosupport returns a 'C' in the Condominium Flag in WA2. In addition, the following information is returned for condominiums:

- Condominium Billing BBL (or the billing BBL of the portion of the condominium in the tax block containing the input address, if the condominium is in more than one tax block). In some instances there may be a condominium that has not yet been assigned a Billing BBL by DOF (or the Billing BBL was not yet available when the Geosupport data files were generated); in these cases the BBL that is returned by Geosupport is set to zero and a warning message issued.
- DOF Condominium Identification Number (provided that DOF has assigned an ID number to the condominium and GSS has entered it into the Geosupport data).
- The low BBL of all the condominium units in the building identified by the input address.
- The high BBL of all the condominium units in the building identified by the input address. For the positions of these fields in Work Area 2, see Appendix 2 and Appendix 13 for MSW and COW respectively.

Function 1A Extended Work Area 2 (Mode Switch set to 'X'). This option is available in COW only. The first 246 bytes of the Extended Work Area 2 for Function 1A, up to the "Number of Entries in List of Geographic Identifiers" field, are the same as with regular COW Work Area 2. Aside from adding some filler and the new Function 1A Reason Code, Warning Code, and GRC fields (which are identical to the WA1 fields) to the work area for Function 1A Extended, the only change is in the address list. The street codes in the address list are B7SCs instead of B5SCs. **The Principal Street Name (based on the B7SC in the address list) has been added to each element in the address list for the user's convenience.** Note that Mode Switch of "X" is not valid with the Long Work Area 2 Flag set to Y, since the Function 1A Long Work Area 2 primarily returns BINs, not street codes.

VI.7 Function BL

The input to Function BL is a BBL identifying a tax lot. Like Function 1A , Function BL can be called with the long WA2 option. As with COW Function 1A, COW Function BL can be called requesting the Extended Work Area 2 (Mode Switch set to 'X').

The layouts of the regular, long and extended WA2s for Function BL are the same as the corresponding layouts for Function 1A, as described in Chapter VI.6. However, since the input information to Function BL identifies only a tax lot, whereas the input information to Function 1A identifies a specific building via its address, the contents of certain WA2 fields have a different significance for Function BL than for Function 1A. These fields are the BBL (in positions 29-38 for MSW and 34-44 for COW), the BIN (in positions 70-76 for MSW and 82-88 for COW), and the LGI (in positions 184-939 for MSW and 251-1363 for COW) of the regular WA2. All other WA2 fields have the same contents for both functions. For Function BL, the contents of the WA2 fields for the BBL, BIN and LGI are as follows:

- If the input BBL identifies a single-building non-condominium tax lot: The output BBL field contains the input BBL. The BIN field contains the BIN of the tax lot's only building. The LGI may contain all types of entries. As with Function 1A, the LGI may or may not be comprehensive with respect to the tax lot's real address ranges and with respect to its BINs.

- If the input BBL identifies a multi-building non-condominium tax lot: The output BBL field contains the input BBL. The BIN field contains the BIN of an arbitrary one of the tax lot's buildings. The LGI may contain all types of entries. As with Function 1A, the LGI may or may not be comprehensive with respect to the tax lot's real address ranges and with respect to its BINs.

- If the input BBL identifies a vacant tax lot, i.e., a tax lot that has no buildings: The output BBL field contains the input BBL. The BIN field contains the Borough Code followed by all zeros. The LGI consists of all of the pseudo-address ranges (type Q entries) assigned to the tax lot, and all vacant street frontages (type F entries) of the tax lot.

- If the input BBL identifies a condominium unit: The output BBL field contains the billing BBL of the condominium (except in cases where a billing BBL has not yet been assigned by DOF (or the billing BBL was not available when the Geosupport data files were

generated), in which case the BBL returned contains zeros and a warning message is issued). If the condominium occupies portions of more than one tax block, the output BBL field contains the billing BBL of the portion of the condominium that is specific to the tax block containing the input condominium unit. The BIN field contains the BIN of the building that contains that unit. The LGI contains building-related entries (real address ranges, NAUBs (type B entries), NAPs (type G, N and X entries) and blank-wall building frontages (type W entries)) only for the building containing the input condominium unit, and is comprehensive for that building. The LGI can contain all non-building-related types of entries (vacant street frontages (type F entries) and pseudo-address ranges (type Q entries)).

- If the input BBL is a billing BBL of a condominium: The output BBL field contains the input BBL. The BIN field contains the BIN of an arbitrary one of the condominium's buildings on the tax block identified by the input billing BBL. The LGI may contain all types of entries. As with Function 1A, the LGI may or may not be comprehensive with respect to the tax lot's real address ranges and with respect to its BINs.

VI.8 Standard and Legacy Versions of Functions 1A and BL

The version of Functions 1A and BL that is documented in this *User Programming Guide* is called the standard version. The standard version was first created in 1995 when major modifications were made to Functions 1A and BL. The predecessor version of Functions 1A and BL is called the legacy version. The legacy version is no longer supported and was discontinued as of version 10.0. If you have programs that use the legacy PAD, please refer to the Geosupport Technical Bulletin 05-1 dated February 18, 2005 for information on converting to standard PAD. Copies of this bulletin are available upon request to GSS_Feedback@planning.nyc.gov.

All MSW applications that invoke Functions 1A and BL must set the 1ABL Version Switch to the value 'S'. Note: COW applications only support standard PAD, so the 1ABL Version Switch is not applicable.

VI.9 Function BN

Function BN processes a building specified by an input BIN. Function BN does not have the long WA2 option. However, the Mode Switch of X (Extended) is available as an option.

The layout of the regular WA2 for Function BN is identical to that of the regular WA2 for Function 1A, while the layout of the Extended WA2 is the same as that of the Extended WA2 for Function 1A. However, in Function BN's WA2, the LGI contains entries only for the input building; not for any other buildings on the tax lot. It also does not contain any vacant street frontage (type F) or pseudo-address (type Q) entries. Function BN's LGI is always complete with respect to the input building, since there is no building in New York City that has more than 21 geographic identifiers.

Except for the difference in the contents of the LGI and its list counter field, the Number of Entries in the
LGI, the contents of Function BN's WA2 and Function 1A's regular WA2 are identical for a given tax lot.

VI.10 Function AP (COW Only)

Emergency Management and the Department of Health and Mental Hygiene have a need to geocode addresses to their corresponding CSCL address points. By geocoding to a CSCL address point, the user application will presumably geocode to a 'real' posted address – not an address that might be part of an administrative range for a building. The Functions AP and AP Extended [6] (a.k.a. APX) return the desired information.

Function AP processes input addresses. When Function AP is called using two work areas, it returns information in WA2 related to Address Point, tax lot and the building identified by the input data. Work Area 2 contains the Address Point ID and X, Y coordinates of the Address Point. It also contains some property information such as the BBL and BIN of the input address. Note that the Work Area 2 contains information related only to the input address, not to any other addresses or buildings on the lot.

The Work Area 2 layouts for Functions AP and AP Extended are very similar to those of Functions 1A and 1A Extended. Only those fields deemed necessary for the AP function are returned with AP and AP Extended. Fields that are not needed are filler. The field names in the copylibs are typically very similar to each other except for the prefixes.

Since the AP function is requesting the address point of only one address, Geosupport returns only one address in the Work Area 2 address list.

See the Function AP work area layouts in Appendix 13 (COW).

See Chapter V for a general discussion of Geosupport address processing, much of which is applicable to Function AP.

Function AP Extended Work Area 2 (Mode Switch set to 'X'). The first 246 bytes of the Extended Work Area 2 for Function AP, up to the "Number of Entries in List of Geographic Identifiers" field, are the same as with regular COW Work Area 2. Aside from adding some filler and the Function AP Reason Code, Warning Code, and GRC fields (which are identical to the WA1 fields) to the work area for Function AP Extended, the only change is in the address list. The street codes in the address list are B7SCs instead of B5SCs. **The Principal Street Name (based on the B7SC in the address list) is added to each element in the address list for the user's convenience.**

---

[6] Function AP Extended is also known as Function APX. It is invoked by calling Function AP with the Mode Switch set to X.

VI.11 Transitional Property Address Directory (TPAD) Building Identification Number (BIN) and status information for Functions 1A, 1B, BL and BN (COW Only)

(Note: For more information about the TPAD feature, including error processing, be sure to see Appendix 17.)

The TPAD File: The TPAD (Transitional Property Address Directory) file, allows users to get some up−to−date property related information. Geosupport has four functions (1A, 1B, BL and BN) that access the Property Address Directory (PAD) file. The PAD file contains property level information and is updated on a quarterly[7] basis. In order for users to get more up−to−date information regarding the status of new building construction and/or demolition, the Department of City Planning (DCP) has created the TPAD file.

The TPAD file is updated daily with new information received from the Department of Buildings (DOB) regarding job filings for new buildings (NB). DOB uses the BIN-On-Demand system to obtain a new BIN at the time that an applicant pre-files an application on an address not currently in Geosupport. The newly assigned BINs are included in the TPAD file. In addition, changes in status of both NB and demolition (DM) jobs are updated weekly.

Invoking the TPAD functionality: To invoke TPAD processing, Geosupport users set the TPAD request switch in Work Area 1. When this switch is set to 'Y' for a 1A, 1B, BL or BN call, Geosupport will read the TPAD file along with the PAD file, thereby being able to return more up−to−date information to users.

The TPAD Switch is located in position 329 of the COW Work Area 1. If the switch is set to 'N' or blank, then no TPAD processing is performed. If the TPAD Switch is set to "Y", then the following TPAD information will be returned to the user for Functions 1A, 1B, BL, and BN:

Work Area 2 Fixed Portion
Status of DM Job for BIN of the Input Address
New BIN for NB Job for Input Address or BBL
Status of NB Job
Conflict Flag

Work Area 2 Address List
Status of Job for this BIN in the Address List

TPAD Status Values are as follows:

TPAD Status Value	Associated Job Type	Description
space	n/a	No activity for this address
0	NB	New BIN issued (for DOB); NB Job application not yet filed

1	NB	NB Job application filed and paid for
2	NB	NB Job signed off [temporary or final Certificate of Occupancy (T/CO or C/O) issued]
3	NB	New BIN issued (for HPD[8]); NB Job application not yet filed
5	DM	DM Job application filed and paid for
6	DM	DM Job signed off (building demolished)

When the TPAD Switch is set 'on', Geosupport will always return a value in the TPAD Conflict Flag in Work Area 2. On occasion, when there are conflicts between the data in the PAD and the TPAD record, the Conflict Flag in Work Area 2 will be set to a value greater than '1'. The possible values of the Conflict Flag are described in the table below. See Appendix 17 for a detailed description of the contents of the Geosupport Return Code, Reason Code, Reason Code Qualifier, and Error Message, when TPAD processing is requested.

TPAD Conflict Flag Value	**Meaning (and associated TPAD Warning Message)**
0	TPAD data found, no conflicts with PAD data (no warning message returned)
1	PAD found, no TPAD data found (no warning message returned)
2	TPAD BBL used, no existing PAD BBL
3	TPAD BBL used, PAD pseudo−address on different BBL than TPAD NB BIN
4	TPAD BBL used, existing PAD BIN of Input Address on different BBL than TPAD NB BIN
5	(Not implemented)
6	TPAD BBL used, existing PAD BIN of Input Address with DM−5 on different BBL than TPAD NB BIN
7	TPAD BBL used, existing PAD BIN of Input Address with DM−6 on different BBL than TPAD NB BIN
8	PAD BBL used, TPAD NB BIN with NB−0 on different BBL than PAD BIN
9	PAD BBL used, TPAD NB BIN with NB−1 on different BBL than PAD BIN
A	PAD BBL used, TPAD NB BIN with NB−2 on different BBL than PAD BIN
B	PAD BBL used, TPAD NB BIN with NB−3 on different BBL than PAD BIN
C	TPAD data found, TPAD address overlaps PAD address
D	Address Found in TPAD, not found in PAD
E	BIN found in TPAD, not found in PAD

In mainframe GOAT (CICS), the TPAD information can be retrieved by entering a 'Y' in the 'TPADData' or 'TPAD' field on the 1A, 1B, BL and BN screens.

The mainframe GBAT control card for TPAD processing is TPADDATA, with values of 'YES' or 'NO'.

Interpreting the TPAD data

Because of the transitional nature of the data that can be returned by requesting the TPAD data, interpreting the data can sometimes be confusing. This section will describe how the transitional information is returned and try to reduce some of this confusion. The user should note, however, some situations will be inherently confusing and will require additional Geosupport function calls to clarify the situation.

Geosupport Processing when TPAD Information IS NOT requested:

The **BIN of Input Address** field will contain the BIN of a building that existed at the time of the Geosupport release.

The relationship of the **BIN of Input Address field** to the input for Geosupport 1A, 1B, BL and BN calls is as follows:

- 1A and 1B: The content of the BIN of Input Address field will be the BIN associated with the input address (if any).
- BL: For most BBLs the content of the BIN of Input Address field will be the single BIN associated with the input BBL. For those BBLs that have multiple associated BINs, this will be one of the BINs. There is no way of determining which BIN it will be.
- BN: The content will always be the input BIN.

Geosupport Processing when TPAD Information IS requested:

The goal of the Transitional PAD Data (TPAD) enhancements is to supplement the above information with data maintained in the Transitional PAD file. To accomplish this, Geosupport first makes a regular 1A, 1B, BL, or BN call. It then reads the Transitional PAD file for additional information. Three new fields (not including the TPAD Request Switch and Conflict Flag) have been added to WA2 to reflect this TPAD information. The new fields are:

1. The **TPAD BIN of Input Address Status** field will hold the status for the **BIN of Input Address** field.
2. The **TPAD New BIN** field will contain the BIN that has recently been issued for potential new construction.
3. The **TPAD New BIN Status** field will hold the status for the **TPAD New BIN** field.

TPAD Status For BIN of Input Address	Interpretation
Space	Building exists, there is no demolition pending
0	This status will not be used here
1	This status will not be used here
2	Building previously did not exist, but new building issued Certificate of Occupancy (C/O) after last PAD release
5	Building exists; a DM permit has been paid for

6	Building previously existed; DM was signed off after last PAD release

TPAD Status for New BIN

Value	Associated Job	Type Description
Blank		No activity for this address
0	NB	New BIN issued (for DOB); application not yet filed
1	NB	NB Job application filed and paid for
2	NB	NB Job signed off [temporary or final Certificate of Occupancy (T/CO or C/O) issued]
3	NB	New BIN issued (for HPD); application not yet filed
5	DM	DM Job application filed and paid for
6	DM	DM Job signed off (building demolished)

Address List TPAD Enhancements

For regular 1A, 1B, BL, and BN calls, the Address List contains alternate addresses associated with the BBL for 1A, 1B, and BL calls and with the BIN for BN calls. Each entry represents an address range and the BIN (if any) associated with this address. For TPAD enhancements we have done two things. We added a TPAD status field for each address entry. And, we have changed the order of the display of Addresses in the list. We list the BIN of Input Address first, followed by New BINs, if any, followed by Demolitions, followed by the rest of the addresses in the PAD record. For Long Work Area 2 requests, we have added a new field for each BIN, the TPAD Status field. Only 2187 BINs will be displayed in the Long Work Area 2 for TPAD requests.

Address List entries with BIN that existed at the time of the Geosupport Release

TPAD Status For Existing BIN	Interpretation
Space	Building exists, there is no demolition pending
0	This status is not used here
1	This status is not used here
2	This status is not used here
5	Building exists; a DM permit has been paid for
6	Building previously existed; DM was signed off after last PAD release

Address List entries with TPAD New BIN contain a newly assigned BIN for the input address.

TPAD Status For New BIN	Interpretation
Space	This status will not be used here

0	A New BIN has been assigned to the address, but its purpose is unknown
1	A New BIN has been assigned and a New Building Job has been paid for at DOB
2	A New BIN has been assigned and the building has been given a T/CO or C/O by DOB
5	This status is not used here
6	This status is not used here

The field names of the various TPAD−related fields in COW Work Area 1 and Work Area 2 are available in Appendix 13.

---

[7] As of Release 17A, those users who are on the DoITT mainframe typically will have PAD data that is updated weekly via the UPAD (Update PAD) file. Other users, e.g. Desktop users, will have PAD data that is updated quarterly. If desired, those users can make arrangements for more frequent updates. [8] HPD - Department of Housing Preservation and Development

CHAPTER VII

STREET CONFIGURATION PROCESSING - FUNCTIONS 2, 3, 3C, 3S

VII.1 Introduction

This chapter discusses various types of geographic locations known collectively as 'street configurations', and the Geosupport functions that process them. Street configurations are locations that are specified in terms of a combination of either two or three streets or a node ID (aka node number) .[9]

- The two-street configurations are street intersections, which are specified in terms of a pair of intersecting streets, or in terms of a single intersection name, or in terms of a node ID.
- The three-street configurations are locations that are specified in terms of an 'on' street between two cross streets. There are three types of three-street configurations: street segments, blockfaces, and street stretches.

Table VII-1 lists the types of street configurations that Geosupport can process, the data items required to specify each type, the functions that process them, and the sections of this chapter in which they are discussed. The final Chapter in this chapter describes borough boundary processing, a special feature of all the street configuration functions except Function 3S.

Table VII-1: Street Configuration Types and the Functions that Process Them

Street Configuration Type	**Specified By**	**Function**	**Section**
Intersections	● 2 intersecting streets and, if the 2 streets intersect twice, a compass direction specifying which intersection to process, -or- ● one intersection name –or- ● **(COW Only)** one node ID (required if streets intersect more than twice)	2 or 2W	VII.2
Street Segments (and related configurations)	● 'On' street and 2 consecutive (or 'nearly' consecutive) cross streets	3	VII.3 & VII.4
Blockfaces	● 'On' street, 2 consecutive cross streets, and compass direction specifying side of street	3C	VII.3 & VII.5
Street Stretches	● 'On' street and (optionally) any 2 cross streets and, if the 'on' street intersects a cross street twice, a compass direction specifying which intersection to process	3S	VII.3 & VII.6

Applications pass input streets to the street configuration functions in the appropriate WA1 input fields, either in the form of street names or in the form of street codes. In the case of two-street configurations, the order of the two input streets is immaterial; either input street may be passed in either WA1 input street field. In the case of three-street configurations, the 'on' street must be passed in the WA1 input 'on' street field; the two cross streets may be passed in either order in the two WA1 input cross street fields.

For any of the street configuration functions, input street names may be pseudo-street names or intersection names, except for the 'on' street in a three-street configuration. Place names may not serve as input street names. (For a discussion of non-street features, pseudo-street names, place names and intersection names, see Chapter III.6.) In the remainder of this chapter, the term 'street' refers to a street name or street code that conforms to the above criteria.

Geosupport processes street configurations based on a simplified model of the city's geography embodied in a digital map of New York City called CSCL (Citywide Street Centerline). The CSCL is a single-line map, that is, it represents streets and other linear geographic features, including railroad lines and shorelines, as single lines with no thickness, and it represents intersections as single points with no area or internal detail. In reality, of course, intersections occupy areas of various sizes and shapes, as reflected in a more realistic type of map known as a double-line map. The distinction between a single-line map and a double-line map is illustrated in Figure VII-1. The Department of City Planning extracts a version of the CSCL known as LION which may be more familiar to Geosupport Users and is available for download or for view on DCP's website:

http://www1.nyc.gov/site/planning/data-maps/open-data.page#lion

Figure VII-1: Single Line and Double-Line Maps Contrasted

[9] Node ID is described in [Chapter VII.2](/chapters/chapterVII/section02/). The phrase 'node number' may occasionally appear in Geosupport documentation and in copy books.

VII.2 Intersections: Function 2 and Function 2W

Note that any references to Function 2 apply to Function 2W as well, unless specifically stated otherwise. Note also that Function 2W is a COW-only function.

Function 2 is the Geosupport function that processes street intersections. Function 2 can process not only conventional street intersections, but also node IDs (COW only), intersection names and 'pseudo-intersections', that is, intersections of a conventional street with a pseudo-street (see Chapter III.6). There are three types of pseudo-intersections: dead ends, points at which a street intersects with the city limits, and bending points of streets. A point is considered a bending point if the angle of the street at that point is not within the range 160-200 degrees (i.e., not within 20 degrees of a straight line).

Nodes

We use the term node generically to refer to all types of intersections, both conventional and pseudo. Each node is assigned a unique node ID. Nodes, defined via street names and street codes, can serve not only as Function 2 input, but also as the delimiting endpoints of street stretches for input to the functions that process three-street configurations. Node IDs can serve as input only to a COW Function 2 or Function 2W call.

Formally, a node is a point along a street where one of the following occurs:

Figure VII-2: City Limit Point

- Conventional intersection of two streets: The street intersects with at least one other street (called a cross street). Example: 'the intersection of BROADWAY and CHAMBERS STREET in Manhattan'
- City Limit Point: The street (or non-street feature e.g. bridge or tunnel) intersects with the city limits. (The street may terminate at that point or it may continue as a suburban street). City Limit points occur at the Bronx-Westchester County border, the Queens-Nassau County border, the New York-New Jersey border and the Staten Island –New Jersey border.
  The New Jersey borders occur in the Hudson River, for example HOLLAND TUNNEL and CITY LIMIT in Manhattan. An example of Queens city limit is (see Figure VII-2): 'LINDEN BOULEVARD at the CITY LIMITS in Queens'

Figure VII-3: Dead End

- Dead End: The street has a termination point (called a dead end) that is not at the city limits and at which there are no cross streets. Example (see Figure VII-3): 'DEAD END of CROES AVENUE in the Bronx'. City limit points are excluded from being treated as possible dead ends because city streets may continue across the city limits into the adjacent suburban county.)

Figure VII-4: Bends

- Bend: The street has a bending point. Example (see Figure VII-4): 'BEND of COMMERCE STREET' and 'BEND of BARROW STREET' in Manhattan. Note that the bending point of Barrow is also a conventional street intersection, the intersection of Barrow and Commerce Streets. The Commerce Street bending point is not a conventional intersection, and can only be specified in terms of the pseudo-street BEND.

Conceptually, nodes can be characterized as those points along streets that can be specified in a form recognizable to Geosupport, that is, in the form of an intersection name, or a pair of street codes or a pair of street names that possess street codes, or a node ID (in a COW function call). One, and only one, street of a pair may be a pseudo-street.

The allowable pseudo-streets are DEAD END and its aliases, CITY LIMITS and its aliases, and BEND and its aliases. See Chapter III.6 for a discussion of pseudo-street names.

Number of Intersections of a Pair of Streets

Given any pair of New York City streets (or a street and a pseudo-street), there are four possibilities:

- The two streets do not intersect at all.
- They intersect at one location (the 'unique-node case').
- They intersect twice (the 'two-node case').
- They intersect more than twice (the 'many-node case').

Function 2 can process a pair of input streets in the unique-node case and in the two-node case, but a node ID is required as input in the many-node case (supported only in COW). If the user does not know the node ID, Function 2W may be used to assist the user in determining the appropriate node ID. For a description of this process, see the Overview of Function 2 Node Enhancements and the discussion of the many-node case in Specifying Function 2 Input Data below. Note that aside from dead ends, bends, subway lines, highways, etc., the many-node case is rare. There are numerous streets that have more than two dead ends, and there are numerous streets that have more than two bends.

The Two-Node Case

The two-node case occurs with greater frequency than might be expected. Some types of situations in which the two-node case occurs are the following:

Figure VII-5: Street Intersecting Twice with Curved Street

- A street bends or curves, causing it to intersect with a second street at two different points. An example in Queens is the two intersections of the curved street Cromwell Crescent with Alderton Street (see Figure VII-5).

Figure VII-6: 'Dogleg'

- A street has a displacement or offset as it crosses another street (a configuration sometimes called a 'dogleg'), so that there are two points where the two streets intersect. An example in Brooklyn is Ditmas Avenue where it crosses Coney Island Avenue (Figure VII-6).

Figure VII-7: Street Fork

- A street forks into two branches (for example, around a traffic island, plaza or small park) such that both branches have the same street name and they both intersect with another street. An example in Manhattan is Duane Street, which forks around a small triangular park; both branches of Duane Street intersect with Hudson Street (Figure VII-7).

Figure VII-8: Street With Two Dead Ends

- A street has exactly two dead ends. An example in the Bronx is Odell Street (Figure VII-8). The two pseudo-intersections of Odell Street with the pseudo-street DEAD END are considered to be an instance of the two-node case. Similarly, streets that have exactly two intersections with the city limit, and streets that have exactly two bending points, are instances of the two-node case.

Overview of Function 2 Node Enhancements

(COW Only)
Node ID (Node Number) as Input
Processing the 'Many-Node' Case

A unique Node Number known as a node ID is assigned to each of New York City's intersections. Geosupport returns node IDs for many of its functions, e.g. 1/1E Extended, 1B, 2, 3, 3C, 3S. Users in a GIS environment also have access to the node IDs via CSCL or LION. Users can specify a node ID as input to Function 2 and get information about the intersection without specifying cross streets or an intersection name. Geosupport also uses node IDs to allow processing of streets that intersect more than twice.

Function 2W is available to all users
Function 2W returns a 4000-byte Work Area 2. The first 200 bytes are identical to the entire Work Area 2 of regular Function 2. Additional information appears in the remainder of the Function 2W Work Area 2, which can be used in processing streets that intersect more than twice.

Node as Input to Function 2
Users have requested the ability to retrieve information about an intersection based on the intersection's Node Number. That capability has been added to Function 2 (and Function 2W). Work Area 1 has a Node Number input field where the user specifies the node input. A Node Number output field is also defined in Work Area 1 where the normalized (right-justified and zero-filled) Node Number appears. If the user also inputs street names or street codes, they will be ignored and the Node Number input will take priority.

Processing Two Streets that Intersect more than twice ('Many-Node case')
Users have also requested the ability to retrieve information about an intersection of two streets that intersect more than twice. If two streets intersect more than twice for a Function 2 call, the user will now get an error message (GRC 03 Reason Code A) suggesting that the user run Function 2W to get related nodes.

The same input that is rejected above (streets that intersect more than twice) will be rejected when those streets are processed by Function 2W. Function 2W will return an error message (GRC 03 Reason Code B) that tells the user to use a node as input – **However, - In Addition to GRC 03/A and an Error Message, Function 2W will also Return A Work Area 2 (WA2) that Contains Related Nodes and Street Codes.** This is unique in Geosupport because rejected calls normally do not return information in Work Area 2. The Function 2W WA2 will include the Node Numbers of all the nodes satisfying the input (up to 20 nodes) and a list of B7SCs of the intersecting streets at each node,

Based on the Node Numbers and the Street Codes, the user can choose which node should be processed. The user then issues a Function 2 or 2W call with the node ID as input and that call should execute successfully.

GBAT support of Node Input to Function 2
GBAT has a new option called NODE where the user specifies the location of the Node input. When NODE is input to GBAT the GBAT statistics will not be broken down by borough since

borough is not a required part of the input. It is recommended that users not specify streets as input together with nodes for a GBAT run since none of the output statistics will be broken down by borough.

GBAT support of Streets that Intersect more than twice

GBAT has a new option, called RELATEDNODES, for Function 2. If the user requests RELATEDNODES and the streets intersect more than twice (GRC 03 Reason Code A or B) GBAT will issue a Function 2W call under the covers, and get the nodes and street codes information from WA2. GBAT will place this information in a separate error file, viz. ERRFIL3 which the user can examine and then choose the node to be processed. The NODE can then be used as input to a subsequent run.

In addition to the entry in ERRFIL3 (which contains the nodes and street codes list), GBAT creates a normal error entry in the standard error file (viz. ERRFILE)

Note that when a GBAT entry is rejected with GRC03 it will not be written to the GBAT output file (OUTFILE) even if it is for Function 2W which generates a WA2 in this situation. The information is returned to the user in ERRFIL3.

GOAT support of Streets that Intersect more than twice

When input streets intersect more than twice, Mainframe GOAT (CICS) and the web version of GOAT on the Web display a list of up to 20 nodes and the cross streets at these nodes, with their street codes and street names. The user can then more easily choose a node and reissue the GOAT call using the chosen node as input.

Specifying Function 2 Input Data

Applications pass input to Function 2/2W by specifying either an intersection name, or two distinct streets (i.e., two streets that have different B5SCs), or a node ID (COW only) identifying the intersection. If the input information is in the form of an intersection name, it may be passed in either WA1 input street name field, and the other field should preferably be left blank or it may contain any conventional street that exists at the given intersection. If the input data are in the form of two streets that are an instance of the two-node case, an input compass direction ('N', 'S', 'E' or 'W') must also be specified. The compass direction identifies which of the two nodes is to be processed, by specifying that node's spatial position relative to the other one. For example, if 'N' is specified as the input compass direction, then Function 2 will process the northernmost of the two nodes. If the user knows the node ID of the intersection, this may be used as input instead of the two streets and a compass direction. If the input information is in the form of a node ID, a borough code is not required and is ignored if supplied.

Figure VII-9: Simultaneous 2-Node and Unique-Node Case

Note that an intersection may be an instance of the two-node case when specified (with a compass direction) in
terms of a particular pair of streets, while the same intersection may be an instance of the unique-node case when specified (without a compass direction) in terms of a different pair of streets. For example, in Staten Island, Industrial Loop and Arthur Kill Road intersect at two nodes (see Figure VII-9). When specifying either of those nodes as an intersection of Industrial Loop and Arthur Kill Road, a compass direction is required. However, at the northern (or alternatively, the eastern) one of those nodes, there is a third street, Grille Court. That node can be specified, without a compass direction, as the unique intersection either of Grille Court and Industrial Loop, or of Grille Court and Arthur Kill Road. That node could alternatively be identified by its node ID (viz. 0000890) and no street names are needed.
In some instances of the two-node case, the two nodes are 'nearly' (i.e., within 10 compass degrees of) due east-west of each other. In that event, attempting to distinguish between the two nodes in terms of the compass directions north and south would be highly error-prone. In those cases, therefore, Function 2 accepts only 'E' and 'W' as valid input compass directions. Similarly, if the spatial relationship between the two nodes is 'nearly' (within 10 degrees of) due north-south, Function 2 accepts only 'N' and 'S'.

For Manhattan only, in the two-node case, Geosupport rotates the spatial relationship between the pairs of nodes 30 degrees counterclockwise before determining whether they are 'nearly' north-south or east-west of each other. This comports with the widespread conventional treatment of the avenues and streets in most of Manhattan as if they were oriented due north-south and due east-west, respectively. In reality, Manhattan's principal street pattern lies approximately at a 30-degree clockwise rotation from the cardinal points of the compass. For a more detailed discussion of the 30-degree rotation for Manhattan, see the entry for Segment Orientation in Appendix 3.

In most instances of the two-node case, the two nodes have a pronounced 'diagonal' spatial relationship, that is, they are not within 10 degrees of either due north-south or due east-west of each other. In that case, Function 2 accepts all four compass directions as valid input. For example, either 'N' or 'W' is accepted as a specification for the northwestern intersection of Alderton Street and Cromwell Crescent (the intersection highlighted on the upper left in Figure VII-5); either 'S' or 'E' is accepted as a specification for the southeastern (lower right) intersection of these streets.

In the two-node case, a user must supply a compass direction, with street names, to issue a successful call. Alternatively, the user may supply a node ID instead of the street names and a compass direction. If the two nodes in the two-node-case are close together, under certain conditions it may not matter which intersection is selected. For example, if a medical emergency occurred at the intersection of Reade and Elk Streets in Manhattan, when reporting the location it would not matter which of the two intersections was provided since the two intersections are separated by about 21 feet. On the other hand, if the medical emergency is reported as having occurred at the intersection of Castle Hill Avenue and Zerega Avenue in the Bronx, a more precise compass direction is required since the two intersections are separated by about 10,631 feet or roughly two miles.

When no compass direction is supplied, the error message returned by Geosupport (GRC 02) for a two-node case includes the distance, in feet, between the two nodes. Depending upon the circumstance, the user may make a reasoned decision as to whether the precise intersection is required or if it does not make any difference which intersection is requested.

In the many-node case, a user must supply a node ID as input to issue a successful call. A node ID is accepted as input only to COW Function 2 or 2W. If the user does not have the node ID Function 2W may be invoked to retrieve the node IDs and B7SCs that exist at the duplicate intersections. The user may then invoke Function 2 or 2W with the node ID of his choice.

The procedure is as follows:

- When an **MSW Function 2 call** is issued with streets that intersect more than twice, the resulting message is:
  GRC 03 Reason Code is ‘blank’.

```
‘STREETS INTERSECT MORE THAN TWICE - CAN ONLY BE PROCESSED BY
COW FUNCTION CALL’
```

The user can now modify his application to issue a COW Function 2 call and proceed as defined below. Note that the Reason Code no longer contains the number of times that the streets intersect (3 through 9).

- When a **COW Function 2 call** is issued with streets that intersect more than twice, the resulting message is:
  GRC 03 Reason Code is ‘A’.

  ```
  ‘STREETS INTERSECT MORE THAN TWICE-USE FUNCTION 2W TO FIND
  RELATED NODES’
  ```

  The user can now modify his application to issue a COW Function 2W call and proceed as follows.

- When a **COW Function 2W call** is issued with streets that intersect more than twice, the resulting message is:
  GRC 03 Reason Code is ‘B’.

‘STREETS INTERSECT MORE THAN TWICE - USE NODE AS INPUT’

In addition to the error message, Function 2W also returns a Work Area 2 which contains the node IDs (up to 20 nodes) where the streets intersect and also the B7SCs of the streets at those nodes. There can be up to 5 intersecting streets at each node, and each of those streets may have up to 4 aliases. The user can then choose a node and issue a COW Function 2 or 2W call with that node ID as input. The call should then be successful. See Appendix 13 for the detail layout of Work Area 2 for Function 2W.

Note: The GRC 03 message returns ‘blank’, ‘A’, or ‘B’ as the Reason Code. It no longer returns the number of intersections (3 through 9) as the Reason Code .

Possible Outcomes of a Function 2 or 2W Call

Table VII-2 lists possible outcomes of a Function 2 or 2W call by Geosupport Return Code (GRC). Table VII-2 does not include standard reject conditions that are applicable to most Geosupport functions, such as an inability to normalize or recognize an input street name. In Table VII-2, the term ‘intersection’ also encompasses pseudo-intersections.

Table VII-2: Possible Outcomes of a Function 2 and 2W Call
Possible Outcomes of a Function 2 and 2W Call

Possible Outcomes of a Function 2 and 2W Call	
GRC/ Reason Code	**Meaning**
00	(Successful call) If the input information was in the form of an intersection name, it was recognized as a valid name of a specific intersection. If the input information was in the form of two streets, they intersect once or twice, and if twice, an input compass direction has been supplied which is a valid descriptor for one of those intersections. A full complement of output data is returned in the work areas.
01/H	(Warning) The two input streets intersect once, but the input compass direction field is non-blank. The input compass direction field is ignored. A full complement of output data is returned in the work areas.
01/N	(Warning) Both a node ID and street names or street codes were specified as input. The node ID will be used; the street names/codes will be ignored.
01/T	(Warning) The input street name is ignored if an intersection name is specified along with a street name that is part of the intersection.
02	(Reject) The two input streets intersect twice, but the input compass direction field is blank. A valid input compass direction value is required for these input streets.
03/blank	(Reject) MSW - The two input streets intersect more than twice. MSW Function 2 calls cannot process such intersections. The Reason Code value is blank. The message suggests that the user use a COW function call.

03/A	(Reject) COW - The two input streets intersect more than twice. Function 2 calls cannot process such intersections. The message suggests that the user issue a Function 2W call to find related nodes.
03/B	(Reject) COW – Function 2W only - The two input streets intersect more than twice. Function 2W returns node IDs and street codes. The message suggests that the user use a node ID as input.
12	(Reject) The input information was in the form of an intersection name or a street code of an intersection name. Geosupport recognizes this name or code as valid, but does not yet have this name or code associated with a specific intersection.
30	(Reject) An input intersection name was specified along with an input street name, but the input street is not part of the intersection.
32	(Reject) An invalid node ID was specified as input. It was non-numeric or had embedded blanks..
33	(Reject) A node ID was specified as input, but no intersection was found with that node ID.
39	(Reject) The input compass direction field contains a non-blank value other than ‘E’, ‘N’, ‘S’ or ‘W’.
40	(Reject) The two input streets intersect twice, but the two intersections are nearly N-S or E-W of each other and the input compass direction is an invalid descriptor for either of the intersections.
62	(Reject) If the input data were in the form of two input street names or codes, the two input streets do not intersect.

Function 2 Output Data

Among COW Function 2’s WA1 output items are the following:

- **B7SCs and 32-byte street names of the intersecting streets** appear in the List of Street Codes and List of Street Names fields..

Among Function 2’s WA2 output items are the following:

- **Identifiers for a set of geographic districts** that contain the intersection, including Census Tract, Community District and Police Precinct. The COW WA2 also includes Sanitation District and Health Center District.
- **Spatial Coordinates of the intersection.** These correspond to a nominal center point of the intersection and should not be treated as a precise identification of any particular point location on the earth’s surface. (For a more detailed discussion, see the Spatial Coordinates entry in Appendix 3.)
- **A List of Intersecting Streets** (in the form of PB5SCs for MSW and B5SCs for COW) identifying up to five streets incident upon the intersection. Subject to the space limitation, the list may include the PB5SCs or B5SCs of the two input streets, unless one is the pseudo-street BEND, which for Function 2 is never included in the list. The list may also

include the PB5SCs or B5SCs of the pseudo-streets CITY LIMIT and DEAD END, and it may include the PB5SCs or B5SCs of any intersection names that are valid for the given intersection. If the application has a need to display the street names of the intersecting streets, the Cross Street Names Flag in WA1 can be turned 'on' and the names will be returned in the List of Street Names in WA1 (see entries for Cross Street Names Flag and List of Street Names in Appendix 3). Note that the cross street names feature incurs processing overhead, and should only be used when necessary.

- A Compass Direction for Intersection Key. If the first two entries in the List of Intersecting Streets are an instance of the two-node case (i.e., they intersect twice), the Compass Direction for Intersection Key contains a compass direction value identifying the intersection in terms of those two streets. If the two streets are not an instance of the two-node case, this field is blank. If both a 'longitudinal' compass direction ('N' or 'S') and a 'latitudinal' compass direction ('E' or 'W') are valid for this intersection, the longitudinal compass direction value appears in this field.
- **A Compass Direction for Intersection Key**. If the first two entries in the List of Intersecting Streets are an instance of the two-node case (i.e., they intersect twice), the Compass Direction for Intersection Key contains a compass direction value identifying the intersection in terms of those two streets. If the two streets are not an instance of the two-node case, this field is blank. If both a 'longitudinal' compass direction ('N' or 'S') and a 'latitudinal' compass direction ('E' or 'W') are valid for this intersection, the longitudinal compass direction value appears in this field.
- **Political geography and CD Eligibility (COW Only)**. Function 2 returns Assembly District, Congressional District, State Senatorial District, Civil Court District, City Council District and CD Eligibility. Since it is possible that multiple political geographies may exist at an intersection, Geosupport returns the political geography associated with the most frequently occurring Election District / Assembly District (ED/AD). If there is no one political geography that occurs more frequently than any other, then the political geography associated with the ED/AD that is one of the most frequently occurring ED/ADs and that has the lowest numeric value is selected. This insures that the same data will be returned from one data cycle to the next data cycle. The only exception should be the changes in the political geography associated with the decennial census conducted by the federal government. No indication is provided that the intersection lies on a political boundary

Since Function 2 treats street intersections as if they were single points, Geosupport does not provide a means for a user to request information specific to a portion of an intersection, such as a particular block corner. In the event that an intersection lies on a boundary of two or more geographic districts of a particular type, Function 2 returns the identifier for one of those districts, but provides no indication that some of the intersection's corners may lie in other districts. The district identifier that is returned for such an intersection is selected using an algorithm based on the community districts and atomic polygons (previously known as dynamic blocks) at that intersection. This algorithm typically allows for data consistency from one data release to the next. Note that the same district identifier will be returned no matter how the intersection is specified.

For example, the intersection of East 116 Street and Fifth Avenue in Manhattan lies on the boundaries of three different School Districts (SDs) (see Figure VII-10). Two of the four block corners at this intersection lie in SD 3, one lies in SD 4 and one lies in SD 5. For this intersection, Function 2 returns SD 3, and provides no indication that the intersection lies on a SD boundary.

Figure V11-10: Multiple Districts at an Intersection

Multi-Street Intersections and Retrieval Consistency

This subsection discusses the common situation of intersections at which there are more than two streets. Geosupport accepts any pair of those streets as a valid input specification for the intersection. (The concept of an intersection of multiple streets should not be confused with the concept of two streets that intersect at multiple points, which was discussed in the preceding subsection.)

For example, consider the three-street intersection of Hudson Street, Chambers Street and West Broadway in Manhattan (Figure VII-11). The user can specify this intersection as input to Function 2 in three ways: as the intersection of Hudson Street and Chambers Street; Hudson Street and West Broadway; or Chambers Street and West Broadway.

Figure V11-11: Three - Street Intersection

Similarly, a four-street intersection can be specified in six ways, etc. Function 2 returns identical WA2 information (other than that related to which streets were the input streets for the call) for an intersection regardless of which pair of streets is used to specify it.
Since an intersection of more than two streets can be specified in more than one way, an important issue for some applications that process data by intersection is the ability to retrieve or match data from an application file consistently by intersection. (For a general discussion of the concept of application file geographic retrieval consistency, see Section I.3.) That is, it is desirable for applications to be able to retrieve data successfully for a multi-street intersection regardless of which pair of streets is used to identify the intersection. A data item called the Node ID, which is returned in Function 2's WA2, is designed to serve effectively as a unique, consistent intersection identifier. It is able to so serve because the same Node ID Number is returned regardless of how the intersection is specified. Moreover, the Node ID assigned to an intersection is kept constant over time. That is, the same Node ID is returned for a given intersection by every Geosupport release, even in cases where there is a change in the set of streets defining an intersection (such as the presence of a new street, the closure of an existing street, or a change in the street code assigned to a street).

Fuzzy Intersection Processing (Function 2) - Front-truncated street names

Under certain conditions, Function 2 will return data when front-truncated street names are given as input; e.g. 14 STREET instead of EAST 14 STREET or WEST 14 STREET. If a user supplies a front-truncated street name as one of the names that define an intersection, Geosupport will attempt to find the intersection using the appropriate street names. If Geosupport is successful in finding the

intersection, it will process the call and issue a warning message (Reason Code J) indicating which street name was assumed. The following are a number of examples and special cases of this processing.

Consider the example of a user who issues a Function 2 call with 24 STREET and THIRD AVENUE in Manhattan as the input. Since 24 STREET in Manhattan is a front-truncated street name, Geosupport knows that there exists an EAST 24 STREET and a WEST 24 STREET in Manhattan. Geosupport attempts to find the intersection of East 24 Street and Third Avenue and the intersection of West 24 Street and Third Avenue in Manhattan. Since the intersection of East 24 Street and Third Avenue does exist in Manhattan and the intersection of West 24 Street and Third Avenue does not exist, data for the intersection of East 24 Street and Third Avenue in Manhattan is returned to the user, together with a warning message indicating that East 24 Street is assumed.

If the user supplies the front-truncated street name 34 STREET and FIFTH AVENUE in Manhattan as input to a Function 2 call, Geosupport will discover that both the intersection of EAST 34 STREET and FIFTH AVENUE and the intersection of WEST 34 STREET and FIFTH AVENUE exist. In this case, the Node IDs will be compared. Since, in this case, the Node IDs are the same, data for the intersection will be returned to the user. The street with the lower numeric value for its street code will be returned, which in this example is East 34 Street. The user will also receive a warning message indicating that East 34 Street is assumed.

If the user supplies the front-truncated street name 177 STREET and JEROME AVENUE in the Bronx as input to a Function 2 call, Geosupport will find that both the intersection of EAST 177 STREET and JEROME AVENUE and the intersection of WEST 177 STREET and JEROME AVENUE exist. However in this case the Node IDs will be different because a dogleg exists at the intersection. The Function 2 call would be rejected with an error message indicating that the intersection is not unique. As a result, the user must determine whether East or West 177 Street is the desired street.

Non-addressable Place Names (NAPs) will not be considered when processing truncated street names at an intersection. For example, if the user supplies ‘33’ and MADISON AVENUE in Manhattan as the input to a Function 2 call, Geosupport will find that in addition to EAST 33 STREET and WEST 33 STREET, there is also 33 POLICE PRECINCT. 33 Police Precinct is eliminated as a possibility because it is a NAP which may not be used in a Function 2 call. This leaves only East and West 33 Street as possibilities and since only East 33 Street intersects Madison Avenue in Manhattan, the call will be processed successfully and a warning message will indicate a street name change.

Note Concerning the ‘Vestigial’ Function 2C:

A Geosupport enhancement that was implemented in Version 9.5 (March 1998) enabled Function 2 to process pairs of streets that intersect twice, using the input compass direction field to identify the specific intersection to be processed. Prior to that enhancement, Function 2 could only process pairs of streets that intersect once, and a separate function, Function 2C, had to be used to process pairs of streets that intersect twice. The enhancement enabled Function 2 to process both types of

intersection input, rendering Function 2C obsolete. Function 2C is a 'vestigial' function, in the sense in which this term is described in Chapter I.5. In particular, all new applications should be designed to perform all intersection processing using Function 2 only. It is recommended that users modify existing applications by replacing all Function 2C calls with Function 2 calls. To do so, it may be necessary or appropriate to modify the application's reject handling routines to reflect the situations and GRC's delineated in Table VII-2. Function 2C is not further documented in this *User Programming Guide*.

VII.3 Three-Street Configurations - Concepts and Terminology

There are many applications in which geographic locations to be processed are identified in terms of an 'on' street between two cross streets. Geosupport can process several types of such locations, namely street segments, blockfaces and street stretches. We refer generically to all these types of locations as three-street configurations.

This section introduces concepts and terminology needed to discuss three-street configurations. The three succeeding sections discuss the Geosupport functions that process the various types of three-street configurations:

- Chapter VII.4 discusses Function 3, which processes street segments
- Chapter VII.5 discusses Function 3C, which processes blockfaces
- Chapter VII.6 discusses Function 3S, which processes street stretches.

The definitions below are based on Geosupport's single-line map model of the city's geography, as explained in Chapter VII.1. Also, recall that the term 'street' refers to a street name or street code that satisfies the criteria delineated in Chapter VII.1. The term 'node' is as defined in Chapter VII-2.

Street Stretches and Street Segments

A street stretch is a portion (possibly all) of a street (called the 'on' street) between any two nodes along it (called the delimiting nodes of the stretch). A street stretch is considered to comprise both sides of the 'on' street.

For Geosupport purposes, a street segment is defined as a street stretch between a pair of delimiting nodes which may not coincide with an intersecting street . A street segment can therefore consist of a set of one or more CSCL segments.

In Geosupport, the general term 'street segment' is used to describe two situations.

- A street segment is strictly defined as a street stretch such that the two delimiting nodes are consecutive along the 'on' street. Every such segment is uniquely identified by a segment ID.

- For Geosupport purposes, a street segment often refers to a street stretch consisting of more than one segment, such that at least one side of the street stretch is a single entire blockface. This street stretch is defined by multiple segments id's, all of which may optionally be returned to the user. For a more detailed discussion see Chapter VII.4, which describes Function 3.

Every street stretch is composed of a set of one or more street segments, which do not necessarily form a continuously connected chain. That is, a street stretch can encompass gaps in the street.

Some examples of street stretches and segments follow.

Figure V11-12: Street Stretch

- The stretch of Madison Avenue between East 51st Street and East 52nd Street in Manhattan (see Figure VII-12) is a street segment. The stretch of Madison Avenue between East 51st Street and East 54th Street is not a segment because its delimiting nodes are not consecutive along the 'on' street; it is a stretch consisting of three segments.

FigureV11-13: Street Stretch Containing Gap

- An example of a street stretch that is not connected is Manhattan's West 64th Street between Central Park West and West End Avenue (see Figure VII-13). West 64th Street has a gap (does not exist) between Columbus Avenue and Amsterdam Avenue, where it is interrupted by Lincoln Center. As a result, the stretch in question consists of two sub-stretches that are not connected to each other.

Street stretches can be delimited by pseudo-intersections and intersection names as well as conventional street intersections:

- An example of a street segment in the Bronx delimited by a dead end is CROES AVENUE between WATSON AVENUE and DEAD END (see Figure VII-3).

- An example of a street stretch in Queens delimited by the city limits is LINDEN BOULEVARD between CROSS ISLAND PARKWAY and CITY LIMITS (see Figure VII-2).

- Some examples of street segments in Manhattan delimited by bends are: BARROW STREET between HUDSON STREET and BEND (also specifiable in terms of conventional streets as BARROW STREET between HUDSON STREET and COMMERCE STREET); and COMMERCE STREET between BARROW STREET and BEND (the only way to specify this segment) (see Figure VII-4).

Logical Direction Assigned to Streets

GSS has assigned a logical direction to every street segment in New York City. References to the left and right sides of any segment, and references to its delimiting nodes as the 'from' node and 'to' node, are relative to the segment's logical direction.

For streets that have addresses, the logical direction is always assigned as the direction of increasing addresses. Therefore, for any street with addresses, the 'from' node of any segment is always the node at its low address end, and the 'to' node is the node at the high address end; the left and right sides of the segment are determined accordingly.

For features that have no addresses, such as all railroad tracks and some highways, the logical direction is assigned arbitrarily, but consistently, along the feature's full extent. Note that a street's logical direction, and thus the meaning of 'from', 'to', 'left' and 'right', is unrelated to the street's traffic direction, to its orientation with respect to the points of the compass, or to the order in which cross streets delimiting a stretch are specified.

Blockfaces

A blockface is a continuous frontage of a physical city block along one street, ignoring the presence of any bending points or other intervening nodes. That is, the portions of a street frontage of a block that lie on both sides of a bending point are considered to be parts of the same blockface.

FigureV11-14: Block with Four Blockfaces

For example, the Manhattan block bounded by Madison and Park Avenues and East 51st and East 52nd Streets has the following four blockfaces (see Figure VII-14, which, unlike most of the figures in this chapter, contains a double-line map to illustrate clearly the concept of a blockface):

- The east side of Madison Avenue between East 51st and East 52nd Streets
- The south side of East 52nd Street between Madison and Park Avenues
- The west side of Park Avenue between East 51st and East 52nd Streets
- The north side of East 51st Street between Madison and Park Avenues

An example of a stretch with a bending point in Manhattan is Commerce Street between Bedford and Barrow Streets (see Figure VII-4). Both sides of this stretch are single blockfaces, even though the stretch consists of two segments connected at the bending point.

T-Intersections

Figure VII-15 T-Intersection

A street stretch, and in particular a street segment, is considered to comprise both sides of the 'on' street. In the case of a street segment, each side necessarily is either a single entire blockface or a portion of one. Many segments consist of a pair of facing entire blockfaces along the 'on' street. However, this is not the case at a street configuration called a T-intersection. A T-intersection (so named because the streets are configured like the letter 'T') is an intersection where a cross street intersects the 'on' street on one side of the 'on' street only, and there are no cross streets on the other side of the 'on' street at that intersection. At a T-intersection, the 'on' street has a blockface that encompasses more than one segment, and conversely, at least one side of each of those segments consists of only a portion of that blockface.

An example of a T-intersection in Manhattan is the intersection of Fifth Avenue and East 41st Street (Figure VII-15). Because of the presence of the New York Public Library main building along the west side of Fifth Avenue between West 40th and West 42nd Streets, there are no cross streets on the west side of Fifth Avenue where it intersects with East 41st Street. The long blockface on the west side of Fifth Avenue encompasses two segments, each consisting of a portion of this long blockface facing a shorter entire blockface on the east side of Fifth Avenue.

Figure VII-16: Two Consecutive T- Intersections

It is possible for a street to have T-intersections at several consecutive nodes. An example in Manhattan is the three-segment stretch of Lexington Avenue between East 42nd and East 45th Streets (Figure VII-16). Because of the presence of the Grand Central Terminal complex on the west side of Lexington Avenue, East 43rd Street and East 44th Street intersect Lexington Avenue only on its east side, forming two consecutive T-intersections along Lexington Avenue. As a result, the west side of this stretch is a single long blockface, which faces three shorter blockfaces on the east side of Lexington Avenue.

Figure VII-17: T-Intersections on Alternating Sides of street

When a street has consecutive T-intersections at which the cross streets are on alternating sides of the 'on' street, then long blockfaces on both sides of the 'on' street face each other in overlapping fashion, forming segments both sides of which consist of portions of those long blockfaces. Union Avenue in Staten Island is an example (Figure VII-17). Note that Union Avenue between Leyden Avenue and Walloon Street is a street segment, because the two delimiting intersections are consecutive along Union Avenue, even though the cross streets are on opposite sides of the 'on' street.

VII.4 Street Segments and Related Configurations: Function 3

Function 3 is designed to accept as input portions of a street that are, loosely speaking, ‘one block long’. More precisely, Function 3 processes two types of input street stretches:

- Street segments (i.e., portions of a street between two consecutive nodes).
- Street stretches consisting of more than one segment, such that at least one side of the street stretch is a single entire blockface. (Note that the user has the option of requesting that all segment ids in this type of output stretch be returned. See discussion of the Auxiliary Segment switch in the description of Function 3 output.) This type of input street stretch has three sub-cases:
    - At a T-intersection, there is a street stretch in which one side is a single entire blockface.
    - At a bending point at which there are no cross streets, there is a street stretch in which both sides are single entire blockfaces.
    - Physical street segments that are split into multiple sub-segments because of a change in some district such as ZIP codes or police beats.

The following examples illustrate the types of input data acceptable and not acceptable to Function 3. For the Lexington Avenue examples (in Manhattan), see Figure VII-16. For the Union Avenue examples (in Staten Island), see Figure VII-17. For the Commerce Street examples (in Manhattan), see Figure VII-4. For the Croes Avenue example (in the Bronx), see Figure VII-3.

Input Data Examples for Function 3

Input ‘On’ Street	**One Cross Str.**	**Other Cross Str.**	**Fn 3 Action**	**Reason for Action**
Lexington Avenue	East 42 Street	East 43 Street	Accepted	Single segment
Lexington Avenue	East 43 Street	East 44 Street	Accepted	Single segment
Lexington Avenue	East 44 Street	East 45 Street	Accepted	Single segment
Lexington Avenue	East 42 Street	East 45 Street	Accepted	Single entire blockface on west side of Lexington Ave
Lexington Avenue	East 42 Street	East 44 Street	Rejected	Multi-segment, neither side of Lex. Ave is a single entire blockface - west side is a portion of a blockface, east side comprises 2 blockfaces.

Lexington Avenue	East 43 Street	East 45 Street	Rejected	Multi-segment, neither side of Lex. Ave is a single entire blockface - west side is a portion of a blockface, east side comprises 2 blockfaces.
Union Avenue	Leyden Avenue	Walloon Street	Accepted	Single segment
Union Avenue	Walloon Street	Journey Street	Accepted	Single segment
Union Avenue	Journey Street	Union Court	Accepted	Single segment
Union Avenue	Union Court	Brabant Street	Accepted	Single segment
Union Avenue	Leyden Avenue	Journey Street	Accepted	Single entire blockface on west side of Union Avenue
Union Avenue	Walloon Street	Union Court	Accepted	Single entire blockface on east side of Union Avenue
Union Avenue	Journey Street	Brabant Street	Accepted	Single entire blockface on west side of Union Avenue
Commerce Street	Barrow Street	Bend	Accepted	Single segment
Commerce Street	Bedford Street	Bend	Accepted	Single segment
Commerce Street	Barrow Street	Bedford Street	Accepted	Both sides are single entire blockfaces
Croes Avenue	Watson Avenue	Dead End	Accepted	Single entire segment

Function 3 Input Data Specification and Validation

Applications pass an input stretch to Function 3 by specifying three input streets, consisting of the ‘on’ street and two cross streets, in the appropriate WA1 input fields. The input cross streets, but not the ‘on’ street, may be pseudo-streets or intersection names. The input cross streets may be specified in either order. As with all Geosupport street input, the three input streets to a Function 3 call are specified in the form of either street names or street codes.

If either or both of the delimiting intersections of the input stretch has more than one cross street, the stretch may be specified using any of those cross streets. For example, the segment of Chambers Street illustrated in Figure VII-11 may be specified either as ‘Chambers Street between Church Street and West Broadway’, or as ‘Chambers Street between Church Street and Hudson Street’.

A successful two-work-area call to Function 3 signifies that the three input streets form a combination of an ‘on’ street and two cross streets that specify either a valid street segment or a valid street stretch at least one side of which is a single entire blockface.

FigureVII-18: Ambiguous Segment Specification

Ambiguous Function 3 Input Data

Some combinations of an 'on' street and two cross streets are ambiguous as Function 3 input data, that is, the data specify more than one stretch that satisfies Function 3's input criteria. An example of ambiguous Function 3 input data in Queens is 'Alderton Street between Asquith Crescent and 64th Road' (Figure VII-18). This combination of streets describes two different segments of Alderton Street.

Function 3 rejects such ambiguous input. Unlike Function 2, which provides a means (compass direction input) for users to specify unambiguously an intersection of two streets that intersect in two different places, Geosupport provides the user with no recourse when Function 3 rejects an input stretch specification as ambiguous.

Function 3 Output Data

If a two-work-area call to Function 3 is successful, information about both sides of the input stretch is returned in WA2. (Note that the long WA2 option is available for the MSW Function 3. See Section II.5.) Some of the data items apply to both the left and right sides of the segment, e.g. the 'on' street name and street code, segment length, 'From' node (COW only), 'To' node (COW only), etc. Many of the data items in Function 3's WA2 (both regular and long) are paired, with one item for the left side of the 'on' street and another item of the same type for the right side. For example, there are fields for left and right ZIP code, for left and right 2010 census tract, and for left and right address ranges (each range consisting of a 'from' house number and a 'to' house number). Other examples exist in the COW WA2 for Function 3, e.g. fields for left and right Elections District (ED), for left and right Assembly District (AD), and for left and right Blockface ID (in COW Function 3 Extended). As explained in Chapter VII.3, left and right are determined by the 'on' street's logical direction, and therefore are independent of the order in which the user specifies the input cross streets.

In the case of an input stretch encompassing more than one segment (the T-intersection and bend cases), the values of the WA2 items that Function 3 returns for the side of the street comprising more than one blockface are as follows. The low and high house number values that are returned correspond to the entire stretch. The values that are returned for all other side-

related items correspond to the 'last' (relative to the stretch's logical direction) blockface. For example, consider Fifth Avenue in Manhattan between East 40 and East 42 Streets (see Figure VII-15). Since the direction of increasing addresses along Fifth Avenue is from south to north, that is also Fifth Avenue's logical direction. It follows that the right side of the given stretch is the east side. It consists of two blockfaces. Relative to the logical direction, the 'last' of these blockfaces is the one between East 41 and East 42 Streets. Accordingly, the right address range that is returned in WA2, consisting of the right low house number and the right high house number, corresponds to the entire right side of Fifth Avenue between East 40 and East 42 Streets. The values returned for all other items for the right side of the input stretch correspond to the 'last' blockface, the one between East 41 and East 42 Streets. The data returned represents two segments, but only one Segment ID is capable of being returned in the regular Function 3 WA2; consequently only the Segment ID with the lowest value is returned in the regular Function 3 WA2. COW Function 3 is capable of returning all the Segment IDs that exist in the returned segment. (See discussion of Auxiliary Segment Switch below.) If the user requests Fifth Avenue between East 40th street and East 41st Street, the segment ID returned will be 00034174. If the user requests Fifth Avenue between East 41st Street and East 42nd Street, the Segment ID returned will be 00034176. However if the user requests Fifth Avenue between East 40th Street and East 42nd Street, which represents two segments, (and the Auxiliary Segment Option is not requested) the segment ID returned will be 00034174, which is numerically the lower of the two numbers.

A COW Function 3 call may return, at the user's option, all the Segment IDs (up to 70) of the segments that comprise the generated output segment. To request this data, the Auxiliary Segment Switch (AUXSEG a.k.a. SEGAUX) in the COW WA1 must be set to 'Y'. This will result in all the Segment IDs (up to 70) being returned in a 500-byte area appended to the COW Function 3 WA2.

Function 3 returns the Segment Length in WA2. This value is expressed in feet, and is computed from the Spatial Coordinates of the nodes that constitute the segment's endpoints; it is an approximation to the true length of the segment. Segment Length values provided by Geosupport should not be used in applications that require an engineering level of precision. In the case of an input stretch encompassing more than one segment, the Segment Length value that function 3 returns is the sum of the lengths of the constituent segments.

Another item that Function 3 returns in WA2 is called the Curve Flag. It indicates whether the input segment is curved, and if so, whether that curve is an arc of a circle or is an irregular curve. In the case of an arc of a circle, the Curve Flag indicates on which side of the segment's 'secant line' (the straight line joining the segment's endpoint nodes) the curve lies. If the input segment is curved, whether regularly or irregularly, the Segment Length value returned is approximately equal to the true arc length of the curve, rather than the secant length. If the input stretch encompasses more than one segment, the Curve Flag is returned with an 'on' (non-blank) value if at least one of the constituent segments is curved. For further information, see the entries for Curve Flag and Segment Length in Appendix 3.

In COW format, Function 3 also returns the FROM and TO node IDs. In addition, in Extended COW format, Function 3 Extended (with or without Auxiliary Segments) returns the X,Y coordinates associated with each of the nodes as well.

The Extended WA2 Mode Switch can be used to request the Extended COW format for Function 3. The first 450 bytes of Function 3 with the Mode Switch set to "X" will be the same as for regular COW Function 3 calls. The additional fields consist of items such as Bike Lane 2, Bike Traffic Direction, Street Width, X-Y Coordinates, Roadway Type, Traffic Direction, Speed Limit, Neighborhood Tabulation Area (NTA) Names and PUMA codes. For a full list of the data returned, see the COW Work Area layout in Appendix 13.

The long WA2 option is available for the MSW Function 3. The additional data provided in the MSW long WA2 include the census geography and the administrative fire district geography. All this data is included in the regular COW Function 3 WA2.

Fuzzy Street Name Search for Functions 3 and 3C
See Section VII.8 Fuzzy Street Name Search Processing for Functions 3, 3C, and 3S

Cross Street Reversal Flag

A WA2 item returned by Function 3 called the Cross Street Reversal Flag indicates whether the order of the input streets is consistent with, or opposite to, the stretch's logical direction. This flag can be used to determine which side of the street is the left side and which side is the right side in relation to the order of the input cross streets, as follows:

- If the Cross Street Reversal Flag is returned as a blank, the cross street that was specified in the input First Cross Street field in WA1 is at the 'from' end of the stretch and the cross street that was specified in the Second Cross Street field is at the 'to' end, so that left and right are consistent with facing from the first cross street to the second cross street.
- If the Cross Street Reversal Flag contains an 'R', the first input cross street is at the 'to' end and the second is at the 'from' end, so that left and right are consistent with facing from the second cross street to the first cross street.

For example, consider the segment of Lexington Avenue between East 42nd and East 43rd Streets. Since the addresses on Lexington Avenue increase from south to north, East 42nd Street is at the 'from' end of this segment and East 43rd Street is at the 'to' end. If an application specifies this segment to Function 3 by passing East 42nd Street in the First Cross Street WA1 field and East 43rd Street in the Second Cross Street WA1 field, the Cross Street Reversal Flag will be returned as a blank. On the other hand, if East 43rd Street is passed in the First Cross Street field and East 42nd Street is passed in the Second Cross Street field, the flag will be returned containing an 'R'.

Segment Orientation

In applications that involve field operations, such as those that generate work orders to dispatch personnel to specific blockfaces, the use of ‘left’ and ‘right’ as descriptors of the sides of a street can cause confusion for personnel in the field, because their significance is based on the street’s logical direction, which is not necessarily obvious in the field. Compass directions, on the other hand, are absolute descriptors of the sides of a street; the west side of Lexington Avenue in Manhattan is a specific, invariant side of that street, and is independent of how an observer may be facing. So in such applications, compass directions may be more suitable as side-of-street descriptors than ‘left’ and ‘right’.

To determine compass direction descriptors for the left and right sides of a segment, applications can use an item called the Segment Orientation that Function 3 returns in WA2. The Segment Orientation indicates how the input segment (or the last segment of the input stretch, if it consists of more than one segment) is oriented with respect to the points of the compass, taking into consideration the ‘on’ street’s logical direction. For example, if the input segment is Lexington Avenue between East 42nd Street and East 43rd Street, using the Segment Orientation, the application can determine that the left side of this segment (as determined by the street’s assigned logical direction) is the west side and the right side is the east side. See the entry for Segment Orientation in Appendix 3 for details on the possible values of the Segment Orientation and how to use it to determine compass direction descriptors for sides of streets.

In addition, in some applications it is desirable to be able to describe the ‘ends’ of a street segment in terms of a compass direction.

The application can use the Segment Orientation in conjunction with the Cross Street Reversal Flag to express a compass direction descriptor for a side of a street in terms of left or right relative to a particular ordering of the cross streets (as opposed to left and right relative to the street’s logical direction). For example, the application can determine that, when facing from East 42nd Street to East 43rd Street, the left side of Lexington Avenue is the west side; or that, when facing from East 43rd Street to East 42nd Street, the left side of Lexington Avenue is the east side.

Applications can use the Segment Orientation and the Cross Street Reversal Flag to determine compass direction descriptors for the ‘ends’ of a street segment, as well as its sides. For example, it can be determined that East 43rd Street is at the north end of the Lexington Avenue segment in our example, and East 42nd Street is at the south end.

See the entry for Segment Orientation in Appendix 3 for further details.

Consistent Retrieval of Application Data by ‘On’ Street and Two Cross Streets

If a street stretch has a delimiting node at which there is more than one cross street, the stretch can be specified in more than one way. Some applications require the ability to retrieve records for stretches from an application file consistently by geographic location, that is, independently

of which cross streets were used to specify a stretch at record creation time and which cross streets are used at retrieval time. Function 3 provides items that can be used to form a key for such retrieval. Among the output items that Function 3 returns in WA2 are two lists of street codes (in the form of PB5SCs) for all the cross streets at the two delimiting nodes. Each list is ordered so that its first entry is always the numerically smallest PB5SC of all the entries in that list. This arrangement facilitates the formation by the application of a key for consistent geographic retrieval. The key would consist of a combination of the PB5SC for the 'on' street, the first entry in the 'from' cross street list, and the first entry in the 'to' cross street list.

If the application has a need to display the street names of the cross streets, the Cross Street Names Flag in WA1 can be turned 'on' and the names will be returned in the List of Street Names in WA1 (see entries for Cross Street Names Flag and List of Street Names in Appendix 3). Note that the cross street names feature incurs processing overhead, and should only be used when necessary.

Converting Address-Keyed Application Data to 'On' Street/Cross Streets

As mentioned in Chapter V.5, Function 1's WA2 has two lists of cross streets for the two intersections delimiting the blockface containing the input address. Like the cross street lists in Function 3's WA2, Function 1's lists are arranged so that the numerically smallest PB5SC in each list is that list's first entry. (However, unlike Function 3's lists, either or both of Function 1's lists can be empty.) Applications can identify an input address to a street stretch by using Function 1's cross street lists to create a stretch-type key in the same way as described above for Function 3. This is useful in some applications that process geographically heterogeneous input data, with some input records, for example, identified by an address and others by an 'on' street and two cross streets. An example of such an application is the New York City Department of Transportation's Street Light Information and Complaints System, which generates and tracks work orders for street light repair work. Among the ways in which this application improves the efficiency of those operations is by providing a means to consolidate all transactions involving street lights located on the same street segment into a single work order, regardless of whether the initial identification of the location is by an address or by an 'on' street and two cross streets.

VII.5 Blockfaces: Function 3C

In some applications, data are related to blockfaces, which are specific to a side of a street, rather than to street stretches or segments, which comprise both sides of the 'on' street. One way in which users commonly specify blockfaces is in terms of an 'on' street, two cross streets and a compass direction designating the side of the 'on' street, for example: "in Manhattan, the east side of Madison Avenue between East 50th and East 51st Streets". Given such a blockface specification, Function 3C can be used to obtain information specific to that blockface. (For Manhattan only, the compass orientations of blockfaces are shifted 30 degrees counterclockwise, to conform to the widespread conventional treatment of the avenues and

streets in midtown Manhattan as if they were oriented due north-south and due east-west, respectively. For more details on this 30-degree shift, see the description of Segment Orientation in Appendix 3.)

Function 3C accepts as input the long blockfaces formed by T-intersections. The sides of stretches opposite to such long blockfaces consist of more than one blockface and are not accepted as Function 3C input.

The input items to Function 3C are an 'on' street, two cross streets and a compass direction specifying the side of the street. The input cross streets, but not the 'on' street, may be pseudo-streets or intersection names. Note that, for Function 3C, the input compass direction has a different significance than it does for Function 2. In the case of Function 3C, the compass direction identifies which side of the street is to be processed. In the case of Function 2, it identifies, for a pair of input streets that intersect at two distinct locations, which of those two intersections is to be processed.

The same combinations of an 'on' street and two cross streets that Function 3 rejects as ambiguous input data are also rejected as ambiguous input data by Function 3C.

When Function 3C is called using two work areas, it returns in its WA2 those Function 3 WA2 items that are not associated with a specific side of the street, such as the lists of cross streets, the Segment Length, the 'From' node (COW only), 'To' node (COW only), etc. It also returns all of those Function 3 WA2 items that are specific to the side of the street specified by the input compass direction, such as the low and high house numbers, ZIP code and community district for that side of the street.

A successful two-work-area call to Function 3C signifies the following:

- The input 'on' street and two cross streets (or intersection names) specify a street stretch that is valid as Function 3 input (i.e., it is either a single street segment or a multi-segment stretch at least one side of which is a single entire blockface)
- The input compass direction is a valid specification (as defined below) of a side of that stretch
- The specified side of the stretch is a single entire blockface

As the second condition above implies, Function 3C treats some compass directions as invalid side-of-street specifications for some street stretches. The validity of a compass direction as a specification of a side of a street is determined by the orientation of the segment (or of the last segment of the stretch, if it consists of more than one segment) with respect to the points of the compass, as indicated by the value of the Segment Orientation. If the segment is oriented 'nearly' (i.e., within ten degrees of) due east-west, as indicated by a Segment Orientation value of 'E' or 'W', then its sides can only be validly described as the north and south sides, and Function 3C will reject east and west as side-of-street specifications. Similarly, if the segment is within ten degrees of due north-south, as indicated by a Segment Orientation value of 'N' or 'S' , then it is considered to have only east and west sides, and Function 3C will reject north and south as side-of-street specifications. (Note: recall that all Segment Orientation values in

Manhattan are rotated 30 degrees counterclockwise. This has the effect, for example, of causing Geosupport to treat Third Avenue in Midtown Manhattan as a 'nearly' north-south street. Thus, Function 3C accepts as input either the east or west side of Third Avenue between, say, East 50 Street and East 51 Street, but it rejects the north and south sides.)

Of course, most segments are 'diagonal' (not oriented within ten degrees of due north-south or due east-west), in which case all four compass directions are accepted as valid side-of-street specifications. For example, if the segment is oriented northwest-southeast, one side of the segment is simultaneously the north side and the east side, and the other side is simultaneously the south side and the west side.

Consider the example illustrated in Figure VII-15. The east side of Fifth Avenue between East 40th and East 41st Streets is a valid blockface specification and is accepted by Function 3C. The same is true for the east side of Fifth Avenue between East 41st and East 42nd Streets. The west side of Fifth Avenue between East 40th and East 42nd Streets is likewise a valid blockface specification, in this case designating the long blockface of a T-intersection. The east side of Fifth Avenue between East 40th and East 42nd Streets is not a valid blockface specification, and is rejected by Function 3C (even though that combination of 'on' street and two cross streets is accepted by Function 3), since that side of Fifth Avenue between those cross streets consists of two blockfaces. See Chapter VII.4 for a description of the Auxiliary Segment Switch. That switch allows the user to request that Geosupport return all the segment IDs in a long face of a T-intersection, or any other multi-segment situation.

The Extended WA2 Mode Switch is available for Function 3C. The first 300 bytes of Function 3C with the Mode Switch set to "X" will be the same as regular Function 3C calls. The additional fields that are returned with Function 3 Extended are returned with Function 3C Extended as well.

VII.6 Street Stretches: Function 3S

Function 3S processes street stretches. An input stretch is specified by an 'on' street and (optionally) any two cross streets, using the same WA1 input fields as are used for Function 3. If the 'on' street intersects an input cross street twice, an input compass direction must also be specified to identify which of those two intersections is intended to delimit the stretch. Input cross streets, but not the 'on' street, may be pseudo-streets or intersection names. If no input cross streets are specified, the delimiting nodes of the input stretch default to the 'on' street's beginning and ending nodes, and the input stretch consists of the entire 'on' street. If the 'on' street is a locally-valid name, then only the intersections in that portion of the street, where the name is valid, will appear in the list. Similarly, if street code input is used, the B7SC will determine the stretch of the locally-valid street.

Function 3S's WA2 contains a list of all of the input stretch's 'intersections' in sequence between the beginning and ending delimiting nodes of the stretch. An 'intersection' can either be a node (as defined in Chapter VII.2), or it can be a non-specifiable intersection, that is, a

point at which the street intersects only with a geographic feature to which a street code has not been assigned.

WA2 also contains a list counter containing the number of such intersections. There is space in the list for a maximum of 350 intersections.

- Each entry in the list typically contains the numerically smallest and second smallest PB5SCs for MSW, and up to five B7SCs for COW (the first two B7SCs are typically the numerically smallest and second smallest, of all of the cross streets at the represented intersection, if any).
- Note that to return the most useful information to the user, 'normal' streets in numerical order appear first in the list entry, followed by 'special' streets, such as Ramps and Exits. Railroads, Shorelines and Borough Boundaries will then appear followed by Named Intersections, CITY LIMITs, DEAD ENDs, and BENDs. This will occur even if the 'special' streets have lower street codes than the 'normal' streets.
- To avoid unnecessary listing of BENDs, Function 3S recognizes a BEND only if the angle of the bend is 60 degrees or more. (Prior to Release 16D, a bend was listed if the angle was 20 degrees or more.) Also, a bend is not included in the list of cross streets when another real street intersects there as well.
- The 'on' street is not included in the list of cross streets at each intersection.
- If there is only one cross street at an intersection, the list entry contains packed zeros in the second cross street field for MSW and blanks in remaining cross street fields for COW.
- List entries representing non-specifiable intersections contain packed zeros in both cross street fields for MSW and blanks in all cross street fields for COW.
- Two streets with different B7SCs but with the same B5SCs may appear in a COW list entry. This can happen when the Preferred Street Name of a street changes at an intersection. For example, in Brooklyn, the Preferred Street Name of Livingston Street becomes Aitken Place when Livingston Street intersects Clinton Street. The COW list entry for that intersection on Clinton Street will include B7SCs for both Livingston Street (B7SC 3-56530-01) and Aitken Place (B7SC 3-56530-02).
  Note: An MSW Function 3S call returns only B5SCs and in this situation the list may include two identical streets codes with the same B5SC. This, at least, informs the MSW user that there are two street names at that point. As in the past, we strongly encourage MSW Work Area users to migrate to the COW Work Areas so you can benefit from multiple Geosupport enhancements that are not included in MSW.

Each list entry also contains the distance in feet between the node represented by this list entry and the node represented by the previous list entry. The maximum value this field can contain is 99,999. Please note that the distance information is only a rough approximation and cannot be used for applications that require precise distance measurements. Note, also, that the distance field will always contain zero in the first list entry returned by Function 3S since there is no previous list entry.

There is also a field in each list entry for a **Gap Flag**. A non-blank value in the Gap Flag indicates that one of the following is true:

a. There is some kind of gap in the ‘on’ street between the node represented by this list entry and the node represented by the previous list entry
b. Multiple segments have been combined to create this entry so that only Real Street intersections are listed. Intersections with bends and other non-street features are combined to create one entry.

In other words, a non-blank value indicates that either there is no segment of the ‘on’ street connecting those two nodes, or that multiple segments have been combined to represent a ‘single’ segment between the two nodes. Note that the Gap Flag will always be blank in the first list entry returned by Function 3S since there is no previous list entry.

The Gap Flag is set to ‘G’ when there is a break in a street, such as exists with 7 Avenue between Central Park South (a.k.a. West 59 Street) and Central Park North (a.k.a. West 110 Street) in Manhattan. The length returned represents the distance between the end of one string of segments and the start of the next string of segments. With 7 Avenue in Manhattan, the length of the gap would be the distance from the intersection of 7 Avenue and Central Park South and the intersection of 7 Avenue and Central Park North.

The Gap Flag will be blank even if there is a gap between the first intersection in the list and the preceding intersection in the entire street; since, from the user’s perspective there is no gap within in the stretch. An example of this is the partial street stretch of Broadway in Manhattan between East 17 Street and East 20 Street. There is a gap between East 14 Street and East 17 Street, but there will not be any indication of that gap in the list of intersections. If, on the other hand, the user requested the partial street stretch of Broadway in Manhattan between East 10 Street and East 20 Street, the gap between East 14 Street and East 17 Street will appear in the list.

There are situations (e.g. dogleg and new stretch) where merely indicating that a gap exists is not sufficiently descriptive.

The Gap Flag is also used to indicate that segments have been combined when ‘Real Streets Only’ are requested.

To handle these situations, the Gap Flag has three values in addition to ‘G’.

1. ‘D’ for a Dogleg
2. ‘N’ for a New Stretch.
   Note: For entries with the value of ‘N’, the length from the previous node is set to zero.
3. ‘C’ for Combined Segments. This occurs when the user requests ‘real streets only’ which results in some segments being combined. See the description of the ‘Real Street Only’ flag below.

<u>Example of **Dogleg**</u>
Looking at Elk Street in Manhattan, which exists between Chambers Street and Duane Street, there is a gap at Reade Street. This is not a real gap, but rather a dogleg. Gaps of this nature are identified with the letter ‘D’ to indicate the existence of a dogleg. The length field contains the length of the dogleg. (see Figure VII.6 for example of dogleg.

Examples of **New Stretch**

1. A new stretch may involve situations where there are multiple roadbeds like Ocean Parkway in Brooklyn and Allen Street in Manhattan. In these cases one roadbed is listed first and then the first segment of each of the other roadbeds is listed as New ('N'). The length field which contains the distance from the previous node is set to zero.

2. A new stretch may involve a triangle, which occurs when a road veers off for one or more segments and then comes back. Examples of this exist in the Bronx involving White Plains Road and Rhinelander Avenue. In this case, Rhinelander Avenue appears twice in the White Plains Road stretch; once as part of the entire street and once as a "New" one-segment stretch between nodes 0079418 and 0079417. Another example of a triangle is Queens Boulevard between Yellowstone Boulevard and 70 Road. On the southern side of Queens Blvd, there is a "spur" of Queens Boulevard between Yellowstone Boulevard and 70 Road separated from the main portion of Queens Boulevard by MacDonald Park. In any case the length field is set to zero.

3. A new stretch may involve a 'street' that has several separate stretches. In the Bronx, an example of this is the Throgs Neck Expressway which has several separate stretches, some of which have a different name (e.g. Throgs Neck Boulevard), but use the same five-digit street code. The first segment of each of these separate street stretches is listed as New ('N'), and the distance from the previous node is set to zero.

Description of **Combined Segments and the "Real Street Only" Flag**

In the COW there is an input flag in WA1 called the "Real Street Only" flag for users who seek only "real" cross streets along a stretch of a street, and not items defined as "Non-Street Feature" or "Bend".

If the "Real Street Only" flag is set to **R**, only "Real" street list entries are returned. This means that "Non-Street Feature" or "Bend" items are not returned. The length from the previous node to the node with "Non-Street Feature" or "Bend" is added to the next segment and the **Gap Flag** is set to **C**, which indicates that segment lengths have been combined and one or more nodes have been omitted. There are two exceptions to this situation; namely, if the Gap Flag of the current node is equal to **N or G** which means a new stretch has commenced or if the Gap Flag of the next node is equal to **N or G**. In this case, a new stretch is starting and adding in the length of the preceding segment does not make sense. If the "Real Street Only" flag is set to any value other than **R**, all segments are displayed.

Example of **Combined Segments**

Consider the street stretch in Manhattan on A C Powell Boulevard between West 137 Street and West 140 Street. A normal function 3S call will result in seven intersections listed, including three non-street feature intersections. If "Real Street Only" is requested, only four intersections are listed, and the distances between the intersections are adjusted accordingly.

Additional COW List entry items
In the COW, for Function 3S, each list entry also includes a **Marble Hill/Rikers Island flag**, the Node ID of the intersection and a count of the number of streets at the intersection.

Note: In COW work areas, the entries in the list of intersections include B7SCs instead of B5SCs (as had been returned prior to Version 10.6). Users who are still using MSW work areas will find B5SCs in the list of intersections as in the past.

Locally Valid Street Name or Street Code processing

In Function 3S, if the on-street is a **locally-valid street name**, e.g. 'FASHION AVENUE' in Manhattan, Geosupport returns only the intersections where the name 'FASHION AVENUE' in Manhattan is valid. In this example, Geosupport will return approximately 16 intersections for 'FASHION AVENUE' in Manhattan.

If the user provides street code input instead of street name input, Geosupport uses the B7SC of the input to find the stretch of the locally-valid street. Of course, if the user supplies only the B5SC the entire street will be searched, which, hopefully, is what the user intended.

In COW work areas, the entries in the list of intersections will include B7SCs instead of the B5SCs as had been returned previously. Users who are still using MSW work areas will find B5SCs in the list of intersections as in the past.

Roadbed Street Stretches: Function 3S Partial Implementation

Function 3S may be used to obtain information about roadbed street stretches via the Roadbed Request Switch (as opposed to only generic street[10] stretches). Please be aware that the roadbed processing, which is only partially implemented, may change and is being provided to enable you, the user, to take advantage of this enhancement while in its infancy.

Information about generic street stretches may be obtained for the entire street stretch or for part of a street stretch. However information about roadbed street stretches may only be obtained for certain types of stretches. Information about certain parts of a street stretch is not fully functional and will result in a Geosupport Return Code (GRC) of 96. It is expected to be fully functional in a future release of Geosupport.

It is the user's responsibility to set the Roadbed Request Switch which is in Work Area 1.

If the Roadbed Request Switch is set to **R**, then a roadbed street stretch will be returned to the user. A blank in the Roadbed Request Switch will result in a generic street stretch being returned to the user. Any other value will result in a Geosupport Return Code (GRC) of 65.

If a user supplies a generic name for a multi-roadbed street and the Roadbed Request Switch indicates that generic processing is desired (i.e. value of the switch is ‘blank’), the output will be virtually the same as prior to implementation of the Roadbed Request Switch. An example of this would be Park Row in Manhattan.

If a user supplies a generic name for a multi-roadbed street and the Roadbed Request Switch indicates that roadbed processing is desired (i.e. value of the switch is ‘R’), the output may or may not be what was provided in the past. If the generic name supplied represents an undivided street, the generic and roadbed processing will produce the same output and it is possible to request part of the street stretch. If the generic name supplied represents a multi-roadbed street either in part or in full, then the entire stretch may be requested. Also, a street stretch that begins and ends with an undivided portion of the street may be requested. If only part of the street involves a multi-roadbed, then the undivided portion may be requested in part. For example, 58 Avenue in Queens is undivided in part. Consequently you may ask for roadbed processing from, say, 211 Street to 219 Street. If you ask for roadbed processing from, say, 214 Street to 218 Street, you will receive GRC 96 indicating that this functionality is under construction. If the entire stretch is requested with roadbed processing, the output will be different than what the output is for generic processing. The output starts with Rust Street and continues supplying the cross streets until about 213 Street where 58 Avenue becomes a multi-roadbed street. All of the intersecting streets on one roadbed are presented until about 219 Street, where 58 Avenue becomes undivided. The output then returns to earlier segments where 58 Avenue branched off as well as the segments for the other roadbed between 211 Street and 219 Street.

If a user supplies a street name that is defined as a roadbed name, but does not set the Roadbed Request Switch to indicate that roadbed processing is requested, then a GRC of 57 with the associated error message of “INPUT INCLUDES ROADBED NAME, BUT ROADBED REQUEST SWITCH IS OFF” will be returned to the user.

If a user supplies a street name that is defined as a roadbed name and sets the Roadbed Request Switch to indicate that roadbed processing is requested, then only those streets within the two cross streets that intersect the specified roadbed will be returned in the output. For example if you request the stretch for Park Avenue Northbound Roadbed and set the Roadbed Request Switch to indicate that roadbed processing is requested, then the output will include the streets that cross the northbound roadbed.

Coincident Segments: Function 3S Processing

Coincident segment processing (where one road is above another road) has become more consistent as of Release 16C. Coincident segments (streets, subways, railroads) were sometimes being listed as cross streets in releases prior to 16C. As of Release 16C, the B7SCs of segments coincident with the ‘on’ street are no longer listed as cross streets at both the ‘from’ node and ‘to’ node unless the coincident segment diverges at either the ‘from’ node or the ‘to’ node of the ‘on’ street. The new rules for coincident segments are as follows:

i. At a point where one of the two coincident segments' stretch ends, the coincident segment will not be listed as a cross street.
ii. At a point where one of the two coincident segments diverges (no longer coincident), the divergent segment will be listed as a cross street.
iii. At a point where two divergent segments become coincident, the incoming divergent segment will be listed as a cross street.
iv. At a point where a coincident segment stretch ends and a new coincidence begins with another 'on street. The continuing and terminated segments will be listed as cross streets.

---

[10] Generic streets are single line representations of streets that have multiple roadbeds, such as Queens Boulevard in Queens, the Grand Concourse in the Bronx, Broadway (in the Upper West Side) in Manhattan and Ocean Parkway in Brooklyn.

VII.7 Borough Boundary Processing (Functions 2, 3 and 3C)

All of the street configuration functions other than Function 3S allow users to specify locations that lie along a boundary of two boroughs in terms of streets from both boroughs. Function 2, for example, accepts the intersection of Brooklyn's Ridgewood Avenue and Queens's Rockaway Boulevard as a valid input street intersection lying on the Brooklyn Queens boundary. A more unusual example that Function 2 also accepts as a valid input intersection is the intersection of Atlantic Avenue in Brooklyn and Atlantic Avenue in Queens. Although physically, Atlantic Avenue is a single continuous street that crosses the Brooklyn-Queens border; Geosupport treats the portions of Atlantic Avenue in the two boroughs as two different streets, and therefore recognizes their meeting point at the borough boundary as an intersection.

A borough boundary location can be specified in terms of streets from different boroughs as follows. For street input data that are in the form of street names, there are three WA1 input fields for borough codes called Borough Code 1, Borough Code 2 and Borough Code 3 (see the WA1 layout in Appendix 2). These fields correspond respectively to the three WA1 input street name fields called Street Name 1, Street Name 2 and Street Name 3. A value is always required in Borough Code 1. If no values are loaded into Borough Code 2 and/or Borough Code 3, the default values are the value in Borough Code 1. When not all of the input street names are in the same borough, the proper value(s) must be inserted into Borough Code 2 and/or Borough Code 3, as appropriate.

If the street input data are in the form of street codes, either as PB5SCs or as B10SCs, each input street code field contains a borough code in its first byte position. This makes it possible to specify input streets from different boroughs using street code input.

The borough boundary processing feature described in this section is not implemented for Function 3S, which requires all three input streets to be from the same borough. If the input streets are in the form of street names, the borough must be specified in the WA1 input field

Borough Code 1; Function 3S ignores the contents of the WA1 input fields Borough Code 2 and Borough Code 3.

VII.8 Fuzzy Name Search Processing for Functions 3, 3C, and 3S – Front-truncated street names

Under certain conditions, Functions 3, 3C, and 3S will return data when front-truncated street names are given as input; e.g. when 14 STREET in Manhattan is given as input instead of EAST 14 STREET or WEST 14 STREET.

When a user supplies a street that is a front-truncated street name, Geosupport will process that front-truncated street name if the front-truncated street name supplied may only refer to a single street name. For example, if a user supplies '7 STREET' in Manhattan as an input street, Geosupport knows that the only possibility is 'EAST 7 STREET' in Manhattan since there is no 'WEST 7 STREET'.

When a user supplies a street name that is a front-truncated street name such as 57 STREET where there are two viable street names, such as EAST 57 STREET and WEST 57 STREET in Manhattan, then Geosupport will determine which of the two street names actually intersects with the other input street. (Geosupport invokes Function 2 under-the-covers to check the intersections.) Geosupport will accept the call if only one of the two street names actually intersects the other input street. As an example, if a user inputs '57 STREET' between 'PARK AVENUE' and 'MADISON AVENUE', Geosupport will provide data, because in Manhattan 'EAST 57 STREET' intersects 'PARK AVENUE' and 'MADISON AVENUE'. As another example, if a user inputs 'PARK AVENUE' between 57 STREET and 58 STREET, Geosupport will accept the call, because in Manhattan EAST 57 STREET intersects 'PARK AVENUE' as does EAST 58 STREET.

A warning message with Reason Code J will be issued when Geosupport assumes a name that is different from the input street name.

There are situations where a front-truncated street name will not be accepted. As an example, a Function 3S call where a user inputs '57 STREET' between 'PARK AVENUE' and 'SEVENTH AVENUE', Geosupport will not provide data, because, in Manhattan, 'EAST 57 STREET' intersects 'PARK AVENUE' and 'WEST 57 STREET' intersects 'SEVENTH AVENUE'. 'EAST 57 STREET' and 'WEST 57 STREET' are not considered to be the same streets. As another example, a Function 3S call where a user inputs '57 STREET' with no cross streets. Geosupport will not provide data, because it has no cross street to help determine whether the user wants East 57 Street or West 57 Street. When no data is returned, Geosupport will return the Geosupport Return Code (GRC) of 'EE' for '57 STREET' and provide a list of similar names which will include both 'EAST 57 STREET' and 'WEST 57 STREET'.

The fuzzy search involving Functions 3, 3C and 3S is similar to the fuzzy search for Function 2 Intersection Processing, which is described in a sub-section of VII.2.

CHAPTER VIII

THE GEOSUPPORT API - USER PROGRAM CODING AND JCL

VIII.1 Introduction

The Geosupport System's Application Programming Interface (API), the mechanism by which a user-written batch or CICS application program interfaces with the Geosupport System, was described in broad terms in Chapter II. The present chapter describes in detail, for the programming languages most widely used to develop applications on city mainframes, the statements that the user must code in an application program to access Geosupport via the API. The languages covered are COBOL, Assembler (i.e., any dialect of IBM mainframe assembler language), PL/1, C (supported on the mainframe at the Department of Information Technology and Communications (DoITT) by the IBM/C compiler) and NATURAL (a proprietary programming language used with the ADABAS database management system). An important optional user programming aid, the Geosupport COPY facility, is also discussed. The Geosupport-related JCL that the user must code to compile, link and (for batch applications) execute an application program is also described.

Notes for non-DoITT mainframe users:

- All JCL documented in this chapter is valid for the DoITT mainframe. Variations from this JCL are possible at other data centers where Geosupport is installed, for a variety of reasons. For example, the DSNs of the Geosupport files may differ from those at DoITT to conform to local file naming standards. Variations from DoITT may also be caused by software environment differences, such as the version of the operating system that is running. In addition, certain software products mentioned in this chapter, such as IBM/C or ADABAS, that are installed at DoITT may be unavailable at other data centers. Non-DoITT users should refer any Geosupport-related JCL questions or problems to their data center's Geosupport System Administrator (the system programmer at the data center who is responsible for installing new Geosupport releases).

- Non-DoITT users should also be aware that certain Geosupport files and functions that are available at DoITT may not currently be installed at their data center. Specifically, a foreground file named PAD, which is accessed only by Functions 1A, BL and BN, is relatively large and therefore is not installed at some data centers at which there are no current applications that require Functions 1A, BL or BN. At those data centers, Functions 1A, BL and BN are not available for use. If future applications at those data centers require Functions 1A, BL and/or BN, the PAD file can then be installed, thereby activating those functions.

VIII.2 Review of the Geosupport API

The Geosupport API consists of the following elements:

- Driver: A Geosupport program called the driver that serves as an intermediary between the user's application program and the Geosupport foreground software. The driver exists in the form of a load module, which the user must link-edit with the application program. (The link-editing is performed automatically for NATURAL programs.)

- Work Areas: One or two standard-layout work areas that are used to pass data back and forth between the application program and Geosupport. The user must include the Geosupport work area(s) in the application program.

- Programming Statements: Programming statements that the user must code in the application program to utilize the driver and work area(s) to interface with Geosupport.

The work areas and required programming statements are identical in the batch and CICS environments, except that there is a different driver for each environment. The driver for batch applications is named GBI. The driver for CICS applications is named GOAIDRV. The driver serves two purposes:

- It passes execution control from the user's application program to the Geosupport foreground software, which is external to the application program load module.

- It passes the memory address(es) of the work area(s), which are located within the application program, to the Geosupport foreground software, enabling Geosupport to access the work areas.

The user program must include the required Geosupport work area(s) in its working storage (COBOL, Assembler or C), automatic storage (PL/1) or U size buffer (NATURAL). When the application program issues a call to the driver, either one or two work areas (more precisely, their memory addresses) are passed as parameters of the call. The length and layout of Work Area 1 (WA1) are fixed. The length and layout of Work Area 2 (WA2) are determined by the function and, for functions that have either the long WA2 option or the Mode Switch of 'X' – Extended (discussed in Chapter II.5), by which option is specified. The distinction between one-work-area and two-work-area calls is discussed in Chapter II.4.

For the convenience of users whose application programs are written in COBOL, Assembler, PL/1, C or NATURAL, Geosupport COPY files are maintained. They contain source code descriptions of all of the work area layouts in each programming language. The Geosupport COPY files are discussed in detail in Chapter VIII.4. The use of the Geosupport COPY facility is optional but strongly recommended.

In batch applications, the user JCL for the execute step must include JOBLIB or STEPLIB DD statements for the load libraries that contain the Geosupport foreground software. Chapter VIII.8 describes the JCL required for batch execution, and Appendix 8 contains examples.

Important note for CICS applications written in NATURAL:

In order for Geosupport's CICS driver to be able to pass control to the Geosupport foreground software properly, the driver must determine whether the user program is written in NATURAL. (This is necessary because NATURAL programs make non-standard program calls in the CICS environment. In a standard call, the address of the parameter list is passed in Register 1. Programs written in COBOL, Assembler, PL/1 and C generate standard calls. However, CICS NATURAL programs use Register 1 for a different purpose. Therefore, for NATURAL programs only, the Geosupport CICS driver uses the Transaction Work Area instead of Register 1 to pass the addresses of the work areas to Geosupport.)

The Geosupport CICS driver determines whether the calling program is a NATURAL program by examining an internal Geosupport table that contains the transaction-IDs of all applications written in NATURAL. If the transaction-ID of a CICS NATURAL program is not in that table, the transaction will terminate abnormally when attempting to call Geosupport. At DoITT, the updating of the Geosupport NATURAL transaction-ID table is the responsibility of DoITT staff. Therefore, DoITT users developing new CICS applications written in NATURAL must make a request to the appropriate DoITT staff to enter the new transaction-IDs into the Geosupport table. NATURAL CICS users running at other computer centers should contact GSS at GSS_Software@planning.nyc.gov.

VIII.3 Coding API Calls

This section describes the source code statements that the user must code in the application program to call the driver. Also described, for PL/1 and C applications, are the statements required to declare the driver as an external entry point. Such a declaration is not required for COBOL, Assembler and NATURAL.

For all programming languages, the driver can be called either with one or with two calling parameters. The first parameter passes the address of Work Area 1 to the driver. If the application program is making a two-work-area call, the second parameter passes the address of Work Area 2 to the driver.

The programming statements to declare and call the driver are shown below in the form that must be coded for batch application programs. For CICS programs, the user must code these statements in the same way, but with the name of the CICS driver, GOAIDRV, in place of the batch driver, GBI.

In a (batch) PL/1 program, the driver must be declared as an external entry point as follows:

```
DCL GBI EXTERNAL ENTRY OPTION (ASM,INTER);
```

In a (batch) IBM/C program, the driver should be declared as follows:

```
#pragma linkage (GBI,OS)
long GBI(void *,... );
```

If ‘WA1’ and WA2 are the names that the user has given to the work areas within the application program source code, the statement calling the driver would be coded as follows in a (batch) application program:

Language	One-Work-Area Call	Two-Work-Area Call
COBOL	CALL ‘GBI’ USING WA1.	CALL ‘GBI’ USING WA1, WA2.
Assembler	CALL GBI,WA1,VL	CALL GBI,(WA1,WA2),VL
PL/1	CALL GBI (WA1);	CALL GBI (WA1, WA2);
IBM/C	GBI(&WA1);	GBI(&WA1,&WA2);
NATURAL	CALL ‘GBI’ USING WA1	CALL ‘GBI’ USING WA1 WA2

VIII.4 The Geosupport Copy Files

This section describes an optional feature of Geosupport, its COPY files. The Geosupport COPY files contain source code layouts of the Geosupport API work areas in the COBOL, Assembler, PL/1, C and NATURAL programming languages. The use of the Geosupport COPY files can greatly facilitate user programming and is strongly recommended for all applications. The Geosupport COPY files are contained in the Geosupport COPY libraries, which are described below.

In this section, basic concepts of COPY files are explained, and the organization of the Geosupport COPY libraries is described. In Chapter VIII.5, the specific source code statements that users must code in their programs to utilize the Geosupport COPY files are described. Chapter VIII.6 describes the JCL required to compile a program that utilizes the Geosupport COPY files.

Overview of COPY Files in General

Many programming languages, including COBOL, Assembler, PL/1, C and NATURAL, have a facility for referring, within the source code of a program, to external files (generically referred to as ‘COPY files’ in this document) containing source code to be inserted into the program at compile time. (C ‘COPY files’ are usually called header files; NATURAL ‘COPY files’ are called Local Data Areas (LDAs).) Each programming language has a declarative command (‘COPY’ in COBOL and Assembler, ‘%INCLUDE’ in PL/1, ‘#include’ in C, ‘LOCAL USING’ in NATURAL) for referring to such external COPY files. During program compilation, when the compiler encounters such a command, it dynamically retrieves the source code stored in the named COPY file and processes that source code as if it were an integral part of the program source code. The source code retrieved at compile time from the COPY file serves as input to the compiler only; it is not inserted permanently into the user’s program source code file. Only the declarative statement that refers to the COPY file is permanently present in the program source code. Note: declarative statements referencing external source code COPY files are not to be confused with external program calls.

Declarative statements are directives to the compiler, and are processed at source code compilation time; program calls are executable statements, performed at application execution time.

For COBOL, Assembler, PL/1 and C, COPY files must reside as members of a Partitioned Data Set (PDS) called a COPY library, which must be made accessible to the compiler by coding a SYSLIB DD statement in the JCL for the compile step. In addition, for COBOL and PL/1, an appropriate compiler option must be specified. For NATURAL, COPY files are called Local Data Areas (LDAs) and reside in the system library in each ADABAS database. The Database Administrator (DBA) must modify each NATURAL application's security profile to make the LDAs accessible to the application.

An ideal situation in which to use COPY files is when numerous programs in an application must all describe the same data structure(s). Using this technique, a source code description of each data structure is stored centrally in a COPY library. All programs requiring one or more of the data structures need only contain declarative statement(s) referring to the appropriate member file(s) in the COPY library. This approach insures that all the programs define the given storage layout in exactly the same way, using the same data item names, data types and data lengths. This facilitates application-wide maintenance and debugging. Changes to a data structure need only be made centrally in the COPY file, rather than separately and redundantly in each program.

Of course, the source code in a program that references a COPY file must be written so that it is compatible with the source code in that COPY file. In particular, for fields that are defined in the COPY file and referred to in the program, the program must use the same data names and must assume the same data types and lengths as does the COPY file.

The Geosupport COPY Libraries

There are two Geosupport COPY libraries that collectively contain COBOL, Assembler, PL/1 and C source code COPY files for all of the Geosupport API work area layouts. Geosupport also has a set of NATURAL LDAs for the work area layouts. The use of these facilities can greatly facilitate user application programming. Among the potential productivity benefits are the following:

- Elimination of the need for application programmers to key into their programs lengthy source code descriptions of the Geosupport work area layouts line by line.
- Standardization of Geosupport data item names among the programs in an application, facilitating troubleshooting and the reassignment of programming staff to programs written by others.
- Standardization of the descriptions (data types and lengths) of Geosupport data items in an application, fostering accuracy and compatibility among programs and files.

- Simplification of the updating of programs to reflect changes to Geosupport work area layouts. Each time a program that references the Geosupport COPY libraries is recompiled, the latest versions of the work area layouts are automatically retrieved.

The Geosupport COPY libraries supporting COBOL, Assembler, PL/1 and C applications are two catalogued Partitioned Data Sets (PDSs) named A030.GEO.COPYLIB2 and A030.GEO.COPYLIB.

For NATURAL applications at DoITT, the DoITT Database Administration staff is responsible for installing the Geosupport LDAs in the system library (CSCLIB) for each ADABAS database and for making the LDAs accessible to each application that needs such access by updating the application's profile. It is the user's responsibility to communicate with the appropriate DoITT staff to request such installation and profile updating.

The Geosupport COPY libraries contain a complete set of COPY files for the Geosupport API work areas in COBOL, Assembler, PL/1, C and NATURAL. Each COPY file contains source code descriptions of one or more of the work areas in one of the supported programming languages, as explained below. The Geosupport COPY libraries support both batch and CICS applications.

The MSW Work Area 2s of Functions 1, and 1E, (regular WA2), 2, 3 and 3C all have the same length, 200 bytes. For each of the supported programming languages except C, the layouts of these work areas are stored together in a single COPY file, coded as redefinitions of the same memory area. (In the COBOL files, this is done using REDEFINES. In the Assembler files, it is done using an ORG to reset the Location Counter. In the PL/1 files, it is done using BASED. In the NATURAL LDAs, it is done using REDEFINE.) Except for C, each of the remaining work area layouts has its own COPY file. For C, there is a single COPY file (called a 'header file' in C terminology) containing the layouts of all of the work areas, including WA1.

The COW Work Area 2s are handled in a similar fashion, though they may not all have the same length.

Tables VIII-1 and VIII-2, below, list all of the MSW and COW COPY files respectively for COBOL, Assembler, PL/1, NATURAL and C. The tables indicate the work areas for which each file contains layouts, the lengths of those work areas in bytes, and the name of each file by programming language. Appendix 5 and Appendix 14 contain printouts of the MSW and COW COPY files respectively.

Table VIII-1: MSW COPY Files for COBOL, Assembler, PL/1, C and NATURAL

			- - - - - - - - - - COPY File Name - - - - - - - -				
MSW WORK AREA	**FUNCTION(S)**	**LENGTH (bytes)**	**COBOL**	**ASSEMBLER**	**PL/1**	**C**	**NATURAL**
WA1	All	884	W1COB	W1BAL	W1PL1	WAC	GEOLW1
WA2	1 (regular WA2), 1E (regular WA2), 2, 3	200	W2COB	W2BAL	W2PL1	WAC	GEOLW2

	(regular WA2), 3C						
WA2	1 (long WA2), 1E (long WA2), 3 (long WA2)	300	W2COBL	W2BALL	W2PL1L	WAC	GEOLW2L
WA2	1A&BL (regular WA2), BN (*)	939	W2COB1A	W2BAL1A	W2PL11A	WAC	GEOLW2LA
WA2	1A&BL (long WA2) (**)	17,683	W2COB1AL	W2BAL1AL	W2PL11AL	WAC	GEOLW2LAL
WA2	3S	4,224	W2COB3S	W2BAL3S	W2PL13S	WAC	GEOLW23S

The COW COPY Files Table (Table VIII-2) appears on the following page.

			- - - - - - - - - - COPY File Name - - - - - - - -				
MSW WORK AREA	**FUNCTION(S)**	**LENGTH (bytes)**	**COBOL**	**ASSEMBLER**	**PL/1**	**C**	**NATURA**
WA1	All	1,200	P1COB	P1BAL	P1PL1	PAC	GEOLP1
WA2	1 & 1E (Regular WA2), 3C (Regular WA2)	300	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	2	200	P2COB	P2BALL	P2PL1L	PAC	GEOLP2
WA2	2W	4000	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3 (Regular WA2)	450	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3 (WA2 with AUXSEG option)	950	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3C (WA2 with AUXSEG option)	800	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3C (WA2 with AUXSEG option)	800	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3 (Extended WA2)	1,000	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3C (Extended WA2)	850	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3 (Extended WA2 w/AUXSEG)	1,500	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3C (Extended WA2 w/AUXSEG)	1,350	P2COB	P2BAL	P2PL1	PAC	GEOLP2

WA2	1A & BL (Regular WA2), BN (*)	1,363	P2COB1A	P2BAL1A	P2PL11A	PAC	GEOLP21A
WA2	1A & BL (Long WA2) (**) 1A & BL (TPAD Long WA2) (***)	17,750	P2COB1AL	P2BAL1A	P2PL11AL	PAC	GEOLP2A
WA2	1A & BL & BN (Extended WA2) (****)	2,800	P2COB1AL	P2BAL1A	P2PL11AL	PAC	GEOLP2A
WA2	1 & 1E (Extended WA2)	1,500	P2COB1AL	P2BAL1A	P2PL11AL	PAC	GEOLP2A
WA2	1B	4,300	P2COB1AL	P2BAL1A	P2PL11AL	PAC	GEOLP2A
WA2	3S	19,274	P2COB3S	P2BAL3S	P2PL13S	PAC	GEOLP23S
WA2	AP	1,363	P2COBAP	P2BALAP	P2PL1AP	PAC	GEOL2AP
WA2	AP (Extended WA2)	2,800	P2COBAP	P2BALAP	P2PL1AP	PAC	GEOL2AP

(*) Functions 1A, BL and BN share a single regular WA2 layout.
(*) *Functions 1A and BL share a single long WA2 layout. (Function BN has no long WA2 option.).*
(*) Functions 1A and BL share a single TPAD long WA2 layout. (Function BN has no TPAD long WA2 option.).
(***) Functions 1A, BL and BN share a single extended WA2 layout.

VIII.5 Coding API Calls When Using Geosupport COPY Files

This section describes the source code statements that COBOL, Assembler, PL/1, C and NATURAL users must code in application programs that use Geosupport COPY files. The required statements consist of declarative statements to reference the COPY files (using the file names in Table VIII-1) and statements calling the driver.

In Chapter VIII.3, the forms of calls to the driver were given using arbitrary data names for the work areas. In programs that do not use Geosupport COPY files, those names are user-selectable. In the present section, the forms of the driver calls are given again, this time with the specific data names that are required for compatibility with the COPY files. COBOL and C are the only supported languages that permit COPY file users to select their own names for the work areas (but not for the fields within the work areas). Prior to each call to the driver, the program must prime Work Area 1 with the input data to be processed by Geosupport, as described in Chapter II.3.

In Chapter VIII.3, the forms of calls to the driver were given using arbitrary data names for the work areas. In programs that do not use Geosupport COPY files, those names are user-selectable. In the present section, the forms of the driver calls are given again, this time with the specific data names that are required for compatibility with the COPY files. COBOL and C are the only supported languages that permit COPY file users to select their own names for the work areas (but not for the fields within the work areas). Prior to each call to the driver, the program must prime Work Area 1 with the input data to be processed by Geosupport, as described in Chapter II.3.

The declarative statements referencing COPY files cause the compiler to process the source code contained therein as if it were present within the application program's own source code at the point in the program where the declarative statement is located. Application programs need only reference those Geosupport COPY files that are required for the Geosupport function(s) the program actually calls, although referencing other COPY files does no harm.

COBOL Source Code Statements

To reference Geosupport MSW COPY files, COBOL programs must contain the appropriate one (or more) of the following statements in WORKING-STORAGE:

01 ANY-NAME-FOR-WA1. COPY W1COB. WA1, all functions
01 ANY-NAME-FOR-WA2. COPY W2COB. WA2, Functions 1 & 1E & 3 (regular WA2), 2, 3C

01 ANY-NAME-FOR-WA2-L. COPY W2COBL. WA2, Functions 1& 1E & 3 (long WA2)

01 ANY-NAME-FOR-WA2-1A. COPY W2COB1A. WA2, Functions 1A & BL (regular WA2), BN

01 ANY-NAME-FOR-WA2-1AL. COPY W2COB1AL. WA2, Functions 1A & BL (long WA2)

01 ANY-NAME-FOR-WA2-3S. COPY W2COB3S. WA2, Function 3S

For COBOL programs that will be executed in the **batch environment** and that use Geosupport COPY files, API calls are coded as follows:

One-work-area calls, all functions:
CALL 'GBI' USING ANY-NAME-FOR-WA1.

Two-work-area calls, Functions 1 & 1E & 3 (regular WA2), 2, 3C:
CALL 'GBI' USING ANY-NAME-FOR-WA1 ANY-NAME-FOR-WA2.

Two-work-area calls, Functions 1 & 1E & 3 (long WA2):
CALL 'GBI' USING ANY-NAME-FOR-WA1 ANY-NAME-FOR-WA2-L.

Two-work-area calls, Functions 1A & BL (regular WA2), BN:
CALL ‘GBI' USING ANY-NAME-FOR-WA1 ANY-NAME-FOR-WA2-1A.

Two-work-area calls, Functions 1A & BL (long WA2):
CALL ‘GBI’ USING ANY-NAME-FOR-WA1 ANY-NAME-FOR-WA2-1AL.

Two-work-area calls, Function 3S:
CALL ‘GBI’ USING ANY-NAME-FOR-WA1 ANY-NAME-FOR-WA2-3S.

CICS programs issue calls as above but with GOAIDRV in place of GBI.

To reference Geosupport **COW COPY files** include the appropriate COPY files whose names begin with P1 and P2 instead of W1 and W2, e.g. P1COB instead of W1COB. Note that in the COW format, there is no long WA2 for Functions 1, 1E, and 3. Note, also, that there are additional function options in the COW format.

* To choose the appropriate COW COPY file, see Table VIII-2.*

Assembler Source Code Statements

To reference Geosupport **MSW COPY files**, Assembler programs must contain the appropriate one (or more) of the following statements:

```
COPY W1BAL          WA1, all functions <br>
COPY W2BAL          WA2, Functions 1 & 1E & 3 (regular WA2), 2, 3C <br>
COPY W2BALL         WA2, Functions 1 & 1E & 3 (long WA2) <br>
COPY W2BAL1A        WA2, Functions 1A & BL (regular WA2), BN <br>
COPY W2BAL1AL       WA2, Functions 1A & BL (long WA2) <br>
COPY W2BAL3S        WA2, Function 3S
```

For Assembler programs that will be executed in the **batch environment** and that use Geosupport COPY files, API calls are coded as follows:

```
     CALL GBI,W1BAL,VL                          One-work-area calls, all functions <br>
     CALL GBI,(W1BAL,W2BAL),VL            Two-work-area calls, Functions 1 & 1E & 3 <br>
(regular WA2), 2, 3C <br>
     CALL GBI,(W1BAL,W2BALL),VL          Two-work-area calls, Functions 1 & 1E & 3 <br> (long
WA2) <br>
     CALL GBI,(W1BAL,W2BAL1A),VL        Two-work-area calls, Functions 1A & BL <br> (regular
WA2), BN <br>
     CALL GBI,(W1BAL,W2BAL1AL),VL       Two-work-area calls, Functions 1A & BL <br> (long WA2)
<br>
     CALL GBI,(W1BAL,W2BAL3S),VL        Two-work-area calls, Function 3S <br>
```

CICS programs issue calls as above but with GOAIDRV in place of GBI.

To reference Geosupport **COW COPY files** include the appropriate COPY files whose names begin with P1 and P2 instead of W1 and W2, e.g. P1BAL instead of W1BAL. Note that in the COW format, there is no long WA2 for Functions 1, 1E, and 3. Note, also, that there are additional function options in the COW format.

* To choose the appropriate COW COPY file, see Table VIII-2. *

PL/1 Source Code Statements

To reference Geosupport **MSW COPY files**, PL/1 programs must contain the appropriate one(s) of the following statements:

```
     %INCLUDE W1PL1;                      WA1, all functions <br>
     %INCLUDE W2PL1;                      WA2, Functions 1 & 1E & 3 (regular WA2), 2, 3C <br>
     %INCLUDE W2PL1L;                    WA2, Functions 1 & 1E & 3 (long WA2) <br>
     %INCLUDE W2PL11A;                 WA2, Functions 1A & BL (regular WA2), BN <br>
     %INCLUDE W2PL11AL;               WA2, Functions 1A & BL (long WA2) <br>
     %INCLUDE W2PL13S;                 WA2, Function 3S <br>
```

For PL/1 programs that will be executed in the **batch environment** and that use Geosupport COPY files, API calls are coded as follows:

```
    CALL GBI (W1PL1);                          One-work-area calls, all functions <br>
    CALL GBI (W1PL1,W2PL1);            Two-work-area calls, Functions 1 & 1E, 2, 3 <br>
(regular WA2), 3C <br>
    CALL GBI (W1PL1,W2PL1L);          Two-work-area calls, Functions 1 & 1E & 3 <br>(long WA2)
<br>
    CALL GBI (W1PL1,W2PL11A);        Two-work-area calls, Functions 1A & BL <br>(regular WA2),
BN <br>
    CALL GBI (W1PL1,W2PL11AL);     Two-work-area calls, Functions 1A & BL <br>(long WA2) <br>
    CALL GBI (W1PL1,W2PL13S);        Two-work-area calls, Function 3S <br>
```

CICS programs issue calls as above but with GOAIDRV in place of GBI.

(Note: for either a batch or a CICS PL/1 program, the appropriate Geosupport driver (GBI or GOAIDRV respectively) must be declared as an external entry point. See Section VIII.3.)

To reference the Geosupport **COW COPY files** include the appropriate copy files whose names begin with P1 and P2 instead of W1 and W2, e.g. P1PL1 instead of W1PL1. Note that in the COW format, there is no long WA2 for Functions 1, 1E, and 3. Note, also, that there are additional function options in the COW format.

/* To choose the appropriate COW COPY file, see Table VIII-2. *

IBM/C Source Code Statements

To reference the Geosupport **MSW COPY file** IBM/C programs must contain the following statement:

#include <wac.h>

In the following C source code examples, the letter ‘L’ appears in upper case to facilitate distinguishing it from the numeric character ‘1’.

```
    C_WA1 anyname_wa1;                                WA1, all functions <br>
    C_WA2_F1 anyname_wa2_f1;                     WA2, Functions 1 & 1E (regular WA2) <br>
    C_WA2_F1 anyname_wa2_f1L;                   WA2, Functions 1 & 1E (long WA2) <br>
    C_WA2_F1A anyname_wa2_f1a;                WA2, Functions 1A & BL (regular WA2), BN <br>
    C_WA2_F1AL anyname_wa2_f1aL;            WA2, Functions 1A & BL (long WA2) <br>
    C_WA2_F2 anyname_wa2_f2;                     WA2, Function 2 <br>
    C_WA2_F3 anyname_wa2_f3;                     WA2, Function 3 (regular WA2) <br>
    C_WA2_F3L anyname_wa2_f3L;                WA2, Function 3 (long WA2) <br>
    C_WA2_F3C anyname_wa2_f3c;                WA2, Function 3C <br>
    C_WA2_F3S anyname_wa2_f3s;                WA2, Function 3S <br>
```

For C programs that will be executed in the **batch environment** and that use the Geosupport COPY file, API calls are coded as follows:

```
C_WA1 anyname_wa1;                                WA1, all functions <br>
C_WA2_F1 anyname_wa2_f1;                     WA2, Functions 1 & 1E (regular WA2) <br>
C_WA2_F1 anyname_wa2_f1L;                   WA2, Functions 1 & 1E (long WA2) <br>
C_WA2_F1A anyname_wa2_f1a;                WA2, Functions 1A & BL (regular WA2), BN <br>
C_WA2_F1AL anyname_wa2_f1aL;            WA2, Functions 1A & BL (long WA2) <br>
C_WA2_F2 anyname_wa2_f2;                      WA2, Function 2 <br>
C_WA2_F3 anyname_wa2_f3;                      WA2, Function 3 (regular WA2) <br>
C_WA2_F3L anyname_wa2_f3L;                  WA2, Function 3 (long WA2) <br>
C_WA2_F3C anyname_wa2_f3c;                  WA2, Function 3C <br>
C_WA2_F3S anyname_wa2_f3s;                  WA2, Function 3S <br>
```

```
GBI (&anyname_wa1);                                          One-work-area calls, all
functions. <br>
GBI (&anyname_wa1,&anyname_wa2_f1);            Two-work-area calls, Functions 1 & 1E <br>
(regular WA2) <br>
GBI (&anyname_wa1,&anyname_wa2_f1L);          Two-work-area calls, Functions 1 & 1E <br>
(long WA2) <br>
GBI (&anyname_wa1,&anyname_wa2_f1a);          Two-work-area calls, Functions 1A & BL <br>
(regular WA2), BN <br>
GBI (&anyname_wa1,&anyname_wa2_f1aL);        Two-work-area calls, Functions 1A & BL <br>
(long WA2) <br>
GBI (&anyname_wa1,&anyname_wa2_f2);            Two-work-area calls, Function 2 <br>
GBI (&anyname_wa1,&anyname_wa2_f3);            Two-work-area calls, Function 3 <br>  (regular
WA2) <br>
GBI (&anyname_wa1,&anyname_wa2_f3L);          Two-work-area calls, Function 3 <br>  (long WA2)
<br>
GBI (&anyname_wa1,&anyname_wa2_f3c);          Two-work-area calls, Function 3C <br>
GBI (&anyname_wa1,&anyname_wa2_f3s);          Two-work-area calls, Function 3S <br>
```

CICS programs issue calls as above but with GOAIDRV in place of GBI.

(Note: for either a batch or a CICS C program, the Geosupport driver (GBI or GOAIDRV respectively) must be declared as an external entry point. (See Section VIII.3.)

To reference the Geosupport **COW COPY files** include the PAC COPY file instead of the WAC COPY file. Note that in the COW format, there is no long WA2 for Functions 1, 1E, and 3. Note, also, that there are additional function options in the COW format.

NATURAL Source Code Statements

NATURAL Source Code Statements

NATURAL programs reference Geosupport MSW LDAs by containing one or more of the following statements in DEFINE DATA:

```
    LOCAL USING GEOLW1                WA1, all functions <br>
    LOCAL USING GEOLW2                WA2, Functions 1 & 1E & 3 (regular WA2), 2, 3C <br>
    LOCAL USING GEOLW2L              WA2, Functions 1 & 1E & 3 (long WA2) <br>
    LOCAL USING GEOLW21A           WA2, Functions 1A & BL (regular WA2), BN <br>
    LOCAL USING GEOLW2AL           WA2, Functions 1A & BL (long WA2) <br>
    LOCAL USING GEOLW23S           WA2, Function 3S <br>
```

For NATURAL MSW programs that will be executed in the **batch environment** and that use the Geosupport COPY files (LDAs), API calls are issued as follows:

```
    CALL 'GBI' USING W1NAT                      One-work-area calls, all functions <br>
    CALL 'GBI' USING W1NAT W2NAT        Two-work-area calls, Functions 1 & 1E & 3 <br>
(regular WA2), 2, 3C  <br>
    CALL 'GBI' USING W1NAT W2NATL       Two-work-area calls, Functions 1 & 1E & 3 <br>
(longWA2)  <br>
    CALL 'GBI' USING W1NAT W2NAT1A    Two-work-area calls, Functions 1A & BL <br> (regular
WA2), BN <br>
    CALL 'GBI' USING W1NAT W2NATAL    Two-work-area calls, Functions 1A & BL <br> (long WA2)
<br>
    CALL 'GBI' USING W1NAT W2NAT3S    Two-work-area calls, Functions 3S <br>
```

CICS NATURAL programs issue calls as above but with GOAIDRV in place of GBI.

Natural COW

NATURAL programs reference Geosupport COW LDAs by containing one or more of the following statements in DEFINE DATA:

```
    LOCAL USING GEOLP1              WA1, all functions <br>
    LOCAL USING GEOLP2              WA2, Functions 1 & 1E & 3C <br>
    LOCAL USING GEOLP2              WA2, Function 2 <br>
    LOCAL USING GEOLP2              WA2, Function 3 <br>
    LOCAL USING GEOLP21A         WA2, Functions 1A & BL (regular WA2), BN <br>
    LOCAL USING GEOLP2AL         WA2, Functions 1A & BL (long WA2) <br>
    LOCAL USING GEOLP23S         WA2, Function 3S <br>
    LOCAL USING GEOL2AP            WA2, Function AP <br>
    LOCAL USING GEOL2APX         WA2, Function AP Extended <br>
```

For NATURAL COW programs that will be executed in the **batch environment** and that use the Geosupport COPY files (LDAs), some samples of API calls follow:

```
    CALL 'GBI' USING P1NAT                        One-work-area calls, all functions <br>
    CALL 'GBI' USING P1NAT P2NAT          Two-work-area calls, Functions 1 & 1E & 3C <br>
    CALL 'GBI' USING P1NAT P2NAT2         Two-work-area calls, Function 2 <br>
    CALL 'GBI' USING P1NAT P2NAT3         Two-work-area calls, Function 3 <br>
    CALL 'GBI' USING P1NAT P2NAT1A       Two-work-area calls, Fns 1A & BL (regular WA2), BN
<br>
    CALL 'GBI' USING P1NAT P2NAT1AL     Two-work-area calls, Functions 1A & BL (long WA2) <br>
    CALL 'GBI' USING P1NAT P2NAT3S       Two-work-area calls, Functions 3S <br>
    CALL 'GBI' USING P1NAT P2NATAP       Two-work-area calls, Functions AP <br>
    CALL 'GBI' USING P1NAT P2NATAPX      Two-work-area calls, Functions AP Extended <br>
```

Note that there are additional function options in the COW format.

* To choose the appropriate COW COPY file (P2NATxxx), see Table VIII-2. *

CICS NATURAL programs issue calls as above but with GOAIDRV in place of GBI.

VIII.6 JCL for the Compile Step

COBOL, Assembler, PL/1 and C programs that do not reference Geosupport COPY files do not require any Geosupport-related JCL in the compile step. When compiling a COBOL, Assembler, PL/1 or C program that references Geosupport COPY files, the Geosupport COPY libraries must be made accessible to the compiler, as described below. NATURAL programs are compiled in the usual way, with no special user action required to access the Geosupport LDAs.

The Geosupport COPY libraries that support COBOL, Assembler, PL/1 and C are two catalogued files which at DoITT have the DSNs A030.GEO.COPYLIB2 and A030.GEO.COPYLIB. (At other installations, users should verify these DSNs with the data center's Geosupport System Administrator.) The COPY libraries must be concatenated under the DDname SYSLIB in the JCL for the compile step. Since the two libraries have some member names in common, it is essential to concatenate their DD statements in the proper order as shown below.

Assuming that one of the standard IBM catalogued procedures for compiling is being used, the JCL for SYSLIB should be coded as follows:

```
COBOL:      //COBOL.SYSLIB     DD DSN=A030.GEO.COPYLIB2,DISP=SHR
            //                 DD DSN=A030.GEO.COPYLIB,DISP=SHR
ASSEMBLER   //ASM.SYSLIB       DD DSN=A030.GEO.COPYLIB2,DISP=SHR
            //                 DD DSN=A030.GEO.COPYLIB,DISP=SHR
            //                 DD DSN=<\name of user macro library>,DISP=SHR
            //                 DD DSN=SYS1.MACLIB,DISP=SHR
PL/1:       //PLI.SYSLIB       DD DSN=A030.GEO.COPYLIB2,DISP=SHR
            //                 DD DSN=A030.GEO.COPYLIB,DISP=SHR
IBM/C:      //COMPILE.SYSLIB   DD
            //                 DD DSN=A030.GEO.COPYLIB,DISP=SHR
```

For Assembler applications, care must be taken to insure that the required Assembler macro libraries are concatenated to SYSLIB, as shown.

For C applications, note that the compiler requires access only to COPYLIB, not to COPYLIB2, and furthermore, care must be taken to insure that COPYLIB is concatenated to the IBM/C header file library, rather than overriding it. Overriding is prevented by coding one DD statement with a blank operand field followed by the DD statement for the Geosupport COPY library, as shown.

For COBOL applications, in addition to providing the DD statements for SYSLIB, the appropriate compiler option, LIB, must also be in effect. Since LIB is the default, it does not have to be explicitly specified.

For PL/1 applications being compiled by a compiler other than the IBM Enterprise PL/1 Compiler, in addition to providing the DD statements for SYSLIB, the appropriate compiler option, MACRO or INCLUDE, must also be in effect. If %INCLUDE is the only kind of preprocessor statement in the program, then the INCLUDE option should be used instead of the MACRO option. This will make compilation faster. If other kinds of preprocessor statements are in the program in addition to the %INCLUDE statement(s), then the MACRO option must be used. For example:

```
// EXEC IBMZC,PARM.PLI=' MACRO'
```

or

// EXEC IBMZC,PARM.PLI=' INCLUDE'

In the IBM Enterprise PL/1 Compiler, the meaning of the INCLUDE compiler option has changed. As a result, if %INCLUDE is the only kind of preprocessor statement in the program, then no compiler option reflecting that fact should be coded. If other kinds of preprocessor statements are in the program in addition to the %INCLUDE statement(s), then as is the case with other PL/1 compilers, the MACRO option must be used.

VIII.7 JCL for the Linkage Editor Step

In both batch and CICS applications, the Geosupport driver must be link-edited into the user program. For applications written in NATURAL, this is done automatically with no special user action required. For non-NATURAL applications, either batch or CICS, users must link-edit their programs as explained below.

When link-editing a non-NATURAL application, the user must provide in the JCL for the linkage editor step a DD statement for the Geosupport load library containing the driver, as well as an INCLUDE statement in the SYSIN file specifying the driver. The DD statement should be coded as follows ("YOURDDN" may be replaced by any DDname):

```
//YOURDDN DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
```

For batch programs, the INCLUDE statement in the SYSIN file should be coded as follows:

```
//LKED.SYSIN DD *
•
•
INCLUDE YOURDDN(GBI)
•
•
/*
```

For CICS programs, the INCLUDE statement should be coded as follows:

```
//LKED.SYSIN DD *
•
```

```
.
INCLUDE YOURDDN(GOAIDRV)
.
.
/*
```

VIII.8 JCL for the Execute Step (Batch Applications)

For user programs being executed in the batch environment, the user must provide seven megabytes of memory for Geosupport, in addition to the memory required for the user program itself.

Geosupport Software Files

User programs that are executed in the batch environment also require Geosupport-related DD statements in the JCL for the execute step. A STEPLIB or JOBLIB DD statement must be provided to make the Geosupport foreground component batch load module library accessible to the application. As of Version 10.1 of Geosupport, users do this by coding either of the following DD statements:

```
//STEPLIB    DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
                or
//JOBLIB     DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
```

(NATURAL users, please see the important note at the end of this section regarding the STEPLIB or JOBLIB DD statement.)

Geosupport Data Files

As of Version 10.1 of Geosupport, the user no longer has to provide DD statements for the Geosupport data files. In fact, if these DD statements are provided they are ignored by Geosupport. The data set names of the Geosupport data files are stored in a module called DSNAMES. If you need to use a non-standard Geosupport data file, please see your systems programmer.

Note for NATURAL Users:

When using a NATURAL batch execution procedure, care must be taken to insure that the Geosupport load library is concatenated to the two standard NATURAL libraries, rather than overriding them. Overriding is prevented by coding two DD statements with blank operand fields, followed by the DD statement for the Geosupport load library. The following JCL is an example (any stepname may be used):

```
//STEPNM   EXEC   ,REGION=7M
//STEPLIB  DD
//         DD
//JOBLIB   DD      DSN=A030.GEO.SUPPORT PDSE LOADLIB,DISP=SHR
//         DD      DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
```

CHAPTER IX

GEOSUPPORT BATCH ADDRESS TRANSLATOR (GBAT)

IX.1 Introduction

This chapter describes the Geosupport Batch Address Translator (GBAT), the Geosupport System's batch utility program. Users can often satisfy their requirements for batch Geosupport processing without having to write custom programs by processing their files through GBAT.

GBAT can process any user file that meets certain easily satisfied requirements (described in Chapter IX.4). It can be used to execute any of the Geosupport functions that are available in the batch environment. It can be used to normalize house numbers and street names, to obtain street codes, to validate geographic locations such as addresses and intersections, and to obtain geographic information about such locations such as cross streets, community district, ZIP code, tax block and tax lot, spatial coordinates or any of the other information that Geosupport provides.

To run GBAT, the user must set up a batch job, and must create a small 'control file' that controls the GBAT execution. Chapter IX.2 discusses JCL considerations for setting up the batch job. Chapter IX.3 outlines the processing that GBAT performs and discusses programmed abnormal terminations. The remaining sections of this chapter discuss each of GBAT's input and output files.

Appendices 9, 10, and 12 also pertain to GBAT. Appendices 9 and 12 contain several GBAT tables that are indispensable references for setting up the control file (Tables A9-1, A9-2 and A9-3), interpreting the MSW GBAT output data (Table A9-4), interpreting the COW GBAT output data (Table A12-2), and setting up the JCL (Table A9-5 for MSW format, Table A12-3 for COW format). Appendix 10 contains annotated sample GBAT jobs, including JCL, control files and output listings.

IX.2 JCL Considerations

GBAT makes calls to the Geosupport System via Geosupport's standard API in the same manner as is done by any user-written batch Geosupport application program. To execute GBAT, the user sets up a batch job that invokes a catalogued procedure called GBAT2, which contains all the JCL necessary to support the Geosupport calls. This 'proc' consists of a single step, the stepname of which is also GBAT2. It contains an EXEC statement that executes the GBAT program and a STEPLIB DD statement specifying the program library containing the GBAT and Geosupport load modules. The user must add DD statements to the GBAT execution step for GBAT's own input and output files. Those files, and their required DDnames, are as follows:

- Input data file, DDname INFILE or INVSAM. Mandatory. Contains the user's geographic information to be processed. Discussed in Chapter IX.4.

- Input control file, DDname CARDIN. Mandatory. Contains encoded information that describes the use's input data file and specifies GBAT processing options. Discussed in Chapter IX.5.

- Input alias file, DDname ALIASES. Optional. Allowable if the function being executed accepts street name input. Contains user-defined street name aliases (alternative names and spelling variants) that GBAT is to use to supplement the street names recognized by Geosupport. Discussed in Chapter IX.6.

- Output file of accepted data, DDname OUTFILE. Optional. Contains one record corresponding to each input data record that is accepted by Geosupport. The record consists of an exact copy of the input data record, followed by data obtained from Geosupport. Discussed in Chapter IX.7.

- Output file of rejected data, DDname ERRFILE. Mandatory (except when WORKAREA1=YES). Contains one record corresponding to each input data record that is rejected by Geosupport. The record consists of the Geosupport Return Code and Reason Code, followed by an exact copy of the input data record. Discussed in Chapter IX.8.

- Output file of rejected data, DDname ERRFIL2. Mandatory when RECTYPE=1B and WORKAREA1=NO. Contains one record corresponding to each input data record that is rejected (or partially rejected) by Geosupport Function 1B. The record consists of the Geosupport Return Code and Reason Code for the Function 1E Extended portion of Function 1B, followed by the Geosupport Return Code and Reason Code from the 1A Extended portion of Function 1B, followed by an exact copy of the input data record. Discussed in Chapter IX.8.

- Output file of rejected data, DDname ERRFIL3. Mandatory when RECTYPE=2 and RELATEDNODES=YES. Contains one record corresponding to each input data record that is rejected by Geosupport with GRC 03 Reason Code B (many-node case). The record consists of the Geosupport Return Code and Reason Code, followed by an exact copy of the input data record, followed by the information needed to choose a node. Discussed in Chapter IX.8.

- Output file of rejected data, DDname ERRFIL4. Mandatory when WORKAREA1=YES. Contains one record corresponding to each input data record that is rejected by Geosupport. The record consists of the Geosupport Return Code and Reason Code, followed by an exact copy of the input data record, followed by a copy of Work Area 1. Discussed in Chapter IX.8.

- Output file of rejected data, DDname ERRFIL5. Mandatory when RECTYPE=1B and WORKAREA1=YES. Contains one record corresponding to each input data record that is rejected (or partially rejected) by Geosupport Function 1B. The record consists of the Geosupport Return Code and Reason Code for the Function 1E Extended portion

of Function 1B, followed by the Geosupport Return Code and Reason Code from the 1A Extended portion of Function 1B, followed by an exact copy of the input data record, followed by a copy of Work Area 1. Discussed in Chapter IX.8.

- Output print file, DDname SYSPRINT. Mandatory. Contains GBAT messages and summary run statistics. Discussed in Chapter IX.9.

Some of the GBAT files, e.g. the input alias file and the output file of accepted data, are optional. GBAT opens these files only if there are certain entries in the control file specifying their use. If an optional file is not used, a DD statement for that file need not be included in the JCL. However, including such a DD statement causes no harm, unless the file it refers to does not exist, which would cause a JCL error.

In the course of execution, certain conditions (described in Chapter IX.3) may arise that cause GBAT to terminate abnormally. In all cases in which GBAT exits via a programmed abnormal termination, it issues a Condition Code[11] of 12 or greater, and it produces incomplete or no output files. If the user's job contains any steps following the GBAT execution step (the step that invokes the GBAT2 proc) that are dependent on the existence of the output files that GBAT is expected to create, it is advisable to code the COND parameter in the EXEC statements of those steps so that those steps are bypassed if the Condition Code issued by the GBAT execution step is 12 or greater. For example, if GBATSTEP is the stepname of the GBAT execution step, then coding COND=(12,LE,GBATSTEP.GBAT2) in the EXEC statement of a subsequent step will cause that step to be bypassed if 12 is less than or equal to the Condition Code of GBATSTEP.

---

[11] Each step of a batch job running on an IBM mainframe can issue a Condition Code upon termination of the step. By convention, a Condition Code of '00' indicates normal completion of the step, '04' indicates generally normal completion but with a minor condition warranting a warning and higher values indicate severe problems or errors causing abnormal termination. Condition Codes appear in the SYSPRINT output job log. A JCL parameter, COND, can be coded in the EXEC statement of any job step to cause that step to be bypassed if the Condition Code of a specified previous step satisfies a specified condition.

Note: Condition Codes are sometimes called 'Return Codes', in IBM documentation and elsewhere. Condition Codes are not to be confused with Geosupport Return Codes (GRCs). The Condition Codes discussed in this chapter are issued by the GBAT program, appear in the output job log and can be tested by the COND JCL parameter. GRCs are issued by the Geosupport System and are returned to the calling application (including to GBAT) in Work Area 1; they do not appear in the output job log and are not accessible to COND. GBAT does include the GRC in each record it writes into the output file of rejected data (discussed in Chapter IX.8).

IX.3 GBAT Processing and Programmed Abnormal Terminations

Before GBAT begins processing the input data file, it first validates the control file and, if appropriate, the alias file. The entire control file is validated for syntax and content, as described in Section IX.5. Regardless of the outcome of that validation, if the function being executed accepts street name input, and the user has provided an alias file, and the user has specified either ALIASES=VAL or ALIASES=YES in the control file, then the contents of the entire alias file are also validated, as described in Section IX.6. For each error encountered during these validations, GBAT issues an appropriate error message but continues the validation processing. Informational and warning messages may also be issued during the control file and alias file validation processing.

After the control file and alias file validation processing is completed, GBAT determines whether to terminate abnormally or to commence processing the input data file. GBAT terminates abnormally at this point if there has been at least one control file error or, when an alias file has been provided, if there has been at least one alias file error and ALIASES=VAL has been specified. (In contrast, when ALIASES=YES is specified, the alias file is validated and error messages are issued as appropriate, but alias file errors do not cause GBAT to terminate abnormally.) Conditions that cause GBAT to issue informational or warning messages do not trigger abnormal termination.

The Condition Codes issued for programmed abnormal terminations triggered by control file and alias file errors are as follows:

- Condition Code 12: only the control file had errors (or both the control file and the alias file had errors, but ALIASES=YES was specified, so that any alias file errors do not affect the manner in which GBAT terminates).
- Condition Code 13: only the alias file had errors, and ALIASES=VAL was specified.
- Condition Code 14: both files had errors, and ALIASES=VAL was specified.

When no alias file is provided, Condition Code 12 can occur, but not Condition Codes 13 and 14.

If the control file and alias file validation processing is completed normally, GBAT processes the input data file and writes data to the output files. Specifically, GBAT reads each record from the input data file, and uses the geographic information obtained there from as the input data for a standard API call to the Geosupport System. If the information is accepted by Geosupport, GBAT writes a record into the output file of accepted data (unless the user has chosen not to create this optional file). If the information is rejected by Geosupport, GBAT writes a record into the output file of rejected data. Both types of output records consist of exact

copies of the input data record together with data that GBAT has obtained from Geosupport. At the completion of execution, GBAT writes out a small report (usually less than one page long) of summary run statistics.

- Condition Code 15:
  GBAT sets the Condition Code to 15 when GBAT execution is terminated because of a record length error for the following files: ERRFILE (COW and MSW), ERRFIL2 (COW only), ERRFIL3 (COW only), ERRFIL4 (COW only) and ERRFIL5 (COW only).

If there is a record length error for other files, e.g. OUTFILE, GBAT may ABEND with U4038. In addition to the ABEND, other messages are generated, e.g. `IBM0122S ONCODE=22 The RECORD condition was raised because the length of the record variable was greater than the record length (ONFILE = OUTFILE)`

- Condition Code 20:
  In the course of processing the input data file, a condition called a MAXREJECTS violation, discussed in detail below, may arise. If so, GBAT ceases processing the input data, writes out the report of run statistics reflecting the processing that has occurred up to that point, and terminates abnormally with Condition Code 20. Otherwise, GBAT continues processing until all input data records have been processed, writes out the report of run statistics, and then terminates normally with Condition Code 00.

The MAXREJECTS Feature: When coding the control file, if the user specifies incorrect record positions for an input data field, it is likely that Geosupport will reject most or all of the input data records. An optional control entry called MAXREJECTS is designed to prevent GBAT, to the extent possible, from wastefully processing an input data file in its entirety when incorrect record positions have been specified in the control file for an input field. The MAXREJECTS feature does this by causing execution to terminate abnormally with Condition Code 20 if a certain number of records at the beginning of the input data file are all rejected by Geosupport for any reason other than an invalid borough code. (The latter exception is designed to prevent a MAXREJECTS termination from occurring inappropriately when a user file has records that intentionally contain blank or otherwise invalid borough codes because those records represent locations outside of New York City.)

The MAXREJECTS control entry is used to specify the number of consecutive rejected records at the beginning of the input data file (ignoring any records rejected for an invalid borough code) that are to trigger a MAXREJECTS termination. For example, the control entry MAXREJECTS=50 directs GBAT to terminate abnormally with Condition Code 20 if every one of the first 50 input data records that are not rejected because of an invalid borough code is rejected for any other reason.

At the user's discretion, warnings can be treated as if they were rejects for the purpose of triggering a MAXREJECTS abnormal termination; see the discussion of the REJECTWARNINGS control entry in Section IX.7.

The MAXREJECTS control entry is optional. If the user does not code a MAXREJECTS control entry, then the value in effect defaults to MAXREJECTS=200. If the user codes MAXREJECTS=NOMAX, the MAXREJECTS feature is turned off; that is, the entire input data file is processed, regardless of how many records at the beginning of the file are rejected.

Coding incorrect input field specifications in the control file tends to make a MAXREJECTS termination likely, but it does not guarantee it. That is because some input data records may contain values in the incorrectly specified field positions that, purely by coincidence, are valid for the intended data item. If there happened to be such a record near the beginning of the input data file, and that record happened to be accepted by Geosupport, that would preclude a MAXREJECTS termination. Conversely, a MAXREJECTS termination can occur even when there are no control file errors. That is because Geosupport may reject all of the input data records that are within the scope of the MAXREJECTS triggering set simply because those particular records happen to contain geographically invalid data.

Note that the completion of a GBAT execution with Condition Code 00 does not by itself signify that no input data records were rejected by Geosupport. It signifies only that no errors were found in the control file nor (if ALIASES=VAL was coded) in the alias file; that a MAXREJECTS violation did not occur; and therefore that all input data records were processed (but not necessarily accepted) by Geosupport.

IX.4 The Input Data File (DDNAME=INFILE or INVSAM)

This mandatory input file contains the user geographic data to be processed by GBAT. In order for GBAT to be able to process a data file, it must satisfy the following requirements:

- The file must be either a sequential file or a VSAM file accessed sequentially. The DDname INFILE is used for sequential files; INVSAM is used for VSAM files. The file can have either fixed or variable length records, but the maximum permissible record length is 32,000 bytes.

- The file must be geographically homogeneous; that is, all of its records must contain the same type of geographic location to be processed. Heterogeneous files, such as a file in which some records contain addresses and others contain intersections, cannot be processed by GBAT. This restriction follows from the fact that, during one execution, GBAT calls the same Geosupport function to process every input record.

- Each data item that serves as an input item must occupy the same field position(s) within every INFILE (INVSAM) record. These field positions are specified in the control file.

IX.5 The Input Control File (DDNAME=CARDIN)

This mandatory input file contains encoded information that controls the GBAT execution, including the Geosupport function being requested, processing options, and the positions of input fields in the input data records. The control file must be provided as a fixed-length file with an LRECL of 80. Users often provide the control file as an in stream file embedded in the JCL.

Control File Syntactic Rules The information in the control file is coded in the form of control entries, which must conform to the following syntactic rules:

- Control entries may be coded in any order.
- Each record in the control file may contain one or more control entries. If more than one control entry is coded within the same record, those entries must be separated from each other by at least one blank, and they may be separated by any number of blanks.
- A control entry must not span two records.
- No blanks are permitted within a control entry.
- A control entry consists of a keyword, followed by an equals sign, followed by either a single variable value or a pair of variable values separated by a comma, depending on the keyword, as follows:
- Keywords other than those specifying the location of a field within the input data records require one variable, and are of the form KEYWORD=V, where V is a variable value specified by the user. For example, the control entry RECTYPE=1E specifies that Function 1E is to be executed during this GBAT run; 'RECTYPE' is the keyword in this control entry, and '1E' is the variable value.
- Most keywords that specify the locations of input data fields require two variables. Such a control entry is of the form KEYWORD=S,L where S and L specify the starting position and length of the input field, respectively. The two variable values must be separated by a comma. For example, the control entry ONSTREET=58,32 specifies that the input street name field starts in position 58 of the input data record and is 32 bytes long.
- For keywords that specify the locations of input fields for data items of invariant length, coding the length variable is usually optional. For example, a BIN is always a seven-byte item; therefore, if an input BIN field starts in, say, position 29, the control entry specifying that field may be coded as either BIN=29 or BIN=29,7. However, a BBL is always a ten-byte item, but must be explicitly coded as such. See Table A9-2 for default information.

Many of the control entries are optional. GBAT assigns predetermined default values to the variables of all relevant optional control entries that the user has not coded. The default values are suitable for most applications. GBAT issues messages in SYSPRINT informing the user of all such default assignments.

Control File Validation Processing GBAT validates the control file for syntax and, to a certain extent, for content, as described below. GBAT issues an error message in SYSPRINT for each control file error encountered. After completing the validation of the control file, if there have been any errors, GBAT terminates abnormally without processing the input data file and exits with a Condition Code of either 12 or 14 as described in Chapter IX.3. Certain conditions encountered during control file validation cause warning messages to be issued, but are otherwise ignored and do not cause GBAT to terminate abnormally.

The control file validations include verifying that all of the control entries that are mandatory for the specified Geosupport function have indeed been coded; that the variable values that have been coded in each control entry are valid values for the given keyword; and that the starting position and length that have been specified for each input data field are consistent with the input data file's record length (that is, they do not in combination specify positions beyond the end of the input data record). To do so, GBAT opens the input data file and obtains its LRECL from its Data Set Control Block (DSCB). In the case of a variable length file, the LRECL in the DSCB is the maximum allowable LRECL of the file, as specified by the user when the file was catalogued. Therefore, for a variable length input data file, GBAT can validate only that the starting positions and lengths of input fields coded in the control file are consistent with the longest possible input data file record. For a variable length file, it is the user's responsibility to insure that all starting positions and lengths specified in the control file are valid for the shortest actual input data file record. If they are not, unpredictable results may ensue.

If the control file contains more than one control entry for the same keyword, the last such control entry is effective and the others are ignored. However, no warning messages are issued indicating the presence of such duplicate keyword entries.

Appendix 9 contains three reference tables that document the full set of control entries. These tables are indispensable references for setting up control files. Tables A9-1 and A9-2 are organized by keyword, and Table A9-3 is organized by Geosupport function. Table A9-1 lists all the control entries along with narrative descriptions of their formats, purposes and usages, and for most of the control entries, citations to sections of the UPG where pertinent topics are discussed in detail. Table A9-2 indicates, for every control entry, the permissible values and the default values of its variables, and the functions for which that control entry may be used. Table A9-3 indicates, for every function, which control entries and combinations of control entries are permissible, mandatory and optional. See also the sample GBAT jobs in Appendix 10 for examples of control files.

An expeditious approach for creating a new GBAT control file is first to ascertain from Table A9-3 which control entries are mandatory and optional for the function to be executed. Tables A9-1 and A9-2 can then be consulted to review those of the control entries with which the user is unfamiliar.

IX.6 The Input Alias File (DDNAME=ALIASES)

For all Geosupport functions that accept street name input, GBAT users have the option to provide a set of user-defined street name aliases (alternative street names and street name spelling variants) in an input alias file. These aliases supplement the set of street names that Geosupport recognizes of its own accord. It is important to note that the user's aliases supplement Geosupport's street names; they do not supersede them. Also, the aliases in an alias file supplement the Geosupport names only temporarily, that is, only during a GBAT execution in which that particular alias file is provided; GBAT does not 'remember' any user-defined aliases that have been supplied in prior GBAT executions.

The alias feature is intended to enable users to customize GBAT execution for a particular data file. This feature is particularly useful for processing a data file that contains a few street names that are misspelled in a consistent manner in many records. By providing just a few entries in an alias file to identify those misspellings with corresponding 'correct' (Geosupport-recognized) spellings, the user may greatly improve the 'hit' rate without having to modify the data file itself. This could be beneficial, for example, if the data file being processed was obtained from an outside source and the user has no software at hand to modify the contents of the file to correct street name misspellings.

To use the alias feature, a control entry containing the keyword ALIASES must be coded as follows:

- ALIASES=VAL directs GBAT to validate the alias file (as described below), and then to process the input data file only if the alias file had no invalid records. If so, then during the processing of the input data file, the user-defined aliases supplement the set of street names that Geosupport recognizes. Records that result in warnings are not considered invalid in this context, and do not prevent the processing of the input data file.

- ALIASES=YES directs GBAT to validate the alias file, and then to process the input data file regardless of whether there were any invalid alias records. During the processing of the input data file, the user-defined aliases that are in the valid alias records supplement the set of street names that Geosupport recognizes, while those in invalid alias records are not used.

If no ALIASES control entry is coded, or if ALIASES=NO is specified, then GBAT performs no alias file processing, even if an ALIASES DD statement appears in the JCL.

If ALIASES=VAL or ALIASES=YES is specified, except for the circumstance discussed in the next paragraph, the user must add a DD statement to the JCL of the GBAT execution step containing the DDname ALIASES, referencing the file that the user wishes to use as the alias file during this GBAT execution.

If ALIASES=VAL or ALIASES=YES is specified, but the function being executed does not accept street name input, then a warning message is issued during control file validation, and the ALIASES control entry, as well as the ALIASES DD statement in the JCL (if any), are otherwise ignored; in particular, no alias file validating is performed in this circumstance.

The alias file must be a sequential file. Although it is expected that most alias files will have at most a few dozen records, GBAT is designed to accommodate alias files of up to 5,000 records. The alias file must have a record length of 80 and must conform to the following layout:

Record Layout of Alias File

Field	Size	Positions	Comments
Borough Code	1	1	Standard Geosupport borough codes
User's Alias Street Name	32	34-65	Need not be in normalized format
Filler	15	66-80	Blanks

Alias File Validation Processing GBAT validates each record in the alias file, and writes an appropriate message to SYSPRINT for each error or warning condition encountered. A basis of the validation processing is that the alias street name is supposed to be a name that is not already recognized by Geosupport, whereas the street name in the field labeled 'Street Name Recognized by Geosupport' is supposed to be recognized. The alias file validation processing is as follows:

- 'Normal' case: if the alias name is not recognized, and the putative Geosupport-recognized name is in fact recognized, the alias file record is valid.
- Error: If the alias name and the putative Geosupport-recognized name are identical, the alias record is invalid. This condition tends to indicate that the user inadvertently entered the alias name incorrectly when creating this record.
- Warning: If the two names are different, and they are both recognized by Geosupport, and they have the same seven-digit street code (B7SC), then the alias record is superfluous but harmless. A warning message is issued, and the alias name is used.
- Error: If both names are recognized, but they have different B7SC values, the alias record is invalid.
- Error: If the putative Geosupport-recognized name is not in fact recognized, the alias record is invalid.

Note: GBAT does not check whether there is more than one record in the alias file containing the same alias name. If there is more than one, only the first valid record (if any) is used during the processing of the input data file; the other records containing that alias name are validated but are otherwise ignored. It is the user's responsibility to insure that the alias file does not have multiple records containing the same alias name. GBAT issues no warning message indicating the existence of such records.

IX.7 The Output File of Accepted Records (DDNAME=OUTFILE)

This optional output file contains a record corresponding to each input data record accepted by Geosupport. The user can specify whether OUTFILE is to be created, and if so, how its records are to be constituted, using the GEOCODE control entry. (The GEOUNIT control entry also plays a role in determining how the OUTFILE records are constituted. GEOUNIT is discussed later in this section.) The user can specify whether warnings are to be treated as accepted records or as rejects using the REJECTWARNINGS control entry. These control entries are discussed in detail below.

Controlling the Creation and Contents of OUTFILE with GEOCODE (and GEOUNIT)
GBAT creates either two or three output files, depending on the (coded or default) value in effect for the GEOCODE control entry. If GEOCODE=VAL is explicitly coded (it is never the default), only ERRFILE and SYSPRINT are created. If the value in effect for GEOCODE is other than VAL, then OUTFILE, the file of accepted records, is also created. When GEOCODE=YES or ALL, then ERRFIL2 or ERRFIL3 may also be created.

The purpose of the option GEOCODE=VAL is to enable the user to validate the input data file while avoiding the execution-time overhead that would be incurred to create OUTFILE. The user can execute GBAT repeatedly with GEOCODE=VAL, each time correcting as many rejected input data records as possible, until the rejection rate is acceptable to the user. At that point, a final execution with GEOCODE=NO, YES or ALL can be run to obtain OUTFILE.

In all cases in which OUTFILE is created, its records are formed by appending data obtained from Geosupport to exact copies of the accepted input data records. The length and layout of the appended Geosupport data depend on the function requested and on the GEOCODE option that is in effect (and, for COW Functions 1, 1E, 1A and 1B, the GEOUNIT option that is in effect) as described below.

For GEOCODE=NO, the appended items consist generally of output items from Work Area 1 appropriate to the given function. For MSW format, Table A9-4 in Appendix 9 lists, by function, the precise layout of the data appended for GEOCODE=NO. For the COW format, see Table A12-2 in Appendix 12.

For GEOUNIT=YES (which is a COW only option), the additional appended items consist of one output item from COW Work Area 1 appropriate to the Unit input for Functions 1, 1E, 1A and 1B. Table A12-2A in Appendix 12 shows the format of the appended data.

In general terms, the items that are appended for GEOCODE=NO (and GEOUNIT=YES) are as follows:

- For functions involving street names, the appended information includes normalized street name(s) and Geosupport street code(s). All normalized street names are provided as 32 byte items, blank filled on the right as necessary. All MSW street codes are provided as ten digit street codes without a borough code (10SCs); all COW street codes are provided as eleven digit street codes with a borough code (B10SCs).

- For functions involving house numbers, normalized house numbers are appended. For Functions 1, 1A, 1E, and 1B each normalized house number is returned as follows: the normalized House Number in Display format (HND) which will be either a 12 byte item in MSW format or a 16-byte item in COW format. Also, for MSW format only, the normalized House Number is returned in a special format for the Department of Housing Preservation and Development (HNHPD), an 8 byte item. For Functions D, DG and DN, the HNHPD is not returned.

- In addition, for COW Functions 1, 1E, 1A and 1B, if GEOUNIT=YES is in effect, the 14-byte Normalized Display Format Unit Output field is also appended. Table A12-2A in Appendix 12 shows the format of the appended data

- For Function BL, the 10-byte BBL in standard format is appended. (The standard BBL consists of the borough code, the 5-byte tax block and the 4-byte tax lot.)

- For Function BN, the 7-byte BIN is appended.

For GEOCODE=YES, each OUTFILE record is formed by appending to a copy of the input record the entire Work Area 2. (See Appendix 2 and Appendix 13 for Geosupport work area layouts, MSW and COW respectively.) GEOCODE=YES is invalid for functions that do not have a WA2. For functions that have the long WA2 option, the long WA2 is appended only if the user has explicitly specified LONGWA2=YES in the GBAT control file; if the user specifies LONGWA2=NO, or does not specify a LONGWA2 control entry, then the regular WA2 is appended. Similarly for COW functions that have the Extended Mode option (MODE=X) and/or the Auxiliary Segment option (AUXSEG=YES) the larger WA2 will be appended only if the option is specifically requested.

For GEOCODE=ALL, each OUTFILE record is formed by concatenating an exact copy of the input record, followed by the data appended for the given function when GEOCODE=NO is specified (as listed in Table A9-4 in Appendix 9 for MSW and Table A12-2 in Appendix 12 for COW), followed by the data appended when GEOCODE=YES is specified. Note, for COW Functions 1, 1E, 1A and 1B when GEOUNIT=YES is specified, the GEOUNIT=YES data appears between the GEOCODE=NO data and the GEOCODE=YES data. GEOCODE=ALL is invalid for functions that do not have a WA2.

For MSW, Table A9-5 in Appendix 9 lists the length of the appended data by function and GEOCODE value. For COW, see Table A12-3 in Appendix 12. When setting up the JCL, the user must specify the LRECL parameter in the OUTFILE DD statement to equal the sum of the LRECL of the input data file and the length of the appended data as indicated in Table A9-5 for MSW, and Table A12-3 for COW.

Controlling the Treatment of Warnings with REJECTWARNINGS

Every input data record that produces a Geosupport Return Code (GRC) of ‘00’ is treated as an accepted record; that is, the following actions are taken:

- If OUTFILE is being created, GBAT writes a corresponding output record into OUTFILE.

- Regardless of whether or not OUTFILE is being created, the record contributes to the count of accepted records that appears in the SYSPRINT report of run statistics (see Chapter IX.9)
- If the record is within the scope of the MAXREJECTS triggering set (see Chapter IX.3), it precludes a MAXREJECTS abnormal termination.

Every input data record that produces a GRC of greater than '01' is treated as a reject; that is, the following actions are taken:

- GBAT writes a corresponding output record into ERRFILE (and ERRFIL2 and ERRFIL3 as needed), the output file of rejected records.
- The record contributes to the count of rejected records that appears in the SYSPRINT report of run statistics (see Chapter IX.9)
- Unless the record is rejected for an invalid borough code, it is counted as a rejected record for the purpose of determining whether a MAXREJECTS abnormal termination is to be triggered.

At the user's discretion, input data records that produce warnings (GRC = '01') either can all be treated as accepted records or they can all be treated as rejects. This choice is specified using the optional REJECTWARNINGS control entry, as follows:

- If REJECTWARNINGS=YES is specified, only the GRC '00' records are treated as accepted records; GRC '01' records are treated as rejects.
- If REJECTWARNINGS=NO is specified, then the GRC '01' records as well as the GRC '00' records are treated as accepted records.
- (Default) If no REJECTWARNINGS control entry is supplied, then the default value is NO; that is, the GRC '01' records as well as the GRC '00' records are treated as accepted records.

IX.8 The Output Files of Rejected Records (DDNAME=ERRFILx)

Each record in the Output Files of Rejected Records typically contains a Geosupport Return Code (GRC), a Reason Code and a copy of the user's input data record. The user may optionally request (via the WORKAREA1 control entry) that Work Area 1 should also be included in the output record. Work Area 1 contains the Geosupport Error Message(s) which

may help the user to correct the input data. ERRFILE and ERRFIL2 are created when Work Area 1 is not requested. When Work Area 1 is requested, ERRFIL4 and ERRFIL5 are created instead of ERRFILE and ERRFIL2.

See more detail below on all the Output Files of Rejected Records, viz. ERRFILE, ERRFIL2, ERRFIL3, ERRFIL4 and ERRFIL5.

IX.8.1 ERRFILE ERRFILE is mandatory when WORKAREA1=NO (which is the GBAT default). This output file contains a record for each 'rejected' input data record. The value of the REJECTWARNINGS option that is in effect determines which input data records are treated as rejects, as explained in [Chapter IX.7](/chapters/chapterIX/section07/).

Each ERRFILE record consists of four bytes, followed by an exact copy of the input data record. The four bytes consist of the two-byte GRC, followed by a one-byte filler containing a '-'(dash character) for display readability, followed by the one-byte Reason Code. The LRECL of ERRFILE must always be four (4) greater than that of the input data file. It is the user's responsibility to specify the LRECL of ERRFILE correctly in the JCL.

IX.8.2 ERRFIL2 (for use by Function 1B only)

ERRFIL2 is mandatory with RECTYPE=1B together with WORKAREA1=NO. It contains a record for each 'rejected' input data record. The value of the REJECTWARNINGS option that is in effect determines which input data records are treated as rejects, as explained in Chapter IX.7.

The contents of each ERRFIL2 record is as follows: The first 4 bytes contain the 2-byte GRC, followed by a dash, followed by the Reason Code for the Block Face level (Function 1E Extended) information. This is followed by 6 bytes of filler. Byte 11 contains the 2-byte GRC, followed by a dash, followed by the Reason Code for the Property level (Function 1A Extended) information. This is followed by 6 bytes of filler. The input record begins in byte 21. The LRECL of ERRFIL2 must always be 20 greater than that of the input data file. It is the user's responsibility to specify the LRECL of ERRFIL2 correctly in the JCL.

The remainder of this section describes ERRFILE / ERRFIL2 processing.
It also applies to ERRFIL4 / ERRFIL5 processing correspondingly.

The GBAT output ERRFIL2 will contain all Function 1B records that were rejected for any reason. It will contain records that were rejected for:

- The Block level but not the Property level call
- The Property level but not for the Block level call
- Both the Block and Property level calls (These rejects will also be in the ERRFILE)

If the input record has been rejected for both Block and Property level information, the output error record will be found both in the ERRFILE output error file, as well as the ERRFIL2 error file. The ERRFILE output record will have the GRC of the results of the Block level call (i.e. Function 1E), and corresponds to the GRC and Reason Code in Work Area 1. ERRFIL2 will have the same output error record and will contain both the GRC and Reason code and the newly defined GRC2 and its corresponding Reason Code. (There will be no Work Area 2 returned by GBAT when the record is rejected for both Block an Property level information.)

Note: If you are not using Function 1B, you do not have to add ERRFIL2 to your GBAT JCL. The file is not opened. No changes have to be made. However, if you are using GBAT for a Function 1B call, GBAT will abend if you do not add a DD card for ERRFIL2 to your JCL.

IX.8.3 ERRFIL3 (for use by Function 2 with RELATEDNODES=YES)

ERRFIL3 is mandatory with RECTYPE=2 and RELATEDNODES=YES. It contains a record for each input data record that is rejected with GRC 03 and Reason Code B ('many-node case').

When the requested streets intersect more than twice (GRC 03), if the user has set RELATEDNODES to YES s/he will get a special error file, ERRFIL3, with a logical record length of 3352 + length of the user's input. The ERRFIL3 record will include for each of the many nodes, the Node ID and the streets (as B7SCs) at the nodes. Therefore, to process streets that intersect more than twice, the GBAT user need only add the RELATEDNODES=YES option to get the information needed. S/He does not have to run a Function 2W GBAT run.

The contents of each ERRFIL3 record is as follows: The first 4 bytes contain the 2-byte GRC ('03'), followed by a dash, followed by the 1-byte Reason Code ('B'). This is followed by 6 bytes of filler. A copy of the input record begins in byte 11. The input record is followed by the list of nodes and the B7SCs at the nodes. The LRECL of ERRFIL3 must always be 3352 greater than that of the input data file. It is the user's responsibility to specify the LRECL of ERRFIL3 correctly in the JCL.

GBAT - ERRFIL3 Record Layout		
Length	**Positions**	**Contents**
4	1-4	'03-B' (which is the GRC-Reason Code)
6	5-10	Blanks
Length of I/P record	11-nn	User's input record
2	After input record	True Replication Counter (maximum of 20) (matches bytes 259-260 of Function 2W's Work Area 2)
140	After input record + 2	List of up to 20 Node ID (7 bytes each) (matches bytes 261-400 of Function 2W's Work Area 2)

3200	After input record + 142	List of B7SCs for Nodes. (matches bytes 401-3600 of Function 2W's Work Area 2) ([See Appendix 13](/appendices/appendix13/) - layout of Function 2W's Work Area 2)
Total length: 3352 + Length of user's input record		

The count of the records in the new ERRFIL3 file will match the statistics for:

```
03 – STREETS INTERSECT MORE THAN TWICE – USE NODE AS INPUT.
```

Note that the rejected input records will also still appear in the regular reject file (ERRFILE) in the standard ERRFILE format.

Important JCL Note: ERRFIL3 must be defined in the user's JCL for RELATEDNODES to take effect. If DDname ERRFIL3 is undefined in the user's JCL, the file will default to DD DUMMY which will not give an appropriate length. The execution will fail with a programmed abnormal termination and a Condition Code of 15. See the following error message which will appear in the output.

Condition Code: 15
GBAT Error Message:
`ERROR: THE RECORD LENGTH OF ERRFIL3 MUST EQUAL THE RECORD LENGTH OF THE INPUT FILE PLUS 3352.` `RECORD LENGTH OF THE INPUT FILE =  xxx  RECORD LENGTH OF ERRFIL3 =  yyy`

Note: If you are not using RELATEDNODES, you do not have to add ERRFIL3 to your GBAT JCL. The file is not opened. No changes have to be made.

IX.8.4 ERRFIL4 (for use with WORKAREA1=YES)

ERRFIL4 is mandatory when WORKAREA1=YES. This output file contains a record for each 'rejected' input data record. The value of the REJECTWARNINGS option that is in effect determines which input data records are treated as rejects, as explained in Chapter IX.7.

The ERRFIL4 record is the same as the ERRFILE record, except that it also includes a copy of Work Area 1. Each ERRFIL4 record consists of four bytes, followed by an exact copy of the input data record, followed by a copy of Work Area 1. The four bytes consist of the two-byte GRC, followed by a one-byte filler containing a '-'(dash character) for display readability, followed by the one-byte Reason Code. The Work Area 1 is 1,200 bytes long. The LRECL of ERRFIL4 must always be 1,204 greater than that of the input data file. It is the user's responsibility to specify the LRECL of ERRFIL4 correctly in the JCL.

IX.8.5 ERRFIL5 (for use by Function 1B only - with WORKAREA1=YES)

ERRFIL5 is mandatory when RECTYPE=1B together with WORKAREA1=YES. It contains a record for each 'rejected' input data record. The value of the REJECTWARNINGS option that is in effect determines which input data records are treated as rejects, as explained in Chapter IX.7.

The ERRFIL5 record is the same as the ERRFIL2 record, except that it also includes a copy of Work Area 1. The contents of each ERRFIL5 record is as follows: The first 4 bytes contain the 2-byte GRC, followed by a dash, followed by the Reason Code for the Block Face level (Function 1E Extended) information. This is followed by 6 bytes of filler. Byte 11 contains the 2-byte GRC, followed by a dash, followed by the Reason Code for the Property level (Function 1A Extended) information. This is followed by 6 bytes of filler. The input record begins in byte 21. The 1,200-byte Work Area 1 follows the input record. The LRECL of ERRFIL5 must always be 1,220 greater than that of the input data file. It is the user's responsibility to specify the LRECL of ERRFIL5 correctly in the JCL.

ERRFIL5 processing is identical to ERRFIL2 processing (except for the Work Area 1 which appears in the ERRFIL5 record). See the description in IX.8.2 above for further information.

IX.9 The Output Print File (DDNAME=SYSPRINT)

This mandatory output file contains all GBAT messages, including routine informational messages, abnormal termination messages, control file and alias file validation error messages, and control file default assignment informational messages.

If GBAT terminates normally, or if it terminates abnormally with a MAXREJECTS violation, SYSPRINT also contains a report of run statistics, which is usually less than one page long. The user can specify a title line for the report, consisting of any character string of up to 73 bytes, by using the TITLE control entry.

The report of run statistics indicates the number of input records processed, the number accepted by Geosupport and the number rejected, all itemized by borough. The rejected record statistics are also itemized by GRC. Input data records that result in Geosupport warnings are counted in the report of run statistics either as accepted records or as rejects, depending on the value of the REJECTWARNINGS option that is in effect, as described in Chapter IX.7. In addition, the report contains a summary list of all the GRCs that have occurred during the given GBAT execution along with their corresponding Geosupport messages.

Statistics for RECTYPE=1B: GBAT run statistics for Function 1B are slightly different. The GBAT statistics for Function 1B are based on what is in the ERRFILE output error file. Since only records that are rejected for both the Blockface (Function 1E) and the Property Level (Function 1A) calls are in the ERRFILE, the output statistics are based on these records. The

errors indicated in the statistics are based on the GRC from the Function 1E call. The report also displays totals for the 1B records that were accepted for the 1A portion but rejected for the 1E portion, and totals for the 1B records that were accepted for the 1E portion but rejected for the 1A portion.

CHAPTER X

DESKTOP EDITION: GEOSUPPORT BATCH ADDRESS TRANSLATOR (GBAT)

X.1 What is GBAT?

GBAT Desktop Edition is Geosupport Desktop Edition's batch utility application and may be executed on any 32-bit Windows platform. GBAT Desktop Edition (referred to as GBAT in this document) can frequently satisfy your batch Geosupport processing needs and eliminate the necessity of your writing your own application program.

GBAT accepts as input and provides as output either text files or most databases that are supported by Microsoft's ODBC (Open Database Connectivity), such as Access[2]

Execution of GBAT is controlled by control files that you create via a user friendly, full featured graphical interface. Once you have created these control files, they may be used repeatedly.

If you are using a database for input and/or output, you must have a fairly thorough knowledge of how to use that database. This document does not discuss how to use any database. For information on the database that you are using, refer to either the vendor documentation on the database or to Microsoft documentation.

GBAT produces two types of output text files or databases. One set of output consists of the successful output and the second consists of the records that resulted in an error condition.

NOTE FOR DATABASE USERS:

GBAT returns empty input fields as Zero Length Strings in the output, even if they were originally NULL. This phenomenon has been observed using Access and is presumed to exist using other databases as well. We hope to fix this in a future release of GBAT Desktop Edition.

---

[2]GBAT has been successfully tested with Access, dBASE, Excel, MS SQL Server and FoxPro. GBAT has not been successfully tested with Paradox.

X.2 Using GBAT

X.2.1 Before You Begin

Use the Geosupport Desktop Edition Installation CD to install the Geosupport Desktop Edition package.

It is recommended that you use GBAT on machines with the latest versions of the “Microsoft Data Access Components” and “Microsoft Jet”. If you want to make certain that you are up to date, download and install the following files from Microsoft’s web site: Mdac_typ.exe,Jet40Sp3_Comp.exe, and Jet40SP6_9xNT.exe.

X.2.2 Starting the Application

To start the application, find and double-click the NYCgbat.exe program icon which appears as shown on the right side, in My Computer or Windows Explorer.

X.2.3 Selecting an ODBC Data Source

Upon starting the application, you will be presented with the following ODBC data source selection screen.

An ODBC Data Source file is a configuration file that contains information about a database that can be accessed through ODBC. If you have previously configured the data source, it will be listed in the list displayed in the “Select Data Source” window, an example of which is

shown above. In that situation, select that Data Source and click on the OK button. Then proceed to Chapter X.2.5 labeled “Function Selection” in this document. If you have not previously configured your data source, you need to create a new data source. This is done by clicking on the New button.

Creating a data source using a database that you are familiar with should be a fairly straightforward process; refer to the documentation or online help of your ODBC driver’s data source configuration for further information. **See Note For Database Users on previous page.**

Creating a data source for text files is more complicated. Follow the steps indicated in Chapter X.2.4 to create a data source for the text files.

X.2.4 Configuring a New Text Data Source

First, click on the New button in the Select Data Source Window, which is illustrated above. You will be presented with a list of drivers for which a data source can be set up as illustrated below on the “Create New Data Source” window. Select the Microsoft Text Driver and click on the Next button.

In the ”Create New Data Source” window illustrated below, choose a name for your data source and click on the Next button.

Click on the finish button in the window shown next, and you will be taken to the ODBC text driver's configuration screen.

The next window illustrates the “ODBC Text Setup” screen as it initially appears.

In the above window, first deselect the “Use Current Directory” checkbox.
Next Using the “Select Directory” button, choose the directory in which your text files are located.
Then click on the Options button to expand the window.

If the extension of the filenames in which your data is stored does not appear on the Extensions List of the above window, type it in the Extension box and click on the Add button. Then, select that extension on the list and click on the “Define Format” button.

You can use the above window labeled “Define Text Format” to specify the schema of the data in each of your text files. This is important because GBAT operates on a database paradigm rather than a flat-file paradigm. It needs to be given data in the form of Tables and Columns (also know as “fields”), rather than files and character positions, in order to make sense out of them.

First from the “Tables” menu select the name of the file whose schema you wish to define. Check the “Column Name Header” checkbox if the first line of the text file that you are configuring contains field names rather than field data. (If the data file does not contain field names, you will have to specify field names later on.)

Now, select the format in which your data is stored.

- Choose “CSV Delimited” if your data items are surrounded by quotation marks and separated by commas
- Choose “Tab Delimited” if your data items are separated by tab characters
- Choose “Custom Delimited” if your data items are separated by some other character. You will have to specify that character in the “Delimiter” field.
- Choose “Fixed Length” if the data items in your text file are a fixed number of characters, consistent on each line, without any sort of delimitation.

If your text file uses the Fixed Length format, and/or you have not selected the "Column Name Header" checkbox, you will now have to specify information about the fields that it contains. (In all other circumstances, the Driver should be able to determine this information automatically. You can click the "Guess" button if you want to make sure.) For each field in your text file:

- Choose the field's Data Type from the "Data Type" drop-down menu. This will usually be "char" for fields in text files.
- Enter a Name by which the field will be identified.
- If you are using a Fixed Length format file, and/or you have chosen "char" for the data type, specify the Width of the field in characters. This is important for any file format, because if you specify a width that is too short, the data that GBAT sees will be truncated. However, it is especially important for Fixed Length format files that the field width be accurate, because the width value is also used to determine the starting position of the following field.
- Click on the Add button to add the field specification to the Columns list.

If, for example, you have a Fixed Length format text file, where two lines appear as:

```
22 Reade St. 1
1541 E28 St. 3
```

This file contains an Address Number field beginning at position one that is five characters long, followed by a street name field beginning at position six that is twelve characters long, followed by a borough code field beginning at position eighteen that is a single character long. To configure the columns for this table, select Char from the data type list, type "ADDRESS NUMBER" for the name, and "5" for the width; then click on the Add button. Then select Char, enter "Street Name", and "12", and click on Add. Finally, select char once again, enter "Borough Code", "1", and click on Add.

When you've finished setting up your table, you can select another text file to configure from the Tables list box. After you have configured all of your tables, click on the OK button to return to the "ODBC Text Setup" window. Click on the OK button in this window. You have now finished setting up your Text ODBC Data Source. Select your newly created data source in the window labeled "Select Data Source", which should be displayed now. Click on the OK button to continue to the next step.

X.2.5 Function Selection

This is the point at which the configuration of your GBAT session proper begins. First, you will be defining the input information to be used by GBAT; that is, where the data is coming from, and what sort of processing should be carried out on it.

If you have already configured the input settings and saved them to a file, you can retrieve those settings here. Select the “Load Configuration” checkbox and find the saved configuration file using the Browse button. You may then proceed to Chapter X.2.7 labeled “General Input Configuration” by clicking on the Next button.

You must choose a table to be the source of your input data. To do this, select a table from the “Select a Table” drop-down list. This will be a data source that you previously configured as described in Chapter X.2.3 of this document.

You must also choose the Geosupport function that will be used to process your data. To do this, select the radio button for the appropriate function. For more information on the capabilities of each of the Geosupport functions, please see Appendix 1.

Click on the Next button to continue on to the next screen.

X.2.6 Function-Specific Configuration

X.2.6.1 Function 1 and Function 1E

If you chose Function 1 on the Function Selection window, the following window will be displayed.

Please note that the window for Function 1E differs from the window for Function 1 only in the label at the top of the window.

The input information required to execute Function 1 or 1E includes an address number, street name or street code, and borough.

Your text file or database may contain the house number in one of three different forms. The most common form is the manner in which you would normally write the house number; e.g. 22, 61-15, 27A, etc. If your data is in this form, select the first button under House Number which is labeled “Address Number”. If your file has been processed by the Geosupport system you may have saved the form of the house number used internally in Geosupport referred to as HNS, which stands for House Number in Sort format. If your data is in this format, select the second button under House Number, which is labeled HNS. The third possibility is that the address number is combined with the street name and, consequently, there will be no separate field for the address number. In this case, select the third button under House Number which is labeled None (Freeform address). If either “Address Number” or “HNS” is selected, then select the field in your file which contains the Address Number or HNS. If you have selected “HNS”, the field must be eleven characters wide. If you have selected “Address Number”, then the field may be any size up to sixteen characters wide. If you have selected “None”, then no field is selected.

Next specify the format of your street data, which will be street name or street code. If you have selected the street code option and the street code field in your database contains a borough code as its first digit, select the “Street Code Contains Borough Code”button. From the drop-down list, select the field in the table that contains the street data.

Now specify the field in your table that contains the borough code. If the borough code in your table is contained within the street code field, this step will not be necessary.

Once you have finished configuring these options, click on the Next button to move on to the next screen, which is described in Chapter X.2.7 labeled “General Input Configuration”.

X.2.6.2 Function 1A

If you chose Function 1A on the Function Selection screen, the following window will now be displayed:

The input information required to execute Function 1A includes an address number, street name or street code, and borough as well as information defined as “Extended Data”. For information on defining the address number, street information and borough refer to the previous section which describes the input information required to execute Function 1 and 1E since this information is the same.

For Function 1A, you have the option of having Geosupport return a list of addresses or a list of Building Identification Numbers commonly referred to as BINs. If you want the list of addresses, select the button labeled “Address List”. If you want the list of BINs, select the button labeled “BIN List”. Since the number of addresses in the address list can vary from one to twenty one and the number of BINs in the BIN list can vary from one to two thousand five hundred, only the first item in the list will be returned as an optional field for your output table. However, if you would like the full list of addresses or BINs, select the “Output Complete List” checkbox and enter the name of the database table to which you would like the list to be output. If you later chose to output the results of the data processing as text files rather than database tables, the name that you specify here will be ignored. If the database table does not exist, it will be created during execution of GBAT.

Once you have finished configuring these options, click on the Next button to move on to the next screen, which is described in Chapter X.2.7 labeled “General Input Configuration”.

X.2.6.3 Function 1N

If you chose Function 1N on the Function Selection screen, the following window will be displayed:

The input information required to execute Function 1N includes a street name and borough. First select from the drop-down list the field in the table that contains the street name. Next specify the field in your table that contains the borough code.

Once you have finished configuring these options, click on the Next button to move on to the next screen, which is described in Chapter X.2.7 labeled “General Input Configuration”.

X.2.6.4 Function 2

If you chose Function 2 on the Function Selection screen, the following window will now be visible:

The input information required to execute Function 2 includes two streets and the borough associated with each street. If the streets intersect exactly twice, a compass direction is required as well. If the streets intersect more than twice, then the intersection cannot be processed by Geosupport.

First, it is necessary to specify the format of your street data, which will be in the form of either street name or street code. The street code may be either the five-digits, seven digits or ten-digits. If the street code field has been selected and it includes the borough code, then select the boxes labeled “Street Code Contains Borough Code”. From the drop- down lists, select for each street the field in the table that contain the street data to be used. Do the same for the borough codes, if they are not contained within the street codes.

If you are using street codes, please ensure that all of the street codes you provide for each street are of the same length; that is, all street codes must be either 5 digit, 7 digit or 10 digit and all must either include or exclude the borough code.

If you would like to specify a field for compass directions, ensure that the “Compass Direction” checkbox is checked and select the appropriate field from the drop-down list. If you do not wish to provide this optional field, ensure that the “Compass Direction” checkbox is not checked.

Once you have finished configuring these options, click on the Next button to move on to the next screen, which is described in Chapter X.2.7 labeled “General Input Configuration”.

X.2.6.5 Function 3

If you chose Function 3 on the Function Selection screen, the following window will be displayed:

The input information required to execute Function 3 includes the on-street, two cross streets and the boroughs of each street.

First, using the radio buttons, specify the format of your street data, which will be street name or street code. For each street for which you have selected the street code option and for your data the borough code is not contained within the street code, check the “External Borough Code” checkbox. From the drop-down lists, for each street select the field in the table that contains the street data. Do the same for the borough codes, if they are not included with the street codes.

If you are using street codes, please ensure that all of the street codes you provide for each street are of the same length; that is, all street codes must be either 5 digit, 7 digit or 10 digit and all must either include or exclude the borough code.

Once you have finished configuring these options, click on the Next button to move on to the next screen, which is described in Chapter X.2.7 labeled “General Input Configuration”.

X.2.6.6 Function 3C

If you chose Function 3C on the Function Selection screen, the following window will now be displayed:

The input information required to execute Function 3C includes a compass direction, an on-street name, two cross streets, and the boroughs for each of the streets.

First, using the radio buttons, specify the format of your street data, which will be street name or street code.
Next select the field containing the compass direction from the “Select a Field for Compass Direction” drop-down.
Refer to Chapter X.2.6.5, which describes the input for Function 3, for information on supplying the rest of the data for Function 3C.
Once you have finished configuring these options, click on the Next button to move on to the next screen, which is described in Chapter X.2.7 labeled “General Input Configuration”.

X.2.6.7 Function BL

If you chose Function BL on the Function Selection screen, the following window will now be displayed:

The input information required to execute Function BL includes a borough, tax block and tax lot. Each of these items may be provided in separate fields or as a single ten-character string in one field.

If you would like to provide the entire BBL in a single field, select the “Full BBL” radio button in the Borough area of the window and then choose the appropriate source field from the drop-down menu.

If, on the other hand, you would prefer to provide each element of the BBL individually, select the “Borough Code” radio button in the Borough area of the window and then choose the appropriate source field for the borough code from the adjacent drop-down. Do the same thing for the tax block and the tax lot in the subsequent areas of the window.

For Function BL as for Function 1A, you have the option of having Geosupport return a list of addresses or a list of Building Identification Numbers commonly referred to as BINs. If you want the list of addresses, select the button labeled “Address List”. If you want the list of BINs, select the button labeled “BIN List”. Since the number of addresses in the address list can vary from one to twenty one and the number of BINs in the BIN list can vary from one to two

thousand five hundred, only the first item in the list will be returned as an optional field for your output table. However, if you would like the full list of addresses or BINs, select the "Output Complete List" checkbox and enter the name of the database table to which you would like the list to be output. If you later chose to output the results of the data processing as text files rather than database tables, the name that you specify here will be ignored. If the database table does not currently exist, it will be created during the GBAT execution.

Once you have finished configuring these options, click on the Next button to move on to the next screen, which is described in Chapter X.2.7 labeled "General Input Configuration".

X.2.6.8 Function BN

If you chose Function BN on the Function Selection screen, the following window will now be displayed:

The input information required to execute Function BN includes only the Building Identification Number (BIN). Select the field containing the list of input BINs using the drop-down menu.

Unlike Functions 1A and BL, only the Address List may be returned with Function BN. The first item on this list will be available as an optional field for your output table. However, if you would like the full list of address ranges, select the "Output Complete List" checkbox and enter

the name of the database table to which you would like the list to be output. If you later chose to output the results of the data processing as text files rather than database tables, the name that you specify here will be ignored.

Once you have finished configuring these options, click on the Next button to move on to the next screen, which is described in Chapter X.2.7 labeled “General Input Configuration”.

X.2.6.9 Function D, DG, DN

If you chose a D Function on the Function Selection screen, a variation on the following window will now be displayed:

The input information required to execute Function D, DG or DN includes one to three street codes and their associated borough. Five digit street codes are supplied for Function D, seven digit street codes are supplied for Function DG and ten digit street codes are supplied for Function DN.

Chose the input field that will be used as the source for the first street code from the drop-down list. If the borough code is not also contained within this field, check the “External Borough Code” checkbox, and choose the source field for the borough code from the adjacent drop-list.

If you have additional input fields for street codes, you may specify them in a similar fashion, after first checking the “Second Street Code” and “Third Street Code” check boxes.

Please ensure that all of the street codes you provide are of the same length; that is, all street codes must be either 5 digit for Function D, 7 digit for Function DG or 10 digit for Function DN and all must either include or exclude the borough code. Please note that if the borough code is included with the street code, then the field width for Function D is six, for Function DG, eight and for Function DN, eleven.

Once you have finished configuring these options, click on the Next button to move on to the next screen, which is described in Chapter X.2.7 labeled “General Input Configuration”.

X.2.7 General Input Configuration

The General Input Configuration Window should now be displayed:

This window is used to configure various options that influence how the data is processed, but are not specific to a particular function.

You can specify the maximum length of street names that Geosupport will process and return by using the “Street Name Length” field. The value that you enter should be between four and thirty-two, inclusive. The default value is thirty-two.

The default format for street names is the Sort Order format. The Sort Order converts all numbers in street names to a four character field; for example the “1" in “1 Avenue” is preceded by three blanks and the “10" in “10 Avenue” is preceded by two blanks. The purpose of the leading blanks is to force “1 Avenue” to precede “10 Avenue” when the street names are sorted. The Compact format eliminates the leading blanks. If you would like street names to be returned in Compact format, check the Compact checkbox; otherwise street names will be returned in Sort Order format.

Certain functions are able to return lists of cross streets in Work Area 1. If you would like the names of the cross streets to be returned as well as their street codes, check the “Cross Street Names” checkbox. This checkbox will be enabled only when you are using a function that can return the cross street list.

Alias Table functionality has not yet been implemented in GBAT Desktop Edition; please ignore the associated controls in this window at this time.

If your data uses some values for borough codes other than the Geosupport standard[3], check the “Use Alternate Borough Codes” checkbox and enter them here. When encountering these non-standard borough codes, GBAT will translate them into the appropriate Geosupport equivalents, allowing successful processing to occur. This option is available only for those functions which accept borough codes for input.

If you would like to save your input configuration settings for later re-use, click on the Save Input Configuration button. You will be presented with a window which enables you to supply the name you wish to use for this file.

Once you have finished configuring the options in this window, click on the “Next” button to continue on to the next screen, which is described in Chapter X.2.8 which is labeled Output Configuration.

---

[3]The standard borough codes are 1=Manhattan, 2= Bronx, 3=Brooklyn, 4=Queens and 5=Staten Island.

X.2.8 Output Configuration

You should now see the following Output Configuration window:

This screen is used to configure various aspects of the behavior of GBAT during the function processing as well as describing the desired output. If you have previously configured these settings and saved them to a file, you can click on the “Load Output Configuration” button to retrieve the file. You will be presented with a window that lists the various output configuration files that are stored in your system.

If you would like GBAT to stop processing after a certain number of input records have been rejected by Geosupport (i.e., caused Geosupport to return an error), check the “Enable Max Rejects” checkbox. The default value is 200 and appears in the box labeled “Maximum Rejects”. If this number is not suitable for your situation, you may specify another value. If you would like records that generate Geosupport warnings as well as errors to be treated as rejects, check the “Reject Warnings” checkbox.

If you would like output to be written to text files rather than to tables in your database, check the “Write to Text Files” checkbox. Buttons labeled “Error File Browse” and “Output File Browse” will appear; these can be used to select the names of the text files in which output will be placed. For Functions 1A, BL and BN where you have selected the check box labeled “Output Complete List” after you have clicked on the “Start” button on the Function Processing window, you will receive a request for the name of the file in which the address list or the BIN list output is to be stored.

If you would like your output written to database tables, make sure that the “Write to Text Files” checkbox is not checked. You must specify a name for the error table in the “Error Table Name” text box, and a name for the output table in the “Output Table Name” text box. If you chose names belonging to tables that already exist, those existing tables will be deleted and replaced with the new tables.

Use the “Output Type” drop down list to select the type of output that you would like GBAT create. “Work Area 1” will place all of the data returned by Work Area 1 into your output table. “Work Area 2” will do the same with all the Work Area 2 fields. “WA1 and WA2” will return all the fields from both work areas into your table. If you select the “Errors Only” section, no output table will be generated at all and only errors will be returned. This is a simple way to validate the data that you have in your database or text file.

Selecting the “Custom” option from the “Output Type” drop down allows you to include whatever fields you want in the output table, in whatever order you want. Chose fields from the “Available Fields” list by selecting them with the left mouse button. Multiple fields can be selected by holding down the Ctrl key and clicking on each. To select a range of fields, hold down the shift key, click on the first fields in the range, and then on the last. To add fields to the “Selected Fields” list, click on the º button. To remove fields from the “Selected Fields” list, select them as you would those in the “Available Fields” list and click on the » button.

When you are finished setting up these configuration options, you can save them to disk for later re-use. To do so, click on the “Save Output Configuration” button.

Click on the Next button to move to the next screen, which is described in Chapter X.2.9, which is labeled Function Processing.

X.2.9 Function Processing

At this point everything is prepared for the actual GBAT execution. The Function Processing window should now appear on your display unit:

Click on the Start button to begin execution. Output messages will periodically be displayed in the window, indicating the process's status, as well as a blue progress bar which will indicate the percentage of the job that has been completed. If at any time you would like to halt the processing, simply click on the upper Cancel button.

When processing has completed, the window will look something like the following window.

If you would like to run the process again, click on the Start button. If you would like to make changes to the configuration before executing GBAT again, click on the Back button until you reach the screen that contains what you want changed.
To exit the application, click on the Finish button.

CHAPTER XI

GEOSUPPORT ON-LINE ADDRESS TRANSLATOR (GOAT)

XI.1 Introduction

IMPORTANT NOTE:

Windows Desktop GOAT has been deprecated. No updates to its functionality will be made. It will continue to be available in the 32-bit Geosupport Desktop Edition only, not in the 64-bit version. The data returned by GOAT will continue to reflect the data in the Geosupport release that came with the installation package; however, new fields that are added to Geosupport will not be added to GOAT.

Please note that a fully-supported version of GOAT is available at:

www.nyc.gov/goat

Description of GOAT:
Geosupport On-Line Address Translator, commonly referred to as GOAT, is the system's principal interactive Windows application. It is an inquiry application that allows the user to request almost any Geosupport Function. The user simply enters input data and receives a formatted screen display of the output information provided by that function. To use GOAT requires no programming skills and it is heavily used by non-technical people who need the information that GOAT can provide.

XI.2 How to Use GOAT

The GOAT icon that is displayed on the right side of this page may appear on your desktop. To invoke GOAT, click on this icon. If the icon is not on your desktop, you may invoke GOAT from the folder in which Geosupport was installed on your system via EXPLORER. The screen displayed on the next page will appear on your desktop.

You may invoke a function by clicking on the tool bar at the top of the GOAT window as illustrated to the below.

An alternate method is to click on “Goat Function” on the line above the tool bar to display a list of Geosupport Functions as illustrated below.

Note: All illustrations are samples and may not appear identical to what appears on your screen.

To invoke any function, click on the function either on the tool bar or in the Goat Function list.

XI.3 Invoking Function 1 or Function 1E

After you have clicked on "1" in the tool bar or "Fn 1" in the “Goat Function” list, the dialogue box displayed below will appear in your GOAT Window.

To invoke Function 1 or 1E, you must enter a house number in the text box labeled “House Number” and a street name in the text box labeled “Street Name”. If you want information about a place name such as the Bronx Zoo or the Empire State Building, then you enter the place name in the text box labeled “Street Name” and leave the text box labeled “House Number” blank. You select the borough by clicking on one of the buttons associated with “Borough”. The borough names are abbreviated. Mn is Manhattan, Bx is the Bronx, Bk is Brooklyn, Qn is Queens and SI is Staten Island. The dialogue box appears with the borough pre-set to Manhattan. You may choose to receive or not to receive information concerning the political districts (Function 1E), such as Election District, Assembly District, etc

The input and the output are displayed as below. In this example the political districts are displayed.

Fn 1: Geographic Information by Address

House Number: 22

Street Name: Reade Street

Borough: (•) Mn ( ) Bx ( ) Bk ( ) Qn ( ) SI

Political Districts Required? (•) Yes ( ) No

OK | Cancel

GeoSupport Online Address Translation (GOAT) - Fn 1: Geographic Information for 22 READE STREET in MANHATTAN

File Goat Functions View Window Help

1 1A 2 3 3S BL BN B D

Fn 1: Geographic Information for 22 READE STREET in MANHATTAN

Address is on the right side of the street when facing in the direction from low to high house numbers.

Zip Code:	10007	Community District:	101	DOT Street Light Area:	1
2000 Census Tract:	31.00	Police Borough Command:	1	School District:	02
2000 Census Block:	2002	Police Precinct:	005	Fire Division:	01
1990 Census Tract:	31.00	Health Area:	77.00	Fire Battalion:	01
Dynamic Block:	210	Health Center District:	15	Fire Company Type:	L
LION Face Code:	3845	Interim Eligibility:	Ineligible	Fire Company:	001
LION Sequence Number:	00040	BOE Preferred Street Code:	2939001	Sanitation District:	101
Segment Id:	0023554	Segment Length:	468	Sanitation Section/SubSection:	3B
Congressional District:	08	State Senatorial District:	25	Regular Sanitation Pick-Up:	TTHS
Civil Court District:	01	City Council District:	01	Recycling Sanitation Pick-Up:	ES
Assembly District:	66	Election District:	004		
X Coordinate:	0982897				
Y Coordinate:	0199487				
Low House Number:	14	High House Number:	50		

Low End Cross Streets	High End Cross Streets
120240 ELK STREET	113610 BROADWAY

For Help, press F1

XI.4 Invoking Function 1A

After you have clicked on the “1A” in the tool bar or the “Fn 1A” in the “Goat Function” list, the dialogue box displayed on the right will appear in your Goat Window. To invoke Function 1A you must enter a house number in the text box labeled “House Number” and a street name in the text box labeled “Street Name”.

If you want information about a place name such as the Bronx Zoo or the Empire State Building, then you enter the place name in the text box labeled “Street Name” and leave the text box labeled “House Number” blank. You select the borough by clicking on one of the buttons associated with “Borough”. The borough names are abbreviated. Mn is Manhattan, Bx is the Bronx, Bk is Brooklyn, Qn is Queens and SI is Staten Island. The dialogue box appears with the borough pre-set to Manhattan.

You may have a choice of receiving a list of addresses associated with the property or a list of Building Identification Numbers (BINs). If you leave the button associated with “BIN List” set to “No” as shown to the right, you will receive a list of addresses associated with the property.

The output resulting from the input illustrated on the right is as displayed below.

XI.5 Invoking Function 2

After you have clicked on "2" in the tool bar or "Fn 2" in the “Goat Function” list, the dialogue box displayed on the right will appear in your GOAT Window. To invoke Function 2, you must enter two street names. The first goes in the text box labeled “First Street Name” and the second goes in the text box labeled “Second Street Name”. Place Names may not be used. You select the borough by clicking on one of the buttons associated with “Borough of First Street Name”. The borough names are abbreviated. Mn is Manhattan, Bx is the Bronx, Bk is Brooklyn, Qn is Queens and SI is Staten Island. The dialogue box appears with the borough pre-set to Manhattan. You do not need to click on a button associated with “Borough of Second Street” if both streets are in the same borough.

There are certain streets in New York City which intersect twice. One example is Cromwell Crescent and Alderton Street in Queens. To obtain information about the intersection you must specify about which one of the two intersections you want the information. This is done by

specifying a compass direction as illustrated in the dialogue box to the right. The output resulting from this input is shown below.

XI.6 Invoking Function 3 or Function 3C

After you have clicked on "3" in the tool bar or "Fn 3"

in the “Goat Function” list, the dialogue box displayed on the right will appear in your GOAT Window. To invoke Function 3 or 3C, you must enter three street names. The first goes in the text box labeled “‘On’ Street”,

the second goes in the text box labeled “First Cross Street” and the third goes in the text box labeled “Second Cross Street”. Place Names may not be used. You select the borough by clicking on one of the buttons associated with “Borough of 'On' Street Name”. The borough names are abbreviated. Mn is Manhattan, Bx is the Bronx, Bk is Brooklyn, Qn is Queens and SI is Staten Island. The dialogue box appears with the borough pre-set to Manhattan. You do not need to click on a button associated with “Borough of First Cross Street” or “Borough of Second Cross Street” if all three streets are in the same borough.

The dialogue box above will result in the output illustrated as shown below.

If you want information about only one side of the street (Function 3C), then you use the compass direction found towards the bottom of the dialogue box to select the side of the street that you are interested in.

This is illustrated in the dialogue box displayed above. The output resulting from this input is shown below.

XI.7 Invoking Function 3S

After you have clicked on the

"3S" in the tool bar or the "Fn 3S" in the “Goat Function” list, the dialogue box displayed on the right will appear in your GOAT Window. To invoke Function 3S, you must enter either one or three street names. If you want to know the names of all streets that a particular street intersects, you would supply only a Borough and an ‘On’ Street. If you are only interested in the names of some of the streets that intersect the ‘On’ Street, you may restrict the output by supplying cross streets that will limit the output.

The first street goes in the text box labeled “‘On’ Street”, the second street goes in the text box labeled “First Cross Street” and the third street goes in the text box labeled “Second Cross Street”. You may not supply a “First Cross Street” unless you supply a “Second Cross Street”. The converse is also true. Place Names may not be used. You select the borough by clicking on one of the buttons associated with “Borough of 'On' Street Name”. The borough names are abbreviated. Mn is Manhattan, Bx is the Bronx, Bk is Brooklyn, Qn is Queens and SI is Staten Island. The dialogue box appears with the borough pre-set to Manhattan.

The dialogue box on the right

requests all of the streets that intersect Reade Street in Manhattan. The output would appear as shown on the top of the next page. Please note that the output includes the approximate length of the street stretch.

Fn 3S: Stretch of READE STREET in MANHATTAN

Number of Intersections: 7

Approximate length of street stretch: 2,332 feet excluding gaps

Street Code	Street Name	Nbr of X Strs	Distance Prev. Str	Gap Flag	Alt. Borough
114590	CENTRE STREET	2	0		
120240	ELK STREET	1	268		
113610	BROADWAY	1	468		
115350	CHURCH STREET	1	535		
144890	WEST BROADWAY	1	413		
123190	HUDSON STREET	1	123		
121790	GREENWICH STREET	1	525		

Fn 3S: Display Street Stretch by 'On' Street & Optionally 2 Cross Streets

Borough of 'On' Street: (•) Mn ( ) Bx ( ) BK ( ) Qn ( ) SI

'On' Street: Reade St

First Cross Street: Elk st

Second Cross Street: Church st

Compass Direction First Intersection: ( ) North ( ) East ( ) West ( ) South

Compass Direction Second Intersection: ( ) North ( ) East ( ) West ( ) South

OK

Compass Direction is only required for duplicate Intersections.

Cancel

If you are only interested in a subset of the streets that ntersect the 'On' Street, you may limit your search by specifying cross streets as illustrated in the dialogue box to the right. The output of this search will yield the results shown below.

Fn 3S: Stretch of READE STREET between ELK STREET & CHURCH STREET in M...

Number of Intersections: 3

Approximate length of street stretch: 1,003 feet excluding gaps

Street Code	Street Name	Nbr of X Strs	Distance Prev. Str	Gap Flag	Alt. Borough
120240	ELK STREET	1	268		
113610	BROADWAY	1	468		
115350	CHURCH STREET	1	535		

If the ‘on’ street and one or both of the cross streets

intersect twice, you must specify a compass direction. In the example shown here, the street stretch being requested is Alderton Street between its northern intersection with Cromwell Crescent and its southern intersection with Cromwell Crescent. The output is shown below.

XI.8 Invoking Function B

Function B has not yet been implemented in Geosupport Desktop Edition.

XI.9 Invoking Function BL

Please note that the output for Function BL is the same as the output for Function 1A except for the information in the Title Bar which will reference your input data.

After you have clicked on the “BL” in the tool bar or the “Fn BL” in the “Goat Function” list,

the dialogue box displayed on the right will appear in your GOAT Window. To invoke Function BL, you must enter a Tax Block Number in the text box labeled “Block” and a Tax Lot Number in the text box labeled “Lot”. You select the borough by clicking on one of the buttons associated with “Borough”. The borough names are abbreviated. Mn is Manhattan, Bx is the Bronx, Bk is Brooklyn, Qn is Queens and SI is Staten Island. The dialogue box appears with the borough pre-set to Manhattan.

You may have a choice of receiving a list of addresses associated with

the property or a list of Building Identification Numbers (BINs). If you leave the button associated with “BIN List” set to “No” as shown in the dialogue box to the right, you will receive a list of addresses associated with the property. The output you would receive from the input shown is displayed on the left side of the page in the section on Function 1A.

If you wish to see a list of the Building Identification Numbers (BINs) on the property,

you need to click on the “Yes” button associated with “BIN List” as shown in the dialogue box to the right. The output resulting from the input illustrated on the right is shown on the right side of the page in the section on Function 1A.

XI.10 Invoking Function BN

Please note that the output for Function BN is the same as the output for Function 1A except for the information in the Title Bar which will reference your input data.

After you have clicked on the “BN” in the tool bar or the “Fn BN” in the “Goat Function” list,

the dialogue box displayed on the right will appear in your GOAT Window. To invoke Function BN, you must enter a Building Identification Number in the text box labeled “BIN.

You may only receive a list of addresses associated with the

Building Identification Number (BIN) that you supplied as input. The output you would receive from the input shown is displayed on the left side of the page in the section on Function 1A.

XI.11 Invoking Function D

To invoke Function D, you must click on “D” in the tool bar or the “FN D” in the “Goat Function” list. As you can see in the dialogue box displayed to the right, you have the option of supplying up to three street codes at once. You must supply the Borough information for the first street code. You only need supply the borough information for the second and third street code if the borough is different than the first one. The street codes may be entered as 5, 7 or 10 digit street codes.

Any order or combination is permitted. In the example illustrated to the right, not only is each street code in another borough, but each street code is of a different length; the first one is five digits, the second is seven and the third is ten.

You may also influence the output by modifying the contents of the text box next to the label “Street Name Length (SNL)”. Leaving the SNL at 32 results in the output illustrated below.

However reducing the SNL value to 14, results in the output below where the word “STREET” is abbreviated to “ST” and “AVENUE” is abbreviated to “AVE”.

Fn D: Street Names for 17670, 2769001 and 4093001010

Borough	Street Code	Street Name
1-Manhattan	1767001010	EAST 34 ST
2-Queens	2769001010	ALDERTON ST
3-Brooklyn	4093001010	FLATBUSH AVE

The second method that you may use to influence the output of Function D using GOAT is the Format Option. The choices are “Compact” and “Sort”. This option affects the format of street names that contain numbers. “Sort” is the default and causes blanks to be inserted in a street name in front of the number. Notice the extra blanks in front of the number 34 in the above output. If instead of leaving the Format Option set to “Sort”, you select “Compact”, the extra blanks in front of '34' will be removed as illustrated in the output below.

Fn D: Street Names for 17670, 2769001 and 4093001010

Borough	Street Code	Street Name
1-Manhattan	1767001010	EAST 34 STREET
2-Queens	2769001010	ALDERTON STREET
3-Brooklyn	4093001010	FLATBUSH AVENUE

Notice also that the “Compact” option has no effect on the display of the street names that include only non-numeric words.

Appendices and Glossary

APPENDIX 1: GEOSUPPORT FUNCTIONS - QUICK REFERENCE

Introduction

This appendix contains a summary description of each Geosupport function. The entry for each function includes the following elements:

- Description of function and UPG citations: A brief narrative description of the function's purposes, main features and principal output data, with references to relevant sections in the body of the UPG. (For a comprehensive list of output data items, see the corresponding work area layouts in Appendix 2.)

- **Validation:** A description of the validation significance of a successful two-work area call to the function. (The nature of the validation significance of a one-work area call is described in Chapter II.4.) Entries in this appendix for functions that cannot be called using two work areas do not have a validation section.

- Input fields: A list of mandatory and optional WA1 input fields used to call the function. All input field names are listed in this appendix as they appear in the WA1 layout in Appendix 2 for MSWs and Appendix 13 for COWs, except for street and house number input fields, which are listed as follows:

- Input street fields are usually listed in this appendix generically, using the terms 'Street-1', 'Street-2' and 'Street-3'. Input street data may be in the form of either street names or street codes; input street code data may be in several forms (see Chapter IV.8). The terms 'Street-1', 'Street-2' and 'Street-3' refer to any of the following three sets of WA1 input fields, the choice of which is at the discretion of the application designer: Street Name-1, Street Name-2 and Street Name-3; or PB5SC-1, PB5SC-2 and PB5SC-3 (MSW only); or B10SC-1, B10SC-2 and B10SC-3. (Note: B5SC-x (where x = 1, 2 or 3) input and B7SC-x input is located left-justified and space-filled in the corresponding B10SC-x input fields.)

The generic street input field names, 'Street-1', 'Street-2' and 'Street-3', are not used in the entries for Function 1N, which accepts input street names only, and Functions D, DG and DN, which accept input street codes only.

- Input house number fields are listed generically using the term 'House Number'. Input house numbers may be in a displayable, character format, using the WA1 input field called House Number, or they may be in HNI format (MSW, see Chapter V.2), using the WA1 input field House Number in Internal Format (HNI), or they may be in HNS format (COW, see Chapter V.2); using the WA1 input field House Number in Sort Format (HNS).

- Selected Geosupport Return Codes: A list of selected Geosupport Return Codes (GRCs) and Reason Codes that the function can issue, with brief explanations. Only certain notable GRCs specific to the function are included. GRCs that are self-explanatory or that apply to many functions, such as those relating to system errors or to street name normalization and recognition problems, are not included. For a complete list of GRCs, Reason Codes and Messages, see Appendix 4.

Appendix 2 (MSW) and Appendix 13 (COW) contain the work area layouts of all of the Geosupport functions. The abbreviated notation for street code items listed in Table IV-1 (at the end of Chapter IV) is used throughout Appendices 1, 2 and 13. Below is a summary list of the Geosupport functions.

Summary of Geosupport Functions		
Function	**User Input**	**Selected Geosupport Output Items**
1	Address or Non-Addressable Place name (NAP)	Block face-level data - Standardized Street Name and Street Code, Address Range, List of Cross Streets, ZIP Code, Community District, Health Area, Health Center District, 1990 Census Tract, 2010 Census Tract and block, Fire Engine or Ladder Company, School District, Police Precinct, Police Patrol Borough, XY Coordinates (based on the State Plane Coordinate System), **COW**: Hurricane Evacuation Zone, **COW Extended**: USPS Preferred City Name, Latitude, Longitude
1B	Address or NAP	Same as for Function 1E + Property Level Information from Function 1A + Street Names for Cross Streets and Address Lists
1E	Address or NAP	Same as for Function 1 + Political Geography (Election District, Assembly District, Congressional District, City Council District, Municipal Court District and State Senatorial District)
1A	Address	Tax lot - and building-level data - Standardized Street Name and Street Code, Tax Block and Lot, Alternative Addresses for Lot, Building Identification Number (BIN), RPAD Building Class, Interior Lot Flag, Vacant Lot Flag, Irregularly-Shaped Lot Flag, Corner Code, Business Improvement District (BID), Latitude, Longitude.
1N	Street Name	Standardized Street Name and Street Code (not available in the Desktop Edition of GOAT)
2 / 2W	Pair of Intersecting Streets, Named Intersection, or Node Number	Intersection-Level data - Standardized Street Name and Street Codes, List of Additional Cross Streets, ZIP Code, Community District, Health Area, 1990 and 2000 Census Tract, Fire Districts, School District, Police Precinct, XY Coordinates (based on State Plane Coordinate System), **COW:** Sanitation District, Health Center District, some Political Geography **COW: 2W:** Latitude, Longitude, Node IDs and Cross Streets
		Segment-level data - Standardized Street Names and Street Codes,

3	On Street and a pair of Consecutive Cross Streets	Lists of Cross Streets at both ends, and information about both sides of the street, (including ZIP Codes, Community Districts, Health Areas, 1990, 2000 and 2010 Census Tracts, Fire Districts, School Districts, Police Precincts) **COW:** 'From' and 'To' Nodes, Election District, Assembly District **COW Extended:** Latitude, Longitude, Blockface ID
3C	On Street and a Pair of Consecutive Cross Streets & a Compass Direction (Side of Street)	Same as Function 3 but for one side of the street only (Blockface information)
3S	On Street and an Optional pair of any Intersecting Streets along the On Street	Stretch-level data - Street Stretch information: List of intersecting streets in order along 'on' street, the distance between them and node IDs
AP	Address	Address Point ID, Spatial Coordinates of CSCL Address Point, BBL, BIN
BF, BB	Character String	List of up to 10 street names in alphabetic order - supports street name browsing
BL	Borough, Tax Block and Lot	Tax lot- and building- level data - List of Addresses for Lot, List of Building Identification Numbers (BINs), RPAD Building Class, Interior Lot Flag, Vacant Log Flag, Flag, Corner Code, etc.
BN	Building Identification Number	Ta lot- and building-level data - List of Address Ranges for Building, Tax Block and Lot, RPAD Building Class, Interior Lot Flag, Vacant Lot Flag, Irregularly Shaped Lot Flag, Corner Code etc.
D, DG, DN	Street Code and/or House Number	Street Name and./or House Number in Displayable
HR	None – CICS GOAT	Geosupport Data Set Information – Creation date, release cycle, number of records
N*	Street Name	Normalized street name (w/o a borough, so no consideration of validity)

Function 1

Description: Function 1 processes an input address or input Non-Addressable Place name (NAP) (see Chapter III.6). When called using two work areas, Function 1 returns information about the blockface containing the input address or NAP. This information includes the cross streets at the two intersections delimiting the blockface, and a set of geographic district identifiers including ZIP code, census tract and community district. MSW Function 1 can be called with the long WA2 option. COW Function 1 may be called with the Extended Mode Switch.

See Chapter V for a detailed discussion of Function 1 and how it differs from Function 1A.

Validation: A successful outcome of a two-work area call to Function 1 signifies (assuming address rather than NAP input) only that the input address falls within a valid range of addresses of the same parity (odd or even house numbers) allocated to some blockface; it does not signify that there is an actual building having the input address. (To validate the latter condition, Function 1A or AP must be used. See Chapter V.4 and Chapter VI.10 for Function 1A and Function AP respectively.)

Input Fields:

Function 1 Input Fields		
Field	**Value**	**Comments**
Function Code	'1 ' ('1' followed by a blank)	Required.
Work Area Format Indicator	'C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12.
Mode Switch	'X' = Extended Mode Work Area 2 Blank = normal mode	Optional; COW Only. See Chapter II.7.
Borough Code-1 (or ZIP Code)	1'=Manhattan, '2'=Bronx, '3'=Brooklyn, '4'=Queens, '5'=Staten Island	Required. (ZIP Code may be used instead of Borough Code)
House Number		Required for address input except free-form addresses (see Chapter V.3). Typically not used for NAP input (see Chapter III.6).
Long WA2 Flag (MSW Only)	'L' = Long WA2, Blank = regular WA2	Optional; default (blank) is regular WA2. See Chapter II.5.
Street-1		Required.
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2.
Street Name Normalization Format Flag	'C' = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.

Cross Street Names Flag	‘E’ = return names Blank = do not return names	Optional
ZIP Code		Optional; may be used instead of Borough Code, or to identify a DAPS. See Chapter III.6 and Chapter V.6.
Roadbed Request Switch	‘R’ = Roadbed info requested Blank = Generic info requested	Optional; default (blank) requests generic information.
Browse Flag (COW Only)	‘P’ = primary street name / code ‘F’ = principal street name / code ‘R’= DCP preferred street name / code Blank = input street name / code	Optional; may be used to select output street name / code. Default (blank) requests use of input street name / code. See Chapter III.8

Selected Function 1 Geosupport Return Codes:

GRC Value/ Reason Code Value	Meaning
01/V	(Warning) The input was a vanity address, an addressable place name, or a NAP. This message returns the underlying address or street name when available
01/P	(Warning) The street segment containing the input address is an irregular curve (i.e., it is curved but not as an arc of a circle). No values are returned in the WA2 Spatial Coordinate fields.
07	The input street was specified as a B5SC (or PB5SC) representing a NAP that is the name of a complex. Five-digit street code input is not permitted for the name of a complex. Either the NAP (the name of the complex) must be specified in the input street name field, or its B7SC or B10SC must be specified in the appropriate input street code field.
28	Partial Street name is not valid for free-form address
29	Intersection name cannot be used as ‘on’ Street.
41	The input street name is valid but this entire street has no addresses
42	The input address does not fall within a valid range of addresses for a blockface of the input street.
50	The input street name is not valid for the portion of the street where the input house number is located. See Chapter IV.5.
75	The input address is a ‘duplicate address’ - i.e., the same address exists at two different locations on the given input street. (Note: this is not a user data error, but an address that is duplicated on this street in reality.) See Chapter V.6.
89	Long workarea2 option is invalid for COW format for function 1. It is only valid for MSW for this function

Function 1A

Description: Function 1A processes an input address or input NAP. When successfully called using two work areas, it returns information in WA2 about the tax lot and the building (if any) identified by the input address or NAP. See Chapter VI and particularly Chapters VI.6.

The information that is returned in WA2 consists of information about the tax lot and the building (if any) identified by the input address or NAP. This information includes the Borough−Block−and−Lot (BBL), which is the Department of Finance's (DOF) identifier for the tax lot; the DOF building class code; the number of buildings on the lot; the number of street frontages of the lot; a flag indicating whether the lot is a condominium; the Building Identification Number (BIN) (see Chapter VI.3) of the building identified by the input address, if any; and the Business Improvement District (BID) if the property is in such a district. Function 1A can be called with the long WA2 option. The regular WA2 includes a List of Geographic Identifiers (LGI) for the tax lot, including address ranges, BINs and street frontages. The long WA2 includes, instead of the LGI, a List of BINs for all the buildings in the tax lot.

Function 1A normally returns information that is updated on a quarterly basis. COW users may request more up-to-date information on new buildings and demolitions using the TPAD Request Switch. The TPAD information will include the status of new building construction and/or demolition. See Chapter VI.11.

The regular, long, and extended WA2s for Function 1A are identical to those for Function BL. Function 1A enables the user to retrieve this information by address, while Function BL enables retrieval by BBL.

The regular and extended WA2s for Function 1A is identical to that for Function BN. Function 1A enables the user to retrieve this information by address, while Function BN enables retrieval by BIN.

Validation: An unconditionally successful outcome of a two-work-area call to Function 1A signifies that a building having the given input address exists. A warning is issued if the input is a pseudo-address (see Chapter VI.5).

Input Fields:

Function 1A Input Fields		
Field	**Value**	**Comments**
Function Code	'1A'	Required.
Work Area Format Indicator	'C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12.
Mode Switch	'X' = Extended Mode Work Area 2	Optional; COW Only. See Chapter II.7.

	Blank = normal mode	
Borough Code-1 (or ZIP Code)	'1'=Manhattan, '2'=Bronx, '3'=Brooklyn, '4'=Queens, '5'=Staten Island	Required. (ZIP Code may be used instead of Borough Code)
House Number		Required for address input except free-form addresses (see Chapter V.3). Typically not used for NAP input (see Chapter III.6).
Street-1		Required.
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2.
Street Name Normalization Format Flag	'C' = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.
ZIP Code		Optional; may be used instead of Borough Code, or to identify a DAPS. See Chapter III.6 and Chapter V.6.
Browse Flag (COW Only)	'P' = primary street name / code 'F' = principal street name / code 'R' = DCP preferred street name Blank = input street name / code	Optional; may be used to select output street name / code. Default (blank) requests use of input street name / code. Chapter III.8
Long WA2 Flag	'L' = Long WA2, Blank = regular WA2	Optional; default (blank) is regular WA2. See Chapters II.5 and VI.6.
TPAD Request Switch (COW Only)	'Y' = TPAD information requested Blank or 'N' = TPAD not requested	Optional; may be used to request Transitional PAD information. See Chapter VI.11
1A/BL Version Switch	'S' = standard version(MSW or COW) Blank = standard version; (COW Only)	'S' is required for MSW; Optional for COW. See Chapter VI.8.
1A/BL Version Switch	'S' = standard version, Blank = standard version; valid only for COW	Required for MSW; Optional for COW. See Chapter VI.8.

<u>Selected Function 1A Geosupport Return Codes:</u>

GRC Value/ Reason Code	**Meaning**

Value	
01/8	(Warning) Input address is a pseudo-address.
01/A	(Warning) Function 1A has been called with the regular WA2, but the tax lot identified by the input address or NAP has the List of Geographic Identifiers (LGI) overflow condition, and therefore the LGI in WA2 is incomplete. If a complete list of BINs for the tax lot is required, Function 1A may be called with the long WA2 option for the same input data to retrieve the BINs of all buildings on the tax lot.
01/*	(Warning) [related to TPAD]See Chapter VI.11.Various messages are returned with this reason code. The Conflict flag is set to correspond to the specific warning message
04	An invalid value has been specified for the 1A/BL Version Switch. Must be 'S' for standard. See Chapter VI.8.
07	The input street was specified as a B5SC (or PB5SC) representing a NAP that is the name of a complex. Five-digit street code input is not permitted for the name of a complex. Either the NAP itself (the name of the complex) must be specified in the input street name field, or its B7SC or B10SC must be specified in the appropriate input street code field.
41	The input street name is valid but this entire street has no addresses.
42	The input address is not valid (as defined in Chapter V.4).
50	The input street name is not valid for the portion of the street where the input house number is located. See Chapter IV.5.
69/B	Invalid TPAD Request Switch. Must be Y, N or blank
73	Legacy version of Function 1A is discontinued. See Technical Bulletin 05-1.
75	The input address is a 'duplicate address' - i.e., the same address exists at two different locations on the given input street. (Note: this is not a user input data error, but an address duplication that exists in reality.) See Chapter V.6.
90	Invalid value specified for Long WA2 Flag – must be 'L' or blank

Function 1E

Description: Function 1E processes an input address or input NAP. When called using two work areas, it returns the same WA2 information that is returned by Function 1, and additionally, it returns a set of political districts, including Election, State Assembly and Senate, City Council and Congressional Districts. The layouts of WA2 for Functions 1 and 1E are identical, except for the political district fields, which are fillers in Function 1's WA2.

Input Fields: Same as Function 1, except for definition of the Browse Flag. When the Browse Flag is set to 'R', the Board of Elections (BOE) preferred street code is returned instead of the DCP preferred street code. See below.

	'P' = primary street name / code	

Browse Flag (COW Only)	‘F’ = principal street name / code ‘R’ = BOE preferred street name / code Blank = input street name / code	Optional; may be used to select output street name / code. Default (blank) requests use of input street name / code. See Chapter III.8

Browse Flag ‘P’ = primary street name / code Optional; may be used to
(COW Only) ‘F’ = principal street name / code select output street name / code.
‘R’ = BOE preferred street name Default (blank) requests use of
/ code input street name / code. See
Blank = input street name / code Chapter III.8

Validation: Same as Function 1.

Selected Function 1E Geosupport Return Codes:

Function 1E’s possible GRC values include all of the ones for Function 1, and also the following:

GRC Value/ Reason Code Value	Meaning
01/E	(Warning) The output address range returned in WA2 is split by an election district boundary. Therefore, the election district value returned in WA2 applies to only a portion of that address range.
56	The input address is associated with more than one Election District (ED). Function 1E requires that this address be specified with a house number suffix to identify a portion of the building specific to one ED. See Chapter V.4.

Function 1B

Description: Function 1B processes an input address or input Non-Addressable Place name (NAP) (see Chapter III.6). When called using two work areas, Function 1B returns information about the blockface as well as information about the tax lot and the building (if any) identified by the input address or NAP. The information that is returned in WA2 includes the cross streets at the two intersections delimiting the blockface, and a set of geographic district identifiers including ZIP code, census tract and community district. Information about the tax lot and the building (if any) identified by the input address or NAP is also returned. This information includes the Borough−Block−and−Lot (BBL), which is the Department of Finance’s (DOF) identifier for the tax lot; the DOF building class code; the number of buildings on the lot; the

number of street frontages of the lot; a flag indicating whether the lot is a condominium; and the Building Identification Number (BIN) (see Chapter VI.3) of the building identified by the input address

Function 1B Input Fields:

Function 1B Input Fields		
Field	**Value**	**Comments**
Function Code	'1B'	Required.
Work Area Format Indicator	'C' = COW format	
Borough Code or ZIP Code	'1'=Manhattan'2'=Bronx, '3'=Brooklyn, '4'=Queens, '5'=Staten Island, or nnnnn	Required.
Street Name		Required.
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2.
Street Name Normalization Format Flag	'C' = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.
ZIP Code	Optional; may be used instead of Borough Code, or to identify a DAPS. See Chapter III.6 and Chapter V.6.	
Browse Flag	'P' = primary street name / code 'F' = principal street name / code 'R'= DCP preferred street name / cod e Blank = input street name / code	Optional; may be used to select Output street name / code. Default (blank) requests use of Input street name / code. See Chapter III.8.

Validation: Same as Function 1 and Function 1A..

Selected Geosupport Return Codes: Function 1B's possible GRC values include all of the ones for Function 1, Function 1E, Function 1A, and also the following:

GRC Value / Reason Code Value	Meaning
??/1 (MSW Only)	INVALID FUNCTION CODE – AVAILABLE IN COW FORMAT ONLY

Function 1N

Description: Function 1N is used to normalize a street name and obtain its street code. Functions 1, 1A and 1E can do this also, but those functions require an input house number. The purpose of Function 1N is to provide a way to process a street name alone, without a house number. Note that since the input to Function 1N is not a specific location along a street, Function 1N does not perform local street name validation.

Function 1N does not have a Work Area 2, and can only be called using one work area. See Chapter III.1.

Function 1N Input Fields:

Function 1N Input Fields		
Field	**Value**	**Comments**
Function Code	'1N'	Required
Work Area Format Indicator	C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12
Borough Code-1	1'=Manhattan, '2'=Bronx, '3'=Brooklyn, '4'=Queens, '5'=Staten Island	Required
Street Name-1		Required. (Note: Street code input is not permitted for Function 1N.)
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2.
Street Name Normalization Format Flag	'C' = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.
Browse Flag (COW Only)	'P' = primary street name / code 'F' = principal street name / code Blank = input street name / code	'P' = primary street name / code 'F' = principal street name / code Blank = input street name / code

Selected Geosupport Return Codes: All are self-explanatory.

Function 2 (and 2W)

Description: Function 2 processes an input intersection specified either in terms of an intersection name, or in terms of two streets (and, when necessary, a compass direction), or in terms of a node ID. If two input streets intersect exactly once, the user should not specify an input compass direction. If the two input streets intersect at two distinct locations, a compass direction must be specified; it serves to identify which of the two intersections the user wishes Geosupport to process. Geosupport has the ability to process a pair of input streets that intersect more than twice, only if the user can identify the intersection by its node ID. If the user does not know the node ID, the user may issue Function 2W to find the node ID. Function 2W is basically identical to Function 2 except when streets intersect more than twice, Function 2W

will reject the call and return a Work Area 2 that includes the node IDs and street codes/street names for all the intersections at the various nodes. Function 2 and Function 2W are discussed in detail in Chapter VII.2.

When successfully called using two work areas, Function 2 returns information about the input intersection in WA2. If there are more than two streets at an intersection, Function 2 accepts any pair of those streets as user input for that intersection. An intersection that lies on a borough boundary can be specified in terms of one street from each borough, by using the WA1 input field Borough Code 2, as described in Chapter VII.7.

The information that Function 2 returns in WA2 includes a list of street codes for all streets at the intersection (including the input streets), spatial coordinates for the intersection, and a set of geographic area identifiers including community district, census tract, police precinct and others. If the intersection lies on the boundary of two or more areas of a given type, the information for one of those areas is returned..

In COW format only, Function 2 also returns political geography and CD Eligibility.

Validation: A successful outcome of a two-work-area Function 2 call signifies that the two input streets intersect exactly once (if no input compass direction was specified) or exactly twice (if a compass direction was specified). In the double-intersection case, a successful outcome also signifies that the input compass direction is a valid designation of one of the two intersections.

Input Fields:

Function 2 (and 2W) Input Fields		
Field	**Value**	**Comments**
Function Code	'2 ' ('2' followed by a blank) '2W'	Required.
Work Area Format Indicator	C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12.
Borough Code-1	'1'=Manhattan, '2'=Bronx, '3'=Brooklyn, '4'=Queens, '5'=Staten Island	Required (unless Node Number is used as input). Specifies borough of Street Name 1.
Street-1		Required (•) (unless Node Number is used as input). Specifies either of the two streets defining the intersection.
Borough Code-2	See Borough Code-1)	Optional unless Street Name 2 is in a different borough from Street Name 1; default is value in Borough Code-1.
Street-2		Required (•) (unless Node Number is used as input). Specifies the other street defining the

		intersection
Compass Direction	‘N’, ‘S’, ‘E’ or ‘W’	Required only when the two input streets intersect twice, in which case it designates which intersection to process
Node Number	Seven-digit number	Required when streets intersect more than twice. Optional at other nodes. May be used instead of borough and street names.
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2] (/chapters/chapterIII/section02/).
Street Name Normalization Format Flag	‘C’ = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.
Cross Street Names Flag	E’ = return names Blank = do not return names	Optional.
Browse Flag (COW Only)	P’ = primary street names / codes F’ = principal street names / codes R’ = DCP preferred street names/Codes Blank = input street names / codes	Optional; may be used to select output street names / codes. Default (blank) requests use of input street names / codes. See Chapter III.8

(•) Note: If either Street 1 or Street 2 contains an intersection name, then the other input street field may either be left blank or it may contain any street that exists at the given intersection.

Selected Function 2 (and 2W) Geosupport Return Codes:

Selected Function 2 (and 2W) Geosupport Return Codes	
GRC Value/ Reason Code Value	**Meaning**
01/H	(Warning) The two input streets intersect only once, but a non-blank input compass direction value has been supplied. The compass direction is superfluous and is ignored. A full complement of output data is returned in the work areas.
01/N	(Warning) Both a node ID and street names or street codes were specified as input. The node ID will be used; the street names/codes will be ignored.
01/T	(Warning) The input street name is ignored if an intersection name is specified along with a street name that is part of the intersection.
02	The two input streets intersect twice, but no input compass direction has been supplied. The distance between the two intersections is included in the message. A

	valid input compass direction value is required for these input streets.
03/blank	(Reject) **MSW** - The two input streets intersect more than twice. MSW Function 2 calls cannot process such intersections. The Reason Code value is blank. The message suggests that the user use a COW function call.
03/A	(Reject) **COW** - The two input streets intersect more than twice. Function 2 calls cannot process such intersections. The message suggests that the user issue a Function 2W call to find related nodes.
03/B	(Reject) **COW – Function 2W only** - The two input streets intersect more than twice. Function 2W returns node IDs and street codes. The message suggests that the user use a node ID as input.
12	The input information was in the form of an intersection name or a street code of an intersection name. Geosupport recognizes this name or code as valid, but does not yet have this name or code associated with a specific intersection.
30	An input intersection name was specified along with an input street name, but the input street is not part of the intersection
32	(Reject) An invalid node ID was specified as input. It was non-numeric or had embedded blanks..
33	(Reject) A node ID was specified as input, but no intersection was found with that node ID.
39	The input compass direction field contains an invalid value, that is, a non-blank value other than ‘N’, ‘S’, ‘E’ or ‘W’.
40	The two input streets intersect twice, but the input compass direction value supplied is an invalid descriptor for either of those intersections. If the value supplied is ‘E’ or ‘W’, it is invalid because the two intersections are situated approximately due north-south of each other; if the value supplied is ‘N’ or ‘S’, it is invalid because the two intersections are situated approximately due east-west of each other.
50	An input street name is not valid for the portion of the street where the input intersection is located. See Chapter IV.5.
62	The two input streets do not intersect.

Function 3

Description: Function 3 processes street segments and closely related three-street configurations. A street segment is a part of a street (called the ‘on' street) between two consecutive cross streets. For example, Madison Avenue (in Manhattan) between East 51st Street and East 52nd Street is a street segment. Madison Avenue between East 51st Street and East 53rd Street is not a street segment, because there is an intervening street, East 52nd Street, between the given cross streets. An exception to the requirement that the input cross streets be consecutive along the ‘on’ street is the case of a T−intersection: Function 3 accepts as input a street configuration that defines the long blockface of a T−intersection. (For precise definitions of the terms ‘three-street configuration’, ‘street segment’, and ‘T-intersection’, see Chapter

VII.3.) A street segment intersecting with or lying on a borough boundary can be specified in terms of streets from both boroughs, by using the WA1 input fields Borough Code 2 and Borough Code 3, as described in Chapter VII.7.

The information returned by a successful two−work−area Function 3 call includes two lists of street codes for all cross streets at the two intersections defined by the input streets; and geographic area codes for the left and right sides of the street, such as the left and right community districts, ZIP codes, census tracts, etc. 'Left' and 'right' are defined relative to the 'on' street's 'logical direction', which in general is the direction of increasing address. The WA2 information also includes two items called the Segment Azimuth and the Segment Orientation that indicate how the street segment is oriented with respect to the points of the compass. Applications can use either of these items to determine compass direction descriptors for the left and right sides of the street. Another WA2 item, the Cross Street Reversal Flag, can be used to determine left and right relative to the order in which the input cross streets were specified.

In COW format, Function 3 also returns the FROM and TO node IDs.

In COW Extended format, Function 3 also returns Latitude and Longitude.

Function 3 in MSW format has the Long Work Area 2 Option (see Chapter II.5).

Function 3 in COW format has the Auxiliary Segment Option (see Chapter II.6).

For a detailed discussion of Function 3, see Chapter VII.4.

Validation: A successful outcome of a two-work-area call to Function 3 signifies that the input 'on' street and two cross streets define a valid street segment or long blockface of a T-intersection.

Input Fields:

Function 3 Input Fields		
Field	**Value**	**Comments**
Function Code	'3 ' ('3' followed by a blank)	Required.
Work Area Format Indicator	'C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12.
Mode Switch	'X' = Extended Mode Work Area 2 Blank = normal mode	Optional; COW Only. See Chapter II.7.
Borough Code-1	'1'=Manhattan, '2'=Bronx, '3'=Brooklyn, '4'=Queens, '5'=Staten	Required. Specifies borough of Street Name-1.

	Island	
Street-1		Required. Specifies ‘on’ street
Borough Code-2	(See Borough Code-1)	Optional unless borough of Street Name-2 differs from that of Street Name-1. Specifies borough of Street Name-2. Default is Borough Code-1 value.
Street-2		Required. Specifies either cross street.
Borough Code-3	(See Borough Code-1)	Optional unless borough of Street Name-3 differs from that of Street Name-1. Specifies borough of Street Name-3. Default is Borough Code-1 value.
Street-3		Required. Specifies other cross street.
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2.
Street Name Normalization Format Flag	‘C’ = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.
Cross Street Names Flag	‘E’ = return names Blank = do not return names	Optional
Long WA2 Flag (MSW only)	‘L’ = Long WA2, Blank = regular WA2	Optional; default (blank) is regular WA2. See Chapter II.5.
Auxiliary Segment Switch (COW only)	‘Y’ = return all segment IDs ‘N’ or Blank = regular WA2	Optional; default (blank) is regular WA2. See Chapter II.6
Browse Flag (COW Only)	‘P’ = primary street names / codes ‘F’ = principal street names / codes ‘R’ = DCP preferred street names / codes Blank = input street names / codes	Optional; may be used to select output street names / codes. Default (blank) requests use of input street names / codes. See Chapter III.8

<u>Selected Function 3 Geosupport Return Codes:</u>

Selected Function 3 Geosupport Return Codes:	
GRC Value/ Reason Code Value	**Meaning**
	(Warning) The input ’on’ street lies on a borough boundary. The side of street

01/L or R	indicated by the Reason Code value is outside of the input borough; no information is returned in WA2 for that side of the street if it is in Nassau or Westchester.
01/Q	These streets involve a dogleg, Shortest Stretch provided. (See Chapter VII.2)
45	Although each of the three input street names was individually recognized, collectively they do not define a valid street segment nor the long blockface of a T−intersection.
46	The geographic location specified by the combination of three input streets is ambiguous, i.e., it defines more than one valid segment or T−intersection blockface. Geosupport cannot process this input.
50	An input street name is not valid for the portion of the street where the input street segment is located. See Chapter IV.5.
55	At least one of the input streets is a Non-Addressable Place Name (NAP). NAPs are not allowed as input streets for this function
69/A	Invalid value specified for Auxiliary Segment Switch. Auxiliary Segment Switch must be 'Y' or 'N' or blank.
89	Long WA2 option is not valid for this function in COW format.
90	Invalid value specified for Long WA2 Flag - must be 'L' or blank.

Function 3C

Description: Function 3C processes blockfaces specified in terms of an input 'on' street, two cross streets and a compass direction designating the side of the street, such as 'the west side of Madison Avenue between East 53rd Street and East 54th Street'. A blockface intersecting with or lying on a borough boundary can be specified in terms of streets from both boroughs, by using the WA1 input fields Borough Code 2 and Borough Code 3, as described in Chapter VII.7.

When called using two work areas, function 3C returns blockface related information in WA2. This information is a subset of the set of items returned in WA2 by Function 3, consisting of those items that are related to the specified side of the street.

Function 3C in COW format has the Auxiliary Segment Option (see Chapter II.6).

Function 3C is discussed in detail in Chapter VII.5.

Validation: A successful outcome of a two-work-area call to Function 3C signifies that the input 'on' street and two cross streets define a valid street segment or long blockface of a T-intersection, and that the input compass direction is a valid designation of a side of this segment. The validity of an input compass direction is determined by the spatial orientation of the segment.

Input Fields:

Function 3C Input Fields		
Field	**Value**	**Comments**
Function Code	'3C'	Required.
Work Area Format Indicator	'C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12.
Mode Switch	'X' = Extended Mode Work Area 2 Blank = normal mode	Optional; COW Only. See Chapter II.7.
Borough Code-1	'1'=Manhattan, '2'=Bronx, '3'=Brooklyn, '4'=Queens, '5'=Staten Island	Required. Specifies borough of Street Name-1.
Street-1		Required. Specifies 'on' street
Borough Code-2	(See Borough Code-1)	Optional unless borough of Street Name-2 differs from that of Street Name-1. Specifies borough of Street Name-2. Default is Borough Code-1 value.
Street-2		Required. Specifies either cross street.
Borough Code-3	(See Borough Code-1)	Optional unless borough of Street Name-3 differs from that of Street Name-1. Specifies borough of Street Name-3. Default is Borough Code-1 value.
Street-3		Required. Specifies other cross street.
Compass Direction	'N', 'S', 'E' or 'W'	Required. Specifies side of street of blockface (relative to street's 'logical direction' - see Chapter VII.3).
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2.
Street Name Normalization Format Flag	'C' = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.
Cross Street Names Flag	'E' = return names Blank = do not return names	Optional
Long WA2 Flag (MSW only)	'L' = Long WA2, Blank = regular WA2	Optional; default (blank) is regular WA2. See Chapter II.5.
Auxiliary Segment Switch (COW only)	'Y' = return all segment IDs 'N' or Blank = regular WA2	Optional; default (blank) is regular WA2. See Chapter II.6

Browse Flag (COW Only)	‘P’ = primary street names / codes ‘F’ = principal street names / codes ‘R’= DCP preferred street names / codes Blank= input street names / codes	Optional; may be used to select output street names / codes. Default (blank) requests use of input street names / codes. See Chapter III.8

Selected Geosupport Return Codes:

Selected Geosupport Return Codes	
GRC Value	**Meaning**
09	The blockface on the side of street specified by the compass direction does not exist in the borough specified for the ‘on’ street.
39	The input compass direction field contains a non-blank value other than ‘N’, ‘S’, ‘E’ or ‘W’
40	The input compass direction value is invalid as a descriptor of a side of the input street segment, because it is incompatible with the segment’s spatial orientation. This condition arises if the segment is oriented approximately east-west and the input compass direction value is specified as ‘E’ or ‘W’ (because a street segment oriented approximately east-west has no east and west sides), or the segment is oriented approximately north-south and the input compass direction value is ‘N’ or ‘S’
44	Although each of the three input street names was individually recognized, collectively they do not define a valid blockface.
46	The combination of these three input streets is ambiguous, i.e., it defines more than one valid blockface. Function 3C cannot process such input.
50	An input street name is not valid for the portion of the street where the input blockface is located. See Chapter IV.5.
69/A	Invalid value specified for Auxiliary Segment Switch. Auxiliary Segment Switch must be ‘Y’ or ‘N’ or blank.

Function 3S

Description: Function 3S processes input street stretches. A street stretch is a portion of a street between any two cross streets. If an input cross street intersects with the ‘on’ street twice, an input compass direction is required to identify which of the two intersections is intended. If the user application does not specify input cross streets, Function 3S returns information about the full length of the ‘on’ street. Note that, in a Function 3S call, the input cross streets need not be consecutive along the ‘on’ street.

When successfully called using two work areas, Function 3S returns, in WA2, a list of all intersections in sequence along the 'on' street between (and including) the two intersections defined by the input 'on' and two cross streets, if any. If the user has not specified input cross streets, the list contains all intersections in sequence from the beginning to the end of the 'on' street. The sequence in which the intersections are listed accords with the direction of increasing addresses along the 'on' street. Each intersection in the list is specified as a pair of street codes for two of the streets at that intersection. One of the street codes listed for an intersection may or not be the street code of the 'on' street.

In a COW function 3S call, if the user requests Real Street Only output, only real street intersections are returned; Bends and Non-Street Features are not included in the list of intersections.

For each entry in the WA2 list of intersections of the street stretch, there are fields for a distance and a gap flag. The distance is the approximate distance in feet between the given intersection and its predecessor in the list; the gap flag indicates whether the intersection and its predecessor are connected by the 'on' street. The gap flag also indicates the nature of the gap. The first entry within a list will always have a zero in the distance field and a blank in the gap flag.

Function 3S is discussed in detail in Chapter VII.6.

Validation: A successful outcome of a two-work-area call to Function 3S using input cross streets signifies that each of the input cross streets intersects the input 'on' street.

Input Fields:

Function 3S Input Fields		
Field	**Value**	**Comments**
Function Code	'3S'	Required.
Work Area Format Indicator	'C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12
Borough Code-1	'1'=Manhattan, '2'=Bronx, '3'=Brooklyn, '4'=Queens, '5'=Staten Island	Required. Specifies borough of Street-1.
Street-1		Required. Specifies 'on' street.
Street-2		Optional. Specifies either cross street.
Compass Direction for First Intersection	'N', 'S', 'E' or 'W'	Required if Street-2 intersects Street-1 ('on'-street) twice. Identifies which of the two intersections is intended.

Street-3		Optional. Specifies other cross street. Must be specified if Street-2 is specified. If Street-2 and Street-3 are not specified, data for full length of street are returned in WA2.
Compass Direction for Second Intersection	'N', 'S', 'E' or 'W'	Required if Street-3 intersects Street-1 ('on'-street) twice. Identifies which of the two intersections is intended.
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2.
Street Name Normalization Format Flag	'C' = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.
Real Street Only Flag (COW Only)	'R' = real streets only Blank = all streets	Optional; default (blank) requests all streets. See Chapter VII.6].
Roadbed Request Switch	R' = Roadbed info requested Blank = Generic info requested	Optional; default (blank) requests generic information See Chapter VII.6

Selected Geosupport Return Codes:

Selected Geosupport Return Codes	
Value	**Meaning**
01/H	(Warning) The input 'on' street intersects only once with one of the input cross streets, but a non-blank input compass direction value has been supplied for that intersection. That compass direction is superfluous and is ignored. A full complement of output data is returned in the work areas.
05	A value was supplied in at least one of the input borough code fields other than Borough Code 1. All Function 3S input streets are required to be from the same borough, which must be supplied in the WA1 field Borough Code 1; Borough Code 2 and Borough Code 3 must be blank.
14	The three input streets do not define a street stretch, because the 'from' and 'to' input intersections are identical.
38	The input 'on' street and an input cross street intersect twice, but the input compass direction value supplied is an invalid descriptor for either of those intersections. If the value supplied is 'E' or 'W', it is invalid because the two intersections are situated approximately due north-south of each other; if the value supplied is 'N' or 'S', it is invalid because the two intersections are situated approximately due east-west of each other.
39	An input compass direction field contains an invalid value, that is, a non-blank value other than 'N', 'S', 'E' or 'W'.

55	At least one of the input streets is a Non-Addressable Place Name (NAP). NAPs are not allowed as input streets for this function.
61	Geosupport has no street stretch data for this ‘on’ street. (This condition should never occur for a normal input street. It occurs if the input ‘on’ street is a pseudo-street name (such as DEAD END) or another type of geographic feature that Geosupport recognizes but that Function 3S cannot process as an input ‘on’ street.)
62	The input ‘on’ street does not intersect with one of the input cross streets.
66	The input ‘on’ street intersects with one of the input cross streets more than twice. Function 3S cannot be used to process this combination of input data. (However, Function 3S could be called for this ‘on’ street with no cross streets specified. That call would return data for the full length of the street, including the intersections in question.)
68	The input ‘on’ street intersects with one of the input cross streets twice. An input compass direction value must be supplied to identify which of the two intersections is intended.
96	The functionality to support part of a roadbed street stretch is under construction

Function AP

Description: Function AP processes an input address. When successfully called using two work areas, it returns information in WA2 about the CSCL Address Point identified by the input address. See Chapter VI and particularly Chapter VI.10. Function AP and its data are currently available to Geosupport users.

The information that is returned in WA2 consists of information about the address point and the tax lot and the building (if any) identified by the input address. This information includes the CSCL Address Point ID, the spatial coordinates of the Address Point, the Building Identification Number (BIN) and the Borough−Block−and−Lot (BBL), which is the Department of Finance’s (DOF) identifier for the tax lot. By geocoding to a CSCL Address Point, the user application will presumably geocode to a ‘real’ posted address – not an address that might be part of an administrative range.

Function AP is also available in an Extended Mode. It includes that Principal Street Name in WA2. See the Function AP work area layouts in Appendix 13.

Validation: An unconditionally successful outcome of a two-work-area call to Function AP signifies that a building having the given input address exists.

Input Fields:

Function AP Input Fields		
Field	**Value**	**Comments**
Function Code	‘AP’	Required.
Work Area		

Format Indicator	‘C’ = COW format	Required. AP is a COW only function
Mode Switch	‘X’ = Extended Mode Work Area 2 Blank = normal mode	Optional
Borough Code-1 (or ZIP Code)	‘1’=Manhattan, ‘2’=Bronx, ‘3’=Brooklyn, ‘4’=Queens, ‘5’=Staten Island	Required. (ZIP Code may be used instead of Borough Code)
House Number		Required for address input except free-form addresses (see Chapter V.3).
Street-1		Required.
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2.
Street Name Normalization Format Flag	‘C’ = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.
ZIP Code		Optional; may be used instead of Borough Code, or to identify a DAPS. See Chapter III.6 and Chapter V.6.
Browse Flag (COW Only)	‘P’ = primary street name / code ‘F’ = principal street name / code ‘R’ = DCP preferred street name Blank = input street name / code	Optional; may be used to select output street name / code. Default (blank) requests use of input street name / code. Chapter III.8

Selected Geosupport Return Codes:

Selected Geosupport Return Codes	
GRC Value/ Reason Code Value	**Meaning**
42	The input address is not valid (as defined in Chapter V.4 .
50	The input street name is not valid for the portion of the street where the input house number is located. See Chapter IV.5.
75	The input address is a ‘duplicate address’ - i.e., the same address exists at two different locations on the given input street. (Note: this is not a user input data error, but an address duplication that exists in reality.) See Chapter V.6.

Functions BB and BF

Description: Function BB ("browse backward") and BF ("browse forward") enable applications to develop street name browse capability, in order to assist user data entry staff to determine valid spellings of street names that have been rejected. Functions BB and BF can only be called using one work area.

A sequence of repeated calls to Functions BB and/or BF will browse backwards and/or forwards in alphabetical order through the set of all valid normalized street names in a given borough. When issuing a COW Function BB or BF call, the user may request that only Primary or Principal street names be returned. This is done by setting the Browse Flag to 'P' or 'F' respectively.

Each call to one of these functions returns up to ten such names in alphabetical order (or fewer, if there are not ten names remaining in the given borough in the given browse direction). The names are returned in the WA1 field List of Street Names. The number of street names returned in the list is returned in the WA1 field Number of Street Names in List. For COWs, corresponding B7SCs are also returned.

To start a browse sequence, the user application calls either of the browse functions , passing a borough code and character string in the WA1 input fields called Borough Code 1 and Street Name 1, respectively. The input character string can be from one to 32 bytes long. When the last set of ten or fewer names in the given borough is reached, a warning is issued.

For a detailed discussion of Functions BB and BF, see Chapter III.7.

Input Fields:

Functions BB / BF Input Fields		
Field	**Value**	**Comments**
Function Code	'BB' or 'BF'	Required.
Work Area Format Indicator	'C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12
Borough Code-1	'1'=Manhattan, '2'=Bronx, '3'=Brooklyn, '4'=Queens, '5'=Staten Island	Required.
Street Name-1	Any character string	Required.
Browse Flag (COW Only)	'P' = primary street names' 'F' = principal street names Blank = all street names	Optional; default (blank) See Chapter III.7.

Selected Geosupport Return Codes:

Selected Geosupport Return Codes	
GRC Value / Reason Code	**Meaning**

Value	
01/4	(Warning) The last street name has been reached in the specified input borough in the given browse direction. It is possible that fewer than ten street names have been returned in WA1
97	The input street name is alphabetically beyond the last street name in the specified input borough.

Function BL

Description: Function BL processes a parcel of real property, or tax lot, specified in terms of a standard Department of Finance set of tax lot identifiers, consisting of a combination of a borough code, a tax block number and a tax lot number, collectively called the BBL. When successfully called using two work areas, Function BL returns information about the tax lot in WA2. The WA2 layouts for Function BL are identical to those for Function 1A. Function 1A enables the user to retrieve this information by address, while Function BL enables retrieval by BBL.

For a detailed discussion of Function BL, see Chapter VI and particularly Chapter VI.7.

Validation: A successful outcome of a two-work-area call to Function BL signifies that the input BBL is valid.

Function BL Input Fields:

Function BL Input Fields		
Field	**Value**	**Comments**
Function Code	'BL'	Required.
Work Area Format Indicator	'C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12
Mode Switch	'X' = Extended Mode Work Area 2 Blank = normal mode	Optional; COW Only. See Chapter II.7.
Borough-Block-Lot (BBL)		Required.
Long WA2 Flag	'L' = Long Blank = regular WA2	Optional default (blank) is regular WA2. See Chapter II.5.
TPAD Request Switch (COW Only)	'Y' = TPAD information requested Blank or 'N' = TPAD not requested	Optional; may be used to request Transitional PAD information. See Chapter VI.11
1A/BL Version Switch	'S' = standard version, Blank = standard version; valid only for COW	Required for MSW; optional for COW. See Chapter VI.8.

Selected Geosupport Return Codes:

Selected Geosupport Return Codes	
GRC Value / Reason Code Value	**Meaning**
01/A	(Warning) Function BL has been called with the regular WA2, but the input tax lot has the List of Geographic Identifiers (LGI) overflow condition, and therefore the LGI in WA2 is incomplete. If a complete list of BINs for the tax lot is required, Function BL may be called with the long WA2 option for the same input data to retrieve the BINs of all buildings on the tax lot.
04	An invalid value has been specified for the 1A/BL Version Switch. See Chapter VI.8.
01/*	(Warning) [related to TPAD]See Chapter VI.11 and Appendix 4.Various messages are returned with this reason code. The Conflict flag is set to correspond the specific warning message.
69/B	Invalid TPAD Request Switch. Must be Y, N or blank
73	Legacy version of Function BL is discontinued. See Technical Bulletin 05-1.
90	Invalid value specified for Long WA2 Flag - must be ‘L’ or blank.

Function BN

Description: Function BN processes a building specified by an input Building Identification Number (BIN). For a discussion of BINs, see Chapter VI.3.

A successful Function BN call using two work areas returns information about the building in WA2. This includes the building's borough−tax block−tax lot (BBL); a list of geographic identifiers associated with the building (in contrast to Functions 1A and BL, which return geographic identifiers for the entire tax lot, subject to the list’s space limitation); a building status flag and date *[not implemented]*; and a condominium flag. Condominiums have unique characteristics discussed in Chapter VI.4.

Function BN is discussed in detail in Chapter VI and particularly in Chapter VI.9.

Validation: A successful outcome of a two-work-area call to Function BN signifies that the input BIN is valid.

Input Fields:

Input Fields		
Field	**Value**	**Comments**
Function Code	‘BN’	Required

Work Area Format Indicator	C' = COW format Blank = MSW format	Optional; default (blank) requests MSW format. See Appendix 12.
Mode Switch	'X' = Extended Mode Work Area 2 Blank = normal mode	Optional; COW Only. See Chapter II.7.
BIN		Required

Selected Geosupport Return Codes:

Selected Geosupport Return Codes	
GRC Value / Reason Code Value	**Meaning**
01/F	(Warning) The input BIN (contains a 9 in the 2nd digit after the borough code) is a temporary BIN assigned by GSS to a multi-building tax lot, the individual buildings of which have not yet been assigned permanent BINs. The temporary BIN will be replaced in the future
20	No input BIN value was specified.
21	The input BIN is not valid
22	The input BIN has an invalid format: either it contains non-numeric characters, or its first digit is not a valid borough code (the digits 1 through 5), or the digits beyond the first digit are all zeros.
23	The input BIN is a 'dummy' BIN (contains an 8 in the 2nd digit after the borough code) assigned by the NYC Department of Buildings. It exists only in DOB files and is not valid in Geosupport.

Functions D, DG and DN

Description: Functions D, DG and DN are the 'display' functions. They do not actually display anything themselves, but can be used to obtain data items that applications can use to format geographic locations for display on reports, screens, mailing labels etc.

The display functions do not have a WA2 and can only be called using one work area. Each of them can process any combination of up to two input House Numbers in Internal format (HNI) for MSWs or up to two input House Numbers in Sort format (HNS) for COWs and up to three input street codes. For each successfully processed input HNI/HNS, the corresponding House Number in Display format (HND) is returned in WA1. (House number processing by the display functions is discussed in detail in Chapter V.2.) For each successfully processed input street code, a corresponding street name is returned in WA1. (Street code processing by the display functions is discussed in Chapter IV.6.) For each unsuccessfully processed input street

code, the corresponding output field is returned containing all question marks. If one input HNI/HNS is supplied, it may be passed in either input HNI/HNS field. Input street codes may not ‘skip’ any input street code fields.

The display functions process each input item independently of the others, and the input data are not treated as collectively forming a geographic location. In particular, a successful call to a display function does not imply the validation of a geographic location. For example, if there is an input house number and an input street code, these are not treated or validated as forming an address, but are independently processed for conversion to display format. If the input consists of two street codes, these are not treated or validated as forming an intersection, etc.

Functions D, DG and DN differ in the type of street code each processes and in the street name each returns:

- Function D processes input borough-code-and-five-digit street codes, specified either in the form of B5SCs or PB5SCs (MSW only). Input B5SCs are passed left-justified and space-filled in the corresponding WA1 input B10SC fields. Input PB5SCs are passed in the corresponding MSW WA1 input PB5SC fields. For each successfully processed input B5SC or PB5SC (MSW only), Function D returns the corresponding ‘primary’ name for the street (a name from among all of the street’s aliases that GSS has designated as ‘best’ representing the street as a whole).

- Function DG processes input borough-code-and-seven-digit street codes (B7SCs). Input B7SCs are passed left-justified and space-filled in the corresponding WA1 input B10SC fields. For each input B7SC, Function DG returns a street name that GSS has designated as the ‘principal’ street name of the local group of names represented by the given B7SC. Function DG can be used in conjunction with a geographic location-processing function to obtain the ‘preferred street name’ customized for a particular geographic location. (For a discussion of seven-digit street codes and local groups, see Chapter IV.5.)

- Function DN processes input borough-code-and-ten-digit street codes (B10SCs). For each input B10SC, Function DN returns the unique street name spelling corresponding to it.

<u>Input Fields:</u>

Input Fields		
Field	**Value**	**Comments**
Function Code	‘D ’ (D followed by a blank) or ‘DG’ or ‘DN’	Required.
Work Area Format Indicator	‘C’ = COW format Blank = MSW	Optional; default (blank) requests MSW format. See Appendix 12

	format	
HNI-1 or HNS-1		Optional.
HNI-2 or HNS-2		Optional.
PB5SC-1 (MSW)		Function D only; optional unless PB5SC-2 is nonblank.
PB5SC-2 (MSW)		Function D only; optional unless PB5SC-3 is nonblank.
PB5SC-3 (MSW)		Function D only; optional.
B10SC-1 (or B5SC-1) (or B7SC-1)		Optional unless B10SC-2 is nonblank. (B5SC-1, B7SC-1are left-justified, space-filled in B10SC-1)
B10SC-2 (or B5SC-2) (or B7SC-2)		Optional unless B10SC-3 is nonblank. (B5SC-2, B7SC-2 are left-justified, space-filled in B10SC-2)
B10SC-3 (or B5SC-3) (or B7SC-3)		Optional. (B5SC-3, B7SC-3 are left- justified, space-filled in B10SC-3)
SNL	A number between 4 and 32	Optional; default is 32. See Chapter III.2.
Street Name Normalization Format Flag	‘C’ = compact format, Blank = sort format	Optional; default (blank) requests sort format. See Chapter III.3.

Selected Geosupport Return Codes:

Selected Geosupport Return Codes	
GRC / Reason Code Value	**Meaning**
13	At least one input HNI/HNS has a format error. There are many possible house number format errors. The specific format error is indicated by the Reason Code and Message. Output HND fields corresponding to unsuccessfully processed input HNI/HNSs are returned containing all blanks.
64	At least one input street code is invalid. Output street name fields corresponding to invalid input street code fields are returned containing all ‘?’.

APPENDIX 2: MAINFRAME-SPECIFIC WORK AREA LAYOUTS(MSW)

(as of Geosupport System Software Version 18.4 - unchanged since 15.3)

This appendix contains layouts of all of the work MSW areas used with the Geosupport System's API. These layouts are current as of the Geosupport software version indicated above.

Some Geosupport functions can only be called using one work area, Work Area 1 (WA1). Other functions can be called using two work areas, WA1 and Work Area 2 (WA2). For a discussion of one-work-area and two-work-area calls, see Chapter II.4. WA1 contains both input fields (fields used to pass data from the application to Geosupport) and output fields (fields used to pass data from Geosupport to the application). WA1 is organized so that the input fields occur first, followed by a filler, followed by the output fields. WA2 contains output fields only.

All functions use the same WA1 layout, but the set of WA1 fields that are used depends on the function. In the layout of WA1 in this appendix, the column labeled 'Functions' indicates which functions use each field.

The functions that can be called using two work areas use various WA2 layouts of various lengths. In some cases, several functions share a single WA2 layout. For some functions, the user has a choice of two WA2 layouts, a 'regular' WA2 and a 'long' WA2. For a discussion of the long WA2 option, see Chapter II.5.

The following is a list of all of the Geosupport MSW work areas, indicating the length of each in bytes. Functions that are listed together share a single Work Area 2 layout. Appendix 3 consists of a data item dictionary describing the fields that occur in the work area.

Mainframe-Specific Work Area (MSW)	Length
WA1, all functions	884
Regular WA2, Function 1	200
Long WA2, Function 1	300
Regular WA2, Functions 1A, BL, BN	939
Long WA2, Functions 1A and BL	17,683
Regular WA2, Function 1E	200
Long WA2, Function 1E	300
WA2, Function 2	200
Regular WA2, Function 3	200
Long WA2, Function 3	300
WA2, Function 3C	200
WA2, Function 3S	4,224

Work Area 1 (MSW) - All Functions

Field	Size	Position	Functions
INPUT FIELDS:			
Geosupport Function Code	2	1-2	All
Borough Code-1[13]	1	3	All but BL, BN, D*
House Number	12	4-15	1, 1A, 1E
House Nr. in Internal Format (HNI)	6	16-21	1, 1A, 1E, D
Street Name-1	32	22-53	All but BL, BN, D*
Street Name-2	32	54−85	2, 3*
Street Name-3	32	86-117	3*
Compass Direction	1	118	2, 3C, 3S
Compass Direction for 2nd Intersection	1	119	3S
PB5SC-1	4	120−123	1, 1A, 1E, 2, 3*, D
PB5SC-2	4	124-127	2, 3*, D
PB5SC-3	4	128-131	3*, D
Roadbed Request Switch	1	132	1, 1E, 3S
Borough Code-2	1	133	2, 3, 3C
Borough Code-3	1	134	3, 3C
Street Name Normalization	2	135−136	All but B*
Length Limit (SNL)			
B10SC-1 (includes B5SC-1 and B7SC-1)	11	137-147	1, 1A, 1E, 2, 3*, D*
B10SC-2 (includes B5SC-2 and B7SC-2)	11	148-158	2, 3*, D*
B10SC-3 (includes B5SC-3 and B7SC-3)	11	159−169	3*, D*
ZIP Code	5	170−174	1, 1A, 1E
Borough−Block−and−Lot (BBL):	10	175−184	
Borough	1	175	BL
Tax Block	5	176-180	BL
Tax Lot	4	181-184	BL
Filler	1	185	
Building Identification Number (BIN)	7	186−192	BN
Street Name Normalization Format Flag	1	193	All but B*
Long Work Area 2 Flag	1	194	1, 1A, 1E, 3, BL
Filler - Reserved for Geosupport Use	12	195-206	
HNI-2	6	207-212	D*
Work Area Format Indicator	1	213	All
1ABL Version Switch	1	214	1A, BL

Cross Street Names Flag	1	215	1, 1E, 2, 3, 3C
Filler	4	216-219	

Work Area 1 (MSW) - All Functions			
Field	Size	Position	Functions
OUTPUT FIELDS:			
HND-2	12	220-231	D*
Borough Name	9	232−240	All but D*
Street Name-1Normalized	32	241−272	All but B*
Street Name-2Normalized	32	273−304	2, 3*, D*
Street Name-3Normalized	32	305−336	3*, D*
HND	12	337−348	1, 1A, 1E, D*
HNI	6	349−354	1, 1A, 1E
Filler	7	355−361	
PB5SC-1	4	362−365	1*, 2, 3*, D*
Filler	2	366−367	
PB5SC-2	4	368−371	2, 3*, D*
Filler	2	372−373	
PB5SC-3	4	374−377	3*, D*
Attribute Bytes	3	378−380	
Up to ten PB5SCs	40	381−420	BB, BF
B10SC-1	11	421−431	1*, 2, 3*, D*
B10SC-2	11	432−442	2, 3*, D*
B10SC-3	11	443−453	3*, D*
Filler	5	454−458	
BBL Normalized	10	459−468	BL
Reserved	8	469-476	
Street Attribute Indicator	1	477	1*
Reason Code	1	478	All
Filler - Reserved for Geosupport Use	2	479−480	
Geosupport Return Code	2	481−482	All
Geosupport Message	80	483−562	All
Number of Street Names in List (packed)	2	563−564	1*, 2, 3*, BB, BF
List of Street Names: (10 Street Name Fields, 32 Bytes Each)	320	565−884	1*, 2, 3*, BB, BF

<u>*NOTE:</u>
An asterisk in the second position of a function code is used as a shorthand notation to represent all function codes having the indicated value in the first position, as follows:

1* = 1 , 1A, 1E, 1N
3* = 3, 3C, 3S
B* = BB, BF, BL, BN
D* = D, DG, DN

Regular Work Area 2 (MSW) Layout for Function 1

Field	Size	Position
Filler	22	1-22
Low House Number of Blockface	6	23-28
High House Number of Blockface	6	29-34
Alley/Cross Streets Flag	1	35
Number of Cross Streets at Low Address End	1	36
List of Cross Streets at Low Address End (up to 5 PB5SCs)	20	37-56
Number of Cross Streets at High Address End	1	57
List of Cross Streets at High Address End (up to 5 PB5SCs)	20	58-77
Community District:	3	78-80
Community District Borough Code	1	78
Community District Number	2	79-80
ZIP Code	5	81-85
DOT Street Light Contractor Area	1	86
Health Center District	2	87-88
Side of Street Indicator	1	89
Continuous Parity Indicator	1	90
2010 Census Tract	6	91-96
2010 Census Block	4	97-100
2010 Census Block Suffix (Not Implemented)	1	101-101
Filler	1	102-102
Filler	2	103-104
Health Area	4	105-108
Sanitation Recycling Collection Schedule	3	109-111
Feature Type Code	1	112
Interim Assistance Eligibility Indicator (IAEI)	1	113
Curve Flag	1	114
Police Patrol Borough Command	1	115

Police Precinct	3	116-118
School District	2	119-120
Filler to Preserve Layout Consistency with WA2 for Function 1E	14	121-134
Coincident Segment Count	1	135
Segment Type Code	1	136
Sanitation District	3	137-139
Sanitation Collection Scheduling Section and Subsection	2	140-141
Fire Division	2	142-143
Fire Battalion	2	144-145
Fire Company Type	1	146
Fire Company Number	3	147-149
Special Address Generated Record Flag	1	150
Reserved for Internal Geosupport Use	1	151
Filler (was Split Community School District Flag)	1	152
DCP-Preferred LGC	2	153-154
Face Code	4	155-158
Sequence Number	5	159-163
1990 Census Tract	6	164-169
Filler	4	170-173
Dynamic Block / Atomic Polygon	3	174-176
X Coordinate	7	177-183
Y Coordinate	7	184-190
Segment Length in Feet	5	191-195
Sanitation Regular Collection Schedule	5	196-200

Long Work Area 2 (MSW) Layout for Function 1

Field	Size	Position
Same as corresponding position in Function 1's regular WA2	200	1-200
Segment-ID	7	201-207
Underlying B7SC of True Street	8	208-215
Underlying HNI on True Street	6	216-221
2000 Census Tract	6	222-227
2000 Census Block	4	228-231
2000 Census Block Suffix (Not Implemented)	1	232-232
Filler	68	233-300

Regular Work Area 2 (MSW) Layout for Functions 1A, BL, BN

Field	Size	Position
Filler	28	1-28
Borough-Tax Block-Tax Lot (BBL):	10	29-38
Borough Code	1	29
Tax Block	5	30-34
Tax Lot	4	35-38
Tax Lot Version Number [not implemented]	1	39
RPAD Self-Check Code (SCC) for BBL	1	40
Filler	1	41
RPAD Building Classification Code	2	42-43
Corner Code	2	44-45
Filler (reserved)	2	46-47
Number of Street Frontages of Lot	2	48-49
Interior Lot Flag	1	50
Vacant Lot Flag	1	51
Irregularly-Shaped Lot Flag	1	52
Alternative Borough Flag	1	53
Filler	1	54
Strolling Key	13	55-67
List of Geographic Identifiers Overflow Flag	1	68
Reserved for Internal Geosupport Use	1	69
Building Identification Number (BIN) of Input Address or NAP	7	70-76
Condominium Flag	1	77
Condominium Identification Number	4	78-81
Low BBL of this Building's Condominium Units	10	82-91
Filler	1	92
Condominium Billing BBL	10	93-102
Filler	1	103
Condominium Billing BBL SCC	1	104
High BBL of this Building's Condominium Units	10	105-114
Filler	1	115
SBVP (Sanborn Map Identifiers):	8	116-123
Sanborn Borough Code	1	116-123
Sanborn Volume and Volume Suffix	3	117-119

Sanborn Page and Page Suffix	4	120-123
Filler (was DCP Commercial Area)	5	124-128
Cooperative Identification Number	4	129-132
Filler	4	133-136
Number of Existing Buildings on Lot	4	137-140
Tax Map Identifiers:	9	141-149
Borough Code:	1	141
Tax Map Section	2	142-143
Tax Map Volume	2	144-145
Tax Map Page [not yet implemented]	4	146-149
X Coordinate of Internal Label Point	7	150-156
Y Coordinate of Internal Label Point	7	157-163
Business Improvement District (BID)	6	164-169
Filler	12	170-181
Number of Entries in List of Geographic Identifiers	2	182-183
List of Geographic Identifiers, up to 21 entries - each entry consisting of 36 bytes as follows:	756	184-939
Low House Number	6	
Filler	3	
High House Number	6	
Filler	3	
B5SC:	1	
Borough Code		
5-Digit Street Code	5	
DCP-Preferred LGC	2	
BIN	7	
Geographic Identifier Type Code	1	
Filler	1	
Side of Street Indicator	1	

Long Work Area 2 (MSW) Layout for Functions 1A and BL

Field	Size	Position
Filler	28	1-28
Borough-Tax Block-Tax Lot (BBL):	10	29-38
Borough Code	1	29
Tax Block	5	30-34

Tax Lot	4	35-38
Filler	3	
Tax Lot Version Number [not implemented]	1	39
RPAD Self-Check Code (SCC) for BBL	1	40
Filler	1	41
RPAD Building Classification Code	2	42-43
Corner Code	2	44-45
Filler (reserved)	2	46-47
Number of Street Frontages of Lot	2	48-49
Interior Lot Flag	1	50
Vacant Lot Flag	1	51
Irregularly-Shaped Lot Flag	1	52
Alternative Borough Flag	1	53
Filler	15	54-68
Reserved for Internal Geosupport Use	1	69
Building Identification Number (BIN) of Input Address or NAP	7	70-76
Condominium Flag	1	77
Condominium Identification Number	4	78-81
Low BBL of this Building's Condominium Units	10	82-91
Filler	1	92
Condominium Billing BBL	10	93-102
Filler	1	103-102
Condominium Billing BBL SCC	1	104
High BBL of this Building's Condominium Units	10	105-114
Filler	1	115
SBVP (Sanborn Map Identifiers):	8	116-123
Sanborn Borough Code	1	116
Sanborn Volume and Volume Suffix	3	117-119
Sanborn Page and Page Suffix	4	120-123
Filler (was DCP Commercial Area)	5	124-128
Cooperative Identification Number	4	129-132
Cooperative Identification Number	4	129-132
Filler	4	133-136
Number of Existing Buildings on Lot	4	137-140
Tax Map Identifiers:	9	141-149
Borough Code	1	141
Tax Map Section	2	142-143
Tax Map Volume	2	144-145

Tax Map Page [not yet implemented]	4	146-149
X Coordinate of Internal Label Point	7	150-156
Y Coordinate of Internal Label Point	7	157-163
Filler	16	164-179
Number of Buildings on Tax Lot (Maximum = 2,500)	4	180-183
List of Buildings on Tax Lot (each represented by a 7-Byte BIN)	17,500	184-17,683

Regular Work Area 2 (MSW) Layout for Function 1E

Field	Size	Positions
Filler	22	1-22
Low House Number of Blockface	6	23-28
High House Number of Blockface	6	29-34
Alley/Cross Streets Flag	1	35
Number of Cross Streets at Low Address End	1	36
List of Cross Streets at Low Address End (up to 5 PB5SCs)	20	37-56
Number of Cross Streets at High Address End	1	57
List of Cross Streets at High Address End (up to 5 PB5SCs)	20	58-77
Community District	3	78-80
Community District Borough Code	1	78
Community District Number	2	79-80
Community District Number	2	79-80
ZIP Code	5	81-85
DOT Street Light Contractor Area	1	86
Health Center District	2	87-88
Side of Street Indicator	1	89
Continuous Parity Indicator	1	90
2010 Census Tract	6	91-96
2010 Census Block	4	97-100
2010 Census Block Suffix	1	101-101
Filler	1	102-102
Filler	1	103-104
Health Area	4	105-108
Sanitation Recycling Collection Schedule	3	109-111
Feature Type Code	1	112
Interim Assistance Eligibility Indicator (IAEI)	1	113
Curve Flag	1	114
Police Patrol Borough Command	1	115

Police Precinct	3	116-118
School District	2	119-120
Election District	3	121-123
Assembly District	2	124-125
Split Election District Flag	1	126
Congressional District	2	127-128
State Senatorial District	2	129-130
Civil Court District	2	131-132
City Council District	2	133-134
Coincident Segment Count	1	135
Segment Type Code	1	136
Sanitation District	3	137-139
Sanitation Collection Scheduling Section and Subsection	2	140-141
Fire Division	2	142-143
Fire Battalion	2	144-145
Fire Company Type	1	146
Fire Company Number	3	147-149
Special Address Generated Record Flag	1	150
Reserved for Internal Geosupport Use	1	151
Filler (was Split Community School District Flag)	1	152
Board of Elections-Preferred LGC	2	153-154
Face Code (was known as LION Face Code)	4	155-158
Sequence Number (was known as LION Sequence Number)	5	159-163
1990 Census Tract	6	164-169
Filler	4	170-173
Atomic Polygon (Previously known as Dynamic Block)	3	174-176
X Coordinate	7	177-183
Y Coordinate	7	184-190
Segment Length in Feet	5	191-195
Sanitation Regular Collection Schedule	5	196-200

Long Work Area 2 (MSW) Layout for Function 1E

Field	Size	Positions
Same as corresponding positions in Function 1E's regular WA2	200	1-200
Segment-ID (was known as LION Segment-ID)	7	201-207
Underlying B7SC of True Street	8	208-215
Underlying HNI on True Street	6	216-221

2000 Census Tract	6	222-227
2000 Census Block	4	228-231
2000 Census Block Filler / Suffix	1	232-232
Filler	68	233-300

Work Area 2 (MSW) Layout for Function 2

Field	Size	Positions
Filler	31	1−31
DCP-Preferred LGC for Street 1	2	32-33
DCP-Preferred LGC for Street 2	2	34-35
Number of Intersecting Streets	1	36
List of Intersecting Streets (up to five PB5SCs, 4 bytes each)	20	37−56
Compass Direction for Intersection Key	1	57
Filler	10	58−67
Filler	2	68−69
Fire Division	2	70-71
Fire Battalion	2	72-73
Fire Company Type	1	74
Fire Company Number	3	75-77
Community District	3	78−80
Community District Borough Code	1	78
Community District Number	2	79-80
ZIP Code	5	81-85
DOT Street Light Contractor Area	1	86
2010 Census Tract	6	87−92
Filler	3	93−95
Health Area	4	96−99
Health Area	4	96−99
Filler	9	100-108
Node Number (was known as LION Node Number)	7	109−115
X Coordinate	7	116-122
Y Coordinate	7	123−129
Filler	4	130−133
Police Patrol Borough Command	1	134
Police Precinct	3	135−137
School District (was known as Community School District)	2	138−139
Reserved for Internal Geosupport Use	1	140

1990 Census Tract	6	141−146
SBVP1 (Sanborn Map Identifiers):	8	147-154
Sanborn Borough Code	1	147
Sanborn Volume and Volume Suffix	3	148-150
Sanborn Page and Page Suffix	4	151-154
SBVP2 (Sanborn Map Identifiers for Second Map, if any)	8	155-162
Sanborn Borough Code	1	155
Sanborn Volume and Volume Suffix	3	156-158
Sanborn Page and Page Suffix	4	159-162
Sanborn Page and Page Suffix	4	159-162
Distance Between Duplicate Intersections	5	163−167
2000 Census Tract	6	168-173
Filler	27	174-200

Work Area 2 (MSW) Layout for Function 3

Field	Size	Positions
Filler	22	1−22
Curve Flag	1	23
Locational Status	1	24
County Boundary Indicator	1	25
Coincident Segment Count	1	26
Filler	3	27-29
DCP-Preferred LGC for Street 1	2	30-31
DCP-Preferred LGC for Street 2	2	32-33
DCP-Preferred LGC for Street 3	2	34-35
DCP-Preferred LGC for Street 3	2	34-35
Number of Cross Streets at Low Address End	1	36
List of Cross Streets at Low Address End (up to five PB5SCs)	20	37−56
Number of Cross Streets at High Address End	1	57
List of Cross Streets at High Address End (up to five PB5SCs)	20	58−77
DOT Street Light Contractor Area	1	78
Cross Street Reversal Flag	1	79
Left Community District	3	80−82
Left Community District Borough Code	1	80
Left Community District Number	2	81-82
Right Community District	3	83−85
Right Community District Borough Code	1	83

Right Community District Number	2	84-85
Left ZIP Code	5	86−90
Right ZIP Code	5	91−95
Filler	18	96−113
Left Health Area	4	114−117
Right Health Area	4	118−121
Filler	2	122-123
Filler	2	124-125
Left Low House Number	7	126−132
Left High House Number	7	133−139
Right Low House Number	7	140−146
Right High House Number	7	147−153
Continuous Parity Indicator	1	154
Face Code (was known as LION Face Code)	4	155-158
Sequence Number (was known as LION Sequence Number)	5	159−163
Generated Record Flag	1	164
Segment Length in Feet (Packed)	3	165-167
Segment Azimuth	3	168−170
Segment Orientation	1	171
Filler	2	172−173
Filler	2	174-175
Left Interim Assistance Eligibility Indicator	1	176
Right Interim Assistance Eligibility Indicator	1	177
Dogleg Flag	1	178
Feature Type Code	1	179
Left Police Patrol Borough Command	1	180
Left Police Precinct	3	181−183
Right Police Patrol Borough Command	1	184
Right Police Precinct	3	185−187
Left School District (was known as Left Community School…)	2	188−189
Right School District (was known as Right Community School…)	2	190−191
Reserved for Internal Geosupport Use	1	192
Segment-ID (was known an LION Segment-ID)	7	193-199
Segment Type code	1	200

Long Work Area 2 (MSW) Layout for Function 3

Field	Size	Positions

Same as corresponding positions in Function 3's regular WA2	200	1-200
Left 1990 Census Tract	6	201−206
Filler	4	207−210
Left Atomic Polygon (Previously known as Dynamic Block)	3	211−213
Right 1990 Census Tract	6	214−219
Filler	4	220−223
Right Atomic Polygon (Previously known as Dynamic Block)	3	224−226
Left Fire Division	2	227-228
Left Fire Battalion	2	229-230
Left Fire Company Type	1	231
Left Fire Company Number	3	232-234
Right Fire Division	2	235-236
Right Fire Battalion	2	237-238
Right Fire Company Type	1	239-239
Right Fire Company Number	3	240-242
Left 2010 Census Tract	6	243-248
Left 2010 Census Block	4	249-252
Left 2010 Census Block Suffix / Filler	1	253
Right 2010 Census Tract	6	254-259
Right 2010 Census Block	4	260-263
Right 2010 Census Block Suffix / Filler	1	264
From Node	7	265-271
To Node	7	272-278
Left 2000 Census Tract	6	279-284
Left 2000 Census Block Suffix	1	289
Right 2000 Census Tract	6	290-295
Right 2000 Census Block	4	296-299
Right 2000 Census Block Suffix	1	300

Work Area 2 (MSW) Layout for Function 3C

Field	Size	Positions
Filler	21	1-21
Curve Flag	1	22
Segment Type Code	1	23
Locational Status	1	24
County Boundary Indicator	1	25
Coincident Segment Count	1	26

Filler	3	27-29
DCP-Preferred LGC for Street 1	2	30-31
DCP-Preferred LGC for Street 2	2	32-33
DCP-Preferred LGC for Street 3	2	34-35
Number of Cross Streets at Low Address End	1	36
Number of Cross Streets at Low Address End	1	36
List of Cross Streets at Low Address End (up to 5 PB5SCs)	20	37−56
Number of Cross Streets at High Address End	1	57
List of Cross Streets at High Address End (up to 5 PB5SCs)	20	58−77
Community District	20	78−80
Community District Borough Code	1	78
Community District Number	2	79-80
ZIP Code	5	81-85
DOT Street Light Contractor Area	1	86
2000 Census Tract	6	87−92
Filler	1	93
2010 Census Tract	6	94−99
2010 Census Block	4	100−103
2010 Census Block Suffix (Future Use)	1	104
Health Area	4	105−108
Cross Street Reversal Flag	1	109
Side of Street Indicator	1	110
Fire Division	2	111-112
Fire Battalion	2	113-114
Fire Company Type	1	115
Fire Company Number	3	116-118
Segment-ID (was known as LION Segment-ID)	7	119−125
Low House Number of Blockface	7	126−132
High House Number of Blockface	7	133−139
Alternate Low House Number	7	140−146
Alternate High House Number	7	147−153
Continuous Parity Indicator	1	154
Face Code (was known as LION Face Code)	4	155-158
Sequence Number (was known as LION Sequence Number)	5	159−163
Generated Record Flag	1	164
Generated Record Flag	1	164
Segment Length in Feet (Packed)	3	165−167
Segment Azimuth	3	168−170

Segment Orientation	1	171
Filler	2	172−173
Interim Assistance Eligibility Indicator (IAEI)	1	174
Feature Type Code	1	175
Police Patrol Borough Command	1	176
Police Precinct	3	177−179
School District (was known as Community School District)	2	180−181
Reserved for Internal Geosupport Use	1	182
1990 Census Tract	6	183−188
Filler	4	189−192
Atomic Polygon (Previously known as Dynamic Block)	3	193−195
2000 Census Block	4	196−199
2000 Census Block Suffix Filler	1	200

Work Area 2 (MSW) Layout for Function 3S

Field	Size	Positions
Filler	21	1-21
Number of Cross Streets in Stretch (Maximum = 350)	3	22−24
List of Cross Streets in Stretch, each list entry 12 bytes as follows:	4200	25−4224
Smallest PB5SC at Intersection	4	
Second smallest PB5SC at Intersection	4	
Distance from Predecessor in Feet	3	
Gap Flag	1	

[13] Borough Code values are: '1'=Manhattan, '2'=Bronx, '3'=Brooklyn, '4'=Queens, "5"=Staten Island

APPENDIX 3: DATA ITEM DICTIONARY

This Data Item Dictionary is an alphabetical list of the data items for which there are fields in the Geosupport API work areas, together with descriptive information. In general, data items are listed in this appendix under the names used in the work area layouts in Appendix 2 (MSW) and Appendix 13 (COW). However, if an item is associated with multiple work area fields having varying field names, and is identical in format and range of values in all those fields, the item is documented in a generically-named entry, and there is also a separate entry for each of those fields consisting only of a reference to the generic entry. For example, there is a generic entry for CENSUS TRACT containing full descriptive information, and there are also entries for 2000 CENSUS TRACT, LEFT 2000 CENSUS TRACT, RIGHT 2000 CENSUS TRACT, 2010 CENSUS TRACT etc., containing only a reference to the entry for CENSUS TRACT.

Each entry consists of an appropriate combination of the following elements:

- Name of Data Item. This might be identical to the name of a specific work area field or it might be a generic name for a data item that is represented by multiple work area fields.

- Field Names. A list of the field names associated with a generic entry.

- Function(s). A list of the Geosupport functions that utilize this data item as either an input or an output item in either WA1 or WA2. If the data item is in the added portion of WA2 that is passed when the function is called with the long WA2 option, this is so stated. Similarly, if the data is passed when the function is called with an Extended or Auxiliary or other option, it is so stated. In the list of functions, an asterisk in the second position of a function code is a 'wild card' signifying all functions having the indicated value in the first position, as follows:

  1 * = 1, 1A, 1B, 1E, 1N; also 1Extended, 1A Extended, 1E Extended

  2 * = 2, 2W

  3 * = 3, 3C, 3S, 3 & 3C with Auxiliary Segments, 3 & 3C Extended (with or without Auxiliary Segments)

  B * = BB, BF, BL, BN

  D * = D, DG, DN

* Work Area Format: A list of the work area format(s) that apply to this entry, namely, MSW (Mainframe-Specific Work Area) and/or COW (Character-Only Work Area).

- Length and Format. The length of this data item in bytes, and a description of its format, including whether it is numeric, alphabetic or alphanumeric (these terms are defined below); whether it contains any special editing characters; and for numeric

items, the justification and the fill character. The following terms and abbreviations are used:

RJ = Right-Justified
LJ = Left-Justified
ZF = Zero-Filled
BF = Blank-Filled

Numeric: Contains only the digits 0 through 9, and possibly blanks serving as fill characters only.
Alphabetic: Contains letters of the alphabet only. LJBF unless otherwise stated.
Alphanumeric: Can contain any allowable characters, including special characters such as hyphens. LJBF unless otherwise stated.

- Description. A brief narrative description of the data item. The description may include citations to sections of the UPG where the data item is principally discussed. Data items that are self−explanatory have no description and/or citations.

- Valid Values and Code Meanings. The values or ranges of values valid for this data item and, if the item consists of codes, the meaning of each code value.

Numeric

1A/BL VERSION FLAG - See FUNCTION 1A/BL VERSION FLAG.
1990 CENSUS TRACT - See CENSUS TRACT.
2000 CENSUS BLOCK - See CENSUS BLOCK.
2000 CENSUS BLOCK SUFFIX - See CENSUS BLOCK SUFFIX.
2000 CENSUS TRACT - See CENSUS TRACT.
2010 CENSUS BLOCK - See CENSUS BLOCK.
2010 CENSUS BLOCK SUFFIX - See CENSUS BLOCK SUFFIX.
2010 CENSUS TRACT - See CENSUS TRACT.

A

ALLEY/CROSS STREETS FLAG (ALX)

Functions:	1, 1E
Work Area Format:	MSW and COW
Length and Format:	1 byte
Description:	Indicates if the segment has been split by alleys, or if the cross streets named in the segment have been copied from a previous or subsequent segment because the segment itself has no cross streets.

Code Value	Meaning
'A'	Split by Alley(s)
'X'	Cross Streets Modified
Blank	Neither Split by Alleys or Cross Streets Modified

ALTERNATE LOW AND HIGH HOUSE NUMBERS

Functions: 3C

Work Area Format: MSW and COW

Length and Format: See HOUSE NUMBER

Description: These two fields are non-blank only if this blockface has addresses of both parities (the parity of a number is its attribute of being odd or even). Such a blockface is said to have 'continuous parity'. If the blockface has continuous parity, the Continuous Parity Indicator is non-blank, the Low and High House Number fields contain the address range for one parity, and the Alternate Low and High House Number fields contain the address range for the other parity. (Which parity is in which set of house number fields is unpredictable.)

ALTERNATIVE BOROUGH FLAG

Functions: 1, 1A, 1B, 1E, 2, 3, 3C, 3S (COW only), BL, BN

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: This flag indicates either that the input address is in Marble Hill or Rikers Island and the alternative (rather than the legal) borough was specified (see Chapter V.7), or that the input address is on Ruby Street in Brooklyn but it was specified using the alternative (Queens) street name 75 Street (see Chapter V.8).

This field was also known as the Marble Hill / Rikers Island Flag.

Code Value	Meaning
'C'	Ruby Street address specified using 75 Street
'M'	Marble Hill address with Bronx specified
'R'	Rikers Island address with Queens specified

ALX FLAG - See ALLEY/CROSS STREETS FLAG

ANNOTATION POINT - No longer used by Geosupport. See SPATIAL COORDINATES OF THE TAX LOT CENTROID

ASSEMBLY DISTRICT

Field Names: LEFT ASSEMBLY DISTRICT
RIGHT ASSEMBLY DISTRICT

Functions: 1E, 2 (COW only), 3 (COW only), 3C (COW only)

Work Area

Format: MSW and COW

Length and Format: 2 bytes. RJZF

Description: A district of the lower house of the New York State legislature. Consists of an aggregation of Election Districts

ATOMIC POLYGON - Previously known as DYNAMIC BLOCK

Functions: 1, 1B, 1E, 3(MSW: Long WA2), 3(COW), 3C

Work Area Format: MSW and COW

Length and Format: 3 bytes RJZF

Description: An atomic polygon is an un-subdivided polygon . Atomic polygons are created based on the New York City CSCL (Citywide Street Centerline) database. Atomic polygons are numbered uniquely within census tract.

ATTRIBUTE BYTE - See STREET ATTRIBUTE INDICATOR

AUXILIARY SEGMENT SWITCH (auxseg or segaux)

Functions: 3, 3C, 3 & 3C Extended

Work Area Format: COW

Length and Format: 1 byte character.

Description: When this flag is set to 'Y', the list of all the Segment IDs that comprise the segment will be added to the end of Work Area 2 for Functions 3 or 3C.

Code Value	Meaning
'N' or Blank	One Segment ID is returned in Work Area 2.
'Y'	A list of all the segment IDs is added to the end of Word Area 2 for Function 3 or 3C.

B

B7SC OF "TRUE" STREET (a.k.a. B7SC OF "UNDERLYING" STREET)

Functions: 1and 1E (MSW: Long WA2 only); 1, 1B and 1E (COW)

Work Area Format: MSW and COW

Length and Format: 8 bytes (B7SC)

Description: This item typically applies to Addressable Place Names, Non-addressable Place Names and Vanity Addresses. It item contains the B7SC of the street segment

upon which the address specified is actually located. This is the street segment that is identified by the field SEGMENT-ID and by the fields FACE CODE and SEQUENCE NUMBER. In most cases, the B5SC portion of this item is identical to the B5SC specified in the key. However, the two B5SCs differ when the SPECIAL ADDRESS GENERATED RECORD FLAG is either 'B', 'N', 'P', or 'V'.

BBL

Functions: 1A, BL, BN, AP

Work Area Format: MSW and COW

Length and Format: 10 bytes in standard version, Numeric. (Note: the legacy version of Functions 1A and BL is no longer supported.)

Standard:

Field	Length	Position	Comments
Borough	1	1-1	
Tax Block	5	2-6	RJZF
Tax Lot	4	7-10	RJZF

Description: The first 6 bytes of the standard BBL consists of the 1-byte borough code followed by the 5-byte tax block field, which contains the tax block value right-justified and zero-filled. The last 4 bytes of the standard BBL is the standard tax lot field, which contains the tax lot value right-justified and zero-filled. See Chapter VI.8. The BBL ('borough-block-and-lot') identifies a parcel of real property in New York City, called a tax lot. The BBL is composed of the concatenation of the Borough Code, Tax Block and Tax Lot. If the property is a condominium (indicated by the Condominium Flag), the WA2 BBL field contains the billing BBL of the condominium (see Chapter VI.4).

BID - See BUSINESS IMPROVEMENT DISTRICT

BIKE LANE BIKE LANE is being replaced by BIKE LANE 2. See also BIKE LANE 2

Functions: 1 Extended, 1B, 1E Extended, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: 1 byte

Notice: As of Release 16D, Bike Lane has 11 codes, instead of 7. A new two-byte field, BIKE LANE 2, is being introduced. The original one-byte Bike Lane field still exists to give users a chance to update their applications. In the one-byte Bike Lane field, the value 'A' will appear when the new code is '10', and the value 'B' will appear when the new code is '11'. We recommend that users update their applications to refer to the new Bike Lane-2 since the one-byte Bike Lane field will be deleted in a later release.

Description: Defines which street segments are part of the bicycle network as defined by the Department of Transportation.

Code Value	Meaning
1 Class I:	Separated Greenway
2 Class II:	Striped Bike Lane
3 Class III:	Signed Bicycle Route
4 Links:	Connecting Segments
5 Class I, II:	Combination of Class I and II
6 Class II, III:	Combination of Class II and III
7 Stairs:	Step streets, bridge stairs, etc.
8 Class I, III	Combination of Class I and III
9 Class II, I	Combination of Class II and I
A Class III, I	Combination of Class III and I
B Class III, II	Combination of Class III and II

BIKE LANE 2

Functions: 1 Extended, 1B, 1E Extended, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: 2 bytes, RJBF

Description: Defines which street segments are part of the bicycle network as defined by the Department of Transportation.

Note: As of Geosupport Version 16.4, Bike Lane 2 is being introduced to replace Bike Lane

The following table contains the values that can appear in the Bike Lane 2 field

Code Value	Meaning	Description
1	Class I:	Separated Greenway
2	Class II:	Striped Bike Lane
3	Class III:	Signed Bicycle Route
4	Links:	Connecting Segments
5	Class I, II:	Combination of Class I and II
6	Class II, III:	Combination of Class II and III
7	Stairs:	Step streets, bridge stairs, etc.
8	Class I, III	Combination of Class I and III
9	Class II, I	Combination of Class II and I
10	Class III, I	Combination of Class III and I
11	Class III, II	Combination of Class III and II

BIKE TRAFFIC DIRECTION

Functions: 1 Extended, 1B, 1E Extended, 3 Extended, 3C Extended

Work Area

COW

Format:

Length and Format: 2 bytes, RJBF

Description: Defines the traffic direction of the bike lanes on a segment.

The following table contains the values that can appear in the Bike Lane 2 field

Code Value	Meaning	Description
Blank	No bike lane	No bike lane exists at this segment
FT	FROM node to TO node	Bike traffic flows with the segment's logical direction, i.e. from the FROM node to the TO node.
TF	TO node to FROM node	Bike traffic flows against the segment's logical direction, i.e. from the TO node to the FROM node.
TW	Two-Way	Bikes travel in both directions

BIN - See BUILDING IDENTIFICATION NUMBER

BLOCKFACE ID

Field Names: LEFT BLOCKFACE ID
RIGHT BLOCKFACE ID

Functions: 1 Extended, 1B, 1E Extended, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: 10 bytes. RJZF

Description: Left Blockface ID is a ten digit number identifying the block face on the left hand side of a segment. Correspondingly, Right Blockface ID identifies the block face on the right hand side of a segment. Block Face is defined as one continuous side of a physical block that is intersected on that side by two other physical through streets. Blockface IDs were established by DoITT's consultants working on the planimetric feature classes for NYC and are not maintained by the Department of City Planning.

BOARD OF ELECTIONS PREFERRED LGC

Functions: 1E

Work Area Format: MSW and COW

Length and Format: 2 bytes. RJZF

Description: This item is the LGC (the sixth and seventh digits of the 10-digit street code) that corresponds to the NYC Board of Elections' preferred street name for a given location.

BOROUGH CODE

Functions: All functions

Work Area Format: MSW and COW
Length and Format: 1 byte. Numeric.
Description:

Code Value	Meaning
1	Manhattan
2	Bronx
3	Brooklyn
4	Queens
5	Staten Island

BOROUGH/BLOCK/LOT - See BBL

BOROUGH/TAX BLOCK/TAX LOT - See BBL

BROWSE FLAG

Functions: 1, 1A, 1B, 1E, 1N, 2, 3, 3C, BB, BF
Work Area Format: COW
Length and Format: 1 byte. Alphabetic
Description:

Code Value	Meaning	
Blank	All streets or normalized input street	
P	Primary streets	
F	Principal streets	
R	Preferred street	Only Functions 1, 1A, 1B. 1E, 2, 3, and 3C. (Not 1N, BB, BF)

See Chapter III.7 for use of Browse Flag with Functions BB and BF.
See Chapter III.8 for use of Browse Flag with Functions 1, 1A, 1B, 1E, 1N, 2, 3, 3C.

BUILDING IDENTIFICATION NUMBER (BIN)

Functions: 1A, BL, BN, 1B (COW only) and AP (COW only)
Work Area Format: MSW and COW
Length and Format: 7 bytes. Numeric
Description: Building Identification Number. A permanent BIN is a seven-digit numerical identifier unique to each building in the City of New York. The first digit is the Borough Code. There are also two types of temporary BINs; those maintained by the Dept. of Buildings (DOB) and those maintained by the Dept. of City Planning

(DCP). The temporary BINs assigned by DOB contain the number ‘8’ as the second digit, and the temporary BINs assigned by DCP contain a ‘9’ in the same position. DCP is currently in the process of phasing out all of its temporary BINs.

BUSINESS IMPROVEMENT DISTRICT (BID)

Functions: 1A, 1B, BL, BN

Work Area Format: MSW and COW

Length and Format: 6 bytes, B5SC

Description: The Business Improvement District (BID) field (which was requested by the Fire Department) consists of a borough and five-digit street code (B5SC). Function D may be used to obtain the 32-byte name of the BID. The ‘Street Attribute Indicator’ is set to ‘C’ for BIDs. An example of a Business Improvement District is ‘5 AVE BID’ Note that a BID may not be used as input to Function 1, 1A, 1B, 1E, 2*, and 3*.

CD - See COMMUNITY DISTRICT or COMMUNITY DEVELOPMENT…

CD ELIGIBILITY FLAG - See INTERIM ASSISTANCE ELIGIBILITY INDICATOR

C

CENSUS BLOCK

Field Names: 2000 CENSUS BLOCK,
LEFT 2000 CENSUS BLOCK,
RIGHT 2000 CENSUS BLOCK,
2010 CENSUS BLOCK
LEFT 2010 CENSUS BLOCK,
RIGHT 2010 CENSUS BLOCK

Functions: 1 & 1E (MSW: for 2010 - Regular WA2, for 2000 - Long WA2 Only;), 1 & 1E(COW). 2, 3 (MSW: Long WA2 Only), 3(COW), 3C

Work Area Format: MSW and COW

Length and Format: 4 bytes, numeric

Description: When appended by the CENSUS BLOCK SUFFIX, this area is the smallest geographic area defined by the U.S. Census Bureau for tabulating the census. Generally (but not always) corresponds to a physical city block. Each census block is numbered uniquely within its census tract.

CENSUS BLOCK SUFFIX

2000 CENSUS BLOCK SUFFIX,
LEFT 2000 CENSUS BLOCK SUFFIX,

Field Names:	RIGHT 2000 CENSUS BLOCK SUFFIX, 2010 CENSUS BLOCK SUFFIX, LEFT 2010 CENSUS BLOCK SUFFIX, RIGHT 2010 CENSUS BLOCK SUFFIX,
Functions:	1&1E (MSW: for 2010 - Regular WA2, for 2000 - Long WA2 Only;), 1, 1B &1E(COW) 2, 3 (MSW: Long WA2 Only), 3(COW), 3C
Work Area Format:	MSW and COW
Length and Format:	1 byte.
Description:	This suffix is defined by the U.S. Census Bureau. At the government's discretion, this field may, or may not, contain data.

CENSUS TRACT

Field Names:	1990 CENSUS TRACT, LEFT 1990 CENSUS TRACT, RIGHT 1990 CENSUS TRACT, 2000 CENSUS TRACT, LEFT 2000 CENSUS TRACT, RIGHT 2000 CENSUS TRACT 2010 CENSUS TRACT, LEFT 2010 CENSUS TRACT, RIGHT 2010 CENSUS TRACT
Functions:	1, 1E, 1B, 2, 3 (MSW: 2010 - Regular WA2; 2000 - Long WA2 Only), 3(COW), 3C
Work Area Format:	MSW and COW
Length and Format:	6 bytes, consisting of numeric 4-digit root followed by numeric 2-digit suffix. The root subfield is RJBF and the suffix subfield is RJZF if any. If the tract number contains no suffix, then the suffix subfield is blank.
Description:	Geographic area defined by the U.S. Census Bureau for the various decennial censuses. Census tracts for a particular census year are numbered uniquely within borough.

CITY COUNCIL DISTRICT

Functions:	1B (COW), 1E, 2(COW only)
Work Area Format:	MSW and COW
Length and Format:	2 bytes.
Description:	A district represented by a member of the New York City Council. Consists of an aggregation of Election Districts. There are currently 51 City Council Districts.

CIVIL COURT DISTRICT

Functions: 1E, 1B (COW), 2(COW only)

Work Area Format: MSW and COW

Length and Format: 2 bytes.

Description: A district from which a Civil Court judge is elected. Consists of an aggregation of Election Districts.

COINCIDENT SEGMENT COUNT

Functions: 1, 1E, 3, 3C

Work Area Format: MSW and COW

Length and Format: 1 byte, numeric

Description: The Coincident Segment Count indicates the situation where one road is above another road. Most streets, such as Broadway in Manhattan have a value of '1' in the Coincident Segment Count. However, there are a few streets where the Coincident Segment Count is greater than one. An example of this is Third Avenue and the Gowanus Expressway in Brooklyn. The Gowanus Expressway is above Third Avenue from about 18th Street until 63rd Street. For these segments, the Coincident Segment Count is '2'.

COMMUNITY DEVELOPMENT BLOCK GRANT (CDBG) - See INTERIM ASSISTANCE
ELIGIBILITY INDICATOR

COMMUNITY DEVELOPMENT ELIGIBILITY FLAG - See INTERIM ASSISTANCE ELIGIBILITY INDICATOR

COMMUNITY DISTRICT (CD)

Functions: 1, 1E, 2, 3, 3C, 1B (COW)

Work Area Format: MSW and COW

Length and Format: 3 bytes. Numeric. The first byte is the Community District Borough Code, and the second and third bytes are the Community District Number, RJZF.

Description: There are 59 community districts in the City of New York, as well as 12 Joint Interest Areas (JIAs). The JIAs are major parks and airports that are not contained within any CD. Examples are Central Park, Van Cortlandt Park, LaGuardia and JFK Airports. The JIAs are the numerically highest items in each borough.

Code Value	Meaning
101-112	**Manhattan** except Marble Hill
164	**Central Park**

201-212	**Bronx**except Rikers Island (Note: the Marble Hill section of Manhattan is in Bronx CDs 7 and 8)
226	Van Cortlandt Park
227	Bronx Park
228	Pelham Bay Park
301-318	**Brooklyn**
355	Prospect Park
356	Brooklyn Gateway National Recreational Area
401-414	**Queens** (Note: the Rikers Island section of the Bronx is in Queens CD 1)
480	LaGuardia Airport
481	Flushing Meadows - Corona Park
482	Forest Park
483	JFK International Airport
484	Queens Gateway National Recreational Area
501-503	**Staten Island**
595	Staten Island Gateway National Recreational Area

COMMUNITY DISTRICT ELIGIBILITY FLAG - See INTERIM ASSISTANCE ELIGIBILITY INDICATOR

COMMUNITY SCHOOL DISTRICT – see SCHOOL DISTRICT

COMPACT FLAG - See STREET NAME NORMALIZATION FORMAT FLAG

COMPASS DIRECTION

Functions:	2, 3C, 3S
Work Area Format:	MSW and COW
Length and Format:	1 byte.
Description:	In the case of Function 2, the compass direction identifies, for a pair of input streets that intersect at two distinct locations, which of those two intersections is to be processed. (See Chapter VII.2) In the case of Function 3C, the compass direction identifies which side of the street is to be processed. (See Section VII.5) In the case of Function 3S, if the 'on' street intersects the first cross street at two distinct locations, the compass direction identifies which of those two intersections is to be processed. (See Chapter VII.6)

COMPASS DIRECTION FOR INTERSECTION KEY

Functions:	2
Work Area Format:	MSW and COW
Length and	1 byte.

Format:

Description: If the first two entries in the LIST OF INTERSECTING STREETS are an instance of the two-node case (i.e., they intersect twice), this field contains a compass direction value identifying the intersection in terms of those two streets. If the two streets are not an instance of the two-node case, this field is blank. If both a 'longitudinal' compass direction ('N' or 'S') and a 'latitudinal' compass direction ('E' or 'W ') are valid for this intersection, the longitudinal compass direction value appears in this field.

COMPASS DIRECTION FOR 2nd INTERSECTION

Functions: 3S

Work Area Format: MSW and COW

Length and Format: 1 byte.

Description: If the 'on' street intersects the second cross street at two distinct locations, this compass direction identifies which of those two intersections is to be processed. (See Chapter VII.6)

CONDOMINIUM FLAG

Functions: 1A, BL, BN, 1B (COW), AP

Work Area Format: MSW and COW

Length and Format: 1 byte.

Description:

Code Value	Meaning
'C'	Property is a condominium
Blank	Property is not a condo.

CONDOMINIUM IDENTIFICATION NUMBER

Functions: 1A, BL, BN, 1B (COW), AP

Work Area Format: MSW and COW

Length and Format: 4 bytes

Description: An identification number assigned by the Department of Finance to each condominium in the city. This field is blank for non-condominiums.

CONGRESSIONAL DISTRICT

Functions: 1E, 1B (COW), 2 (COW only)

Work Area Format: MSW and COW

Length and Format: 2 bytes.

Description: A district of the U.S. House of Representatives. Consists of an aggregation of Election Districts.

CONTINUOUS PARITY INDICATOR

Functions: 1, 1E, 3, 3C, 1B (COW)

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: An ‘address range’ is a sequence of house numbers along an ‘on’ street between (and including) a Low House Number and a High House Number. Every address range has one of three possible parities: odd, even or continuous. An address range of odd parity consists of all odd house numbers along the ‘on’ street between the Low and High House Numbers. An even-parity range consists of all even house numbers between the Low and High House Numbers. A continuous-parity range consists of all house numbers (both even and odd) between the Low and High House Numbers. Most New York City blockfaces contain an address range that is either of even or odd parity. However, some blockfaces have a continuous-parity address range, usually where the opposite side of the street is non-addressable because it is a park, a body of water, etc. Some examples of the continuous parity case in Manhattan are Central Park West (the east side of the street runs along Central Park and is non-addressable, while the west side has both odd and even addresses); Riverside Drive; and the portion of Fifth Avenue that runs alongside Central Park.

If a New York City blockface has a continuous parity address range, Geosupport represents this range as two separate ranges, an odd-parity range and an even-parity range. The practical effect of this depends on the Geosupport function. For Functions 1 and 1E, if an input address lies on a continuous-parity blockface, only the range (i.e., the Low and High House Numbers) whose parity is the same as that of the input address is returned in WA2. For Function 3, if an input street segment contains a continuous parity address range, both the odd and the even ranges are returned, in the WA2 fields called Left Low House Number and Left High House Number for the range of one parity, and in the fields Right Low and High House Numbers for the range of the other parity; note that in this case, in reality both the odd and the even ranges are on the same side of the street, even though they are returned in fields called ‘left’ and ‘right’. For Function 3C, if an input blockface is on a street segment containing a continuous parity address range (regardless of whether the input blockface is on the addressable or the non-addressable side of the segment), both the odd and the even ranges are returned, in the WA2 fields called Low House Number and High House Number for the range of one parity, and in the fields Alternate Low House Number and Alternate High House Number for the range of the other parity.

The field Continuous Parity Indicator indicates, for Functions 1, 1E, 3 and 3C, whether the street segment containing or corresponding to the user input is of the continuous parity type, and if so, which side of the segment is addressable.

Code Value	Meaning
Blank	The street segment does not have a continuous parity address range
'L' or 'R'	The street segment has continuous parity. In this case, the Continuous Parity Indicator indicates which side of the street segment, the left or the right, is addressable. (Left and right are specified with respect to the direction of increasing addresses along the segment)

COOPERATIVE IDENTIFICATION NUMBER

Functions: 1A, BL, BN, 1B (COW)

Work Area Format: MSW and COW

Length and Format: 4 bytes.

Description: This is an identification number assigned by the Department of Finance to each cooperative in the city. This field is blank for non-coops.

CORNER CODE

Functions: 1A, BL, BN, 1B (COW)

Work Area Format: MSW and COW

Length and Format: 2 bytes

Description:

Code Value	Meaning
'SE','SW','NE','NW'	Tax lot occupies the indicated corner of the physical block
'CR'	Tax lot occupies more than one corner
Blank	Tax lot occupies no corners

COUNTY BOUNDARY INDICATOR

Functions: 3, 3C

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: This field is non-blank when the street segment lies along a borough boundary. The value of this field indicates which side of the segment is out of borough.

Code Value	Meaning
'L'	Left side of segment is out of borough
'R'	Right side of segment is out of borough
Blank	Neither side is out of borough

CROSS STREET NAMES FLAG (a.k.a. EXPANDED FORMAT FLAG)

Functions: 1, 1E, 2, 3, 3C, 1B (COW)

Work Area Format: MSW and COW

Length and Format: 1 byte character.

Description: When this flag is set to ‘E’, the LIST OF STREET NAMES is used to return street names corresponding to the street codes in the LIST OF CROSS STREETS (Functions 1, 1B, 1E, 3 and 3C) or in the LIST OF INTERSECTING STREETS (Function 2). See LIST OF STREET NAMES for related details.

When possible, the BBL and BIN are returned in the output area of Work Area 1 for Functions 1, 1A, 1B, and 1E.

The cross street names feature incurs processing overhead, and should only be used when necessary. Note that Function 1B returns the principal street codes and street names of the cross streets in the Blockface portion of Work Area 2. Therefore it is typically not necessary to set the Cross Street Names flag with Function 1B.

Code Value	**Meaning**
Blank	The names of cross or intersecting streets are not returned in the LIST OF STREET NAMES. The BBL an BIN are not returned in the output area of Work Area 1.
‘E’	The names of cross or intersecting streets are returned in the LIST OF STREET NAMES The BIN and BBL of the input address are returned in the output area of Work Area 1.

CROSS STREET REVERSAL FLAG

Functions: 3, 3C

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: This flag indicates the relationship between the order in which the user specified the input cross streets and the direction of increasing addresses along the ‘on’ street.

Code Value	**Meaning**
Blank	The direction from Street Name 2 to Street Name 3 (the two input cross street fields) conforms to the direction of increasing addresses
‘R’	The direction from Street Name 2 to Street Name 3 is opposite to the direction of increasing addresses

CROSS SREETS

See LIST OF CROSS STREETS (Functions 1, 1E, 3, 3C, 1B)
See LIST OF INTERSECTING STREET (Function 2)
See LIST OF CROSS STREET CODES (Function 3S)

CURVE FLAG

Functions: 1, 1E, 3, 3C, 1B (COW)

Work Area Format: MSW and COW

Length and Format: 1 byte character

Description: This flag indicates whether the given geographic feature segment is in reality curved. If so, the curve may be an arc of a circle or an irregular curve. When the segment specified by the input data is an arc of a circle, Functions 1 and 1E return Spatial Coordinates that are positioned relative to this arc rather than to the segment's chord (the imaginary straight line joining the curved feature's endpoints). When the segment specified by the input data is an irregular curve, Functions 1 and 1E return blanks in the Spatial Coordinate fields (q.v.), and issue a warning with Reason Code value 'P'. In the case of Functions 3 and 3C, if the input data define a street stretch encompassing more than one segment (because of a T-intersection or bend), the Curve Flag is set 'on' (non-blank) if at least one of the constituent segments of the stretch is curved. See also discussion of Segment Length.

Code Value	Meaning
Blank	Segment is not curved
'I'	Segment is an irregular curve, i.e., it is curved but it is not an arc of a circle
'L'	Segment is an arc of a circle on the left side of the line joining the segment's FROM and TO nodes
'R'	Segment is an arc of a circle on the right side of the line joining the segment's FROM and TO nodes

D

DCP PREFERRED LGC

Functions: 1, 1A and BL (regular WA2 only), 2, 3, 3C, BN

Work Area Format: MSW and COW

Length and Format: 2 bytes RJZF

Description: Identifies the local group of street names designated by the Department of City Planning as 'preferred' for display purposes for a specific location on a street.

DCP ZONING MAP

Functions:	1A/BL/BN, 1A/BL/BN Extended, 1A/BL Long WA2, 1A/BL TPAD Long WA2, 1B
Work Area Format:	COW
Length and Format:	3 bytes
Description:	The DCP Zoning Map field contains the DCP Zoning Map number.

DEPARTMENT OF SANITATION SNOW PRIORITY CODE - See DSNY SNOW PRIORITY CODE

DISTANCE BETWEEN DUPLICATE INTERSECTIONS

Functions:	2
Work Area Format:	MSW and COW
Length and Format:	5 bytes numeric
Description:	When the two input streets intersect exactly twice, this field contains the distance, in feet, between those two intersections.

DOGLEG FLAG

Functions:	3
Work Area Format:	MSW and COW
Length and Format:	1 byte

Description: A dogleg is a street configuration in which a street has a displacement or offset as it crosses another street. A non-blank value in the Dogleg Flag indicates that at least one of the cross streets forms a dogleg as it crosses the 'on' street, in such a way that at least one side of the 'on' street has a blockface encompassing more than one segment.

When Function 3 returns a non-blank value in this flag, the work area represents the 'innermost' segment of the dogleg configuration.

The Dogleg Flag value indicates which side or sides of the street has (or have) the long blockface(s).

Code	Meaning
Blank	Not a dogleg
'B'	Both sides of the 'on' street have long blockfaces formed by doglegs. This can only occur if both cross streets form doglegs as they cross the 'on' street.
'L'	The left side of the street has a long blockface formed by a dogleg

‘R’ The right side of the street has a long blockface formed by a dogleg

A Function 3C call will return information on the long blockface when the user input data specifies a side of a street where there is a long blockface formed by a dogleg or doglegs. The Dogleg Flag will not be set in response to a function 3C call.

DOT STREET LIGHT CONTRACTOR AREA

Functions: 1, 1E, 2, 3, 3C, 1B (COW)

Work Area Format: MSW and COW

Length and Format: 1 byte

Description:

Code	Meaning
‘1'	Street lights serviced by Manhattan contractors
‘2'	Street lights serviced by Bronx contractors
‘3'	Street lights serviced by Brooklyn contractors
‘4'	Street lights serviced by Queens contractors
‘5'	Street lights serviced by Staten Island contractors
‘X'	Street light is located on the Brooklyn, Queens boundary
‘N’	Street light is located in one borough, but serviced by a different borough

DSNY ... - See also SANITATION ...

DSNY SNOW PRIORITY CODE

Functions: 1/1E, 1/1E Extended, 1B, 3, 3 Extended, 3C, 3C Extended

Work Area Format: COW

Length and Format: 1 byte character

Description: DSNY (Department of Sanitation) Snow Priority code is used during snow emergencies. It helps DSNY to determine the snow removal schedule, routes and resources needed.

The DSNY (Department of Sanitation) Snow Priority indicates the priority of the street with respect to snow removal. New snow priority codes were assigned with Version 16.4 The snow priority codes are as follows:

Code Value	Meaning
C	Critical
S	Critical
S	Sector
H	Haulster
V	Non-DSNY Street (unchanged)

The DSNY definition of the new codes is as follows:

C - Critical Routes: These routes are comprised of highways (main beds, entrances, exits interchanges), arterial roadways, main travel thoroughfares (single lane and multi-lane), bus routes, that contain emergency services & first responder facilities (Hospitals, EMS, FDNY, NYPD) and schools.

C - Critical Routes: These routes are comprised of highways (main beds, entrances, exits interchanges), arterial roadways, main travel thoroughfares (single lane and multi-lane), bus routes, that contain emergency services & first responder facilities (Hospitals, EMS, FDNY, NYPD) and schools.

S - Sector Routes: Designed to encompass all streets that are not classified as Critical Streets and are wide enough to accommodate a full size DSNY collection truck with a plow attached.

H - Haulster Routes: Designed to service dead ends and streets that cannot be serviced with a collection truck or salt spreader with a plow attached due to narrow street width or tight turning radius (either entering or exiting the street).

Important Note: The old code values (i.e. prior to Version 16.4) are no longer in use. They were P (Primary), S (Secondary) and T (Tertiary)**If a user application checks for specific Snow Priority Values, the application will need to be updated**

It is also important to note that the new Snow Priority values provided to DCP were for roadbed geography only. Snow Priority values will not be returned for generic geography, unless requested for a future release by DSNY.

DYNAMIC BOCK - See ATOMIC POLYGON

E

s

ELECTION DISTRICT (ED)

Field Names:	LEFT ELECTION DISTRICT RIGHT ELECTION DISTRICT
Function:	1E, 3 (COW only), 3C (COW only), 1B (COW only)
Work Area Format:	MSW and COW
Length and Format:	3 bytes
Description:	A set of districts defined by the NYC Board of Elections to conduct elections. There are approximately 6,000 Election Districts (EDs) in NYC. Each ED is numbered uniquely within its Assembly District. All of NYC's higher-level political districts, namely Assembly Districts, City Council Districts, Municipal Court Districts, Congressional Districts and State Senatorial Districts, are defined as aggregates of Eds.

EXPANDED FORMAT FLAG - See CROSS STREET NAMES FLAG
EXTENDED MODE SWITCH - See MODE SWTICH

F

FACE CODE

Functions: 1, 1E, 3, 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 4 bytes. Numeric

Description: A Face Code is assigned to each linear geographic feature represented in the LION file. These consist of streets and certain non-street features, such as census boundaries, shorelines and railroad tracks. Face Codes serve as part of LION keys, which identify a unique LION record. Face Code values are assigned uniquely within borough.

FEATURE TYPE CODE

Functions: 1, 1E, 3, 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: Identifies the type of geographic feature represented by the work area

Code	Meaning
blank	Public street that exists physically, other than a type ‘W’ feature (see below)
‘1'	Railroad
‘2'	Shoreline
‘3'	Census block boundary without physical existence
‘4'	Other non-street feature
‘5'	‘Paper street’, i.e., a public street that is legally ‘mapped’ but does not exist physically
‘6'	‘Private street that exists physically
‘7'	Physically nonexistent district boundary, other than a type ‘3’ feature (see above)
‘8'	Physical Boundary such as a cemetery wall
‘9'	Paper street’ that coincides with a non-physical boundary such as a Census block
‘C'	CCO (Corporation Council Opinion). Street dedicated for public use (See Glossary)
‘W'	Path, non-vehicular, addressable

Note: As of Release 16D, Physical Boundaries, such as cemetery walls, will no longer appear as cross streets in Functions 1/1E, 1B, 2, 3 and 3C

FIRE BATTALION

Functions: 1, 1E, 2, 3 (MSW: Long WA2), 3 (COW), 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 2 bytes

Description: An administrative fire district composed of Fire Companies/

FIRE COMPANY NUMBER

Functions: 1, 1E, 2, 3 (MSW: Long WA2), 3 (COW), 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 3 bytes. Numeric RJZF

Description: The smallest kind of administrative fire district defined by the NYC Fire Department. There are three types, indicated by the Fire Company Type: engine companies, Squad and ladder companies.

FIRE COMPANY NUMBER

Functions: 1, 1E, 2, 3 (MSW: Long WA2), 3 (COW), 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: Fire companies are characterized by the type of apparatus they use to fight fires.

Code	Meaning
'E'	Engine Company
'L'	Ladder Company
'Q'	Fire Squad Note: 'Q' may appear as 'SQ' on GOAT screens

FIRE DIVISION

Functions: 1, 1E, 2, 3 (MSW: Long WA2), 3 (COW), 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 2 bytes

Description: An administrative fire district composed of Fire Battalions.

FROM NODE - See NODE NUMBER

FROM NODE ID - See NODE NUMBER

FUNCTION 1A/BL VERSION FLAG

Functions: 1A, BL

Work Area Format: MSW and COW

Work Area Format: MSW and COW

Length and Format: 1 byte

Length and Format: Code Meaning

Description:

Code	Meaning
'S'	Standard version - Required for MSW
'L'	Invalid - No Longer Supported
Blank	COW: Standard version MSW: Invalid

G

GAP FLAG

Functions: 3S

Work Area Format: MSW and COW

Length and Format: 1 byte

Description:

Code Value	Meaning
'E'	Engine Company
'L'	Ladder Company
'Q'	Fire Squad Note: 'Q' may appear as 'SQ' on GOAT screens

1, 1E, 2, 3 (MSW: Long WA2), 3 (COW), 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 2 bytes

Description: An administrative fire district composed of Fire Battalions.

FROM NODE - See NODE NUMBER

FROM NODE ID - See NODE NUMBER

FUNCTION 1A/BL VERSION FLAG

Function: 1A, BL

Work Area Format: MSW and COW

Length and Format: 1 byte

Description:

Code	Meaning
'S'	Standard version - Required for MSW
'L'	Invalid - No Longer Supported
Blank	COW: Standard version MSW: Invalid

GAP FLAG

Functions: 3S

Work Area

Format: MSW and COW

Length and Format: 1 byte

Description:

Code Value	Meaning
Blank	No gap, i.e., the 'on' street connects this intersection with its predecessor in list. The gap flag in the 1st entry in the list is always blank.
'G'	A gap exists along the 'on' street between this intersection and its predecessor
'C'	Real Streets Only have been requested, resulting in segment lengths being 'Combined' and one or more nodes being omitted between this intersection and its predecessor in the list (COW Only).
'D'	A dog-leg type gap exists along the 'on' street between this intersection and its predecessor
'N'	A new stretch exists.

For more information on the types of 'gaps' that can be returned by Function 3S, see Chapter VII.6

GENERATED RECORD FLAG

Functions: 3, 3C

Work Area Format: MSW and COW

Length and Format: 1 byte/td>

Description: This flag indicates that the geography defined by the input 'on' street and two cross streets is not a conventional street segment. There are several cases: a segment one of whose cross-features is a pseudo-street name (codes C, D); a street stretch formed by consolidating more than one consecutive LION segment (codes B, L, M, R, S and T); or a segment that is part of such a street stretch (types F, G). If the input data simultaneously satisfy the criteria for a Generated Record Flag value of C or D and for some other value, the flag contains the value other than C or D.

'B' Record has been generated by consolidating several LION segments to represent a stretch of a street where there is a node that is not at an intersection, such as a bending point (or a consecutive sequence of such nodes).

'C' Record generated because one or both nodes of segment lie on the City Limit (Bronx-Westchester or Queens-Nassau border), but segment itself lies entirely within the City. The cross street list for a node on the City Limit contains the special street code assigned to the pseudo-street name CITY LIMIT in the Bronx or Queens, as appropriate.

Record has been generated for a dead end segment, i.e. a segment at least one of whose nodes either has no other segments incident at it, or has segments of

‘D’ non-street features only. The cross street list at such a node contains only the special street code assigned to the pseudo-street name DEAD END in the given borough.

‘F’ Record represents a segment that is part of a street stretch that either contains a bending point at which there are no cross streets, or the left side of which is the long blockface of a T-intersection or a consecutive sequence of T-intersections.

‘G’ Record represents a segment that is part of a street stretch, that either contains a bending point at which there are no cross streets, or the right side of which is the long blockface of a T-intersection or a consecutive sequence of T-intersections.

‘L’ Record has been generated to represent the long blockface on the left side of a T-intersection.

‘M’ Record has been generated by consolidating two or more LION segments to represent a stretch of a street containing a node or a consecutive sequence of nodes at which the ‘on’ feature intersects with no streets but intersects with more than one type of non-street feature.

‘R’ Record has been generated to represent the long blockface on the right side of a T-intersection.

‘S’ Record has been generated by consolidating two or more LION segments to represent a stretch of a street containing a node or a consecutive sequence of nodes at which the ‘on’ feature intersects with no streets but intersects with one or more shorelines.

‘T’ Record has been generated by consolidating two or more LION segments to represent a stretch of a street containing a node or a consecutive sequence of nodes at which the ‘on’ feature intersects with no streets but intersects with one or more train tracks.

H

HEALTH AREA

Functions: 1, 1E, 2, 3, 3C, 1B

Work Area Format: MSW and COW

Length and Format: 4 bytes

Description: Districts defined by the NYC Department of Health and used to report statistics on births, deaths, communicable diseases etc. Health Areas are aggregates of Census Tracts.

HEALTH CENTER DISTRICT

Functions: 1, 1E, 2 (COW only), 3 Extended, 3C Extended

Work Area

Format: MSW and COW

Work Area Format: 2 bytes

Description: Districts defined by the NYC Department of Health for administrative purposes. Health Center Districts are aggregates of Health Areas.

HEZ - See HURRICANE EVACUATION ZONE

HIGH HOUSE NUMBER - See HOUSE NUMBER

HOUSE NUMBER a.k.a. ADDRESS NUMBER

Field Names: HOUSE NUMBER (WA1 input field, Functions 1, 1A, 1B, 1E,AP);

NORMALIZED HOUSE NUMBER (WA1 output field, Functions 1, 1A, 1B, 1E, AP);

LOW HOUSE NUMBER

HIGH HOUSE NUMBER (WA2 output fields, Functions 1, 1A, 1B, 1E, 3C,AP);

LEFT LOW HOUSE NUMBER,

LEFT HIGH HOUSE NUMBER,

RIGHT LOW HOUSE NUMBER,

RIGHT HIGH HOUSE NUMBER (WA2 output fields, Function 3)

ALTERNATE LOW HOUSE NUMBER,

ALTERNATE HIGH HOUSE NUMBER (WA2 output fields, Function 3C)

UNDERLYING HOUSE NUMBER FOR VANITY ADDRESSES (WA2, 1 and 1E-MSW: Long WA2, 1, 1B, and 1EE-COW, AP?)

Functions: 1, 1A, 1E, 3, 3C, 1B COW only)

Work Area Format: MSW and COW

Length and Format: See Chapter V.2.

Description: If the field name indicates the house number is normalized, for MSW it is in HNI format, and for COW it is in HNS format; otherwise, it is in HND format (see Chapter V.2).

HOUSE NUMBER JUSTIFICATION FLAG

Functions: 1, 1E, 1A, D, DG, DN, 1B?

Work Area Format: COW

Length and Format 1 byte

Description: Indicates whether the HOUSE NUMBERS IN DISPLAY format (HNDs) in the output area should be left-justified or right-justified.

Code Value	Meaning
'L' or Blank	Left-justify Normalized House Numbers (default)
'R'	Right-justify Normalized House Numbers

HOUSE NUMBER NORMALIZATION LENGTH

Functions: 1, 1E, 1A, 1B, D, DG, DN

Work Area Format: COW

Length and Format: 2 bytes, numeric

Description: Indicates the length requested for the HOUSE NUMBERS IN DISPLAY format (HNDs) in the output area. Valid values are between 12 and 16. If the field is left blank, the default is 12. For more information, see Chapter V.2.

HURRICANE EVACUATION ZONE (HEZ)

Function: 1/1E, 1/1E Extended, 1B

Work Area Format: COW

Length and Format: 2 bytes, alphanumeric, RJBF

Description: Information used by Emergency Management (previously known as Office of Emergency Management (OEM)) in emergency situations.

New York City's hurricane contingency plans are based on six evacuation zones: 1, 2, 3, 4, 5, 6. The value of 0 represents water polygons and the value of X indicates land that is not part of an evacuation zone.

Value	Description
0	Coastal Water polygon
1-6	Hurricane Evacuation Zone designation
X	Land not part of an evacuation zone

Additional information may be found at http://www1.nyc.gov/site/em/ready/hurricane-evacuation.page

I

INSTRUCTIONAL DIVISION - See INSTRUCTIONAL REGION

INTERIM ASSISTANCE ELIGIBILITY INDICATOR (IAEI) - a.k.a. CD Eligibility Flag

INTERIM ASSISTANCE ELIGIBILITY INDICATOR (IAEI) - a.k.a. CD Eligibility Flag

Functions: 1, 1E, 2 (COW only), 3, 3C, 1B

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: Indicates whether the input location is in a census tract that is eligible for Community Development Block Grant (CDBG) funding. A census tract is eligible for CDBG funding if at least 51.00% of the residents are low- and moderate-income persons (less than 80% of the Median Family Income) and 50% of its total floor area must be comprised of residential usage. All other census tracts are ineligible.

Note the new residential criteria mentioned above. In Release 16D, the 'CD Eligibility' values were updated to reflect the new criteria. The new values, recalculated by the Economic Development Corporation (EDC) and supplied to the Department of City Planning (DCP) by the New York City Office of Management and Budget (OMB), were revised to reflect new residential floor area data made available in DCP's PLUTO data (16v1)

Code Value	Meaning
'E'	Input location is in a CD-eligible census tract
'I'	Location is not in a CD-eligible census tract
Blank	Location is in a census tract, the CD-eligibility status of which is unknown to the Geosupport System.(Note: This is an error condition and should be reported).

INTERSECTING STREETS - See LIST OF INTERSECTING STREETS

INTERSECTION REPLICATION COUNTER

Functions: 2

Work Area Format: MSW and COW

Length and Format: 1 byte, numeric

Description: The Intersection Replication Counter is non-blank only if the two streets intersect more than once, in which case this field contains the number of such intersections.

INTERIOR LOT FLAG

Functions: 1A, BL, BN

Work Area Format: MSW and COW

Length and Format: 1 byte

Description:

Code Value	Meaning
'I'	Tax lot is interior to physical block, i.e., it has no street frontages.
Blank	Tax lot has at least one street frontage

INTERNAL LABEL POINT - See SPATIAL COORDINATES OF THE TAX LOT CENTROID

IRREGULARLY-SHAPED LOT FLAG

Functions: 1A, BL, BN

Work Area Format: MSW and COW

Length and Format: 1 byte

Description:

Code Value	Meaning
'I'	Tax lot is irregularly-shaped, i.e., non-rectangular
Blank	Tax lot is rectangular

JOINT INTEREST AREA (JIA) - See COMMUNITY DISTRICT

L

LATITUDE, LONGITUDE

Functions: 1/1E Extended, all variations of 1A/BL/BN (viz. Regular, Long and Extended), 1B, 2W, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: Latitude: 9 bytes
Longitude: 11 bytes

Description: Spatial coordinates based on the lines of latitude and longitude. Lines of latitude measure the north-south position between the poles with the equator defined as 0 degrees. Lines of longitude (or meridians) measure the east-west position, with the prime meridian running through Greenwich, England. For NYC, Latitude is always positive and Longitude is always negative.

The latitude and longitude of a location are calculated based on the spatial coordinates (x,y) returned for that location. As a result, the latitude and longitude returned by the Address Processing functions (e.g. 1/1E Extended) will be somewhat different from the values returned by Tax Lot and Building processing functions (e.g. 1A/BL/BN). See also SPATIAL COORDINATES and SPATIAL COORDINATES OF THE TAX LOT CENTROID.

LEFT 1990 CENSUS TRACT - See CENSUS TRACT.
LEFT 2000 CENSUS BLOCK - See CENSUS BLOCK.
LEFT 2000 CENSUS BLOCK SUFFIX - See CENSUS BLOCK SUFFIX
LEFT 2000 CENSUS TRACT - See CENSUS TRACT.
LEFT 2010 CENSUS BLOCK - See CENSUS BLOCK.
LEFT 2010 CENSUS BLOCK SUFFIX - See CENSUS BLOCK SUFFIX.
LEFT 2010 CENSUS TRACT - See CENSUS TRACT.

LEFT ASSEMBLY DISTRICT - See ASSEMBLY DISTRICT.
LEFT BLOCKFACE ID - See BLOCKFACE ID.
LEFT ELECTION DISTRICT - See ELECTION DISTRICT

LENGTH IN FEET FROM PREVIOUS NODE

Functions: 3S
Work Area Format: MSW and COW
Length and Format: MSW: 3 bytes packed; COW: 5 bytes numeric RJZF
Description: The length between two nodes.

LGI - See LIST OF GEOGRAPHIC IDENTIFIERS

LION KEY

Functions: 1, 1E, 3, 3C, 1B (COW only)
Work Area Format: MSW and COW
Length and Format: 10 bytes. Numeric
Description: The LION Key identifies a record in the CSCL file and relates to predecessor file known as LION. It consists of:
BOROUGH CODE (1 byte)
FACE CODE (4 bytes)
SEQUENCE NUMBER (5 bytes)

LION NODE - See NODE NUMBER
LION NODE ID - See NODE NUMBER
LION NODE NUMBER - See NODE NUMBER
LION SEGMENT ID See SEGMENT ID
LION SEQUENCE NUMBER - See SEQUENCE NUMBER
LIST OF ADDRESS RANGES - See LIST OF GEOGRAPHIC IDENTIFIERS

LIST OF BUILDINGS ON TAX LOT

Functions: 1A and BL - Long WA2 only
Work Area Format: MSW and COW
Length and Format: 17,500 bytes, consisting of 2,500 slots for 7-byte BINs
Description: List of the BUILDING IDENTIFICATION NUMBER (BIN) of each building on the tax lot. See Chapter VI.6.

LIST OF BUILDINGS ON TAX LOT

Functions: 1A and BL - Long WA2 only
Work Area Format: MSW and COW

Length and Format: 17,500 bytes, consisting of 2,500 slots for 7-byte BINs

Description: List of the BUILDING IDENTIFICATION NUMBER (BIN) of each building on the tax lot. See Chapter VI.6.

LIST OF CROSS STREET CODES

Functions: 3S

Work Area Format: MSW and COW

Length and Format: MSW: 8 bytes, packed decimal, consisting of 2 slots for intersecting PB5SCs.
COW: 40 bytes, numeric, consisting of 5 slots for intersecting B7SCs.

Description: MSW: For each intersecting street, in general, this is the lowest and second lowest PB5SCs for the cross streets, as described below in COW. COW: For each intersecting street, this is a list of up to five B7SCs, starting, in general (see Note below), with the lowest B7SC, followed by the next lowest, followed by the remaining B7SCs in ascending order.

The purpose of the ordering of the first two street codes is to facilitate the ability of users to form consistent keys for geographic retrieval of application data.

Note 1: In order to provide the user with the most meaningful information, 'normal' streets will be listed first, followed by 'special' streets, such as Ramps and Exits. Railroads, Shorelines and Borough Boundaries will appear next, followed by Named Intersections, CITY LIMITs, DEAD ENDs and BENDs. This will occur even if the 'special' streets have lower street codes than the 'normal'.

Note 2: To avoid unnecessary listing of BENDs, Function 3S lists a BEND only if the angle of the bend is 60 degrees or more. (Prior to Release 16D, a bend was listed if the angle was 20 degrees or more.) Also, a bend is not included in the list of cross streets when another real street intersects there as well.

Note 3: Since Function 3S returns B7SCs, it is now possible for two streets to have the same B5SCs and different B7SCs, e.g. in Brooklyn, at the intersection of Clinton Street with Livingston Street and Aitken Place, Livingston Street and Aitken Place have the same B5SC (3-56530) but different B7SCs (3-56530-01 and 3-56530-02 respectively).

LIST OF CROSS STREETS

Field Names: LIST OF CROSS STREETS AT LOW ADDRESS END
LIST OF CROSS STREETS AT HIGH ADDRESS END

Functions: 1/1E Regular, 1/1E Extended (COW), 3, 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: - MSW: 20 bytes, consisting of slots for up to five 4-byte PB5SCs. 'Empty' slots contain packed zeros.

• COW (Regular): 30 bytes, consisting of slots for up to five 6-byte B5SCs. 'Empty' slots contain either numeric zeros or blanks.

• COW (1/1E Extended): 40 bytes, consisting of slots for up to five 8-byte B7SCs. 'Empty' slots contain either numeric zeros or blanks. This list is in addition to the

B5SC (30 bytes) list.

Description: A list of PB5SCs for MSW and B5SCs (and B7SCs) for COW (and COW 1/1E Extended), for up to five streets incident upon a delimiting node (endpoint) of a blockface or street segment. The number of non-empty list entries is returned in the corresponding WA2 field NUMBER OF CROSS STREETS AT (LOW or HIGH) ADDRESS END. It is possible for the list to be entirely empty. If the node lies on a borough boundary, the list may contain streets from both boroughs. Subject to the space limitation, the list may include the pseudo-streets 'City Limit', 'Dead End' and 'Bend'. The inclusion of 'Bend' in the list indicates that the node is a bending point of the 'on' street, not that it is a bending point of a cross street (although that may also be true). The purpose of the ordering of the first two street codes is to facilitate the ability of users to form consistent keys for geographic retrieval of application data.

Special handling has been given to Railroads, Shorelines, Coincident Streets and streets where two street names having different B5SCs are both valid (a.k.a. Special Address 'Type B' situation)

Note: As a result of this special handling, the first one or two street codes in the lists of intersecting streets may not always be the lowest two street codes. For example a railroad or shoreline would now be put last in the list, even if they have lower street codes than the other intersecting streets.

Some examples follow:

- Consider the situation of coincident street features, e.g. 3rd Avenue and Gowanus Expressway in Brooklyn. The Gowanus Expressway is above 3rd Avenue between approximately 18th Street and 65th Street.

  - If a user issues a Function 3 call requesting information about the segment of 3rd Avenue between 19th and 20th Streets, Geosupport will recognize that 3rd Avenue and the Gowanus Expressway are coincident streets and will not return Gowanus Expressway as an intersecting street. Please note that Geosupport will also accept as input Gowanus Expressway between 19th and 20th Streets. With this input, 3rd Avenue will not be listed as a cross street at either end.
  - If a user issues a Function 3S call, requesting the stretch on 3rd Avenue between 40th Street and 50th Street, Geosupport will recognize that 3rd Avenue and Gowanus Expressway are coincident streets and will not list them as intersecting.

- Consider the situation where a railroad is determined to be one of the cross streets. An example exists in Queens at Kneeland Street between Queens Boulevard and Dead End.

  - A Function 3 call will return QUEENS BOULEVARD and LONG ISLAND RAILROAD as cross streets at the low end. Even though the Long Island Railroad has a numerically smaller street code than Queens Boulevard, it is listed after Queens Boulevard.

- Consider the situation where two street names, with different street codes, are valid for the same blockface. An example exists in Queens where 207th Street and Clearview Expressway are both valid between 39th Avenue and Boyce Avenue.

    - o A Function 3 call will be accepted with either street name (viz. 207th Street or Clearview Expressway) as the on-street.

LIST OF CROSS STREETS AT HIGH ADDRESS END - See LIST OF CROSS STREETS

LIST OF CROSS STREETS AT LOW ADDRESS END - See LIST OF CROSS STREETS

LIST OF GEOGRAPHIC IDENTIFIERS (LGI)

Functions:	1A and BL - regular WA2, BN
Work Area Format:	MSW and COW
Length and Format:	756 bytes total, consisting of space for 21 36-byte entries, each entry having fields for the following data items:/td> Low House Number of Address Range High House Number of Address Range B5SC DCP-Preferred LGC BIN Entry Type Code Side of Street Indicator.
Description:	The List of Geographic Identifiers (LGI) is intended to provide a comprehensive geographic profile of a tax lot by listing, so far as the information is known and space allows, all of the lot's buildings; all of the street addresses and non-addressable street frontages of each building; all of the lot's 'vacant frontages' (i.e., street frontages of the lot not associated with buildings); and any NAPs associated with the lot. The LGI contains space for up to 21 entries. The number of non-empty entries is indicated in the WA2 field NUMBER OF GEOGRAPHIC IDENTIFIERS. The types of entries that the LGI can contain are as follows:

List of Geographic Identifiers - Possible Entry Types

Entry Type Code	Represents	Description
Blank	Address range	A real address range of a building on a given tax lot. There are values in the Low House Number, High House Number, B5SC, DCP-Preferred LGC, Side of Street Indicator and BIN fields. A single address is represented as an address range in which the low and high house numbers are identical.
B	NAUB	A Non-Addressable Un-named Building (NAUB) (see Chapter VI.3). The Low and High House Number and Side of Street Indicator fields are blank. The B5SC and DCP-Preferred LGC fields usually contain the street code

		and LGC, correspondingly, of the street nearest to or most accessible to the NAUB, but they may be blank. The BIN field contains a meaningful value. Note: If the NAUB has frontages on more than one street, there are multiple type B entries to represent all of the NAUB's street frontages.
F	Vacant Street Frontage	A street frontage of the tax lot at which there are no buildings (including NAUBs) and to which no pseudo-addresses have been assigned. The Low and High House Number, BIN and Side of Street Indicator fields are empty. There are values in the B5SC and DCP-Preferred LGC fields.
G	NAP of a Complex	A Non-Addressable Place name (NAP) of a complex of buildings and/or other geographic features, usually on a large site or superblock (see Chapter III.6). The house number and BIN fields are empty. The B5SC, DCP-Preferred LGC, and Side of Street Indicator fields contain the values of these items assigned to the NAP.
N	NAP of a	A NAP of a building or other geographic feature that is not part of Simplex a complex (see Chapter III.6). The house number fields are empty. The B5SC, DCP-Preferred LGC, and Side of Street Indicator fields contain the values of these items assigned to the given NAP. The BIN field is non-empty only if the NAP represents a building.
Q	Pseudo-Address Range	A pseudo-address range assigned to a vacant street frontage of the tax lot. There are values in the Low House Number, High House Number, B5SC, DCP-Preferred LGC and Side of Street Indicator fields. A single address is represented as an address range in which the low and high house numbers are identical. The BIN field is empty
R	Real Street of a Vanity Address	Entry indicates the street and the side of that street on which the building entrance having a vanity address is really located and for which no other address for that building exists. For a discussion of vanity addresses, see Chapter V.9. In a type R entry, the Low and High House Number fields are empty, and there are non-empty values in the B5SC, DCP-Preferred LGC, Side of Street Indicator and BIN fields. Whenever the LGI contains a type R entry, it also contains a type V entry for the associated vanity address
V	Vanity Address	A vanity address or address range. For a detailed discussion of vanity addresses, see Chapter V.9. There are non-empty values in the Low House Number, High House Number, B5SC, DCP-Preferred LGC, Side of Street Indicator and BIN fields. A single address is represented as an address range in which the low and high house numbers are identical. Whenever the LGI contains a type V entry, it also contains an either an address range entry or a type R entry that indicates the street on which the associated building entrance is really located.
W	Blank-Wall Bldg Frontage	A building frontage along a street that is not associated with any addresses, such as some building facades with no entrances. The Low and High House Number and Side of Street Indicator fields are blank. There are values in the B5SC and DCP-Preferred LGC fields. The BIN field contains a meaningful value. Note: Type W entries exist only for buildings that also have at least

one real address range entry. If a building has no real address ranges, the building is a NAUB, and its street frontages, if any, are represented by type B entries rather than type W entries.

X	NAP of a Constituent Entity of a Complex	A NAP of a constituent entity of a complex. (The NAP of the entire complex is represented by a separate entry of type G.) The house number fields are empty. The B5SC, DCP-Preferred LGC and Side of Street Indicator fields contain the values of these items assigned to the NAP. The BIN field is non-empty only if the NAP represents a building.

The combination of fields in an LGI entry that contain information depends on the entry type, as indicated in the following table:

List of Geographic Identifiers - Which Fields Contain Values By Entry Type

Entry Type Code	Entry Type	Low & High House Numbers	B5SC	LGC	Side of Street Indicator	BIN
blank	Real Address Range	✓	✓	✓	✓	✓
B	NAUB		(*)	(*)		✓
F	Vacant Street Frontage		✓	✓		
G	NAP of a complex		✓	✓	✓	
N	NAP of a complex		✓	✓	✓	(**)
Q	Pseudo-Address Range	✓	✓	✓	✓	
R	Real Street of Vanity Address		✓	✓	✓	✓
V	Vanity Address	✓	✓	✓	✓	✓
W	Blank-Wall Building Façade		✓	✓		✓
X	NAP of a constituent entity of a complex		✓	✓	✓	(**)

(*) NAUB entries may or may not contain B5SC and LGC values. An entry for a NAUB contains a B5SC value and an LGC value only if the GSS staff has determined that the NAUB fronts on, is adjacent to or is principally accessible from a particular street.

(**) The BIN field is non-empty only if the NAP represents a building.

The LGI's entries are ordered so that entries with non-empty BINs are listed first, grouped by BIN. Except for a special case (alternative borough for Marble Hill and Rikers Island - see Chapter V.7), if the input address is a real address, the first group of entries in the LGI are those for the BIN corresponding to the input address, and (except for alternative street records for Ruby Street - see Chapter V.8) the address range encompassing the input address is the very first entry in the LGI. After all the entries with non-empty BINs are listed, any entries with

empty BINs, such as entries for pseudo-address ranges, are listed in no particular order as space allows. If the input address is a pseudo-address range, it may or may not appear in the LGI, depending on space and on the order in which the non-BIN entries happen to be listed.

LIST OF GEOGRAPHIC IDENTIFIERS OVERFLOW FLAG - See LGI OVERFLOW FLAG

LIST OF INTERSECTING STREETS – See also LIST OF CROSS STREETS

Function:	2
Work Area Format:	MSW and COW
Length and Format:	MSW: 20 bytes, consisting of slots for up to five 4-byte PB5SCs. 'Empty' slots contain packed zeros. COW: 30 bytes, consisting of slots for up to five 6-byte B5SCs. 'Empty' slots contain numeric zeros or blanks.
Description:	A list of PB5SCS for MSWs and B5SCs for COWs for up to five streets incident upon the intersection. The field NUMBER OF INTERSECTING STREETS contains the number of non-empty entries in the list. If the intersection lies on a borough boundary, the list may contain streets from both boroughs. Subject to the space limitation, the list may include the two input streets, and may include the pseudo-streets 'City Limit' and 'Dead End'. The list never includes the pseudo-street 'Bend'. The list always contains at least one entry (it contains precisely one entry in the case of a bending point of a street at which there are no other streets). The street codes of the input streets may, or may not, be included in the list (depending upon their numerical value.) Note, special handling has been given to Railroads, Coincident Street Features, etc. As a result of this special handling, the first one or two street codes in the list of intersecting streets may not always be the lowest two street codes. See LIST OF CROSS STREETS for further description and examples of the special handling.

LIST OF SEGMENT IDS

Functions:	3 and 3C
Work Area Format:	COW
Length and Format:	500 bytes, consisting of a count of segment ids and 70 slots for 7-byte Segment IDs
Description:	This list is generated only if Auxiliary Segment Switch is set to 'Y'. See Chapter VII.4 and Appendix13.

LIST OF STREET CODES

Functions:	1*, 2, 3*, BB, BF
Work Area Format:	COW
Length and Format:	80 bytes, consisting of 10 fields for B7SCs
Description:	List of borough and 7-byte street codes, corresponding to the LIST OF STREET

NAMES. The number of street codes in the list is returned in the WA1 output field NUMBER OF STREET CODES AND STREET NAMES IN LIST.

LIST OF STREET NAMES (WA1 output field)

Functions: 1*, 2, 3*, BB, BF

Work Area Format: MSW and COW

Length and Format: 320 bytes, consisting of 10 fields for street names, each 32 bytes.

Description: This field is used by several Geosupport features (see below) to return a list of street names. The number of street names in the list is returned in the WA1 output field NUMBER OF STREET NAMES IN LIST for MSWs, and in the WA1 output field NUMBER OF STREET CODES AND STREET NAMES IN LIST for COWs.

The similar names feature uses the List of Street Names to return up to ten street names deemed 'similar' to a rejected input street name (see Chapter III.5).

The browse functions, Functions BB and BF, use the List of Street Names to return up to ten normalized street names in alphabetical order as part of a street name browse (see Chapter III.7).

The local street name validation feature uses the List of Street Names to return up to four locally valid alias street names corresponding to a street name rejected as locally invalid (see Chapter IV.5).

The cross street names feature (see CROSS STREET NAMES FLAG) uses the List of Street Names to return street names corresponding to the street codes in the LIST OF CROSS STREETS (Functions 1, 1E, 3 and 3C) or the LIST OF INTERSECTING STREETS (Function 2).

In the case of Functions 1, 1E, 3 and 3C, the first five 32-byte street name fields in the List of Street Names are used for the street names corresponding to the street codes in the LIST OF CROSS STREETS AT LOW ADDRESS END; the second five 32-byte street name fields in the List of Street Names are used for the street names corresponding to the street codes in the LIST OF CROSS STREETS AT HIGH ADDRESS END. The actual number of street names is found in Work Area 2 in the fields which provide the number of cross streets at each end of the street segment.

In the case of Function 2, the first five 32-byte street name fields in the List of Street Names are used for the street names corresponding to the street codes in the LIST OF INTERSECTING STREETS. The actual number of street names is found in Work Area 2 in the field which provides the number of intersecting streets at the specified intersection.

LOCATIONAL STATUS OF SEGMENT

Functions: 3, 3C

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: Indicates locational status of segment per codes below.

Code	Meaning
‘H’	Segment internal to a block, but not a Dead End (A Land Hook)
‘I’	Dead End Segment
‘X’	Tract Boundary Segment (other than borough boundary)
‘1'	Segment bordering Manhattan
‘2'	Segment bordering Bronx
‘3'	Segment bordering Brooklyn
‘4'	Segment bordering Queens
‘5'	Segment bordering Staten Island
‘9'	Segment bordering City Limits

LONGITUDE - See LATITUDE

LOW HOUSE NUMBER - See HOUSE NUMBER

MARBLE HILL/RIKERS ISLAND FLAG - See ALTERNATIVE BOROUGH FLAG

M

MODE SWITCH

Functions: 1, 1E, 1A, 3, 3C, BL, BN

Work Area Format: COW Only

Length and Format: 1 byte

Description: Indicates request for Extended Work Area 2 for the supported functions. These extended work areas contain street names in addition to Street Codes. Users no longer have to make separate D, DG, or DN calls to get the street names. In addition, CSCL data is returned in the extended Work Area 2. See [Appendix 13] (/appendices/appendix13/) for the Work Area layouts. Also, see Chapter II.7.

Code	Meaning
‘X’	Extended information in Extended WA2 requested
Blank	Extended information not requested (default)

N

NEIGHBORHOOD TABULATION AREA (NTA) CODE

Field Names: NTA or NTA CODE

Functions: 1, 1 Extended, 1E, 1E Extended, 1B, 3, 3 Extended, 3C, 3C Extended

Work Area COW

Format:	
Length and Format:	4 bytes alphanumeric
Description:	The Neighborhood Tabulation Areas (NTAs) are aggregations of census tracts that reflect the 2010 Census. The NTAs are assigned a 4-byte code and a 75-byte name. They are used by the Population Division of the Department of City Planning. See [Appendix 16](/appendices/appendix16/) for a description of the NTA's history and significance. The first two bytes of the NTA code are an alphabetic borough code as follows:

Code	Borough
MN	Manhattan
BX	Bronx
BK	Brooklyn
QN	Queens
SI	Staten Island

The remaining two bytes are numeric and uniquely define the NTA.

NODE ID - See NODE NUMBER

NODE NUMBER (a.k.a. NODE ID)

Field Names:	FROM NODE FROM NODE ID TO NODE TO NODE ID
Functions:	2, 3 (COW only), 3C (COW Only), 3S (COW Only), 1B (COW Only)
Work Area Format:	MSW and COW
Length and Format:	7 bytes. Numeric
Description:	A node is an endpoint of a geographic feature segment represented in CSCL/LION. Most nodes are points where a feature bends or terminates or where two features intersect in CSCL/LION. Each node has a node ID assigned to it, which is unique in the entire city. Node ID assignments are permanent; if a node is deleted from CSCL, its node ID is retired and is never reassigned to a different node. A Node ID may be used to identify an intersection or the end points of a segment. An end point node is often referred to as a From Node or a To Node.

NORMALIZED HOUSE NUMBER - See HOUSE NUMBER

NTA - See NEIGHBORHOOD TABULATION AREA (NTA) CODE

NTA CODE - See NEIGHBORHOOD TABULATION AREA (NTA) CODE

NTA NAME - See also NEIGHBORHOOD TABULATION AREA (NTA) CODE

Field Names: NTA NAME

Functions: 1 Extended, 1E Extended, 1B, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: 75 bytes alphanumeric

Description: See NEIGHBORHOOD TABULATION AREA (NTA) CODE

NUMBER OF BUILDINGS ON TAX LOT

Functions: 1A, BL - long WA2 only

Work Area Format: MSW and COW

Length and Format: 4 bytes numeric.

Description: Indicates the number of entries in the LIST OF BUILDINGS. Maximum value is 2,500

NUMBER OF CROSS STREETS

Field Names: NUMBER OF CROSS STREETS AT LOW ADDRESS END, NUMBER OF CROSS STREETS AT HIGH ADDRESS END

Functions: 1, 1E, 3, 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: One byte, containing a numeric digit from 0 to 5.

Description: Indicates the number of non-empty entries in the corresponding LIST OF CROSS STREETS.

NUMBER OF CROSS STREETS AT HIGH ADDRESS END - See NUMBER OF CROSS STREETS

NUMBER OF CROSS STREETS AT LOW ADDRESS END - See NUMBER OF CROSS STREETS

NUMBER OF GEOGRAPHIC IDENTIFIERS

Functions: 1A and BL - regular WA2 only, BN, AP

Work Area Format: MSW and COW

Length and Format: 2 bytes for MSW; 4 bytes for COW

Description: Indicates the number of entries in the LIST OF GEOGRAPHIC IDENTIFIERS. For Function AP, the number is always ‘0001’

NUMBER OF INTERSECTING STREETS

Functions: 2

Work Area Format: MSW and COW

Length and Format: One byte, containing a numeric digit from 1 to 5.

Description: Indicates the number of non-empty entries in the LIST OF INTERSECTING STREETS.

NUMBER OF PARKING LANES

Functions: 1/1E Extended, 1B, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: 2 bytes, RJBF.

Description: The number of lanes in a carriageway (roadway) that are reserved for parking of vehicles. The number of parking lanes were determined by DoITT's consultants working on the planimetric feature classes for NYC.

NUMBER OF STREET CODES AND STREET NAMES IN LIST

Functions: 1*, 2, 3*, BB, BF

Work Area Format: COW

Length and Format: 2 bytes, Numeric

Description: Indicates the number of street names returned in the LIST OF STREET NAMES, corresponding to the number of street codes returned in the LIST OF STREET CODES..

NUMBER OF STREET FRONTAGES OF LOT

Functions: 1A, BL, BN

Work Area Format: MSW and COW

Length and Format: 2 bytes, RJZF.

Description: Indicates the number of streets on which the given lot has at least one frontage.

NUMBER OF STREET NAMES IN LIST (WA1 output item)

Functions: 1*, 2, 3*, BB, BF

Work Area Format: MSW

Length and Format: 2 bytes, packed decimal

Description: Indicates the number of street names returned in the LIST OF STREET NAMES.

NUMBER OF TOTAL LANES

Functions: 1/1E Extended, 1B, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: 2 bytes, RJBF.

Description: The total number of lanes in a carriageway (roadway) including travel lanes and parking lanes. The total number of lanes were determined by DoITT's consultants working on the planimetric feature classes for NYC.

NUMBER OF TRAVEL LANES

Functions: 1/1E Extended, 1B, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: 2 bytes, RJBF

Description: The number of lanes in a carriageway (roadway) that are designated for the movement of vehicles traveling from one destination to another. The number of travel lanes were determined by DoITT's consultants working on the planimetric feature classes for NYC.

P

PARKING LANES - See NUMBER OF PARKING LANES

PLATFORM INDICATOR - See WORK AREA FORMAT INDICATOR

POLICE PATROL BOROUGH

Functions: 1, 1X, 1E, 1EX, 2, 2W, 3, 3X, 3C, 3CX, 1B

Work Area Format: COW Only

Length and Format: 2 bytes

Description: Police Patrol Boroughs are sub-borough geographic areas defined by the Police Department. They are composed of Police Precincts. Since the Police Department is supporting the Police Patrol Borough field, it is recommended that it be used.. Geosupport still returns the 1-byte POLICE PATROL BOROUGH COMMAND field to support those existing applications that access it.

Code	Meaning
MS	Manhattan South
MN	Manhattan North
BX	Bronx
	Brooklyn

BS	South
BN	Brooklyn North
QN	Queens North
SI	Staten Island
QS	Queens South

POLICE PATROL BOROUGH COMMAND (See also POLICE PATROL BOROUGH)

Functions:	1, 1E, 2, 3, 3C, 1B (COW only)
Work Area Format:	MSW and COW
Length and Format:	1 byte
Description:	These are sub-borough geographic areas defined by the Police Department. They are composed of Police Precincts.

Code	Meaning
1	Manhattan South
2	Manhattan North
3	Bronx
4	Brooklyn South
5	Brooklyn North
6	Queens North
7	Staten Island
8	Queens South

Note: It is recommended that you use the POLICE PATROL BOROUGH field (not the POLICE PATROL BOROUGH COMMAND field) since the Police Department is supporting the POLICE PATROL BOROUGH field.

POLICE PRECINCT

Functions:	1, 1E, 2, 3, 3C, 1B (COW only)
Work Area Format:	MSW and COW

Length and Format:	3 bytes. RJZF.
Description:	Police Patrol Borough Commands are sub-divided into Police Precincts which are defined by the Police Department

PUBLIC USE MICRODATA AREA (PUMA) CODE - See PUMA CODE

PUMA CODE

Field Names:	PUMA CODE
Functions:	1 Extended, 1E Extended, 1B, 3 Extended, 3C Extended
Work Area Format:	COW
Length and Format:	5 bytes, RJZF
Description:	PUMAs (Public Use Microdata Areas) are approximations of New York City's Community Districts which were developed for use with the Census Bureau's Public Use Microdata Samples (PUMS). In order to make the boundaries consistent with PUMAs, NTAs were created using whole census tracts, from the 2010 census, within PUMAs. For more information on the history and significance of NTAs and PUMAs, see Appendix 16. See also NEIGHBORHOOD TABULATION AREA (NTA) CODE

R

REAL STREET ONLY FLAG

Functions:	3S
Work Area Format:	COW
Length and Format:	1 byte. Alphabetic
Description:	

Code Value	Meaning
Blank	Meaning
R	Real streets only (not Bends or Non-Street Features

RIGHT 1990 CENSUS TRACT - See CENSUS TRACT.
RIGHT 2000 CENSUS BLOCK - See CENSUS BLOCK.
RIGHT 2000 CENSUS BLOCK SUFFIX - See CENSUS BLOCK SUFFIX.
RIGHT 2000 CENSUS TRACT - See CENSUS TRACT.
RIGHT 2010 CENSUS BLOCK - See CENSUS BLOCK.
RIGHT 2010 CENSUS BLOCK SUFFIX - See CENSUS BLOCK SUFFIX.
RIGHT 2010 CENSUS TRACT - See CENSUS TRACT.

RIGHT ASSEMBLY DISTRICT - See ASSEMBLY DISTRICT.
RIGHT BLOCKFACE ID - See BLOCKFACE ID.
RIGHT ELECTION DISTRICT - See ELECTION DISTRICT.

ROADBED REQUEST SWITCH

Functions: 1 1, 1E, 3S, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: Indicates request for Roadbed information for roads that are divided into two or more roadbeds. If Roadbed information is requested for a street that is not divided, Geosupport returns the generic information. For functions 1 and 1E, the Segment Type Code will indicate the type of information that is being returned. For more information on function 3S see Chapter VII.6.

Code	Meaning
'R'	Roadbed information requested
Blank	Generic (non-roadbed) information requested (default)

RPAD BUILDING CLASSIFICATION CODE

Functions: 1A, BL, BN, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 2 bytes

Length and Format: 2 bytes

Description: This is a set of land use/building classification codes defined by the Real Property Assessment Division (RPAD) of the Department of Finance. If a tax lot has more than one building or land use, RPAD assigns the building class code they deem to describe best the 'principal' building or the 'predominant' land use on the tax lot. The values and meanings of this set of codes can be obtained from the Department of Finance.

RPAD CONDO IDENTIFICATION NUMBER

Functions: 1A, BL, BN, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 4 bytes

Description: This is an identification number assigned by the Department of Finance to each condominium in the city. It identifies the condominium as a whole and not a specific condominium unit.

RPAD SELF-CHECK CODE (SCC) FOR BBL

Functions: 1A, BL, BN, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: For each BBL value, the Department of Finance has computed a Self-Check Code (SCC). This is a one-digit number computed from the BBL value using an algorithm chosen by DOF. The purpose of the SCC is to assist in validating key-entered BBLs. For more information on SCCs inquire to the information technology division of the Department of Finance.

S

-

SANBORN VOLUME AND PAGE

Functions: 1A, BL, BN, 2, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: The Volume field is 3 bytes (2-digit volume number + 1-digit character suffix). The Page field is 4 bytes (3-digit page number + 1-digit character suffix).

Description: The Sanborn Map Company maintains a 79 volume atlas of New York City geography that is widely used by New York city agencies. The atlases contain approximately 6000 maps covering all five boroughs

SANITATION BULK ITEMS PICKUP

Functions: 1/1E, 1/1E Extended, 1B

Work Area Format: COW

Length and Format: 5 bytes

Description: This field contains the schedule for the Department of Sanitation (DSNY) pilot program of scheduled Bulk Items Pickup. Release 16D includes the implementation of scheduled collection of disposed Bulk Items for specific locations across the City (previously, disposed bulk items were collected in these areas on regular refuse collection. This field indicates which days of the week the Department of Sanitation will pick up recycling at the given address. See SANITATION ORGANICS RECYCLING PICKUP for the codes.

SANITATION COLLECTION SCHEDULING SECTION AND SUBSECTION

Functions: 1, 1E, 1B (COW only), 2 (COW only??)

Work Area Format: MSW and COW

Length and Format: 2 bytes

Description: District Sections and Subsections defined by the Department of Sanitation for waste collection.

SANITATION DISTRICT

Work Area Format: MSW and COW

Length and Format: 3 bytes. Numeric. The first byte is the Borough Code, and the second and third bytes are the District Number.

Description: Districts defined by the Department of Sanitation for waste collection.

SANITATION ORGANICS RECYCLING PICKUP

Functions: 1, 1E, 1/1E Extended, 1B

Work Area Format: COW

Length and Format: 5 bytes

Description: Indicates which days of the week the Department of Sanitation (DSNY) will pick up organics (compostable waste) recycling at the given address. Organics recycling is currently only available in pilot areas. In Release 16D, the pilot program was expanded to include more 'Large Buildings (+10 units)' (as defined by DSNY)

Value	Description
M	Monday
T	Tuesday
W	Wednesday
TH	Thursday
F	Friday
S	Saturday
E	'E' is used in combination with a day of the week (as noted above) to indicate that collection occurs 'every' week on that day.
Z	Recycling is collected privately

SANITATION RECYCLING PICKUP

Functions: 1, 1E, 1B (COW only)??

Work Area Format: MSW and COW

Length and Format: 3 bytes

Description: Indicates which days of the week the Department of Sanitation will pick up recycling at the given address. See SANITATION ORGANICS RECYCLING PICKUP for the codes.

SANITATION REGULAR PICKUP

Functions: 1, 1E, 1B (COW only)

Work Area

Format: MSW and COW

Length and Format: 5 bytes

Description: Indicates which days of the week the Department of Sanitation will pick up non-recycling waste at the given address. See SANITATION ORGANICS RECYCLING PICKUP for the codes.

SCHOOL DISTRICT (previously known as Community School District)

Functions: 1, 1E, 2, 3, 3C, 1B (COW)

Work Area Format: MSW and COW

Length and Format: 2 bytes

Description: School district code

SEGMENT AZIMUTH

Functions: 3, 3C

Work Area Format: MSW and COW

Length and Format: 3 bytes

Description: This item represents the direction in which the segment lies on the earth's surface, expressed as an angle in degrees measured counterclockwise from due east. The segment is considered to be pointing in the direction of increasing addresses, and the azimuth value can range from 0 to 359 degrees, inclusive. For example, a segment pointing due east has an azimuth of 0; one pointing due north has an azimuth of 90; one pointing due west has an azimuth of 180; one pointing halfway between due west and due south (i.e., pointing due southwest) has an azimuth of 225.

SEGMENT ID

Functions: 1 and 1E (MSW: Long WA2 only), 1 and 1E (COW), 3, 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 7 bytes. RJZF

Description: Identifies, uniquely within the entire city, a geographic feature segment represented in the CSCL/LION file.

SEGMENT LENGTH IN FEET

Functions: 1, 1E, 3, 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: MSW: Fns 1 and 1E - 5 bytes numeric, Fns 3 and 3C - 3 bytes packed decimal
COW: Fns 1, 1E, 3, 3C - 5 bytes numeric

Description: Except for curved segments **(see Curve Flag)**, the Segment Length is computed from the **Spatial Coordinates** of the segment's endpoints, as digitized in the

LION file. For curved segments, the Segment Length is computed by summing the lengths of the small straight line segments that approximate the curve in the GIS version of LION; this is a more accurate approximation to the true arc length of the curve than would be the segment's 'secant length', that is, the straight line distance between the curve's extreme endpoints. In the case of Functions 3 and 3C, if the input data define a street stretch encompassing more than one segment (because of a T-intersection or bend), the Segment Length returned is the sum of the lengths of the constituent segments of the stretch. Similarly for Functions 1 and 1E, if the input lies on a segment that is generated from multiple segments, the Segment Length returned is the sum of the lengths of the constituent segments. In all cases, the Segment Length has a very approximate level of accuracy only, and should not be used in applications requiring high precision.

SEGMENT ORIENTATION

Functions: 3, 3C

Work Area Format: MSW and COW

Length and Format: 1 byte character

Description: This item is a set of codes grouping the possible azimuth values of a segment into eight categories. The categories are "approximately" due north, south, east and west, and the four quadrants of the rectangular coordinate system for segments that do not lie approximately due north, south, east or west. "Approximately" as used here means "within 5 degrees". In Manhattan, all orientation codes are defined with a 30−degree clockwise shift (i.e., 30 is subtracted from the azimuth value) in order to conform to the conventional concept that the midtown streets and avenues lie due east−west and due north−south, respectively. For example, "approximately due north" means "within 5 degrees of due north"; for the boroughs other than Manhattan, this corresponds to the range of azimuth values from 85 to 95; in Manhattan, the corresponding azimuth value range is 55 to 65. There is a ninth orientation category, with a code value of 'U', meaning Geosupport could not determine the segment's orientation because of a problem with the segment's **Spatial Coordinates**. All occurrences of an orientation code of 'U' should be reported to Geographic Systems Section staff.

Code Value	Meaning	Manhattan	Other Boroughs
U	Orientation is undefined		
E	Approximately due east	325-335	0-5 and 355-359
1	First quadrant, i.e. northeasterly	336-359 and 0-54	6-84
N	Approximately due north	55-65	85-95
2	Second quadrant, i.e. northwesterly	66-144	96-174
W	Approximately due west	145-155	175-185
3	Third quadrant, i.e. southwesterly	156-234	186-264

S	Approximately due south	235-245	265-275
4	Fourth quadrant, i.e. southeasterly	246-324	276-354

SEGMENT TYPE CODE

Functions: 1, 1E, 3, 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: Indicates type of segment

Code Value	Meaning
'U'	Undivided
'G'	Generic
'B'	Both Generic and Roadbed
'R'	Roadbed
'C'	Connector
'E'	Exit/Entrance Ramp
'T'	Terminator
'F'	Faux segment (used when a street or ramp physically ends at a roadbed, but connectivity needs to be maintained with the generic segment.)

SEQUENCE NUMBER

Functions: 1, 1E, 3, 3C, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 5 bytes

Description: Identifies a CSCL/LION record uniquely within Face Code. Generally,Sequence Numbers are assigned in the geographic order in which the corresponding segments occur along the geographic feature identified by the given face code. The Borough Code, Face Code and Sequence Number concatenated form the LION key, which serves as a unique identifier for one CSCL/LION record.

SIDE OF STREET INDICATOR

Functions: 1, 1E, 1A - regular WA2, 3C

Work Area Format: MSW and COW

Length and Format: 1 byte character

Description: This field indicates on which side of the street, left or right, the blockface containing the input address lies. Left and right are defined with respect to the direction of increasing addresses along the 'on' street.

Code

Value	Meaning
L	Block face is on left side of street with respect to direction of increasing address
R	Generic

SNOW PRIORITY - See DSNY SNOW PRIORITY

SPATIAL COORDINATES (See also SPATIAL COORDINATES OF TAX LOT CENTROID)

Functions:	1, 1B (blockface information), 1E, 2, 3 Extended, 3C Extended, AP (For Function 1A, BL, BN, 1B (property level information) see also SPATIAL COORDINATES OF TAX LOT CENTROID)
Work Area Format:	MSW and COW
Length and Format:	Spatial coordinates consist of two fields, an X Coordinate and a Y Coordinate, each 7 bytes RJZF.
Description:	Spatial coordinates are a pair of numbers that specify a location on the earth's surface. Geosupport returns spatial coordinates for an input address (Functions 1, 1B (blockface information), 1E, and AP), intersection (Function 2), and nodes at the end of a blockface (Functions 3 Extended and 3C Extended). Spatial coordinates are often used in conjunction with separate computer mapping and Geographic Information System (GIS) software to generate maps and for spatial analysis, although the Geosupport System does not itself provide users with such capabilities. **Note: For Functions 1, 1B (blockface information) and 1E, the spatial coordinates that Geosupport returns are imprecise approximations of real-world locations, and are not appropriate for use in applications that require a high level of spatial accuracy.** Spatial coordinates are expressed various geodetic coordinate systems, of which latitude/longitude is a well-known example. The coordinate system that Geosupport uses is known as the State Plane Coordinate (SPC) system. The SPC system is based upon the fact that, in a small enough geographic area, the earth's surface can be assumed to be flat without introducing a significant error. In the SPC system, each state of the U.S. is subdivided into zones small enough to model as planar areas. In each SPC zone, a Cartesian coordinate system is established, with the X and Y coordinate axes oriented due east and due north, respectively, and the origin selected to be a point well to the southwest of the entire zone. (The origin is so selected to insure that the X and Y coordinates of all points within the zone are positive values.) The SPC zone that New York City is in, and which Geosupport uses, is called the New York-Long Island zone, NAD 83. In the SPC system, one unit of X or Y represents one foot of distance on the ground. A major advantage of the SPC system over other map projection systems is the ease of calculating the distance between two points.

In the case of Functions 1, 1B (blockface information) and 1E, if the street segment on which the input address lies is a straight line segment or an arc of a circle, Geosupport computes and returns output spatial coordinates using a complex algorithm, a detailed description of which is beyond the scope of this document. If, however, the input address lies on a irregularly curved geographic feature (see **Curve Flag**), Functions 1, 1B (blockface information), and 1E return blanks in the spatial coordinate fields.

Functions 1, 1B (blockface information), and 1E's spatial coordinates algorithm produces a point position based on how the input address is prorated with respect to the administrative address range allocated to the entire blockface. In addition, the computed point is positioned slightly set off from the segment, on the side of the street where the input address is located. This offset is graphically desirable and also insures that the point will fall within the interiors of the proper political and administrative district boundary polygons for the given address. The computed point is a rough approximation to the location of the input address, intended to be used only for thematic mapping and other purposes that do not require a high level of spatial accuracy.

The spatial coordinates returned by Functions 1/1E/1B (blockface information) for NAPs and Vanity Addresses (see Chapter V.9) were an estimate calculated by Geosupport. As of Version 11.2, Geosupport will use the **Citywide Street Centerline file (CSCL)** X-Y Coordinates. The CSCL information guarantees that the X-Y coordinates fall within the actual location of the NAP or Vanity Address.

In the case of Function 2, the spatial coordinates returned are those of the LION node that corresponds to the input street intersection. Those coordinates represent an approximate center point of the intersection.

In the case of Function 3 Extended and Function 3C Extended, the spatial coordinates returned are those of the nodes at the end of the blockface. Those coordinates represent an approximate center point of the intersection.

In the case of Function AP, the spatial coordinates returned are those of the Address Point which is within 5 feet of the entrance(s) of the building.

In the case of Functions 1A, BL, BN, 1B (property level information),the spatial coordinates returned are those of the Tax Lot Centroid. See SPATIAL COORDINATES OF THE TAX LOT CENTROID

SPATIAL COORDINATES OF THE TAX LOT CENTROID

Functions:	1A, BL, BN, 1B (COW only)
Work Area Format:	MSW and COW
Length and Format:	Spatial coordinates consist of two fields, an X Coordinate and a Y Coordinate, each 7 bytes RJZF.
Description:	Note: Internal Label Points and Annotation Points are no longer used They are replaced by Tax Lot Centroid. The Tax Lot Centroid is created in ESRI's ArcGIS software using the Department of Finance's Digital Tax Map (DTM). The coordinates associated with the Tax

Lot Centroid are guaranteed to be within the property, unlike the coordinates returned by either Function 1 or Function 1E, where the Spatial Coordinates are an approximation based in the address range of the particular street the address is on. In addition, the Function 1/1E Spatial Coordinates always fall in the street bed and not within a tax lot, and most likely will not be adjacent to the tax lot the address is in. Additionally, when using Function 1A, the same coordinates will be returned no matter which of a tax lot's addresses is used as input. There are a few properties which do not have a Tax Lot Centroid; consequently, no coordinates will be returned for these properties.

See SPATIAL COORDINATES for a description of the coordinate system (SPC) used by Geosupport.

SPECIAL ADDRESS GENERATED RECORD FLAG (a.k.a. SAF FLAG or SPECIAL ADDRESS FLAG)

Functions: 1, 1E, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 1 byte character

Description: A non-blank value in this flag indicates one of a variety of special addressing situations.

Code Value	Meaning
'A'	The address range returned in this work area is alternative to the address range that is stored in LION for this blockface. This case arises most commonly when the input address is an old (superseded) address on a blockface on which the buildings were re-numbered at some time in the past. For such an input address, the address range returned in this work area is the old address range, whereas the current address range is stored in LION. Another situation in which this flag is 'A' is when the given street segment has continuous parity address ranges on both sides of the street, such as when buildings are numbered consecutively around the arc of a cul-de-sac.
'B'	The input street name or five-digit street code is different from that stored in LION for this blockface. This case arises when two street names having different B5SCs are both valid along a street or portion of a street. These are situations in which treating the two street names as aliases would result in an address range overlap.
'C'	The input address pertains to Ruby Street, a street along the Brooklyn-Queens border that has a unique addressing situation. See ChapterV.8.
'D'	The input address involves a duplicate address situation. See Chapter V.6.
'E'	The input address is in one of the neighborhoods in which the name of the neighborhood can serve as an alternative street name for the streets in that neighborhood. Two Bronx neighborhoods, Edgewater Park and Harding

	Park, have this characteristic.
‘G’	The input name or street code corresponds to a non-addressable place name of a complex. A complex is a geographic feature that contains constituent entities that are separately geographically identifiable. Typical examples of complexes include airports, housing projects and university and hospital campuses. See Chapter III.6.
‘N’	The input name or street code corresponds to a non-addressable place name of a ‘stand-alone’ geographic feature (a geographic feature that is neither a complex nor a constituent entity of a complex). Typical examples are individual named buildings, such as Empire State Building, Shea Stadium, Carnegie Hall. See Chapter III.6.
‘O’	The blockface contains out-of-sequence and/or opposite-parity addresses. An out-of-sequence address contains a house number that is out of sequence with those of the immediately adjacent buildings. An opposite-parity address contains a house number that is of the opposite parity to the predominant parity on the blockface. See Chapter V.10.
‘P’	The input address contains an addressable place name. Example: 2 Penn Plaza. See Chapter III.6.
‘S’	The input address contains a house number suffix and is either the first or last address on this blockface.
‘V’	The input address is a ‘vanity address’, that is, an address in which the street name refers to a different street than the one on which the referenced building entrance is actually located. See Chapter V.9.
‘X’	The input data specify a non-addressable place name of a constituent entity of a complex. Examples: AVERY FISHER HALL and NEW YORK STATE THEATER are names of constituent entities of the complex LINCOLN CENTER. See Chapter III.6

SPEED LIMIT

Function:	1/1E Extended, 1B, 3/3C Extended
Work Area Format:	COW
Length and Format:	2 bytes, blank if no data.
Description:	The Speed Limit field contains the speed limit, in miles per hour, of the paved area of the input location.

Speed Limit data was provided by the NYC Department of Transportation and currently does not cover the entire city. Additional data will be made available in future releases.

SPLIT ELECTION DISTRICT FLAG

Function:	1E, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 1 byte

Description:

Code Value	Meaning
'S'	Block face is split among two or more election districts
blank	Block face lies entirely within an election district

STATE SENATORIAL DISTRICT

Function:	1E, 1B (COW only), 2 (COW only)
Work Area Format:	MSW and COW
Length and Format:	2 bytes. Numeric.
Description:	A district of the upper house of the New York State legislature. Consists of an aggregation of Election Districts/td>

STREET ATTRIBUTE INDICATOR (a.k.a. ATTRIBUTE BYTE)

Functions:	WA1 output field - 1, 1A, 1B, 1E, 1N, AP, D, DG, DN
Work Area Format:	MSW and COW
Length and Format:	1 byte character
Description:	Indicates certain characteristics of selected streets

Code Value	Meaning
'A'	Address Place Name
'B'	Name of bridge
'C'	Building Improvement District (BID)
'D'	Duplicate Address Pseudo-Street Name (DAPS)
'E'	Input street is entirely in Edgewater Park (a Bronx neighborhood that has special addressing characteristics).
'F'	Input street is partly in Edgewater Park and partly outside of it.
'G'	NAP of a complex.
'H'	All house numbers on input street are hyphenated.
'I'	Intersection Name
'J'	Non-physical Boundary Feature
'M'	House numbers on input street are of mixed hyphenation, i.e., some are hyphenated and some are not.
'N'	Input street is a Non-Addressable Place Name (NAP)
'O'	Shore Line
'P'	Pseudo-street name
'R'	Rail Line
'S'	Front-Truncated Street Name

'T'	Tunnel
'U'	Misc. structure
'X'	NAP Of a Constituent Entity of a Complex
'Z'	Exit or Entrance Rampse
Blank	None of the above. In particular, all addresses on the input street are un-hyphenated

STREET NAME NORMALIZATION FORMAT FLAG

Functions: 1, 1A, 1E, 1N, 2, 3, 3C, 3S, D, DG, DN, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 1 byte.

Description: Specifies the format in which Geosupport is to return output normalized street names. The default is to return street names in the sort format.

Code Value	Meaning
blank	Return normalized street names in the sort format
'C'	Return normalized street names in the compact format
'S'	Return normalized street names in the sort format

STREET NAME NORMALIZATION LENGTH LIMIT (SNL)

Functions: WA1 input item, Functions 1, 1A, 1E, 1N, 2, 3, 3C, 3S, D, DG, DN, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 2 bytes, blank or numeric, either LJBF or RJZF.

Description: Specifies the maximum length in bytes within which Geosupport is to normalize street names. The minimum and maximum permissible SNL values are 4 and 32. The default that is in effect if the application does not specify an SNL value is 32

STREET WIDTH
STREEET WIDTH MAXIMUM

Functions: 1/1E Extended, 1B, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: Street Width: 3 bytes, RJBF
Street Width Maximum, 3 bytes, RJBF

Description: The width, in feet, of the paved area of the street. Street Width contains the width at the narrowest part of the street. Street Width Maximum contains the width at the widest part of the street. If the width is consistent along the street segment then both values are identical.

T

TAX BLOCK

Functions: 1A, BL, BN, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 5 bytes

Description: See Chapter VI.2.

TAX LOT

Function: 1A, BL, BN, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 4 bytes

Description: See Chapter VI.2.

TAX LOT CENTROID - See SPACIAL COORDINATES OF THE TAX LOT CENTROID

TAX MAP SECTION

Function: 1A, BL, BN, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 2 bytes

Description: The Department of Finance real property tax maps are organized into sections; each section is organized into volumes; and each volume consists of pages. Tax Map Section values are unique within borough

TAX MAP VOLUME

Functions: 1A, BL, BN, 1B (COW only)

Work Area Format: MSW and COW

Length and Format: 2 bytes

Description: See description at **Tax Map Section**. Tax Map Volume values are unique within Tax Map Section.

TO NODE - See NODE NUMBER

TO NODE ID - See NODE NUMBER

TOTAL LANES - See NUMBER OF TOTAL LANES

TRAFFIC DIRECTION

Functions: 1/1E Extended, 1B, 3 Extended, 3C Extended

Work Area Format: COW

Length and Format: 1 byte

Description: **blank Non-street feature (or unknown if not a non-street feature)**

A	One way street, traffic flows against the segment's directionality, i.e., from the segment's TO node to the FROM node
P	Pedestrian path, non-vehicular
T	Two−way street
W	One way street, traffic flows with the segment's directionality, i.e., from the FROM node to the TO node

TRAVEL LANES - See NUMBER OF TRAVEL LANES

U

UNDERLYING B7SC OF TRUE STREET - See B7SC OF "TRUE" STREET

UNIT INFORMATION FIELDS

Field Names: UNIT INPUT
UNIT – SORT FORMAT
UNIT – TYPE
UNIT – IDENTIFIER
UNIT – DISPLAY FORMAT

Functions: 1* (COW only)

Work Area Format: COW

Length and Format: See Chapter V.15 Unit Information Feature

Description: See Chapter V.15 Unit Information Feature

USPS PREFERRED CITY NAME

Functions: 1/1E Extended, 1B

Work Area Format: COW

Length and Format: 25 bytes

Description: The USPS (United States Postal Service) Preferred City Name (e.g. Astoria, Jackson Heights) is of particular importance for Queens addresses.

For Queens, the USPS Preferred City Name is based on the ZIP code associated with the input address. Unless there is a special ZIP code, the following holds true for the other boroughs. For Manhattan, the USPS Preferred City Name is New York. For all the other boroughs, the USPS Preferred City Name is the borough name, viz. Bronx, Brooklyn, and Staten Island.

In the rare, and unexpected, instance where there is no city name available for a Queens location, then the city name will be set to a default of QUEENS and the following warning message will be issued: GRC 01, Reason Code Y:

```
ZIP NOT IN CITY NAME TABLE. GENERIC CITY NAME RETURNED.
NOTIFY DCP/GSS
```

V

VACANT LOT FLAG

Work Area Format: MSW and COW

Length and Format: 1 byte

Description:

Code Value	Meaning
'V'	Tax lot is currently vacant, i.e., it has no existing buildings
Blank	Tax lot has at least one existing building

W

WORK AREA FORMAT INDICATOR

Functions: All

Work Area Format: MSW and COW

Length and Format: 1 byte

Description: This indicator specifies which work area layouts are to be used in an API call.
Note: This indicator is also known as the Platform Indicator.

Code	Meaning
blank	The IBM mainframe specific work areas (MSWs) are used. The MSWs contain packed decimal fields. In general, these work areas are the ones described throughout this manual
'C'	The platform-independent work areas known as the Character-Only Work Areas (COWs) are used. These contain no packed decimal fields. For information on using COWs on the mainframe and the differences from the MSWs, see [Appendix 12](/appendices/appendix12/). For the work area layouts of the COWs, see [Appendix 13](/appendices/appendix13/).

X

XY COORDINATES - see SPATIAL COORDINATES

X-Y COORDINATES - see SPATIAL COORDINATES

ZIP CODE

Functions: 1, 1A, 1E, 2, 3, 3C, 1B

Work Area Format: MSW and COW

Length and Format: 5 bytes. Numeric

Description: U.S. Postal Service's 5-digit ZIP code

ZIP code may also be used as input with functions 1, 1A, 1B, and 1E to identify the borough or Duplicate Address Pseudo-Street name (DAPS).

APPENDIX 4: GEOSUPPORT RETURN CODES, REASON CODES AND MESSAGES

This appendix consists of a table listing all of the Geosupport Return Codes (GRCs), Reason Codes and Messages, and the Geosupport function(s) that can elicit each of them. The table is current as of the Geosupport software version indicated in the table heading. See Chapter II.2 for a detailed discussion of application reject handling using GRCs, Reason Codes and Messages.

In the table, an asterisk in the second byte position of a function code is a 'wildcard', signifying all function codes that begin with the character that is in the first byte position. For example, '3* ' signifies all function codes that begin with '3'(namely, as of this writing, Functions 3, 3C and 3S).

An asterisk in the second position of a function code is used as a shorthand notation to represent all function codes having the indicated value in the first position, as follows

1* = 1, 1A, 1B, 1E, 1N, AP
3* = 3, 3C, 3S
B* = BB, BF, BL, BN
D* = D, DG, DN

Typically, any function listed with an asterisk also includes the various forms of the function, e.g. Extended, Long, Auxiliary Segments etc.

GEOSUPPORT SYSTEM RETURN CODES, REASON CODES AND MESSAGES (As of Geosupport Software Version 18.4 - unchanged since V17.1)			
GRC	REASON CODE	FUNCTIONS * = wildcard	MESSAGE (LITERAL TEXT IN UPPERCASE, < Variable values in angled brackets>, [Comments in Square Brackets & Mixed Case])
00		All	[Processing was unconditionally successful-no message issued]
01	**[GRC 01s are warnings]**		
	1	1,1A,1B, 1E,AP	ADDR NUMBER ALTERED: RANGE ASSUMED. USING DIGITS BEFORE DASH ONLY ADDR NUMBER ALTERED: USING DIGITS BEFORE DASH ONLY
	2	1,1A,1B,1E,AP	ADDR NUMBER ALTERED: HYPHEN INSERTED
	3	1,1A,1B,1E,AP	ADDR NUMBER ALTERED: HYPHEN DELETED
	4	BB,BF	YOU HAVE REACHED THE < FIRST or LAST> STREET NAME IN THE BOROUGH OF < boro. name>
	5	1,1A,1B,1E	INPUT IS A COMPLEX. OUTPUT DATA MAY PERTAIN TO ONLY PART OF THE COMPLEX
	6	1,1A,1B,1E	OUTPUT STREET NAME/CODE DIFFER FROM INPUT [Browse Flag P/F/R and Ruby Street/Sapphire Street processing]
			OUTPUT STREET NAME/CODE DIFFER FROM INPUT.

7	1,1A,1B,1E	ADDR NUMBER ALTERED: RANGE ASSUMED OUTPUT STREET NAME/CODE DIFFER FROM INPUT. ADDR NUMBER ALTERED: HYPHEN INSERTED OUTPUT STREET NAME/CODE DIFFER FROM INPUT. ADDR NUMBER ALTERED: HYPHEN DELETED
8	1A,1B	INPUT ADDRESS IS A PSEUDO-ADDRESS
9	1A,1B	INPUT ADDRESS IS PSEUDO-ADDRESS. ADDR NUMBER ALTERED: ADDRESS RANGE ASSUMED INPUT ADDRESS IS PSEUDO-ADDRESS. ADDR NUMBER ALTERED: HYPHEN INSERTED INPUT ADDRESS IS PSEUDO-ADDRESS. ADDR NUMBER ALTERED: HYPHEN DELETED
A	1A,1B,BL	LOT HAS MORE ITEMS THAN LISTED
B	1A,1B	LOT HAS MORE ITEMS THAN LISTED. ADDR NUMBER ALTERED: ADDR RANGE ASSUMED LOT HAS MORE ITEMS THAN LISTED. ADDR NUMBER ALTERED: HYPHEN INSERTED LOT HAS MORE ITEMS THAN LISTED. ADDR NUMBER ALTERED: HYPHEN DELETED
C	1,1A,1B,1E,2,3*	IN MARBLE HILL – LEGAL BORO IS MANHATTAN IN MARBLE HILL - LEGAL BORO IS MANHATTAN. ADDR NUMBER ALTERED: RANGE ASSUMED IN MARBLE HILL - LEGAL BORO IS MANHATTAN. ADDR NUMBER ALTERED: HYPHEN INSERTED IN MARBLE HILL - LEGAL BORO IS MANHATTAN. ADDR NUMBER ALTERED: HYPHEN DELETED ON RIKERS ISL - LEGAL BORO IS THE BRONX ON RIKERS ISL - LEGAL BORO IS THE BRONX. ADDR NUMBER ALTERED: RANGE ASSUMED ON RIKERS ISL - LEGAL BORO IS THE BRONX. ADDR NUMBER ALTERED: HYPHEN INSERTED ON RIKERS ISL - LEGAL BORO IS THE BRONX. ADDR NUMBER ALTERED: HYPHEN DELETED
D	1*,2,3*,AP	PARTIAL STREET NAME USED TO MEET SNL REQUIREMENT
E	1B,1E	OUTPUT ADDRESS RANGE IS SPLIT BY ELECTION DISTRICT BOUNDARY
F	BN	THIS BIN IS TEMPORARY AND WILL BE REPLACED IN THE FUTURE
G	1,1A,1B,1E	ADDR NUMBER ALTERED: RANGE ASSUMED. NOTE: INCONSISTENT ODD/EVEN ADDR RANGE
H	2,3S	THESE STREETS INTERSECT ONCE-COMPASS DIRECTION IGNORED
I	1,1A,1B,1E	INPUT IS NON-ADDRESSABLE PLACE NAME (NAP) - ADDRESS NUMBER IGNORED INPUT IS NAP WITH INVALID ADDRESS NUMBER. ADDRESS NUMBER IGNORED
		< Full street name including EAST or WEST as first word>

J[not implemented]	1,1A,1B,1E,2,3*	ASSUMED [An input Bronx or Manhattan street name is missing EAST or WEST as its first word, and the intended full street name is unambiguous]
J(cont.)	2,3*	< Full street name> AND ASSUMED [Two input Bronx or Manhattan street names are missing EAST or WEST as their first words, and the intended names are unambiguous]
	3*	< ALL THREE STREET NAMES ASSUMED [Three input Bronx or Manhattan street names are missing EAST or WEST as their first words, and the intended names are unambiguous]
K	1,1A,1B,1E,AP	EMBEDDED BLANK IN ADDRESS NUMBER HAS BEEN REPLACED WITH A HYPHEN
L or R	3,3C	< LEFT or RIGHT> SIDE OF SEGMENT IS IN < BROOKLYN or QUEENS> or < LEFT or RIGHT> SIDE OF SEGMENT IS IN < NASSAU or WESTCHESTER> - NO INFO RETURNED FOR THAT SIDE
M	1,1A,1B,1E	INPUT ADDRESS NUMBER IS ZERO
N	1,1A,1B,1E, 2,3* ,D*	STREET NAME(S) AND STREET CODE(S) BOTH SPECIFIED AS INPUT - < CODE(S) or NAMES> IGNORED
O	1,1A,1B,1E	CAUTION: < BLOCK FACE or ADDRESS RANGE> CONTAINS OUT-OF-SEQUENCE AND/OR OPPOSITE PARITY ADDRESSES
P	1,1B,1E	IRREGULARLY CURVED STREET SEGMENT - SPATIAL COORDINATES RETURNED AS BLANKS
Q	3	THESE STREETS INVOLVE A ‘DOGLEG’ - SHORTEST STRETCH PROVIDED
S	1,1A,1B,1E,AP	< HNI or HNS> AND DISPLAY ADDRESS NUMBER BOTH SPECIFIED AS INPUT- < HNI or HNS> IGNORED
T	2	NON-INTERSECTION NAME IGNORED
U	3	STRETCH HAS MORE ITEMS THAN LISTED
V	1,1B,1E	< Normalized input address number> < Norm’d input street name> IS ON < LEFT or RIGHT> SIDE OF < True street name> [This warning is issued for vanity addresses, addressable place names, NAPs other than complexes (for which an underlying address is not available), and certain alternative addresses known as type ‘B’ addresses.] or < Address number> < True street name> IS THE UNDERLYING ADDRESS OF < Normalized input NAP> [This warning is issued for NAPs other than complexes, for which an underlying address is available.]
W	1,1A,1B, 1E,AP,2,3*	INPUT STREET NAME HAS BEEN MODIFIED [a. MSW: Extraneous data were deleted from the end of a free-form address. COW: Same as MSW above, except that, in addition, the first 14 bytes of the extraneous data on a free-form address were

			processed as if they were in the UNIT input field (if there was no other data in the Unit input field).] [b. Neighborhood name was deleted from Duplicate Address Pseudo-Street Name (DAPS) for Functions 2, 3* .]
	X	1E,1B	THERE ARE NO POLITICAL DISTRICTS ASSIGNED TO THIS LOCATION
	Y	1/1E Ext 1B COW Only	ZIP NOT IN CITY NAME TABLE. GENERIC CITY NAME RETURNED. NOTIFY DCP/GSS
	Z	1A,1B,BL,BN	A BILLING BBL HAS NOT YET BEEN ASSIGNED TO THIS CONDOMINIUM
	$	1* COW Only	UNIT IDENTIFIER HAS BEEN TRUNCATED [This warning is generated only when the Unit Input field is used.]
	*	1A,1B BL,BN COW Only	TPAD Warning will appear in message field. [See list of TPAD Warning messages and Reason Code Qualifiers /TPAD Conflict Flag after this table.]
[GRCs greater than 01 are rejects or errors]			
02		2	STREETS INTERSECT TWICE- < number of feet> FT BETWEEN INTERSECTIONS. COMPASS DIRECTION REQ'D
03	BLANK	2 MSW Only	STREETS INTERSECT MORE THAN TWICE-CAN ONLY BE PROCESSED BY COW FUNCTION CALL [Reason Code value is blank]
	A	2 COW Only	STREETS INTERSECT MORE THAN TWICE–USE FUNCTION 2W TO FIND RELATED NODES
	B	2 COW Only	STREETS INTERSECT MORE THAN TWICE – USE NODE AS INPUT
04		1A,BL MSW Only	1A/BL VERSION SWITCH INVALID - MUST BE S. ONLY STANDARD IS SUPPORTED
05		3S	FOR FUNCTION 3S, ONLY FIRST BOROUGH CODE IS PERMITTED
07		1,1A,1B,1E	FOR A NAME OF A COMPLEX, 5-DIGIT STREET CODE INPUT IS NOT PERMITTED
08		All but B*	INVALID STREET NAME NORMALIZATION FORMAT FLAG - MUST BE BLANK, C OR S
09		3C	< Compass direction> SIDE OF STREET SEGMENT IS NOT IN < borough name>
10		All but B*	INVALID SNL VALUE - MUST BE BETWEEN 4 AND 32 INCLUSIVE
11	0	1* ,2,3* , AP	NOT RECOGNIZED. THERE ARE NO SIMILAR NAMES
12		2	INTERSECTION NAME NOT FOUND
13	1	1,1A,1B,1E,AP	ADDRESS NBR < value> CONTAINS AN INVALID CHARACTER < character> IN POSITION < position number>
	2	1,1A,1B,1E,AP	ADDRESS NBR < value> HAS MORE THAN 3 DIGITS AFTER DASH
	3	1,1A,1B,1E,AP	ADDRESS NBR < value> HAS TOO MANY DASHES
	4	1,1A,1B,1E,AP	ADDRESS NBR < value> HAS NO DIGITS AFTER THE DASH
	6	1,1A,1B,1E,AP	ADDRESS NBR HAS TOO MANY DIGITS (MORE THAN 5)

	7	1,1A,1B,1E,AP	ADDRESS NBR < value> IS NOT COMPLETE AS ENTERED
	8	1,1A,1B,1E,AP	ADDRESS NBR < value> PORTION AFTER HYPHEN EXCEEDS ALLOWABLE MAXIMUM
	9	1,1A,1B,1E,AP,D*	ADDRESS NBR < hse nr value> INVALID INTERNAL FORMAT
	A	1,1A,1B,1E,AP,D*	ADDRESS NBR < value> HAS AN UNKNOWN OR INVALID SUFFIX/ENDING
	B	1,1A,1B,1E,AP	INPUT CONTAINS NO ADDRESS NUMBER
	C	1,1A,1B,1E,AP	ADDRESS NBR < value> HAS AN EMBEDDED BLANK
	D	1,1A,1B,1E,AP	ADDRESS NBR HAS INVALID FORMAT FOR EDGEWATER PARK
	E	1,1A,1B,1E,AP	THIS STREET HAS HYPHENATED ADDRESS NBRS ONLY. TRY < address nbr with hyphen ins erted to left of last two digits> OR < address nbr with hyphen inserted to left of last three digits>
	F	1,1A,1B,1E,AP	THIS STREET HAS UNHYPHENATED ADDRESS NBRS ONLY. TRY < digits of address number to left of dash only> OR < digits to left and right of dash concatenated without the dash>
	G	1,1A,1B,1E,AP	ADDRESS NUMBER HAS INVALID HYPHENATION FOR THIS STREET [Input address number is an unhyphenated 2-digit number, but the input street has hyphenated address numbers only.]
14	BLANK	3S	INPUT DOES NOT DEFINE A STREET STRETCH, SINCE INPUT INTERSECTIONS ARE IDENTICAL
	A	3S	INPUT DOES NOT DEFINE A STREET STRETCH [e.g. On-street has a different 5-digit street code than the underlying street]
15		All but B*	STREET NAME CANNOT BE NORMALIZED
16		1* ,AP	STREET NAME IS MISSING
17		All	BOROUGH CODE IS MISSING
18		BL	TAX BLOCK NOT NUMERIC
19		BL	TAX LOT NOT NUMERIC
20		BN	BUILDING IDENTIFICATION NUMBER (BIN) IS MISSING
21		BN	BUILDING IDENTIFICATION NUMBER (BIN) NOT FOUND
22		BN	INVALID BIN FORMAT: NON-NUMERIC, FIRST DIGIT NOT 1-5 OR REST OF DIGITS ALL ZERO
23		BN	TEMPORARY DEPARTMENT OF BUILDINGS BIN: EXISTS ONLY IN D.O.B FILES
24		3*	ON STREET IS MISSING
25		2,3*	CROSS STREET 1 IS MISSING
26		2,3*	CROSS STREET 2 IS MISSING
27		All	INVALID WORK AREA FORMAT INDICATOR - MUST BE C OR BLANK
28		1,1A,1B,1E,AP	A PARTIAL STREET NAME MAY NOT BE USED IN A FREE-FORM ADDRESS
29		1,1A,1B,1E,AP,3*	INTERSECTION < INTERSECTION NAME> MAY NOT SERVE AS ON-STREET

30		2	< STREET NAME> IS NOT PART OF < INTERSECTION NAME>
31	1	1A,BL COW Only	MODE SWITCH OF X NOT VALID WITH LONG-WORK-AREA-2 SET TO L
32		2,2W COW Only	INVALID NODE – NON-NUMERIC OR EMBEDDED BLANKS FOUND
33		2,2W COW Only	ACCESS BY NODE FAILED – NODE NOT FOUND
38		3S	< Compass direction value> IS AN INVALID COMPASS DIRECTION VALUE FOR < FIRST or SECOND> INPUT INTERSECTION
39		2,3C	INVALID COMPASS DIRECTION VALUE - MUST BE N, S, E OR W
40		2,3C	COMPASS DIRECTION VALUE IS INVALID FOR THIS INPUT LOCATION
41		1,1A,1B,1E,AP	THIS STREET HAS NO ADDRESSES
42	blank	1,1A,1B,1E,AP	ADDRESS NUMBER OUT OF RANGE
	1	1,1A,1B,1E,AP	ADDRESS NUMBER OUT OF RANGE. CORRECT DIGITS OR INSERT HYPHEN AS < AB-CD> OR < A-BCD> [where input was of the form ABCD]
	2	1,1A,1B,1E,AP	ADDRESS NUMBER OUT OF RANGE. CORRECT DIGITS OR TRY < AB> OR < ABCD> [where input was of the form AB-CD]
44		3C	INPUT DOES NOT DEFINE A BLOCK FACE
45		3	INPUT DOES NOT DEFINE A STREET SEGMENT
46		3,3C	STREET COMBINATION NOT UNIQUE [The input is ambiguous, i.e., it describes more than one valid street segment.]
47		1,1A,1B,1E COW Only	INVALID HNL VALUE - MUST BE BETWEEN 12 AND 16 INCLUSIVE
48		1,1A,1B,1E COW Only	INVALID HOUSE NUMBER JUSTIFICATION VALUE - MUST BE L, R OR BLANK
49		1,1A,1B,1E COW Only	ADDRESS NUMBER CANNOT BE NORMALIZED WITHIN REQUESTED HNL
50	1 thru 4	1,1A,1B,1E,2,3* ,AP	< Input street name> IS AN INVALID STREET NAME FOR THIS LOCATION [The Reason Code indicates the number of valid street names returned in the Similar Names List.]
55		2,3 *	NON-ADDRESSABLE PLACE NAME PROCESSING IS NOT AVAILABLE FOR THIS FUNCTION
56		1E	ADDRESS IS SPLIT AMONG MULTIPLE ELECTION DISTRICTS. ADDRESS NBR SUFFIX REQUIRED [The input address is associated with more than one Election District (ED). Function 1E requires an address number suffix to be included with this address to identify a portion of the building specific to one ED.]

57		3S	INPUT INCLUDES ROADBED NAME, BUT ROADBED REQUEST SWITCH IS OFF
58		1,1A,1B,1E,AP	NON-ADDRESSABLE PLACE NAME, BRIDGE, TUNNEL OR MISC STRUCTURE NOT FOUND
59		1*,2,3*, AP	STREET NAME CANNOT BE NORMALIZED WITHIN REQUESTED SNL
61		3S	STREET STRETCH NOT FOUND
62		2,3S	< Street name> & < other street name> DO NOT INTERSECT
63	2 thru 4	2	INPUT STREET NAMES DO NOT FORM A UNIQUE INTERSECTION [Issued when there is more than one possibility for an assumed front- truncated street name (where EAST or WEST is added at the beginning of the name). Reason Code indicates the number of possible names. The possible names are returned in the List of Street Names in WA1.]
64		1,1A,1B,1E,2,3*,AP,D*	STREET CODE NOT FOUND
65		All	INVALID ROADBED REQUEST SWITCH. MUST BE R OR BLANK
66		3S	< Street name> & < other street name> INTERSECT MORE THAN TWICE-CANNOT BE PROCESSED
67	A-Z	All	ERROR ACCESSING GEOSUPPORT FILE: . NOTIFY SYSTEM SUPPORT [This can be an installation error or a system error. Notify System Support.]
68		3S	< Street name> & < other street name> INTERSECT TWICE-COMPASS DIRECTION REQ'D
69	A	3,3C COW Only	INVALID AUXSEG REQUEST SWITCH. MUST BE Y, N OR BLANK
	B	1A,1B, BL,BN COW Only	INVALID TPAD REQUEST SWITCH. MUST BE Y, N OR BLANK
	C	1,1E,1A,3,3C,AP BL,BN COW Only	INVALID MODE SWITCH VALUE. MUST BE X OR BLANK
	D	All COW Only	INVALID WTO SWITCH VALUE. MUST BE Y, N, OR BLANK
69	A	All but 3,3C COW Only	AUXSEG REQUEST SWITCH NOT VALID FOR THIS FUNCTION
	B	All but 1A,1B,BL,BN COW Only	TPAD REQUEST SWITCH NOT VALID FOR THIS FUNCTION
	C	All but 1,1E,1A,3,3C,AP,BL,BN COW Only	MODE SWITCH OF X (EXTENDED) NOT VALID FOR THIS FUNCTION
71		1,1A,1B,1E.AP	INPUT ZIP CODE IS NOT A NEW YORK CITY ZIP CODE
72		1,1A,1B,1E,AP	INPUT ZIP CODE IS NOT ALL NUMERIC
73		1A,BL MSW Only	LEGACY VERSION OF FUNCTIONS 1A AND BL IS DISCONTINUED. SEE TECH BULLETIN 05-1
74		2,3*	ADDRESSABLE PLACE NAME PROCESSING IS NOT AVAILABLE FOR THIS FUNCTION
75		1,1A,1B,1E	DUPLICATE ADDRESS-USE < pseudo-streetname1> OR <

			pseudo-streetname2>
76		All but 1,1B,1E,3S	ROADBED REQUEST SWITCH NOT IMPLEMENTED FOR THIS FUNCTION
77		BL	TAX LOT NOT FOUND
78		All COW Only	INVALID BROWSE FLAG VALUE. MUST BE P, F, R, OR BLANK
79		3S,BL,BN,D* COW Only	BROWSE FLAG NOT VALID FOR THIS REQUEST
57		3S	INPUT INCLUDES ROADBED NAME, BUT ROADBED REQUEST SWITCH IS OFF
80		1,1A,1B,1E,2,3*	BUSINESS IMPROVEMENT DISTRICT (BID) IS NOT VALID AS INPUT FOR THIS FUNCTION
88	Blank	All	GEOSUPPORT ERROR. EMAIL GSS_FEEDBACK@PLANNING.NYC.GOV AND REPORT 88- [An internal Geosupport problem, not a user error.]
	1-9,A-Z	All	GEOSUPPORT ERROR. EMAIL GSS_FEEDBACK@PLANNING.NYC.GOV AND REPORT 88- < value > ERROR [where is the reason code.] [An internal Geosupport problem, not a user error.]
89		2,3C,3S,BN	LONG WORK-AREA-2 OPTION IS INVALID FOR THIS FUNCTION
		1,1B,1E,3 COW Only	
90		1,1A,1E,3,BL	LONG WORK-AREA-2 FLAG MUST BE L OR BLANK
96		All	FUNCTIONALITY UNDER CONSTRUCTION
97		BB,BF	INPUT IS BEYOND THE LAST STREET NAME IN THE BOROUGH OF
98		All	NO INPUT DATA RECEIVED
99		All	INVALID BOROUGH CODE. MUST BE 1, 2, 3, 4 OR 5
EE	1	1*,2,3*,AP	< Street name > NOT RECOGNIZED. IS IT < similar street name >? [Issued when there is precisely one similar name.]
	2 thru 9, A	1*,2,3*,AP	< Street name > NOT RECOGNIZED. THERE ARE < number > SIMILAR NAMES [Issued when there is more than one similar name. Reason Code indicates number of similar names. Reason Code 'A' signifies 10 similar names. The similar names are returned in WA1.]
??		N/A	INVALID FUNCTION CODE
	1	1B,AP MSW Only	INVALID FUNCTION CODE- AVAILABLE IN COW FORMAT ONLY

TPAD WARNING MESSAGES and TPAD Conflict Flag / REASON CODE QUALIFIERS in ( )

"TPAD BBL USED, NO EXISTING PAD BBL"; (2)

"TPAD BBL USED, PAD PSEUDO-ADDRESS ON DIFFERENT BBL THAN TPAD NB BIN"; (3)

"TPAD BBL USED, EXISTING PAD BIN OF INPUT ADDR ON DIFF BBL THAN TPAD NB BIN"; (4)

"TPAD BBL USED, PAD BIN OF INPUT ADDR W/DM-5 ON DIFF BBL THAN TPAD NB BIN"; (6)

"TPAD BBL USED, PAD BIN OF INPUT ADDR W/DM-6 ON DIFF BBL THAN TPAD NB BIN"; (7)

"PAD BBL USED, TPAD NB BIN WITH NB-0 ON DIFFERENT BBL THAN PAD BIN"; (8)

"PAD BBL USED, TPAD NB BIN WITH NB-1 ON DIFFERENT BBL THAN PAD BIN"; (9)

"PAD BBL USED, TPAD NB BIN WITH NB-2 ON DIFFERENT BBL THAN PAD BIN"; (A)

"PAD BBL USED, TPAD NB BIN WITH NB-3 ON DIFFERENT BBL THAN PAD BIN"; (B)

"TPAD DATA FOUND, TPAD ADDRESS OVERLAPS PAD ADDRESS"; (C)

"ADDRESS FOUND IN TPAD, NOT FOUND IN PAD"; (D)

"BIN FOUND IN TPAD, NOT FOUND IN PAD"; (E)

APPENDIX 5: GEOSUPPORT COPY FILES (MSW)

This appendix contains printouts of the Geosupport MSW COPY files for COBOL, Assembler, PL/1, C and NATURAL. (For C, COPY files take the form of header files. For NATURAL, COPY files take the form of Local Data Areas.)

The Geosupport COPY files contain source code layouts of the Geosupport work areas. These files are stored in a COPY library that can be accessed by user application programs at compile time. Each supported programming language has an appropriate declarative statement for referencing COPY files at compile time. The Geosupport COPY files are listed below.

GEOSUPPORT SYSTEM COPY FILES (MSW)

			- - - - - - - - - - - - - COPY File Name - - - - - - - - - - - - - -				
MSW WORK AREA		LENGTH(bytes)	COBOL	ASSEMBLER	PL/1	C	NATURAL
WA1	All	884	W1COB	W1BAL	W1PL1	WAC	GEOLW1
WA2	1 (regular WA2), 1E (regular WA2), 2, 3 (regular WA2), 3C	200	W2COB	W2BAL	W2PL1	WAC	GEOLW2
WA2	1 (long WA2), 1E (long WA2), 3 (long WA2)	300	W2COBL	W2BALL	W2PL1L	WAC	GEOLW2L
WA2	1A&BL (regular WA2),BN (*)	939	W2COB1A	W2BAL1A	W2PL11A	WAC	GEOLW21A
WA2	1A&BL (long WA2) (**)	17,683	W2COB1AL	W2BAL1AL	W2PL11AL	WAC	GEOLW2AL
WA2	3S	4,224	W2COB3S	W2BAL3S	W2PL13S	WAC	GEOLW23S

(*) Functions 1A, BL and BN share a single regular WA2 layout.
(**) Functions 1A and BL share a single long WA2 layout. (Function BN does not have the long WA2 option.)
See Chapter VIII.4 for a detailed discussion of the Geosupport COPY feature.

COBOL COPY Files (MSW)

W1COB COPY File

```
*********************************************************************** 00000100
*****  THIS IS GEOSUPPORT SYSTEM COPY FILE W1COB, CONTAINING   ***** 00000200
*****  LAYOUT OF WORK AREA 1.        COPYLIB2       04/07/98   ***** 00000300
*********************************************************************** 00000400
*****                INPUT FIELDS                               ***** 00000500
*********************************************************************** 00000600
```

```
      05  GEO-WA1-IN-FUNCTION-CODE.                                  00000700
         10  GEO-WA1-IN-FUNCTION-1             PIC X.               00000800
         10  GEO-WA1-IN-FUNCTION-2             PIC X.               00000900
      05  GEO-WA1-IN-BORO                      PIC X.               00001000
** NOTE  GEO-WA1-IN-HOUSENUM - HIGH HSE# INPUT IF FUNC 5            00001100
      05  GEO-WA1-IN-HOUSENUM                  PIC X(12).           00001200
** NOTE  GEO-WA1-IN-HOUSENUM-INTERNAL - HIGH HSE# INPUT IF FUN5     00001300
      05  GEO-WA1-IN-HOUSENUM-INTERNAL         PIC X(6).            00001400
      05  GEO-WA1-IN-STREET-1                  PIC X(32).           00001500
      05  GEO-WA1-IN-STREET-2                  PIC X(32).           00001600
      05  GEO-WA1-IN-STREET-3                  PIC X(32).           00001700
      05  GEO-WA1-IN-COMPASS                   PIC X.               00001802
      05  GEO-WA1-IN-COMPASS2                  PIC X.               00001904
      05  GEO-WA1-IN-STREETCODE-1              PIC S9(6) COMP-3.    00002104
      05  GEO-WA1-IN-STREETCODE-2              PIC S9(6) COMP-3.    00002204
      05  GEO-WA1-IN-STREETCODE-3              PIC S9(6) COMP-3.    00002304
      05  GEO-WA1-IN-ROADBED-REQ-SWITCH        PIC X.               00002508
      05  GEO-WA1-IN-BORO-2                    PIC X.               00002604
      05  GEO-WA1-IN-BORO-3                    PIC X.               00002704
      05  GEO-WA1-IN-SNL                       PIC X(2).            00002804
      05  GEO-WA1-IN-10SC-1                    PIC X(11).           00002904
      05  GEO-WA1-IN-10SC-2                    PIC X(11).           00003004
      05  GEO-WA1-IN-10SC-3                    PIC X(11).           00003104
      05  GEO-WA1-IN-ZIPIN                     PIC X(5).            00003309
      05  GEO-WA1-IN-BBL.                                           00003404
         10  GEO-WA1-IN-BL-BORO                PIC X.               00003504
         10  GEO-WA1-IN-BLOCKNUM               PIC X(5).            00003604
         10  GEO-WA1-IN-LOTNUM                 PIC X(4).            00003704
      05  FILLER                               PIC X.               00003804
      05  GEO-WA1-IN-BIN                       PIC X(7).            00004004
*****************************************************************  00004104
** NOTE: TO REQUEST COMPACT NAMES OPTION, SET                    **  00004204
**       GEO-WA1-IN-COMPACT-NAME-FLAG TO "C".                   **  00004304
** NOTE: TO REQUEST THE LONG WORKAREA 2, SET                     **  00004404
**       GEO-WA1-IN-LONG-WORKAREA2-FLAG TO "L".  AT PRESENT,    **  00004504
**       ONLY FUNCTION 3 HAS THE LONG WA2 OPTION.               **  00004604
** NOTE: IF APPLICATION IS RUNNING ON A NON-IBM MAIN FRAME,      **  00004704
**       SET GEO-WA1-IN-NON-IBM-MAIN-FRAME EQUAL TO "X"         **  00004804
** NOTE: FOR FUNCTIONS 1A AND BL, TO REQUEST THE STANDARD        **  00004904
**       WORKAREA2 FORMAT, SET GEO-WA1-IN-1ABL-VERSION TO "S" **  00005004
** NOTE: TO REQUEST THE LEGACY WORKAREA2 FORMAT,                 **  00005104
**       SET GEO-WA1-IN-1ABL-VERSION TO " " OR "L".             **  00005204
*****************************************************************  00005704
      05  GEO-WA1-IN-COMPACT-NAME-FLAG         PIC X.               00005804
      05  GEO-WA1-IN-LONG-WORKAREA2-FLAG       PIC X.               00005904
```

```
        05  GEO-WA1-IN-LOW-HOUSENUM             PIC X(12).         00006004
        05  GEO-WA1-IN-LOW-HSENUM-INTERNAL       PIC X(6).          00006104
        05  GEO-WA1-IN-NON-IBM-MAIN-FRAME        PIC X(1).          00006204
        05  GEO-WA1-IN-1ABL-VERSION              PIC X(1).          00006304
        05  GEO-WA1-IN-XSTREET-FLAG              PIC X(1).          00006404
        05  GEO-WA1-IN-NONEED-STNAME-FLAG        PIC X(1).          00006504
        05  FILLER                               PIC X(3).          00006604
*******************************************************************00006704
*****              OUTPUT FIELDS                            *****00006804
*******************************************************************00006904
        05  GEO-WA1-OUT-LOW-HOUSENUM             PIC X(12).         00007004
        05  GEO-WA1-OUT-BORONAME                 PIC X(9).          00007104
        05  GEO-WA1-OUT-STREET-1                 PIC X(32).         00007204
        05  GEO-WA1-OUT-STREET-2                 PIC X(32).         00007304
        05  GEO-WA1-OUT-STREET-3                 PIC X(32).         00007404
        05  GEO-WA1-OUT-HOUSENUM                 PIC X(12).         00007504
        05  GEO-WA1-OUT-HOUSENUM-INTERNAL        PIC X(6).          00007604
        05  GEO-WA1-OUT-HOUSE-INT-FORMAT REDEFINES                  00007704
            GEO-WA1-OUT-HOUSENUM-INTERNAL.                         00007804
            10  GEO-WA1-OUT-HOUSE-INT-PACKED     PIC X(5).          00007904
            10  GEO-WA1-OUT-HOUSE-INT-SUFFIX     PIC X.             00008004
        05  FILLER                               PIC X(7).          00008104
        05  GEO-WA1-OUT-PB5SC-1                  PIC S9(6) COMP-3.  00008204
        05  GEO-WA1-OUT-PB-5SC-1 REDEFINES GEO-WA1-OUT-PB5SC-1.     00008304
            10  FILLER                           PIC X(1).          00008404
            10  GEO-WA1-OUT-STREETCODE-1-KEY     PIC S9(5) COMP-3.  00008504
        05  FILLER                               PIC X(2).          00008604
        05  GEO-WA1-OUT-PB5SC-2                  PIC S9(6) COMP-3.  00008704
        05  GEO-WA1-OUT-PB-5SC-2 REDEFINES GEO-WA1-OUT-PB5SC-2.     00008804
            10  FILLER                           PIC X(1).          00008904
            10  GEO-WA1-OUT-STREETCODE-2-KEY     PIC S9(5) COMP-3.  00009004
        05  FILLER                               PIC X(2).          00009104
        05  GEO-WA1-OUT-PB5SC-3                  PIC S9(6) COMP-3.  00009204
        05  GEO-WA1-OUT-PB-5SC-3 REDEFINES GEO-WA1-OUT-PB5SC-3.     00009304
            10  FILLER                           PIC X(1).          00009404
            10  GEO-WA1-OUT-STREETCODE-3-KEY     PIC S9(5) COMP-3.  00009504
        05  FILLER                               PIC X(3).          00009604
        05  GEO-WA1-BROWSE                       PIC X(40).         00009704
        05  GEO-WA1-OUT-10SC-1                   PIC X(11).         00009804
        05  GEO-WA1-OUT-10SC-2                   PIC X(11).         00009904
        05  GEO-WA1-OUT-10SC-3                   PIC X(11).         00010004
        05  GEO-WA1-OUT-CUI                      PIC X(5).          00010104
   ** NOTE: GEO-WA1-OUT-CUI       NOT IMPLEMENTED   **             00010204
        05  GEO-WA1-OUT-BBL.                                        00010304
           10  GEO-WA1-OUT-BL-BORO               PIC X.             00010404
```

```
          10  GEO-WA1-OUT-BLOCKNUM              PIC X(5).          00010504
          10  GEO-WA1-OUT-LOTNUM                PIC X(4).          00010604
      05  FILLER                                PIC X.             00010704
      05  GEO-WA1-OUT-BIN                       PIC X(7).          00010806
      05  GEO-WA1-OUT-SND-ATTR                  PIC X.             00011304
      05  GEO-WA1-OUT-REASON-CODE               PIC X.             00011404
      05  FILLER                                PIC X(2).          00011504
      05  GEO-WA1-OUT-RETURN-CODE.                                 00011604
          10  GEO-WA1-OUT-RC-1                  PIC X.             00011704
          10  GEO-WA1-OUT-RC-2                  PIC X.             00011804
      05  GEO-WA1-OUT-ERROR-MESSAGE             PIC X(80).         00011904
      05  GEO-WA1-OUT-NUM-SIMILAR-NAMES         PIC S999 COMP-3.   00012004
      05  GEO-WA1-OUT-SIMILAR-NAMES             PIC X(32)          00012104
                                                 OCCURS 10 TIMES.   00013002
```

W2COB COPY File

```
*****************************************************************  00010040
***  THIS IS GEOSUPPORT SYSTEM COPY FILE W2COB, CONTAINING THE ***  00020040
***  LAYOUT OF WORK AREA 2 FOR FUNCTIONS: 1, 1E, 2, 2C, 3, 3C, ***  00030040
***  5. PLEASE NOTE THAT FUNCTIONS 2 AND 2C SHARE A SINGLE WORK***  00040040
***  AREA 2 LAYOUT.                                 04/03/01 ***  00050040
*****************************************************************  00060040
***  LAST MODIFIED  06/08/10                                ***  00070040
*****************************************************************  00080040
      05  GEO-WA2-FUNCTION1.                                       00090040
          10  FILLER                            PIC X(21).         00100040
          10  GEO-WA2-FN1-CONT-PARITY            PIC X.             00110040
          10  GEO-WA2-FN1-LOW-HOUSENUM-INT.                         00120040
              15  GEO-WA2-FN1-LOW-HOUSENUM       PIC X(5).          00130040
              15  GEO-WA2-FN1-LOW-HOUSENUMSFX    PIC X.             00140040
                                                                    00150040
          10  GEO-WA2-FN1-HI-HOUSENUM-INT.                          00160040
              15  GEO-WA2-FN1-HI-HOUSENUM        PIC X(5).          00170040
              15  GEO-WA2-FN1-HI-HOUSENUMSFX     PIC X.             00180040
                                                                    00190040
          10  GEO-WA2-FN1-ALX                    PIC X.             00200040
          10  GEO-WA2-FN1-NUM-X-ST-LOW-END       PIC X.             00210040
          10  GEO-WA2-FN1-LOW-PBSC               PIC S9(7) COMP-3   00220040
                                                  OCCURS 5 TIMES.    00230040
          10  GEO-WA2-FN1-NUM-X-ST-HI-END        PIC X.             00240040
          10  GEO-WA2-FN1-HI-PBSC                PIC S9(7) COMP-3   00250040
                                                  OCCURS 5 TIMES.    00260040
          10  GEO-WA2-FN1-COMDIST.                                  00270040
              15  GEO-WA2-FN1-COMDIST-BORO       PIC X.             00280040
```

```
            15  GEO-WA2-FN1-COMDIST-NUMBER    PIC X(2).          00290040
        10  GEO-WA2-FN1-ZIP                   PIC X(5).          00300040
        10  GEO-WA2-FN1-SLA                   PIC X.             00310040
        10  GEO-WA2-FN1-HCD                   PIC X(2).          00320047
        10  GEO-WA2-FN1-SOS                   PIC X.             00330040
        10  GEO-WA2-FN1-CONT-PARITY-IND       PIC X.             00340040
        10  GEO-WA2-FN1-2010-CENS-TRCT        PIC X(6).          00350042
        10  GEO-WA2-FN1-2010-CENS-BLK         PIC X(4).          00360042
        10  GEO-WA2-FN1-2010-CENS-BLK-SFX     PIC X.             00370042
        10  FILLER                            PIC X(3).          00380040
        10  GEO-WA2-FN1-HEALTHAREA            PIC X(4).          00390047
        10  GEO-WA2-FN1-SANI-REC              PIC X(3).          00400040
        10  GEO-WA2-FN1-FEATURE-TYPE          PIC X.             00410040
        10  GEO-WA2-FN1-RESDCP                PIC X.             00420040
        10  GEO-WA2-FN1-CURVE-FLAG            PIC X.             00430040
        10  GEO-WA2-FN1-POLICEDIST.                              00440040
           15  GEO-WA2-FN1-POL-PATR-BORO-CMD  PIC X.             00450040
           15  GEO-WA2-FN1-POL-PRECINCT       PIC X(3).          00460040
        10  GEO-WA2-FN1-SCHOOLDIST            PIC X(2).          00470040
        10  FILLER                            PIC X(14).         00480040
        10  GEO-WA2-FN1-COINCIDENT-CNT        PIC X.             00490040
        10  GEO-WA2-FN1-SEGMENT-TYPE          PIC X.             00500040
        10  GEO-WA2-FN1-SANIDIST.                                00510040
            15  GEO-WA2-FN1-SANIDIST-BORO     PIC X.             00520040
            15  GEO-WA2-FN1-SANIDIST-NUMBER   PIC X(2).          00530040
        10  GEO-WA2-FN1-SANITATION-SUBSEC     PIC X(2).          00540040
** NOTE:10  GEO-WA2-FN1-FIRESEC ==> FIRE DIVISION **             00550040
        10  GEO-WA2-FN1-FIRESEC               PIC X(2).          00560040
        10  GEO-WA2-FN1-FIREBAT               PIC X(2).          00570040
        10  GEO-WA2-FN1-FIRECO.                                  00580040
            15  GEO-WA2-FN1-FIRECO-TYPE       PIC X.             00590040
            15  GEO-WA2-FN1-FIRECO-NUM        PIC X(3).          00600040
        10  GEO-WA2-FN1-SPECIAL-ADDR-FLAG     PIC X.             00610040
        10  GEO-WA2-FN1-MARBLE-RIKER-FLAG     PIC X.             00620040
        10  GEO-WA2-FN1-SPLIT-SCHOOL-FILL     PIC X.             00630044
        10  GEO-WA2-FN1-PREFERRED-LGC         PIC X(2).          00640040
        10  GEO-WA2-FN1-LIONFACECODE          PIC X(4).          00650040
        10  GEO-WA2-FN1-LIONSEQ               PIC X(5).          00660040
        10  GEO-WA2-FN1-1990-CENSUSTRACT      PIC X(6).          00670040
        10  FILLER                            PIC X(4).          00680040
        10  GEO-WA2-FN1-DYN-BLOCK             PIC X(3).          00690040
        10  GEO-WA2-FN1-XCOORD                PIC X(7).          00700040
        10  GEO-WA2-FN1-YCOORD                PIC X(7).          00710040
        10  GEO-WA2-FN1-SEGMENTLENGTH         PIC X(5).          00720040
        10  GEO-WA2-FN1-SANI-REG              PIC X(5).          00730040
```

```
     05  GEO-WA2-FUNCTION2   REDEFINES GEO-WA2-FUNCTION1.         00740040
        10  FILLER                            PIC X(21).          00750040
        10  GEO-WA2-FN2-DUPINTERFLAG          PIC X.              00760040
        10  FILLER                            PIC X(9).           00770040
        10  GEO-WA2-FN2-PREFERRED-LGC1        PIC X(2).           00780040
        10  GEO-WA2-FN2-PREFERRED-LGC2        PIC X(2).           00790040
        10  GEO-WA2-FN2-NUM-OF-INTERSECTS     PIC X.              00800040
        10  GEO-WA2-FN2-INTERSECT-PBSC        PIC 9(7) COMP-3     00810040
                                               OCCURS 5 TIMES.     00820040
        10  GEO-WA2-FN2-COMPDIR               PIC X.              00830040
        10  GEO-WA2-FN2-LEVEL-LIST OCCURS 5 TIMES.                00840040
            15 GEO-WA2-FN2-LEVEL-CODES                            00850040
               OCCURS 2 TIMES                  PIC X.              00860040
***     NEXT LINE WAS PREVIOUSLY INSTRUC-DIV                       00870040
        10  FILLER                            PIC X(2).           00880040
** NOTE:10  GEO-WA2-FN2-FIRESEC ==> FIRE DIVISION **               00890040
        10  GEO-WA2-FN2-FIRESEC               PIC X(2).           00900040
        10  GEO-WA2-FN2-FIREBAT               PIC X(2).           00910040
        10  GEO-WA2-FN2-FIRECO.                                   00920040
            15  GEO-WA2-FN2-FIRECO-TYPE       PIC X.              00930040
            15  GEO-WA2-FN2-FIRECO-NUM        PIC X(3).           00940040
        10  GEO-WA2-FN2-COMDIST.                                  00950040
            15  GEO-WA2-FN2-COMDIST-BORO      PIC X.              00960040
            15  GEO-WA2-FN2-COMDIST-NUMBER    PIC X(2).           00970040
        10  GEO-WA2-FN2-ZIP                   PIC X(5).           00980040
        10  GEO-WA2-FN2-SLA                   PIC X.              00990040
        10  GEO-WA2-FN2-2010-CENS-TRCT        PIC X(6).           01000042
        10  FILLER                            PIC X(3).           01010040
        10  GEO-WA2-FN2-HEALTHAREA            PIC X(4).           01020047
        10  FILLER                            PIC X(9).           01030040
        10  GEO-WA2-FN2-NODE-NUM              PIC X(7).           01040040
        10  GEO-WA2-FN2-XCOORD                PIC X(7).           01050040
        10  GEO-WA2-FN2-YCOORD                PIC X(7).           01060040
        10  FILLER                            PIC X(4).           01070040
        10  GEO-WA2-FN2-POLICEDIST.                               01080040
           15  GEO-WA2-FN2-POL-PATR-BORO-CMD  PIC X.              01090040
           15  GEO-WA2-FN2-POL-PRECINCT       PIC X(3).           01100040
        10  GEO-WA2-FN2-SCHOOLDIST            PIC X(2).           01110040
        10  GEO-WA2-FN2-MARBLE-RIKER-FLAG     PIC X.              01120040
        10  GEO-WA2-FN2-1990-CENSUSTRACT      PIC X(6).           01130040
        10  GEO-WA2-FN2-SANBORN1-BVOLPAGE.                        01140040
           15  GEO-WA2-FN2-SANBORN1-BORO      PIC X.              01150040
           15  GEO-WA2-FN2-SANBORN1-VOL-NUM   PIC X(3).           01160040
           15  GEO-WA2-FN2-SANBORN1-PAGE-NUM  PIC X(4).           01170040
        10  GEO-WA2-FN2-SANBORN2-BVOLPAGE.                        01180040
```

```
            15  GEO-WA2-FN2-SANBORN2-BORO      PIC X.              01190040
            15  GEO-WA2-FN2-SANBORN2-VOL-NUM   PIC X(3).           01200040
            15  GEO-WA2-FN2-SANBORN2-PAGE-NUM  PIC X(4).           01210040
        10  GEO-WA2-FN2-DUP-INT-DISTANCE      PIC X(5).           01220040
        10  GEO-WA2-FN2-2000-CENS-TRACT       PIC X(6).           01240043
        10  FILLER                            PIC X(27).          01250040
    05  GEO-WA2-FUNCTION3   REDEFINES GEO-WA2-FUNCTION1.          01260040
        10  FILLER                            PIC X(21).          01270040
        10  GEO-WA2-FN3-DUP-KEY-FLAG          PIC X.              01280040
        10  GEO-WA2-FN3-CURVE-FLAG            PIC X.              01290040
        10  GEO-WA2-FN3-LOCATION-STATUS       PIC X.              01300040
        10  GEO-WA2-FN3-COUNTY-BOUNDARY       PIC X.              01310040
        10  GEO-WA2-FN3-COINCIDENT-CNT        PIC X.              01320040
        10  FILLER                            PIC X(3).           01330040
        10  GEO-WA2-FN3-PREFERRED-LGC1        PIC X(2).           01340040
        10  GEO-WA2-FN3-PREFERRED-LGC2        PIC X(2).           01350040
        10  GEO-WA2-FN3-PREFERRED-LGC3        PIC X(2).           01360040
        10  GEO-WA2-FN3-NUM-X-ST-LOW-END      PIC X.              01370040
        10  GEO-WA2-FN3-LOW-PBSC              PIC S9(7) COMP-3    01380040
                                               OCCURS 5 TIMES.     01390040
        10  GEO-WA2-FN3-NUM-X-ST-HI-END       PIC X.              01400040
        10  GEO-WA2-FN3-HI-PBSC               PIC S9(7) COMP-3    01410040
                                               OCCURS 5 TIMES.     01420040
        10  GEO-WA2-FN3-SLA                   PIC X.              01430040
        10  GEO-WA2-FN3-REVERSALFLAG          PIC X.              01440040
        10  GEO-WA2-FN3-LEFT-COMDIST.                             01450040
            15  GEO-WA2-FN3-LEFT-COMDIST-BORO PIC X.              01460040
            15  GEO-WA2-FN3-LEFT-COMDIST-NUM  PIC X(2).           01470040
        10  GEO-WA2-FN3-RIGHT-COMDIST.                            01480040
            15 GEO-WA2-FN3-RIGHT-COMDIST-BORO PIC X.              01490040
            15  GEO-WA2-FN3-RIGHT-COMDIST-NUM PIC X(2).           01500040
        10  GEO-WA2-FN3-LEFT-ZIP              PIC X(5).           01510040
        10  GEO-WA2-FN3-RIGHT-ZIP             PIC X(5).           01520040
        10  FILLER                            PIC X(18).          01530040
        10  GEO-WA2-FN3-LEFT-HEALTHAREA       PIC X(4).           01540047
        10  GEO-WA2-FN3-RIGHT-HEALTHAREA      PIC X(4).           01550047
***     NEXT LINE WAS PREVIOUSLY LEFT-INSTRUC-DIV                  01560040
        10  FILLER                            PIC X(2).           01570040
***     NEXT LINE WAS PREVIOUSLY RIGHT-INSTRUC-DIV                 01580040
        10  FILLER                            PIC X(2).           01590040
        10  GEO-WA2-FN3-LEFT-LOW-HOUSENUM     PIC X(7).           01600040
        10  GEO-WA2-FN3-LEFT-HI-HOUSENUM      PIC X(7).           01610040
        10  GEO-WA2-FN3-RIGHT-LOW-HOUSENUM    PIC X(7).           01620040
        10  GEO-WA2-FN3-RIGHT-HI-HOUSENUM     PIC X(7).           01630040
        10  GEO-WA2-FN3-CONT-PARITY-IND       PIC X.              01640040
```

```
    10  GEO-WA2-FN3-LIONFACECODE          PIC X(4).           01650040
    10  GEO-WA2-FN3-LIONSEQ               PIC X(5).           01660040
    10  GEO-WA2-FN3-GENRECFLAG            PIC X.              01670040
    10  GEO-WA2-FN3-SEGMENTLENGTH         PIC S9(5) COMP-3.   01680040
    10  GEO-WA2-FN3-SEGMENTSLOPE          PIC X(3).           01690040
    10  GEO-WA2-FN3-SEGMENTORIENT         PIC X.              01700040
    10  FILLER                            PIC X(4).           01710040
    10  GEO-WA2-FN3-RESDCP                PIC X(2).           01720040
    10  GEO-WA2-FN3-DOG-LEG               PIC X.              01730040
    10  GEO-WA2-FN3-FEATURE-TYPE          PIC X.              01740040
    10  GEO-WA2-FN3-LEFT-POLDIST.                             01750040
       15  GEO-WA2-FN3-L-POL-PATR-BOR-CMD PIC X.              01760040
       15  GEO-WA2-FN3-L-POL-PRECINCT     PIC X(3).           01770040
    10  GEO-WA2-FN3-RIGHT-POLDIST.                            01780040
       15  GEO-WA2-FN3-R-POL-PATR-BOR-CMD PIC X.              01790040
       15  GEO-WA2-FN3-R-POL-PRECINCT     PIC X(3).           01800040
    10  GEO-WA2-FN3-LEFT-SCHLDIST         PIC X(2).           01810040
    10  GEO-WA2-FN3-RIGHT-SCHLDIST        PIC X(2).           01820040
    10  GEO-WA2-FN3-MARBLE-RIKER-FLAG     PIC X.              01830040
    10  GEO-WA2-FN3-SEG-ID                PIC X(7).           01840040
    10  GEO-WA2-FN3-SEGMENT-TYPE          PIC X.              01850040
 05  GEO-WA2-FUNCTION3C  REDEFINES GEO-WA2-FUNCTION1.         01860040
    10  GEO-WA2-FN3C-ACCESS-KEY           PIC X(21).          01870040
    10  GEO-WA2-FN3C-CURVE-FLAG           PIC X.              01880040
    10  GEO-WA2-FN3C-SEGMENT-TYPE         PIC X.              01890040
    10  GEO-WA2-FN3C-LOCATION-STATUS      PIC X.              01900040
    10  GEO-WA2-FN3C-COUNTY-BOUNDARY      PIC X.              01910040
    10  GEO-WA2-FN3C-COINCIDENT-CNT       PIC X.              01920040
    10  FILLER                            PIC X(3).           01930040
    10  GEO-WA2-FN3C-PREFERRED-LGC1       PIC X(2).           01940040
    10  GEO-WA2-FN3C-PREFERRED-LGC2       PIC X(2).           01950040
    10  GEO-WA2-FN3C-PREFERRED-LGC3       PIC X(2).           01960040
    10  GEO-WA2-FN3C-NUM-X-ST-LOW-END     PIC X.              01970040
    10  GEO-WA2-FN3C-LOW-PBSC             PIC S9(7) COMP-3    01980040
                                           OCCURS 5 TIMES.     01990040
    10  GEO-WA2-FN3C-NUM-X-ST-HI-END      PIC X.              02000040
    10  GEO-WA2-FN3C-HI-PBSC              PIC S9(7) COMP-3    02010040
                                           OCCURS 5 TIMES.     02020040
    10  GEO-WA2-FN3C-COMDIST.                                 02030040
        15  GEO-WA2-FN3C-COMDIST-BORO     PIC X.              02040040
        15  GEO-WA2-FN3C-COMDIST-NUMBER   PIC X(2).           02050040
    10  GEO-WA2-FN3C-ZIP                  PIC X(5).           02060040
    10  GEO-WA2-FN3C-SLA                  PIC X.              02070040
    10  GEO-WA2-FN3C-2000-CENS-TRACT      PIC X(6).           02090043
    10  FILLER                            PIC X.              02100040
```

```
        10  GEO-WA2-FN3C-2010-CENS-TRCT       PIC X(6).           02110042
        10  GEO-WA2-FN3C-2010-CENS-BLK        PIC X(4).           02120042
        10  GEO-WA2-FN3C-2010-CENS-BLK-SFX    PIC X.              02130042
        10  GEO-WA2-FN3C-HEALTHAREA           PIC X(4).           02140047
        10  GEO-WA2-FN3C-REVERSALFLAG         PIC X.              02150040
        10  GEO-WA2-FN3C-SOS                  PIC X.              02160040
** NOTE:10  GEO-WA2-FN3C-FIRESEC ==> FIRE DIVISION **             02170040
        10  GEO-WA2-FN3C-FIRESEC              PIC X(2).           02180040
        10  GEO-WA2-FN3C-FIREBAT              PIC X(2).           02190040
        10  GEO-WA2-FN3C-FIRECO.                                  02200040
            15  GEO-WA2-FN3C-FIRECO-TYPE      PIC X.              02210040
            15  GEO-WA2-FN3C-FIRECO-NUM       PIC X(3).           02220040
        10  GEO-WA2-FN3C-SEG-ID               PIC X(7).           02230040
        10  GEO-WA2-FN3C-LOW-HOUSENUM         PIC X(7).           02240040
        10  GEO-WA2-FN3C-HI-HOUSENUM          PIC X(7).           02250040
        10  GEO-WA2-FN3C-LOW-HOUSENUM2        PIC X(7).           02260040
        10  GEO-WA2-FN3C-HI-HOUSENUM2         PIC X(7).           02270040
* HOUSENUM2 ONLY PRESENT IF ODD & EVEN RANGES ARE ON             02280040
* SAME SIDE OF STREET.                                           02290040
        10  GEO-WA2-FN3C-CONT-PARITY-IND      PIC X.              02300040
        10  GEO-WA2-FN3C-LIONFACECODE         PIC X(4).           02310040
        10  GEO-WA2-FN3C-LIONSEQ              PIC X(5).           02320040
        10  GEO-WA2-FN3C-GENRECFLAG           PIC X.              02330040
        10  GEO-WA2-FN3C-SEGMENTLENGTH        PIC S9(5) COMP-3.   02340040
        10  GEO-WA2-FN3C-SEGMENTSLOPE         PIC X(3).           02350040
        10  GEO-WA2-FN3C-SEGMENTORIENT        PIC X.              02360040
***     NEXT LINE WAS PREVIOUSLY INSTRUC-DIV                       02370040
        10  FILLER                            PIC XX.             02380040
        10  GEO-WA2-FN3C-RESDCP               PIC X.              02390040
        10  GEO-WA2-FN3C-FEATURE-TYPE         PIC X.              02400040
        10  GEO-WA2-FN3C-POLICEDIST.                              02410040
           15  GEO-WA2-FN3C-POL-PATR-BORO-CMD PIC X.             02420040
           15  GEO-WA2-FN3C-POL-PRECINCT      PIC X(3).          02430040
        10  GEO-WA2-FN3C-SCHOOLDIST           PIC X(2).           02440040
        10  GEO-WA2-FN3C-MARBLE-RIKER-FLAG    PIC X.              02450040
        10  GEO-WA2-FN3C-1990-CENSUSTRACT     PIC X(6).           02460040
        10  FILLER                            PIC X(4).           02470040
        10  GEO-WA2-FN3C-DYN-BLOCK            PIC X(3).           02480040
        10  GEO-WA2-FN3C-2000-CENS-BLOCK      PIC X(4).           02500043
        10  GEO-WA2-FN3C-2000-CENS-BLK-SUF    PIC X.              02510043
     05  GEO-WA2-FUNCTION1E  REDEFINES GEO-WA2-FUNCTION1.         02520040
        10  FILLER                            PIC X(21).          02530040
        10  GEO-WA2-FN1E-CONT-PARITY          PIC X.              02540040
        10  GEO-WA2-FN1E-LOW-HOUSENUM-INT.                        02550040
            15  GEO-WA2-FN1E-LOW-HOUSENUM     PIC X(5).           02560040
```

```
    15  GEO-WA2-FN1E-LOW-HSENUMSFX    PIC X.              02570040
10  GEO-WA2-FN1E-HI-HOUSENUM-INT.                         02580040
    15  GEO-WA2-FN1E-HI-HOUSENUM      PIC X(5).           02590040
    15  GEO-WA2-FN1E-HI-HSENUMSFX     PIC X.              02600040
10  FILLER                            PIC X.              02610040
10  GEO-WA2-FN1E-NUM-X-ST-LOW-END     PIC X.              02620040
10  GEO-WA2-FN1E-LOW-PBSC             PIC S9(7) COMP-3    02630040
                                      OCCURS 5 TIMES.     02640040
10  GEO-WA2-FN1E-NUM-X-ST-HI-END      PIC X.              02650040
10  GEO-WA2-FN1E-HI-PBSC              PIC S9(7) COMP-3    02660040
                                      OCCURS 5 TIMES.     02670040
10  GEO-WA2-FN1E-COMDIST.                                 02680040
    15  GEO-WA2-FN1E-COMDIST-BORO     PIC X.              02690040
    15  GEO-WA2-FN1E-COMDIST-NUMBER   PIC X(2).           02700040
10  GEO-WA2-FN1E-ZIP                  PIC X(5).           02710040
10  GEO-WA2-FN1E-SLA                  PIC X.              02720040
10  GEO-WA2-FN1E-HCD                  PIC X(2).           02730047
10  GEO-WA2-FN1E-SOS                  PIC X.              02740040
10  GEO-WA2-FN1E-CONT-PARITY-IND      PIC X.              02750040
10  GEO-WA2-FN1E-2010-CENS-TRCT       PIC X(6).           02760042
10  GEO-WA2-FN1E-2010-CENS-BLK        PIC X(4).           02770042
10  GEO-WA2-FN1E-2010-CENS-BLK-SFX    PIC X.              02780042
10  FILLER                            PIC X(3).           02790040
10  GEO-WA2-FN1E-HEALTHAREA           PIC X(4).           02800047
10  GEO-WA2-FN1E-SANI-REC             PIC X(3).           02810040
10  GEO-WA2-FN1E-FEATURE-TYPE         PIC X.              02820040
10  GEO-WA2-FN1E-RESDCP               PIC X.              02830040
10  GEO-WA2-FN1E-CURVE-FLAG           PIC X.              02840040
10  GEO-WA2-FN1E-POLICEDIST.                              02850040
   15  GEO-WA2-FN1E-POL-PATR-BORO-CMD PIC X.              02860040
   15  GEO-WA2-FN1E-POL-PRECINCT      PIC X(3).           02870040
10  GEO-WA2-FN1E-SCHOOLDIST           PIC X(2).           02880040
10  GEO-WA2-FN1E-ELECTDIST            PIC X(3).           02890040
10  GEO-WA2-FN1E-ASSEMDIST            PIC X(2).           02900040
10  GEO-WA2-FN1E-SPLIT-ED-FLAG        PIC X.              02910040
10  GEO-WA2-FN1E-CONGDIST             PIC X(2).           02920040
10  GEO-WA2-FN1E-SENATEDIST           PIC X(2).           02930040
10  GEO-WA2-FN1E-COURTDIST            PIC X(2).           02940040
10  GEO-WA2-FN1E-COUNCILDIST          PIC X(2).           02950040
10  GEO-WA2-FN1E-COINCIDENT-CNT       PIC X.              02960040
10  FILLER                            PIC X.              02970040
10  GEO-WA2-FN1E-SANIDIST.                                02980040
    15  GEO-WA2-FN1E-SANIDIST-BORO    PIC X.              02990040
    15  GEO-WA2-FN1E-SANIDIST-NUMBER  PIC X(2).           03000040
10  GEO-WA2-FN1E-SANITATION-SUBSEC    PIC X(2).           03010040
```

```
** NOTE:10  GEO-WA2-FN1E-FIRESEC ==> FIRE DIVISION **          03020040
        10  GEO-WA2-FN1E-FIRESEC              PIC X(2).        03030040
        10  GEO-WA2-FN1E-FIREBAT              PIC X(2).        03040040
        10  GEO-WA2-FN1E-FIRECO.                               03050040
            15  GEO-WA2-FN1E-FIRECO-TYPE      PIC X.           03060040
            15  GEO-WA2-FN1E-FIRECO-NUM       PIC X(3).        03070040
        10  GEO-WA2-FN1E-SPECIAL-ADDR-FLAG    PIC X.           03080040
        10  GEO-WA2-FN1E-MARBLE-RIKER-FLAG    PIC X.           03090040
        10  GEO-WA2-FN1E-SPLIT-SCHOOL-FILL    PIC X.           03100044
        10  GEO-WA2-FN1E-PREFERRED-LGC        PIC X(2).        03110040
        10  GEO-WA2-FN1E-LIONFACECODE         PIC X(4).        03120040
        10  GEO-WA2-FN1E-LIONSEQ              PIC X(5).        03130040
        10  GEO-WA2-FN1E-1990-CENSUSTRACT     PIC X(6).        03140040
        10  FILLER                            PIC X(4).        03150040
        10  GEO-WA2-FN1E-DYN-BLOCK            PIC X(3).        03160040
        10  GEO-WA2-FN1E-XCOORD               PIC X(7).        03170040
        10  GEO-WA2-FN1E-YCOORD               PIC X(7).        03180040
        10  GEO-WA2-FN1E-SEGMENTLENGTH        PIC X(5).        03190040
        10  GEO-WA2-FN1E-SANI-REG             PIC X(5).        03200040
    05  GEO-WA2-FUNCTION5   REDEFINES GEO-WA2-FUNCTION1.       03210040
        10  GEO-WA2-FN5-ADDR-MATCHING-KEY     PIC X(28).       03220040
        10  FILLER                            PIC X(172).      03230040
```

W2COBL COPY File

```
*****************************************************************  00010021
***  THIS IS GEOSUPPORT SYSTEM COPY FILE W2COBL, CONTAINING  ***   00020021
***  THE LAYOUT OF THE OPTIONAL LONG WORK AREA 2 FOR FUNCTIONS *   00030021
***  1/1E AND 3.  THIS WORK AREA SHOULD BE USED ONLY WHEN    ***   00040021
***  FUNCTION 1/1E,3 ARE CALLED WITH THE "LONG" WORK AREA2   ***   00050021
***                                  APRIL 3 2001        ***      00060021
*****************************************************************  00070021
***                    LAST MODIFIED    06/08/10            ***   00080021
*****************************************************************  00090021
      05  GEO-WA2-1L-FUNCTION1.                                    00100021
        10  FILLER                          PIC X(21).           00110021
        10  GEO-WA2-1L-CONT-PARITY           PIC X.               00120021
        10  GEO-WA2-1L-LOW-HOUSENUM-INT.                          00130021
           15  GEO-WA2-1L-LOW-HOUSENUM       PIC X(5).            00140021
           15  GEO-WA2-1L-LOW-HOUSENUMSFX    PIC X.               00150021
        10  GEO-WA2-1L-HI-HOUSENUM-INT.                           00160021
           15  GEO-WA2-1L-HI-HOUSENUM        PIC X(5).            00170021
           15  GEO-WA2-1L-HI-HOUSENUMSFX     PIC X.               00180021
        10  GEO-WA2-1L-ALX                   PIC X.               00190021
        10  GEO-WA2-1L-NUM-X-ST-LOW-END      PIC X.               00200021
```

```
          10  GEO-WA2-1L-LOW-PBSC              PIC S9(7) COMP-3     00210021
                                               OCCURS 5 TIMES.      00220021
          10  GEO-WA2-1L-NUM-X-ST-HI-END       PIC X.               00230021
          10  GEO-WA2-1L-HI-PBSC               PIC S9(7) COMP-3     00240021
                                               OCCURS 5 TIMES.      00250021
          10  GEO-WA2-1L-COMDIST.                                   00260021
              15  GEO-WA2-1L-COMDIST-BORO      PIC X(1).            00270021
              15  GEO-WA2-1L-COMDIST-NUMBER    PIC X(2).            00280021
          10  GEO-WA2-1L-ZIP                   PIC X(5).            00290021
          10  GEO-WA2-1L-SLA                   PIC X.               00300021
          10  GEO-WA2-1L-HCD                   PIC X(2).            00310028
          10  GEO-WA2-1L-SOS                   PIC X.               00320021
          10  GEO-WA2-1L-CONT-PARITY-IND       PIC X.               00330021
          10  GEO-WA2-1L-2010-CENS-TRCT        PIC X(6).            00340023
          10  GEO-WA2-1L-2010-CENS-BLK         PIC X(4).            00350023
          10  GEO-WA2-1L-2010-CENS-BLK-SFX     PIC X.               00360023
          10  FILLER                           PIC X(3).            00370021
          10  GEO-WA2-1L-HEALTHAREA            PIC X(4).            00380028
          10  GEO-WA2-1L-SANI-REC              PIC X(3).            00390021
          10  GEO-WA2-1L-FEATURE-TYPE          PIC X(1).            00400021
          10  GEO-WA2-1L-RESDCP                PIC X(1).            00410021
          10  GEO-WA2-1L-CURVE-FLAG            PIC X(1).            00420021
          10  GEO-WA2-1L-POLICEDIST.                                00430021
             15  GEO-WA2-1L-POL-PATR-BORO-CMD  PIC X(1).            00440021
             15  GEO-WA2-1L-POL-PRECINCT       PIC X(3).            00450021
          10  GEO-WA2-1L-SCHOOLDIST            PIC X(2).            00460021
          10  FILLER                           PIC X(14).           00470021
          10  GEO-WA2-1L-COINCIDENT-CNT        PIC X.               00480021
          10  GEO-WA2-1L-SEGMENT-TYPE          PIC X.               00490021
          10  GEO-WA2-1L-SANIDIST.                                  00500021
              15  GEO-WA2-1L-SANIDIST-BORO     PIC X(1).            00510021
              15  GEO-WA2-1L-SANIDIST-NUMBER   PIC X(2).            00520021
          10  GEO-WA2-1L-SANITATION-SUBSEC     PIC X(2).            00530021
** NOTE:10  GEO-WA2-1L-FIRESEC ==> FIRE DIVISION **                 00540021
          10  GEO-WA2-1L-FIRESEC               PIC X(2).            00550021
          10  GEO-WA2-1L-FIREBAT               PIC X(2).            00560021
          10  GEO-WA2-1L-FIRECO.                                    00570021
              15  GEO-WA2-1L-FIRECO-TYPE       PIC X(1).            00580021
              15  GEO-WA2-1L-FIRECO-NUM        PIC X(3).            00590021
          10  GEO-WA2-1L-SPECIAL-ADDR-FLAG     PIC X(1).            00600021
          10  GEO-WA2-1L-MARBLE-RIKER-FLAG     PIC X(1).            00610021
          10  GEO-WA2-1L-SPLIT-SCHOOL-FILL     PIC X.               00620025
          10  GEO-WA2-1L-PREFERRED-LGC         PIC X(2).            00630021
          10  GEO-WA2-1L-LIONFACECODE          PIC X(4).            00640021
          10  GEO-WA2-1L-LIONSEQ               PIC X(5).            00650021
```

```
    10  GEO-WA2-1L-1990-CENSUSTRACT      PIC X(6).            00660021
    10  FILLER                           PIC X(4).            00670021
    10  GEO-WA2-1L-DYN-BLOCK             PIC X(3).            00680021
    10  GEO-WA2-1L-XCOORD                PIC X(7).            00690021
    10  GEO-WA2-1L-YCOORD                PIC X(7).            00700021
    10  GEO-WA2-1L-SEGMENTLENGTH         PIC X(5).            00710021
    10  GEO-WA2-1L-SANI-REG              PIC X(5).            00720021
    10  GEO-WA2-1L-SEG-ID                PIC X(7).            00730021
    10  GEO-WA2-1L-TRUE-B7SC             PIC X(8).            00740021
    10  GEO-WA2-1L-TRUE-HNI              PIC X(6).            00750021
    10  GEO-WA2-1L-2000-CENS-TRACT       PIC X(6).            00770024
    10  GEO-WA2-1L-2000-CENS-BLOCK       PIC X(4).            00780024
    10  GEO-WA2-1L-2000-CENS-BLK-SUF     PIC X.               00790024
    10  FILLER                           PIC X(68).           00800021
 05  GEO-WA2-1EL-FUNCTION1E REDEFINES GEO-WA2-1L-FUNCTION1.   00810021
    10  FILLER                           PIC X(21).           00820021
    10  GEO-WA2-1EL-CONT-PARITY          PIC X.               00830021
    10  GEO-WA2-1EL-LOW-HOUSENUM-INT.                         00840021
       15  GEO-WA2-1EL-LOW-HOUSENUM      PIC X(5).            00850021
       15  GEO-WA2-1EL-LOW-HOUSENUMSFX   PIC X.               00860021
    10  GEO-WA2-1EL-HI-HOUSENUM-INT.                          00870021
       15  GEO-WA2-1EL-HI-HOUSENUM       PIC X(5).            00880021
       15  GEO-WA2-1EL-HI-HOUSENUMSFX    PIC X.               00890021
    10  FILLER                           PIC X.               00900021
    10  GEO-WA2-1EL-NUM-X-ST-LOW-END     PIC X.               00910021
    10  GEO-WA2-1EL-LOW-PBSC             PIC S9(7) COMP-3     00920021
                                         OCCURS 5 TIMES.      00930021
    10  GEO-WA2-1EL-NUM-X-ST-HI-END      PIC X.               00940021
    10  GEO-WA2-1EL-HI-PBSC              PIC S9(7) COMP-3     00950021
                                         OCCURS 5 TIMES.      00960021
    10  GEO-WA2-1EL-COMDIST.                                  00970021
        15  GEO-WA2-1EL-COMDIST-BORO     PIC X(1).            00980021
        15  GEO-WA2-1EL-COMDIST-NUMBER   PIC X(2).            00990021
    10  GEO-WA2-1EL-ZIP                  PIC X(5).            01000021
    10  GEO-WA2-1EL-SLA                  PIC X.               01010021
    10  GEO-WA2-1EL-HCD                  PIC X(2).            01020028
    10  GEO-WA2-1EL-SOS                  PIC X.               01030021
    10  GEO-WA2-1EL-CONT-PARITY-IND      PIC X.               01040021
    10  GEO-WA2-1EL-2010-CENS-TRCT       PIC X(6).            01050023
    10  GEO-WA2-1EL-2010-CENS-BLK        PIC X(4).            01060023
    10  GEO-WA2-1EL-2010-CENS-BLK-SFX    PIC X.               01070023
    10  FILLER                           PIC X(3).            01080021
    10  GEO-WA2-1EL-HEALTHAREA           PIC X(4).            01090028
    10  GEO-WA2-1EL-SANI-REC             PIC X(3).            01100021
    10  GEO-WA2-1EL-FEATURE-TYPE         PIC X(1).            01110021
```

```
          10  GEO-WA2-1EL-RESDCP              PIC X(1).           01120021
          10  GEO-WA2-1EL-CURVE-FLAG          PIC X(1).           01130021
          10  GEO-WA2-1EL-POLICEDIST.                             01140021
             15  GEO-WA2-1EL-POL-PATR-BORO-CMD PIC X(1).          01150021
             15  GEO-WA2-1EL-POL-PRECINCT      PIC X(3).          01160021
          10  GEO-WA2-1EL-SCHOOLDIST          PIC X(2).           01170021
          10  GEO-WA2-1EL-ELECTDIST           PIC X(3).           01180021
          10  GEO-WA2-1EL-ASSEMDIST           PIC X(2).           01190021
          10  GEO-WA2-1EL-SPLIT-ED-FLAG       PIC X(1).           01200021
          10  GEO-WA2-1EL-CONGDIST            PIC X(2).           01210021
          10  GEO-WA2-1EL-SENATEDIST          PIC X(2).           01220021
          10  GEO-WA2-1EL-COURTDIST           PIC X(2).           01230021
          10  GEO-WA2-1EL-COUNCILDIST         PIC X(2).           01240021
          10  GEO-WA2-1EL-COINCIDENT-CNT      PIC X.              01250021
          10  FILLER                          PIC X.              01260021
          10  GEO-WA2-1EL-SANIDIST.                               01270021
              15  GEO-WA2-1EL-SANIDIST-BORO   PIC X(1).           01280021
              15  GEO-WA2-1EL-SANIDIST-NUMBER PIC X(2).           01290021
          10  GEO-WA2-1EL-SANITATION-SUBSEC   PIC X(2).           01300021
** NOTE:10  GEO-WA2-1EL-FIRESEC==> FIRE DIVISION **               01310021
          10  GEO-WA2-1EL-FIRESEC             PIC X(2).           01320021
          10  GEO-WA2-1EL-FIREBAT             PIC X(2).           01330021
          10  GEO-WA2-1EL-FIRECO.                                 01340021
              15  GEO-WA2-1EL-FIRECO-TYPE     PIC X(1).           01350021
              15  GEO-WA2-1EL-FIRECO-NUM      PIC X(3).           01360021
          10  GEO-WA2-1EL-SPECIAL-ADDR-FLAG   PIC X(1).           01370021
          10  GEO-WA2-1EL-MARBLE-RIKER-FLAG   PIC X(1).           01380021
          10  GEO-WA2-1EL-SPLIT-SCHOOL-FILL   PIC X.              01390025
          10  GEO-WA2-1EL-PREFERRED-LGC       PIC X(2).           01400021
          10  GEO-WA2-1EL-LIONFACECODE        PIC X(4).           01410021
          10  GEO-WA2-1EL-LIONSEQ             PIC X(5).           01420021
          10  GEO-WA2-1EL-1990-CENSUSTRACT    PIC X(6).           01430021
          10  FILLER                          PIC X(4).           01440021
          10  GEO-WA2-1EL-DYN-BLOCK           PIC X(3).           01450021
          10  GEO-WA2-1EL-XCOORD              PIC X(7).           01460021
          10  GEO-WA2-1EL-YCOORD              PIC X(7).           01470021
          10  GEO-WA2-1EL-SEGMENTLENGTH       PIC X(5).           01480021
          10  GEO-WA2-1EL-SANI-REG            PIC X(5).           01490021
          10  GEO-WA2-1EL-SEG-ID              PIC X(7).           01500021
          10  GEO-WA2-1EL-TRUE-B7SC           PIC X(8).           01510021
          10  GEO-WA2-1EL-TRUE-HNI            PIC X(6).           01520021
          10  GEO-WA2-1EL-2000-CENS-TRACT     PIC X(6).           01540024
          10  GEO-WA2-1EL-2000-CENS-BLOCK     PIC X(4).           01550024
          10  GEO-WA2-1EL-2000-CENS-BLK-SUF   PIC X.              01560024
          10  FILLER                          PIC X(68).          01570021
```

```
     05  GEO-WA2-3L-FUNCTION3 REDEFINES GEO-WA2-1L-FUNCTION1.     01580021
        10  FILLER                          PIC X(21).           01590021
        10  GEO-WA2-3L-DUP-KEY-FLAG         PIC X.               01600021
        10  GEO-WA2-3L-CURVE-FLAG           PIC X.               01610021
        10  GEO-WA2-3L-LOCATION-STATUS      PIC X.               01620021
        10  GEO-WA2-3L-COUNTY-BOUNDARY      PIC X.               01630021
        10  GEO-WA2-3L-COINCIDENT-CNT       PIC X.               01640021
        10  FILLER                          PIC X(3).            01650021
        10  GEO-WA2-3L-PREFERRED-LGC1       PIC X(2).            01660021
        10  GEO-WA2-3L-PREFERRED-LGC2       PIC X(2).            01670021
        10  GEO-WA2-3L-PREFERRED-LGC3       PIC X(2).            01680021
        10  GEO-WA2-3L-NUM-X-ST-LOW-END     PIC X.               01690021
        10  GEO-WA2-3L-LOW-PBSC             PIC S9(7) COMP-3     01700021
                                              OCCURS 5 TIMES.     01710021
        10  GEO-WA2-3L-NUM-X-ST-HI-END      PIC X.               01720021
        10  GEO-WA2-3L-HI-PBSC              PIC S9(7) COMP-3     01730021
                                              OCCURS 5 TIMES.     01740021
        10  GEO-WA2-3L-SLA                  PIC X.               01750021
        10  GEO-WA2-3L-REVERSALFLAG         PIC X.               01760021
        10  GEO-WA2-3L-LEFT-COMDIST.                             01770021
            15  GEO-WA2-3L-LEFT-COMDIST-BORO PIC X(1).           01780021
            15  GEO-WA2-3L-LEFT-COMDIST-NUM  PIC X(2).           01790021
        10  GEO-WA2-3L-RIGHT-COMDIST.                            01800021
            15 GEO-WA2-3L-RIGHT-COMDIST-BORO PIC X(1).           01810021
            15  GEO-WA2-3L-RIGHT-COMDIST-NUM PIC X(2).           01820021
        10  GEO-WA2-3L-LEFT-ZIP             PIC X(5).            01830021
        10  GEO-WA2-3L-RIGHT-ZIP            PIC X(5).            01840021
        10  FILLER                          PIC X(18).           01850021
        10  GEO-WA2-3L-LEFT-HEALTHAREA      PIC X(4).            01860028
        10  GEO-WA2-3L-RIGHT-HEALTHAREA     PIC X(4).            01870028
***     NEXT LINE WAS PREVIOUSLY LEFT-INSTRUC-DIV                 01880021
        10  FILLER                          PIC X(2).            01890021
***     NEXT LINE WAS PREVIOUSLY RIGHT-INSTRUC-DIV                01900021
        10  FILLER                          PIC X(2).            01910021
        10  GEO-WA2-3L-LEFT-LOW-HOUSENUM    PIC X(7).            01920021
        10  GEO-WA2-3L-LEFT-HI-HOUSENUM     PIC X(7).            01930021
        10  GEO-WA2-3L-RIGHT-LOW-HOUSENUM   PIC X(7).            01940021
        10  GEO-WA2-3L-RIGHT-HI-HOUSENUM    PIC X(7).            01950021
        10  GEO-WA2-3L-CONT-PARITY-IND      PIC X.               01960021
        10  GEO-WA2-3L-LIONFACECODE         PIC X(4).            01970021
        10  GEO-WA2-3L-LIONSEQ              PIC X(5).            01980021
        10  GEO-WA2-3L-GENRECFLAG           PIC X.               01990021
        10  GEO-WA2-3L-SEGMENTLENGTH        PIC S9(5) COMP-3.    02000021
        10  GEO-WA2-3L-SEGMENTSLOPE         PIC X(3).            02010021
        10  GEO-WA2-3L-SEGMENTORIENT        PIC X.               02020021
```

```
        10  FILLER                          PIC X(4).           02030021
        10  GEO-WA2-3L-RESDCP               PIC X(2).           02040021
        10  GEO-WA2-3L-DOG-LEG              PIC X.              02050021
        10  GEO-WA2-3L-FEATURE-TYPE         PIC X(1).           02060021
        10  GEO-WA2-3L-LEFT-POLDIST.                            02070021
           15  GEO-WA2-3L-L-POL-PATR-BOR-CMD PIC X(1).          02080021
           15  GEO-WA2-3L-L-POL-PRECINCT     PIC X(3).          02090021
        10  GEO-WA2-3L-RIGHT-POLDIST.                           02100021
           15  GEO-WA2-3L-R-POL-PATR-BOR-CMD PIC X(1).          02110021
           15  GEO-WA2-3L-R-POL-PRECINCT     PIC X(3).          02120021
        10  GEO-WA2-3L-LEFT-SCHLDIST        PIC X(2).           02130021
        10  GEO-WA2-3L-RIGHT-SCHLDIST       PIC X(2).           02140021
        10  GEO-WA2-3L-MARBLE-RIKER-FLAG    PIC X(1).           02150021
        10  GEO-WA2-3L-SEG-ID               PIC X(7).           02160021
        10  GEO-WA2-3L-SEGMENT-TYPE         PIC X.              02170021
*************************************************************     02180021
**  THE PORTION OF THIS WORK AREA ABOVE THIS POINT IS      **     02190021
**  IDENTICAL TO THE STANDARD WORK AREA 2 FOR FUNCTION 3.  **     02200021
**  THE PORTION BELOW THIS POINT IS PRESENT ONLY FOR THE   **     02210021
**  LONG WORK AREA 2 OPTION.                               **     02220021
*************************************************************     02230021
        10  GEO-WA2-3L-L-1990-CENSUSTRACT   PIC X(6) .          02240021
        10  FILLER                          PIC X(4).           02250021
        10  GEO-WA2-3L-L-DYN-BLOCK          PIC X(3).           02260021
        10  GEO-WA2-3L-R-1990-CENSUSTRACT   PIC X(6).           02270021
        10  FILLER                          PIC X(4).           02280021
        10  GEO-WA2-3L-R-DYN-BLOCK          PIC X(3).           02290021
** NOTE:10  GEO-WA2-3L-L-FIRESEC ==> FIRE DIV **                 02300021
** NOTE:10  GEO-WA2-3L-R-FIRESEC ==> FIRE DIV **                 02310021
        10  GEO-WA2-3L-L-FIRESEC            PIC X(2).           02320021
        10  GEO-WA2-3L-L-FIREBAT            PIC X(2).           02330021
        10  GEO-WA2-3L-L-FIRECO.                                02340021
            15  GEO-WA2-3L-L-FIRECO-TYPE    PIC X(1).           02350021
            15  GEO-WA2-3L-L-FIRECO-NUM     PIC X(3).           02360021
        10  GEO-WA2-3L-R-FIRESEC            PIC X(2).           02370021
        10  GEO-WA2-3L-R-FIREBAT            PIC X(2).           02380021
        10  GEO-WA2-3L-R-FIRECO.                                02390021
            15  GEO-WA2-3L-R-FIRECO-TYPE    PIC X(1).           02400021
            15  GEO-WA2-3L-R-FIRECO-NUM     PIC X(3).           02410021
        10  GEO-WA2-3L-L-2010-CENS-TRCT     PIC X(6).           02420023
        10  GEO-WA2-3L-L-2010-CENS-BLK      PIC X(4).           02430023
        10  GEO-WA2-3L-L-2010-CENS-BLK-SFX  PIC X.              02440023
        10  GEO-WA2-3L-R-2010-CENS-TRCT     PIC X(6).           02450023
        10  GEO-WA2-3L-R-2010-CENS-BLK      PIC X(4).           02460023
        10  GEO-WA2-3L-R-2010-CENS-BLK-SFX  PIC X.              02470023
```

```
          10  GEO-WA2-3L-FROM-NODE            PIC X(7).          02480021
          10  GEO-WA2-3L-TO-NODE              PIC X(7).          02490021
          10  GEO-WA2-3L-L-2000-CENS-TRACT    PIC X(6).          02510024
          10  GEO-WA2-3L-L-2000-CENS-BLOCK    PIC X(4).          02520024
          10  GEO-WA2-3L-L-2000-CENS-BLK-SUF  PIC X.             02530024
          10  GEO-WA2-3L-R-2000-CENS-TRACT    PIC X(6).          02540024
          10  GEO-WA2-3L-R-2000-CENS-BLOCK    PIC X(4).          02550024
          10  GEO-WA2-3L-R-2000-CENS-BLK-SUF  PIC X.             02560024
```

W2COB1A COPY File

```
*****************************************************************  00000100
**  THIS IS GEOSUPPORT SYSTEM COPY FILE W2COB1A, CONTAINING   **   00000200
**  THE LAYOUT OF WORK AREA 2 FOR FUNCTIONS 1A AND BL WHICH   **   00000300
**  SHARE A SINGLE WORK AREA 2 LAYOUT.          10/18/96      **   00000400
*****************************************************************  00000500
 *  NEW FORMAT  *                                                  00000600
     05  GEO-WA2-1A-ACCESS-KEY              PIC X(21).          00000700
     05  GEO-WA2-1A-CONT-PARITY             PIC X.              00000800
     05  GEO-WA2-1A-LOW-HOUSENUM            PIC X(6).           00000900
     05  GEO-WA2-1A-ALTKEY-1.                                   00001000
        10 GEO-WA2-1A-ALTKEY-1-BORO         PIC X.              00001100
        10 GEO-WA2-1A-ALTKEY-1-TAXBLOCK     PIC X(5).           00001200
        10 GEO-WA2-1A-ALTKEY-1-TAXLOT       PIC X(4).           00001300
     05  FILLER                             PIC X.              00001400
     05  GEO-WA2-1A-SCC                     PIC X.              00001500
     05  FILLER                             PIC X.              00001600
     05  GEO-WA2-1A-GENERAL-LOT-INFO.                           00001700
        10 GEO-WA2-1A-RPAD-BLDG-CLASS       PIC X(2).           00001800
        10 GEO-WA2-1A-CORNER-CODE           PIC X(2).           00001900
        10 GEO-WA2-1A-NUM-OF-STRUCTURES     PIC X(2).           00002000
        10 GEO-WA2-1A-NUM-OF-BLOCKFACES     PIC X(2).           00002100
        10 GEO-WA2-1A-INTERIOR-FLAG         PIC X.              00002200
        10 GEO-WA2-1A-VACANT-FLAG           PIC X.              00002300
        10 GEO-WA2-1A-IRREG-FLAG            PIC X.              00002400
     05  GEO-WA2-1A-ALT-BORO-FLAG           PIC X.              00002500
     05  FILLER                             PIC X.              00002600
     05  GEO-WA2-1A-STROLL-KEY              PIC X(13).          00002700
     05  GEO-WA2-1A-OVERFLOW-FLAG           PIC X(1).           00002801
     05  FILLER-DCP                         PIC X(1).           00002900
     05  GEO-WA2-1A-BLDG-ID-NUM             PIC X(7).           00003000
     05  GEO-WA2-1A-CONDO-LOT-FLAG          PIC X.              00003100
     05  GEO-WA2-1A-RPAD-COND-NUM           PIC X(4).           00003200
     05  GEO-WA2-1A-CONDO-LOW-BBL           PIC X(10).          00003300
```

```
        05  FILLER                              PIC X.              00003400
        05  GEO-WA2-1A-CONDO-BILLING-BBL        PIC X(10).          00003500
        05  FILLER                              PIC X.              00003600
        05  GEO-WA2-1A-CONDO-BILL-BBL-SCC       PIC X.              00003700
        05  GEO-WA2-1A-CONDO-HIGH-BBL           PIC X(10).          00003800
        05  FILLER                              PIC X.              00003900
        05  GEO-WA2-1A-SANBORN-BVOLPAGE.                            00004000
            10  GEO-WA2-1A-SANBORN-BORO         PIC X(1).           00004100
            10  GEO-WA2-1A-SANBORN-VOL-PAGE.                        00004200
                15  GEO-WA2-1A-SANBORN-VOL-NUM  PIC X(3).           00004300
                15  GEO-WA2-1A-SANBORN-PAGE-NUM PIC X(4).           00004400
        05  GEO-WA2-1A-COMMERC-DIST             PIC X(5).           00004500
        05  GEO-WA2-1A-CO-OP-NBR                PIC X(4).           00004602
        05  FILLER                              PIC X(4).           00004703
        05  GEO-WA2-1A-TOT-NBR-BLDG             PIC X(4).           00004802
        05  GEO-WA2-1A-DOF-MAP-BOROUGH          PIC X.              00004904
        05  GEO-WA2-1A-TAX-MAP-NBR              PIC X(4).           00005004
        05  FILLER-FOR-TAX-MAP-PAGE             PIC X(4).           00005105
        05  GEO-WA2-1A-X-COORD                  PIC X(7).           00005205
        05  GEO-WA2-1A-Y-COORD                  PIC X(7).           00005305
        05  GEO-WA2-1A-BID                      PIC X(6).           00005406
        05  FILLER                              PIC X(2).           00005506
        05  GEO-WA2-1A-FILLER-LGCS              PIC X(8).           00005607
        05  FILLER                              PIC X(2).           00005706
        05  GEO-WA2-1A-NUM-OF-ADDR-FOR-LOT      PIC X(2).           00005806
        05  GEO-WA2-1A-LIST-OF-ADDRESSES        OCCURS 21 TIMES.    00005906
           10  GEO-WA2-1A-LIST-LOW-HOUSENUM     PIC X(6).           00006006
           10  FILLER                           PIC X(3).           00006106
           10  GEO-WA2-1A-LIST-HI-HOUSENUM      PIC X(6).           00006206
           10  FILLER                           PIC X(3).           00006306
           10  GEO-WA2-1A-LIST-STREETCODE       PIC X(8).           00006406
           10  GEO-WA2-1A-LIST-BIN              PIC X(7).           00006506
           10  GEO-WA2-1A-ADDR-TYPE             PIC X.              00006606
           10  FILLER                           PIC X.              00006706
           10  GEO-WA2-1A-LIST-SOS              PIC X.              00007002
```

W2COB1AL COPY File

```
      ****************************************************************  00000100
      **  THIS IS GEOSUPPORT SYSTEM COPY FILE W2COB1AL, CONTAINING   **  00000200
      **  THE LAYOUT OF LONG WORK AREA 2 FOR FUNCTIONS 1A AND BL     **  00000300
      **  WHICH SHARE A SINGLE WORK AREA 2 LAYOUT.       11/06/97    **  00000400
      ****************************************************************  00000500
       *  1A/BL LONG WORK AREA 2 *                                      00000600
        05  GEO-WA2-1AL-ACCESS-KEY              PIC X(21).          00000700
```

```
     05  GEO-WA2-1AL-CONT-PARITY              PIC X.            00000800
     05  GEO-WA2-1AL-LOW-HOUSENUM             PIC X(6).         00000900
     05  GEO-WA2-1AL-ALTKEY-1.                                  00001000
        10 GEO-WA2-1AL-ALTKEY-1-BORO          PIC X.            00001100
        10 GEO-WA2-1AL-ALTKEY-1-TAXBLOCK      PIC X(5).         00001200
        10 GEO-WA2-1AL-ALTKEY-1-TAXLOT        PIC X(4).         00001300
     05  FILLER                              PIC X.            00001400
     05  GEO-WA2-1AL-SCC                      PIC X.            00001500
     05  FILLER                              PIC X.            00001600
     05  GEO-WA2-1AL-GENERAL-LOT-INFO.                          00001700
        10 GEO-WA2-1AL-RPAD-BLDG-CLASS        PIC X(2).         00001800
        10 GEO-WA2-1AL-CORNER-CODE            PIC X(2).         00001900
        10 GEO-WA2-1AL-NUM-OF-STRUCTURES      PIC X(2).         00002000
        10 GEO-WA2-1AL-NUM-OF-BLOCKFACES      PIC X(2).         00002100
        10 GEO-WA2-1AL-INTERIOR-FLAG          PIC X.            00002200
        10 GEO-WA2-1AL-VACANT-FLAG            PIC X.            00002300
        10 GEO-WA2-1AL-IRREG-FLAG             PIC X.            00002400
     05  GEO-WA2-1AL-ALT-BORO-FLAG            PIC X.            00002500
     05  FILLER                              PIC X.            00002600
     05  GEO-WA2-1AL-STROLL-KEY               PIC X(13).        00002700
     05  FILLER                              PIC X(1).         00002800
     05  FILLER-DCP                          PIC X(1).         00002900
     05  GEO-WA2-1AL-BLDG-ID-NUM              PIC X(7).         00003000
     05  GEO-WA2-1AL-CONDO-LOT-FLAG           PIC X.            00003100
     05  GEO-WA2-1AL-RPAD-COND-NUM            PIC X(4).         00003200
     05  GEO-WA2-1AL-CONDO-LOW-BBL            PIC X(10).        00003300
     05  FILLER                              PIC X.            00003400
     05  GEO-WA2-1AL-CONDO-BILLING-BBL        PIC X(10).        00003500
     05  FILLER                              PIC X.            00003600
     05  GEO-WA2-1AL-CONDO-BILL-BBL-SCC       PIC X.            00003700
     05  GEO-WA2-1AL-CONDO-HIGH-BBL           PIC X(10).        00003800
     05  FILLER                              PIC X.            00003900
     05  GEO-WA2-1AL-SANBORN-BVOLPAGE.                          00004000
         10  GEO-WA2-1AL-SANBORN-BORO         PIC X(1).         00004100
         10  GEO-WA2-1AL-SANBORN-VOL-PAGE.                      00004200
             15  GEO-WA2-1AL-SANBORN-VOL-NUM  PIC X(3).         00004300
             15  GEO-WA2-1AL-SANBORN-PAGE-NUM PIC X(4).         00004400
     05  GEO-WA2-1AL-COMMERC-DIST             PIC X(5).         00004500
     05  GEO-WA2-1AL-CO-OP-NBR                PIC X(4).         00004604
     05  FILLER                               PIC X(4).         00004705
     05  GEO-WA2-1AL-TOT-NBR-BLDG             PIC X(4).         00004804
     05  GEO-WA2-1AL-DOF-MAP-BORO             PIC X.            00004907
     05  GEO-WA2-1AL-DOF-MAP-SECVOL           PIC X(4).         00005007
*******  GEO-WA2-1AL-DOF-MAP-PAGE  NOT IMPLEMENTED              00005107
     05  GEO-WA2-1AL-DOF-MAP-PAGE             PIC X(4).         00005207
```

```
          05  GEO-WA2-1AL-X-COORD                PIC X(7).          00005308
          05  GEO-WA2-1AL-Y-COORD                PIC X(7).          00005408
          05  GEO-WA2-1AL-BID                    PIC X(6).          00005509
          05  FILLER                             PIC X(2).          00005609
          05  GEO-WA2-1AL-FILLER-LGCS            PIC X(8).          00005709
          05  GEO-WA2-1AL-NUM-OF-BINS            PIC X(4).          00005809
          05  GEO-WA2-1AL-BINS                   PIC X(7)           00005909
                                             OCCURS 2500 TIMES.  00006004
```

W2COB3S COPY File

```
     ****************************************************************  00010000
     ***  THIS IS GEOSUPPORT SYSTEM COPY FILE W2COB3S, CONTAINING    **  00020000
     ***  THE LAYOUT OF WORK AREA 2 FOR FUNCTION 3S.        9/22/93 **  00030000
     ****************************************************************  00040000
           05  GEO-WA2-3S-ACCESS-KEY              PIC X(21).         00050000
           05  GEO-WA2-3S-NUM-OF-INTERSECTS       PIC X(3).          00060000
           05  GEO-WA2-3S-LIST-OFINTERSECTS       OCCURS 350 TIMES.  00070000
              10 GEO-WA2-3S-SMALLEST-PBSC         PIC S9(7) COMP-3.  00080000
              10 GEO-WA2-3S-2ND-SMALLEST-PBSC     PIC S9(7) COMP-3.  00090000
              10 GEO-WA2-3S-DISTANCE              PIC S9(5) COMP-3.  00100000
              10 GEO-WA2-3S-GAP-FLAG              PIC X.             00110000
```

ASSEMBLER COPY FILES (MSW)

W1BAL COPY File

```
\*/*********************************************************************/ 00000100
\*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE W1BAL,    \***/ 00000200
\*/*****  CONTAINING THE LAYOUT OF WORK AREA 1.                     \***/ 00000300
\*/*********************************************************************/ 00000400
\*/*****  Last Updated - 17 October 2006                            \***/ 00000410
\*/*********************************************************************/ 00000420
W1BAL    DS   0H                                                        00000500
\*/****************************                                         00000600
\*/*****  INPUT FIELDS  *******                                         00000700
\*/****************************                                         00000800
W1IFUNC  DS    0CL2      FUNCTION CODE                                  00000900
W1IFUNC1 DS     CL1      FUNCTION CODE, BYTE 1                          00001000
W1IFUNC2 DS     CL1      FUNCTION CODE, BYTE 2                          00001100
W1IBORO  DS    0CL1                                                     00001200
W1IBORO1 DS     CL1      BORO CODE  (1=MN;2=BX;3=BK;4=QN;5=SI)          00001300
W1IHSE#  DS    CL12      UNFORMATED HSNUM FOR FUNCTION: 1; 1A; 1E.      00001400
W1IHSE#P DS    CL6       HOUSE NUM (INTERNAL FORMAT FOR FUNC D)         00001500
W1ISTRT1 DS    CL32      STREET NAME 1                                  00001600
```

```
W1ISTRT2 DS    CL32      STREET NAME 2                                  00001700
W1ISTRT3 DS    CL32      STREET NAME 3                                  00001800
W1ICOMP  DS    CL1       COMPASS DIRECTION (TYPES 2, 3C & 3S)           00001900
W1ICOMP2 DS    CL1       COMPASS DIRECTION (TYPE 3S)                    00001950
W1ICDE1  DS    PL4       PB5SC FOR STREET 1                             00002000
W1ICDE2  DS    PL4       PB5SC FOR STREET 2                             00002100
W1ICDE3  DS    PL4       PB5SC FOR STREET 3                             00002200
W1IRBRQS DS    CL1       ROADBED REQUEST SWITCH                         00002300
W1IBORO2 DS    CL1       BORO CODE OF CROSS ST. 1                       00002400
W1IBORO3 DS    CL1       BORO CODE OF CROSS ST. 2                       00002500
W1ISNL   DS    CL2       LENGTH STREET NAME IS TO BE NORMALIZED TO      00002600
W1I10SC1 DS    CL11      BORO + 10 BYTE STREET CODE FOR CROSS STREET 1  00002700
W1I10SC2 DS    CL11      BORO + 10 BYTE STREET CODE FOR CROSS STREET 2  00002800
W1I10SC3 DS    CL11      BORO + 10 BYTE STREET CODE FOR CROSS STREET 3  00002900
W1IZIPIN DS    CL5       INPUT ZIP CODE                                 00003000
W1IBBL   DS    0CL10     BORO,BLOCK,LOT FOR "BL" FUNCTION               00003100
W1IBLBOR DS     CL1      BORO FOR FUNCTION "BL"                         00003200
W1IBLOCK DS     CL5      TAX BLOCK - FOR  FUNCTION "BL"                 00003300
W1ILOT   DS     CL4      TAX LOT   - FOR  FUNCTION "BL"                 00003400
         DS    CL1       FILLER                                         00003410
W1IBIN   DS    CL7       BUILDING ID NUMBER                             00003500
W1ICMPCT DS    CL1       'C' IF STREET NAMES ARE TO BE COMPACTED        00003600
W1ILONG3 DS    CL1       'L' IF LONG WORKAREA 2 FOR FUNC 3 DESIRED      00003700
W1ILHSE  DS    CL12      UNFORMATED LOW HSNUM FOR FUNCTION: 1; 1A; 1E.  00003800
W1ILHSEP DS    CL6       LOW HOUSE NUM (INTERNAL FORMAT FOR FUNC D)     00003900
W1INIBMF DS    CL1       NON-IBM MAIN FRAMME FLAG                       00004000
W1I1ABLV DS    CL1       Set to "S" for St'd Func. 1A & BL WORKAREA     00004100
\*                        Set to "L" or " " for Legacy 1A & BL Workarea  00004200
W1IXSTF  DS    CL1       CROSS STREET NAME FLAG                         00004300
         DS    CL4       FILLER                                         00004400
\*/*****************************                                        00004500
\*/*****  OUTPUT FIELDS  *******                                        00004600
\*/*****************************                                        00004700
W1OLHSE  DS    CL12      LOW HOUSE NUMBER IN DISPLAY FORMAT
W1OBORO  DS    CL9       BORO NAME                                      00004800
W1OSTRT1 DS    CL32      STREET 1 NAME, NORMALIZED                      00004900
W1OSTRT2 DS    CL32      STREET 2 NAME, NORMALIZED                      00005000
W1OSTRT3 DS    CL32      STREET 3 NAME, NORMALIZED                      00005100
W1OHSE#  DS    CL12      HOUSE NUMBER, NORMALIZED, DISPLAY FORMAT       00005200
W1OHSE#P DS    CL6       HOUSE NUMBER (INTERNAL FORMAT)                 00005300
         DS    CL7       FILLER                                         00005400
W1OPB51K DS    0PL4      Packed Borough and Street Code 1               00005500
W1OBOR1K DS    XL1       Packed unsigned Borough Code                   00005600
W1OCDE1K DS    PL3       STREET CODE 1 (KEY)                            00005700
         DS    PL2       Filler                                         00005800
```

```
W1OPB52K DS    0PL4      Packed Borough and Street Code 2              00005900
W1OBOR2K DS    XL1       Packed unsigned Borough Code                  00006000
W1OCDE2K DS    PL3       STREET CODE 2 (KEY)                           00006100
         DS    PL2       Filler                                        00006200
W1OPB53K DS    0PL4      Packed Borough and Street Code 3              00006300
W1OBOR3K DS    XL1       Packed unsigned Borough Code                  00006400
W1OCDE3K DS    PL3       STREET CODE 3 (KEY)                           00006500
W1OATTR  DS    CL3       Attribute Bytes - Internal Use Only           00006600
W1BROWSE DS    CL40      10 PB5SC'S FOR  FUNCTION: BB; BF.             00006700
W1O10SC1 DS    CL11      BORO + 10 BYTE STREET CODE FOR CROSS STREET 1 00006800
W1O10SC2 DS    CL11      BORO + 10 BYTE STREET CODE FOR CROSS STREET 2 00006900
W1O10SC3 DS    CL11      BORO + 10 BYTE STREET CODE FOR CROSS STREET 2 00007000
W1OCONDO DS    CL5       CONDO UNIT ID NUMBER - NOT IMPLEMENTED        00007100
W1OBBL   DS    0CL10     OUTPUT BORO,BLOCK,LOT FOR FUNCTION "BL"       00007200
W1OBLBOR DS     CL1      BORO FOR FUNCTION "BL"                        00007300
W1OBLOCK DS     CL5      TAX BLOCK - FOR FUNCTION "BL"                 00007400
W1OLOT   DS     CL4      TAX LOT   - FOR FUNCTION "BL"                 00007500
         DS    CL1     FILLER                                         00007510
W1OBIN   DS    CL7     BUILDING IDENTIFICATION Number                 00007600
W1OINTU1 DS    CL1       INTERNAL USE ONLY - ATTR BYTE
W1OREASN DS    CL1       REASON CODE                                   00007900
W1OINTR0 DS    CL1       INTERNAL USE ONLY - RETURN CODE               00008000
W1OINTRC DS    CL1       INTERNAL USE ONLY - RETURN CODE               00008100
W1ORC    DS    0CL2      RETURN CODE                                   00008200
W1ORC1   DS     CL1      RETURN CODE, BYTE 1                           00008300
W1ORC2   DS     CL1      RETURN CODE, BYTE 2                           00008400
W1OERROR DS    CL80      ERROR MESSAGE                                 00008500
W1O#SIM  DS    PL2       NUMBER OF SIMILAR NAMES                       00008600
W1ONAMES DS  10CL32      UP TO 10 SIMILAR NAMES                        00008700
W1END    EQU   *                                                       00008800
W1LENGTH EQU   W1END-W1BAL    LENGTH OF W1BAL                          00008900
```

W2BAL COPY File

```
\*/*******************************************************************/ 00010000
\*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE W2BAL,    \***/ 00020000
\*/*****  CONTAINING THE LAYOUT OF WORK AREA 2 FOR FUNCTIONS        \***/ 00030000
\*/*****  1, 1E, 2, 2C, 3, 3C. PLEASE NOTE THAT FUNCTIONS 2 AND 2C  \***/ 00040000
\*/*****  SHARE A SINGLE WORK AREA 2 LAYOUT.                        \***/ 00050000
\*/*******************************************************************/ 00060000
\*/*****              LAST MODIFIED JANUARY 2012                    \***/ 00070044
\*/*******************************************************************/ 00080012
W2BAL    DS   0H                                                       00090000
W2ACCKEY DS    CL21          ACCESS KEY                                00100000
W2LAYOUT DS   0CL179                                                   00110002
```

```
W2F1CPAR DS     CL1          CONTINUOUS PARITY INDICATOR                00120002
W2F1LHNI DS    0CL6          LOW HOUSE NUMBER                           00130000
W2F1HSEL DS     CL5          LOW HOUSE NUMBER ON BLOCK FACE             00140000
W2F1SFXL DS     CL1          LOW HOUSE NUMBER SUFFIX                    00150013
W2F1HHNI DS    0CL6          HIGH HOUSE NUMBER                          00160000
W2F1HSEH DS     CL5          HIGH HOUSE NUMBER ON BLOCK FACE            00170000
W2F1SFXH DS     CL1          HI HOUSE NUMBER SUFFIX                     00180013
W2F1ALX  DS    CL1           A=ALLEYS INTERSECT SEGMENT                 00190025
\*                            X=CROSS STREETS MODIFIED                   00191025
W2F1#STL DS    CL1           NUMBER OF CROSS STREETS AT LOW END         00200000
W2F1CDEL DS    CL20          UP TO FIVE PB5SC'S FOR LOW END             00210000
W2F1#STH DS    CL1           NUMBER OF CROSS STREETS AT HIGH END        00220000
W2F1CDEH DS    CL20          UP TO FIVE PB5SC'S FOR HIGH END            00230000
W2F1CD   DS    0CL3          COMMUNITY DISTRICT                         00240000
W2F1CDB  DS     CL1          COMMUNITY DISTRICT BORO                    00250000
W2F1CDN  DS     CL2          COMMUNITY DISTRICT NUMBER                  00260000
W2F1ZIP  DS    CL5           ZIP CODE                                   00270000
W2F1SLA  DS    CL1           STREET LIGHT AREA                          00280000
W2F1HCD  DS    CL2           HEALTH CODE DISTRICT                       00290045
W2F1SOS  DS    CL1           SIDE OF STREET INDICATOR                   00300000
W2F1PAR  DS    CL1           CONTINUOUS PARITY INDICATOR                00310000
W2F1CT10 DS    CL6           2010 CENSUS TRACT                          00320037
W2F1CB10 DS    CL4           2010 CENSUS BLOCK                          00350037
W2F1CBS1 DS    CL1           2010 CENSUS BLOCK SUFFIX NOT IMPLEMENTED   00351042
         DS    CL3           FILLER                                     00352032
W2F1HA   DS    CL4           HEALTH AREA                                00360045
W2F1SREC DS    CL3           SANITATION RECYCLE PICK-UP                 00370007
W2F1FEAT DS    CL1           FEATURE TYPE CODE                          00380023
RES1     DS    CL1           RESERVED FOR DCP/GSS USE                   00400000
         ORG   RES1                                                     00401030
W2F1ELCD DS    CL1           COMMUNITY DEVELOPMENT ELIGIBILITY          00402031
W2F1CURV DS    CL1           CURVE FLAG                                 00410014
W2F1POL  DS    0CL4          POLICE DISTRICT                            00420000
W2F1PBC  DS     CL1          POLICE PATROL BORO COMMAND                 00430000
W2F1POP  DS     CL3          POLICE PRECINCT                            00440000
W2F1SCH  DS    CL2           SCHOOL DISTRICT                            00450000
         DS    CL14         RESERVED FOR POLITICAL INFORMATION          00460028
W2F1CSC  DS    CL1           COINCIDENT SEGMENT COUNT                   00460128
W2F1STC  DS    CL1           SEGMENT TYPE CODE                          00461026
W2F1SAND DS    CL3           SANITATION DISTRICT                        00470002
W2F1SANT DS    CL2           SANITATION DEPT SUBSECTION                 00480000
W2F1FS   DS    CL2           FIRE DIVISION                              00490001
W2F1FB   DS    CL2           FIRE BATTALION                             00500000
W2F1FC   DS    0CL4          FIRE COMPANY                               00510000
W2F1FCT  DS     CL1          FIRE COMPANY TYPE                          00520000
```

```
W2F1FCN  DS     CL3          FIRE COMPANY NUMBER                      00530000
W2F1SPAD DS    CL1           SPECIAL ADDRESS FLAG                     00540000
W2F1MHRI DS    CL1           MARBLE HILL/RIKERS ISLAND FLAG           00550000
W2F1FILS DS    CL1           FILLER-WAS SPLIT SCHOOL DISTRICT FLAG    00560039
W2F1LGC  DS    CL2           LOGICAL GROUP CODE (PREFERRED)           00570000
W2F1FACE DS    CL4           LION FACE CODE                           00580000
W2F1SEQ  DS    CL5           LION SEQUENCE NUMBER                     00590000
W2F1CT90 DS    CL6           1990 CENSUS TRACT                        00600000
         DS    CL4           FILLER                                   00610015
W2F1CPB  DS    CL3           DYNAMIC BLOCK/ATOMIC POLYGON             00640038
W2F1XCOR DS    CL7           X COORDINATE                             00650000
W2F1YCOR DS    CL7           Y COORDINATE                             00660000
W2F1SEGL DS    CL5           SEGMENT LEGNTH                           00670000
W2F1SREG DS    CL5           SANITATION REGULAR PICK-UP               00680012
\*                                                                      00690000
*********************************************************************   00700000
         ORG   W2F1SCH+2     PATCH FOR FUNCTION 1E FIELDS             00710000
*********************************************************************   00720000
\*                                                                      00730000
W2F1EED  DS    CL3           ELECTION DISTRICT                        00740000
W2F1EAD  DS    CL2           ASSEMBLY DISTRICT                        00750000
W2F1ESED DS    CL1           SPLIT E.D. FLAG                          00760000
W2F1ECON DS    CL2           CONGRESSIONAL DISTRICT                   00770000
W2F1ESEN DS    CL2           SENATORIAL DISTRICT                      00780000
W2F1ECIV DS    CL2           CIVIL COURT DISTRICT                     00790000
W2F1ECOU DS    CL2           CITY COUNCIL DISTRICT                    00800000
         DS    CL18                                                   00810000
W2F1ELGC DS    CL2           LOGICAL GROUP CODE (PREFERRED)           00820000
\*                                                                      00830000
*********************************************************************   00840000
         ORG   W2LAYOUT      RESET LOCATION COUNTER FOR FUNCTION 2    00850000
*********************************************************************   00860000
\*                                                                      00870000
W2F2DUPI DS    CL1           DUPLICATE INTERSECT FLAG                 00880000
         DS    CL9           FILLER                                   00890000
W2F2LGC1 DS    CL2           STREET 1 PREFERRED LGC                   00900013
W2F2LGC2 DS    CL2           STREET 2 PREFERRED LGC                   00910013
W2F2#INT DS    CL1           NUMBER OF INTERSECTING STREETS           00920000
W2F2CODE DS    CL20          INTERSECTING PB5SC'S                     00930000
W2F2CDIR DS    CL1           COMPASS DIRECTION OF TWO LOWEST STREETS  00940011
W2F2LEVC DS    CL10          LEVEL CODES ASSOCIATED WITH CROSS STREETS 00941022
         DS    CL2           WAS INSTRUCTIONAL DIVISION               00950046
W2F2FS   DS    CL2           FIRE DIVISION                            00960003
W2F2FB   DS    CL2           FIRE BATTALION                           00970000
W2F2FC   DS    0CL4          FIRE COMPANY                             00980000
```

```
W2F2FCT  DS     CL1          FIRE COMPANY TYPE                        00990000
W2F2FCN  DS     CL3          FIRE COMPANY NUMBER                      01000000
W2F2CD   DS    0CL3          COMMUNITY DISTRICT                       01010000
W2F2CDB  DS     CL1          COMMUNITY DISTRICT BORO                  01020000
W2F2CDN  DS     CL2          COMMUNITY DISTRICT NUMBER                01030000
W2F2ZIP  DS    CL5           ZIP CODE                                 01040000
W2F2SLA  DS    CL1           STREET LIGHT AREA                        01050000
W2F2CT10 DS    CL6           2010 CENSUS TRACT                        01060037
         DS    CL3           FILLER                                   01080000
W2F2HA   DS    CL4           HEALTH AREA                              01090045
         DS    CL9           FILLER                                   01100010
W2F2NDNB DS    CL7           LION NODE NUMBER                         01110010
W2F2XCOR DS    CL7           X COORDINATE                             01120000
W2F2YCOR DS    CL7           Y COORDINATE                             01130000
         DS    CL4           FILLER                                   01150013
W2F2POL  DS    0CL4          POLICE DISTRICT                          01160000
W2F2PBC  DS     CL1          POLICE PATROL BORO COMMAND               01170000
W2F2POP  DS     CL3          POLICE PRECINCT                          01180000
W2F2SCH  DS    CL2           SCHOOL DISTRICT                          01190000
W2F2MHRI DS    CL1           MARBLE HILL/RIKERS ISLAND FLAG           01200000
W2F2CT90 DS    CL6           1990 CENSUS TRACT                        01210000
W2F2SVP1 DS    0CL8          FIRST SANBORN BOROUGH, PAGE, VOLUME      01220003
W2F2SB1  DS    CL1           FIRST SANBORN BOROUGH CODE               01230003
W2F2SP1  DS    CL3           FIRST SANBORN PAGE                       01240003
W2F2SV1  DS    CL4           FIRST SANBORN VOLUME                     01250003
W2F2SVP2 DS    0CL8          SECOND SANBORN BOROUGH, PAGE, VOLUME     01260003
W2F2SB2  DS    CL1           SECOND SANBORN BOROUGH CODE              01270003
W2F2SP2  DS    CL3           SECOND SANBORN PAGE                      01280003
W2F2SV2  DS    CL4           SECOND SANBORN VOLUME                    01290003
W2F2DID  DS    CL5           DUPLICATE INTERSECTION DISTANCE          01291034
W2F2T00  DS    CL6           2000 CENSUS TRACT                        01292040
         DS    CL27          FILLER                                   01300034
\*                                                                     01310000
*********************************************************************  01320000
         ORG   W2LAYOUT      RESET LOCATION COUNTER FOR FUNCTION 3    01330000
*********************************************************************  01340000
\*                                                                     01350000
W2F3DUPF DS    CL1           DUPLICATE KEY FLAG                       01360013
W2F3CURV DS    CL1           CURVE FLAG                               01361014
W2F3LST  DS    CL1           LOCATIONAL STATUS                        01362018
W2F3CBI  DS    CL1           COUNTY BOUNDARY INDICATOR                01363017
W2F3CSC  DS    CL1           COINCIDENT SEGMENT COUNT                 01364028
         DS    CL3                                                    01370028
W2F3LGC1 DS    CL2           STREET 1 PREFERRED LGC                   01380013
W2F3LGC2 DS    CL2           STREET 2 PREFERRED LGC                   01390013
```

```
W2F3LGC3 DS    CL2          STREET 3 PREFERRED LGC                    01400013
W2F3#STL DS    CL1          NUMBER OF CROSS STREETS AT LOW END        01410000
W2F3CDEL DS    CL20         CROSS STREET PB5SC'S AT LOW END           01420000
W2F3#STH DS    CL1          NUMBER OF CROSS STREETS AT HIGH END       01430000
W2F3CDEH DS    CL20         CROSS STREET PB5SC'S AT HIGH END          01440000
W2F3SLA  DS    CL1          STREET LIGHT AREA                         01450000
W2F3REVF DS    CL1          REVERSAL FLAG                             01460000
W2F3CDL  DS    0CL3         LEFT COMMUNITY DISTRICT                   01470000
W2F3CDBL DS    CL1          LEFT COMMUNITY DISTRICT BORO              01480006
W2F3CDNL DS    CL2          LEFT COMMUNITY DISTRICT NUMBER            01490006
W2F3CDR  DS    0CL3         RIGHT COMMUNITY DISTRICT                  01500000
W2F3CDBR DS     CL1         RIGHT COMMUNITY DISTRICT BORO             01510006
W2F3CDNR DS     CL2         RIGHT COMMUNITY DISTRICT NUMBER           01520006
W2F3ZIPL DS    CL5          LEFT ZIP CODE                             01530000
W2F3ZIPR DS    CL5          RIGHT ZIP CODE                            01540000
         DS    CL18         FILLER - FORMER 1980 CENSUS GEOGRAPHY     01541015
W2F3HAL  DS    CL4          LEFT HEALTH AREA                          01610045
W2F3HAR  DS    CL4          RIGHT HEALTH AREA                         01620045
         DS    CL2          WAS LEFT INSTRUCTIONAL DIVISION           01630046
         DS    CL2          WAS RIGHT INSTRUCTIONAL DIVISION          01631046
W2F3LO#L DS    CL7          LEFT LOW HOUSE NUMBER                     01640000
W2F3HI#L DS    CL7          LEFT HIGH HOUSE NUMBER                    01650000
W2F3LO#R DS    CL7          RIGHT LOW HOUSE NUMBER                    01660000
W2F3HI#R DS    CL7          RIGHT HIGH HOUSE NUMBER                   01670000
W2F3PAR  DS    CL1          CONTINUOUS PARITY INDICATOR               01680000
W2F3FACE DS    CL4          LION FACE CODE                            01690000
W2F3SEQ  DS    CL5          LION SEQUENCE NUMBER                      01700000
W2F3GEN  DS    CL1          GENERATED RECORD FLAG                     01710000
W2F3SEGL DS    PL3          SEGMENT LENGTH IN FEET                    01720000
W2F3SLOP DS    CL3          SEGMENT SLOPE IN DEGREES                  01730000
W2F3ORNT DS    CL1          SEGMENT ORIENTATION                       01740000
         DS    CL4          FILLER                                    01750013
RES2     DS    CL2          RESERVED FOR DCP/GSS USE                  01770000
         ORG   RES2                                                   01770130
W2F3ELCD DS    CL2          COMMUNITY DEVELOPMENT ELIGIBILITY         01770231
W2F3DGLG DS    CL1          DOG LEG FLAG                              01771015
W2F3FEAT DS    CL1          FEATURE TYPE CODE                         01780024
W2F3POLL DS    0CL4         LEFT POLICE DISTRICT                      01790000
W2F3PBCL DS     CL1         LEFT POLICE PATROL BORO COMMAND           01800000
W2F3POPL DS     CL3         LEFT POLICE PRECINCT                      01810000
W2F3POLR DS    0CL4         RIGHT POLICE DISTRICT                     01820000
W2F3PBCR DS     CL1         RIGHT POLICE PATROL BORO COMMAND          01830000
W2F3POPR DS     CL3         RIGHT POLICE PRECINCT                     01840000
W2F3SCHL DS    CL2          LEFT SCHOOL DISTRICT                      01850000
W2F3SCHR DS    CL2          RIGHT SCHOOL DISTRICT                     01860000
```

```
W2F3MHRI DS    CL1          MARBLE HILL/RIKERS ISLAND FLAG            01870000
W2F3SEGT DS    CL7          SEGMENT IDENTIFIER                        01871015
W2F3STC  DS    CL1          SEGMENT TYPE CODE                         01880026
\*                                                                     01890000
*****************************************************************    01900000
         ORG   W2LAYOUT     RESET LOCATION COUNTER FOR FUNCTION 3C    01910000
*****************************************************************    01920000
\*                                                                     01930000
W23CCURV DS    CL1          CURVE FLAG                                01931014
W23CSTC  DS    CL1          SEGMENT TYPE CODE                         01932026
W23CLST  DS    CL1          LOCATIONAL STATUS                         01933018
W23CCBI  DS    CL1          COUNTY BOUNDARY INDICATOR                 01934017
W23CCSC  DS    CL1          COINCIDENT SEGMENT COUNT                  01935028
         DS    CL3          FILLER                                    01940028
W23CLGC1 DS    CL2          STREET 1 PREFERRED LGC                    01950013
W23CLGC2 DS    CL2          STREET 2 PREFERRED LGC                    01960013
W23CLGC3 DS    CL2          STREET 3 PREFERRED LGC                    01970013
W23C#STL DS    CL1          NUMBER OF CROSS STREETS AT LOW END        01980000
W23CCDEL DS    CL20         UP TO FIVE PB5SC'S FOR LOW END            01990000
W23C#STH DS    CL1          NUMBER OF CROSS STREETS AT HIGH END       02000000
W23CCDEH DS    CL20         UP TO FIVE PB5SC'S FOR HIGH END           02010000
W23CCD   DS    0CL3         COMMUNITY DISTRICT                        02020000
W23CCDB  DS     CL1         COMMUNITY DISTRICT BORO                   02030000
W23CCDN  DS     CL2         COMMUNITY DISTRICT NUMBER                 02040000
W23CZIP  DS    CL5          ZIP CODE                                  02050000
W23CSLA  DS    CL1          STREET LIGHT AREA                         02060000
W23CT00  DS    CL6          2000 CENSUS TRACT -                       02070040
         DS    CL1          FILLER                                    02080034
W23CCT10 DS    CL6          2010 CENSUS TRACT                         02100037
W23CCB10 DS    CL4          2010 CENSUS BLOCK                         02110037
W23CCBS1 DS    CL1          2010 CENSUS BLOCK SUFFIX NOT IMPLEMENTED  02111042
W23CHA   DS    CL4          HEALTH AREA                               02120045
W23CREVF DS    CL1          CROSS STREET REVERSAL FLAG                02130005
W23CSOS  DS    CL1          SIDE OF STREET INDICATOR                  02140005
W23CFS   DS    CL2          FIRE DIVISION                             02150003
W23CFB   DS    CL2          FIRE BATTALION                            02160000
W23CFC   DS    0CL4         FIRE COMPANY                              02170000
W23CFCT  DS     CL1         FIRE COMPANY TYPE                         02180000
W23CFCN  DS     CL3         FIRE COMPANY NUMBER                       02190000
W23CSEGT DS    CL7          SEGMENT IDENTIFIER                        02200015
W23CHSEL DS    CL7          LOW HOUSE NUMBER                          02210000
W23CHSEH DS    CL7          HIGH HOUSE NUMBER                         02220000
W23CHS2L DS    CL7          2ND LOW HSE # - USED IF ODD & EVEN RANGES 02230000
W23CHS2H DS    CL7          2ND HI HSE #    ARE ON SAME SIDE OF STREET 02240000
W23CPAR  DS    CL1          CONTINUOUS PARITY INDICATOR               02250000
```

```
W23CFACE DS    CL4          LION FACE CODE                          02260000
W23CSEQ  DS    CL5          LION SEQUENCE NUMBER                    02270000
W23CGEN  DS    CL1          GENERATED RECORD FLAG                   02280000
W23CSEGL DS    PL3          SEGMENT LENGTH IN FEET                  02290000
W23CSLOP DS    CL3          SEGMENT SLOPE IN DEGREES                02300000
W23CORNT DS    CL1          SEGMENT ORIENTATION                     02310000
         DS    CL2          WAS INSTRUCTIONAL DIVISION              02320046
RES3     DS    CL1          RESERVED FOR DCP/GSS USE                02330000
         ORG   RES3                                                 02331030
W23CELCD DS    CL1          COMMUNITY DEVELOPMENT ELIGIBILITY       02332031
W23CFEAT DS    CL1          FEATURE TYPE CODE                       02340024
W23CPOL  DS    0CL4         POLICE DISTRICT                         02350000
W23CPBC  DS     CL1         POLICE PATROL BORO COMMAND              02360000
W23CPOP  DS     CL3         POLICE PRECINCT                         02370000
W23CSCH  DS    CL2          SCHOOL DISTRICT                         02380000
W23CMHRI DS    CL1          MARBLE HILL/RIKERS ISLAND FLAG          02390000
W23CCT90 DS    CL6          1990 CENSUS TRACT                       02400000
         DS    CL4          FILLER                                  02410015
W23CCPB  DS    CL3          DYNAMIC BLOCK/ATOMIC POLYGON            02440038
W23CB00  DS    CL4          2000 CENSUS BLOCK                       02441040
W23CS00  DS    CL1          2000 CENSUS BLOCK SUFFIX                02442040
\*                                                                   02460000
*******************************************************************  02470000
         ORG   W2BAL        RESET LOCATION COUNTER FOR FUNCTION 5   02480000
*******************************************************************  02490000
\*                                                                   02500000
W2F5AMK  DS    CL28         ACCESS MATCHING KEY                     02510000
         DS    CL172        FILLER                                  02520000
W2END    EQU   *                                                   02530000
W2LENGTH EQU   W2END-W2BAL  LENGTH OF W2BAL                          02540000
```

W2BALL COPY File

```
\*/*******************************************************************/ 00000100
\*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE W2BALL,   \***/ 00000200
\*/*****  CONTAINING THE LAYOUT OF THE OPTIONAL LONG WORK AREA 2    \***/ 00000300
\*/*****  FOR FUNCTIONS 1 AND 3.                                   \***/ 00000400
\*/*******************************************************************/ 00000500
\*/*****         LAST UPDATED JANUARY 2012                         \***/ 00000603
\*/*******************************************************************/ 00000702
W2BALL   DS   0H                                                     00000802
W2LACKEY DS    CL21         ACCESS KEY                              00100000
W21LCPAR DS     CL1         CONTINUOUS PARITY INDICATOR             00120002
W21LLHNI DS    0CL6         LOW HOUSE NUMBER                        00130000
W21LHSEL DS     CL5         LOW HOUSE NUMBER ON BLOCK FACE          00140000
```

```
W21LSFXL DS     CL1          LOW HOUSE NUMBER SUFFIX                    00150013
W21LHHNI DS    0CL6          HIGH HOUSE NUMBER                          00160000
W21LHSEH DS     CL5          HIGH HOUSE NUMBER ON BLOCK FACE            00170000
W21LSFXH DS     CL1          HI HOUSE NUMBER SUFFIX                     00180013
W21LALX  DS    CL1           A=ALLEYS INTERSECT SEGMENT                 00190000
*                            X=CROSS STREETS MODIFIED
W21L#STL DS    CL1           NUMBER OF CROSS STREETS AT LOW END         00200000
W21LCDEL DS    CL20          UP TO FIVE PB5SC'S FOR LOW END             00210000
W21L#STH DS    CL1           NUMBER OF CROSS STREETS AT HIGH END        00220000
W21LCDEH DS    CL20          UP TO FIVE PB5SC'S FOR HIGH END            00230000
W21LCD   DS    0CL3          COMMUNITY DISTRICT                         00240000
W21LCDB  DS     CL1          COMMUNITY DISTRICT BORO                    00250000
W21LCDN  DS     CL2          COMMUNITY DISTRICT NUMBER                  00260000
W21LZIP  DS    CL5           ZIP CODE                                   00270000
W21LSLA  DS    CL1           STREET LIGHT AREA                          00280000
W21LHCD  DS    CL2           HEALTH CODE DISTRICT                       00290000
W21LSOS  DS    CL1           SIDE OF STREET INDICATOR                   00300000
W21LPAR  DS    CL1           CONTINUOUS PARITY INDICATOR                00310000
W21LCT10 DS    CL6           2010 CENSUS TRACT                          00320015
W21LCB10 DS    CL4           2010 CENSUS BLOCK                          00350015
W21LCBS1 DS    CL1           2010 CENSUS BLOCK SUFFIX                   00351015
         DS    CL3           FILLER                                     00352015
W21LHA   DS    CL4           HEALTH AREA                                00360000
W21LSREC DS    CL3           SANITATION RECYCLE PICK-UP                 00370007
W21LFEAT DS    CL1           FEATURE TYPE CODE                          00380007
RES1L    DS    CL1           RESERVED FOR DCP/GSS USE                   00400000
         ORG   RES1L
W21LELCD DS    CL1           COMMUNITY DEVELOPMENT ELIGIBILITY
W21LCURV DS    CL1           CURVE FLAG                                 00410014
W21LPOL  DS    0CL4          POLICE DISTRICT                            00420000
W21LPBC  DS     CL1          POLICE PATROL BORO COMMAND                 00430000
W21LPOP  DS     CL3          POLICE PRECINCT                            00440000
W21LSCH  DS    CL2           SCHOOL DISTRICT                            00450000
         DS    CL14         RESERVED FOR POLITICAL INFORMATION          00460013
W21LCSC  DS    CL1           COINCIDENT SEGMENT COUNT
W21LSTC  DS    CL1           SEGMENT TYPE CODE
W21LSAND DS    CL3           SANITATION DISTRICT                        00470002
W21LSANT DS    CL2           SANITATION DEPT SUBSECTION                 00480000
W21LFS   DS    CL2           FIRE DIVISION                              00490001
W21LFB   DS    CL2           FIRE BATTALION                             00500000
W21LFC   DS    0CL4          FIRE COMPANY                               00510000
W21LFCT  DS     CL1          FIRE COMPANY TYPE                          00520000
W21LFCN  DS     CL3          FIRE COMPANY NUMBER                        00530000
W21LSPAD DS    CL1           SPECIAL ADDRESS FLAG                       00540000
W21LMHRI DS    CL1           MARBLE HILL/RIKERS ISLAND FLAG             00550000
```

```
W21LFILS DS    CL1          FILLER-WAS SPLIT SCHOOL DISTRICT FLAG      00560000
W21LLGC  DS    CL2          LOGICAL GROUP CODE (PREFERRED)             00570000
W21LFACE DS    CL4          LION FACE CODE                             00580000
W21LSEQ  DS    CL5          LION SEQUENCE NUMBER                       00590000
W21LCT90 DS    CL6          1990 CENSUS TRACT                          00600000
         DS    CL4          FILLER                                     00610015
W21LCPB  DS    CL3          DYNAMIC BLOCK/ATOMIC POLYGON               00640000
W21LXCOR DS    CL7          X COORDINATE                               00650000
W21LYCOR DS    CL7          Y COORDINATE                               00660000
W21LSEGL DS    CL5          SEGMENT LEGNTH                             00670000
W21LSREG DS    CL5          SANITATION REGULAR PICK-UP                 00680012
W21LSEGT DS    CL7          SEGMENT IDENTIFIER
W21LB7SC DS    CL8          "TRUE" BOROUGH AND 7 DIGIT STREET CODE
W21LHNI  DS    CL6          UNDERLYING HOUSE NUMBER
W21LT00  DS    CL6          2000 CENSUS TRACT                          00320015
W21LB00  DS    CL4          2000 CENSUS BLOCK                          00350015
W21LS00  DS    CL1          2000 CENSUS BLOCK SUFFIX                   00351015
         DS    CL68         FILLER - FUTURE USE
\*                                                                       00690000
*********************************************************************   00700000
         ORG   W21LSCH+2    PATCH FOR FUNCTION 1E FIELDS               00710000
*********************************************************************   00720000
\*                                                                       00730000
W21LEED  DS    CL3          ELECTION DISTRICT                          00740000
W21LEAD  DS    CL2          ASSEMBLY DISTRICT                          00750000
W21LESED DS    CL1          SPLIT E.D. FLAG                            00760000
W21LECON DS    CL2          CONGRESSIONAL DISTRICT                     00770000
W21LESEN DS    CL2          SENATORIAL DISTRICT                        00780000
W21LECIV DS    CL2          CIVIL COURT DISTRICT                       00790000
W21LECOU DS    CL2          CITY COUNCIL DISTRICT                      00800000
         DS    CL18                                                    00810000
W21LELGC DS    CL2          LOGICAL GROUP CODE (PREFERRED)             00820000
\*                                                                       00830000
*********************************************************************   00840000
         ORG   W2LACKEY     RESET LOCATION COUNTER FOR FUNCTION 3      00850000
*********************************************************************   00860000
\*                                                                       00870000
         DS    CL21                                                    00000902
W23LDUPF DS    CL1          DUPLICATE KEY FLAG                         00001002
W23LCURV DS    CL1          CURVE FLAG                                 00001103
W23LLST  DS    CL1          LOCATION STATUS OF SEGMENT
W23LCBI  DS    CL1          COUNTY BOUNDARY INDICATOR
W23LCSC  DS    CL1          COINCIDENT SEGMENT COUNT
         DS    CL3                                                     00001203
W23LLGC1 DS    CL2          STREET 1 PREFERRED LGC                     00001302
```

```
W23LLGC2 DS    CL2          STREET 2 PREFERRED LGC                    00001402
W23LLGC3 DS    CL2          STREET 3 PREFERRED LGC                    00001502
W23L#STL DS    CL1          NUMBER OF CROSS STREETS AT LOW END        00001602
W23LCDEL DS    CL20         CROSS STREET PB5SC'S AT LOW END           00001702
W23L#STH DS    CL1          NUMBER OF CROSS STREETS AT HIGH END       00001802
W23LCDEH DS    CL20         CROSS STREET PB5SC'S AT HIGH END          00001902
W23LSLA  DS    CL1          STREET LIGHT AREA                         00002002
W23LREVF DS    CL1          REVERSAL FLAG                             00002102
W23LCDL  DS    0CL3         LEFT COMMUNITY DISTRICT                   00002202
W23LCDBL DS     CL1         LEFT COMMUNITY DISTRICT BORO              00002302
W23LCDNL DS     CL2         LEFT COMMUNITY DISTRICT NUMBER            00002402
W23LCDR  DS    0CL3         RIGHT COMMUNITY DISTRICT                  00002502
W23LCDBR DS     CL1         RIGHT COMMUNITY DISTRICT BORO             00002602
W23LCDNR DS     CL2         RIGHT COMMUNITY DISTRICT NUMBER           00002702
W23LZIPL DS    CL5          LEFT ZIP CODE                             00002802
W23LZIPR DS    CL5          RIGHT ZIP CODE                            00002902
         DS    CL18
W23LHAL  DS    CL4          LEFT HEALTH AREA                          00003602
W23LHAR  DS    CL4          RIGHT HEALTH AREA                         00003702
         DS    CL2          WAS LEFT INSTRUCTIONAL DIVISION           00003802
         DS    CL2          WAS RIGHT INSTRUCTIONAL DIVISION
W23LLO#L DS    CL7          LEFT LOW HOUSE NUMBER                     00003902
W23LHI#L DS    CL7          LEFT HIGH HOUSE NUMBER                    00004002
W23LLO#R DS    CL7          RIGHT LOW HOUSE NUMBER                    00004102
W23LHI#R DS    CL7          RIGHT HIGH HOUSE NUMBER                   00004202
W23LPAR  DS    CL1          CONTINUOUS PARITY INDICATOR               00004302
W23LFACE DS    CL4          LION FACE CODE                            00004402
W23LSEQ  DS    CL5          LION SEQUENCE NUMBER                      00004502
W23LGEN  DS    CL1          GENERATED RECORD FLAG                     00004602
W23LSEGL DS    PL3          SEGMENT LENGTH IN FEET                    00004702
W23LSLOP DS    CL3          SEGMENT SLOPE IN DEGREES                  00004802
W23LORNT DS    CL1          SEGMENT ORIENTATION                       00004902
         DS    CL4          FILLER                                    00005002
RESL1    DS    CL2          RESERVED FOR DCP/GSS USE                  00005102
         ORG   RESL1
W23LELCD DS    CL2          COMMUNITY DEVELOPMENT ELIGIBILITY
W23LDGLG DS    CL1          DOG LEG FLAG
W23LFEAT DS    CL1          FEATURE TYPE CODE                         00005202
W23LPOLL DS    0CL4         LEFT POLICE DISTRICT                      00005302
W23LPBCL DS     CL1         LEFT POLICE PATROL BORO COMMAND           00005402
W23LPOPL DS     CL3         LEFT POLICE PRECINCT                      00005502
W23LPOLR DS    0CL4         RIGHT POLICE DISTRICT                     00005602
W23LPBCR DS     CL1         RIGHT POLICE PATROL BORO COMMAND          00005702
W23LPOPR DS     CL3         RIGHT POLICE PRECINCT                     00005802
W23LSCHL DS    CL2          LEFT SCHOOL DISTRICT                      00005902
```

```
W23LSCHR DS    CL2           RIGHT SCHOOL DISTRICT                      00006002
W23LMHRI DS    CL1           MARBLE HILL / RIKERS ISLAND                00006102
W23LSEGT DS    CL7           SEGMENT IDENTIFIER
W23LSTC  DS    CL1           SEGMENT TYPE CODE                          00006202
W23LT90L DS    CL6           1990 LEFT CENSUS TRACT                     00006302
         DS    CL4           FILLER
W23LCPBL DS    CL3           CURRENT LEFT DYNAMIC BLOCK/ATOMIC POLYGON  00006702
W23LT90R DS    CL6           1990 RIGHT CENSUS TRACT                    00006802
         DS    CL4           FILLER
W23LCPBR DS    CL3           CURRENT RIGHT DYNAMIC BLOCK/ATOMIC POLYGON 00007202
W23LFSL  DS    CL2           LEFT FIRE DIVISION                         00007302
W23LFBL  DS    CL2           LEFT FIRE BATTALION                        00007402
W23LFCL  DS    0CL4          LEFT FIRE COMPANY                          00007502
W23LFCTL DS     CL1          LEFT FIRE COMPANY TYPE                     00007602
W23LFCNL DS     CL3          LEFT FIRE COMPANY NUMBER                   00007702
W23LFSR  DS    CL2           RIGHT FIRE DIVISION                        00007802
W23LFBR  DS    CL2           RIGHT FIRE BATTALION                       00007902
W23LFCR  DS    0CL4          RIGHT FIRE COMPANY                         00008002
W23LFCTR DS     CL1          RIGHT FIRE COMPANY TYPE                    00008102
W23LFCNR DS     CL3          RIGHT FIRE COMPANY NUMBER                  00008202
W23LT10L DS    CL6           LEFT 2010 CENSUS TRACT
W23LB10L DS    CL4           LEFT 2010 CENSUS BLOCK
W23LBS1L DS    CL1           LEFT 2010 CENSUS BLOCK SUFFIX
W23LT10R DS    CL6           RIGHT 2010 CENSUS TRACT
W23LB10R DS    CL4           RIGHT 2010 CENSUS BLOCK
W23LBS1R DS    CL1           RIGHT 2010 CENSUS BLOCK SUFFIX
W23FNODE DS    CL7           FROM NODE
W23TNODE DS    CL7           TO NODE
W23L00TL DS    CL6           LEFT 2000 CENSUS TRACT
W23L00BL DS    CL4           LEFT 2000 CENSUS BLOCK
W23L00SL DS    CL1           LEFT 2000 CENSUS BLOCK SUFFIX
W23L00TR DS    CL6           RIGHT 2000 CENSUS TRACT
W23L00BR DS    CL4           RIGHT 2000 CENSUS BLOCK
W23L00SR DS    CL1           RIGHT 2000 CENSUS BLOCK SUFFIX
W23LEND  EQU   *                                                        00008402
W23LLEN  EQU   W23LEND-W2BALL    LENGTH OF W2BALL                       00008502
```

W2BAL1A COPY File

```
\*/*********************************************************************/ 00000100
\*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE W2BAL1A,  \***/ 00000200
\*/*****  CONTAINING THE LAYOUT OF WORK AREA 2 FOR FUNCTION         \***/ 00000300
\*/*****  1A, BL AND BN WHICH SHARE A SINGLE WORK AREA 2 LAYOUT.    \***/ 00000408
\*/*********************************************************************/ 00000500
\*/*****          LAST UPDATED 5 MARCH 2009                         \***/ 00000608
```

```
\*/*****************************************************************/ 00000703
W2BAL1A  DS   0H                                                     00000803
         DS    CL21                                                  00000903
W21ACPAR DS    CL1          CONTINUOUS PARITY INDICATOR              00001003
W21AHSEL DS    CL6          LOW HOUSE NUMBER ON BLOCK                00001103
W21AALT1 DS   0CL10         ALTERNATE KEY                            00001203
W21ABOR1 DS    CL1          ALTERNATE KEY - BORO                     00001303
W21ATXB1 DS    CL5          ALTERNATE KEY - TAX BLOCK                00001403
W21ATXL1 DS    CL4          ALTERNATE KEY - TAX LOT                  00001503
         DS    CL1             FILLER                                00001603
W21ARSCC DS    CL1          RPAD SCC                                 00001703
         DS    CL1          FILLER                                   00001803
W21AGLI  DS   0CL11         GENERAL LOT INFO                         00001903
W21ARBLC DS    CL2          RPAD BUILDING CLASSIFICATION             00002003
W21ACORC DS    CL2          CORNER CODE                              00002103
W21A#STC DS    CL2          TOTAL NUMBER STRUCTURES                  00002203
W21A#BFA DS    CL2          TOTAL NUMBER BLOCKFACES                  00002303
W21AINTF DS    CL1          INTERIOR LOT FLAG                        00002403
W21AVACF DS    CL1          VACANT LOT FLAG                          00002503
W21AIRLF DS    CL1          IRREGULARLY-SHAPED LOT FLAG              00002603
W21AMHRI DS    0CL1         MARBLE HILL/RIKERS ISLAND FLAG           00002703
W21AABFL DS    CL1          ALTERNATE BORO FLAG                      00002803
         DS    CL1          STROLLING FLAG  (W21ASTRF)               00002903
W21ASTRK DS    CL13         STROLLING KEY                            00003003
W21AOVFL DS    CL1          ADDRESS RANGE LIST OVERFLOW FLAG         00003103
W21ARFIU DS    CL1          RESERVED FOR INTERNAL USE                00003203
W21ABIN  DS    CL7          BUILDING IDENTIFICATION NUMBER (BIN)     00003303
W21ACONF DS    CL1          CONDO LOT FLAG                           00003403
W21ARCO# DS    CL4          RPAD CONDO NUMBER                        00003503
W21ACLBL DS    CL10         CONDO LOW BBL                            00003603
         DS    CL1             FILLER                                00003703
W21ACBBL DS    CL10         CONDO BILLING BBL                        00003803
         DS    CL1             FILLER                                00003903
W21ACBBS DS    CL1          CONDO BILLING BBL SCC                    00004003
W21ACHBL DS    CL10         CONDO HIGH BBL                           00004103
         DS    CL1             FILLER                                00004203
W21ASBVP DS    CL8          SANDBORN BOROUGH/VOLUME/PAGE             00004303
W21ABUSA DS    CL5          BUSINESS AREA                            00004403
W21ACOOP DS    CL4          COOP ID NUMBER                           00004503
         DS    CL4             FILLER                                00004605
W21ANBST DS    CL4          ACTUAL TOTAL NBR OF BLDGS ON LOT         00004704
W21ATAXB DS    CL1          TAX MAP BOROUGH                          00004805
W21ATAXM DS    CL4          TAX MAP NBR - SECTION AND VOLUME         00004905
         DS    CL4          RESERVED FOR TAX MAP PAGE NUMBER         00005005
W21AXCO  DS    CL7          X COORDINATE OF ANNOTATION POINT         00005107
```

```
W21AYCO  DS    CL7           Y COORDINATE OF ANNOTATION POINT          00005207
W21ABID  DS    CL6           BUSINESS IMPROVEMENT DISTRICT             00005308
         DS    CL2              FILLER                                 00005408
W21AINT  DS    CL10          INTERNAL USE                              00005508
W21A#ADR DS    CL2           TOTAL ADDRESSES FOR LOT                   00005603
W21ALIST DS   0CL756         LIST OF ADDRESSES, MAXIMUM OF 21          00005703
W21ALOW# DS    CL6           LOW HOUSE NUMBER                          00005803
         DS    CL3              FILLER                                 00005903
W21AHI#  DS    CL6           HIGH HOUSE NUMBER                         00006003
         DS    CL3           FILLER                                    00006103
W21ACODE DS    CL8           STREET CODE                               00006203
W21ALBIN DS    CL7           LIST BIN                                  00006303
W21AATYP DS    CL1           ADDRESS TYPE                              00006403
         DS    CL1           FILLER                                    00006503
W21ALSOS DS    CL1           LIST SOS                                  00006603
*  STORAGE IS RESERVED FOR THE REMAINING 20 ADDRESS STRUCTURES.        00006703
*  EACH STRUCTURE IS IDENTICAL TO THE ONE DEFINED ABOVE.               00006803
         DS    CL720         REMAINING ADDRESSES                       00006903
W21AEND  EQU   *                                                       00007003
W21ALEN  EQU   W21AEND-W2BAL1A    LENGTH OF W2BAL1A                    00008003
```

W2BAL1AL COPY File

```
\*/*********************************************************************/ 00000100
\*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE W2BAL1AL, \***/ 00000200
\*/*****  CONTAINING THE LONG LAYOUT OF WORK AREA 2 FOR FUNCTION    \***/ 00000300
\*/*****  1A, BL and BN WHICH SHARE A SINGLE WORK AREA 2 LAYOUT.    \***/ 00000416
\*/*********************************************************************/ 00000500
\*/*****        Last Updated 5 March 2009                          \***/ 00000616
\*/*********************************************************************/ 00000710
W2BAL1AL DS   0H                                                       00000810
         DS    CL21                                                    00000910
W21ALCPA DS    CL1           CONTINUOUS PARITY INDICATOR               00001010
W21ALHSE DS    CL6           LOW HOUSE NUMBER ON BLOCK                 00001110
W21ALALT DS   0CL10          ALTERNATE KEY                             00001210
W21ALBOR DS    CL1           ALTERNATE KEY - BORO                      00001310
W21ALTXB DS    CL5           ALTERNATE KEY - TAX BLOCK                 00001410
W21ALTXL DS    CL4           ALTERNATE KEY - TAX LOT                   00001510
         DS    CL1              FILLER                                 00001610
W21ALRSC DS    CL1           RPAD SCC                                  00001710
         DS    CL1           FILLER                                    00001810
W21ALGLI DS   0CL11          GENERAL LOT INFO                          00001910
W21ALRBL DS    CL2           RPAD BUILDING CLASSIFICATION              00002010
W21ALCOR DS    CL2           CORNER CODE                               00002110
W21AL#ST DS    CL2           TOTAL NUMBER STRUCTURES                   00002210
```

```
W21AL#BF DS    CL2          TOTAL NUMBER BLOCKFACES                  00002310
W21ALINT DS    CL1          INTERIOR LOT FLAG                        00002410
W21ALVAC DS    CL1          VACANT LOT FLAG                          00002510
W21ALIRL DS    CL1          IRREGULARLY-SHAPED LOT FLAG              00002610
W21ALMHR DS    0CL1         Marble Hill/Rikers Island Flag           00002710
W21ALABF DS    CL1          ALTERNATE BORO FLAG                      00002810
         DS    CL1          STROLLING FLAG  (W21ALSTRF)              00002910
W21ALSTR DS    CL13         STROLLING KEY                            00003010
         DS    CL1             FILLER                                00003110
W21ALRFI DS    CL1          RESERVED FOR INTERNAL USE                00003210
W21ALNGB DS    CL7          BUILDING IDENTIFICATION NUMBER (BIN)     00003310
W21ALCON DS    CL1          CONDO LOT FLAG                           00003410
W21ALRCO DS    CL4          RPAD CONDO NUMBER                        00003510
W21ALCLB DS    CL10         CONDO LOW BBL                            00003610
         DS    CL1             FILLER                                00003710
W21ALCBB DS    CL10         CONDO BILLING BBL                        00003810
         DS    CL1             FILLER                                00003910
W21ALCBS DS    CL1          CONDO BILLING BBL SCC                    00004010
W21ALCHB DS    CL10         CONDO HIGH BBL                           00004110
         DS    CL1             FILLER                                00004210
W21ALSBV DS    CL8          SANDBORN BOROUGH/VOLUME/PAGE             00004310
W21ALBUS DS    CL5          BUSINESS AREA                            00004410
W21ALCOO DS    CL4          COOP ID NUMBER                           00004510
         DS    CL4                                                   00004613
W21ALNBS DS    CL4          Actual Nbr of Bldgs on Lot               00004711
W21ALTMB DS    CL1          TAX MAP BOROUGH                          00004814
W21ALTAX DS    CL4          Tax Map NBR - Section and Volume         00004913
         DS    CL4          RESERVED FOR TAX PAGE NUMBER             00005013
W21ALXCO DS    CL7          X COORDINATE OF ANNOTATION POINT         00005115
W21ALYCO DS    CL7          Y COORDINATE OF ANNOTATION POINT         00005215
W21ALBID DS    CL6          Business Improvement District            00005316
         DS    CL2             FILLER                                00005416
W21ALINU DS    CL8          Internal Use Only                        00005517
W21AL#BN DS    CL4          TOTAL Number of BINS for Lot             00005610
W21ALLST DS    2500CL7      LIST OF BINS, MAXIMUM OF 2500            00005709
W21ALEND EQU   *                                                     00005802
W21ALLEN EQU   W21ALEND-W2BAL1AL    Length of W2BAL1AL               00006002
```

W2BAL3S COPY File

```
\*/*******************************************************************/ 00000100
\*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE W2BAL3S,  \***/ 00000200
\*/*****  CONTAINING THE LAYOUT OF WORK AREA 2 FOR FUNCTION 3S.     \***/ 00000300
\*/*******************************************************************/ 00000400
W2BAL3S  DS   0H                                                       00000500
W23SAKEY DS    CL21          ACCESS KEY                                00000600
W23S#INT DS    CL3           NUMBER OF INTERSECTIONS ON STRETCH        00000700
W23SINT  DS   0CL12          INTERSECTION LAYOUT                       00000800
W23SCDE1 DS    PL4           NUMERICALLY SMALLEST PB5SC                00000900
W23SCDE2 DS    PL4           NUMERICALLY 2ND SMALLEST PB5SC            00001000
W23SDIST DS    PL3           DISTANCE IN FEET FROM PREVIOUS INTERSECT. 00001100
W23SGAPF DS    CL1           GAP FLAG ("G" IF NO SEGMENT CONNECTS THIS 00001200
\*                            INTERSECTION TO THE PREVIOUS ONE)         00001300
\*                                                                      00001400
\*     THE MAXIMUM NUMBER OF INTERSECTIONS IS 350. THE LAYOUT OF EACH   00001500
\*  INTERSECTION IS IDENTICAL TO THE 12 BYTES DEFINED BY "W23SINT".     00001600
\*  RATHER THAN DEFINE 349 MORE INTERSECTIONS, WE ALLOCATE THE STORAGE  00001700
\*  NECESSSARY SHOULD THE MAXIMUM NUMBER OF INTERSECTIONS BY FOUND.     00001800
\*     ALL INTERSECTIONS BUT THE FIRST ONE MUST BE REFERENCED BY        00001900
\*  DISPLACEMENT.                                                       00002000
\*                                                                      00002100
W23SREST DS    CL4188        REMAINING INTERSECTIONS                   00002200
W23SEND  EQU   *                                                       00002300
W23SLEN  EQU   W23SEND-W2BAL3S     LENGTH OF W2BAL3S                   00002400
```

PL/1 COPY Files (MSW)

W1PL1 COPY File

```
/*****************************************************************/  00000100
/***  THIS IS GEOSUPPORT SYSTEM COPY FILE W1PL1, CONTAINING THE \***/  00000200
/\***  LAYOUT OF WORK AREA 1.     COPYLIB2            04/07/98  \***/  00000300
/\*****************************************************************/  00000400
 DCL PW1 POINTER;                                                      00000500
 DCL                                                                   00000600
   1 W1PL1,                                                            00000700
     /*******************************************************/         00000802
     /*****              INPUT  FIELDS                 *****/         00000902
     /*******************************************************/         00001002
     2 GEO_WA1_IN_FUNCTION_CODE,                                       00001100
       3 GEO_WA1_IN_FUNCTION_1          CHAR(1),                      00001200
       3 GEO_WA1_IN_FUNCTION_2          CHAR(1),                      00001300
     2 GEO_WA1_IN_BORO                  CHAR(1),                      00001400
     2 GEO_WA1_IN_HOUSENUM              CHAR(12),/\*HIGH HSE# INPUT*/ 00001500
```

```
2 GEO_WA1_IN_HOUSENUM_INTERNAL      CHAR(6), /\*IF FUNCTION 5  \*/ 00001600
2 GEO_WA1_IN_STREET_1               CHAR(32),                      00001700
2 GEO_WA1_IN_STREET_2               CHAR(32),                      00001800
2 GEO_WA1_IN_STREET_3               CHAR(32),                      00001900
2 GEO_WA1_IN_COMPASS                CHAR(01),                      00002008
2 GEO_WA1_IN_COMPASS2               CHAR(01),                      00002110
2 GEO_WA1_IN_STREETCODE_1           FIXED DEC(6),                  00002200
2 GEO_WA1_IN_STREETCODE_2           FIXED DEC(6),                  00002300
2 GEO_WA1_IN_STREETCODE_3           FIXED DEC(6),                  00002400
2 GEO_WA1_IN_ROADBED_REQ_SWITCH     CHAR(1),                       00002514
2 GEO_WA1_IN_BORO_2                 CHAR(1),                       00002600
2 GEO_WA1_IN_BORO_3                 CHAR(1),                       00002700
2 GEO_WA1_IN_SNL                    CHAR(2),                       00002800
2 GEO_WA1_IN_10SC_1                 CHAR(11),                      00002900
2 GEO_WA1_IN_10SC_2                 CHAR(11),                      00003000
2 GEO_WA1_IN_10SC_3                 CHAR(11),                      00003100
2 GEO_WA1_IN_ZIPIN                  CHAR(5),                       00003215
2 GEO_WA1_IN_BBL,                                                  00003300
  3 GEO_WA1_IN_BL_BORO              CHAR(1),                       00003400
  3 GEO_WA1_IN_BLOCKNUM             CHAR(5),                       00003500
  3 GEO_WA1_IN_LOTNUM               CHAR(4),                       00003600
2 FILLER_W1_010                     CHAR(1),                       00003700
2 GEO_WA1_IN_BIN                    CHAR(7),                       00003802
/*************************************************************/    00003903
/*******------ USAGE NOTES FOR SELECTED FIELDS -------*******/    00004004
/*************************************************************/    00004103
/** GEO_WA1_IN_COMPACT_NAME_FLAG: SET TO "C" TO REQUEST    \**/    00004203
/**     COMPACT NAMES OPTION.                              \**/    00004303
/** GEO_WA1_IN_LONG_WORKAREA2_FLAG: SET TO "L" TO REQUEST  \**/    00004403
/**     THE LONG WORKAREA 2. AT PRESENT, ONLY FUNCTIONS    \**/    00004503
/**     1A AND 3 HAVE THE LONG WA2 OPTION.                 \**/    00004603
/** GEO_WA1_IN_NON_IBM_MAIN_FRAME: SET TO "X" IF           \**/    00004703
/**     APPLICATION IS RUNNING ON A NON-IBM MAIN FRAME.    \**/    00004803
/** GEO_WA1_IN_1ABL_VERSION: SET TO "L" OR " " TO REQUEST  \**/    00004903
/**     THE LEGACY WORKAREA2 FORMAT FOR FUNCTION 1A OR BL. \**/    00005003
/** GEO_WA1_IN_1ABL_VERSION: SET TO "S" TO REQUEST THE     \**/    00005103
/**     STANDARD WORKAREA2 FORMAT FOR FUNCTION 1A OR BL.   \**/    00005203
/*************************************************************/    00005903
2 GEO_WA1_IN_COMPACT_NAME_FLAG      CHAR(1),                       00006000
2 GEO_WA1_IN_LONG_WORKAREA2_FLAG    CHAR(1),                       00006100
2 GEO_WA1_IN_LOW_HOUSENUM           CHAR(12),                      00006200
2 GEO_WA1_IN_LOW_HSENUM_INTERNAL    CHAR(6),                       00006300
2 GEO_WA1_IN_NON_IBM_MAIN_FRAME     CHAR(1),                       00006400
2 GEO_WA1_IN_1ABL_VERSION           CHAR(1),                       00006500
2 GEO_WA1_IN_XSTREET_FLAG           CHAR(1),                       00006610
```

```
    2 FILLER_W1_100                    CHAR(04),                    00006809
    /*******************************************************/       00006902
    /*****                OUTPUT  FIELDS              *****/       00007002
    /*******************************************************/       00007102
    2 GEO_WA1_OUT_LOW_HOUSENUM         CHAR(12),                    00007209
    2 GEO_WA1_OUT_BORONAME             CHAR(9),                     00007300
    2 GEO_WA1_OUT_STREET_1             CHAR(32),                    00007400
    2 GEO_WA1_OUT_STREET_2             CHAR(32),                    00007500
    2 GEO_WA1_OUT_STREET_3             CHAR(32),                    00007600
    2 GEO_WA1_OUT_HOUSENUM             CHAR(12), /\*HI-HND*/         00007709
    2 GEO_WA1_OUT_HOUSENUM_INTERNAL    CHAR(6),                     00007800
    2 FILLER_W1_200                    CHAR(7),                     00007900
    2 GEO_WA1_OUT_PB5SC_1              FIXED DEC(6),                00008006
    2 FILLER_W1_210                    CHAR(2),                     00008300
    2 GEO_WA1_OUT_PB5SC_2              FIXED DEC(6),                00008406
    2 FILLER_W1_220                    CHAR(2),                     00008800
    2 GEO_WA1_OUT_PB5SC_3              FIXED DEC(6),                00008906
    2 GEO_WA1_OUT_STREET_ATTR(3)       CHAR(1),                     00009312
    2 GEO_WA1_BROWSE                   CHAR(40),                    00009400
    2 GEO_WA1_OUT_10SC_1               CHAR(11),                    00009500
    2 GEO_WA1_OUT_10SC_2               CHAR(11),                    00009600
    2 GEO_WA1_OUT_10SC_3               CHAR(11),                    00009700
    2 GEO_WA1_OUT_CUI                  CHAR(5), /\*NOT IMPLEMENTED*/ 00009800
    2 GEO_WA1_OUT_BBL,                                              00009900
      3 GEO_WA1_OUT_BL_BORO            CHAR(1),                     00010000
      3 GEO_WA1_OUT_BLOCKNUM           CHAR(5),                     00010100
      3 GEO_WA1_OUT_LOTNUM             CHAR(4),                     00010200
    2 FILLER_W1_240                    CHAR(1),                     00010300
    2 GEO_WA1_OUT_BIN                  CHAR(7),                     00010411
    2 GEO_WA1_OUT_SND_ATTR             CHAR(1), /\*DCP/GSS USE*/     00010705
    2 GEO_WA1_OUT_REASON_CODE          CHAR(1),                     00010800
    2 FILLER_W1_400                    CHAR(2),                     00010900
    2 GEO_WA1_OUT_RETURN_CODE,                                      00011007
      3 GEO_WA1_OUT_RC_1               CHAR(1),                     00011107
      3 GEO_WA1_OUT_RC_2               CHAR(1),                     00011207
    2 GEO_WA1_OUT_ERROR_MESSAGE        CHAR(80),                    00011400
    2 GEO_WA1_OUT_NUM_SIMILAR_NAMES    FIXED DEC(3),                00011500
    2 GEO_WA1_OUT_SIMILAR_NAMES(10)    CHAR(32);                    00011600
                                                                    00011702
/*************************************************************/     00011801
                                                                    00011902
DCL 1 GEO_WA1_OUT_PB_5SC_1                                          00012006
          BASED (ADDR(GEO_WA1_OUT_PB5SC_1)),                        00012106
      3 GEO_WA1_OUT_PACKBORO_NOSIGN_1  CHAR(1),                     00012206
      3 GEO_WA1_OUT_STREETCODE_1_KEY   FIXED DEC(5),                00012306
```

```
    1 GEO_WA1_OUT_PB_5SC_2                                          00012406
          BASED (ADDR(GEO_WA1_OUT_PB5SC_2)),                        00012506
      3 GEO_WA1_OUT_PACKBORO_NOSIGN_2   CHAR(1),                    00012606
      3 GEO_WA1_OUT_STREETCODE_2_KEY    FIXED DEC(5),               00012706
    1 GEO_WA1_OUT_PB_5SC_3                                          00012806
          BASED (ADDR(GEO_WA1_OUT_PB5SC_3)),                        00012906
      3 GEO_WA1_OUT_PACKBORO_NOSIGN_3   CHAR(1),                    00013006
      3 GEO_WA1_OUT_STREETCODE_3_KEY    FIXED DEC(5);               00013106
                                                                    00013202
/*************************************************************/     00013301
                                                                    00013402
DCL GEO_WA1_OUT_GRC                     CHAR(02)                    00013507
                    BASED(ADDR(GEO_WA1_OUT_RETURN_CODE));           00013607
                                                                    00013902
/*************************************************************/     00014001
                                                                    00014102
DCL 1 WORK1PL1   BASED(PW1)               CHAR(884);                00014201
                                                                    00014302
/*************************************************************/     00014401
                                                                    00014502
PW1=ADDR(W1PL1);                                                    00015000
```

W2PL1 COPY File

```
/*****************************************************************/   00000100
/***  THIS IS GEOSUPPORT SYSTEM COPY FILE W2PL1, CONTAINING THE \***/   00000300
/***  LAYOUT OF WORK AREA 2 FOR FUNCTIONS: 1, 1E, 2, 2C, 3, 3C, \***/   00000400
/***  5.  PLEASE NOTE THAT FUNCTIONS 2 AND 2C SHARE A SINGLE    \***/   00000500
/***  WORK AREA 2 LAYOUT.                            12/30/97   \***/   00000600
/***  LAST UPDATED JANUARY 2012                                 \***/   00000749
/*****************************************************************/   00000800
DCL PW2 POINTER;                                                      00000900
                                                                      00001001
DCL 1 W2PL1             CHAR(200) INIT(' ');                          00001101
                                                                      00001201
DCL                                                                   00001300
  1 GEO_WA2_FUNCTION1   BASED(PW2),                                   00001400
    2 GEO_WA2_FN1_ACCESS_KEY              CHAR(21),                 00001500
    2 GEO_WA2_FN1_CONT_PARITY             CHAR(1),                  00001600
    2 GEO_WA2_FN1_LOW_HOUSENUM_INT        CHAR(6),                  00001700
    2 GEO_WA2_FN1_HI_HOUSENUM_INT         CHAR(6),                  00001800
    2 GEO_WA2_FN1_ALX                     CHAR(1),                  00001931
    2 GEO_WA2_FN1_NUM_X_ST_LOW_END        CHAR(1),                  00002000
    2 GEO_WA2_FN1_LOW_PBSC(5)             FIXED DEC(7),             00002100
    2 GEO_WA2_FN1_NUM_X_ST_HI_END         CHAR(1),                  00002200
```

```
2 GEO_WA2_FN1_HI_PBSC(5)              FIXED DEC(7),              00002300
2 GEO_WA2_FN1_COMMUN_DIST,                                       00002400
  3 GEO_WA2_FN1_COMDIST_BORO          CHAR(1),                   00002500
  3 GEO_WA2_FN1_COMDIST_NUMBER        CHAR(2),                   00002600
2 GEO_WA2_FN1_ZIP                     CHAR(5),                   00002700
2 GEO_WA2_FN1_SLA                     CHAR(1),                   00002800
2 GEO_WA2_FN1_HCD                     CHAR(2),                   00002951
2 GEO_WA2_FN1_SOS                     CHAR(1),                   00003150
2 GEO_WA2_FN1_CONT_PARITY_IND         CHAR(1),                   00003250
2 GEO_WA2_FN1_2010_CENSUS_TRACT       CHAR(6),                   00003350
2 GEO_WA2_FN1_2010_CENSUS_BLOCK       CHAR(4),                   00003450
2 GEO_WA2_FN1_2010_CENSUS_BLK_SF      CHAR(1), /\*NOT IMPLEMENTED*/00003550
2 GEO_WA2_FN1_FILLER_INDV             CHAR(1),                   00003650
2 FILLER_W2_260                       CHAR(2),                   00003750
2 GEO_WA2_FN1_HEALTHAREA              CHAR(4),                   00003851
2 GEO_WA2_FN1_SANI_REC                CHAR(3),                   00003950
2 GEO_WA2_FN1_FEATURE_TYPE            CHAR(1),                   00004050
2 GEO_WA2_FN1_RESDCP /\*RESERVED FOR*/  CHAR(1), /\*DCP/GSS USE*/    00004150
2 GEO_WA2_FN1_CURVE_FLAG              CHAR(1),                   00004250
2 GEO_WA2_FN1_POLICE_DIST,                                       00004350
  3  GEO_WA2_FN1_POL_PAT_B_CMD        CHAR(1),                   00004450
  3  GEO_WA2_FN1_POL_PRECINCT         CHAR(3),                   00004550
2 GEO_WA2_FN1_SCHOOLDIST              CHAR(2),                   00004650
2 FILLER_W2_250                       CHAR(14), /\*1E POL DIST*/   00004750
2 GEO_WA2_FN1_COINCIDENT_SEG_CTR      CHAR(1),                   00004850
2 GEO_WA2_FN1_SEGMENT_TYPE            CHAR(1),                   00004950
2 GEO_WA2_FN1_SANI_DIST,                                         00005050
  3 GEO_WA2_FN1_SANIDIST_BORO         CHAR(1),                   00005150
  3 GEO_WA2_FN1_SANIDIST_NUMBER       CHAR(2),                   00005250
2 GEO_WA2_FN1_SANITATION_SUBSEC       CHAR(2),                   00005350
2 GEO_WA2_FN1_FIRESEC   /\*FIRE DIV*/   CHAR(2),                   00005450
2 GEO_WA2_FN1_FIREBAT                 CHAR(2),                   00005550
2 GEO_WA2_FN1_FIRECO,                                            00005650
  3 GEO_WA2_FN1_FIRECO_TYPE           CHAR(1),                   00005750
  3 GEO_WA2_FN1_FIRECO_NUM            CHAR(3),                   00005850
2 GEO_WA2_FN1_SPECIAL_ADDR_FLAG       CHAR(1),                   00005950
2 GEO_WA2_FN1_MARBLE_RIKERS_FLAG      CHAR(1),                   00006050
2 GEO_WA2_FN1_SPLIT_SCHOOL_FILL       CHAR(1),                   00006150
2 GEO_WA2_FN1_PREFERRED_LGC           CHAR(2),                   00006250
2 GEO_WA2_FN1_LIONFACECODE            CHAR(4),                   00006350
2 GEO_WA2_FN1_LIONSEQ                 CHAR(5),                   00006450
2 GEO_WA2_FN1_1990_CENSUSTRACT        CHAR(6),                   00006550
2 FILLER_W2_260B                      CHAR(4),                   00006650
2 GEO_WA2_FN1_DYN_BLOCK               CHAR(3), /\*ATOMIC POLYGON*/ 00006750
2 GEO_WA2_FN1_XCOORD                  CHAR(7),                   00006850
```

```
    2 GEO_WA2_FN1_YCOORD                  CHAR(7),                    00006950
    2 GEO_WA2_FN1_SEGMENTLENGTH           CHAR(5),                    00007050
    2 GEO_WA2_FN1_SANI_REG                CHAR(5);                    00007150
                                                                      00007250
/*******************************************************************/ 00007350
                                                                      00007450
DCL 1 GEO_WA2_FN1_LOW_HOUSE_NUM                                       00007550
        BASED(ADDR(GEO_WA2_FN1_LOW_HOUSENUM_INT)),                    00007650
      3 GEO_WA2_FN1_LOW_HOUSENUM          CHAR(5),                    00007750
      3 GEO_WA2_FN1_LOW_HOUSENUMSFX       CHAR(1);                    00007850
                                                                      00008001
DCL 1 GEO_WA2_FN1_HI_HOUSE_NUM                                        00008100
        BASED(ADDR(GEO_WA2_FN1_HI_HOUSENUM_INT)),                     00008200
      3 GEO_WA2_FN1_HI_HOUSENUM           CHAR(5),                    00008300
      3 GEO_WA2_FN1_HI_HOUSENUMSFX        CHAR(1);                    00008425
                                                                      00008501
DCL 1 GEO_WA2_FN1_COMDIST                 CHAR(3)                     00008600
        BASED(ADDR(GEO_WA2_FN1_COMMUN_DIST));                         00008700
                                                                      00008801
DCL 1 GEO_WA2_FN1_SANIDIST                 CHAR(3)                    00008900
        BASED(ADDR(GEO_WA2_FN1_SANI_DIST));                           00009000
                                                                      00009101
DCL 1 GEO_WA2_FN1_POLICEDIST              CHAR(4)                     00009200
        BASED(ADDR(GEO_WA2_FN1_POLICE_DIST));                         00009300
                                                                      00009401
/*******************************************************************/ 00009801
                                                                      00009901
DCL                                                                   00010000
  1 GEO_WA2_FUNCTION2   BASED(PW2),                                   00010100
    2 GEO_WA2_FN2_ACCESS_KEY              CHAR(21),                   00010200
    2 GEO_WA2_FN2_DUPINTERFLAG            CHAR(1),                    00010300
    2 FILLER_W2_270                       CHAR(9),                    00010400
    2 GEO_WA2_FN2_PREFERRED_LGC1          CHAR(2),                    00010500
    2 GEO_WA2_FN2_PREFERRED_LGC2          CHAR(2),                    00010600
    2 GEO_WA2_FN2_NUM_OF_INTERSECTS       CHAR(1),                    00010700
    2 GEO_WA2_FN2_INTERSECT_PBSC(5)       FIXED DEC(7),               00010800
    2 GEO_WA2_FN2_COMPDIR                 CHAR(01),                   00010906
    2 GEO_WA2_FN2_LEVEL_CODES(5,2)        CHAR(01),                   00011020
    2 GEO_WA2_FN2_FILLER_INDV             CHAR(02),                   00011134
    2 GEO_WA2_FN2_FIRESEC   /\*FIRE DIV*/   CHAR(2),                   00011200
    2 GEO_WA2_FN2_FIREBAT                 CHAR(2),                    00011300
    2 GEO_WA2_FN2_FIRECO,                                             00011400
      3 GEO_WA2_FN2_FIRECO_TYPE           CHAR(1),                    00011500
      3 GEO_WA2_FN2_FIRECO_NUM            CHAR(3),                    00011600
    2 GEO_WA2_FN2_COMMUN_DIST,                                        00011700
```

```
      3 GEO_WA2_FN2_COMDIST_BORO          CHAR(1),                  00011800
      3 GEO_WA2_FN2_COMDIST_NUMBER        CHAR(2),                  00011900
    2 GEO_WA2_FN2_ZIP                     CHAR(5),                  00012000
    2 GEO_WA2_FN2_SLA                     CHAR(1),                  00012100
    2 GEO_WA2_FN2_2010_CENSUS_TRACT       CHAR(6),                  00012241
    2 FILLER_W2_290                       CHAR(3),                  00012300
    2 GEO_WA2_FN2_HEALTHAREA              CHAR(4),                  00012451
    2 FILLER_W2_300                       CHAR(9),                  00012504
    2 GEO_WA2_FN2_LIONNODENUM             CHAR(7),                  00012605
    2 GEO_WA2_FN2_XCOORD                  CHAR(7),                  00013000
    2 GEO_WA2_FN2_YCOORD                  CHAR(7),                  00013100
    2 FILLER_W2_320                       CHAR(4),                  00013300
    2 GEO_WA2_FN2_POLICE_DIST,                                      00013400
      3  GEO_WA2_FN2_POL_PAT_B_CMD        CHAR(1),                  00013500
      3  GEO_WA2_FN2_POL_PRECINCT         CHAR(3),                  00013600
    2 GEO_WA2_FN2_SCHOOLDIST              CHAR(2),                  00013700
    2 GEO_WA2_FN2_MARBLE_RIKERS_FLAG      CHAR(1),                  00013800
    2 GEO_WA2_FN2_1990_CENSUSTRACT        CHAR(6),                  00013900
    2 GEO_WA2_FN2_SANBORN1_BORO           CHAR(1),                  00014000
    2 GEO_WA2_FN2_SANBORN1_VOL_PAGE,                                00014100
      3 GEO_WA2_FN2_SANBORN1_VOL_NUM      CHAR(3),                  00014200
      3 GEO_WA2_FN2_SANBORN1_PAGE_NUM     CHAR(4),                  00014300
    2 GEO_WA2_FN2_SANBORN2_BORO           CHAR(1),                  00014400
    2 GEO_WA2_FN2_SANBORN2_VOL_PAGE,                                00014500
      3 GEO_WA2_FN2_SANBORN2_VOL_NUM      CHAR(3),                  00014600
      3 GEO_WA2_FN2_SANBORN2_PAGE_NUM     CHAR(4),                  00014700
    2 GEO_WA2_FN2_DUP_INTRSCT_DISTNCE     CHAR(5),                  00014837
    2 GEO_WA2_FN2_2000_CENS_TRACT         CHAR(6),                  00014944
    2 FILLER_W2_330                       CHAR(27);                 00015038
                                                                    00015101
/*******************************************************************/ 00015201
                                                                    00015301
DCL 1 GEO_WA2_FN2_COMDIST                 CHAR(3)                   00015400
        BASED(ADDR(GEO_WA2_FN2_COMMUN_DIST));                       00015500
                                                                    00015601
DCL 1 GEO_WA2_FN2_POLICEDIST              CHAR(4)                   00015700
        BASED(ADDR(GEO_WA2_FN2_POLICE_DIST));                       00015800
                                                                    00015901
DCL 1 GEO_WA2_FN2_SANBORN1_BVOLPAGE       CHAR(8)                   00016000
        BASED(ADDR(GEO_WA2_FN2_SANBORN1_BORO)),                     00016100
    1 GEO_WA2_FN2_SANBORN2_BVOLPAGE       CHAR(8)                   00016200
        BASED(ADDR(GEO_WA2_FN2_SANBORN2_BORO));                     00016300
                                                                    00016401
/*******************************************************************/ 00016501
                                                                    00016601
```

```
DCL                                                                 00016700
  1 GEO_WA2_FUNCTION3   BASED(PW2),                                 00016800
    2 GEO_WA2_FN3_ACCESS_KEY              CHAR(21),                 00016900
    2 GEO_WA2_FN3_DUP_KEY_FLAG            CHAR(1),                  00017023
    2 GEO_WA2_FN3_CURVE_FLAG              CHAR(1),                  00017108
    2 GEO_WA2_FN3_LOCATION_STATUS         CHAR(1),                  00017216
    2 GEO_WA2_FN3_COUNTY_BOUNDARY         CHAR(1),                  00017316
    2 GEO_WA2_FN3_COINCIDENT_SEG_CTR      CHAR(1),                  00017432
    2 FILLER_W2_340                       CHAR(3),                  00017532
    2 GEO_WA2_FN3_PREFERRED_LGC1          CHAR(2),                  00017632
    2 GEO_WA2_FN3_PREFERRED_LGC2          CHAR(2),                  00017732
    2 GEO_WA2_FN3_PREFERRED_LGC3          CHAR(2),                  00017832
    2 GEO_WA2_FN3_NUM_X_ST_LOW_END        CHAR(1),                  00017932
    2 GEO_WA2_FN3_LOW_PBSC(5)             FIXED DEC(7),             00018032
    2 GEO_WA2_FN3_NUM_X_ST_HI_END         CHAR(1),                  00018132
    2 GEO_WA2_FN3_HI_PBSC(5)              FIXED DEC(7),             00018232
    2 GEO_WA2_FN3_SLA                     CHAR(1),                  00018332
    2 GEO_WA2_FN3_REVERSALFLAG            CHAR(1),                  00018432
    2 GEO_WA2_FN3_LEFT_COMMUN_DIST,                                 00018532
      3 GEO_WA2_FN3_LEFT_COMDIST_BORO     CHAR(1),                  00018632
      3 GEO_WA2_FN3_LEFT_COMDIST_NUM      CHAR(2),                  00018732
    2 GEO_WA2_FN3_RIGHT_COMMUN_DIST,                                00018832
      3 GEO_WA2_FN3_RIGHT_COMDIST_BORO    CHAR(1),                  00018932
      3 GEO_WA2_FN3_RIGHT_COMDIST_NUM     CHAR(2),                  00019032
    2 GEO_WA2_FN3_LEFT_ZIP                CHAR(5),                  00019132
    2 GEO_WA2_FN3_RIGHT_ZIP               CHAR(5),                  00019232
    2 FILLER_WA2_350A                     CHAR(18),                 00019332
    2 GEO_WA2_FN3_LEFT_HEALTHAREA         CHAR(4),                  00019451
    2 GEO_WA2_FN3_RIGHT_HEALTHAREA        CHAR(4),                  00019551
    2 GEO_WA2_FN3_LEFT_FILLER_INDV        CHAR(2),                  00019634
    2 GEO_WA2_FN3_RIGHT_FILLER_INDV       CHAR(2),                  00019734
    2 GEO_WA2_FN3_LEFT_LOW_HOUSENUM       CHAR(7),                  00019800
    2 GEO_WA2_FN3_LEFT_HI_HOUSENUM        CHAR(7),                  00019900
    2 GEO_WA2_FN3_RIGHT_LOW_HOUSENUM      CHAR(7),                  00020000
    2 GEO_WA2_FN3_RIGHT_HI_HOUSENUM       CHAR(7),                  00020100
    2 GEO_WA2_FN3_CONT_PARITY_IND         CHAR(1),                  00020200
    2 GEO_WA2_FN3_LIONFACECODE            CHAR(4),                  00020300
    2 GEO_WA2_FN3_LIONSEQ                 CHAR(5),                  00020400
    2 GEO_WA2_FN3_GENRECFLAG              CHAR(1),                  00020500
    2 GEO_WA2_FN3_SEGMENTLENGTH           FIXED DEC(5),             00020600
    2 GEO_WA2_FN3_SEGMENTSLOPE            CHAR(3),                  00020700
    2 GEO_WA2_FN3_SEGMENTORIENT           CHAR(1),                  00020800
    2 FILLER_W2_355                       CHAR(4),                  00020900
    2 GEO_WA2_FN3_RESDCP /\*RESERVED FOR \*/ CHAR(2), /\*DCP/GSS USE*/    00021000
    2 GEO_WA2_FN3_DOG_LEG                 CHAR(1),                  00021111
```

```
    2 GEO_WA2_FN3_FEATURE_TYPE            CHAR(1),                  00021221
    2 GEO_WA2_FN3_LEFT_POLICE_DIST,                                 00021300
      3  GEO_WA2_FN3_LEFT_POL_PAT_B_CMD   CHAR(1),                  00021400
      3  GEO_WA2_FN3_LEFT_POL_PRECINCT     CHAR(3),                 00021500
    2 GEO_WA2_FN3_RIGHT_POLICE_DIST,                                00021600
      3  GEO_WA2_FN3_RIGHT_POL_PAT_B_CMD  CHAR(1),                  00021700
      3  GEO_WA2_FN3_RIGHT_POL_PRECINCT     CHAR(3),                 00021800
    2 GEO_WA2_FN3_LEFT_SCHLDIST           CHAR(2),                  00021900
    2 GEO_WA2_FN3_RIGHT_SCHLDIST          CHAR(2),                  00022000
    2 GEO_WA2_FN3_MARBLE_RIKERS_FLAG      CHAR(1),                  00022100
    2 GEO_WA2_FN3_SEGMENT_ID              CHAR(7),                  00022211
    2 GEO_WA2_FN3_SEGMENT_TYPE            CHAR(1);                  00022329
                                                                    00022501
/*******************************************************************/ 00022601
                                                                    00022701
DCL 1 GEO_WA2_FN3_LEFT_COMDIST                CHAR(3)               00022800
        BASED(ADDR(GEO_WA2_FN3_LEFT_COMMUN_DIST));                  00022900
                                                                    00023001
DCL 1 GEO_WA2_FN3_RIGHT_COMDIST               CHAR(3)               00023100
        BASED(ADDR(GEO_WA2_FN3_RIGHT_COMMUN_DIST));                 00023200
                                                                    00023301
DCL 1 GEO_WA2_FN3_LEFT_POLICEDIST             CHAR(4)               00023400
        BASED(ADDR(GEO_WA2_FN3_LEFT_POLICE_DIST));                  00023500
                                                                    00023601
DCL 1 GEO_WA2_FN3_RIGHT_POLICEDIST             CHAR(4)              00023700
        BASED(ADDR(GEO_WA2_FN3_RIGHT_POLICE_DIST));                 00023800
                                                                    00023901
DCL                                                                 00024000
  1 GEO_WA2_FUNCTION3C  BASED(PW2),                                 00024100
    2 GEO_WA2_FN3C_ACCESS_KEY             CHAR(21),                 00024200
    2 GEO_WA2_FN3C_CURVE_FLAG             CHAR(1),                  00024308
    2 GEO_WA2_FN3C_SEGMENT_TYPE           CHAR(1),                  00024430
    2 GEO_WA2_FN3C_LOCATION_STATUS        CHAR(1),                  00024630
    2 GEO_WA2_FN3C_COUNTY_BOUNDARY        CHAR(1),                  00024730
    2 GEO_WA2_FN3C_COINCIDENT_SEG_CTR     CHAR(1),                  00024832
    2 FILLER_W2_380                       CHAR(3),                  00024932
    2 GEO_WA2_FN3C_PREFERRED_LGC1         CHAR(2),                  00025032
    2 GEO_WA2_FN3C_PREFERRED_LGC2         CHAR(2),                  00025132
    2 GEO_WA2_FN3C_PREFERRED_LGC3         CHAR(2),                  00025232
    2 GEO_WA2_FN3C_NUM_X_ST_LOW_END       CHAR(1),                  00025332
    2 GEO_WA2_FN3C_LOW_PBSC(5)            FIXED DEC(7),             00025432
    2 GEO_WA2_FN3C_NUM_X_ST_HI_END        CHAR(1),                  00025532
    2 GEO_WA2_FN3C_HI_PBSC(5)             FIXED DEC(7),             00025632
    2 GEO_WA2_FN3C_COMMUN_DIST,                                     00025732
      3 GEO_WA2_FN3C_COMDIST_BORO         CHAR(1),                  00025832
```

```
      3 GEO_WA2_FN3C_COMDIST_NUMBER        CHAR(2),                    00025932
    2 GEO_WA2_FN3C_ZIP                     CHAR(5),                    00026032
    2 GEO_WA2_FN3C_SLA                     CHAR(1),                    00026132
    2 GEO_WA2_FN3C_2000_CENS_TRACT         CHAR(6),                    00026244
    2 FILLER_W2_390                        CHAR(1),                    00026338
    2 GEO_WA2_FN3C_2010_CENSUS_TRACT       CHAR(6),                    00026441
    2 GEO_WA2_FN3C_2010_CENSUS_BLOCK       CHAR(4),                    00026541
    2 GEO_WA2_FN3C_2010_CENSUS_BLK_SF      CHAR(1), /\*NOTIMPLEMENTED*/ 00026647
    2 GEO_WA2_FN3C_HEALTHAREA              CHAR(4),                    00026751
    2 GEO_WA2_FN3C_REVERSALFLAG            CHAR(1),                    00026835
    2 GEO_WA2_FN3C_SOS                     CHAR(1),                    00026935
    2 GEO_WA2_FN3C_FIRESEC  /\*FIRE DIV*/   CHAR(2),                    00027035
    2 GEO_WA2_FN3C_FIREBAT                 CHAR(2),                    00027135
    2 GEO_WA2_FN3C_FIRECO,                                             00027235
      3 GEO_WA2_FN3C_FIRECO_TYPE           CHAR(1),                    00027335
      3 GEO_WA2_FN3C_FIRECO_NUM            CHAR(3),                    00027435
    2 GEO_WA2_FN3C_SEGMENT_ID              CHAR(7),                    00027535
    2 GEO_WA2_FN3C_LOW_HOUSENUM            CHAR(7),                    00027635
    2 GEO_WA2_FN3C_HI_HOUSENUM             CHAR(7),                    00027735
    2 GEO_WA2_FN3C_LOW_HOUSENUM2           CHAR(7),                    00027835
    2 GEO_WA2_FN3C_HI_HOUSENUM2            CHAR(7),                    00027935
/*   2 HOUSENUM2 ONLY PRESENT IF ODD & EVEN RANGES ARE ON     \*/       00028035
/*   2 SAME SIDE OF STREET                                    \*/       00028135
    2 GEO_WA2_FN3C_CONT_PARITY_IND         CHAR(1),                    00028235
    2 GEO_WA2_FN3C_LIONFACECODE            CHAR(4),                    00028335
    2 GEO_WA2_FN3C_LIONSEQ                 CHAR(5),                    00028435
    2 GEO_WA2_FN3C_GENRECFLAG              CHAR(1),                    00028535
    2 GEO_WA2_FN3C_SEGMENTLENGTH           FIXED DEC(5),               00028635
    2 GEO_WA2_FN3C_SEGMENTSLOPE            CHAR(3),                    00028735
    2 GEO_WA2_FN3C_SEGMENTORIENT           CHAR(1),                    00028835
    2 GEO_WA2_FN3C_FILLER_INDV             CHAR(2),                    00028935
    2 GEO_WA2_FN3C_RESDCP /\*RESERVED FOR*/ CHAR(1), /\*DCP/GSS USE*/    00029035
    2 GEO_WA2_FN3C_FEATURE_TYPE            CHAR(1),                    00029135
    2 GEO_WA2_FN3C_POLICE_DIST,                                        00029235
      3  GEO_WA2_FN3C_POL_PAT_B_CMD        CHAR(1),                    00029335
      3  GEO_WA2_FN3C_POL_PRECINCT         CHAR(3),                    00029435
    2 GEO_WA2_FN3C_SCHOOLDIST              CHAR(2),                    00029535
    2 GEO_WA2_FN3C_MARBLE_RIKERS_FLAG      CHAR(1),                    00029635
    2 GEO_WA2_FN3C_1990_CENSUSTRACT        CHAR(6),                    00029735
    2 FILLER_W2_410B                       CHAR(4),                    00029835
    2 GEO_WA2_FN3C_DYN_BLOCK               CHAR(3), /\*ATOMIC POLYGON*/ 00029942
    2 GEO_WA2_FN3C_2000_CENS_BLOCK         CHAR(4),                    00030044
    2 GEO_WA2_FN3C_2000_CENS_BL_SFX        CHAR(1);                    00030144
                                                                       00030335
/*********************************************************************/ 00030435
```

```
                                                                    00030535
DCL 1 GEO_WA2_FN3C_COMDIST                CHAR(3)                   00030635
        BASED(ADDR(GEO_WA2_FN3C_COMMUN_DIST));                      00030735
DCL 1 GEO_WA2_FN3C_POLICEDIST             CHAR(4)                   00030835
        BASED(ADDR(GEO_WA2_FN3C_POLICE_DIST));                      00030935
                                                                    00031035
/*******************************************************************/ 00031135
                                                                    00031235
DCL                                                                 00031335
  1 GEO_WA2_FUNCTION1E  BASED(PW2),                                 00031435
    2 GEO_WA2_FN1E_ACCESS_KEY             CHAR(21),                 00031535
    2 GEO_WA2_FN1E_CONT_PARITY            CHAR(1),                  00031635
    2 GEO_WA2_FN1E_LOW_HOUSENUM_INT       CHAR(6),                  00031735
    2 GEO_WA2_FN1E_HI_HOUSENUM_INT        CHAR(6),                  00031835
    2 FILLER_W2_435                       CHAR(1),                  00031935
    2 GEO_WA2_FN1E_NUM_X_ST_LOW_END       CHAR(1),                  00032035
    2 GEO_WA2_FN1E_LOW_PBSC(5)            FIXED DEC(7),             00032135
    2 GEO_WA2_FN1E_NUM_X_ST_HI_END        CHAR(1),                  00032235
    2 GEO_WA2_FN1E_HI_PBSC(5)             FIXED DEC(7),             00032335
    2 GEO_WA2_FN1E_COMMUN_DIST,                                     00032435
      3 GEO_WA2_FN1E_COMDIST_BORO         CHAR(1),                  00032535
      3 GEO_WA2_FN1E_COMDIST_NUMBER       CHAR(2),                  00032635
    2 GEO_WA2_FN1E_ZIP                    CHAR(5),                  00032735
    2 GEO_WA2_FN1E_SLA                    CHAR(1),                  00032835
    2 GEO_WA2_FN1E_HCD                    CHAR(2),                  00032951
    2 GEO_WA2_FN1E_SOS                    CHAR(1),                  00033150
    2 GEO_WA2_FN1E_CONT_PARITY_IND        CHAR(1),                  00033250
    2 GEO_WA2_FN1E_2010_CENSUS_TRACT      CHAR(6),                  00033350
    2 GEO_WA2_FN1E_2010_CENSUS_BLOCK      CHAR(4),                  00033450
    2 GEO_WA2_FN1E_2010_CENSUS_BLK_SF     CHAR(1), /\*NOTIMPLEMENTED*/ 00033550
    2 GEO_WA2_FN1E_FILLER_INDV            CHAR(1),                  00033650
    2 FILLER_W2_440                       CHAR(2),                  00033750
    2 GEO_WA2_FN1E_HEALTHAREA             CHAR(4),                  00033851
    2 GEO_WA2_FN1E_SANI_REC               CHAR(3),                  00033950
    2 GEO_WA2_FN1E_FEATURE_TYPE           CHAR(1),                  00034050
    2 GEO_WA2_FN1E_RESDCP /\*RESERVED FOR*/ CHAR(1), /\*DCP/GSS USE*/   00034150
    2 GEO_WA2_FN1E_CURVE_FLAG             CHAR(1),                  00034250
    2 GEO_WA2_FN1E_POLICE_DIST,                                     00034350
      3  GEO_WA2_FN1E_POL_PAT_B_CMD       CHAR(1),                  00034450
      3  GEO_WA2_FN1E_POL_PRECINCT        CHAR(3),                  00034550
    2 GEO_WA2_FN1E_SCHOOLDIST             CHAR(2),                  00034650
    2 GEO_WA2_FN1E_ELECTDIST              CHAR(3),                  00034750
    2 GEO_WA2_FN1E_ASSEMDIST              CHAR(2),                  00034850
    2 GEO_WA2_FN1E_SPLIT_ED_FLAG          CHAR(1),                  00034950
    2 GEO_WA2_FN1E_CONGDIST               CHAR(2),                  00035050
```

```
    2 GEO_WA2_FN1E_SENATEDIST              CHAR(2),                    00035150
    2 GEO_WA2_FN1E_COURTDIST               CHAR(2),                    00035250
    2 GEO_WA2_FN1E_COUNCILDIST             CHAR(2),                    00035350
    2 GEO_WA2_FN1E_COINCIDENT_SEG_CTR      CHAR(1),                    00035450
    2 GEO_WA2_FN1E_SEGMENT_TYPE_CODE       CHAR(1),                    00035550
    2 GEO_WA2_FN1E_SANI_DIST,                                          00035650
      3 GEO_WA2_FN1E_SANIDIST_BORO         CHAR(1),                    00035750
      3 GEO_WA2_FN1E_SANIDIST_NUMBER       CHAR(2),                    00035850
    2 GEO_WA2_FN1E_SANITATION_SUBSEC       CHAR(2),                    00035950
    2 GEO_WA2_FN1E_FIRESEC  /\*FIRE DIV*/   CHAR(2),                    00036050
    2 GEO_WA2_FN1E_FIREBAT                 CHAR(2),                    00036150
    2 GEO_WA2_FN1E_FIRECO,                                             00036250
      3 GEO_WA2_FN1E_FIRECO_TYPE           CHAR(1),                    00036350
      3 GEO_WA2_FN1E_FIRECO_NUM            CHAR(3),                    00036450
    2 GEO_WA2_FN1E_SPECIAL_ADDR__FLAG      CHAR(1),                    00036550
    2 GEO_WA2_FN1E_MARBLE_RIKERS_FLAG      CHAR(1),                    00036650
    2 GEO_WA2_FN1E_SPLIT_SCHOOL_FILL       CHAR(1),                    00036750
    2 GEO_WA2_FN1E_PREFERRED_LGC           CHAR(2),                    00036850
    2 GEO_WA2_FN1E_LIONFACECODE            CHAR(4),                    00036950
    2 GEO_WA2_FN1E_LIONSEQ                 CHAR(5),                    00037050
    2 GEO_WA2_FN1E_1990_CENSUSTRACT        CHAR(6),                    00037150
    2 FILLER_W2_480B                       CHAR(4),                    00037250
    2 GEO_WA2_FN1E_DYN_BLOCK               CHAR(3), /\*ATOMIC POLYGON*/ 00037350
    2 GEO_WA2_FN1E_XCOORD                  CHAR(7),                    00037450
    2 GEO_WA2_FN1E_YCOORD                  CHAR(7),                    00037550
    2 GEO_WA2_FN1E_SEGMENTLENGTH           CHAR(5),                    00037650
    2 GEO_WA2_FN1E_SANI_REG                CHAR(5);                    00037750
                                                                       00037850
/*********************************************************************/ 00037950
                                                                       00038050
DCL 1 GEO_WA2_FN1E_LOW_HOUSE_NUM                                       00038150
        BASED(ADDR(GEO_WA2_FN1E_LOW_HOUSENUM_INT)),                    00038250
      3 GEO_WA2_FN1E_LOW_HOUSENUM            CHAR(5),                  00038350
      3 GEO_WA2_FN1E_LOW_HOUSENUMSFX         CHAR(1);                  00038450
                                                                       00038550
DCL 1 GEO_WA2_FN1E_HI_HOUSE_NUM                                        00038650
        BASED(ADDR(GEO_WA2_FN1E_HI_HOUSENUM_INT)),                     00038750
      3 GEO_WA2_FN1E_HI_HOUSENUM             CHAR(5),                  00038850
      3 GEO_WA2_FN1E_HI_HOUSENUMSFX          CHAR(1);                  00038950
                                                                       00039050
DCL 1 GEO_WA2_FN1E_COMDIST                   CHAR(3)                   00039150
        BASED(ADDR(GEO_WA2_FN1E_COMMUN_DIST));                         00039250
                                                                       00039350
DCL 1 GEO_WA2_FN1E_SANIDIST                    CHAR(3)                 00039450
        BASED(ADDR(GEO_WA2_FN1E_SANI_DIST));                           00039550
```

```
                                                                    00039650
DCL 1 GEO_WA2_FN1E_POLICEDIST              CHAR(4)                  00039750
        BASED(ADDR(GEO_WA2_FN1E_POLICE_DIST));                      00039850
                                                                    00039950
/*******************************************************************/ 00040050
                                                                    00040150
DCL                                                                 00040250
  1 GEO_WA2_FUNCTION5   BASED(PW2),                                 00040350
    2 GEO_WA2_FN5_ADDR_MATCHING_KEY        CHAR(28),                00040450
    2 FILLER_W2_210                        CHAR(172);               00040550
                                                                    00041000
/*******************************************************************/ 00042001
                                                                    00043001
PW2=ADDR(W2PL1);                                                    00050000
```

W2PL1L COPY File

```
/*******************************************************************/ 00000100
/***  THIS IS GEOSUPPORT SYSTEM COPY FILE W2PL1L, CONTAINING      \***/ 00000200
/***  THE LAYOUT OF THE OPTIONAL LONG WORK AREA 2 FOR             \***/ 00000300
/***  FUNCTION 1,1E, & 3. THIS WORK AREA SHOULD BE USED ONLY WHEN \***/ 00000400
/***  FUNCTION IS CALLED WITH THE "LONG" WORK AREA2 OPTION.       \***/ 00000500
/***                                              07/23/2001    \***/ 00000600
/***  LAST MODIFIED JANUARY 2012                                  \***/ 00000739
/*******************************************************************/ 00000824
DCL PW2L POINTER;                                                   00000924
DCL 1 W2PL1L            CHAR(300) INIT(' ');                        00001024
DCL                                                                 00001124
  1 GEO_WA2_1L_FUNCTION1   BASED(PW2L),                             00001224
    2 GEO_WA2_1L_ACCESS_KEY               CHAR(21),                 00001324
    2 GEO_WA2_1L_CONT_PARITY              CHAR(1),                  00001424
    2 GEO_WA2_1L_LOW_HOUSENUM_INT         CHAR(6),                  00001524
    2 GEO_WA2_1L_HI_HOUSENUM_INT          CHAR(6),                  00001624
    2 GEO_WA2_1L_ALX                      CHAR(1),                  00001724
    2 GEO_WA2_1L_NUM_X_ST_LOW_END         CHAR(1),                  00001824
    2 GEO_WA2_1L_LOW_PBSC(5)              FIXED DEC(7),             00001924
    2 GEO_WA2_1L_NUM_X_ST_HI_END          CHAR(1),                  00002024
    2 GEO_WA2_1L_HI_PBSC(5)               FIXED DEC(7),             00002124
    2 GEO_WA2_1L_COMMUN_DIST,                                       00002224
      3 GEO_WA2_1L_COMDIST_BORO           CHAR(1),                  00002324
      3 GEO_WA2_1L_COMDIST_NUMBER         CHAR(2),                  00002424
    2 GEO_WA2_1L_ZIP                      CHAR(5),                  00002524
    2 GEO_WA2_1L_SLA                      CHAR(1),                  00002624
    2 GEO_WA2_1L_HCD                      CHAR(2),                  00002740
    2 GEO_WA2_1L_SOS                      CHAR(1),                  00002939
```

```
2 GEO_WA2_1L_CONT_PARITY_IND          CHAR(1),                      00003039
2 GEO_WA2_1L_2010_CENSUS_TRACT        CHAR(6),                      00003139
2 GEO_WA2_1L_2010_CENSUS_BLOCK        CHAR(4),                      00003239
2 GEO_WA2_1L_2010_CENSUS_BLK_SF       CHAR(1), /\*NOTIMPLEMENTED*/  00003339
2 GEO_WA2_1L_FILLER_INDV              CHAR(1),                      00003439
2 FILLER_W2_230                       CHAR(2),                      00003539
2 GEO_WA2_1L_HEALTHAREA               CHAR(4),                      00003640
2 GEO_WA2_1L_SANI_REC                 CHAR(3),                      00003739
2 GEO_WA2_1L_FEATURE_TYPE             CHAR(1),                      00003839
2 GEO_WA2_1L_RESDCP /\*RESERVED FOR*/  CHAR(1), /\*DCP/GSS USE*/     00003939
2 GEO_WA2_1L_CURVE_FLAG               CHAR(1),                      00004039
2 GEO_WA2_1L_POLICE_DIST,                                           00004139
  3  GEO_WA2_1L_POL_PAT_B_CMD         CHAR(1),                      00004239
  3  GEO_WA2_1L_POL_PRECINCT          CHAR(3),                      00004339
2 GEO_WA2_1L_SCHOOLDIST               CHAR(2),                      00004439
2 FILLER_W2_250                       CHAR(14), /\*1E POL DIST*/    00004539
2 GEO_WA2_1L_COINCIDENT_SEG_CTR       CHAR(1),                      00004620
2 GEO_WA2_1L_SEGMENT_TYPE             CHAR(1),                      00004720
2 GEO_WA2_1L_SANI_DIST,                                             00004820
  3 GEO_WA2_1L_SANIDIST_BORO          CHAR(1),                      00004920
  3 GEO_WA2_1L_SANIDIST_NUMBER        CHAR(2),                      00005020
2 GEO_WA2_1L_SANITATION_SUBSEC        CHAR(2),                      00005120
2 GEO_WA2_1L_FIRESEC   /\*FIRE DIV*/   CHAR(2),                      00005220
2 GEO_WA2_1L_FIREBAT                  CHAR(2),                      00005320
2 GEO_WA2_1L_FIRECO,                                                00005420
  3 GEO_WA2_1L_FIRECO_TYPE            CHAR(1),                      00005520
  3 GEO_WA2_1L_FIRECO_NUM             CHAR(3),                      00005620
2 GEO_WA2_1L_SPECIAL_ADDR_FLAG        CHAR(1),                      00005720
2 GEO_WA2_1L_MARBLE_RIKERS_FLAG       CHAR(1),                      00005820
2 GEO_WA2_1L_SPLIT_SCHOOL_FILL        CHAR(1),                      00005938
2 GEO_WA2_1L_PREFERRED_LGC            CHAR(2),                      00006020
2 GEO_WA2_1L_LIONFACECODE             CHAR(4),                      00006120
2 GEO_WA2_1L_LIONSEQ                  CHAR(5),                      00006220
2 GEO_WA2_1L_1990_CENSUSTRACT         CHAR(6),                      00006320
2 FILLER_W2_260B                      CHAR(4),                      00006423
2 GEO_WA2_1L_DYN_BLOCK                CHAR(3), /\*ATOMIC POLYGON*/  00006534
2 GEO_WA2_1L_XCOORD                   CHAR(7),                      00006620
2 GEO_WA2_1L_YCOORD                   CHAR(7),                      00006720
2 GEO_WA2_1L_SEGMENTLENGTH            CHAR(5),                      00006820
2 GEO_WA2_1L_SANI_REG                 CHAR(5),                      00006920
2 GEO_WA2_1L_SEGMENT_ID               CHAR(7),                      00007020
2 GEO_WA2_1L_REAL_B7SC                CHAR(08),                     00007120
2 GEO_WA2_1L_UNDERLY_HOUSENUM_INT     CHAR(6),                      00007223
2 GEO_WA2_1L_2000_CENS_TRACT          CHAR(6),                      00007336
2 GEO_WA2_1L_2000_CENS_BLOCK          CHAR(4),                      00007436
```

```
    2 GEO_WA2_1L_2000_CENS_BLK_SUF        CHAR(1),                    00007536
    2 FILLER_W2_260C                      CHAR(68);                   00007629
                                                                      00007723
/*******************************************************************/ 00007823
                                                                      00007923
DCL 1 GEO_WA2_1L_LOW_HOUSE_NUM                                        00008023
        BASED(ADDR(GEO_WA2_1L_LOW_HOUSENUM_INT)),                     00008123
      3 GEO_WA2_1L_LOW_HOUSENUM           CHAR(5),                    00008223
      3 GEO_WA2_1L_LOW_HOUSENUMSFX        CHAR(1);                    00008323
                                                                      00008423
DCL 1 GEO_WA2_1L_HI_HOUSE_NUM                                         00008523
        BASED(ADDR(GEO_WA2_1L_HI_HOUSENUM_INT)),                      00008623
      3 GEO_WA2_1L_HI_HOUSENUM            CHAR(5),                    00008723
      3 GEO_WA2_1L_HI_HOUSENUMSFX         CHAR(1);                    00008823
                                                                      00008923
DCL 1 GEO_WA2_1L_UNDERLY_HOUSE_NUM                                    00009023
        BASED(ADDR(GEO_WA2_1L_UNDERLY_HOUSENUM_INT)),                 00009123
      3 GEO_WA2_1L_UNDERLY_HOUSENUM       CHAR(5),                    00009223
      3 GEO_WA2_1L_UNDERLY_HOUSENUMSFX    CHAR(1);                    00009323
                                                                      00009423
DCL 1 GEO_WA2_1L_COMDIST                  CHAR(3)                     00009523
        BASED(ADDR(GEO_WA2_1L_COMMUN_DIST));                          00009623
                                                                      00009723
DCL 1 GEO_WA2_1L_SANIDIST                  CHAR(3)                    00009823
        BASED(ADDR(GEO_WA2_1L_SANI_DIST));                            00009923
                                                                      00010023
DCL 1 GEO_WA2_1L_POLICEDIST               CHAR(4)                     00010123
        BASED(ADDR(GEO_WA2_1L_POLICE_DIST));                          00010223
                                                                      00010323
/*******************************************************************/ 00010423
                                                                      00010523
DCL                                                                   00010623
  1 GEO_WA2_1EL_FUNCTION1E  BASED(PW2L),                              00010723
    2 GEO_WA2_1EL_ACCESS_KEY              CHAR(21),                   00010823
    2 GEO_WA2_1EL_CONT_PARITY             CHAR(1),                    00010923
    2 GEO_WA2_1EL_LOW_HOUSENUM_INT        CHAR(6),                    00011023
    2 GEO_WA2_1EL_HI_HOUSENUM_INT         CHAR(6),                    00011123
    2 GEO_WA2_1EL_ALX                     CHAR(1),                    00011223
    2 GEO_WA2_1EL_NUM_X_ST_LOW_END        CHAR(1),                    00011323
    2 GEO_WA2_1EL_LOW_PBSC(5)             FIXED DEC(7),               00011423
    2 GEO_WA2_1EL_NUM_X_ST_HI_END         CHAR(1),                    00011523
    2 GEO_WA2_1EL_HI_PBSC(5)              FIXED DEC(7),               00011623
    2 GEO_WA2_1EL_COMMUN_DIST,                                        00011723
      3 GEO_WA2_1EL_COMDIST_BORO          CHAR(1),                    00011823
      3 GEO_WA2_1EL_COMDIST_NUMBER        CHAR(2),                    00011923
```

```
2 GEO_WA2_1EL_ZIP                    CHAR(5),                    00012023
2 GEO_WA2_1EL_SLA                    CHAR(1),                    00012123
2 GEO_WA2_1EL_HCD                    CHAR(2),                    00012240
2 GEO_WA2_1EL_SOS                    CHAR(1),                    00012439
2 GEO_WA2_1EL_CONT_PARITY_IND        CHAR(1),                    00012539
2 GEO_WA2_1EL_2010_CENSUS_TRACT      CHAR(6),                    00012639
2 GEO_WA2_1EL_2010_CENSUS_BLOCK      CHAR(4),                    00012739
2 GEO_WA2_1EL_2010_CENSUS_BLK_SF     CHAR(1), /\*NOTIMPLEMENTED*/  00012839
2 GEO_WA2_1EL_FILLER_INDV            CHAR(1),                    00012939
2 FILLER_W2_240                      CHAR(2),                    00013039
2 GEO_WA2_1EL_HEALTHAREA             CHAR(4),                    00013140
2 GEO_WA2_1EL_SANI_REC               CHAR(3),                    00013239
2 GEO_WA2_1EL_FEATURE_TYPE           CHAR(1),                    00013339
2 GEO_WA2_1EL_RESDCP /\*RESERVED FOR*/ CHAR(1), /\*DCP/GSS USE*/     00013439
2 GEO_WA2_1EL_CURVE_FLAG             CHAR(1),                    00013539
2 GEO_WA2_1EL_POLICE_DIST,                                       00013639
  3  GEO_WA2_1EL_POL_PAT_B_CMD       CHAR(1),                    00013739
  3  GEO_WA2_1EL_POL_PRECINCT        CHAR(3),                    00013839
2 GEO_WA2_1EL_SCHOOLDIST             CHAR(2),                    00013939
2 GEO_WA2_1EL_ELECTDIST              CHAR(3),                    00014039
2 GEO_WA2_1EL_ASSEMDIST              CHAR(2),                    00014139
2 GEO_WA2_1EL_SPLIT_ED_FLAG          CHAR(1),                    00014239
2 GEO_WA2_1EL_CONGDIST               CHAR(2),                    00014339
2 GEO_WA2_1EL_SENATEDIST             CHAR(2),                    00014439
2 GEO_WA2_1EL_COURTDIST              CHAR(2),                    00014539
2 GEO_WA2_1EL_COUNCILDIST            CHAR(2),                    00014639
2 GEO_WA2_1EL_COINCIDENT_SEG_CTR     CHAR(1),                    00014739
2 GEO_WA2_1EL_SEGMENT_TYPE_CODE      CHAR(1),                    00014839
2 GEO_WA2_1EL_SANI_DIST,                                         00014939
  3 GEO_WA2_1EL_SANIDIST_BORO        CHAR(1),                    00015039
  3 GEO_WA2_1EL_SANIDIST_NUMBER      CHAR(2),                    00015139
2 GEO_WA2_1EL_SANITATION_SUBSEC      CHAR(2),                    00015239
2 GEO_WA2_1EL_FIRESEC  /\*FIRE DIV*/   CHAR(2),                    00015339
2 GEO_WA2_1EL_FIREBAT                CHAR(2),                    00015439
2 GEO_WA2_1EL_FIRECO,                                            00015539
  3 GEO_WA2_1EL_FIRECO_TYPE          CHAR(1),                    00015639
  3 GEO_WA2_1EL_FIRECO_NUM           CHAR(3),                    00015739
2 GEO_WA2_1EL_SPECIAL_ADDR__FLAG     CHAR(1),                    00015839
2 GEO_WA2_1EL_MARBLE_RIKERS_FLAG     CHAR(1),                    00015939
2 GEO_WA2_1EL_SPLIT_SCHOOL_FILL      CHAR(1),                    00016039
2 GEO_WA2_1EL_PREFERRED_LGC          CHAR(2),                    00016139
2 GEO_WA2_1EL_LIONFACECODE           CHAR(4),                    00016239
2 GEO_WA2_1EL_LIONSEQ                CHAR(5),                    00016339
2 GEO_WA2_1EL_1990_CENSUSTRACT       CHAR(6),                    00016439
2 FILLER_W2_480B                      CHAR(4),                    00016539
```

```
    2 GEO_WA2_1EL_DYN_BLOCK              CHAR(3), /\*ATOMIC POLYGON*/  00016639
    2 GEO_WA2_1EL_XCOORD                 CHAR(7),                     00016739
    2 GEO_WA2_1EL_YCOORD                 CHAR(7),                     00016839
    2 GEO_WA2_1EL_SEGMENTLENGTH          CHAR(5),                     00016939
    2 GEO_WA2_1EL_SANI_REG               CHAR(5),                     00017039
    2 GEO_WA2_1EL_SEGMENT_ID             CHAR(7),                     00017139
    2 GEO_WA2_1EL_TRUE_B7SC              CHAR(8),                     00017239
    2 GEO_WA2_1EL_UNDER_HOUSENUM_INT     CHAR(6),                     00017339
    2 GEO_WA2_1EL_2000_CENS_TRACT        CHAR(6),                     00017439
    2 GEO_WA2_1EL_2000_CENS_BLOCK        CHAR(4),                     00017539
    2 GEO_WA2_1EL_2000_CENS_BLK_SUF      CHAR(1),                     00017639
    2 FILLER_W2_480                      CHAR(68);                    00017739
                                                                      00017839
/*******************************************************************/ 00017939
                                                                      00018039
DCL 1 GEO_WA2_1EL_LOW_HOUSE_NUM                                       00018139
        BASED(ADDR(GEO_WA2_1EL_LOW_HOUSENUM_INT)),                    00018239
      3 GEO_WA2_1EL_LOW_HOUSENUM         CHAR(5),                     00018339
      3 GEO_WA2_1EL_LOW_HOUSENUMSFX      CHAR(1);                     00018439
                                                                      00018539
DCL 1 GEO_WA2_1EL_HI_HOUSE_NUM                                        00018639
        BASED(ADDR(GEO_WA2_1EL_HI_HOUSENUM_INT)),                     00018739
      3 GEO_WA2_1EL_HI_HOUSENUM          CHAR(5),                     00018839
      3 GEO_WA2_1EL_HI_HOUSENUMSFX       CHAR(1);                     00018939
                                                                      00019039
DCL 1 GEO_WA2_1EL_UNDER_HOUSE_NUM                                     00019139
        BASED(ADDR(GEO_WA2_1EL_UNDER_HOUSENUM_INT)),                  00019239
      3 GEO_WA2_1EL_UNDER_HOUSENUM      CHAR(5),                      00019339
      3 GEO_WA2_1EL_UNDER_HOUSENUMSFX   CHAR(1);                      00019439
                                                                      00019539
DCL 1 GEO_WA2_1EL_COMDIST                CHAR(3)                      00019639
        BASED(ADDR(GEO_WA2_1EL_COMMUN_DIST));                         00019739
                                                                      00019839
DCL 1 GEO_WA2_1EL_SANIDIST                 CHAR(3)                    00019939
        BASED(ADDR(GEO_WA2_1EL_SANI_DIST));                           00020039
                                                                      00020139
DCL 1 GEO_WA2_1EL_POLICEDIST             CHAR(4)                      00020239
        BASED(ADDR(GEO_WA2_1EL_POLICE_DIST));                         00020339
                                                                      00020439
/*******************************************************************/ 00020539
                                                                      00020639
DCL                                                                   00020739
  1 GEO_WA2_FUNCTION3L  BASED(PW2L),                                  00020839
    2 GEO_WA2_3L_ACCESS_KEY              CHAR(21),                    00020939
    2 GEO_WA2_3L_DUP_KEY_FLAG            CHAR(1),                     00021039
```

```
2 GEO_WA2_3L_CURVE_FLAG              CHAR(1),                  00021139
2 GEO_WA2_3L_LOCATION_STATUS         CHAR(1),                  00021239
2 GEO_WA2_3L_COUNTY_BOUNDARY         CHAR(1),                  00021339
2 GEO_WA2_3L_COINCIDENT_SEG_CTR      CHAR(1),                  00021439
2 FILLER_W340                        CHAR(3),                  00021539
2 GEO_WA2_3L_PREFERRED_LGC1          CHAR(2),                  00021639
2 GEO_WA2_3L_PREFERRED_LGC2          CHAR(2),                  00021739
2 GEO_WA2_3L_PREFERRED_LGC3          CHAR(2),                  00021839
2 GEO_WA2_3L_NUM_X_ST_LOW_END        CHAR(1),                  00021939
2 GEO_WA2_3L_LOW_PBSC(5)             FIXED DEC(7),             00022039
2 GEO_WA2_3L_NUM_X_ST_HI_END         CHAR(1),                  00022139
2 GEO_WA2_3L_HI_PBSC(5)              FIXED DEC(7),             00022239
2 GEO_WA2_3L_SLA                     CHAR(1),                  00022339
2 GEO_WA2_3L_REVERSALFLAG            CHAR(1),                  00022439
2 GEO_WA2_3L_LEFT_COMMUN_DIST,                                 00022539
  3 GEO_WA2_3L_LEFT_COMDIST_BORO     CHAR(1),                  00022639
  3 GEO_WA2_3L_LEFT_COMDIST_NUMBER   CHAR(2),                  00022739
2 GEO_WA2_3L_RIGHT_COMMUN_DIST,                                00022839
  3 GEO_WA2_3L_RIGHT_COMDIST_BORO    CHAR(1),                  00022939
  3 GEO_WA2_3L_RIGHT_COMDIST_NUMBER  CHAR(2),                  00023039
2 GEO_WA2_3L_LEFT_ZIP                CHAR(5),                  00023139
2 GEO_WA2_3L_RIGHT_ZIP               CHAR(5),                  00023239
2 FILLER_W340B                       CHAR(18),                 00023339
2 GEO_WA2_3L_LEFT_HEALTHAREA         CHAR(4),                  00023440
2 GEO_WA2_3L_RIGHT_HEALTHAREA        CHAR(4),                  00023540
2 GEO_WA2_3L_LEFT_FILLER_INDV        CHAR(2),                  00023639
2 GEO_WA2_3L_RIGHT_FILLER_INDV       CHAR(2),                  00023739
2 GEO_WA2_3L_LEFT_LOW_HOUSENUM       CHAR(7),                  00023839
2 GEO_WA2_3L_LEFT_HI_HOUSENUM        CHAR(7),                  00023939
2 GEO_WA2_3L_RIGHT_LOW_HOUSENUM      CHAR(7),                  00024039
2 GEO_WA2_3L_RIGHT_HI_HOUSENUM       CHAR(7),                  00024139
2 GEO_WA2_3L_CONT_PARITY_IND         CHAR(1),                  00024239
2 GEO_WA2_3L_LIONFACECODE            CHAR(4),                  00024339
2 GEO_WA2_3L_LIONSEQ                 CHAR(5),                  00024439
2 GEO_WA2_3L_GENRECFLAG              CHAR(1),                  00024539
2 GEO_WA2_3L_SEGMENTLENGTH           FIXED DEC(5),             00024639
2 GEO_WA2_3L_SEGMENTSLOPE            CHAR(3),                  00024739
2 GEO_WA2_3L_SEGMENTORIENT           CHAR(1),                  00024839
2 FILLER_W355                        CHAR(4),                  00024939
2 GEO_WA2_3L_RESDCP                  CHAR(2),                  00025039
2 GEO_WA2_3L_DOG_LEG                 CHAR(1),                  00025139
2 GEO_WA2_3L_FEATURE_TYPE            CHAR(1),                  00025239
2 GEO_WA2_3L_LEFT_POLICE_DIST,                                 00025339
  3  GEO_WA2_3L_LEFT_POL_PAT_B_CMD   CHAR(1),                  00025439
  3  GEO_WA2_3L_LEFT_POL_PRECINCT    CHAR(3),                  00025539
```

```
    2 GEO_WA2_3L_RIGHT_POLICE_DIST,                                  00025639
      3  GEO_WA2_3L_RIGHT_POL_PAT_B_CMD   CHAR(1),                   00025739
      3  GEO_WA2_3L_RIGHT_POL_PRECINCT    CHAR(3),                   00025839
    2 GEO_WA2_3L_LEFT_SCHLDIST            CHAR(2),                   00025939
    2 GEO_WA2_3L_RIGHT_SCHLDIST           CHAR(2),                   00026039
    2 GEO_WA2_3L_MARBLE_RIKERS_FLAG       CHAR(1),                   00026139
    2 GEO_WA2_3L_SEGMENT_ID               CHAR(7),                   00026239
    2 GEO_WA2_3L_SEGMENT_TYPE             CHAR(1),                   00026339
/*************************************************************/       00026439
/**  THE PORTION OF THIS WORK AREA ABOVE THIS POINT IS      \**/       00026539
/**  IDENTICAL TO THE STANDARD WORK AREA 2 FOR FUNCTION 3.  \**/       00026639
/**  THE PORTION BELOW THIS POINT IS PRESENT ONLY FOR THE   \**/       00026739
/**  LONG WORK AREA 2 OPTION.                               \**/       00026839
/*************************************************************/       00026939
    2 GEO_WA2_3L_L_1990_CENSUSTRACT       CHAR(6),                   00027039
    2 FILLER_W370B                        CHAR(4),                   00027139
    2 GEO_WA2_L_3L_DYN_BLOCK              CHAR(3),/\*ATOMIC POLYGON*/  00027239
    2 GEO_WA2_3L_R_1990_CENSUSTRACT       CHAR(6),                   00027339
    2 FILLER_W370C                        CHAR(4),                   00027439
    2 GEO_WA2_R_3L_DYN_BLOCK              CHAR(3),/\*ATOMIC POLYGON*/  00027539
    2 GEO_WA2_3L_LEFT_FIRESEC             CHAR(2),/\*FIRE DIV*/       00027639
    2 GEO_WA2_3L_LEFT_FIREBAT             CHAR(2),                   00027739
    2 GEO_WA2_3L_LEFT_FIRECO,                                        00027839
      3 GEO_WA2_3L_LEFT_FIRECO_TYPE       CHAR(1),                   00027939
      3 GEO_WA2_3L_LEFT_FIRECO_NUM        CHAR(3),                   00028039
    2 GEO_WA2_3L_RIGHT_FIRESEC            CHAR(2),/\*FIRE DIV*/       00028139
    2 GEO_WA2_3L_RIGHT_FIREBAT            CHAR(2),                   00028239
    2 GEO_WA2_3L_RIGHT_FIRECO,                                       00028339
      3 GEO_WA2_3L_RIGHT_FIRECO_TYPE      CHAR(1),                   00028439
      3 GEO_WA2_3L_RIGHT_FIRECO_NUM       CHAR(3),                   00028539
    2 GEO_WA2_3L_L_2010_CENSUS_TRACT      CHAR(6),                   00028639
    2 GEO_WA2_3L_L_2010_CENSUS_BLOCK      CHAR(4),                   00028739
    2 GEO_WA2_3L_L_2010_CENSUS_BLK_SF     CHAR(1), /\*NOTIMPLEMENTED*/  00028839
    2 GEO_WA2_3L_R_2010_CENSUS_TRACT      CHAR(6),                   00028939
    2 GEO_WA2_3L_R_2010_CENSUS_BLOCK      CHAR(4),                   00029039
    2 GEO_WA2_3L_R_2010_CENSUS_BLK_SF     CHAR(1), /\*NOTIMPLEMENTED*/  00029139
    2 GEO_WA2_3L_FROM_NODE                CHAR(7),                   00029239
    2 GEO_WA2_3L_TO_NODE                  CHAR(7),                   00029339
    2 GEO_WA2_3L_L_2000_CENS_TRACT        CHAR(6),                   00029439
    2 GEO_WA2_3L_L_2000_CENS_BLOCK        CHAR(4),                   00029539
    2 GEO_WA2_3L_L_2000_CENS_BL_SUF       CHAR(1),                   00029639
    2 GEO_WA2_3L_R_2000_CENS_TRACT        CHAR(6),                   00029739
    2 GEO_WA2_3L_R_2000_CENS_BLOCK        CHAR(4),                   00029839
    2 GEO_WA2_3L_R_2000_CENS_BL_SUF       CHAR(1);                   00029939
DCL 1 GEO_WA2_3L_LEFT_COMDIST             CHAR(3)                    00030025
```

```
        BASED(ADDR(GEO_WA2_3L_LEFT_COMMUN_DIST));                    00030125
DCL 1 GEO_WA2_3L_RIGHT_COMDIST            CHAR(3)                    00030225
        BASED(ADDR(GEO_WA2_3L_RIGHT_COMMUN_DIST));                   00030325
DCL 1 GEO_WA2_3L_LEFT_POLICEDIST          CHAR(4)                    00030425
        BASED(ADDR(GEO_WA2_3L_LEFT_POLICE_DIST));                    00030525
DCL 1 GEO_WA2_3L_RIGHT_POLICEDIST         CHAR(4)                    00030625
        BASED(ADDR(GEO_WA2_3L_RIGHT_POLICE_DIST));                   00030725
PW2L=ADDR(W2PL1L);                                                   00030825
                                                                     00031025
/*******************************************************************/ 00040012
```

W2PL11A COPY File

```
/*******************************************************************/ 00000100
/***  THIS IS GEOSUPPORT SYSTEM COPY FILE W2PL11A, CONTAINING THE \***/ 00000200
/***  LAYOUT OF WORK AREA 2 FOR FUNCTIONS 1A AND BL WHICH SHARE   \***/ 00000300
/***  A SINGLE WORK AREA 2 LAYOUT.                     11/28/00  \***/ 00000403
/*******************************************************************/ 00000500
                                                                     00000600
 /*  STANDARD FORMAT  \*/                                             00000701
                                                                     00000800
 DCL                                                                 00000900
   1 W2PL11A,                                                        00001000
     2 GEO_WA2_1A_ACCESS_KEY              CHAR(21),                  00001100
     2 GEO_WA2_1A_CONT_PARITY             CHAR(1),                   00001200
     2 GEO_WA2_1A_LOW_HOUSENUM            CHAR(6),                   00001300
     2 GEO_WA2_1A_ALTKEY_1,                                          00001400
       3 GEO_WA2_1A_ALTKEY_1_BORO         CHAR(1),                   00001500
       3 GEO_WA2_1A_ALTKEY_1_TAXBLOCK     CHAR(5),                   00001600
       3 GEO_WA2_1A_ALTKEY_1_TAXLOT       CHAR(4),                   00001700
     2 GEO_WA2_1A_FILLER_230              CHAR(1),                   00001800
     2 GEO_WA2_1A_SCC                     CHAR(1),                   00001900
     2 GEO_WA2_1A_FILLER_240              CHAR(1),                   00002000
     2 GEO_WA2_1A_GENERAL_LOT_INFO,                                  00002100
       3 GEO_WA2_1A_RPAD_BLDG_CLASS       CHAR(2),                   00002200
       3 GEO_WA2_1A_CORNER_CODE           CHAR(2),                   00002300
       3 GEO_WA2_1A_NUM_OF_STRUCTURES     CHAR(2),                   00002400
       3 GEO_WA2_1A_NUM_OF_BLOCKFACES     CHAR(2),                   00002500
       3 GEO_WA2_1A_INTERIOR_FLAG         CHAR(1),                   00002600
       3 GEO_WA2_1A_VACANT_FLAG           CHAR(1),                   00002700
       3 GEO_WA2_1A_IRREG_LOT_FLAG        CHAR(1),                   00002800
     2 GEO_WA2_1A_ALT_BORO_FLAG           CHAR(1),                   00002900
     2 GEO_WA2_1A_FILLER_245              CHAR(1),                   00003000
     2 GEO_WA2_1A_STROLL_KEY              CHAR(13),                  00003100
     2 GEO_WA2_1A_OVERFLOW_FLAG           CHAR(1),                   00003202
```

```
      2 GEO_WA2_1A_FILLER_251              CHAR(1), /\*USED FOR DCP*/  00003300
      2 GEO_WA2_1A_BIN                     CHAR(7),                    00003400
      2 GEO_WA2_1A_CONDO_FLAG              CHAR(1),                    00003500
      2 GEO_WA2_1A_RPAD_CONDO_ID_NUM       CHAR(4),                    00003600
      2 GEO_WA2_1A_CONDO_LOW_BBL           CHAR(10),                   00003700
      2 GEO_WA2_1A_FILLER_260              CHAR(1),                    00003800
      2 GEO_WA2_1A_CONDO_BILL_BBL          CHAR(10),                   00003900
      2 GEO_WA2_1A_FILLER_270              CHAR(1),                    00004000
      2 GEO_WA2_1A_CONDO_BILL_BBL_SCC      CHAR(1),                    00004100
      2 GEO_WA2_1A_CONDO_HIGH_BBL          CHAR(10),                   00004200
      2 GEO_WA2_1A_FILLER_275              CHAR(1),                    00004300
      2 GEO_WA2_1A_SANBORN_BORO            CHAR(1),                    00004400
      2 GEO_WA2_1A_SANBORN_VOL_PAGE,                                   00004500
        3 GEO_WA2_1A_SANBORN_VOL_NUM       CHAR(3),                    00004600
        3 GEO_WA2_1A_SANBORN_PAGE_NUM      CHAR(4),                    00004700
      2 GEO_WA2_1A_COMMERC_DIST            CHAR(5),                    00004800
      2 GEO_WA2_1A_COOP_NUM                CHAR(4),                    00004904
      2 GEO_WA2_1A_FILLER_276              CHAR(4),                    00005007
      2 GEO_WA2_1A_ACTUAL_NUM_OF_STRUCT    CHAR(4),                    00005106
      2 GEO_WA2_1A_DOF_MAP_BORO            CHAR(1),                    00005207
      2 GEO_WA2_1A_DOF_MAP_SECVOL          CHAR(4),                    00005307
      2 GEO_WA2_1A_DOF_MAP_PAGE            CHAR(4),                    00005407
      2 GEO_WA2_1A_X_COORD                 CHAR(7),                    00005508
      2 GEO_WA2_1A_Y_COORD                 CHAR(7),                    00005608
      2 GEO_WA2_1A_BID                     CHAR(6),                    00005809
      2 GEO_WA2_1A_FILLER_280              CHAR(2),                    00005909
      2 GEO_WA2_1A_FILLER_LGCS             CHAR(8),                    00006010
      2 GEO_WA2_1A_FILLER_280A             CHAR(2),                    00006109
      2 GEO_WA2_1A_NUM_OF_ADDR_FOR_LOT     CHAR(2),                    00006209
      2 GEO_WA2_1A_LIST_OF_ADDRESSES(21),                              00006309
        3 GEO_WA2_1A_LIST_LOW_HOUSENUM     CHAR(6),                    00006409
        3 GEO_WA2_1A_FILLER_290            CHAR(3),                    00006509
        3 GEO_WA2_1A_LIST_HI_HOUSENUM      CHAR(6),                    00006609
        3 GEO_WA2_1A_FILLER_300            CHAR(3),                    00006709
        3 GEO_WA2_1A_LIST_STREETCODE       CHAR(8),                    00006809
        3 GEO_WA2_1A_LIST_BIN              CHAR(7),                    00006909
        3 GEO_WA2_1A_ADDR_TYPE             CHAR(1),                    00007009
        3 GEO_WA2_1A_FILLER_310            CHAR(1),                    00007109
        3 GEO_WA2_1A_LIST_SOS              CHAR(1);                    00007209
DCL   GEO_WA2_1A_SANBORN_BVOLPAGE          CHAR(8)                     00007309
        BASED(ADDR(GEO_WA2_1A_SANBORN_BORO));                          00008009
```

W2PL11AL COPY File

```
/*********************************************************************/ 00000100
```

```
/***  THIS IS GEOSUPPORT SYSTEM COPY FILE W2PL11AL, CONTAINING THE***/ 00000200
/***  LAYOUT OF LONG WORK AREA 2 FOR FUNCTIONS 1A AND BL WHICH    \***/ 00000300
/***  SHARE A SINGLE WORK AREA 2 LAYOUT.              11/28/00   \***/ 00000402
/*******************************************************************/ 00000500
                                                                      00000600
 /*  1A/BL LONG WORK AREA 2 \*/                                        00000700
                                                                      00000800
 DCL                                                                  00000900
   1 W2PL11AL,                                                        00001000
     2 GEO_WA2_1AL_ACCESS_KEY                CHAR(21),                00001100
     2 GEO_WA2_1AL_CONT_PARITY               CHAR(1),                 00001200
     2 GEO_WA2_1AL_LOW_HOUSENUM              CHAR(6),                 00001300
     2 GEO_WA2_1AL_ALTKEY_1,                                          00001400
       3 GEO_WA2_1AL_ALTKEY_1_BORO           CHAR(1),                 00001500
       3 GEO_WA2_1AL_ALTKEY_1_TAXBLOCK       CHAR(5),                 00001600
       3 GEO_WA2_1AL_ALTKEY_1_TAXLOT         CHAR(4),                 00001700
     2 GEO_WA2_1AL_FILLER_230                CHAR(1),                 00001800
     2 GEO_WA2_1AL_SCC                       CHAR(1),                 00001900
     2 GEO_WA2_1AL_FILLER_240                CHAR(1),                 00002000
     2 GEO_WA2_1AL_GENERAL_LOT_INFO,                                  00002100
       3 GEO_WA2_1AL_RPAD_BLDG_CLASS         CHAR(2),                 00002200
       3 GEO_WA2_1AL_CORNER_CODE             CHAR(2),                 00002300
       3 GEO_WA2_1AL_NUM_OF_STRUCTURES       CHAR(2),                 00002400
       3 GEO_WA2_1AL_NUM_OF_BLOCKFACES       CHAR(2),                 00002500
       3 GEO_WA2_1AL_INTERIOR_FLAG           CHAR(1),                 00002600
       3 GEO_WA2_1AL_VACANT_FLAG             CHAR(1),                 00002700
       3 GEO_WA2_1AL_IRREG_LOT_FLAG          CHAR(1),                 00002800
     2 GEO_WA2_1AL_ALT_BORO_FLAG             CHAR(1),                 00002900
     2 GEO_WA2_1AL_FILLER_245                CHAR(1),                 00003000
     2 GEO_WA2_1AL_STROLL_KEY                CHAR(13),                00003100
     2 GEO_WA2_1AL_FILLER_250                CHAR(1),                 00003200
     2 GEO_WA2_1AL_FILLER_251                CHAR(1), /\*USED FOR DCP*/ 00003300
     2 GEO_WA2_1AL_BIN                       CHAR(7),                 00003400
     2 GEO_WA2_1AL_CONDO_FLAG                CHAR(1),                 00003500
     2 GEO_WA2_1AL_RPAD_CONDO_ID_NUM         CHAR(4),                 00003600
     2 GEO_WA2_1AL_CONDO_LOW_BBL             CHAR(10),                00003700
     2 GEO_WA2_1AL_FILLER_260                CHAR(1),                 00003800
     2 GEO_WA2_1AL_CONDO_BILL_BBL            CHAR(10),                00003900
     2 GEO_WA2_1AL_FILLER_270                CHAR(1),                 00004000
     2 GEO_WA2_1AL_CONDO_BILL_BBL_SCC        CHAR(1),                 00004100
     2 GEO_WA2_1AL_CONDO_HIGH_BBL            CHAR(10),                00004200
     2 GEO_WA2_1AL_FILLER_275                CHAR(1),                 00004300
     2 GEO_WA2_1AL_SANBORN_BORO              CHAR(1),                 00004400
     2 GEO_WA2_1AL_SANBORN_VOL_PAGE,                                  00004500
       3 GEO_WA2_1AL_SANBORN_VOL_NUM         CHAR(3),                 00004600
```

```
        3 GEO_WA2_1AL_SANBORN_PAGE_NUM        CHAR(4),                  00004700
      2 GEO_WA2_1AL_COMMERC_DIST              CHAR(5),                  00004800
      2 GEO_WA2_1AL_COOP_NUM                  CHAR(4),                  00004903
      2 GEO_WA2_1AL_FILLER_276                CHAR(4),                  00005008
      2 GEO_WA2_1AL_ACTUAL_NUM_STRUCTS        CHAR(4),                  00005106
      2 GEO_WA2_1AL_DOF_MAP_BORO              CHAR(1),                  00005208
      2 GEO_WA2_1AL_DOF_MAP_SECVOL            CHAR(4),                  00005308
      2 GEO_WA2_1AL_DOF_MAP_PAGE              CHAR(4),                  00005408
      2 GEO_WA2_1AL_X_COORD                   CHAR(7),                  00005509
      2 GEO_WA2_1AL_Y_COORD                   CHAR(7),                  00005609
      2 GEO_WA2_1AL_BID                       CHAR(6),                  00005710
      2 GEO_WA2_1AL_FILLER_280                CHAR(2),                  00005810
      2 GEO_WA2_1AL_FILLER_LGCS               CHAR(8),                  00005911
      2 GEO_WA2_1AL_NUM_OF_BINS_FOR_LOT       CHAR(4),                  00006110
      2 GEO_WA2_1AL_BINS(2500)                CHAR(7);                  00006210
                                                                        00006310
DCL   GEO_WA2_1AL_SANBORN_BVOLPAGE            CHAR(8)                   00006410
        BASED(ADDR(GEO_WA2_1AL_SANBORN_BORO));                          00007009
```

W2PL13S COPY File

```
/*****************************************************************/  00000010
/** THIS IS GEOSUPPORT SYSTEM COPY FILE W2PL13S, CONTAINING THE   \**/  00000020
/** LAYOUT OF WORK AREA 2 FOR FUNCTION 3S.              9/22/93  \**/  00000030
/*****************************************************************/  00000040
 DCL                                                                   00000050
   1 W2PL13S,                                                          00000060
     2 GEO_WA2_3S_ACCESS_KEY                CHAR(21),                  00000070
     2 GEO_WA2_3S_NUM_OF_INTERSECTS         CHAR(3),                   00000080
     2 GEO_WA2_3S_LIST_OF_INTERSECTS(350),                             00000090
       3 GEO_WA2_3S_SMALLEST_PBSC           FIXED DEC(7),              00000100
       3 GEO_WA2_3S_2ND_SMALLEST_PBSC       FIXED DEC(7),              00000110
       3 GEO_WA2_3S_DISTANCE                FIXED DEC(5),              00000120
       3 GEO_WA2_3S_GAP_FLAG                CHAR(1);                   00000130
```

C COPY File (MSW)

WAC COPY File

```
/*****************************************************************/
/* Modified - 2 June  2011 (added fields: 2010 Census Tract,Block   \*/
/*                          and Suffix for funcions 1,1E,2,3,3c).   \*/
/* Modified - 5 March 2009                                          \*/
/*****************************************************************/
typedef struct {
```

```
struct {
        char func_code[2];      /* Function Code           \*/
        char boro_1;            /* Borough Code of First St \*/
        char hse_nbr_disp[12];  /* House nbr in Disp form   \*/
        char hse_nbr_hni[6];    /* House nbr in HNI form    \*/
        char street_name_1[32]; /* First Street Name        \*/
        char street_name_2[32]; /* Second Street Name       \*/
        char street_name_3[32]; /* Third Street Name        \*/
        char comp_direction;    /* Compass Direction        \*/
        char comp_direction2;   /* Compass Direction-Fn 3S  \*/
        char PB5SC_1[4];        /* Packd Boro 5 digt St Code*/
        char PB5SC_2[4];        /* Packd Boro 5 digt St Code*/
        char PB5SC_3[4];        /* Packd Boro 5 digt St Code*/
        char roadbedreq;        /* Roadbed Request Switch   \*/
        char boro_2;            /* Boro Code of Second Strt \*/
        char boro_3;            /* Boro Code of Third Street*/
        char snl[2];            /* Street Name Norm Length  \*/
        char B10SC_1[11];       /* 1st Boro & 10 Digt St Cod*/
        char B10SC_2[11];       /* 2nd Boro & 10 Digt St Cod*/
        char B10SC_3[11];       /* 3rd Boro & 10 Digt St Cod*/
        char zipin[5];          /* Input Zip Code           \*/
        char BBL[10];           /* Boro(len=1), Block(len=5)\*/
                                /* and Lot (len=4)          \*/
        char filler04;
        char bld_id[7];         /* Bld Id Number (BIN)      \*/
        char compact_flag;      /* Compact Street Names flag*/
        char long_WA_flag;      /* Long Work Area 2 Flag    \*/
        char lo_range_hnd[12];  /* Low HND of Range         \*/
        char lo_range_hni[6];   /* Low HNI of Range         \*/
        char not_IBM_flag;      /* Non-IBM Mainframe Flag   \*/
        char BL1A;              /* 1A/BL Version Switch     \*/
        char xstreet_flag;      /* Cross Street Names Flag  \*/
        char filler06[4 ];
       } input;
struct {
        char lo_hse_nbr_disp[12]; /* Low HND of Range       \*/
        char boro_name[9];      /* Boro Name of First Street*/
        char street_name_1[32]; /* 1st St Name - Normalized \*/
        char street_name_2[32]; /* 2nd St Name - Normalized \*/
        char street_name_3[32]; /* 3rd St Name - Normalized \*/
        char hse_nbr_disp[12];  /* House nbr in Normalized  \*/
                                /* Display form             \*/
        char hse_nbr_hni[6];    /* House number in HNI form \*/
        char filler01[7];
        char PB5SC_1[4];        /* Packd Boro 5 digt St Code*/
```

```
                 char filler02[2];
                 char PB5SC_2[4];        /* Packd Boro 5 digt St Code*/
                 char filler03[2];
                 char PB5SC_3[4];        /* Packd Boro 5 digt St Code*/
                 char attrbytes[3];      /* Attribute Bytes - int use*/
                 char br_pb5sc[10][4];   /* Up to 10 PB5SCs-Browse fn*/
                 char B10SC_1[11];       /* 1st Boro & 10 Digt St Cod*/
                 char B10SC_2[11];       /* 2nd Boro & 10 Digt St Cod*/
                 char B10SC_3[11];       /* 3rd Boro & 10 Digt St Cod*/
                 char condo_nbr[5];      /* Condo Number             \*/
                 char BBL[10];           /* Boro(len=1), Block(len=5)\*/
                                         /* and Lot (len=4)-Normalizd*/
                 char filler06[1];
                 char bld_id[7];         /* Building Id Number       \*/
                 char intuse1;           /* Internal Use Only        \*/
                 char reject_reason_code;/* Reject Reason Code       \*/
                 char filler07[2];
                 char ret_code[2];       /* GeoSupport Return Code   \*/
                 char msg[80];           /* GeoSupport Message       \*/
                 char nbr_sim_names[2];  /* Nbr of Similar St Names  \*/
                 char sim_names[10][32]; /* Up to 10 Similar St Names*/
                } output;
               } C_WA1;

typedef struct { char filler01[21];
                 char cont_parity_ind;   /* Continuous Parity Ind.   \*/
                 char lo_hse_nbr[6];     /* Low House nbr in HNI form*/
                 char hi_hse_nbr[6];     /* Hi House Nbr in HNI form \*/
                 char alx;               /* A=Alley intersects segmnt*/
                                         /* X=Cross Streets modified \*/
                 char lo_nbr_x_sts;      /* Nbr of cross streets at  \*/
                                         /* low house nbr end of st  \*/
                 char l_x_sts[5][4];     /* PB5SCs of lo end cross st*/
                 char hi_nbr_x_sts;      /* Nbr of cross streets at  \*/
                                         /* low house nbr end of st  \*/
                 char h_x_sts[5][4];     /* PB5SCs of lo end cross st*/
                 char com_dist[3];       /* Community District       \*/
                                         /* Position 0 contains the  \*/
                                         /* Legacy Boro Code & Pos 1 \*/
                                         /* & 2, the district nbr    \*/
                 char zip_code[5];       /* Zip code for st seg      \*/
                 char DOT_slca;          /* DOT St Lght Contractr Are*/
                 char health_cent[2];    /* Health Center District   \*/
                 char sos_ind;           /* Side of Street Indicator \*/
                 char cont_par;          /* Continuous Parity Ind.   \*/
```

```
char cen_tract_10[6];   /* 2010 Census Tract        \*/
char cen_blk_10[4];     /* 2010 Census Block        \*/
char cen_blk_10_sufx;   /* 2010 Census Block Suffix \*/
char filler_indv;       /* Was Instructional Divisn \*/
char filler07[2];       /* Filler                   \*/
char health_area[4];    /* Health Area              \*/
char sanit_recycle[3];  /* Recycling Sanit pick-up  \*/
char feature_type;      /* Feature Type Code        \*/
char iaei;              /* Community Development    \*/
                        /* Eligibility Indicator    \*/
char curve_flag;        /* Curve Flag               \*/
char police_boro_com;   /* Police Patrol Boro Commnd*/
char police_pre[3];     /* Police Precinct          \*/
char com_schl_dist[2];  /* Community School District*/
                        /* Following 7 fields are   \*/
                        /* used for Function 1E only*/
char ed[3];             /* Election District        \*/
char ad[2];             /* Assembly District        \*/
char sped_flag;         /* Split Elect District Flag*/
char congress_dist[2];  /* Congressional District   \*/
char state_sen_dist[2]; /* State Senatorial District*/
char civil_court[2];    /* Civil Court District     \*/
char civil_council[2];  /* City Council District    \*/
char coincident_seg_cnt; /* Coincident Segment      \*/
                        /*   Count                  \*/
char segtypecode;       /* Segment Type Code        \*/
char sanit_dist[3];     /* Sanitation District      \*/
char sanit_sub_sect[2]; /* Sanit Collect Scheduling \*/
                        /* Section and Subsection   \*/
char fire_divisn[2];    /* Fire Division            \*/
char fire_bat[2];       /* Fire Battalion           \*/
char fire_co_type;      /* Fire Company Type        \*/
char fire_co_nbr[3];    /* Fire Company Number      \*/
char sagr_flag;         /* Special Address Generated*/
                        /* Record flag              \*/
char mh_ri_flag;        /* Marble Hill/Rikers Island*/
                        /* Alternative Borough flag \*/
char scsd_flag;         /* Split Com School District*/
                        /* flag                     \*/
char DCP_lgc[2];        /* DCP preferred LGC        \*/
char face_code[4];      /* LION Face Code           \*/
char seq_nbr[5];        /* LION Sequence Number     \*/
char cen_tract_90[6];   /* 1990 Census Tract        \*/
char filler09  [4];     /* Filler                   \*/
char dynam_blk[3];      /* Dynamic Block            \*/
```

```
                  char X_coord[7];        /* X coordinate            \*/
                  char Y_coord[7];        /* Y coordinate            \*/
                  char seg_len[5];        /* Segment Length in Feet  \*/
                  char sanit_reg_sched[5];/* Regularly Sanit pick-up \*/
                } C_WA2_F1;

typedef struct { C_WA2_F1 c_wa2_f1;       /* First 200 Bytes         \*/
                  char seg_id[7];         /* Segment Identifier      \*/
                  char true_b7sc[8];      /* "true" Boro 7 Str code  \*/
                  char true_hni [6];      /* Underlying HNI          \*/
                  char cen_tract_2000[6]; /* 2000 Census Tract       \*/
                  char cen_blk_2000[4];   /* 2000 Census Block       \*/
                  char cen_blk_2000_sufx; /* 2000 Census Block Suffix \*/
                  char filler01[68];      /* Filler - Future Use     \*/
            /*    char filler01[79];      /* Filler - Future Use     \*/
                } C_WA2_F1L;

typedef struct { char lo_hse_nbr[6];      /* Low House nbr in HNI form*/
                  char filler01[3];
                  char hi_hse_nbr[6];     /* Hi House Nbr in HNI form \*/
                  char filler02[3];
                  char B5SC[6];           /* Boro & 5 digit Str Code  \*/
                  char lgc[2];            /* LGC of Street           \*/
                  char bld_id[7];         /* BIN of address range    \*/
                  char addr_type;         /* Address Type            \*/
                  char filler04;
                  char sos_ind;           /* Side of Street Indicator \*/
                } ADDR_RANGE;

typedef struct { char sanborn_boro;       /* Sanborn Borough Code    \*/
                  char sanborn_vol[3];    /* Sanborn Volume          \*/
                  char sanborn_page[4];   /* Sanborn Page            \*/
                } SANBORN;

typedef struct { char filler01[21];
                  char cont_parity_ind;   /* Continuous Parity Ind   \*/
                  char lo_hse_nbr[6];     /* Low House Number        \*/
                  char BBL[10];           /* Boro(len=1), Block(len=5)\*/
                                          /* and Lot (len=4)         \*/
                  char tax_lot_ver_nbr;   /* Tax Lot Version Number  \*/
                  char RPAD_scc;          /* RPAD Self_Check Code(SCC)\*/
                  char filler02;
                  char RPAD_lucc[2];      /* RPAD Land Use Class. Code*/
                  char corner[2];         /* Corner Code             \*/
                  char nbr_blds[2];       /* Nbr of buildings on lot \*/
```

```
                 char nbr_str[2];        /* Nbr Street Frontages     \*/
                 char inter_flag;        /* Interior Lot Flag        \*/
                 char vacant_flag;       /* Vacant Lot Flag          \*/
                 char irreg_flag;        /* Irregularly-Shaped Lot Fl*/
                 char mh_ri_flag;        /* Marble Hill/Rikers Island*/
                 char filler03;          /* Former Pseudo-Address Flg*/
                 char stroll_key[13];    /* Strolling key            \*/
                 char overflow_flag;     /* More than 21 Addresses   \*/
                 char res_internal_use;  /* Reserved for Internal Use*/
                 char bld_id[7];         /* Bld Identification Nbr   \*/
                                         /* (BIN) of Input Address of*/
                                         /* Existing Building, If any*/
                 char condo_flag;        /* Condominium Flag         \*/
                 char RPAD_cin[4];       /* RPAD Condo Id Number     \*/
                 char condo_lo_BBL[10];  /* Low BBL of Condo         \*/
                 char filler05;
                 char condo_bill_BBL[10];/* Condo Billing BBL        \*/
                 char filler06;
                 char condo_bill_BBL_scc;/* Condo Billing BBL        \*/
                                         /* Self-Check Code          \*/
                 char condo_hi_BBL[10];  /* High BBL of Condo        \*/
                 char filler07;
                 SANBORN fn1A_Sanborn;   /* Sanborn Information      \*/
                 char business_area[5];  /* Business Area            \*/
                 char co_op_nbr[4 ];     /* Co-op Number             \*/
                 char filler08[4 ];
                 char tot_nbr_bldgs[4 ]; /* Actual Nbr Bldgs on lot  \*/
                 char tax_map_nbr[5 ];   /* Tax Map Nbr-Sect and Vol \*/
                 char filler09[04];
                 char X_coord[7];        /* X coordinate-Annotation p*/
                 char Y_coord[7];        /* Y coordinate-Annotation p*/
                 char bid_id[6];         /* Business Improvement Dist*/
                 char filler10[2];
                 char int_use[8];
                 char filler11[2];
                 char nbr_addr[2];       /* Nbr of Addr Ranges on Lot*/
                 ADDR_RANGE addr_range[21]; /* Addr Range structure  \*/
               } C_WA2_F1A;

typedef struct { char filler01[21];
                 char cont_parity_ind;   /* Continuous Parity Ind    \*/
                 char lo_hse_nbr[6];     /* Low House Number         \*/
                 char BBL[10];           /* Boro(len=1), Block(len=5)\*/
                                         /* and Lot (len=4)          \*/
                 char tax_lot_ver_nbr;   /* Tax Lot Version Number   \*/
```

```
                    char RPAD_scc;          /* RPAD Self_Check Code(SCC)\*/
                    char filler02;
                    char RPAD_lucc[2];      /* RPAD Land Use Class. Code*/
                    char corner[2];         /* Corner Code              \*/
                    char nbr_blds[2];       /* Nbr of buildings on lot  \*/
                    char nbr_str[2];        /* Nbr Street Frontages     \*/
                    char inter_flag;        /* Interior Lot Flag        \*/
                    char vacant_flag;       /* Vacant Lot Flag          \*/
                    char irreg_flag;        /* Irregularly-Shaped Lot Fl*/
                    char mh_ri_flag;        /* Marble Hill/Rikers Island*/
                    char filler03;          /* Former Pseudo-Address Flg*/
                    char stroll_key[13];    /* Strolling key            \*/
                    char filler04;
                    char res_internal_use;  /* Reserved for Internal Use*/
                    char bld_id[7];         /* Bld Identification Nbr   \*/
                                            /* (BIN) of Input Address of*/
                                            /* Existing Building, If any*/
                    char condo_flag;        /* Condominium Flag         \*/
                    char RPAD_cin[4];       /* RPAD Condo Id Number     \*/
                    char condo_lo_BBL[10];  /* Low BBL of Condo         \*/
                    char filler05;
                    char condo_bill_BBL[10];/* Condo Billing BBL        \*/
                    char filler06;
                    char condo_bill_BBL_scc;/* Condo Billing BBL        \*/
                                            /* Self-Check Code          \*/
                    char condo_hi_BBL[10];  /* High BBL of Condo        \*/
                    char filler07;
                    SANBORN fn1A_Sanborn;   /* Sanborn Information      \*/
                    char business_area[5];  /* Business Area            \*/
                    char co_op_nbr[4 ];     /* Co-op number             \*/
                    char filler08[4 ];
                    char tot_nbr_bldgs[4 ]; /* Actual Nbr Bldgs on lot  \*/
                    char tax_map_nbr[5 ];   /* Tax Map Nbr-Sect and Vol \*/
                    char filler09[04];
                    char X_coord[7];        /* X coordinate-Annotation p*/
                    char Y_coord[7];        /* Y coordinate-Annotation p*/
                    char bid_id[6];         /* Business Improvement Dist*/
                    char filler10[2];
                    char int_use[8];
                    char nbr_bins[4];       /* Nbr of BINS on Lot       \*/
                    char bin_list[2500][7]; /* List of BINS on Lot      \*/
                  } C_WA2_F1AL;

typedef struct { char filler01[31];
                    char lgc[2][2];         /* Preferred LGCs           \*/
```

```
                char nbr_x_sts;         /* Number of Intersecting St*/
                char x_sts[5][4];       /* PB5SCs of Intersection St*/
                char compdir[1];        /* Compass Direction if 2   \*/
                                        /* lowest str codes cross   \*/
                                        /* exactly twice            \*/
                char level_codes[10];   /* Level Codes of X Streets \*/
                char instruc_div[2];    /* Instructional Division   \*/
                char fire_sector[2];    /* Fire Sector              \*/
                char fire_bat[2];       /* Fire Battalion           \*/
                char fire_co_type;      /* Fire Company Type        \*/
                char fire_co_nbr[3];    /* Fire Company Number      \*/
                char com_dist[3];       /* Community District       \*/
                                        /* Pos 0 contains the Boro  \*/
                                        /* Code and Positions 1 & 2 \*/
                                        /* contain the district nbr \*/
                char zip_code[5];       /* Zip code for st segment  \*/
                char DOT_slca;          /* DOT St Lght Contractr Are*/
                char cen_tract_10[6];   /* 2010 Census Tract        \*/
                char filler03[3];
                char health_area[4];    /* Health Area              \*/
                char filler04[9];
                char node_nbr[7 ];      /* Node Number              \*/
                char X_coord[7];        /* X coordinate             \*/
                char Y_coord[7];        /* Y coordinate             \*/
                char filler04a[2];      /*                          \*/
                char filler05[2];
                char police_boro_com;   /* Police Patrol Boro Commnd*/
                char police_pre[3];     /* Police Precinct          \*/
                char com_schl_dist[2];  /* Community School District*/
                                        /* Following 7 fields are   \*/
                                        /* used forFunction 1E only \*/
                char mh_ri_flag;        /* Marble Hill/Rikers Island*/
                char cen_tract_90[6];   /* 1990 Census Tract        \*/
                SANBORN fn2_Sanborn[2]; /* Sanborn Information      \*/
                char dup_intersect_distance[5];  /* Distance in Feet*/
                                        /* Bet Duplicate Intersects \*/
                char cen_tract_2000[6]; /* 2000 Census Tract        \*/
                char filler06[27];
            /*  char filler06[33]; \*/
              } C_WA2_F2;

typedef struct { char filler01[21];
                char dup_key_flag;      /* Duplicate Key Flag      \*/
                char curve_flag;        /* Curve Flag              \*/
                char loc_stat_seg;      /* Locational Status of Seg*/
```

```
char cnty_bnd_ind;      /* County Boundary Indicat \*/
char coincident_seg_cnt; /* Coincident Segment      \*/
                        /*   Count                 \*/
char filler03[3];       /* Future Use              \*/
char lgc[3][2];         /* Preferred LGCs          \*/
char lo_nbr_x_sts;      /* Nbr of cross sts at low  \*/
                        /* house nbr end of street  \*/
char l_x_sts[5][4];     /* PB5SCs of lo end X sts   \*/
char hi_nbr_x_sts;      /* Number of X streets at lo*/
                        /* house nbr end of street  \*/
char h_x_sts[5][4];     /* PB5SCs of low end X sts  \*/
char DOT_slca;          /* DOT St Lght Contractr Are*/
char x_street_reversal_flag; /* X St Reversal Flag  \*/
char l_com_dist[3];     /* Left Community District  \*/
                        /* Position 0 contains the  \*/
                        /* Boro Code and Pos 1 & 2  \*/
                        /* contain the district nbr \*/
char r_com_dist[3];     /* Right Community District \*/
                        /* Position 0 contains the  \*/
                        /* Boro Code and Pos 1 & 2  \*/
                        /* contain the district nbr \*/
char l_zip_code[5];     /* Left Zip code for st seg \*/
char r_zip_code[5];     /* Right Zip code for st seg*/
char filler07 [18];
char l_health_area[4];  /* Left Health Area        \*/
char r_health_area[4];  /* Right Health Area       \*/
char l_fill_in_div[2];  /* Was Left Instructionl Div*/
char r_fill_in_div[2];  /* Was Right Instructnl Div \*/
char l_lo_hse_nbr[7];   /* Left Lo Hse nbr in Disp  \*/
char l_hi_hse_nbr[7];   /* Left Hi Hse Nbr in Disp  \*/
char r_lo_hse_nbr[7];   /* rght Lo Hse nbr in Disply*/
char r_hi_hse_nbr[7];   /* rght Hi Hse Nbr in Disply*/
char cont_par;          /* Continuous Parity Ind    \*/
char face_code[4];      /* LION Face Code          \*/
char seq_nbr[5];        /* LION Sequence Nbr       \*/
char genr_flag;         /* Generated Record Flag   \*/
char seg_len[3];        /* Segment Length in Feet  \*/
char seg_azm[3];        /* Segment Azimuth         \*/
char seg_orient;        /* Segment Orientation     \*/
char filler04a[2];      /*                         \*/
char filler04b[2];      /*                         \*/
char l_iaei;            /* Community Development   \*/
                        /* Eligibility Indicator for*/
                        /* left side               \*/
char r_iaei;            /* Community Development   \*/
```

```
                                        /* Eligibility Indicator for*/
                                        /* right side               \*/
                  char dog_leg;         /* Dog Leg Flag             \*/
                  char feature_type;    /* Feature Type Code        \*/
                  char l_police_boro_com; /* Lft Police Patrl Boro Com*/
                  char l_police_pre[3];   /* Left Police Precinct     \*/
                  char r_police_boro_com; /* Rght Police Patrl Boro Cm*/
                  char r_police_pre[3];   /* Right Police Precinct    \*/
                  char l_com_schl_dist[2];/* Lft Com School District  \*/
                  char r_com_schl_dist[2];/* Rght Com School District \*/
                  char mh_ri_flag;        /* Marble Hill/Rikers Island*/
                                          /* Alternative Boro flag    \*/
                  char seg_id[7];         /* Segment Identifier       \*/
                  char segtypecode;       /* Segment Type Code        \*/
                } C_WA2_F3;

typedef struct { C_WA2_F3 c_wa2_f3;       /* First 200 Bytes          \*/
                  char l_cen_tract_90[6]; /* Left 1990 Census Tract   \*/
                  char filler01[4];       /* Filler                   \*/
                  char l_dynam_blk[3];    /* Left Dynamic Block       \*/
                  char r_cen_tract_90[6]; /* Right 1990 Census Tract  \*/
                  char filler03[4];       /* Filler                   \*/
                  char r_dynam_blk[3];    /* Right Dynamic Block      \*/
                  char l_fire_sector[2];  /* Left Fire Sector         \*/
                  char l_fire_bat[2];     /* Left Fire Battalion      \*/
                  char l_fire_co_type;    /* Left Fire Company Type   \*/
                  char l_fire_co_nbr[3];  /* Left Fire Company Nbr    \*/
                  char r_fire_sector[2];  /* Right Fire Sector        \*/
                  char r_fire_bat[2];     /* Right Fire Battalion     \*/
                  char r_fire_co_type;    /* Right Fire Company Type  \*/
                  char r_fire_co_nbr[3];  /* Right Fire Company Nbr   \*/
                  char l_cen_tract_10[6]; /* Left 2010 Census Tract   \*/
                  char l_cen_blk_10[4];   /* Left 2010 Census Block   \*/
                  char l_cen_blk_10_sufx; /* Left 2010 Census Blk Sufx*/
                  char r_cen_tract_10[6]; /* Right 2010 Census Tract  \*/
                  char r_cen_blk_10[4];   /* Right 2010 Census Block  \*/
                  char r_cen_blk_10_sufx; /* Right 2010 Census Blk Sfx*/
                  char nodes[2][7];       /* From and To Nodes        \*/
                  char l_cen_tract_2000[6];/\*Left 2000 Census Tract   \*/
                  char l_cen_blk_2000[4];  /\*Left 2000 Census Block   \*/
                  char l_cen_blk_2000_sufx;/\*Left 2000 Census Blk Sufx\*/
                  char r_cen_tract_2000[6];/\*Right 2000 Census Tract  \*/
                  char r_cen_blk_2000[4];  /\*Right 2000 Census Block  \*/
                  char r_cen_blk_2000_sufx;/\*Right 2000 Census Blk Sfx*/
            //    char filler02[22];
```

```
                } C_WA2_F3L;

typedef struct { char filler01[21];
                 char curve_flag;        /* curve flag               \*/
                 char segtypecode;       /* Segment Type Code        \*/
                 char loc_stat_seg;      /* Location Status of Seg.  \*/
                 char cnty_bnd_ind;      /* County Boundary Indicator*/
                 char coincident_seg_cnt; /* Coincident Segment      \*/
                                         /*   Count                 \*/
                 char filler0A[3]; /* Future Use               \*/
                 char lgc[3][2];         /* Preferred LGCs           \*/
                 char lo_nbr_x_sts;      /* Nbr of cross sts at low  \*/
                                         /* house nbr end of street  \*/
                 char l_x_sts[5][4];     /* PB5SCs of lo end cross st*/
                 char hi_nbr_x_sts;      /* Nbr of cross sts at low  \*/
                                         /* house nbr end of street  \*/
                 char h_x_sts[5][4];     /* PB5SCs of lo end X sts   \*/
                 char com_dist[3];       /* Community District Pos 0 \*/
                                         /* contains the Boro Code & \*/
                                         /* Positions 1&2 contain the*/
                                         /* district nbr             \*/
                 char zip_code[5];       /* Zip code for street seg  \*/
                 char DOT_slca;          /* DOT St Lght Contractr Are*/
                 char cen_tract_2000[6]; /* 2000 Census Tract        \*/
                 char filler02[1];
               // char filler02[7];
                 char cen_tract_10[6];   /* 2010 Census Tract        \*/
                 char cen_blk_10[4];     /* 2010 Census Block        \*/
                 char cen_blk_10_sufx;   /* 2010 Census Block Suffix \*/
                 char health_area[4];    /* Health Area              \*/
                 char x_street_reversal_flag; /* X St Reversal Flag  \*/
                 char sos_ind;           /* Side of Street Indicator \*/
                 char fire_sector[2];    /* Fire Sector              \*/
                 char fire_bat[2];       /* Fire Battalion           \*/
                 char fire_co_type;      /* Fire Company Type        \*/
                 char fire_co_nbr[3];    /* Fire Company Nbr         */
                 char seg_id[7];         /* Segment Identifier       */
                 char lo_hse_nbr[7];     /* Low House nbr in Display */
                 char hi_hse_nbr[7];     /* High House Nbr in Display*/
                 char a_lo_hse_nbr[7];   /* Alt. Lo Hse nbr in Disply*/
                 char a_hi_hse_nbr[7];   /* Alt.Hi Hse Nbr in Display*/
                 char cont_par;          /* Continuous Parity Ind    \*/
                 char face_code[4];      /* LION Face Code           \*/
                 char seq_nbr[5];        /* LION Sequence Nbr        \*/
                 char genr_flag;         /* Generated Record Flag    \*/
```

```
                    char seg_len[3];        /* Segment Length in Feet   \*/
                    char seg_azm[3];        /* Segment Azimuth          \*/
                    char seg_orient;        /* Segment Orientation      \*/
                    char instruc_div[2];    /* Instructional Division   \*/
                    char iaei;              /* Community Development    \*/
                                            /* Eligibility Indicator    \*/
                    char feature_type;      /* Feature Type Code        \*/
                    char police_boro_com;   /* Police Patrol Boro Com.  \*/
                    char police_pre[3];     /* Police Precinct          \*/
                    char com_schl_dist[2];  /* Community School District*/
                    char mh_ri_flag;        /* Marble Hill/Rikers Island*/
                                            /* Alternative Boro flag    \*/
                    char cen_tract_90[6];   /* 1990 Census Tract        \*/
                    char filler03[4];       /* Filler                   \*/
                    char dynam_blk[3];      /* Dynamic Block            \*/
                    char cen_blk_2000[4];   /* 2000 Census Block        \*/
                    char cen_blk_2000_sufx; /* 2000 Census Block Suffix \*/
                //  char filler06[5];
                  } C_WA2_F3C;

typedef struct { char lo_x_PB5SC[4];     /* Lowest PB5SC at Intersect*/
                    char lo2x_PB5SC[4];     /* 2nd Lowest PB5SC at Inter*/
                    char len[3];            /* Len in ft from prev node \*/
                    char gap_flag;          /* Gap Flag                 \*/
                  } CROSS_STRS;

typedef struct { char filler01[21];
                    char nbr_x_str[3];      /* Nbr of X sts in list     \*/
                    CROSS_STRS cross_strs[350];/* Cross Street structure*/
                  } C_WA2_F3S;
```

NATURAL LDAs (MSW)

GEOLW1 COPY File

```
                \*    USER PROGRAMS MUST RESET GEOLW1        BEFORE PRIMING WORKAREA 1
                   1 GEOLW1                                        /* LRECL=200
                \*    THE FIELD W1NAT IS USED AS A        PARAMETER TO CALL GEOSUPPORT
RT
                   2 W1NAT                            A          2
                R  2 W1NAT
                \*  * * * *   INPUT FIELDS    * * * *  *  * * * * * /* WORK AREA 1 FOR
                \*  *                                                /* ALL FUNCTIONS
                   3 GEO-WA1-IN-FUNCTION-CODE         A          2
```

```
                R  3 GEO-WA1-IN-FUNCTION-CODE
                   4 GEO-WA1-IN-FUNCTION-1            A          1
                   4 GEO-WA1-IN-FUNCTION-2            A          1
                   2 GEO-WA1-IN-BORO                  A          1
                   2 GEO-WA1-IN-HOUSENUM              A         12 /* FOR FCT 5, INPUT HIGH HSE
NUM
                   2 GEO-WA1-IN-HOUSENUM-INTERNAL     A          6 /* FOR FCT 5, INPUT HIGH HSE
NUM
                   2 GEO-WA1-IN-STREET-1              A         32
                   2 GEO-WA1-IN-STREET-2              A         32
                   2 GEO-WA1-IN-STREET-3              A         32
                   2 GEO-WA1-IN-COMPASS               A          1
                   2 GEO-WA1-IN-COMPASS2              A          1
                   2 GEO-WA1-IN-STREETCODE-1          P          6
                   2 GEO-WA1-IN-STREETCODE-2          P          6
                   2 GEO-WA1-IN-STREETCODE-3          P          6
                   2 GEO-WA1-IN-ROADBED-REQ-SWITCH-SF A          1
                   2 GEO-WA1-IN-BORO-2                A          1
                   2 GEO-WA1-IN-BORO-3                A          1
                   2 GEO-WA1-IN-SNL                   A          2
                   2 GEO-WA1-IN-10SC-1                A         11
                   2 GEO-WA1-IN-10SC-2                A         11
                   2 GEO-WA1-IN-10SC-3                A         11
                   2 GEO-WA1-IN-ZIPCODE               A          5
                   2 GEO-WA1-IN-BBL                   A         10
                R  2 GEO-WA1-IN-BBL
                   3 GEO-WA1-IN-BBL-BORO              A          1
                   3 GEO-WA1-IN-BLOCKNUM              A          5
                   3 GEO-WA1-IN-LOTNUM                A          4
                   2 FILLER-WA1-10                    A          1
                   2 GEO-WA1-IN-BIN                   A          7
                   2 GEO-WA1-IN-COMPACT-NAME-FLAG     A          1 /* TO REQUEST THE COMPACT
NAMES
                \*                                                  OPTION,
                \*                                                  MOVE 'C' TO THIS FIELD.
                \*
                   2 GEO-WA1-IN-LONG-WORKAREA2-FLAG   A          1 /* TO REQUEST THE LONG
WORKAREA
                \*                                                  OPTION,
                \*                                                  MOVE 'L' TO THIS FIELD.
                \*                                                  ONLY FCT 3 HAS THIS
OPTION.
                \*
                   2 GEO-WA1-IN-LOW-HOUSENUM          A         12
                   2 GEO-WA1-IN-LOW-HSENUM-INTERNAL   A          6
```

```
                 2 GEO-WA1-IN-NON-IBM-MAIN-FRAME    A          1 /* NOT IMPLEMENTED
               \*                                                FOR ANY APPLICATION
RUNNING
               \*                                                ON NON-IBM MAINFRAM,
               \*                                                MOVE 'X' TO THIS FIELD.
               \*
                 2 GEO-WA1-IN-1ABL-VERSION          A          1 /* FOR FCT 1A & BL, TO
REQUEST
               \*                                                THE STANDARD WA2 FORMAT,
SET
               \*                                                THIS FIELD TO 'S'. TO
REQUEST
               \*                                                THE LEGACY WA2 FORMAT,
SET
               \*                                                THIS FILED TO ' ' OR
'L'.
               \*
                 2 GEO-WA1-IN-XSTREET-FLAG          A          1
                 2 FILLER-WA1-100                   A          4
               \*  * * * *   OUTPUT FIELDS   * * * *  *
                 2 GEO-WA1-OUT-LOW-HOUSENUM         A         12
                 2 GEO-WA1-OUT-BORONAME             A          9
                 2 GEO-WA1-OUT-STREET-1             A         32
                 2 GEO-WA1-OUT-STREET-2             A         32
                 2 GEO-WA1-OUT-STREET-3             A         32
                 2 GEO-WA1-OUT-HOUSENUM             A         12 /* HI HND
                 2 GEO-WA1-OUT-HOUSENUM-INTERNAL    A          6
                 2 FILLER-WA1-200                   A          7
                 2 GEO-WA1-OUT-PB5SC-1              P          6 /* 4 BYTES
               R 2 GEO-WA1-OUT-PB5SC-1
                 3 GEO-WA1-OUT-PACKBORO-NOSIGN-1    N          1
                 3 GEO-WA1-OUT-STREETCODE-1-KEY     P          5 /* 3 BYTES
                 2 FILLER-WA1-210                   A          2
                 2 GEO-WA1-OUT-PB5SC-2              P          6 /* 4 BYTES
               R 2 GEO-WA1-OUT-PB5SC-2
                 3 GEO-WA1-OUT-PACKBORO-NOSIGN-2    N          1
                 3 GEO-WA1-OUT-STREETCODE-2-KEY     P          5 /* 3 BYTES
                 2 FILLER-WA1-220                   A          2
                 2 GEO-WA1-OUT-PB5SC-3              P          6 /* 4 BYTES
               R 2 GEO-WA1-OUT-PB5SC-3
                 3 GEO-WA1-OUT-PACKBORO-NOSIGN-3    N          1
                 3 GEO-WA1-OUT-STREETCODE-3-KEY     P          5 /* 3 BYTES
                 2 GEO-WA1-OUT-STREET-ATTR          A          1 (1:3) /* INTERNAL USE
                 2 GEO-WA1-BROWSE                   A         40
                 2 GEO-WA1-OUT-10SC-1               A         11
```

```
   2 GEO-WA1-OUT-10SC-2              A         11
   2 GEO-WA1-OUT-10SC-3              A         11
   2 GEO-WA1-OUT-CUI                 A          5 /* NOT IMPLEMENTED
   2 GEO-WA1-OUT-BBL                 A         10
R  2 GEO-WA1-OUT-BBL
   3 GEO-WA1-OUT-BBL-BORO            A          1
   3 GEO-WA1-OUT-BLOCKNUM            A          5
   3 GEO-WA1-OUT-LOTNUM              A          4
   2 FILLER-WA1-240                  A          1
   2 GEO-WA1-OUT-BIN                 A          7
   2 GEO-WA1-OUT-SND-ATTR            A          1 /* DCP/GSS USE
   2 GEO-WA1-OUT-REASON-CODE         A          1
   2 FILLER-WA1-400                  A          2 /* INTERNAL USE
   2 GEO-WA1-OUT-RETURN-CODE         A          2
R  2 GEO-WA1-OUT-RETURN-CODE
   3 GEO-WA1-OUT-RC-1                A          1
   3 GEO-WA1-OUT-RC-2                A          1
   2 GEO-WA1-OUT-ERROR-MESSAGE       A         80
   2 GEO-WA1-OUT-NUM-SIMILAR-NAMES   P          3
   2 GEO-WA1-OUT-SIMILAR-NAMES       A         32 (1:10)
```

GEOLW2 COPY File

```
   1 GEOLW2
*    THE FIELD W2NAT IS USED AS A        PARAMETER TO CALL GEOSUPPORT FOR ALLLL
*        FUNCTIONS THAT ARE REDEFINED           ON GEOLW2
   2 W2NAT                           A         21
R  2 W2NAT
*  *  BEGINNING OF FUNCTION 1 LAYOUT  *       **** *******
   3 GEO-WA2-FN1-ACCESS-KEY          A         21
   2 GEO-WA2-FN1-CONT-PARITY         A          1
   2 GEO-WA2-FN1-LOW-HOUSENUM-INT    A          6
R  2 GEO-WA2-FN1-LOW-HOUSENUM-INT
   3 GEO-WA2-FN1-LOW-HOUSENUM        A          5
   3 GEO-WA2-FN1-LOW-HOUSENUMSFX     A          1
   2 GEO-WA2-FN1-HI-HOUSENUM-INT     A          6
R  2 GEO-WA2-FN1-HI-HOUSENUM-INT
   3 GEO-WA2-FN1-HI-HOUSENUM         A          5
   3 GEO-WA2-FN1-HI-HOUSENUMSFX      A          1
   2 GEO-WA2-FN1-ALX                 A          1 /\*ALLEYS INTERSECT SEGMENT
   2 GEO-WA2-FN1-NUM-X-ST-LOW-END    N          1
   2 GEO-WA2-FN1-LOW-PBSC            P          6 (1:5) /* 4 BYTES X 5 = 20
   2 GEO-WA2-FN1-NUM-X-ST-HI-END     N          1
   2 GEO-WA2-FN1-HI-PBSC             P          6 (1:5)
   2 GEO-WA2-FN1-COMDIST             A          3
```

```
R  2 GEO-WA2-FN1-COMDIST
   3 GEO-WA2-FN1-COMDIST-BORO         A          1
   3 GEO-WA2-FN1-COMDIST-NUM          A          2
   2 GEO-WA2-FN1-ZIP                  A          5
   2 GEO-WA2-FN1-SLA                  A          1
   2 GEO-WA2-FN1-HCD                  A          2
   2 GEO-WA2-FN1-SOS                  A          1
   2 GEO-WA2-FN1-CONT-PARITY-IND      A          1
   2 GEO-WA2-FN1-2010-CENSUSTRACT     A          6
   2 GEO-WA2-FN1-2010-CENSUSBLOCK     A          4
   2 GEO-WA2-FN1-2010-CENSUSBLKSFX    A          1
   2 GEO-WA2-FN1-FILLER_INDV          A          1
   2 FILLER-WA2-260                   A          2
   2 GEO-WA2-FN1-HEALTHAREA           A          4
   2 GEO-WA2-FN1-SANI-REC             A          3
   2 GEO-WA1-FN1-FEATURE-TYPE         A          1
   2 GEO-WA2-FN1-RESDCP               A          1 /* RESERVED FOR DCP/GSS USE
   2 GEO-WA2-FN1-CURVE-FLAG           A          1
   2 GEO-WA2-FN1-POLICEDIST           A          4
R  2 GEO-WA2-FN1-POLICEDIST
   3 GEO-WA2-FN1-POL-PATR-BORO-CMD    A          1
   3 GEO-WA2-FN1-POL-PRECINCT         A          3
   2 GEO-WA2-FN1-SCHOOLDIST           A          2
   2 FILLER-WA2-250                   A         15
   2 GEO-WA2-FN1-SEGMENT-TYPE         A          1
   2 GEO-WA2-FN1-SANIDIST             A          3
R  2 GEO-WA2-FN1-SANIDIST
   3 GEO-WA2-FN1-SANIDIST-BORO        A          1
   3 GEO-WA2-FN1-SANIDIST-NUM         A          2
   2 GEO-WA2-FN1-SANITATION-SUBSEC    A          2
   2 GEO-WA2-FN1-FIRESEC              A          2 /* FIRE DIVISION
   2 GEO-WA2-FN1-FIREBAT              A          2
   2 GEO-WA2-FN1-FIRECO               A          4
R  2 GEO-WA2-FN1-FIRECO
   3 GEO-WA2-FN1-FIRECO-TYPE          A          1
   3 GEO-WA2-FN1-FIRECO-NUM           A          3
   2 GEO-WA2-FN1-SPECIAL-ADDR-FLAG    A          1
   2 GEO-WA2-FN1-MARBLE-RIKERS-FLAG   A          1
   2 GEO-WA2-FN1-SPLIT-SCHOOL-FLAG    A          1
   2 GEO-WA2-FN1-PREFERRED-LGC        A          2
   2 GEO-WA2-FN1-LIONFACECODE         A          4
   2 GEO-WA2-FN1-LIONSEQ              A          5
   2 GEO-WA2-FN1-1990-CENSUSTRACT     A          6
   2 FILLER-WA2-260B                  A          4
   2 GEO-WA2-FN1-DYN-BLOCK            A          3
```

```
                 2 GEO-WA2-FN1-XCOORD              A          7
                 2 GEO-WA2-FN1-YCOORD              A          7
                 2 GEO-WA2-FN1-SEGMENTLENGTH       A          5
                 2 GEO-WA2-FN1-SANI-REG            A          5
               *  *  END OF FUNCTION 1 LAYOUT      *       **** *******
               *  - ------------------------------ -       ---- ---------------------------
               *  *  BEGINNING OF FUNCTION 2 LAYOUT  *       **** *******
               R  1 GEOLW2
                 2 GEO-WA2-FN2-ACCESS-KEY          A         21 /\*FCT 2,2C SHARE SAME WA2
LAYO
                 2 GEO-WA2-FN2-DUPINTERFLAG        A          1 /*
                 2 FILLER-WA2-270                  A          9
                 2 GEO-WA2-FN2-PREFERRED-LGC1      A          2
                 2 GEO-WA2-FN2-PREFERRED-LGC2      A          2
                 2 GEO-WA2-FN2-NUM-OF-INTERSECTS   N          1
                 2 GEO-WA2-FN2-INTERSECT-PBSC      P          6 (1:5)
                 2 GEO-WA2-FN2-COMPDIR             A          1
                 2 GEO-WA2-FN2-LEVEL-CODES-TBL     A         10
               R  2 GEO-WA2-FN2-LEVEL-CODES-TBL
                 3 GEO-WA2-FN2-LEVEL-CODES         A          1 (5,2)
                 2 GEO-WA2-FN2-INSTRUCT-REG        A          2
                 2 GEO-WA2-FN2-FIRESEC             A          2
                 2 GEO-WA2-FN2-FIREBAT             A          2
                 2 GEO-WA2-FN2-FIRECO              A          4
               R  2 GEO-WA2-FN2-FIRECO
                 3 GEO-WA2-FN2-FIRECO-TYPE         A          1
                 3 GEO-WA2-FN2-FIRECO-NUM          A          3
                 2 GEO-WA2-FN2-COMDIST             A          3
               R  2 GEO-WA2-FN2-COMDIST
                 3 GEO-WA2-FN2-COMDIST-BORO        A          1
                 3 GEO-WA2-FN2-COMDIST-NUM         A          2
                 2 GEO-WA2-FN2-ZIP                 A          5
                 2 GEO-WA2-FN2-SLA                 A          1
                 2 GEO-WA2-FN2-2010-CENSUSTRACT    A          6
                 2 FILLER-WA2-290                  A          3
                 2 GEO-WA2-FN2-HEALTHAREA          A          4
                 2 FILLER-WA2-300                  A          9
                 2 GEO-WA2-FN2-LIONNODENUM         A          7
                 2 GEO-WA2-FN2-XCOORD              A          7
                 2 GEO-WA2-FN2-YCOORD              A          7
                 2 FILLER-WA2-320                  A          4
                 2 GEO-WA2-FN2-POLICEDIST          A          4
               R  2 GEO-WA2-FN2-POLICEDIST
                 3 GEO-WA2-FN2-POL-PATR-BORO-CMD   A          1
                 3 GEO-WA2-FN2-POL-PRECINCT        A          3
```

```
                 2 GEO-WA2-FN2-SCHOOLDIST           A          2
                 2 GEO-WA2-FN2-MARBLE-RIKERS-FLAG   A          1
                 2 GEO-WA2-FN2-1990-CENSUSTRACT     A          6
                 2 GEO-WA2-FN2-SANBORN1-BVOLPAGE    A          8
               R 2 GEO-WA2-FN2-SANBORN1-BVOLPAGE
                 3 GEO-WA2-FN2-SANBORN1-BORO        A          1
                 3 GEO-WA2-FN2-SANBORN1-VOLPAGE     A          7
               R 3 GEO-WA2-FN2-SANBORN1-VOLPAGE
                 4 GEO-WA2-FN2-SANBORN1-VOL-NUM     A          3
                 4 GEO-WA2-FN2-SANBORN1-PAGE-NUM    A          4
                 2 GEO-WA2-FN2-SANBORN2-BVOLPAGE    A          8
               R 2 GEO-WA2-FN2-SANBORN2-BVOLPAGE
                 3 GEO-WA2-FN2-SANBORN2-BORO        A          1
                 3 GEO-WA2-FN2-SANBORN2-VOLPAGE     A          7
               R 3 GEO-WA2-FN2-SANBORN2-VOLPAGE
                 4 GEO-WA2-FN2-SANBORN2-VOL-NUM     A          3
                 4 GEO-WA2-FN2-SANBORN2-PAGE-NUM    A          4
                 2 GEO-WA2-FN2-DUP-INTRSCT-DISTNCE  A          5
                 2 GEO-WA2-FN2-2000-CENSUSTRACT     A          6
                 2 FILLER-WA2-330                   A         27
               *  *  END OF FUNCTION 2 LAYOUT       *       **** *******
               *  - ------------------------------- -       ---- ----------------------------
--
               *  *  BEGINNING OF FUNCTION 3 LAYOUT *       **** *******
               R  1 GEOLW2
                 2 GEO-WA2-FN3-ACCESS-KEY           A         21
                 2 GEO-WA2-FN3-DUP-KEY-FLAG         A          1 /* OR FN3 CONTI PARITY
                 2 GEO-WA2-FN3-CURVE-FLAG           A          1
                 2 GEO-WA2-FN3-LOCATION-STATUS      A          1
                 2 GEO-WA2-FN3-COUNTY-BOUNDARY      A          1
                 2 FILLER-WA2-340                   A          4
                 2 GEO-WA2-FN3-PREFERRED-LGC1       A          2
                 2 GEO-WA2-FN3-PREFERRED-LGC2       A          2
                 2 GEO-WA2-FN3-PREFERRED-LGC3       A          2
                 2 GEO-WA2-FN3-NUM-X-ST-LOW-END     N          1
                 2 GEO-WA2-FN3-LOW-PBSC             P          6 (1:5)
                 2 GEO-WA2-FN3-NUM-X-ST-HI-END      N          1
                 2 GEO-WA2-FN3-HI-PBSC              P          6 (1:5)
                 2 GEO-WA2-FN3-SLA                  A          1
                 2 GEO-WA2-FN3-REVERSALFLAG         A          1
                 2 GEO-WA2-FN3-LEFT-COMDIST         A          3
               R 2 GEO-WA2-FN3-LEFT-COMDIST
                 3 GEO-WA2-FN3-LEFT-COMDIST-BORO    A          1
                 3 GEO-WA2-FN3-LEFT-COMDIST-NUM     A          2
                 2 GEO-WA2-FN3-RIGHT-COMDIST        A          3
```

```
R  2 GEO-WA2-FN3-RIGHT-COMDIST
   3 GEO-WA2-FN3-RIGHT-COMDIST-BORO   A          1
   3 GEO-WA2-FN3-RIGHT-COMDIST-NUM    A          2
   2 GEO-WA2-FN3-LEFT-ZIP             A          5
   2 GEO-WA2-FN3-RIGHT-ZIP            A          5
   2 FILLER-WA2-350A                  A         18
   2 GEO-WA2-FN3-LEFT-HEALTHAREA      A          4
   2 GEO-WA2-FN3-RIGHT-HEALTHAREA     A          4
   2 GEO-WA2-FN3-LEFT-INSTRUCT-REG    A          2
   2 GEO-WA2-FN3-RIGHT-INSTRUCT-REG   A          2
   2 GEO-WA2-FN3-LEFT-LOW-HOUSENUM    A          7
   2 GEO-WA2-FN3-LEFT-HI-HOUSENUM     A          7
   2 GEO-WA2-FN3-RIGHT-LOW-HOUSENUM   A          7
   2 GEO-WA2-FN3-RIGHT-HI-HOUSENUM    A          7
   2 GEO-WA2-FN3-CONT-PARITY-IND      A          1
   2 GEO-WA2-FN3-LIONFACECODE         A          4
   2 GEO-WA2-FN3-LIONSEQ              A          5
   2 GEO-WA2-FN3-GENRECFLAG           A          1
   2 GEO-WA2-FN3-SEGMENTLENGTH        P          5
   2 GEO-WA2-FN3-SEGMENTSLOPE         A          3
   2 GEO-WA2-FN3-SEGMENTORIENT        A          1
   2 FILLER-WA2-355                   A          4
   2 GEO-WA2-FN3-RESSDCP              A          2 /* RESERVED FOR DCP/GSS USE
   2 GEO-WA2-FN3-DOG-LEG              A          1
   2 GEO-WA2-FN3-FEATURE-TYPE         A          1
   2 GEO-WA2-FN3-LEFT-POLICEDIST      A          4
R  2 GEO-WA2-FN3-LEFT-POLICEDIST
   3 GEO-WA2-FN3-L-POL-PATR-BORO-CMD  A          1
   3 GEO-WA2-FN3-LEFT-POL-PRECINCT    A          3
   2 GEO-WA2-FN3-RIGHT-POLICEDIST     A          4
R  2 GEO-WA2-FN3-RIGHT-POLICEDIST
   3 GEO-WA2-FN3-R-POL-PATR-BORO-CMD  A          1
   3 GEO-WA2-FN3-RIGHT-POL-PRECINCT   A          3
   2 GEO-WA2-FN3-LEFT-SCHOOLDIST      A          2
   2 GEO-WA2-FN3-RIGHT-SCHOOLDIST     A          2
   2 GEO-WA2-FN3-MARBLE-RIKERS-FLAG   A          1
   2 GEO-WA2-FN3-SEGMENT-ID           A          7
   2 GEO-WA2-FN3-SEGMENT-TYPE         A          1
*  *  END OF FUNCTION 3 LAYOUT                 **** ********
*  - ------------------------------- -         ---- ----------------------------
--
*  *  BEGINNING OF FUNCTION 3C LAYOUT          **** ********
R  1 GEOLW2
   2 GEO-WA2-FN3C-ACCESS-KEY          A         21
   2 GEO-WA2-FN3C-CURVE-FLAG          A          1
```

```
                 2 GEO-WA2-FN3C-SEGMENT-TYPE        A          1
                 2 GEO-WA2-FN3C-LOCATION-STATUS     A          1
                 2 GEO-WA2-FN3C-COUNTY-BOUNDARY     A          1
                 2 FILLER-WA2-380                   A          4
                 2 GEO-WA2-FN3C-PREFERRED-LGC1      A          2
                 2 GEO-WA2-FN3C-PREFERRED-LGC2      A          2
                 2 GEO-WA2-FN3C-PREFERRED-LGC3      A          2
                 2 GEO-WA2-FN3C-NUM-X-ST-LOW-END    N          1
                 2 GEO-WA2-FN3C-LOW-PBSC            P          6 (1:5)
                 2 GEO-WA2-FN3C-NUM-X-ST-HI-END     N          1
                 2 GEO-WA2-FN3C-HI-PBSC             P          6 (1:5)
                 2 GEO-WA2-FN3C-COMDIST             A          3
               R 2 GEO-WA2-FN3C-COMDIST
                 3 GEO-WA2-FN3C-COMDIST-BORO        A          1
                 3 GEO-WA2-FN3C-COMDIST-NUM         A          2
                 2 GEO-WA2-FN3C-ZIP                 A          5
                 2 GEO-WA2-FN3C-SLA                 A          1
                 2 GEO-WA2-FN3C-2000-CENSUSTRACT    A          6
                 2 FILLER-WA2-390                   A          1
                 2 GEO-WA2-FN3C-2010-CENSUSTRACT    A          6
                 2 GEO-WA2-FN3C-2010-CENSUSBLOCK    A          4
                 2 GEO-WA2-FN3C-2010-CENSUSBLKSFX   A          1 /* NOT IMPLEMENTED \*/
                 2 GEO-WA2-FN3C-HEALTHAREA          A          4
                 2 GEO-WA2-FN3C-REVERSALFLAG        A          1
                 2 GEO-WA2-FN3C-SOS                 A          1
                 2 GEO-WA2-FN3C-FIRESEC             A          2
                 2 GEO-WA2-FN3C-FIREBAT             A          2
                 2 GEO-WA2-FN3C-FIRECO              A          4
               R 2 GEO-WA2-FN3C-FIRECO
                 3 GEO-WA2-FN3C-FIRECO-TYPE         A          1
                 3 GEO-WA2-FN3C-FIRECO-NUM          A          3
                 2 GEO-WA2-FN3C-SEGMENT-ID          A          7
                 2 GEO-WA2-FN3C-LOW-HOUSENUM        A          7
                 2 GEO-WA2-FN3C-HI-HOUSENUM         A          7
                 2 GEO-WA2-FN3C-LOW-HOUSENUM2       A          7 /* HOUSENUM2 ONLY PRESENT IF
                 2 GEO-WA2-FN3C-HI-HOUSENUM2        A          7 /* ODD & EVEN ARE ON SAME
SIDE
                 2 GEO-WA2-FN3C-CONT-PARITY-IND     A          1
                 2 GEO-WA2-FN3C-LIONFACECODE        A          4
                 2 GEO-WA2-FN3C-LIONSEQ             A          5
                 2 GEO-WA2-FN3C-GENRECFLAG          A          1
                 2 GEO-WA2-FN3C-SEGMENTLENGTH       P          5
                 2 GEO-WA2-FN3C-SEGMENTSLOPE        A          3
                 2 GEO-WA2-FN3C-SEGMENTORIENT       A          1
                 2 FILLER-WA2-408                   A          2
```

```
   2 GEO-WA2-FN3C-RESDCP              A          1 /* RESERVED FOR DCP/GSS USE
   2 GEO-WA2-FN3C-FEATURE-TYPE        A          1
   2 GEO-WA2-FN3C-POLICEDIST          A          4
R  2 GEO-WA2-FN3C-POLICEDIST
   3 GEO-WA2-FN3C-POL-PATR-BORO-CMD   A          1
   3 GEO-WA2-FN3C-POL-PRECINCT        A          3
   2 GEO-WA2-FN3C-SCHOOLDIST          A          2
   2 GEO-WA2-FN3C-MARBLE-RIKERS-FLAG  A          1
   2 GEO-WA2-FN3C-1990-CENSUSTRACT    A          6
   2 FILLER-WA2-410B                  A          4
   2 GEO-WA2-FN3C-DYN-BLOCK           A          3
   2 GEO-WA2-FN3C-2000-CENSUSBLOCK    A          4
   2 GEO-WA2-FN3C-2000-CENSUSBLKSFX   A          1
\*  *  END OF FUNCTION 3C LAYOUT       *       **** *******
\*  - ------------------------------- -       ---- ---------------------------
---
\*  *  BEGINNING OF FUNCTION 1E LAYOUT *       **** *******
R  1 GEOLW2
   2 GEO-WA2-FN1E-ACCESS-KEY          A         21
   2 GEO-WA2-FN1E-CONT-PARITY         A          1
   2 GEO-WA2-FN1E-LOW-HOUSENUM-INT    A          6
R  2 GEO-WA2-FN1E-LOW-HOUSENUM-INT
   3 GEO-WA2-FN1E-LOW-HOUSENUM        A          5
   3 GEO-WA2-FN1E-LOW-HOUSENUMSFX     A          1 /* NOT IMPLEMENTED
   2 GEO-WA2-FN1E-HI-HOUSENUM-INT     A          6
R  2 GEO-WA2-FN1E-HI-HOUSENUM-INT
   3 GEO-WA2-FN1E-HI-HOUSENUM         A          5
   3 GEO-WA2-FN1E-HI-HOUSENUMSFX      A          1 /* NOT IMPLEMENTED
   2 FILLER-WA2-435                   A          1
   2 GEO-WA2-FN1E-NUM-X-ST-LOW-END    N          1
   2 GEO-WA2-FN1E-LOW-PBSC            P          6 (1:5)
   2 GEO-WA2-FN1E-NUM-X-ST-HI-END     N          1
   2 GEO-WA2-FN1E-HI-PBSC             P          6 (1:5)
   2 GEO-WA2-FN1E-COMDIST             A          3
R  2 GEO-WA2-FN1E-COMDIST
   3 GEO-WA2-FN1E-COMDIST-BORO        A          1
   3 GEO-WA2-FN1E-COMDIST-NUM         A          2
   2 GEO-WA2-FN1E-ZIP                 A          5
   2 GEO-WA2-FN1E-SLA                 A          1
   2 GEO-WA2-FN1E-HCD                 A          2
   2 GEO-WA2-FN1E-SOS                 A          1
   2 GEO-WA2-FN1E-CONT-PARITY-IND     A          1
   2 GEO-WA2-FN1E-2010-CENSUSTRACT    A          6
   2 GEO-WA2-FN1E-2010-CENSUSBLOCK    A          4
   2 GEO-WA2-FN1E-2010-CENSUSBLKSFX   A          1
```

```
   2 FILLER-WA2-FN1E-FILLER-INDV      A          1
   2 FILLER-WA2-440                   A          2
   2 GEO-WA2-FN1E-HEALTHAREA          A          4
   2 GEO-WA2-FN1E-SANI-REC            A          3
   2 GEO-WA2-FN1E-FEATURE-TYPE        A          1
   2 GEO-WA2-FN1E-RESDCP              A          1 /* RESERVED FOR DCP/GSS USE
   2 GEO-WA2-FN1E-CURVE-FLAG          A          1
   2 GEO-WA2-FN1E-POLICEDIST          A          4
R  2 GEO-WA2-FN1E-POLICEDIST
   3 GEO-WA2-FN1E-POL-PATR-BORO-CMD   A          1
   3 GEO-WA2-FN1E-POL-PRECINCT        A          3
   2 GEO-WA2-FN1E-SCHOOLDIST          A          2
   2 GEO-WA2-FN1E-ELECTDIST           A          3
   2 GEO-WA2-FN1E-ASSEMDIST           A          2
   2 GEO-WA2-FN1E-SPLIT-ED-FLAG       A          1
   2 GEO-WA2-FN1E-CONGDIST            A          2
   2 GEO-WA2-FN1E-SENATEDIST          A          2
   2 GEO-WA2-FN1E-COURTDIST           A          2
   2 GEO-WA2-FN1E-COUNCILDIST         A          2
   2 FILLER-WA2-470                   A          2
   2 GEO-WA2-FN1E-SANIDIST            A          3
R  2 GEO-WA2-FN1E-SANIDIST
   3 GEO-WA2-FN1E-SANIDIST-BORO       A          1
   3 GEO-WA2-FN1E-SANIDIST-NUM        A          2
   2 GEO-WA2-FN1E-SANITATION-SUBSEC   A          2
   2 GEO-WA2-FN1E-FIRESEC             A          2
   2 GEO-WA2-FN1E-FIREBAT             A          2
   2 GEO-WA2-FN1E-FIRECO              A          4
R  2 GEO-WA2-FN1E-FIRECO
   3 GEO-WA2-FN1E-FIRECO-TYPE         A          1
   3 GEO-WA2-FN1E-FIRECO-NUM          A          3
   2 GEO-WA2-FN1E-SPECIAL-ADDR-FLAG   A          1
   2 GEO-WA2-FN1E-MARBLE-RIKERS-FLAG  A          1
   2 GEO-WA2-FN1E-SPLIT-SCHOOL-FLAG   A          1
   2 GEO-WA2-FN1E-PREFERRED-LGC       A          2
   2 GEO-WA2-FN1E-LIONFACECODE        A          4
   2 GEO-WA2-FN1E-LIONSEQ             A          5
   2 GEO-WA2-FN1E-1990-CENSUSTRACT    A          6
   2 FILLER-WA2-480B                  A          4
   2 GEO-WA2-FN1E-DYN-BLOCK           A          3
   2 GEO-WA2-FN1E-XCOORD              A          7
   2 GEO-WA2-FN1E-YCOORD              A          7
   2 GEO-WA2-FN1E-SEGMENTLENGTH       A          5
   2 GEO-WA2-FN1E-SANI-REG            A          5
\*  *  END OF FUNCTION 1E LAYOUT       *       **** *******
```

```
\*  - ------------------------------- -       ---- ---------------------------
---
\*  *  BEGINNING OF FUNCTION 5 LAYOUT  *       **** *******
R  1 GEOLW2
   2 GEO-WA2-FN5-ADDR-MATCHING-KEY    A         28
   2 FILLER-WA2-490                   A        172
\*  *  END OF FUNCTION 5 LAYOUT        *       **** *******
\*  - ------------------------------- -       ---- ---------------------------
---
```

GEOLW2L COPY File

```
1 GEOLW2L
\*  * THE FIELD W2NATL IS USED AS A       PARAMETER TO CALL GEOSUPPORT
2 W2NATL                            A         21
R  2 W2NATL
\*  * BEGINNING OF FUNCTION 1                  LONG  WORKAREA LAYOUT ******
3 GEO-WA2-1L-ACCESS-KEY             A         21
2 GEO-WA2-1L-CONT-PARITY            A          1
2 GEO-WA2-1L-LOW-HOUSENUM-INT       A          6
R  2 GEO-WA2-1L-LOW-HOUSENUM-INT
3 GEO-WA2-1L-LOW-HOUSENUM           A          5
3 GEO-WA2-1L-LOW-HOUSENUMSFX        A          1
2 GEO-WA2-1L-HI-HOUSENUM-INT        A          6
R  2 GEO-WA2-1L-HI-HOUSENUM-INT
3 GEO-WA2-1L-HI-HOUSENUM            A          5
3 GEO-WA2-1L-HI-HOUSENUMSFX         A          1
2 FILLER-WA2-215                    A          1
2 GEO-WA2-1L-NUM-X-ST-LOW-END       N          1
2 GEO-WA2-1L-LOW-PBSC               P          6 (1:5)
2 GEO-WA2-1L-NUM-X-ST-HI-END        N          1
2 GEO-WA2-1L-HI-PBSC                P          6 (1:5)
2 GEO-WA2-1L-COMDIST                A          3
R  2 GEO-WA2-1L-COMDIST
3 GEO-WA2-1L-COMDIST-BORO           A          1
3 GEO-WA2-1L-COMDIST-NUM            A          2
2 GEO-WA2-1L-ZIP                    A          5
2 GEO-WA2-1L-SLA                    A          1
2 GEO-WA2-1L-HCD                    A          2
2 GEO-WA2-1L-SOS                    A          1
2 GEO-WA2-1L-CONT-PARITY-IND        A          1
2 GEO-WA2-1L-2010-CENSUSTRACT       A          6
2 GEO-WA2-1L-2010-CENSUSBLOCK       A          4
2 GEO-WA2-1L-2010-CENSUSBLKSFX      A          1
2 FILLER-1L-INDV                    A          1
```

```
2 FILLER-1L-260                    A          2
2 GEO-WA2-1L-HEALTHAREA            A          4
2 GEO-WA2-1L-SANI-REC              A          3
2 GEO-WA2-1L-FEATURE-TYPE          A          1
2 GEO-WA2-1L-RESDCP                A          1 /* RESERVED FOR DCP/GSS USE
2 GEO-WA2-1L-CURVE-FLAG            A          1
2 GEO-WA2-1L-POLICEDIST            A          4
R  2 GEO-WA2-1L-POLICEDIST
3 GEO-WA2-1L-POL-PATR-BORO-CMD     A          1
3 GEO-WA2-1L-POL-PRECINCT          A          3
2 GEO-WA2-1L-SCHOOLDIST            A          2
2 FILLER-WA2-250                   A         16 /* 1E POL DIST
2 GEO-WA2-1L-SANIDIST              A          3
R  2 GEO-WA2-1L-SANIDIST
3 GEO-WA2-1L-SANIDIST-BORO         A          1
3 GEO-WA2-1L-SANIDIST-NUM          A          2
2 GEO-WA2-1L-SANITATION-SUBSEC     A          2
2 GEO-WA2-1L-FIRESEC               A          2 /* FIRE DIVISION
2 GEO-WA2-1L-FIREBAT               A          2
2 GEO-WA2-1L-FIRECO                A          4
R  2 GEO-WA2-1L-FIRECO
3 GEO-WA2-1L-FIRECO-TYPE           A          1
3 GEO-WA2-1L-FIRECO-NUM            A          3
2 GEO-WA2-1L-SPECIAL-ADDR-FLAG     A          1
2 GEO-WA2-1L-MARBLE-RIKERS-FLAG    A          1
2 GEO-WA2-1L-SPLIT-SCHOOL-FLAG     A          1
2 GEO-WA2-1L-PREFERRED-LGC         A          2
2 GEO-WA2-1L-LIONFACECODE          A          4
2 GEO-WA2-1L-LIONSEQ               A          5
2 GEO-WA2-1L-1990-CENSUSTRACT      A          6
2 FILLER-WA2-260B                  A          4
2 GEO-WA2-1L-DYN-BLOCK             A          3
2 GEO-WA2-1L-XCOORD                A          7
2 GEO-WA2-1L-YCOORD                A          7
2 GEO-WA2-1L-SEGMENTLENGTH         A          5
2 GEO-WA2-1L-SANI-REG              A          5
2 GEO-WA2-1L-SEGMENT-ID            A          7
2 GEO-WA2-1L-TRUE-B7SC             A          8
2 GEO-WA2-1L-UNDERLY-HOUSENUM-INT  A          6
R  2 GEO-WA2-1L-UNDERLY-HOUSENUM-INT
3 GEO-WA2-1L-UNDERLY-HOUSENUM      A          5
3 GEO-WA2-1L-UNDERLY-HOUSENUMSFX   A          1
2 GEO-WA2-1L-2000-CENSUSTRACT      A          6
2 GEO-WA2-1L-2000-CENSUSBLOCK      A          4
2 GEO-WA2-1L-2000-CENSUSBLKSFX     A          1
```

```
2 FILLER-WA2-260C                 A         68
\*  * END OF FUNCTION 1                       LONG  WORKAREA LAYOUT ******
\*  - ------------------------------- -       ---- ---------------------------
-
\*  * BEGINNING OF FUNCTION 1E                LONG  WORKAREA LAYOUT ******
R  1 GEOLW2L
2 GEO-WA2-1EL-ACCESS-KEY          A         21
2 GEO-WA2-1EL-CONT-PARITY         A          1
2 GEO-WA2-1EL-LOW-HOUSENUM-INT    A          6
R  2 GEO-WA2-1EL-LOW-HOUSENUM-INT
3 GEO-WA2-1EL-LOW-HOUSENUM        A          5
3 GEO-WA2-1EL-LOW-HOUSENUMSFX     A          1 /* NOT IMPLEMENTED
2 GEO-WA2-1EL-HI-HOUSENUM-INT     A          6
R  2 GEO-WA2-1EL-HI-HOUSENUM-INT
3 GEO-WA2-1EL-HI-HOUSENUM         A          5
3 GEO-WA2-1EL-HI-HOUSENUMSFX      A          1 /* NOT IMPLEMENTED
2 FILLER-WA2-435                  A          1
2 GEO-WA2-1EL-NUM-X-ST-LOW-END    N          1
2 GEO-WA2-1EL-LOW-PBSC            P          6 (1:5)
2 GEO-WA2-1EL-NUM-X-ST-HI-END     N          1
2 GEO-WA2-1EL-HI-PBSC             P          6 (1:5)
2 GEO-WA2-1EL-COMDIST             A          3
R  2 GEO-WA2-1EL-COMDIST
3 GEO-WA2-1EL-COMDIST-BORO        A          1
3 GEO-WA2-1EL-COMDIST-NUM         A          2
2 GEO-WA2-1EL-ZIP                 A          5
2 GEO-WA2-1EL-SLA                 A          1
2 GEO-WA2-1EL-HCD                 A          2
2 GEO-WA2-1EL-SOS                 A          1
2 GEO-WA2-1EL-CONT-PARITY-IND     A          1
2 GEO-WA2-1EL-2010-CENSUSTRACT    A          6
2 GEO-WA2-1EL-2010-CENSUSBLOCK    A          4
2 GEO-WA2-1EL-2010-CENSUSBLKSFX   A          1
2 FILLER-WA2-1EL-INDV             A          1
2 FILLER-WA2-440C                 A          2
2 GEO-WA2-1EL-HEALTHAREA          A          4
2 GEO-WA2-1EL-SANI-REC            A          3
2 GEO-WA2-1EL-FEATURE-TYPE        A          1
2 GEO-WA2-1EL-RESDCP              A          1 /* RESERVED FOR DCP/GSS USE
2 GEO-WA2-1EL-CURVE-FLAG          A          1
2 GEO-WA2-1EL-POLICEDIST          A          4
R  2 GEO-WA2-1EL-POLICEDIST
3 GEO-WA2-1EL-POL-PATR-BORO-CMD   A          1
3 GEO-WA2-1EL-POL-PRECINCT        A          3
2 GEO-WA2-1EL-SCHOOLDIST          A          2
```

```
2 GEO-WA2-1EL-ELECTDIST            A          3
2 GEO-WA2-1EL-ASSEMDIST            A          2
2 GEO-WA2-1EL-SPLIT-ED-FLAG        A          1
2 GEO-WA2-1EL-CONGDIST             A          2
2 GEO-WA2-1EL-SENATEDIST           A          2
2 GEO-WA2-1EL-COURTDIST            A          2
2 GEO-WA2-1EL-COUNCILDIST          A          2
2 FILLER-WA2-470                   A          2
2 GEO-WA2-1EL-SANIDIST             A          3
R  2 GEO-WA2-1EL-SANIDIST
3 GEO-WA2-1EL-SANIDIST-BORO        A          1
3 GEO-WA2-1EL-SANIDIST-NUM         A          2
2 GEO-WA2-1EL-SANITATION-SUBSEC    A          2
2 GEO-WA2-1EL-FIRESEC              A          2
2 GEO-WA2-1EL-FIREBAT              A          2
2 GEO-WA2-1EL-FIRECO               A          4
R  2 GEO-WA2-1EL-FIRECO
3 GEO-WA2-1EL-FIRECO-TYPE          A          1
3 GEO-WA2-1EL-FIRECO-NUM           A          3
2 GEO-WA2-1EL-SPECIAL-ADDR-FLAG    A          1
2 GEO-WA2-1EL-MARBLE-RIKERS-FLAG   A          1
2 GEO-WA2-1EL-SPLIT-SCHOOL-FLAG    A          1
2 GEO-WA2-1EL-PREFERRED-LGC        A          2
2 GEO-WA2-1EL-LIONFACECODE         A          4
2 GEO-WA2-1EL-LIONSEQ              A          5
2 GEO-WA2-1EL-1990-CENSUSTRACT     A          6
2 FILLER-WA2L-480B                 A          4
2 GEO-WA2-1EL-DYN-BLOCK            A          3
2 GEO-WA2-1EL-XCOORD               A          7
2 GEO-WA2-1EL-YCOORD               A          7
2 GEO-WA2-1EL-SEGMENTLENGTH        A          5
2 GEO-WA2-1EL-SANI-REG             A          5
2 GEO-WA2-1EL-SEGMENT-ID           A          7
2 GEO-WA2-1EL-TRUE-B7SC            A          8
2 GEO-WA2-1EL-UNDER-HOUSENUM-INT   A          6
2 GEO-WA2-1EL-2000-CENSUSTRACT     A          6
2 GEO-WA2-1EL-2000-CENSUSBLOCK     A          4
2 GEO-WA2-1EL-2000-CENSUSBLKSFX    A          1
2 FILLER-WA2-480                   A         68
\*  * END OF FUNCTION 1E                      LONG WORKAREA LAYOUT ******
\*  - ------------------------------- -       ---- ---------------------------
-
\*  * BEGINNING OF FUNCTION 3                 LONG WORKAREA LAYOUT ******
R  1 GEOLW2L
2 GEO-WA2-3L-ACCESS-KEY            A         21
```

```
2 GEO-WA2-3L-DUP-KEY-FLAG          A          1 /* NOT IMPLEMENTED
2 GEO-WA2-3L-CURVE-FLAG            A          1
2 GEO-WA2-3L-LOCATION-STATUS       A          1
2 GEO-WA2-3L-COUNTY-BOUNDARY       A          1
2 FILLER-WA2-340                   A          4
2 GEO-WA2-3L-PREFERRED-LGC1        A          2
2 GEO-WA2-3L-PREFERRED-LGC2        A          2
2 GEO-WA2-3L-PREFERRED-LGC3        A          2
2 GEO-WA2-3L-NUM-X-ST-LOW-END      N          1
2 GEO-WA2-3L-LOW-PBSC              P          6 (1:5)
2 GEO-WA2-3L-NUM-X-ST-HI-END       N          1
2 GEO-WA2-3L-HI-PBSC               P          6 (1:5)
2 GEO-WA2-3L-SLA                   A          1
2 GEO-WA2-3L-REVERSALFLAG          A          1
2 GEO-WA2-3L-LEFT-COMDIST          A          3
R  2 GEO-WA2-3L-LEFT-COMDIST
3 GEO-WA2-3L-LEFT-COMDIST-BORO     A          1
3 GEO-WA2-3L-LEFT-COMDIST-NUM      A          2
2 GEO-WA2-3L-RIGHT-COMDIST         A          3
R  2 GEO-WA2-3L-RIGHT-COMDIST
3 GEO-WA2-3L-RIGHT-COMDIST-BORO    A          1
3 GEO-WA2-3L-RIGHT-COMDIST-NUM     A          2
2 GEO-WA2-3L-LEFT-ZIP              A          5
2 GEO-WA2-3L-RIGHT-ZIP             A          5
2 FILLER-WA2-340B                  A         18
2 GEO-WA2-3L-LEFT-HEALTHAREA       A          4
2 GEO-WA2-3L-RIGHT-HEALTHAREA      A          4
2 GEO-WA2-3L-LEFT-INSTRUCT-REG     A          2
2 GEO-WA2-3L-RIGHT-INSTRUCT-REG    A          2
2 GEO-WA2-3L-LEFT-LOW-HOUSENUM     A          7
2 GEO-WA2-3L-LEFT-HI-HOUSENUM      A          7
2 GEO-WA2-3L-RIGHT-LOW-HOUSENUM    A          7
2 GEO-WA2-3L-RIGHT-HI-HOUSENUM     A          7
2 GEO-WA2-3L-CONT-PARITY-IND       A          1
2 GEO-WA2-3L-LIONFACECODE          A          4
2 GEO-WA2-3L-LIONSEQ               A          5
2 GEO-WA2-3L-GENRECFLAG            A          1
2 GEO-WA2-3L-SEGMENTLENGTH         P          5
2 GEO-WA2-3L-SEGMENTSLOPE          A          3
2 GEO-WA2-3L-SEGMENTORIENT         A          1
2 FILLER-WA2-3L-355                A          4
2 GEO-WA2-3L-RESDCP                A          2 /* RESERVED FOR DCP/GSS USE
2 GEO-WA2-3L-DOG-LEG               A          1
2 GEO-WA2-3L-FEATURE-TYPE          A          1
2 GEO-WA2-3L-LEFT-POLICEDIST       A          4
```

```
                R  2 GEO-WA2-3L-LEFT-POLICEDIST
                3 GEO-WA2-3L-L-POL-PATR-BORO-CMD   A          1
                3 GEO-WA2-3L-LEFT-POL-PRECINCT     A          3
                2 GEO-WA2-3L-RIGHT-POLICEDIST      A          4
                R  2 GEO-WA2-3L-RIGHT-POLICEDIST
                3 GEO-WA2-3L-R-POL-PATR-BORO-CMD   A          1
                3 GEO-WA2-3L-RIGHT-POL-PRECINCT    A          3
                2 GEO-WA2-3L-LEFT-SCHOOLDIST       A          2
                2 GEO-WA2-3L-RIGHT-SCHOOLDIST      A          2
                2 GEO-WA2-3L-MARBLE-RIKERS-FLAG    A          1
                2 GEO-WA2-3L-SEGMENT-ID            A          7
                2 FILLER-WA2-3L-370                A          1
                \*  * ******************************* *       ****
****************************
                \*    THE   PORTION   OF   THIS   WORK         AREA ABOVE THIS POINT IS
                \*    IDENTICAL  TO  THE STANDARD WORK         AREA 2 FOR FUNCTION 3.
                \*    THE  PORTION  BELOW  THIS  POINT           IS PRESENT ONLY FOR THE
                \*    LONG WORK AREA 2 OPTION.
                \*  * ******************************* *       ****
****************************
                2 GEO-WA2-3L-L-1990-CENSUSTRACT    A          6
                2 FILLER-WA2-370B                  A          4
                2 GEO-WA2-3L-LEFT-DYN-BLK          A          3
                2 GEO-WA2-3L-R-1990-CENSUSTRACT    A          6
                2 GEO-WA2-370C                     A          4
                2 GEO-WA2-3L-RIGHT-DYN-BLK         A          3
                2 GEO-WA2-3L-LEFT-FIRESEC          A          2
                2 GEO-WA2-3L-LEFT-FIREBAT          A          2
                2 GEO-WA2-3L-LEFT-FIRECO           A          4
                R  2 GEO-WA2-3L-LEFT-FIRECO
                3 GEO-WA2-3L-LEFT-FIRECO-TYPE      A          1
                3 GEO-WA2-3L-LEFT-FIRECO-NUM       A          3
                2 GEO-WA2-3L-RIGHT-FIRESEC         A          2
                2 GEO-WA2-3L-RIGHT-FIREBAT         A          2
                2 GEO-WA2-3L-RIGHT-FIRECO          A          4
                R  2 GEO-WA2-3L-RIGHT-FIRECO
                3 GEO-WA2-3L-RIGHT-FIRECO-TYPE     A          1
                3 GEO-WA2-3L-RIGHT-FIRECO-NUM      A          3
                2 GEO-WA2-3L-L-2010-CENSUSTRACT    A          6
                2 GEO-WA2-3L-L-2010-CENSUSBLOCK    A          4
                2 GEO-WA2-3L-L-2010-CENSUSBLKSFX   A          1
                2 GEO-WA2-3L-R-2010-CENSUSTRACT    A          6
                2 GEO-WA2-3L-R-2010-CENSUSBLOCK    A          4
                2 GEO-WA2-3L-R-2010-CENSUSBLKSFX   A          1
                2 GEO-WA2-3L-FROM-NODE             A          7
```

```
                2 GEO-WA2-3L-TO-NODE                A          7
                2 GEO-WA2-3L-L-2000-CENSUSTRACT     A          6
                2 GEO-WA2-3L-L-2000-CENSUSBLOCK     A          4
                2 GEO-WA2-3L-L-2000-CENSUSBLKSFX    A          1
                2 GEO-WA2-3L-R-2000-CENSUSTRACT     A          6
                2 GEO-WA2-3L-R-2000-CENSUSBLOCK     A          4
                2 GEO-WA2-3L-R-2000-CENSUSBLKSFX    A          1
                \*  * END OF FUNCTION 3                         LONG WORKAREA LAYOUT ******
                \*  - ------------------------------- -        ---- --------------------------
-
```

GEOLW21A COPY File

```
                1 GEOLW21A                                     /\*FCT 1A,BL USE SAME WA2
                                                                 LAYOUT
            \*  * THE FIELD W2NAT1A IS USED AS A      PARAMETER TO CALL GEOSUPPORT
                2 W2NAT1A                           A         21
            R   2 W2NAT1A
                3 GEO-WA2-1A-ACCESS-KEY             A         21
                2 GEO-WA2-1A-CONT-PARITY            A          1
                2 GEO-WA2-1A-LOW-HOUSENUM           A          6
                2 GEO-WA2-1A-ALTKEY-1               A         10
            R   2 GEO-WA2-1A-ALTKEY-1
                3 GEO-WA2-1A-ALTKEY-1-BORO          A          1
                3 GEO-WA2-1A-ALTKEY-1-TAXBLOCK      A          5
                3 GEO-WA2-1A-ALTKEY-1-TAXLOT        A          4
                2 FILLER-WA2-1A-230                 A          1
                2 GEO-WA2-1A-SCC                    A          1
                2 FILLER-WA2-1A-240                 A          1
                2 GEO-WA2-1A-GENERAL-LOT-INFO
                3 GEO-WA2-1A-RPAD-BLDG-CLASS        A          2
                3 GEO-WA2-1A-CORNER-CODE            A          2
                3 GEO-WA2-1A-NUM-OF-STRUCTURES      A          2
                3 GEO-WA2-1A-NUM-OF-BLOCKFACES      A          2
                3 GEO-WA2-1A-INTERIOR-FLAG          A          1
                3 GEO-WA2-1A-VACANT-FLAG            A          1
                3 GEO-WA2-1A-IRREG-FLAG             A          1
                2 GEO-WA2-1A-ALT-BORO-FLAG          A          1
                2 FILLER-WA2-1A-245                 A          1
                2 GEO-WA2-1A-STROLL-KEY             A         13
                2 GEO-WA2-1A-OVERFLOW-FLAG          A          1
                2 FILLER-WA2-1A-251                 A          1 /* USED FOR DCP
                2 GEO-WA2-1A-BIN                    A          7
                2 GEO-WA2-1A-CONDO-FLAG             A          1
                2 GEO-WA2-1A-RPAD-CONDO-NUM         A          4
```

```
    2 GEO-WA2-1A-CONDO-LOW-BBL         A         10
    2 FILLER-WA2-1A-260                A          1
    2 GEO-WA2-1A-CONDO-BILL-BBL        A         10
    2 FILLER-WA2-1A-270                A          1
    2 GEO-WA2-1A-CONDO-BILL-BBL-SCC    A          1
    2 GEO-WA2-1A-CONDO-HIGH-BBL        A         10
    2 FILLER-WA2-1A-275                A          1
    2 GEO-WA2-1A-SANBORN-BVOLPAGE      A          8
R   2 GEO-WA2-1A-SANBORN-BVOLPAGE
    3 GEO-WA2-1A-SANBORN-BORO          A          1
    3 GEO-WA2-1A-SANBORN-VOLPAGE       A          7
R   3 GEO-WA2-1A-SANBORN-VOLPAGE
    4 GEO-WA2-1A-SANBORN-VOL-NUM       A          3
    4 GEO-WA2-1A-SANBORN-VOL-PAGE      A          4
    2 GEO-WA2-1A-COMMERC-DIST          A          5
    2 GEO-WA2-1A-COOP-NUM              A          4
    2 FILLER-WA2-1A-276                A          4
    2 GEO-WA2-1A-ACTUAL-NUM-STRUCTS    A          4
    2 GEO-WA2-1A-DOF-MAP-BORO          A          1
    2 GEO-WA2-1A-DOF-MAP-SECVOL        A          4
    2 GEO-WA2-1A-DOF-MAP-PAGE          A          4
    2 GEO-WA2-1A-X-COORD               A          7
    2 GEO-WA2-1A-Y-COORD               A          7
    2 FILLER-WA2-1A-280                A         18
    2 GEO-WA2-1A-NUM-OF-ADDR-FOR-LOT   N          2
    2 GEO-WA2-1A-LIST-OF-ADDRESSES                 (1:21)
    3 GEO-WA2-1A-LIST-LOW-HOUSENUM     A          6
    3 FILLER-WA2-1A-290                A          3
    3 GEO-WA2-1A-LIST-HI-HOUSENUM      A          6
    3 FILLER-WA2-1A-300                A          3
    3 GEO-WA2-1A-LIST-STREETCODE       A          8
    3 GEO-WA2-1A-LIST-BIN              A          7
    3 GEO-WA2-1A-LIST-ADDR-TYPE        A          1
    3 FILLER-WA2-1A-310                A          1
    3 GEO-WA2-1A-LIST-SOS              A          1
```

GEOLW2AL COPY File

```
    1 GEOLW2AL                                /\*FCT 1A,BL USE SAME LONG WA2
  \* * THE FIELD W2NAT1AL IS USED AS A  P  ARA METER TO CALL GEOSUPPORT
    2 W2NAT1AL                         A   21
  R 2 W2NAT1AL
    3 GEO-WA2-1AL-ACCESS-KEY           A   21
    2 GEO-WA2-1AL-CONT-PARITY          A    1
    2 GEO-WA2-1AL-LOW-HOUSENUM         A    6
```

```
  2 GEO-WA2-1AL-ALTKEY-1            A   10
R 2 GEO-WA2-1AL-ALTKEY-1
  3 GEO-WA2-1AL-ALTKEY-1-BORO       A    1
  3 GEO-WA2-1AL-ALTKEY-1-TAXBLOCK   A    5
  3 GEO-WA2-1AL-ALTKEY-1-TAXLOT     A    4
  2 FILLER-WA2-1AL-230              A    1
  2 GEO-WA2-1AL-SCC                 A    1
  2 FILLER-WA2-1AL-240              A    1
  2 GEO-WA2-1AL-GENERAL-LOT-INFO
  3 GEO-WA2-1AL-RPAD-BLDG-CLASS     A    2
  3 GEO-WA2-1AL-CORNER-CODE         A    2
  3 GEO-WA2-1AL-NUM-OF-STRUCTURES   A    2
  3 GEO-WA2-1AL-NUM-OF-BLOCKFACES   A    2
  3 GEO-WA2-1AL-INTERIOR-FLAG       A    1
  3 GEO-WA2-1AL-VACANT-FLAG         A    1
  3 GEO-WA2-1AL-IRREG-LOT-FLAG      A    1
  2 GEO-WA2-1AL-ALT-BORO-FLAG       A    1
  2 FILLER-WA2-1AL-245              A    1
  2 GEO-WA2-1AL-STROLL-KEY          A   13
  2 FILLER-WA2-1AL-250              A    1
  2 FILLER-WA2-1AL-251              A    1 /* USED FOR DCP
  2 GEO-WA2-1AL-BIN                 A    7
  2 GEO-WA2-1AL-CONDO-FLAG          A    1
  2 GEO-WA2-1AL-RPAD-CONDO-NUM      A    4
  2 GEO-WA2-1AL-CONDO-LOW-BBL       A   10
  2 FILLER-WA2-1AL-260              A    1
  2 GEO-WA2-1AL-CONDO-BILL-BBL      A   10
  2 FILLER-WA2-1AL-270              A    1
  2 GEO-WA2-1AL-CONDO-BILL-BBL-SCC  A    1
  2 GEO-WA2-1AL-CONDO-HIGH-BBL      A   10
  2 FILLER-WA2-1AL-275              A    1
  2 GEO-WA2-1AL-SANBORN-BVOLPAGE    A    8
R 2 GEO-WA2-1AL-SANBORN-BVOLPAGE
  3 GEO-WA2-1AL-SANBORN-BORO        A    1
  3 GEO-WA2-1AL-SANBORN-VOLPAGE     A    7
R 3 GEO-WA2-1AL-SANBORN-VOLPAGE
  4 GEO-WA2-1AL-SANBORN-VOL-NUM     A    3
  4 GEO-WA2-1AL-SANBORN-VOL-PAGE    A    4
  2 GEO-WA2-1AL-COMMERC-DIST        A    5
  2 GEO-WA2-1AL-COOP-NUM            A    4
  2 FILLER-WA2-1AL-276              A    4
  2 GEO-WA2-1AL-ACTUAL-NUM-STRUCTS  A    4
  2 GEO-WA2-1AL-DOF-MAP-BORO        A    1
  2 GEO-WA2-1AL-DOF-MAP-SECVOL      A    4
  2 GEO-WA2-1AL-DOF-MAP-PAGE        A    4
```

```
  2 GEO-WA2-1AL-X-COORD              A    7
  2 GEO-WA2-1AL-Y-COORD              A    7
  2 FILLER-WA2-1AL-280               A   16
  2 GEO-WA2-1AL-NUM-OF-BINS-FOR-LOT  N    4
  2 GEO-WA2-1AL-LIST-OF-BINS                (1:2500)
  3 GEO-WA2-1AL-BINS                 N    7
```

GEOLW23S COPY File

```
   1 GEOLW23S
\*  * THE FIELD W2NAT3S IS USED AS A      PARAMETER TO CALL GEOSUPPORT
   2 W2NAT3S                          A         21
R  2 W2NAT3S
   3 GEO-WA2-3S-ACCESS-KEY            A         21
   2 GEO-WA2-3S-NUM-OF-INTERSECTS     N          3
   2 GEO-WA2-3S-LIST-OF-INTERSECTS                 (1:350)
   3 GEO-WA2-3S-SMALLEST-PBSC         P          6
   3 GEO-WA2-3S-2ND-SMALLEST-PBSC     P          6
   3 GEO-WA2-3S-DISTANCE              P          5
   3 GEO-WA2-3S-GAP-FLAG              A          1
```

APPENDIX 6: USER FEEDBACK PROCEDURES

This appendix describes the procedures for users to provide feedback to GSS of geographic data that have either been rejected by the Geosupport System or produced unexpected results. Only items that the user has reviewed and believes to be valid geographic data should be provided as feedback to GSS.

These feedback procedures should also be used for reporting software issues.

Feedback from users is a crucial resource in GSS's efforts to maintain accurate and up-to-date Geosupport data files. The staff of GSS's Geographic Research Unit researches the feedback received from users and corrects errors and omissions in Geosupport files as appropriate. Those corrections become accessible to users when the next release of Geosupport is installed on the computer where the user's application is running.

The user should review all items and screen out those caused by obvious user data coding or data entry errors, such as an obvious street name misspelling, the specification of the intersection of two streets that are obviously parallel, etc.

The user should provide feedback on those items that the user considers to be valid data, or is uncertain about, to GSS's Geographic Research Unit by submitting one or more completed Geosupport System User Feedback Forms. There are spaces to report up to three items on a single form. A sample form is included in this appendix and the user can replicate it as needed.

Printouts, sketch maps and/or any other material documenting the validity and location of the items should be attached to the form if possible. The user should provide any available information that would assist the GSS staff to research the issue. For example, if an address is rejected, the user should provide, if it is known, alternate addresses for the building, the names of the adjacent cross streets, the BBL (tax lot identifiers) etc.

In the case of large computer-generated reject reports, the user may submit the User Feedback Form as a transmittal form attached to the printout. In that case, it is not necessary for the user to transcribe all the reject information onto the form. If possible, the printout should display only the user input geographic data that Geosupport has rejected, not application-related data that is not passed to Geosupport. In addition, the printout should display the Geosupport Return Code, the Reason Code, and if there is space in the report, the Geosupport Message. When designing the reject report, it is advisable for the user to contact GSS Manager of Geographic Research to ascertain how the report should be sorted. Appropriate sorting of user reject reports greatly facilitates GSS's research.

Feedback materials and inquiries about feedback procedures should be submitted to:

Email: GSS_Feedback@planning.nyc.gov

Email is the preferred mode of communication. If email is not feasible, feedback may be submitted to: Manager of Gegraphic Reserach, Department fo City Planning 120 Broadway, 31stFloor New York, New York 10271 Phone: (212)720-3441 FAX: (212)720-3488

Software issues may be directed to: Email: GSS_Software@planning.nyc.gov

APPENDIX 7: MAINFRAME DATA CENTERS WHERE GEOSUPPORT IS INSTALLED

Current as of December, 2016

NAME OF AGENCY	LOCATION	LPARs at DOITT
DoITT/CSC - Department of Information Technology and Telecommunications / Computer Service Center	2 Metro Tech Center, Brooklyn	See below
DEP - Department of Environment Protection	DoITT	MVSW
DOE - Department of Education	DoITT	EDU*
DOF - Department of Finance	DoITT	DOF*
FISA – Financial Information Services Agency	450 West 33 Street, Manhattan	n/a
HHC - Health and Hospitals Corporation	230 West 41 Street, Manhattan	n/a
HRA – Human Resources Administration	DoITT	HRAP
NYCHA - New York City Housing Authority	250 Broadway, Manhattan	n/a
NYPD – New York Police Department	1 Police Plaza, Manhattan	n/a
All other city agencies	DoITT	MVSP

APPENDIX 8: SAMPLE APPLICATION PROGRAMS AND JCL

This appendix exhibits sample batch user application programs written in COBOL, Assembler, PL/1, C and NATURAL. These programs exemplify how a user-written application program may be coded to interact with Geosupport via its Application Programming Interface (API).

For each sample program, this appendix contains a printout of the job-stream input for an MSW application, the job-stream input for a COW application, and a printout of the program execution output report. The job-stream input contains the JCL to compile, link-edit and execute the program and, embedded in the JCL, the program source code (except for NATURAL) and a few in-stream records of sample input data. The NATURAL program source code is not embedded in the job-stream, and is printed separately. The MSW and COW sample programs both generate the same output report.

Please note that the sample application programs are not guaranteed to run exactly as shown in this appendix. The samples are here as an aid in developing Geosupport application programs.

All of the sample programs use the Geosupport COPY facility. Since this appendix displays un-compiled source code rather than compilation output listings, the source code is shown without the COPY file expansions. Therefore, the source code as shown contains references to fields in Geosupport work areas but does not contain the definitions of those fields. To see those definitions, refer to the listings of the COPY file contents in Appendix 5 (for MSW) and Appendix 14 (for COW).

There are two sample programs in each programming language, referred to as Sample Programs #1 and #2. The processing performed in Sample Program #1 is similar for all of the programming languages, as is the processing performed in Sample Program #2. Note: there is an MSW and COW version of each of the sample programs.

In brief, Sample Program #1 reads a record containing an address from the in-stream input file; calls Functions 1 and D, checking the Geosupport Return Code (GRC) generated by each call; and writes a record into a formatted output report. The report displays the input address data and, as appropriate, selected output data obtained from Geosupport and/or the GRC, Reason Code and Message.

Sample Program #2 performs similar processing, but its input file contains street intersections instead of addresses, and accordingly it calls Function 2 instead of Function 1.

Both sample programs use the Compact Names feature to direct Geosupport to return street names in a format suitable for display in the output report. In addition, Sample Program #1, but not Sample Program #2, uses the Street Name Normalization Length Limit (SNL) feature to limit the lengths of normalized street names so they will fit into that program's output report.

In both sample programs, Function D is called to generate the cross street names. Note, that Geosupport will generate all the cross street names automatically if the user specifies the Cross Street Names Flag in the initial Function 1 or Function 2 call or if the user calls Functions 1/1E Extended or Function 1B. (See Cross Street Names Flag in Appendix 3.) The Function D call, however, is used in the sample programs to demonstrate use of Function D and a one work-area-call.

In detail, the processing performed by Sample Program #1 is as follows:

- Read a record from the in-stream input file.
- Prime Work Area 1 with the function code, the Work Area Format Indicator (required for COW), the address information (Borough Code, House Number and Street Name) from the input record, the appropriate SNL value, and the code required to request street names in the compact format.
- Call Function 1.
- Examine the Geosupport Return Code (GRC).
- If the GRC indicates a successful call or a warning, use the street codes of the cross streets retrieved in WA2 as input to a Function D call to obtain their street names for display in the output report [14]. The Function D processing is performed as follows:
- Prime Work Area 1 with the function code value, the Work Area Format Indicator (required for COW), and the street codes of the cross streets obtained from the Function 1 call.
- Call Function D
- Note: If the Cross Street Names Flag is used in the original call to Function 1 (or if Extended Mode of Function1 is used or if Function 1B is used), all the cross street names will be returned.
- Examine the GRC.
- If the GRC is zeros, include the street names obtained from Function D in the output report. Otherwise, include the GRC, the Reason Code and the warning/reject message in the output report.
- Write an output report line containing the input information and, selected output information obtained from Work Area 2 (e.g., the ZIP code, Community District, and cross streets) and/or the Geosupport Return Code, Reason Code and Message

[14] Note: The sample programs have been written in a skeletal fashion to illustrate the use of the Geosupport API as clearly as possible. Thus, for example, Sample Program #1 assumes, when it gets a 'hit' for an input address, that WA2 contains at least one cross street at each end of the block face containing the address. In reality, this is not necessarily the case; in a real application, the program would check for the presence of cross street codes before calling Function D.

COBOL SAMPLE PROGRAM #1

- Input Job Stream - MSW

- Input Job Stream - COW

- Output Report

COBOL SAMPLE PROGRAM #1-JOB Stream-MSW

```
//COBF1SRC JOB   YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//***  COBOL SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1  ****
//***                     MSW FORMAT                               ****
//*******************************************************************
//STEP1 EXEC   IGYWCLG,PARM.COBOL=(NOWORD,OPTIMIZE)
//COBOL.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//             DD DSN=A030.GEO.COPYLIB,DISP=SHR
//COBOL.SYSIN  DD *
      ******************************************************************
      \* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING *
      \* BORO, HOUSE NUMBER & STREET NAME SUPPLIED BY AN INSTREAM FILE.*
      \* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     *
      \* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  *
      \* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
      \*       NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE   *
      \*             ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET *
      \*             NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 1.     *
      ******************************************************************
      *
       IDENTIFICATION DIVISION.
         PROGRAM-ID. COBS1JOB.

      ****************************************

       ENVIRONMENT DIVISION.
         INPUT-OUTPUT SECTION.
```

```
   FILE-CONTROL.
     SELECT IN-FILE ASSIGN TO INFILE.
     SELECT RPT-FILE ASSIGN TO RPTFILE.

****************************************

 DATA DIVISION.
   FILE SECTION.

**** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DEFINTION *****
   FD  IN-FILE
       RECORDING MODE IS F
       RECORD CONTAINS 80 CHARACTERS
       LABEL RECORDS ARE OMITTED.

 01  INPUT-TO-GEOSUPPORT.
     05  IN-BORO-CODE        PIC X.
     05  FILLER              PIC X.
     05  IN-HOUSE-NUMBER     PIC X(12).
     05  FILLER              PIC X.
     05  IN-STREET           PIC X(32).
     05  FILLER              PIC X(33).

   FD  RPT-FILE
       RECORDING MODE IS F
       RECORD CONTAINS 132 CHARACTERS
       LABEL RECORDS ARE OMITTED.

 01  RPT-LINE                PIC X(132).
 WORKING-STORAGE SECTION.
 ***************************************************************
*** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE ***
*** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                  ***
*****************************************************************
 01  WORK1.    COPY  W1COB.
 01  WORK2.    COPY  W2COB.

**** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT    *********

 01  RPT-DATA-LINE1.
     05  OUT-BOR             PIC X.
     05  FILLER              PIC X         VALUE ' '.
     05  OUT-HN              PIC X(12).
     05  FILLER              PIC X         VALUE ' '.
     05  OUT-ST              PIC X(32).
```

```
        05  FILLER              PIC X         VALUE ' '.
        05  OUT-ZIP             PIC X(5).
        05  FILLER              PIC X         VALUE ' '.
        05  OUT-CD              PIC X(2).
        05  FILLER              PIC X         VALUE ' '.
        05  OUT-NYPD-PCT        PIC X(3).
        05  FILLER              PIC X(6)      VALUE ' '.
        05  OUT-SCHLDIST        PIC X(2).
        05  FILLER              PIC X(58)     VALUE ' '.

    01  RPT-DATA-LINE2.
        05  FILLER              PIC X(74)     VALUE ' '.
        05  OUT-LO-X-STREET     PIC X(25).
        05  FILLER              PIC X VALUE ' '.
        05  OUT-HI-X-STREET     PIC X(25).

    01  RPT-ERR-LINE-1.
        05  ERR-BOR             PIC X.
        05  FILLER              PIC X         VALUE ' '.
        05  ERR-HN              PIC X(12).
        05  FILLER              PIC X         VALUE ' '.
        05  ERR-ST              PIC X(32).
        05  FILLER              PIC X(14)
            VALUE ' *** FUNCTION '.
        05  ERR-FUNCTION        PIC X.
        05  FILLER              PIC X(7)
            VALUE ' GRC = '.
        05  ERR-GRC             PIC X(2).
        05  FILLER              PIC X(15) VALUE ' REASON CODE = '.
        05  ERR-REASON          PIC X.
        05  FILLER              PIC X(45) VALUE ' '.

    01  RPT-ERR-LINE-2.
        05  FILLER              PIC X(48) VALUE ' '.
        05  FILLER              PIC X(4) VALUE '*** '.
        05  OUT-ERR-MSG         PIC X(80).

    01  RPT-WRN-LINE.
        05  WRN-BOR             PIC X.
        05  FILLER              PIC X         VALUE ' '.
        05  WRN-HN              PIC X(12).

05  FILLER             PIC X         VALUE ' '.
        05  WRN-ST              PIC X(32).
        05  FILLER              PIC X(14)
```

```
        VALUE ' *** FUNCTION '.
    05  WRN-FUNCTION        PIC X.
    05  FILLER              PIC X(16)
  VALUE ' WARNING, GRC = '.
    05  WRN-GRC             PIC X(2).
    05  FILLER              PIC X(15) VALUE ' REASON CODE = '.
    05  WRN-REASON          PIC X(1).
    05  FILLER              PIC X(36) VALUE ' '.

01  RPT-HEADER-1.
    05  FILLER              PIC X(40)  VALUE
    'SAMPLE COBOL PROGRAM \#1 EXECUTION OUTPUT'.
    05  FILLER              PIC X(72) VALUE ' '.

01  RPT-HEADER-2.
    05  FILLER              PIC X(58)  VALUE
    '*****---------- INPUT ADDRESS ------------***** *****-----'.
    05  FILLER              PIC X(58)  VALUE
    '---------------- SELECTED OUTPUT ITEMS -------------------'.
    05  FILLER              PIC X(16)  VALUE
    '----*****       '.

01  RPT-HEADER-3.
    05  FILLER              PIC X(58)  VALUE
    'B HOUSE NUMBER IN-STREET-NAME                    ZIP CD N'.
    05  FILLER              PIC X(58)  VALUE
    'YPD-PCT SCHLDST LOW CROSS STREET         HIGH CROSS STREE'.
    05  FILLER              PIC X(16)  VALUE
    'T               '.

01  RPT-HEADER-4.
    05  FILLER              PIC X(58)  VALUE
    '_ ____________ ________________________________ _____ __ \_'.
    05  FILLER              PIC X(58)  VALUE
    '_______ _______ ________________________ ________________'.
    05  FILLER              PIC X(16)  VALUE
    '_________       '.

01  FLAGS.
    05 DATA-FLAG    PIC XXX   VALUE 'YES'.
      88 MORE-DATA            VALUE 'YES'.
      88 NO-DATA              VALUE 'NO '.

****************************************
```

```
        PROCEDURE DIVISION.

            OPEN INPUT IN-FILE, OUTPUT RPT-FILE.
            WRITE RPT-LINE FROM RPT-HEADER-1 AFTER ADVANCING 1 LINES.
            WRITE RPT-LINE FROM RPT-HEADER-2 AFTER ADVANCING 2 LINES.
            WRITE RPT-LINE FROM RPT-HEADER-3 AFTER ADVANCING 2 LINES.
            WRITE RPT-LINE FROM RPT-HEADER-4 AFTER ADVANCING 0 LINES.
            READ IN-FILE AT END MOVE 'NO ' TO DATA-FLAG.
            PERFORM PROCESS THRU PROCESS-EX
     UNTIL NO-DATA.
            CLOSE IN-FILE, RPT-FILE.
            MOVE 0 TO RETURN-CODE
            STOP RUN.

Process.
      ****************************************************************
      \* TO MAKE A FUNCTION 1 CALL:                                   *
      \*   (1) INITIALIZE WORKAREA 1 TO SPACES                        *
      \*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                     *
      \*   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD     *
      \*   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER *
      \*       FIELD                                                  *
      \*   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  *
      \*   (6) CALL GBI WITH 2 WORKAREAS                              *
      \*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS              *
      ****************************************************************
      ****************************************************************
      \* AS OF GEOSUPPORT 10.1,                                       *
      \* TO RECEIVE ROADBED-SPECIFIC INFORMATION,                     *
      \* SET THE ROADBED REQUEST SWITCH TO 'R', AS FOLLOWS:           *
      \* MOVE 'R' TO GEO-WA1-IN-ROADBED-REQ-SWITCH.                   *
      ****************************************************************
            MOVE SPACES TO WORK1.
            MOVE '1 ' TO GEO-WA1-IN-FUNCTION-CODE.
            MOVE IN-BORO-CODE TO GEO-WA1-IN-BORO OUT-BOR ERR-BOR WRN-BOR.
            MOVE IN-HOUSE-NUMBER TO GEO-WA1-IN-HOUSENUM OUT-HN ERR-HN
                                                    WRN-HN.
            MOVE IN-STREET TO GEO-WA1-IN-STREET-1 OUT-ST ERR-ST WRN-ST.
            CALL 'GBI' USING WORK1 WORK2.

            IF GEO-WA1-OUT-RETURN-CODE NOT = 00
               MOVE '1' TO ERR-FUNCTION WRN-FUNCTION
               PERFORM PRINT-ERROR-LINE THRU P-E-EX.

            IF (GEO-WA1-OUT-RETURN-CODE = 00) OR
```

```
       (GEO-WA1-OUT-RETURN-CODE = 01)
        PERFORM SUCCESSFUL-FUNC1 THRU S-F1-EX.

     READ IN-FILE AT END MOVE 'NO ' TO DATA-FLAG.

 PROCESS-EX.
     EXIT.

 SUCCESSFUL-FUNC1.

*************************************************************
***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ***********
***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS          *****
*************************************************************
     MOVE GEO-WA2-FN1-ZIP            TO OUT-ZIP.
     MOVE GEO-WA2-FN1-COMDIST-NUMBER TO OUT-CD.
     MOVE GEO-WA2-FN1-POL-PRECINCT   TO OUT-NYPD-PCT.
     MOVE GEO-WA2-FN1-SCHOOLDIST     TO OUT-SCHLDIST.
     IF GEO-WA1-OUT-RETURN-CODE = 00
       WRITE RPT-LINE FROM RPT-DATA-LINE1 AFTER ADVANCING 2 LINES
     ELSE
       MOVE SPACES TO OUT-BOR OUT-HN OUT-ST
       WRITE RPT-LINE FROM RPT-DATA-LINE1 AFTER ADVANCING 1 LINES.

*************************************************************
\* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND  *
\* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE    *
\* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS     *
\* FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D: *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                    *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO D                 *
\*   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED      *
\*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE     *
\*              HAS SPACE FOR ONLY 25 CHARACTERS)           *
\*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN      *
\*       STREET NAMES FORMATTED FOR DISPLAY                 *
\*   (5) MOVE WA2'S LOW PBSC FIELD TO WA1'S INPUT STREET    *
\*       CODE 1 FIELD                                       *
\*   (6) MOVE WA2'S HIGH PBSC FIELD TO WA1'S INPUT STREET   *
\*       CODE 2 FIELD                                       *
\*   (7) CALL GBI WITH 1 WORKAREA                           *
\*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS          *
*************************************************************
     MOVE SPACES TO WORK1.
     MOVE 'D ' TO GEO-WA1-IN-FUNCTION-CODE.
```

```
            MOVE 'C' TO GEO-WA1-IN-COMPACT-NAME-FLAG.
            MOVE '25' TO GEO-WA1-IN-SNL.
            MOVE GEO-WA2-FN1-LOW-PBSC (1) TO GEO-WA1-IN-STREETCODE-1.
            MOVE GEO-WA2-FN1-HI-PBSC  (1) TO GEO-WA1-IN-STREETCODE-2.
            CALL 'GBI' USING WORK1.

            IF GEO-WA1-OUT-RETURN-CODE NOT = 00
               MOVE 'D' TO ERR-FUNCTION WRN-FUNCTION
               PERFORM PRINT-ERROR-LINE THRU P-E-EX.

            IF (GEO-WA1-OUT-RETURN-CODE = 00) OR
               (GEO-WA1-OUT-RETURN-CODE = 01)
               PERFORM SUCCESSFUL-FUNCD THRU S-FD-EX.

        S-F1-EX.
            EXIT.

        SUCCESSFUL-FUNCD.

            MOVE GEO-WA1-OUT-STREET-1 TO OUT-LO-X-STREET
            MOVE GEO-WA1-OUT-STREET-2 TO OUT-HI-X-STREET
            WRITE RPT-LINE FROM RPT-DATA-LINE2 AFTER ADVANCING 0 LINES.

        S-FD-EX.
            EXIT.


        PRINT-ERROR-LINE.
            MOVE GEO-WA1-OUT-RETURN-CODE TO ERR-GRC WRN-GRC.
            MOVE GEO-WA1-OUT-REASON-CODE TO ERR-REASON WRN-REASON.
            MOVE GEO-WA1-OUT-ERROR-MESSAGE TO OUT-ERR-MSG.

            IF GEO-WA1-OUT-RETURN-CODE = 01
       **** INSERT YOUR OWN WARNING ROUTINE HERE  ****
              WRITE RPT-LINE FROM RPT-WRN-LINE AFTER ADVANCING 2 LINES
            ELSE
       **** INSERT YOUR OWN WARNING ROUTINE HERE  ****


    WRITE RPT-LINE FROM RPT-ERR-LINE-1 AFTER ADVANCING 2 LINES.

            WRITE RPT-LINE FROM RPT-ERR-LINE-2 AFTER ADVANCING 1 LINES.

        P-E-EX.
            EXIT.
```

```
/*
//LKED.SYSIN DD *
  INCLUDE INCLIB(GBI)
//LKED.INCLIB   DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR

//*****************************************************************//
//*                                                               \*//
//*  AS OF GEOSUPPPORT VERSION 10.0,                              \*//
//*  THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP     \*//
//*  MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:        \*//
//*       A030.GEO.SUPPORT.PDSE.LOADLIB                           \*//
//*       A030.GEO.SUPPORT.LOADLIB                                \*//
//*                                                               \*//
//*****************************************************************//
//GO.STEPLIB DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//           DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//*****************************************************************//
//*                                                               \*//
//*  AS OF GEOSUPPPORT VERSION 10.0,                              \*//
//*  DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD, ETC) \*//
//*  ARE NO LONGER NEEDED AND ARE IGNORED.  GEOSUPPORT IS TAILORED \*//
//*  TO USE STANDARD GEOSUPPORT DATA SET NAMES.                   \*//
//*  TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.      \*//
//*                                                               \*//
//*****************************************************************//
//*
//GO.SYSUDUMP DD SYSOUT=A,OUTLIM=3000
//GO.SYSOUT   DD SYSOUT=A
//GO.RPTFILE  DD SYSOUT=A
//GO.INFILE  DD *
1 22           READE ST
1 500          DUANE ST
1 82-84        BROADWAY
4 165-100      BAISLEY BLVD
4 165-1000     BAISLEY BLVD
/*
//
```

COBOL SAMPLE PROGRAM #1 – Job Stream - COW

```
//COBC1SRC JOB   YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//***  COBOL SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM #1  ****
```

```
//***                    COW FORMAT                          ****
//*****************************************************************
//STEP1 EXEC   IGYWCLG,PARM.COBOL=(NOWORD,OPTIMIZE)
//COBOL.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//             DD DSN=A030.GEO.COPYLIB,DISP=SHR
//COBOL.SYSIN  DD *
      ****************************************************************
      \* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING *
      \* BORO, HOUSE NUMBER & STREET NAME SUPPLIED BY AN INSTREAM FILE.*
      \* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     *
      \* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  *
      \* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
      \*       NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE   *
      \*             ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET *
      \*             NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 1.     *
      ****************************************************************
      *
       IDENTIFICATION DIVISION.
         PROGRAM-ID. COBS1JOB.

      ****************************************

       ENVIRONMENT DIVISION.
         INPUT-OUTPUT SECTION.

 FILE-CONTROL.
           SELECT IN-FILE ASSIGN TO INFILE.
           SELECT RPT-FILE ASSIGN TO RPTFILE.

      ****************************************

       DATA DIVISION.
         FILE SECTION.

      **** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DEFINTION *****
         FD  IN-FILE
             RECORDING MODE IS F
             RECORD CONTAINS 80 CHARACTERS
             LABEL RECORDS ARE OMITTED.

       01  INPUT-TO-GEOSUPPORT.
           05  IN-BORO-CODE        PIC X.
           05  FILLER              PIC X.
           05  IN-HOUSE-NUMBER     PIC X(12).
           05  FILLER              PIC X.
```

```
            05  IN-STREET           PIC X(32).
            05  FILLER              PIC X(33).

          FD  RPT-FILE
              RECORDING MODE IS F
              RECORD CONTAINS 132 CHARACTERS
              LABEL RECORDS ARE OMITTED.

        01  RPT-LINE                PIC X(132).

        WORKING-STORAGE SECTION.

*****************************************************************
      *** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE ***
      *** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                  ***
      *****************************************************************
        01  WORK1.    COPY  P1COB.
        01  WORK2.    COPY  P2COB.

      **** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT    *********

        01  RPT-DATA-LINE1.
            05  OUT-BOR             PIC X.
            05  FILLER              PIC X         VALUE ' '.
            05  OUT-HN              PIC X(12).
            05  FILLER              PIC X         VALUE ' '.
            05  OUT-ST              PIC X(32).
            05  FILLER              PIC X         VALUE ' '.
            05  OUT-ZIP             PIC X(5).
            05  FILLER              PIC X         VALUE ' '.
            05  OUT-CD              PIC X(2).
            05  FILLER              PIC X         VALUE ' '.
            05  OUT-NYPD-PCT        PIC X(3).
            05  FILLER              PIC X(6)      VALUE ' '.
            05  OUT-SCHLDIST        PIC X(2).
            05  FILLER              PIC X(58)     VALUE ' '.

        01  RPT-DATA-LINE2.
            05  FILLER              PIC X(74)     VALUE ' '.
            05  OUT-LO-X-STREET     PIC X(25).
            05  FILLER              PIC X VALUE ' '.
            05  OUT-HI-X-STREET     PIC X(25).

            01  RPT-ERR-LINE-1.
            05  ERR-BOR             PIC X.
```

```
        05  FILLER              PIC X         VALUE ' '.
        05  ERR-HN              PIC X(12).
        05  FILLER              PIC X         VALUE ' '.
        05  ERR-ST              PIC X(32).
        05  FILLER              PIC X(14)
            VALUE ' *** FUNCTION '.
        05  ERR-FUNCTION        PIC X.
        05  FILLER              PIC X(7)
            VALUE ' GRC = '.
        05  ERR-GRC             PIC X(2).
        05  FILLER              PIC X(15) VALUE ' REASON CODE = '.
        05  ERR-REASON          PIC X.
        05  FILLER              PIC X(45) VALUE ' '.

    01  RPT-ERR-LINE-2.
        05  FILLER              PIC X(48) VALUE ' '.
        05  FILLER              PIC X(4) VALUE '*** '.
        05  OUT-ERR-MSG         PIC X(80).

    01  RPT-WRN-LINE.
        05  WRN-BOR             PIC X.
        05  FILLER              PIC X         VALUE ' '.
        05  WRN-HN              PIC X(12).

  05  FILLER              PIC X         VALUE ' '.
        05  WRN-ST              PIC X(32).
        05  FILLER              PIC X(14)

VALUE ' *** FUNCTION '.
        05  WRN-FUNCTION        PIC X.
        05  FILLER              PIC X(16)
            VALUE ' WARNING, GRC = '.
        05  WRN-GRC             PIC X(2).
        05  FILLER              PIC X(15) VALUE ' REASON CODE = '.
        05  WRN-REASON          PIC X(1).
        05  FILLER              PIC X(36) VALUE ' '.

    01  RPT-HEADER-1.
        05  FILLER              PIC X(40)  VALUE
        'SAMPLE COBOL PROGRAM \#1 EXECUTION OUTPUT'.
        05  FILLER              PIC X(72) VALUE ' '.

    01  RPT-HEADER-2.
        05  FILLER              PIC X(58)  VALUE
        '*****---------- INPUT ADDRESS ------------***** *****-----'.
```

```
    05  FILLER              PIC X(58)  VALUE
    '---------------- SELECTED OUTPUT ITEMS -------------------'.
    05  FILLER              PIC X(16)  VALUE
    '----*****       '.

 01  RPT-HEADER-3.
    05  FILLER              PIC X(58)  VALUE
    'B HOUSE NUMBER IN-STREET-NAME                    ZIP CD N'.
    05  FILLER              PIC X(58)  VALUE
    'YPD-PCT SCHLDST LOW CROSS STREET          HIGH CROSS STREE'.
    05  FILLER              PIC X(16)  VALUE
    'T               '.

 01  RPT-HEADER-4.
    05  FILLER              PIC X(58)  VALUE
    '_ ____________ ________________________________ _____ __ \_'.

    05  FILLER              PIC X(58)  VALUE
    '_______ _______ ________________________ ________________'.
    05  FILLER              PIC X(16)  VALUE
    '_________       '.

 01  FLAGS.
    05 DATA-FLAG    PIC XXX   VALUE 'YES'.
      88 MORE-DATA            VALUE 'YES'.
      88 NO-DATA              VALUE 'NO '.

****************************************

 PROCEDURE DIVISION.

    OPEN INPUT IN-FILE, OUTPUT RPT-FILE.
    WRITE RPT-LINE FROM RPT-HEADER-1 AFTER ADVANCING 1 LINES.
    WRITE RPT-LINE FROM RPT-HEADER-2 AFTER ADVANCING 2 LINES.
    WRITE RPT-LINE FROM RPT-HEADER-3 AFTER ADVANCING 2 LINES.
    WRITE RPT-LINE FROM RPT-HEADER-4 AFTER ADVANCING 0 LINES.
    READ IN-FILE AT END MOVE 'NO ' TO DATA-FLAG.


    PERFORM PROCESS THRU PROCESS-EX
    UNTIL NO-DATA.
    CLOSE IN-FILE, RPT-FILE.
    MOVE 0 TO RETURN-CODE
    STOP RUN.
```

```
 PROCESS.

*****************************************************************
\* TO MAKE A FUNCTION 1 CALL:                                    *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                         *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                      *
\*   (3) SET THE PLATFORM INDICATOR SWITCH (NON-IBM-MAINFRAME)   *
\*       TO USE CHARACTER-ONLY WORK AREAS (COWS)                 *
\*   (4) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD      *
\*   (5) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER *
\*       FIELD                                                   *
\*   (6) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  *
\*   (7) CALL GBI WITH 2 WORKAREAS                               *
\*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS               *
*****************************************************************
*****************************************************************
\* AS OF GEOSUPPORT 10.1,                                        *
\* TO RECEIVE ROADBED-SPECIFIC INFORMATION,                      *
\* SET THE ROADBED REQUEST SWITCH TO 'R', AS FOLLOWS:            *
\* MOVE 'R' TO PIWA1-IN-ROADBED-REQ-SWITCH.                      *
*****************************************************************
     MOVE SPACES TO WORK1.
     MOVE '1 ' TO PIWA1-IN-FUNC-CODE.
     MOVE 'C' TO GEO-WA1-IN-NON-IBM-MAIN-FRAME.
     MOVE IN-BORO-CODE TO GEO-WA1-IN-BORO OUT-BOR ERR-BOR WRN-BOR.
     MOVE IN-HOUSE-NUMBER TO PIWA1-IN-HOUSENUM-DISPLAY OUT-HN
                                        ERR-HN WRN-HN.
     MOVE IN-STREET TO GEO-WA1-IN-STREET-1 OUT-ST ERR-ST WRN-ST.
     CALL 'GBI' USING WORK1 WORK2.

     IF GEO-WA1-OUT-RETURN-CODE NOT = 00
        MOVE '1' TO ERR-FUNCTION WRN-FUNCTION
        PERFORM PRINT-ERROR-LINE THRU P-E-EX.

     IF (GEO-WA1-OUT-RETURN-CODE = 00) OR
       (GEO-WA1-OUT-RETURN-CODE = 01)
        PERFORM SUCCESSFUL-FUNC1 THRU S-F1-EX.

 READ IN-FILE AT END MOVE 'NO ' TO DATA-FLAG.

 PROCESS-EX.
     EXIT.

 SUCCESSFUL-FUNC1.
```

```
  ************************************************************
  ***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ***********
  ***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS          *****
  ************************************************************
       MOVE GEO-WA2-FN1-ZIP            TO OUT-ZIP.
       MOVE GEO-WA2-FN1-COMDIST-NUMBER TO OUT-CD.


MOVE GEO-WA2-FN1-POL-PRECINCT   TO OUT-NYPD-PCT.
       MOVE GEO-WA2-FN1-SCHOOLDIST     TO OUT-SCHLDIST.
       IF GEO-WA1-OUT-RETURN-CODE = 00
         WRITE RPT-LINE FROM RPT-DATA-LINE1 AFTER ADVANCING 2 LINES
       ELSE
         MOVE SPACES TO OUT-BOR OUT-HN OUT-ST
         WRITE RPT-LINE FROM RPT-DATA-LINE1 AFTER ADVANCING 1 LINES.


  ****************************************************************
  \* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND      *
  \* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE        *
  \* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS         *
  \* FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D:     *
  \*   (1) INITIALIZE WORKAREA 1 TO SPACES                        *
  \*   (2) SET WA1'S FUNCTION CODE FIELD TO D                     *
  \*   (3) SET THE PLATFORM INDICATOR SWITCH (NON-IBM-MAINFRAME)  *
  \*       TO USE CHARACTER-ONLY WORK AREAS (COWS)                *
  \*   (4) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED          *
  \*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE         *
  \*              HAS SPACE FOR ONLY 25 CHARACTERS)               *
  \*   (5) USE THE COMPACT STREET NAMES OPTION TO OBTAIN          *
  \*       STREET NAMES FORMATTED FOR DISPLAY                     *
  \*   (6) MOVE WA2'S LOW BSC FIELD TO WA1'S INPUT STREET         *
  \*       CODE 1 FIELD                                           *
  \*   (7) MOVE WA2'S HIGH BSC FIELD TO WA1'S INPUT STREET        *
  \*       CODE 2 FIELD                                           *
  \*   (8) CALL GBI WITH 1 WORKAREA                               *
  \*   (9) CHECK RETURN CODES FOR ERRORS OR WARNINGS              *
  ****************************************************************
       MOVE SPACES TO WORK1.
       MOVE 'D ' TO PIWA1-IN-FUNC-CODE.
       MOVE 'C' TO GEO-WA1-IN-NON-IBM-MAIN-FRAME.
       MOVE 'C' TO GEO-WA1-IN-COMPACT-NAME-FLAG.
       MOVE '25' TO GEO-WA1-IN-SNL.
       MOVE PIWA2-FN1-LOW-B5SC (1) TO GEO-WA1-IN-10SC-1.
       MOVE PIWA2-FN1-HI-B5SC  (1) TO GEO-WA1-IN-10SC-2.
```

```
            CALL 'GBI' USING WORK1.

            IF GEO-WA1-OUT-RETURN-CODE NOT = 00
               MOVE 'D' TO ERR-FUNCTION WRN-FUNCTION
               PERFORM PRINT-ERROR-LINE THRU P-E-EX.

            IF (GEO-WA1-OUT-RETURN-CODE = 00) OR
               (GEO-WA1-OUT-RETURN-CODE = 01)
               PERFORM SUCCESSFUL-FUNCD THRU S-FD-EX.

        S-F1-EX.
        EXIT.

        SUCCESSFUL-FUNCD.

            MOVE GEO-WA1-OUT-STREET-1 TO OUT-LO-X-STREET
            MOVE GEO-WA1-OUT-STREET-2 TO OUT-HI-X-STREET
            WRITE RPT-LINE FROM RPT-DATA-LINE2 AFTER ADVANCING 0 LINES.

        S-FD-EX.

            EXIT.


        PRINT-ERROR-LINE.
            MOVE GEO-WA1-OUT-RETURN-CODE TO ERR-GRC WRN-GRC.
            MOVE GEO-WA1-OUT-REASON-CODE TO ERR-REASON WRN-REASON.
            MOVE GEO-WA1-OUT-ERROR-MESSAGE TO OUT-ERR-MSG.

            IF GEO-WA1-OUT-RETURN-CODE = 01
       **** INSERT YOUR OWN WARNING ROUTINE HERE  ****
              WRITE RPT-LINE FROM RPT-WRN-LINE AFTER ADVANCING 2 LINES
            ELSE
       **** INSERT YOUR OWN ERROR ROUTINE HERE  ****
              WRITE RPT-LINE FROM RPT-ERR-LINE-1 AFTER ADVANCING 2 LINES.

  WRITE RPT-LINE FROM RPT-ERR-LINE-2 AFTER ADVANCING 1 LINES.

        P-E-EX.
            EXIT.
/*
//LKED.SYSIN DD *
  INCLUDE INCLIB(GBI)
//LKED.INCLIB   DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************//
```

```
//*                                                                  \*//
//*  AS OF GEOSUPPPORT VERSION 10.0,                                 \*//
//*  THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP        \*//
//*  MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:           \*//
//*       A030.GEO.SUPPORT.PDSE.LOADLIB                              \*//
//*       A030.GEO.SUPPORT.LOADLIB                                   \*//
//*                                                                  \*//
//*******************************************************************//
//GO.STEPLIB DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//           DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//*******************************************************************//
//*                                                                  \*//
//*  AS OF GEOSUPPPORT VERSION 10.0,                                 \*//
//*  DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD, ETC) \*//
//*  ARE NO LONGER NEEDED AND ARE IGNORED.  GEOSUPPORT IS TAILORED \*//
//*  TO USE STANDARD GEOSUPPORT DATA SET NAMES.                      \*//
//*  TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.         \*//
//*                                                                  \*//
//*******************************************************************//
//*
//GO.SYSUDUMP DD SYSOUT=A,OUTLIM=3000
//GO.SYSOUT   DD SYSOUT=A
//GO.RPTFILE  DD SYSOUT=A
//GO.INFILE  DD *
1 22           READE ST
1 500          DUANE ST
1 82-84        BROADWAY
4 165-100      BAISLEY BLVD
4 165-1000     BAISLEY BLVD
/*
//
```

COBOL SAMPLE PROGRAM #1 – Output Report

```
          SAMPLE COBOL PROGRAM \#1 EXECUTION OUTPUT

           *****---------- INPUT ADDRESS ------------***** *****--------------------- SELECTED
OUTPUT ITEMS -----------------------*****

           B HOUSE NUMBER IN-STREET-NAME                     ZIP CD NYPD-PCT SCHLDST LOW CROSS
STREET          HIGH CROSS STREET
           - ------------ ------------------------------- ----- -- -------- ------- ----------
--------------- ------------------------

           1 22           READE ST                        10007 01 005      02      ELK STREET
BROADWAY

           1 500          DUANE ST                        *** FUNCTION 1 GRC = 42 REASON CODE
=
                                                          *** ADDRESS NUMBER OUT OF RANGE

           1 82-84        BROADWAY                        *** FUNCTION 1 WARNING, GRC = 01
REASON CODE = 1
                                                          *** ADDR NUMBER ALTERED: RANGE
ASSUMED. USING DIGITS BEFORE DASH ONLY
                                                          10005 01 001      02      RECTOR
STREET             WALL GREEN

           4 165-100      BAISLEY BLVD                    11434 12 113      28      SMITH
STREET              166 STREET

           4 165-1000     BAISLEY BLVD                    *** FUNCTION 1 GRC = 13 REASON CODE
= 2
                                                          *** ADDRESS NBR 165-1000  HAS MORE
THAN 3 DIGITS AFTER THE DASH.
```

COBOL SAMPLE PROGRAM #2

- Input Job Stream - MSW

- Input Job Stream - COW

- Output Report - COW

COBOL SAMPLE PROGRAM #2- Job Stream - MSW

```
     //COBF2SRC JOB   YOUR-JOB-CARD-INFORMATION
     //*
     //*******************************************************************
```

```
//***  COBOL SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#2  ****
//***                     MSW FORMAT                              ****
//*****************************************************************
//STEP1 EXEC   IGYWCLG,PARM.COBOL=(NOWORD,OPTIMIZE)
//COBOL.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//             DD DSN=A030.GEO.COPYLIB,DISP=SHR
//COBOL.SYSIN  DD *
      ****************************************************************
      \* THIS PROGRAM MAKES FUNCTION 2 AND D CALLS TO GEOSUPPORT USING *
      \* TWO BOROS AND TWO STREET NAMES SUPPLIED BY AN INSTREAM FILE.  *
      \* FUNCTION 2 RETURNS GEOGRAPHIC INFORMATION FOR AN INTERSECTION.*
      \* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  *
      \* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
      \*       NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE   *
      \*             ORIGINAL CALL TO FUNCTION 2, ALL THE CROSS STREET *
      \*             NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 2.     *
      ****************************************************************
      *
       IDENTIFICATION DIVISION.
         PROGRAM-ID. COBS1JOB.

      ****************************************

       ENVIRONMENT DIVISION.
         INPUT-OUTPUT SECTION.
         FILE-CONTROL.
           SELECT IN-FILE ASSIGN TO INFILE.
           SELECT RPT-FILE ASSIGN TO RPTFILE.

      ****************************************

       DATA DIVISION.
         FILE SECTION.

      **** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DEFINTION *****
         FD  IN-FILE
             RECORDING MODE IS F
             RECORD CONTAINS 80 CHARACTERS
             LABEL RECORDS ARE OMITTED.

       01  INPUT-TO-GEOSUPPORT.
           05  IN-BOR1            PIC X.
           05  FILLER             PIC X.
           05  IN-STREET1         PIC X(32).
           05  FILLER             PIC X.
```

```
            05  IN-BOR2             PIC X.
            05  FILLER              PIC X.
            05  IN-STREET2          PIC X(32).
            05  FILLER              PIC X(11).

          FD  RPT-FILE
              RECORDING MODE IS F
              RECORD CONTAINS 132 CHARACTERS
              LABEL RECORDS ARE OMITTED.

        01  RPT-LINE                PIC X(132).

        WORKING-STORAGE SECTION.

77  I                       PIC 9 VALUE 0.

      ****************************************************************
      *** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE ***
      *** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                  ***
      ****************************************************************
        01  WORK1.    COPY  W1COB.
        01  WORK2.    COPY  W2COB.

      **** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT    *********

        01  RPT-DATA-LINE1.
            05  OUT-BOR1            PIC X.
            05  FILLER              PIC X         VALUE ' '.
            05  OUT-ST1             PIC X(32).
            05  FILLER              PIC X         VALUE ' '.
            05  OUT-BOR2            PIC X.
            05  FILLER              PIC X         VALUE ' '.
            05  OUT-ST2             PIC X(32).
            05  OUT-DETAIL.
              10  FILLER            PIC X         VALUE ' '.
              10  OUT-ZIP           PIC X(5).
              10  FILLER            PIC X         VALUE ' '.
              10  OUT-CD            PIC X(2).
              10  FILLER            PIC X         VALUE ' '.
              10  OUT-NYPD-PCT      PIC X(3).
              10  FILLER            PIC X(6)      VALUE ' '.
              10  OUT-SCHLDIST      PIC X(2).
              10  FILLER            PIC X(42)     VALUE ' '.

        01  RPT-DATA-LINE2.
```

```
        05  FILLER              PIC X(96)     VALUE ' '.
        05  OUT-ST              PIC X(32).
        05  FILLER              PIC X(4) VALUE ' '.

    01  RPT-ERR-LINE.
        05  FILLER              PIC X(15) VALUE '***** FUNCTION '.
        05  ERR-FUNCTION        PIC X.
        05  FILLER              PIC X(7)  VALUE ' GRC = '.
        05  ERR-GRC             PIC X(2).
        05  FILLER              PIC X(15) VALUE ' REASON CODE = '.
        05  ERR-REASON          PIC X.
        05  FILLER              PIC X(2)  VALUE '. '.
        05  OUT-ERR-MSG         PIC X(80).
        05  FILLER              PIC X(9) VALUE ' '.

    01  RPT-WRN-LINE.
        05  FILLER              PIC X(15) VALUE '***** FUNCTION '.
        05  WRN-FUNCTION        PIC X.
        05  FILLER              PIC X(15) VALUE ' WARNING GRC = '.
        05  WRN-GRC             PIC X(2).
        05  FILLER              PIC X(15) VALUE ' REASON CODE = '.
        05  WRN-REASON          PIC X.
        05  FILLER              PIC X(2)  VALUE '. '.
        05  OUT-WRN-MSG         PIC X(80).
        05  FILLER              PIC X    VALUE ' '.

    01  RPT-HEADER-1.
        05  FILLER              PIC X(40)  VALUE
        'SAMPLE COBOL PROGRAM \#2 EXECUTION OUTPUT'.
        05  FILLER              PIC X(72) VALUE ' '.

  01  RPT-HEADER-2.
        05  FILLER              PIC X(58)  VALUE
        '*****----------------- INPUT INTERSECTION ----------------'.
        05  FILLER              PIC X(58)  VALUE
        '------***** *****------------ SELECTED OUTPUT ITEMS ------'.
        05  FILLER              PIC X(16)  VALUE
        '-------*****'.

    01  RPT-HEADER-3.
        05  FILLER              PIC X(58)  VALUE
        'B IN-STREET-NAME-1                 B IN-STREET-NAME-2     '.
        05  FILLER              PIC X(58)  VALUE
        '              ZIP CD NYPD-PCT SCHLDST INTERSECTING STREET '.
        05  FILLER              PIC X(16)  VALUE
```

```
    'NAMES           '.

 01  RPT-HEADER-4.
     05  FILLER              PIC X(58)  VALUE
     '_ ________________________________ _ ____________________'.
     05  FILLER              PIC X(58)  VALUE
     '___________ _____ __ ________ _______ ____________________'.
     05  FILLER              PIC X(16)  VALUE
     '____________    '.

 01  FLAGS.
     05 DATA-FLAG    PIC XXX   VALUE 'YES'.
       88 MORE-DATA            VALUE 'YES'.
       88 NO-DATA              VALUE 'NO '.

****************************************

 PROCEDURE DIVISION.

     OPEN INPUT IN-FILE, OUTPUT RPT-FILE.
     WRITE RPT-LINE FROM RPT-HEADER-1 AFTER ADVANCING 1 LINES.
     WRITE RPT-LINE FROM RPT-HEADER-2 AFTER ADVANCING 2 LINES.
     WRITE RPT-LINE FROM RPT-HEADER-3 AFTER ADVANCING 2 LINES.
     WRITE RPT-LINE FROM RPT-HEADER-4 AFTER ADVANCING 0 LINES.
     READ IN-FILE AT END MOVE 'NO ' TO DATA-FLAG.
     PERFORM PROCESS THRU PROCESS-EX
         UNTIL NO-DATA.
     CLOSE IN-FILE, RPT-FILE.
     MOVE 0 TO RETURN-CODE
     STOP RUN.

 PROCESS.




*******************************************************************
\* TO MAKE A FUNCTION 2 CALL:                                      *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                           *
\*   (2) SET WA1'S FUNCTION-CODE TO 2                              *
\*   (3) MOVE THE 1ST INPUT BORO TO WA1'S INPUT BORO CODE FIELD    *
\*   (4) MOVE THE 1ST INPUT STREET TO WA1'S INPUT STREET NAME      *
\*       FIELD                                                     *
\*   (5) MOVE THE 2ND INPUT BORO TO WA1'S INPUT BORO CODE 2 FIELD  *
\*   (6) MOVE THE 2ND INPUT STREET TO WA1'S INPUT STREET NAME 2    *
```

```
\*       FIELD                                                  *
\*   (7) CALL GBI WITH 2 WORKAREAS                              *
\*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS              *
*****************************************************************
     MOVE SPACES TO WORK1.
     MOVE '2 ' TO GEO-WA1-IN-FUNCTION-CODE.
   MOVE IN-BOR1 TO GEO-WA1-IN-BORO   OUT-BOR1.
     MOVE IN-BOR2 TO GEO-WA1-IN-BORO-2 OUT-BOR2.
     MOVE IN-STREET1 TO GEO-WA1-IN-STREET-1 OUT-ST1.
  MOVE IN-STREET2 TO GEO-WA1-IN-STREET-2 OUT-ST2.
     CALL 'GBI' USING WORK1 WORK2.

     IF GEO-WA1-OUT-RETURN-CODE NOT = 00
        MOVE '2' TO ERR-FUNCTION WRN-FUNCTION
        PERFORM PRINT-ERROR-LINE THRU P-E-EX.

     IF (GEO-WA1-OUT-RETURN-CODE = 00) OR
       (GEO-WA1-OUT-RETURN-CODE = 01)
        PERFORM SUCCESSFUL-FUNC2 THRU S-F2-EX
     ELSE
       MOVE SPACES TO OUT-DETAIL
       WRITE RPT-LINE FROM RPT-DATA-LINE1 AFTER ADVANCING 1 LINES.

     READ IN-FILE AT END MOVE 'NO ' TO DATA-FLAG.

 PROCESS-EX.
     EXIT.

 SUCCESSFUL-FUNC2.

*************************************************************
***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ***********
***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS          *****
*************************************************************
     MOVE GEO-WA2-FN2-ZIP            TO OUT-ZIP.
     MOVE GEO-WA2-FN2-COMDIST-NUMBER TO OUT-CD.
     MOVE GEO-WA2-FN2-POL-PRECINCT   TO OUT-NYPD-PCT.
     MOVE GEO-WA2-FN2-SCHOOLDIST     TO OUT-SCHLDIST.
\* PROCESS CROSS STREET** CHECK FOR AT LEAST 1.
     WRITE RPT-LINE FROM RPT-DATA-LINE1 AFTER ADVANCING 2 LINES.

     PERFORM CALL-D THRU CALL-D-EX
        VARYING I FROM 1 BY 1 UNTIL
            (I > GEO-WA2-FN2-NUM-OF-INTERSECTS).
```

```
   S-F2-EX.
       EXIT.

   CALL-D.

  *******************************************************
  \* TO GET STREET NAMES FOR INTERSECTING STREET CODES   *
  \* MAKE A FUNCTION D CALL:                             *
  \*   (1) INITIALIZE WORKAREA 1 TO SPACES               *
  \*   (2) SET THE WA1'S FUNCTION CODE FIELD TO D        *
  \*   (3) USE THE COMPACT STREET NAMES OPTION TO OBTAIN *
  \*       STREET NAMES FORMATTED FOR DISPLAY            *
  \*   (4) MOVE THE PACKED BORO AND STREET CODE TO       *
  \*       WA1'S INPUT STREET CODE 1 FIELD               *
  \*   (5) CALL GBI WITH 1 WORKAREA                      *
  \*   (6) CHECK RETURN CODES FOR ERRORS OR WARNINGS     *
  *******************************************************
       MOVE SPACES TO WORK1.
       MOVE 'D ' TO GEO-WA1-IN-FUNCTION-CODE.
       MOVE 'C' TO GEO-WA1-IN-COMPACT-NAME-FLAG.
       MOVE '25' TO GEO-WA1-IN-SNL.
       MOVE GEO-WA2-FN2-INTERSECT-PBSC (I)
           TO GEO-WA1-IN-STREETCODE-1

 CALL 'GBI' USING WORK1.

       IF GEO-WA1-OUT-RETURN-CODE NOT = 00
          MOVE 'D' TO ERR-FUNCTION WRN-FUNCTION
          PERFORM PRINT-ERROR-LINE THRU P-E-EX.

IF (GEO-WA1-OUT-RETURN-CODE = 00) OR
          (GEO-WA1-OUT-RETURN-CODE = 01)
          PERFORM SUCCESSFUL-FUNCD THRU S-FD-EX.

   CALL-D-EX.
       EXIT.

   SUCCESSFUL-FUNCD.

         MOVE GEO-WA1-OUT-STREET-1 TO OUT-ST
         IF I = 1
         WRITE RPT-LINE FROM RPT-DATA-LINE2 AFTER ADVANCING 0 LINES
         ELSE
         WRITE RPT-LINE FROM RPT-DATA-LINE2 AFTER ADVANCING 1 LINES.
```

```
       S-FD-EX.
           EXIT.


       PRINT-ERROR-LINE.
           MOVE GEO-WA1-OUT-RETURN-CODE TO ERR-GRC WRN-GRC.
           MOVE GEO-WA1-OUT-REASON-CODE TO ERR-REASON WRN-REASON.
           MOVE GEO-WA1-OUT-ERROR-MESSAGE TO OUT-ERR-MSG OUT-WRN-MSG.

           IF GEO-WA1-OUT-RETURN-CODE = 01
      **** INSERT YOUR OWN WARNING ROUTINE HERE  ****
             WRITE RPT-LINE FROM RPT-WRN-LINE AFTER ADVANCING 2 LINES
           ELSE
      **** INSERT YOUR OWN WARNING ROUTINE HERE  ****
             WRITE RPT-LINE FROM RPT-ERR-LINE AFTER ADVANCING 2 LINES.

       P-E-EX.
           EXIT.
/*
//LKED.SYSIN DD *
  INCLUDE INCLIB(GBI)
//LKED.INCLIB   DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************//
//*                                                               \*//
//*  AS OF GEOSUPPPORT VERSION 10.0,                              \*//
//*  THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP     \*//
//*  MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:        \*//
//*       A030.GEO.SUPPORT.PDSE.LOADLIB                           \*//
//*       A030.GEO.SUPPORT.LOADLIB                                \*//
//*                                                               \*//
//*****************************************************************//
//GO.STEPLIB DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//           DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//*****************************************************************//
//*                                                               \*//
//*  AS OF GEOSUPPPORT VERSION 10.0,                              \*//
//*  DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD, ETC) \*//
//*  ARE NO LONGER NEEDED AND ARE IGNORED.  GEOSUPPORT IS TAILORED \*//
//*  TO USE STANDARD GEOSUPPORT DATA SET NAMES.                   \*//
//*  TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.      \*//
/*                                                              \*//
//*****************************************************************//
//*
//GO.SYSUDUMP DD SYSOUT=A,OUTLIM=3000
```

```
//GO.SYSOUT   DD SYSOUT=A
//GO.RPTFILE  DD SYSOUT=A
//GO.INFILE  DD *
1 CHAMBERS ST                      1 HUDSON ST
1 SIXTH AVE                        1 W. 8 ST
1 DUANE ST                         1 READE ST
/*
//
```

COBOL SAMPLE PROGRAM #2- Job Stream- COW

```
//COBC2SRC JOB   YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//***  COBOL SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM #2  ****
//***                     COW FORMAT                              ****
//*******************************************************************
//STEP1 EXEC   IGYWCLG,PARM.COBOL=(NOWORD,OPTIMIZE)
//COBOL.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//             DD DSN=A030.GEO.COPYLIB,DISP=SHR
//COBOL.SYSIN  DD *
      ******************************************************************
      * THIS PROGRAM MAKES FUNCTION 2 AND D CALLS TO GEOSUPPORT USING *
      * TWO BOROS AND TWO STREET NAMES SUPPLIED BY AN INSTREAM FILE.  *
      * FUNCTION 2 RETURNS GEOGRAPHIC INFORMATION FOR AN INTERSECTION.*
      * FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  *
      * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
      *       NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE   *
      *             ORIGINAL CALL TO FUNCTION 2, ALL THE CROSS STREET *
      *             NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 2.     *
      ******************************************************************
      *
       IDENTIFICATION DIVISION.
         PROGRAM-ID. COBS1JOB.

      ****************************************

       ENVIRONMENT DIVISION.
         INPUT-OUTPUT SECTION.
         FILE-CONTROL.
           SELECT IN-FILE ASSIGN TO INFILE.
           SELECT RPT-FILE ASSIGN TO RPTFILE.

      ****************************************
```

```
 DATA DIVISION.
   FILE SECTION.

**** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DEFINTION *****
   FD  IN-FILE
       RECORDING MODE IS F
       RECORD CONTAINS 80 CHARACTERS
       LABEL RECORDS ARE OMITTED.

 01  INPUT-TO-GEOSUPPORT.
     05  IN-BOR1             PIC X.
     05  FILLER              PIC X.
     05  IN-STREET1          PIC X(32).
     05  FILLER              PIC X.
     05  IN-BOR2             PIC X.
     05  FILLER              PIC X.
     05  IN-STREET2          PIC X(32).
     05  FILLER              PIC X(11).

   FD  RPT-FILE
       RECORDING MODE IS F
       RECORD CONTAINS 132 CHARACTERS
       LABEL RECORDS ARE OMITTED.

 01  RPT-LINE                PIC X(132).

 WORKING-STORAGE SECTION.

 77  I                       PIC 9 VALUE 0.

*****************************************************************
*** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE ***
*** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                   ***
*****************************************************************
 01  WORK1.    COPY  P1COB.
 01  WORK2.    COPY  P2COB.

**** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT    *********

 01  RPT-DATA-LINE1.
     05  OUT-BOR1            PIC X.
     05  FILLER              PIC X         VALUE ' '.
     05  OUT-ST1             PIC X(32).
     05  FILLER              PIC X         VALUE ' '.
     05  OUT-BOR2            PIC X.
```

```
    05  FILLER              PIC X         VALUE ' '.
    05  OUT-ST2             PIC X(32).
    05  OUT-DETAIL.
      10  FILLER            PIC X         VALUE ' '.
      10  OUT-ZIP           PIC X(5).
      10  FILLER            PIC X         VALUE ' '.
      10  OUT-CD            PIC X(2).
      10  FILLER            PIC X         VALUE ' '.
      10  OUT-NYPD-PCT      PIC X(3).
      10  FILLER            PIC X(6)      VALUE ' '.
      10  OUT-SCHLDIST      PIC X(2).
      10  FILLER            PIC X(42)     VALUE ' '.

01  RPT-DATA-LINE2.
    05  FILLER              PIC X(96)     VALUE ' '.
    05  OUT-ST              PIC X(32).
    05  FILLER              PIC X(4) VALUE ' '.

01  RPT-ERR-LINE.
    05  FILLER              PIC X(15) VALUE '***** FUNCTION '.
    05  ERR-FUNCTION        PIC X.
    05  FILLER              PIC X(7)  VALUE ' GRC = '.
    05  ERR-GRC             PIC X(2).
    05  FILLER              PIC X(15) VALUE ' REASON CODE = '.
    05  ERR-REASON          PIC X.
    05  FILLER              PIC X(2)  VALUE '. '.
    05  OUT-ERR-MSG         PIC X(80).
    05  FILLER              PIC X(9) VALUE ' '.

01  RPT-WRN-LINE.
    05  FILLER              PIC X(15) VALUE '***** FUNCTION '.
    05  WRN-FUNCTION        PIC X.
    05  FILLER              PIC X(15) VALUE ' WARNING GRC = '.
    05  WRN-GRC             PIC X(2).
    05  FILLER              PIC X(15) VALUE ' REASON CODE = '.
    05  WRN-REASON          PIC X.
    05  FILLER              PIC X(2)  VALUE '. '.
    05  OUT-WRN-MSG         PIC X(80).
    05  FILLER              PIC X    VALUE ' '.

01  RPT-HEADER-1.
    05  FILLER              PIC X(40)  VALUE
    'SAMPLE COBOL PROGRAM #2 EXECUTION OUTPUT'.
    05  FILLER              PIC X(72) VALUE ' '.
```

```
 01  RPT-HEADER-2.
     05  FILLER              PIC X(58)  VALUE
     '*****----------------- INPUT INTERSECTION ----------------'.
     05  FILLER              PIC X(58)  VALUE
     '------***** *****------------ SELECTED OUTPUT ITEMS ------'.
     05  FILLER              PIC X(16)  VALUE
     '-------*****'.

 01  RPT-HEADER-3.
     05  FILLER              PIC X(58)  VALUE
     'B IN-STREET-NAME-1                 B IN-STREET-NAME-2     '.
     05  FILLER              PIC X(58)  VALUE
     '              ZIP CD NYPD-PCT SCHLDST INTERSECTING STREET '.
     05  FILLER              PIC X(16)  VALUE
     'NAMES           '.

 01  RPT-HEADER-4.
     05  FILLER              PIC X(58)  VALUE
     '_ ________________________________ _ ____________________'.
     05  FILLER              PIC X(58)  VALUE
     '___________ _____ __ ________ _______ ___________________'.
     05  FILLER              PIC X(16)  VALUE
     '____________    '.

 01  FLAGS.
     05 DATA-FLAG    PIC XXX   VALUE 'YES'.
       88 MORE-DATA            VALUE 'YES'.
       88 NO-DATA              VALUE 'NO '.

****************************************

 PROCEDURE DIVISION.

     OPEN INPUT IN-FILE, OUTPUT RPT-FILE.
     WRITE RPT-LINE FROM RPT-HEADER-1 AFTER ADVANCING 1 LINES.
     WRITE RPT-LINE FROM RPT-HEADER-2 AFTER ADVANCING 2 LINES.
     WRITE RPT-LINE FROM RPT-HEADER-3 AFTER ADVANCING 2 LINES.
     WRITE RPT-LINE FROM RPT-HEADER-4 AFTER ADVANCING 0 LINES.
     READ IN-FILE AT END MOVE 'NO ' TO DATA-FLAG.
     PERFORM PROCESS THRU PROCESS-EX
         UNTIL NO-DATA.
     CLOSE IN-FILE, RPT-FILE.
     MOVE 0 TO RETURN-CODE
     STOP RUN.
```

```
 PROCESS.




*****************************************************************
* TO MAKE A FUNCTION 2 CALL:                                    *
*   (1) INITIALIZE WORKAREA 1 TO SPACES                         *
*   (2) SET WA1'S FUNCTION-CODE TO 2                            *
*   (3) SET THE PLATFORM INDICATOR SWITCH (NON-IBM-MAINFRAME)   *
*       TO USE CHARACTER-ONLY WORK AREAS (COWS)                 *
*   (4) MOVE THE 1ST INPUT BORO TO WA1'S INPUT BORO CODE FIELD  *
*   (5) MOVE THE 1ST INPUT STREET TO WA1'S INPUT STREET NAME    *
*       FIELD                                                   *
*   (6) MOVE THE 2ND INPUT BORO TO WA1'S INPUT BORO CODE 2 FIELD *
*   (7) MOVE THE 2ND INPUT STREET TO WA1'S INPUT STREET NAME 2  *
*       FIELD                                                   *
*   (8) CALL GBI WITH 2 WORKAREAS                               *
*   (9) CHECK RETURN CODES FOR ERRORS OR WARNINGS               *
*****************************************************************
     MOVE SPACES TO WORK1.
     MOVE '2 ' TO PIWA1-IN-FUNC-CODE.
     MOVE 'C' TO GEO-WA1-IN-NON-IBM-MAIN-FRAME.
     MOVE IN-BOR1 TO GEO-WA1-IN-BORO   OUT-BOR1.
     MOVE IN-BOR2 TO GEO-WA1-IN-BORO-2 OUT-BOR2.
     MOVE IN-STREET1 TO GEO-WA1-IN-STREET-1 OUT-ST1.
     MOVE IN-STREET2 TO GEO-WA1-IN-STREET-2 OUT-ST2.
     CALL 'GBI' USING WORK1 WORK2.

     IF GEO-WA1-OUT-RETURN-CODE NOT = 00
        MOVE '2' TO ERR-FUNCTION WRN-FUNCTION
        PERFORM PRINT-ERROR-LINE THRU P-E-EX.

     IF (GEO-WA1-OUT-RETURN-CODE = 00) OR
       (GEO-WA1-OUT-RETURN-CODE = 01)
        PERFORM SUCCESSFUL-FUNC2 THRU S-F2-EX
     ELSE
       MOVE SPACES TO OUT-DETAIL
       WRITE RPT-LINE FROM RPT-DATA-LINE1 AFTER ADVANCING 1 LINES.

     READ IN-FILE AT END MOVE 'NO ' TO DATA-FLAG.

 PROCESS-EX.
     EXIT.
```

```
 SUCCESSFUL-FUNC2.

*********************************************************
***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ***********
***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS          *****
*********************************************************
     MOVE GEO-WA2-FN2-ZIP            TO OUT-ZIP.
     MOVE GEO-WA2-FN2-COMDIST-NUMBER TO OUT-CD.
     MOVE GEO-WA2-FN2-POL-PRECINCT   TO OUT-NYPD-PCT.
     MOVE GEO-WA2-FN2-SCHOOLDIST     TO OUT-SCHLDIST.
* PROCESS CROSS STREET** CHECK FOR AT LEAST 1.
     WRITE RPT-LINE FROM RPT-DATA-LINE1 AFTER ADVANCING 2 LINES.

     PERFORM CALL-D THRU CALL-D-EX
        VARYING I FROM 1 BY 1 UNTIL
            (I > GEO-WA2-FN2-NUM-OF-INTERSECTS).

 S-F2-EX.
     EXIT.

 CALL-D.

*****************************************************************
* TO GET STREET NAMES FOR INTERSECTING STREET CODES             *
* MAKE A FUNCTION D CALL:                                       *
*   (1) INITIALIZE WORKAREA 1 TO SPACES                         *
*   (2) SET THE WA1'S FUNCTION CODE FIELD TO D                  *
*   (3) SET THE PLATFORM INDICATOR SWITCH (NON-IBM-MAINFRAME)   *
*       TO USE CHARACTER-ONLY WORK AREAS (COWS)                 *
*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN           *
*       STREET NAMES FORMATTED FOR DISPLAY                      *
*   (5) MOVE THE BORO AND STREET CODE                           *
*       WA1'S INPUT STREET CODE 1 FIELD                         *
*   (6) CALL GBI WITH 1 WORKAREA                                *
*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS               *
*****************************************************************
     MOVE SPACES TO WORK1.
MOVE 'D ' TO PIWA1-IN-FUNC-CODE.
     MOVE 'C' TO GEO-WA1-IN-NON-IBM-MAIN-FRAME.
     MOVE 'C' TO GEO-WA1-IN-COMPACT-NAME-FLAG.
     MOVE '25' TO GEO-WA1-IN-SNL.
     MOVE PIWA2-FN2-INTERSECT-B5SC (I)
         TO GEO-WA1-IN-10SC-1
     CALL 'GBI' USING WORK1.
```

```
           IF GEO-WA1-OUT-RETURN-CODE NOT = 00
              MOVE 'D' TO ERR-FUNCTION WRN-FUNCTION
              PERFORM PRINT-ERROR-LINE THRU P-E-EX.

           IF (GEO-WA1-OUT-RETURN-CODE = 00) OR
              (GEO-WA1-OUT-RETURN-CODE = 01)
              PERFORM SUCCESSFUL-FUNCD THRU S-FD-EX.

       CALL-D-EX.
           EXIT.

       SUCCESSFUL-FUNCD.

             MOVE GEO-WA1-OUT-STREET-1 TO OUT-ST
             IF I = 1
             WRITE RPT-LINE FROM RPT-DATA-LINE2 AFTER ADVANCING 0 LINES
             ELSE
             WRITE RPT-LINE FROM RPT-DATA-LINE2 AFTER ADVANCING 1 LINES.

       S-FD-EX.
           EXIT.


       PRINT-ERROR-LINE.
           MOVE GEO-WA1-OUT-RETURN-CODE TO ERR-GRC WRN-GRC.
           MOVE GEO-WA1-OUT-REASON-CODE TO ERR-REASON WRN-REASON.
           MOVE GEO-WA1-OUT-ERROR-MESSAGE TO OUT-ERR-MSG OUT-WRN-MSG.

           IF GEO-WA1-OUT-RETURN-CODE = 01
      **** INSERT YOUR OWN WARNING ROUTINE HERE  ****
             WRITE RPT-LINE FROM RPT-WRN-LINE AFTER ADVANCING 2 LINES
           ELSE
      **** INSERT YOUR OWN WARNING ROUTINE HERE  ****
             WRITE RPT-LINE FROM RPT-ERR-LINE AFTER ADVANCING 2 LINES.

       P-E-EX.
           EXIT.
/*
//LKED.SYSIN DD *
  INCLUDE INCLIB(GBI)
//LKED.INCLIB   DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************//
//*                                                               *//
//*  AS OF GEOSUPPPORT VERSION 10.0,                              *//
//*  THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP     *//
```

```
//*  MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:         *//
//*       A030.GEO.SUPPORT.PDSE.LOADLIB                            *//
//*       A030.GEO.SUPPORT.LOADLIB                                 *//
//*                                                                *//
//******************************************************************//
//GO.STEPLIB DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//           DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//******************************************************************//
//*                                                                *//
//*  AS OF GEOSUPPPORT VERSION 10.0,                               *//
//*  DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD, ETC) *//
//*  ARE NO LONGER NEEDED AND ARE IGNORED.  GEOSUPPORT IS TAILORED *//
//*  TO USE STANDARD GEOSUPPORT DATA SET NAMES.                    *//
//*  TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.       *//
//*                                                                *//
//******************************************************************//
//*
//GO.SYSUDUMP DD SYSOUT=A,OUTLIM=3000
//GO.SYSOUT   DD SYSOUT=A
//GO.RPTFILE  DD SYSOUT=A
//GO.INFILE  DD *
1 CHAMBERS ST                      1 HUDSON ST
1 SIXTH AVE                        1 W. 8 ST

1 DUANE ST                         1 READE ST
/*
//
```

SAMPLE COBOL PROGRAM #2 EXECUTION OUTPUT

```
        *****---------------- INPUT INTERSECTION ----------------------***** *****------------
SELECTED OUTPUT ITEMS ---*****

         B IN-STREET-NAME-1                B IN-STREET-NAME-2                  ZIP CD NYPD-
PCT SCHLDST INTERSECTING STREET NM
         - ------------------------------- - ------------------------------- ----- -- -------
- ------- ----------------------

         1 CHAMBERS ST                     1 HUDSON ST                       10007 01 001
02      CHAMBERS STREET

HUDSON STREET

WEST BROADWAY

         1 SIXTH AVE                       1 W. 8 ST                         10014 02 006
02      6 AVENUE

GREENWICH AVENUE

WEST 8 STREET

         ***** FUNCTION 2 GRC = 62 REASON CODE =  . READE STREET & DUANE STREET DO NOT
INTERSECT
         1 DUANE ST                        1 READE ST
```

ASSEMBLER SAMPLE PROGRAM #1

- Input Job Stream - MSW

- Input Job Stream - COW

- Output Report

ASSEMBLER SAMPLE PROGRAM #1 –Job Stream-MSW

```
//ASMF1SRC JOB   YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//**  ASSEMBLER SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1 **
//**                        MSW FORMAT                             **
//*******************************************************************
//STEP1  EXEC  ASMACLG,
//         PARM.ASM='OBJECT,NODECK',
//         PARM.LKED='XREF,LET,LIST,NCAL'
```

```
//ASM.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//           DD DSN=A030.GEO.COPYLIB,DISP=SHR
//           DD DSN=SYS1.MACLIB,DISP=SHR
//ASM.SYSIN  DD *
ASMF1SRC TITLE 'SAMPLE GEOSUPPORT ASSEMBLER PROGRAM 1 - MSW FORMAT'
ASMF1SRC CSECT
*****************************************************************
\* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING *
\* BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.*
\* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     *
\* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  *
\* - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - *
\* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE         *
\*       ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET NAMES *
\*       WOULD HAVE BEEN RETURNED BY FUNCTION 1.                 *
*****************************************************************
*
*************************************************************************
\*                                                                      *
\*  This program will do the following:                                 *
\*                                                                      *
\*     * Read an instream record containing a house number,            *
\*       street name, and borough code                                  *
\*                                                                      *
\*     * Build Work Area 1 for a Function 1 call                        *
\*                                                                      *
\*     * Call Function 1                                                *
\*                                                                      *
\*     * Get ZIP code, community district, police precinct, school     *
\*       district, and lists of street codes of streets intersecting   *
\*       at the low and high ends of the input street address's block. *
\*       These will be displayed along with the input address which    *
\*       consists of borough code, house number, and street name.      *
\*                                                                      *
\*     * Call Function D to get the street names of the first          *
\*       intersecting street on both low and high ends.                *
\*                                                                      *
\*     * Print the information                                          *
\*                                                                      *
\* NOTE that after each Geosupport call, the Return Code is checked.   *
\*      If it is greater than 01, an error message is printed, and     *
\*      the next input record, if any, is read.                        *
\*      If it is 01, a warning message is printed, the input record is *
\*      processed, and the next record is read.                        *
\*      If it is zero, the input record is processed, and the next     *
```

```
\*      record is read.                                          *
\*                                                               *
*****************************************************************
         SPACE
  STM   R14,R12,12(R13)   Save caller's registers
         LR    R3,R15
         LA    R12,4095(,R3)     (second base register
         LA    R12,1(,R12)        to accomodate Work Areas 1 and 2)
   USING ASMF1SRC,R3,R12
\* Chain save areas
         LA    R4,MYSAVE
         ST    R13,4(,R4)    Save caller's savearea address
         ST    R4,8(,R13)    Save pgm's savearea adr in caller savearea
         LR    R13,R4        Ensure that R13 points to pgm's savearea
         SPACE 2
         XR    R15,R15                 (set OS return code to zero)
\* Open input and output files
         OPEN  (INFILE,,OUTFILE,(OUTPUT))
         TM    INFILE+48,X'10'   Did input file open successfully?
         BNO   INOPNERR             (no..)
         TM    OUTFILE+48,X'10'  Did output file open successfully?
         BNO   OUTOPNER             (no..)
\* Print page and report header lines
         SPACE
         PUT   OUTFILE,HDR1
         PUT   OUTFILE,HDR2
         PUT   OUTFILE,HDR3
         PUT   OUTFILE,HDR4
         B     NEXTREC
         SPACE 2
         TITLE 'READ IN-STREAM INPUT AND PREPARE FUNCTION 1 CALL'
\* Read (next) input record
NEXTREC  DS    0H
         GET   INFILE,INREC
\* Move input data to output record for display
         MVC   DBORO,INBORO                   borough code
         MVC   DHSE(L'W1IHSE#),INHOUSE        house number
         MVC   DSTRT,INSTREET                 street name
         SPACE
*****************************************************************
\* TO MAKE A FUNCTION 1 CALL:                                    *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                         *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                      *
\*   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD      *
\*   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER *
```

```
\*       FIELD                                                  *
\*   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  *
\*   (6) CALL GBI WITH 2 WORKAREAS                               *
\*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS               *
*****************************************************************
 \* Clear WA1 to blanks
         LA    R8,W1BAL    "To" address for MVCL
         LA    R9,W1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
\* and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         SPACE
\* Prime Work Area 1 for Function 1 call

         MVC   W1IFUNC,=CL2'1 '              Get function code
         MVC   W1IBORO1,INBORO                   borough code
         MVC   W1IHSE#(L'W1IHSE#),INHOUSE        house number
         MVC   W1ISTRT1,INSTREET                 street name
         MVC   W1ISNL(L'W1ISNL),=C'25'    Normalized street name length

** * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
\*                                                                    *
\*        As of Geosupport Version 10.1,                              *
\*        to receive roadbed-specific information,                    *
\*        set the Roadbed Request Switch to 'R', as follows:          *
\*        MVC   W1IRBRQS,C'R'                                         *
\*                                                                    *
\* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
*
\* Call Function 1 (2-Work-Area call)
         CALL  GBI,(W1BAL,W2BAL),VL
\* Check Return code
         CLC   W1ORC(2),=C'00'         Good return?
         BE    PROCESS                     Yes, process returned data
\* Handle errors and warnings
ERREXIT  DS    0H
         CLC   W1ORC(2),=C'01'         Warning condition?
         BE    PUTWARN                    Yes, process warning
\*                                              and then process input;
\*                                          otherwise, process error
         MVC   ERINPUT,DSPLYIN    Boro code, hse no., street name
         MVC   ERFUNC,W1IFUNC              function code
```

```
         MVC   ERRET(L'W1ORC),W1ORC        return code
         MVC   ERREAS(L'W1OREASN),W1OREASN reason code
         PUT   OUTFILE,ERR1            Print error messages 1
         B     PUTMSG                                  and 2
PUTWARN  DS    0H
         MVC   WRINPUT,DSPLYIN    Boro code, hse no., street name
         MVC   WRFUNC,W1IFUNC              function code
         MVC   WRRET(L'W1ORC),W1ORC        return code
         MVC   WRREAS(L'W1OREASN),W1OREASN reason code
         PUT   OUTFILE,WRN1            Print warning messages 1
PUTMSG   DS    0H                                        and 2
         MVC   ERRWRN(L'W1OERROR),W1OERROR
         PUT   OUTFILE,ERRWRN2         Print error/warning message 2
         CLC   W1ORC(2),=C'01'         Warning condition?
         BNE   NEXTREC                  No, get next record, if any
         MVI   OINPUT,C' '              Yes,
         MVC   OINPUT+1(L'OINPUT-1),OINPUT  ensure input NOT displayd
         MVI   OUTVALID,C' '     ensure single-spacing after warning
         B     GETZIP            and continue normal processing
         SPACE
\* Handle successful Geosupport calls (Return Code <= 01)
PROCESS  DS    0H
         MVC   OINPUT,DSPLYIN    Boro code, hse no., street name
         MVI   OUTVALID,C'0'     Ensure double-spacing
GETZIP   DS    0H
         MVC   OZIP,W2F1ZIP      ZIP code
         MVC   OCOMM,W2F1CDN     community district number
         MVC   OPCT,W2F1POP      police precinct
         MVC   OSCHL,W2F1SCH     school district
ASSEMBLER SAMPLE PROGRAM #1- Job stream- MSW (continue


***** At this point, clear WA1 again, call Function D, and move ******
***** its reported Low and High Instersecting Street Names to output *
         TITLE 'GET LOW, HIGH INTERSECTING STREETS, USING FUNCTION D'
         SPACE 2
*************************************************************
\* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND   *
\* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE     *
\* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS      *
\* FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D:  *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                     *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO D                  *
\*   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED       *
\*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE      *
```

```
\*              HAS SPACE FOR ONLY 25 CHARACTERS)            *
\*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN       *
\*       STREET NAMES FORMATTED FOR DISPLAY                  *
\*   (5) MOVE WA2'S LOW PBSC FIELD TO WA1'S INPUT STREET     *
\*       CODE 1 FIELD                                        *
\*   (6) MOVE WA2'S HIGH PBSC FIELD TO WA1'S INPUT STREET    *
\*       CODE 2 FIELD                                        *
\*   (7) CALL GBI WITH 1 WORKAREA                            *
\*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS           *
*************************************************************
         SPACE
\* Clear WA1 to blanks
         LA    R8,W1BAL    "To" address for MVCL
         LA    R9,W1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
\* and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         MVC   W1ICDE1,W2F1CDEL
         MVC   W1ICDE2,W2F1CDEH
         MVC   W1IFUNC(2),=CL2'D '
   MVC   W1ISNL(L'W1ISNL),=C'25'    normalized street name length
         MVI   W1ICMPCT,C'C'              streets to be compacted
         CALL  GBI,W1BAL,VL   Call Function D
\* Check Return code
         CLC   W1ORC(2),=C'00'         Good return?
         BNE   ERREXIT                     No, error or warning
\*                                          Yes, complete the record
\*                                               and write it out
PUTREC   DS    0H
         MVC   OLOSTRT,W1OSTRT1
         MVC   OHISTRT,W1OSTRT2
\* Print an output record and get the next input record, if any
         PUT   OUTFILE,OUTVALID
         B     NEXTREC
EXIT     DS    0H
OUTOPNER DS    0H
         CLOSE (INFILE)
         TM    OUTFILE+48,X'10'   Did OUTFILE open successfully?
         BNO   INOPNERR              No, bypass closing it
         CLOSE (OUTFILE)
ASSEMBLER SAMPLE PROGRAM #1- Job stream- MSW (continue)
```

```
INOPNERR DS    0H
         L     R13,4(,R13)
         L     R14,12(,R13)
         LM    R0,R12,20(R13)
         BR    R14
         SPACE 2
PARAMERR DS    0H       parameter error, missing or invalid
         LA    R15,8    rc=8
         B     EXIT
         TITLE 'DATA SECTION - REGISTER ASSIGNMENTS'
R0       EQU   0
R1       EQU   1
R2       EQU   2
R3       EQU   3
R4       EQU   4
R5       EQU   5
R6       EQU   6
R7       EQU   7
R8       EQU   8
R9       EQU   9
R10      EQU   10
R11      EQU   11
R12      EQU   12
R13      EQU   13
R14      EQU   14
R15      EQU   15
         TITLE 'FILE AND RECORD DEFINITIONS'
         PUSH  PRINT
         PRINT NOGEN
INFILE   DCB   DSORG=PS,MACRF=(GM),DDNAME=INFILE,                    *
               RECFM=FB,LRECL=80,BLKSIZE=400,EODAD=EXIT
         SPACE
OUTFILE  DCB   DSORG=PS,MACRF=(PM),DDNAME=SYSPRINT,                  *
               RECFM=FBA,LRECL=133,BLKSIZE=1330
*
         POP PRINT
         SPACE
INREC    DS    0CL80              Input record
INBORO   DS    CL1                    Borough code
INHOUSE  DS    CL12                   House number
INSTREET DS    CL32                   Street name
         DC    35C' '                 filler
         SPACE
\* Output records: error, warning, and normal
ERR1     DS    0CL133
```

```
         DC    C'0'
ERINPUT  DS    CL48
         DC    C'*** FUNCTION '
ERFUNC   DS    CL2
         DC    C' GRC = '
ERRET    DS    CL2
         DC    C' REASON CODE = '
ERREAS   DS    CL1
         DC    CL(133-89)' '
         SPACE
WRN1     DS    0CL133
         DC    C'0'
WRINPUT  DS    CL48
         DC    C'*** FUNCTION '
WRFUNC   DS    CL2
         DC    C' WARNING, GRC = '
WRRET    DS    CL2
         DC    C' REASON CODE = '
WRREAS   DS    CL1
         DC    CL(133-98)' '
         SPACE
ERRWRN2  DS    0CL133
         DC    C' '
         DC    48C' '          Boro Code, House Number, Street Name
         DC    CL4'*** '
ERRWRN   DS    CL80            Error/Warning message
         SPACE
HDR1     DC    CL133'1SAMPLE ASSEMBLER \#1 EXECUTION OUTPUT            *
                 '
HDR2     DC    CL133'0*****---------- INPUT ADDRESS ------------***** \*C
               ****--------------------- SELECTED OUTPUT ITEMS --------C
        ----------------------*****'
HDR3     DC    CL133'0B HOUSE NUMBER IN-STREET-NAME                    *
                ZIP CD NYPD-PCT SCHLDST LOW CROSS STREET          HIGH *
               CROSS STREET               '
HDR4     DC    CL133' - ------------ ------------------------------- -*
               ---- -- -------- ------- ------------------------- -----*
               ---------------------------'
OUTVALID DS    0CL133
\* Borough code, house number, and street name are from input record
         DC    C'0'
OINPUT   DS    CL48
OZIP     DS    CL5
         DC    C' '
OCOMM    DS    CL2
```

```
         DC    C' '
OPCT     DS    CL3
         DC    6C' '
OSCHL    DS    CL2
         DC    6C' '
OLOSTRT  DS    CL25  Normalized name of intersecting street at low end
         DC    C' '
OHISTRT  DS    CL25  Normalized name of intersecting street at high end
         DC    7C' '
         TITLE 'WORKING VARIABLES, VALUES, ETC.'
MYSAVE   DC    18F'0'
***********************************************************************
***** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     ***
***** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                      ***
***********************************************************************
         COPY  W1BAL              COPY WORK AREA 1
         EJECT
         COPY  W2BAL              COPY WORK AREA 2
         EJECT
         SPACE 2
DSPLYIN  DS    0CL48
DBORO    DS    CL1
         DC    C' '
DHSE     DS    CL12
         DC    C' '
DSTRT    DS    CL32
  DC    C' '
         SPACE 2
         TITLE 'CONSTANTS AND LITERAL POOL'
         SPACE 2
         LTORG
         END   ASMF1SRC
//LKED.SYSIN  DD  *
 INCLUDE INCLIB(GBI)
/*
//LKED.INCLIB   DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*                                                          \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                          \*//
//*  AS OF GEOSUPPORT VERSION 10.0,                          \*//
//*  THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP  \*//
//*  MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:     \*//
//*       A030.GEO.SUPPORT.PDSE.LOADLIB                      \*//
//*       A030.GEO.SUPPORT.LOADLIB                           \*//
//*                                                          \*//
```

```
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//GO.STEPLIB  DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//*           DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                               \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                              \*//
//*   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD,    \*//
//*   ETC) ARE NO LONGER NEEDED AND ARE IGNORED. GEOSUPPORT       \*//
//*   IS TAILORED TO USE STANDARD GEOSUPPORT DATA SET NAMES.      \*//
//*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER      \*//
//*                                                               \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*
//SYSUDUMP DD  SYSOUT=\*,OUTLIM=2000
//SYSPRINT DD  SYSOUT=*
//INFILE   DD  *
122          READE ST
1500         DUANE ST
12-4         BROADWAY
4165-100     BAISLEY BLVD
4165-1000    BAISLEY BLVD
/*
//
```

ASSEMBLER SAMPLE PROGRAM #1 –Job Stream-MSW

```
//ASMC1SRC JOB   YOUR-JOB-CARD-INFORMATION
//*
//*****************************************************************
//**  ASSEMBLER SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1 **
//**                        COW FORMAT                           **
//*****************************************************************
//STEP1  EXEC  ASMACLG,
//         PARM.ASM='OBJECT,NODECK',
//         PARM.LKED='XREF,LET,LIST,NCAL'
//ASM.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//           DD DSN=A030.GEO.COPYLIB,DISP=SHR
//           DD DSN=SYS1.MACLIB,DISP=SHR
//ASM.SYSIN  DD *
ASMC1SRC TITLE 'SAMPLE GEOSUPPORT ASSEMBLER PROGRAM 1 - COW FORMAT'
ASMC1SRC CSECT
*****************************************************************
\* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING *
\* BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.*
```

```
\* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     *
\* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  *
\* - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - *
\* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE         *
\*       ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET NAMES *
\*       WOULD HAVE BEEN RETURNED BY FUNCTION 1.                 *
*****************************************************************
*
*********************************************************************
\*                                                                   *
\*  This program will do the following:                              *
\*                                                                   *
\*     * Read an instream record containing a house number,          *
\*       street name, and borough code                               *
\*                                                                   *
\*     * Build Work Area 1 for a Function 1 call                     *
\*                                                                   *
\*     * Call Function 1                                             *
\*                                                                   *
\*     * Get ZIP code, community district, police precinct, school   *
\*       district, and lists of street codes of streets intersecting *
\*       at the low and high ends of the input street address's block. *
\*       These will be displayed along with the input address which  *
\*       consists of borough code, house number, and street name.    *
\*                                                                   *
\*     * Call Function D to get the street names of the first        *
\*       intersecting street on both low and high ends.              *
\*                                                                   *
\*     * Print the information                                       *
\*                                                                   *
\* NOTE that after each Geosupport call, the Return Code is checked. *
\*      If it is greater than 01, an error message is printed, and   *
\*      the next input record, if any, is read.                      *
\*      If it is 01, a warning message is printed, the input record is *
\*      processed, and the next record is read.                      *
\*      If it is zero, the input record is processed, and the next   *
\*      record is read.                                              *
\*                                                                   *
*********************************************************************
         SPACE
         STM   R14,R12,12(R13)   Save caller's registers
         LR    R3,R15
         LA    R12,4095(,R3)     (second base register
         LA    R12,1(,R12)        to accomodate Work Areas 1 and 2)
         USING ASMC1SRC,R3,R12
```

```
\* Chain save areas
         LA    R4,MYSAVE
         ST    R13,4(,R4)    Save caller's savearea address
         ST    R4,8(,R13)    Save pgm's savearea adr in caller savearea
         LR    R13,R4        Ensure that R13 points to pgm's savearea
         SPACE 2
         XR    R15,R15                 (set OS return code to zero)
\* Open input and output files
         OPEN  (INFILE,,OUTFILE,(OUTPUT))
         TM    INFILE+48,X'10'   Did input file open successfully?
         BNO   INOPNERR             (no..)
         TM    OUTFILE+48,X'10'  Did output file open successfully?
         BNO   OUTOPNER             (no..)
\* Print page and report header lines
         SPACE
         PUT   OUTFILE,HDR1
         PUT   OUTFILE,HDR2
         PUT   OUTFILE,HDR3
         PUT   OUTFILE,HDR4
         B     NEXTREC
         SPACE 2
         TITLE 'READ IN-STREAM INPUT AND PREPARE FUNCTION 1 CALL'
\* Read (next) input record
NEXTREC  DS    0H
         GET   INFILE,INREC
\* Move input data to output record for display
         MVC   DBORO,INBORO                  borough code
         MVC   DHSE(L'INHOUSE),INHOUSE       house number
         MVC   DSTRT,INSTREET                street name
         SPACE
*****************************************************************
\* TO MAKE A FUNCTION 1 CALL:                                    *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                         *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                      *
\*   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD      *
\*   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER *
\*       FIELD                                                   *
\*   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  *
\*   (6) CALL GBI WITH 2 WORKAREAS                               *
\*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS               *
*****************************************************************
\* Clear WA1 to blanks
         LA    R8,P1BAL    "To" address for MVCL
         LA    R9,P1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
```

```
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
\* and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         SPACE
\* Prime Work Area 1 for Function 1 call
         MVI   P1IPLIND,C'C'                Set Work Area Format to COW
         MVC   P1IFUNC,=CL2'1 '              Get function code
         MVC   P1IBORO1,INBORO                   borough code
*
\* Note COW - MSW: Display House # - P1IHSE# is a 16-byte field
\*                                   W1IHSE# is a 12-byte field
*
         MVC   P1IHSE#(L'INHOUSE),INHOUSE        house number
         MVC   P1ISTRT1,INSTREET                 street name
*

\* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
\*                                                                     *
\*        As of Geosupport Version 10.1,                               *
\*        to receive roadbed-specific information,                     *
\*        set the Roadbed Request Switch to 'R', as follows:           *
\*        MVC   P1IRBRQS,C'R'                                          *
\*                                                                     *
\* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
*
         MVC   P1ISNL(L'P1ISNL),=C'25'    Normalized street name length
\* Call Function 1 (2-Work-Area call)
         CALL  GBI,(P1BAL,P2BAL),VL
\* Check Return code
         CLC   P1ORC(2),=C'00'         Good return?
         BE    PROCESS                     Yes, process returned data
\* Handle errors and warnings
ERREXIT  DS    0H
         CLC   P1ORC(2),=C'01'         Warning condition?
         BE    PUTWARN                    Yes, process warning
\*                                             and then process input;
\*                                          otherwise, process error
         MVC   ERINPUT,DSPLYIN    Boro code, hse no., street name
         MVC   ERFUNC,P1IFUNC              function code
         MVC   ERRET(L'P1ORC),P1ORC        return code
         MVC   ERREAS(L'P1OREASN),P1OREASN reason code
         PUT   OUTFILE,ERR1            Print error messages 1
         B     PUTMSG                                  and 2
```

```
PUTWARN  DS    0H
         MVC   WRINPUT,DSPLYIN    Boro code, hse no., street name
         MVC   WRFUNC,P1IFUNC              function code
         MVC   WRRET(L'P1ORC),P1ORC        return code
  MVC   WRREAS(L'P1OREASN),P1OREASN reason code
         PUT   OUTFILE,WRN1            Print warning messages 1
PUTMSG   DS    0H                                        and 2
         MVC   ERRWRN(L'P1OERROR),P1OERROR
         PUT   OUTFILE,ERRWRN2         Print error/warning message 2
         CLC   P1ORC(2),=C'01'         Warning condition?
         BNE   NEXTREC                  No, get next record, if any
         MVI   OINPUT,C' '              Yes,
         MVC   OINPUT+1(L'OINPUT-1),OINPUT  ensure input NOT displayd
         MVI   OUTVALID,C' '     ensure single-spacing after warning
         B     GETZIP            and continue normal processing
         SPACE
\* Handle successful Geosupport calls (Return Code <= 01)
PROCESS  DS    0H
         MVC   OINPUT,DSPLYIN    Boro code, hse no., street name
         MVI   OUTVALID,C'0'     Ensure double-spacing
GETZIP   DS    0H
         MVC   OZIP,P2F1ZIP      ZIP code
         MVC   OCOMM,P2F1CDN     community district number
         MVC   OPCT,P2F1POP      police precinct
         MVC   OSCHL,P2F1SCH     school district
***** At this point, clear WA1 again, call Function D, and move ******
***** its reported Low and High Intersecting Street Names to output *
         TITLE 'GET LOW, HIGH INTERSECTING STREETS, USING FUNCTION D'
         SPACE 2
*************************************************************
\* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND   *
\* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE     *
\* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS      *
\* FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D:  *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                     *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO D                  *
\*   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED       *
\*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE      *
\*              HAS SPACE FOR ONLY 25 CHARACTERS)            *
\*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN       *
\*       STREET NAMES FORMATTED FOR DISPLAY                  *
\*   (5) MOVE WA2'S LOW B5SC FIELD TO WA1'S INPUT STREET     *
\*       CODE 1 FIELD                                        *
\*   (6) MOVE WA2'S HIGH B5SC FIELD TO WA1'S INPUT STREET    *
\*       CODE 2 FIELD                                        *
```

```
\*   (7) CALL GBI WITH 1 WORKAREA                          *
\*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS         *
*************************************************************
         SPACE
\* Clear WA1 to blanks
         LA    R8,P1BAL    "To" address for MVCL
         LA    R9,P1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         MVI   P1IPLIND,C'C'                Set Work Area Format to COW
*
\* Note  COW - MSW: P1ICDEx is the 10-digit street code (no boro)
\*                  P1IBCDx is the Boro and 10-digit street code
\*                  W1ICDEx is the packed Boro and 5-digit street code
\*                  P2F1CDEx is Boro and 5-digit street code list
\*                  W2F1CDEx is packed Boro and 5-digit street code list
*
         MVC   P1IBCD1(6),P2F1CDEL
         MVC   P1IBCD2(6),P2F1CDEH
         MVC   P1IFUNC(2),=CL2'D '
         MVC   P1ISNL(L'P1ISNL),=C'25'    normalized street name length
         MVI   P1ICMPCT,C'C'              streets to be compacted
         CALL  GBI,P1BAL,VL   Call Function D
\* Check Return code
         CLC   P1ORC(2),=C'00'         Good return?
         BNE   ERREXIT                     No, error or warning
\*                                          Yes, complete the record
\*                                               and write it out
PUTREC   DS    0H
         MVC   OLOSTRT,P1OSTRT1
         MVC   OHISTRT,P1OSTRT2
\* Print an output record and get the next input record, if any
         PUT   OUTFILE,OUTVALID
         B     NEXTREC
EXIT     DS    0H
OUTOPNER DS    0H
         CLOSE (INFILE)
         TM    OUTFILE+48,X'10'   Did OUTFILE open successfully?
         BNO   INOPNERR              No, bypass closing it
         CLOSE (OUTFILE)
INOPNERR DS    0H
```

```
         L     R13,4(,R13)
         L     R14,12(,R13)
         LM    R0,R12,20(R13)
         BR    R14
         SPACE 2
PARAMERR DS    0H       parameter error, missing or invalid
         LA    R15,8    rc=8
         B     EXIT
         TITLE 'DATA SECTION - REGISTER ASSIGNMENTS'
R0       EQU   0
R1       EQU   1
R2       EQU   2
R3       EQU   3
R4       EQU   4
R5       EQU   5
R6       EQU   6
R7       EQU   7
R8       EQU   8
R9       EQU   9
R10      EQU   10
R11      EQU   11
R12      EQU   12
R13      EQU   13
R14      EQU   14
R15      EQU   15
         TITLE 'FILE AND RECORD DEFINITIONS'
         PUSH  PRINT
         PRINT NOGEN
INFILE   DCB   DSORG=PS,MACRF=(GM),DDNAME=INFILE,                    *
               RECFM=FB,LRECL=80,BLKSIZE=400,EODAD=EXIT
         SPACE
OUTFILE  DCB   DSORG=PS,MACRF=(PM),DDNAME=SYSPRINT,                  *
               RECFM=FBA,LRECL=133,BLKSIZE=1330
*
         POP PRINT
         SPACE
INREC    DS    0CL80              Input record
INBORO   DS    CL1                    Borough code
INHOUSE  DS    CL12                   House number
INSTREET DS    CL32                   Street name
         DC    35C' '                 filler
         SPACE
\* Output records: error, warning, and normal
ERR1     DS    0CL133
         DC    C'0'
```

```
ERINPUT  DS    CL48
         DC    C'*** FUNCTION '
ERFUNC   DS    CL2
         DC    C' GRC = '
ERRET    DS    CL2
         DC    C' REASON CODE = '
ERREAS   DS    CL1
         DC    CL(133-89)' '
         SPACE
WRN1     DS    0CL133
         DC    C'0'
WRINPUT  DS    CL48
         DC    C'*** FUNCTION '
WRFUNC   DS    CL2
         DC    C' WARNING, GRC = '
WRRET    DS    CL2
         DC    C' REASON CODE = '
WRREAS   DS    CL1
         DC    CL(133-98)' '
         SPACE
ERRWRN2  DS    0CL133
         DC    C' '
         DC    48C' '          Boro Code, House Number, Street Name
         DC    CL4'*** '
ERRWRN   DS    CL80            Error/Warning message
         SPACE
HDR1     DC    CL133'1SAMPLE ASSEMBLER \#1 EXECUTION OUTPUT             *
                                          '
HDR2     DC    CL133'0*****---------- INPUT ADDRESS ------------***** \*C
               ****--------------------- SELECTED OUTPUT ITEMS --------C
               ----------------------*****'
HDR3     DC    CL133'0B HOUSE NUMBER IN-STREET-NAME                    *
                ZIP CD NYPD-PCT SCHLDST LOW CROSS STREET          HIGH *
               CROSS STREET                '
HDR4     DC    CL133' - ------------ ------------------------------- -*
               ---- -- -------- ------- ------------------------- -----*
               ---------------------------'
OUTVALID DS    0CL133
\* Borough code, house number, and street name are from input record
         DC    C'0'
OINPUT   DS    CL48
OZIP     DS    CL5
         DC    C' '
OCOMM    DS    CL2
         DC    C' '
```

```
OPCT     DS    CL3
         DC    6C' '
OSCHL    DS    CL2
         DC    6C' '
OLOSTRT  DS    CL25  Normalized name of intersecting street at low end
         DC    C' '
OHISTRT  DS    CL25  Normalized name of intersecting street at high end
         DC    7C' '
         TITLE 'WORKING VARIABLES, VALUES, ETC.'
MYSAVE   DC    18F'0'
***********************************************************************
***** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     ***
***** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                      ***
***********************************************************************
         COPY  P1BAL              COPY WORK AREA 1
         EJECT
         COPY  P2BAL              COPY WORK AREA 2
         EJECT
         SPACE 2
DSPLYIN  DS    0CL48
DBORO    DS    CL1
         DC    C' '
DHSE     DS    CL12
         DC    C' '
DSTRT    DS    CL32
         DC    C' '
         SPACE 2
         TITLE 'CONSTANTS AND LITERAL POOL'
         SPACE 2
         LTORG
         END   ASMC1SRC
//LKED.SYSIN  DD  *
 INCLUDE INCLIB(GBI)
/*
//LKED.INCLIB   DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*                                                          \*//
//*     AS OF GEOSUPPORT VERSION 10.0,                       \*//
//*     GEO.SUPPORT.PDSE.LOADLIB AND GEO.SUPPORT.LOADLIB     \*//
//*     ARE REQUIRED IN THE STEPLIB (OR JOBLIB) OF THE       \*//
//*     GEOSUPPORT EXECUTION STEP.                           \*//
//*                                                          \*//
//GO.STEPLIB  DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//*           DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*                                                          \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                         \*//
```

```
//*   DD STATEMENTS ARE NO LONGER USED TO DEFINE?              \*//
//*   GEOSUPPORT DATA FILES.                                   \*//
//*   DD STATEMENTS ARE NO LONGER INCLUDED FOR THE             \*//
//*   GEOSUPPORT FOREGROUND FILES.                             \*//
//*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER   \*//
//*                                                            \*//
//SYSUDUMP DD  SYSOUT=\*,OUTLIM=2000
//SYSPRINT DD  SYSOUT=*
//INFILE   DD  *
122          READE ST
1500         DUANE ST
12-4         BROADWAY
4165-100     BAISLEY BLVD
4165-1000    BAISLEY BLVD
/*
//


<center><b>ASSEMBLER SAMPLE PROGRAM \#1 –Job Stream-COW</b></center>

//ASMC1SRC JOB   YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//**  ASSEMBLER SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1 **
//**                        COW FORMAT                             **
//*******************************************************************
//STEP1  EXEC  ASMACLG,
//         PARM.ASM='OBJECT,NODECK',
//         PARM.LKED='XREF,LET,LIST,NCAL'
//ASM.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//           DD DSN=A030.GEO.COPYLIB,DISP=SHR
//           DD DSN=SYS1.MACLIB,DISP=SHR
//ASM.SYSIN  DD *
ASMC1SRC TITLE 'SAMPLE GEOSUPPORT ASSEMBLER PROGRAM 1 - COW FORMAT'
ASMC1SRC CSECT
*****************************************************************
\* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING *
\* BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.*
\* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     *
\* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  *
\* - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - *
\* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE         *
\*       ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET NAMES *
\*       WOULD HAVE BEEN RETURNED BY FUNCTION 1.                 *
*****************************************************************
```

```
*
**********************************************************************
\*                                                                    *
\*  This program will do the following:                               *
\*                                                                    *
\*     * Read an instream record containing a house number,           *
\*       street name, and borough code                                *
\*                                                                    *
\*     * Build Work Area 1 for a Function 1 call                      *
\*                                                                    *
\*     * Call Function 1                                              *
\*                                                                    *
\*     * Get ZIP code, community district, police precinct, school    *
\*       district, and lists of street codes of streets intersecting  *
\*       at the low and high ends of the input street address's block. *
\*       These will be displayed along with the input address which   *
\*       consists of borough code, house number, and street name.     *
\*                                                                    *
\*     * Call Function D to get the street names of the first         *
\*       intersecting street on both low and high ends.               *
\*                                                                    *
\*     * Print the information                                        *
\*                                                                    *
\* NOTE that after each Geosupport call, the Return Code is checked.  *
\*      If it is greater than 01, an error message is printed, and    *
\*      the next input record, if any, is read.                       *
\*      If it is 01, a warning message is printed, the input record is *
\*      processed, and the next record is read.                       *
\*      If it is zero, the input record is processed, and the next    *
\*      record is read.                                               *
\*                                                                    *
**********************************************************************
         SPACE
         STM   R14,R12,12(R13)   Save caller's registers
         LR    R3,R15
         LA    R12,4095(,R3)     (second base register
         LA    R12,1(,R12)        to accomodate Work Areas 1 and 2)
         USING ASMC1SRC,R3,R12
\* Chain save areas
         LA    R4,MYSAVE
         ST    R13,4(,R4)    Save caller's savearea address
         ST    R4,8(,R13)    Save pgm's savearea adr in caller savearea
         LR    R13,R4        Ensure that R13 points to pgm's savearea
         SPACE 2
         XR    R15,R15                (set OS return code to zero)
```

```
\* Open input and output files
         OPEN  (INFILE,,OUTFILE,(OUTPUT))
         TM    INFILE+48,X'10'   Did input file open successfully?
         BNO   INOPNERR             (no..)
         TM    OUTFILE+48,X'10'  Did output file open successfully?
         BNO   OUTOPNER             (no..)
\* Print page and report header lines
         SPACE
         PUT   OUTFILE,HDR1
         PUT   OUTFILE,HDR2
         PUT   OUTFILE,HDR3
         PUT   OUTFILE,HDR4
         B     NEXTREC
         SPACE 2
         TITLE 'READ IN-STREAM INPUT AND PREPARE FUNCTION 1 CALL'
\* Read (next) input record
NEXTREC  DS    0H
         GET   INFILE,INREC
\* Move input data to output record for display
         MVC   DBORO,INBORO                   borough code
         MVC   DHSE(L'INHOUSE),INHOUSE        house number
         MVC   DSTRT,INSTREET                 street name
         SPACE
*****************************************************************
\* TO MAKE A FUNCTION 1 CALL:                                    *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                         *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                      *
\*   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD      *
\*   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER *
\*       FIELD                                                   *
\*   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  *
\*   (6) CALL GBI WITH 2 WORKAREAS                               *
\*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS               *
*****************************************************************
\* Clear WA1 to blanks
         LA    R8,P1BAL    "To" address for MVCL
         LA    R9,P1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
\* and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         SPACE
\* Prime Work Area 1 for Function 1 call
```

```
         MVI   P1IPLIND,C'C'                Set Work Area Format to COW
         MVC   P1IFUNC,=CL2'1 '              Get function code
         MVC   P1IBORO1,INBORO                   borough code
*
\* Note COW - MSW: Display House # - P1IHSE# is a 16-byte field
\*                                   W1IHSE# is a 12-byte field
*
         MVC   P1IHSE#(L'INHOUSE),INHOUSE        house number
         MVC   P1ISTRT1,INSTREET                 street name
*

\* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
\*                                                                   *
\*        As of Geosupport Version 10.1,                             *
\*        to receive roadbed-specific information,                   *
\*        set the Roadbed Request Switch to 'R', as follows:         *
\*        MVC   P1IRBRQS,C'R'                                        *
\*                                                                   *
\* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
*
         MVC   P1ISNL(L'P1ISNL),=C'25'    Normalized street name length
\* Call Function 1 (2-Work-Area call)
         CALL  GBI,(P1BAL,P2BAL),VL
\* Check Return code
         CLC   P1ORC(2),=C'00'         Good return?
         BE    PROCESS                     Yes, process returned data
\* Handle errors and warnings
ERREXIT  DS    0H
         CLC   P1ORC(2),=C'01'         Warning condition?
         BE    PUTWARN                    Yes, process warning
\*                                             and then process input;
\*                                         otherwise, process error
         MVC   ERINPUT,DSPLYIN    Boro code, hse no., street name
         MVC   ERFUNC,P1IFUNC              function code
         MVC   ERRET(L'P1ORC),P1ORC        return code
         MVC   ERREAS(L'P1OREASN),P1OREASN reason code
         PUT   OUTFILE,ERR1            Print error messages 1
         B     PUTMSG                                  and 2
PUTWARN  DS    0H
         MVC   WRINPUT,DSPLYIN    Boro code, hse no., street name
         MVC   WRFUNC,P1IFUNC              function code
         MVC   WRRET(L'P1ORC),P1ORC        return code
  MVC   WRREAS(L'P1OREASN),P1OREASN reason code
         PUT   OUTFILE,WRN1            Print warning messages 1
PUTMSG   DS    0H                                        and 2
```

```
         MVC   ERRWRN(L'P1OERROR),P1OERROR
         PUT   OUTFILE,ERRWRN2         Print error/warning message 2
         CLC   P1ORC(2),=C'01'         Warning condition?
         BNE   NEXTREC                  No, get next record, if any
         MVI   OINPUT,C' '              Yes,
         MVC   OINPUT+1(L'OINPUT-1),OINPUT  ensure input NOT displayd
         MVI   OUTVALID,C' '     ensure single-spacing after warning
         B     GETZIP            and continue normal processing
         SPACE
\* Handle successful Geosupport calls (Return Code <= 01)
PROCESS  DS    0H
         MVC   OINPUT,DSPLYIN    Boro code, hse no., street name
         MVI   OUTVALID,C'0'     Ensure double-spacing
GETZIP   DS    0H
         MVC   OZIP,P2F1ZIP      ZIP code
         MVC   OCOMM,P2F1CDN     community district number
         MVC   OPCT,P2F1POP      police precinct
         MVC   OSCHL,P2F1SCH     school district
***** At this point, clear WA1 again, call Function D, and move ******
***** its reported Low and High Intersecting Street Names to output *
         TITLE 'GET LOW, HIGH INTERSECTING STREETS, USING FUNCTION D'
         SPACE 2
*************************************************************
\* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND   *
\* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE     *
\* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS      *
\* FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D:  *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                     *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO D                  *
\*   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED       *
\*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE      *
\*              HAS SPACE FOR ONLY 25 CHARACTERS)            *
\*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN       *
\*       STREET NAMES FORMATTED FOR DISPLAY                  *
\*   (5) MOVE WA2'S LOW B5SC FIELD TO WA1'S INPUT STREET     *
\*       CODE 1 FIELD                                        *
\*   (6) MOVE WA2'S HIGH B5SC FIELD TO WA1'S INPUT STREET    *
\*       CODE 2 FIELD                                        *
\*   (7) CALL GBI WITH 1 WORKAREA                            *
\*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS           *
*************************************************************
         SPACE
\* Clear WA1 to blanks
         LA    R8,P1BAL    "To" address for MVCL
         LA    R9,P1LENGTH     "To" length
```

```
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         MVI   P1IPLIND,C'C'                Set Work Area Format to COW
*
\* Note  COW - MSW: P1ICDEx is the 10-digit street code (no boro)
\*                  P1IBCDx is the Boro and 10-digit street code
\*                  W1ICDEx is the packed Boro and 5-digit street code
\*                  P2F1CDEx is Boro and 5-digit street code list
\*                  W2F1CDEx is packed Boro and 5-digit street code list
*
         MVC   P1IBCD1(6),P2F1CDEL
         MVC   P1IBCD2(6),P2F1CDEH
         MVC   P1IFUNC(2),=CL2'D '
         MVC   P1ISNL(L'P1ISNL),=C'25'    normalized street name length
         MVI   P1ICMPCT,C'C'              streets to be compacted
         CALL  GBI,P1BAL,VL   Call Function D
\* Check Return code
         CLC   P1ORC(2),=C'00'         Good return?
         BNE   ERREXIT                     No, error or warning
\*                                          Yes, complete the record
\*                                               and write it out
PUTREC   DS    0H
         MVC   OLOSTRT,P1OSTRT1
         MVC   OHISTRT,P1OSTRT2
\* Print an output record and get the next input record, if any
         PUT   OUTFILE,OUTVALID
         B     NEXTREC
EXIT     DS    0H
OUTOPNER DS    0H
         CLOSE (INFILE)
         TM    OUTFILE+48,X'10'   Did OUTFILE open successfully?
         BNO   INOPNERR              No, bypass closing it
         CLOSE (OUTFILE)
INOPNERR DS    0H
         L     R13,4(,R13)
         L     R14,12(,R13)
         LM    R0,R12,20(R13)
         BR    R14
         SPACE 2
PARAMERR DS    0H       parameter error, missing or invalid
         LA    R15,8    rc=8
```

```
         B     EXIT
         TITLE 'DATA SECTION - REGISTER ASSIGNMENTS'
R0       EQU   0
R1       EQU   1
R2       EQU   2
R3       EQU   3
R4       EQU   4
R5       EQU   5
R6       EQU   6
R7       EQU   7
R8       EQU   8
R9       EQU   9
R10      EQU   10
R11      EQU   11
R12      EQU   12
R13      EQU   13
R14      EQU   14
R15      EQU   15
         TITLE 'FILE AND RECORD DEFINITIONS'
         PUSH  PRINT
         PRINT NOGEN
INFILE   DCB   DSORG=PS,MACRF=(GM),DDNAME=INFILE,                    *
               RECFM=FB,LRECL=80,BLKSIZE=400,EODAD=EXIT
         SPACE
OUTFILE  DCB   DSORG=PS,MACRF=(PM),DDNAME=SYSPRINT,                  *
               RECFM=FBA,LRECL=133,BLKSIZE=1330
*
         POP PRINT
         SPACE
INREC    DS    0CL80              Input record
INBORO   DS    CL1                    Borough code
INHOUSE  DS    CL12                   House number
INSTREET DS    CL32                   Street name
         DC    35C' '                 filler
         SPACE
\* Output records: error, warning, and normal
ERR1     DS    0CL133
         DC    C'0'
ERINPUT  DS    CL48
         DC    C'*** FUNCTION '
ERFUNC   DS    CL2
         DC    C' GRC = '
ERRET    DS    CL2
         DC    C' REASON CODE = '
ERREAS   DS    CL1
```

```
         DC    CL(133-89)' '
         SPACE
WRN1     DS    0CL133
         DC    C'0'
WRINPUT  DS    CL48
         DC    C'*** FUNCTION '
WRFUNC   DS    CL2
         DC    C' WARNING, GRC = '
WRRET    DS    CL2
         DC    C' REASON CODE = '
WRREAS   DS    CL1
         DC    CL(133-98)' '
         SPACE
ERRWRN2  DS    0CL133
         DC    C' '
         DC    48C' '          Boro Code, House Number, Street Name
         DC    CL4'*** '
ERRWRN   DS    CL80            Error/Warning message
         SPACE
HDR1     DC    CL133'1SAMPLE ASSEMBLER \#1 EXECUTION OUTPUT             *
                                                '
HDR2     DC    CL133'0*****---------- INPUT ADDRESS ------------***** \*C
               ****--------------------- SELECTED OUTPUT ITEMS --------C
               ----------------------*****'
HDR3     DC    CL133'0B HOUSE NUMBER IN-STREET-NAME                    *
                ZIP CD NYPD-PCT SCHLDST LOW CROSS STREET          HIGH *
               CROSS STREET                '
HDR4     DC    CL133' - ------------ ------------------------------- -*
               ---- -- -------- ------- ------------------------- -----*
               ---------------------------'
OUTVALID DS    0CL133
\* Borough code, house number, and street name are from input record
         DC    C'0'
OINPUT   DS    CL48
OZIP     DS    CL5
         DC    C' '
OCOMM    DS    CL2
         DC    C' '
OPCT     DS    CL3
         DC    6C' '
OSCHL    DS    CL2
         DC    6C' '
OLOSTRT  DS    CL25  Normalized name of intersecting street at low end
         DC    C' '
OHISTRT  DS    CL25  Normalized name of intersecting street at high end
```

```
         DC    7C' '
         TITLE 'WORKING VARIABLES, VALUES, ETC.'
MYSAVE   DC    18F'0'
*********************************************************************
***** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     ***
***** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                      ***
*********************************************************************
         COPY  P1BAL              COPY WORK AREA 1
         EJECT
         COPY  P2BAL              COPY WORK AREA 2
         EJECT
         SPACE 2
DSPLYIN  DS    0CL48
DBORO    DS    CL1
         DC    C' '
DHSE     DS    CL12
         DC    C' '
DSTRT    DS    CL32
         DC    C' '
         SPACE 2
         TITLE 'CONSTANTS AND LITERAL POOL'
         SPACE 2
         LTORG
         END   ASMC1SRC
//LKED.SYSIN  DD  *
 INCLUDE INCLIB(GBI)
/*
//LKED.INCLIB   DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*                                                          \*//
//*     AS OF GEOSUPPORT VERSION 10.0,                       \*//
//*     GEO.SUPPORT.PDSE.LOADLIB AND GEO.SUPPORT.LOADLIB     \*//
//*     ARE REQUIRED IN THE STEPLIB (OR JOBLIB) OF THE       \*//
//*     GEOSUPPORT EXECUTION STEP.                           \*//
//*                                                          \*//
//GO.STEPLIB  DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//*           DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*                                                          \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                         \*//
//*   DD STATEMENTS ARE NO LONGER USED TO DEFINE?            \*//
//*   GEOSUPPORT DATA FILES.                                 \*//
//*   DD STATEMENTS ARE NO LONGER INCLUDED FOR THE           \*//
//*   GEOSUPPORT FOREGROUND FILES.                           \*//
//*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER \*//
//*                                                          \*//
//SYSUDUMP DD  SYSOUT=\*,OUTLIM=2000
```

```
//SYSPRINT DD  SYSOUT=*
//INFILE   DD  *
122          READE ST
1500         DUANE ST
12-4         BROADWAY
4165-100     BAISLEY BLVD
4165-1000    BAISLEY BLVD
/*
//
```

ASSEMBLER SAMPLE PROGRAM #1 –Job Stream-COW

```
//ASMC1SRC JOB   YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//**  ASSEMBLER SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1 **
//**                        COW FORMAT                            **
//*******************************************************************
//STEP1  EXEC  ASMACLG,
//         PARM.ASM='OBJECT,NODECK',
//         PARM.LKED='XREF,LET,LIST,NCAL'
//ASM.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//           DD DSN=A030.GEO.COPYLIB,DISP=SHR
//           DD DSN=SYS1.MACLIB,DISP=SHR
//ASM.SYSIN  DD *
ASMC1SRC TITLE 'SAMPLE GEOSUPPORT ASSEMBLER PROGRAM 1 - COW FORMAT'
ASMC1SRC CSECT
*****************************************************************
\* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING *
\* BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.*
\* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     *
\* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  *
\* - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - *
\* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE         *
\*       ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET NAMES *
\*       WOULD HAVE BEEN RETURNED BY FUNCTION 1.                 *
*****************************************************************
*
*********************************************************************
\*                                                                  *
\*  This program will do the following:                             *
\*                                                                  *
\*     * Read an instream record containing a house number,         *
\*       street name, and borough code                              *
\*                                                                  *
```

```
\*     * Build Work Area 1 for a Function 1 call                        *
\*                                                                      *
\*     * Call Function 1                                                *
\*                                                                      *
\*     * Get ZIP code, community district, police precinct, school      *
\*       district, and lists of street codes of streets intersecting    *
\*       at the low and high ends of the input street address's block. *
\*       These will be displayed along with the input address which     *
\*       consists of borough code, house number, and street name.       *
\*                                                                      *
\*     * Call Function D to get the street names of the first           *
\*       intersecting street on both low and high ends.                 *
\*                                                                      *
\*     * Print the information                                          *
\*                                                                      *
\* NOTE that after each Geosupport call, the Return Code is checked.    *
\*      If it is greater than 01, an error message is printed, and      *
\*      the next input record, if any, is read.                         *
\*      If it is 01, a warning message is printed, the input record is *
\*      processed, and the next record is read.                         *
\*      If it is zero, the input record is processed, and the next      *
\*      record is read.                                                 *
\*                                                                      *
************************************************************************
         SPACE
         STM   R14,R12,12(R13)   Save caller's registers
         LR    R3,R15
         LA    R12,4095(,R3)     (second base register
         LA    R12,1(,R12)        to accomodate Work Areas 1 and 2)
         USING ASMC1SRC,R3,R12
\* Chain save areas
         LA    R4,MYSAVE
         ST    R13,4(,R4)    Save caller's savearea address
         ST    R4,8(,R13)    Save pgm's savearea adr in caller savearea
         LR    R13,R4        Ensure that R13 points to pgm's savearea
         SPACE 2
         XR    R15,R15                 (set OS return code to zero)
\* Open input and output files
         OPEN  (INFILE,,OUTFILE,(OUTPUT))
         TM    INFILE+48,X'10'   Did input file open successfully?
         BNO   INOPNERR             (no..)
         TM    OUTFILE+48,X'10'  Did output file open successfully?
         BNO   OUTOPNER             (no..)
\* Print page and report header lines
         SPACE
```

```
         PUT   OUTFILE,HDR1
         PUT   OUTFILE,HDR2
         PUT   OUTFILE,HDR3
         PUT   OUTFILE,HDR4
         B     NEXTREC
         SPACE 2
         TITLE 'READ IN-STREAM INPUT AND PREPARE FUNCTION 1 CALL'
\* Read (next) input record
NEXTREC  DS    0H
         GET   INFILE,INREC
\* Move input data to output record for display
         MVC   DBORO,INBORO                  borough code
         MVC   DHSE(L'INHOUSE),INHOUSE       house number
         MVC   DSTRT,INSTREET                street name
         SPACE
*****************************************************************
\* TO MAKE A FUNCTION 1 CALL:                                    *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                         *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                      *
\*   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD      *
\*   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER *
\*       FIELD                                                   *
\*   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  *
\*   (6) CALL GBI WITH 2 WORKAREAS                               *
\*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS               *
*****************************************************************
\* Clear WA1 to blanks
         LA    R8,P1BAL    "To" address for MVCL
         LA    R9,P1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
\* and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         SPACE
\* Prime Work Area 1 for Function 1 call
         MVI   P1IPLIND,C'C'                Set Work Area Format to COW
         MVC   P1IFUNC,=CL2'1 '              Get function code
         MVC   P1IBORO1,INBORO                   borough code
*
\* Note COW - MSW: Display House # - P1IHSE# is a 16-byte field
\*                                   W1IHSE# is a 12-byte field
*
         MVC   P1IHSE#(L'INHOUSE),INHOUSE        house number
```

```
         MVC   P1ISTRT1,INSTREET                 street name
*

\* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
\*                                                                    *
\*        As of Geosupport Version 10.1,                              *
\*        to receive roadbed-specific information,                    *
\*        set the Roadbed Request Switch to 'R', as follows:          *
\*        MVC   P1IRBRQS,C'R'                                         *
\*                                                                    *
\* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *
*
         MVC   P1ISNL(L'P1ISNL),=C'25'    Normalized street name length
\* Call Function 1 (2-Work-Area call)
         CALL  GBI,(P1BAL,P2BAL),VL
\* Check Return code
         CLC   P1ORC(2),=C'00'         Good return?
         BE    PROCESS                     Yes, process returned data
\* Handle errors and warnings
ERREXIT  DS    0H
         CLC   P1ORC(2),=C'01'         Warning condition?
         BE    PUTWARN                    Yes, process warning
\*                                              and then process input;
\*                                          otherwise, process error
         MVC   ERINPUT,DSPLYIN    Boro code, hse no., street name
         MVC   ERFUNC,P1IFUNC              function code
         MVC   ERRET(L'P1ORC),P1ORC        return code
         MVC   ERREAS(L'P1OREASN),P1OREASN reason code
         PUT   OUTFILE,ERR1            Print error messages 1
         B     PUTMSG                                 and 2
PUTWARN  DS    0H
         MVC   WRINPUT,DSPLYIN    Boro code, hse no., street name
         MVC   WRFUNC,P1IFUNC              function code
         MVC   WRRET(L'P1ORC),P1ORC        return code
  MVC   WRREAS(L'P1OREASN),P1OREASN reason code
         PUT   OUTFILE,WRN1            Print warning messages 1
PUTMSG   DS    0H                                        and 2
         MVC   ERRWRN(L'P1OERROR),P1OERROR
         PUT   OUTFILE,ERRWRN2         Print error/warning message 2
         CLC   P1ORC(2),=C'01'         Warning condition?
         BNE   NEXTREC                  No, get next record, if any
         MVI   OINPUT,C' '              Yes,
         MVC   OINPUT+1(L'OINPUT-1),OINPUT  ensure input NOT displayd
         MVI   OUTVALID,C' '     ensure single-spacing after warning
         B     GETZIP            and continue normal processing
```

```
         SPACE
\* Handle successful Geosupport calls (Return Code <= 01)
PROCESS  DS    0H
         MVC   OINPUT,DSPLYIN    Boro code, hse no., street name
         MVI   OUTVALID,C'0'     Ensure double-spacing
GETZIP   DS    0H
         MVC   OZIP,P2F1ZIP      ZIP code
         MVC   OCOMM,P2F1CDN     community district number
         MVC   OPCT,P2F1POP      police precinct
         MVC   OSCHL,P2F1SCH     school district
***** At this point, clear WA1 again, call Function D, and move ******
***** its reported Low and High Intersecting Street Names to output *
         TITLE 'GET LOW, HIGH INTERSECTING STREETS, USING FUNCTION D'
         SPACE 2
*************************************************************
\* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND   *
\* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE     *
\* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS      *
\* FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D:  *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                     *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO D                  *
\*   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED       *
\*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE      *
\*              HAS SPACE FOR ONLY 25 CHARACTERS)            *
\*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN       *
\*       STREET NAMES FORMATTED FOR DISPLAY                  *
\*   (5) MOVE WA2'S LOW B5SC FIELD TO WA1'S INPUT STREET     *
\*       CODE 1 FIELD                                        *
\*   (6) MOVE WA2'S HIGH B5SC FIELD TO WA1'S INPUT STREET    *
\*       CODE 2 FIELD                                        *
\*   (7) CALL GBI WITH 1 WORKAREA                            *
\*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS           *
*************************************************************
         SPACE
\* Clear WA1 to blanks
         LA    R8,P1BAL    "To" address for MVCL
         LA    R9,P1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         MVI   P1IPLIND,C'C'               Set Work Area Format to COW
*
```

```
\* Note  COW - MSW: P1ICDEx is the 10-digit street code (no boro)
\*                  P1IBCDx is the Boro and 10-digit street code
\*                  W1ICDEx is the packed Boro and 5-digit street code
\*                  P2F1CDEx is Boro and 5-digit street code list
\*                  W2F1CDEx is packed Boro and 5-digit street code list
*
         MVC   P1IBCD1(6),P2F1CDEL
         MVC   P1IBCD2(6),P2F1CDEH
         MVC   P1IFUNC(2),=CL2'D '
         MVC   P1ISNL(L'P1ISNL),=C'25'    normalized street name length
         MVI   P1ICMPCT,C'C'              streets to be compacted
         CALL  GBI,P1BAL,VL   Call Function D
\* Check Return code
         CLC   P1ORC(2),=C'00'         Good return?
         BNE   ERREXIT                     No, error or warning
\*                                          Yes, complete the record
\*                                               and write it out
PUTREC   DS    0H
         MVC   OLOSTRT,P1OSTRT1
         MVC   OHISTRT,P1OSTRT2
\* Print an output record and get the next input record, if any
         PUT   OUTFILE,OUTVALID
         B     NEXTREC
EXIT     DS    0H
OUTOPNER DS    0H
         CLOSE (INFILE)
         TM    OUTFILE+48,X'10'   Did OUTFILE open successfully?
         BNO   INOPNERR              No, bypass closing it
         CLOSE (OUTFILE)
INOPNERR DS    0H
         L     R13,4(,R13)
         L     R14,12(,R13)
         LM    R0,R12,20(R13)
         BR    R14
         SPACE 2
PARAMERR DS    0H       parameter error, missing or invalid
         LA    R15,8    rc=8
         B     EXIT
         TITLE 'DATA SECTION - REGISTER ASSIGNMENTS'
R0       EQU   0
R1       EQU   1
R2       EQU   2
R3       EQU   3
R4       EQU   4
R5       EQU   5
```

```
R6       EQU   6
R7       EQU   7
R8       EQU   8
R9       EQU   9
R10      EQU   10
R11      EQU   11
R12      EQU   12
R13      EQU   13
R14      EQU   14
R15      EQU   15
         TITLE 'FILE AND RECORD DEFINITIONS'
         PUSH  PRINT
         PRINT NOGEN
INFILE   DCB   DSORG=PS,MACRF=(GM),DDNAME=INFILE,                    *
               RECFM=FB,LRECL=80,BLKSIZE=400,EODAD=EXIT
         SPACE
OUTFILE  DCB   DSORG=PS,MACRF=(PM),DDNAME=SYSPRINT,                  *
               RECFM=FBA,LRECL=133,BLKSIZE=1330
*
         POP PRINT
         SPACE
INREC    DS    0CL80              Input record
INBORO   DS    CL1                    Borough code
INHOUSE  DS    CL12                   House number
INSTREET DS    CL32                   Street name
         DC    35C' '                 filler
         SPACE
\* Output records: error, warning, and normal
ERR1     DS    0CL133
         DC    C'0'
ERINPUT  DS    CL48
         DC    C'*** FUNCTION '
ERFUNC   DS    CL2
         DC    C' GRC = '
ERRET    DS    CL2
         DC    C' REASON CODE = '
ERREAS   DS    CL1
         DC    CL(133-89)' '
         SPACE
WRN1     DS    0CL133
         DC    C'0'
WRINPUT  DS    CL48
         DC    C'*** FUNCTION '
WRFUNC   DS    CL2
         DC    C' WARNING, GRC = '
```

```
WRRET    DS    CL2
         DC    C' REASON CODE = '
WRREAS   DS    CL1
         DC    CL(133-98)' '
         SPACE
ERRWRN2  DS    0CL133
         DC    C' '
         DC    48C' '          Boro Code, House Number, Street Name
         DC    CL4'*** '
ERRWRN   DS    CL80            Error/Warning message
         SPACE
HDR1     DC    CL133'1SAMPLE ASSEMBLER \#1 EXECUTION OUTPUT             *
                                '
HDR2     DC    CL133'0*****---------- INPUT ADDRESS ------------***** \*C
               ****--------------------- SELECTED OUTPUT ITEMS --------C
               ----------------------*****'
HDR3     DC    CL133'0B HOUSE NUMBER IN-STREET-NAME                    *
                ZIP CD NYPD-PCT SCHLDST LOW CROSS STREET          HIGH *
               CROSS STREET               '
HDR4     DC    CL133' - ------------ ------------------------------- -*
               ---- -- -------- ------- ------------------------- -----*
               ---------------------------'
OUTVALID DS    0CL133
\* Borough code, house number, and street name are from input record
         DC    C'0'
OINPUT   DS    CL48
OZIP     DS    CL5
         DC    C' '
OCOMM    DS    CL2
         DC    C' '
OPCT     DS    CL3
         DC    6C' '
OSCHL    DS    CL2
         DC    6C' '
OLOSTRT  DS    CL25  Normalized name of intersecting street at low end
         DC    C' '
OHISTRT  DS    CL25  Normalized name of intersecting street at high end
         DC    7C' '
         TITLE 'WORKING VARIABLES, VALUES, ETC.'
MYSAVE   DC    18F'0'
***********************************************************************
***** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     ***
***** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                      ***
***********************************************************************
         COPY  P1BAL              COPY WORK AREA 1
```

```
         EJECT
         COPY  P2BAL              COPY WORK AREA 2
         EJECT
         SPACE 2
DSPLYIN  DS    0CL48
DBORO    DS    CL1
         DC    C' '
DHSE     DS    CL12
         DC    C' '
DSTRT    DS    CL32
         DC    C' '
         SPACE 2
         TITLE 'CONSTANTS AND LITERAL POOL'
         SPACE 2
         LTORG
         END   ASMC1SRC
//LKED.SYSIN  DD  *
 INCLUDE INCLIB(GBI)
/*
//LKED.INCLIB   DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*                                                          \*//
//*     AS OF GEOSUPPORT VERSION 10.0,                       \*//
//*     GEO.SUPPORT.PDSE.LOADLIB AND GEO.SUPPORT.LOADLIB     \*//
//*     ARE REQUIRED IN THE STEPLIB (OR JOBLIB) OF THE       \*//
//*     GEOSUPPORT EXECUTION STEP.                           \*//
//*                                                          \*//
//GO.STEPLIB  DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//*           DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*                                                          \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                         \*//
//*   DD STATEMENTS ARE NO LONGER USED TO DEFINE?            \*//
//*   GEOSUPPORT DATA FILES.                                 \*//
//*   DD STATEMENTS ARE NO LONGER INCLUDED FOR THE           \*//
//*   GEOSUPPORT FOREGROUND FILES.                           \*//
//*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER \*//
//*                                                          \*//
//SYSUDUMP DD  SYSOUT=\*,OUTLIM=2000
//SYSPRINT DD  SYSOUT=*
//INFILE   DD  *
122          READE ST
1500         DUANE ST
12-4         BROADWAY
4165-100     BAISLEY BLVD
4165-1000    BAISLEY BLVD
/*
```

```
//
```

SAMPLE ASSEMBLER #1 EXECUTION OUTPUT

```
*****---------- INPUT ADDRESS ------------***** *****--------------------- SELECTED
OUTPUT ITEMS ----------------*****

B HOUSE NUMBER IN-STREET-NAME                    ZIP CD NYPD-PCT SCHLDST LOW CROSS
STREET          HIGH CROSS STREET
- ------------ ------------------------------- ----- -- -------- ------- ----------
--------------- ------------------

1 22           READE ST                        10007 01 005      02      ELK STREET
BROADWAY

1 500          DUANE ST                        *** FUNCTION 1  GRC = 42 REASON CODE
=
                                               *** ADDRESS NUMBER OUT OF RANGE

1 2-4          BROADWAY                        *** FUNCTION 1  WARNING, GRC = 01
REASON CODE = 1
                                               *** ADDR NUMBER ALTERED: RANGE
ASSUMED. USING DIGITS BEFORE DASH ONLY
                                               10004 01 001      02      STONE
STREET              BOWLING GREEN

4 165-100      BAISLEY BLVD                    11434 12 113      28      GUY R
BREWER BOULEVARD    BEDELL STREET

4 165-1000     BAISLEY BLVD                    *** FUNCTION 1  GRC = 13 REASON CODE
= 2
                                               *** ADDRESS NBR 165-1000  HAS MORE
THAN 3 DIGITS AFTER THE DASH.
```

ASSEMBLER SAMPLE PROGRAM #1

- Input Job Stream - MSW

- Input Job Stream - COW

- Output Report

ASSEMBLER SAMPLE PROGRAM #2- Job Stream -MSW

```
//ASMF2SRC JOB   YOUR-JOB-CARD-INFORMATION
```

```
//*
//*******************************************************************
//**  ASSEMBLER SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#2 **
//**                          MSW FORMAT                          **
//*******************************************************************
//STEP1  EXEC  ASMACLG,
//         PARM.ASM='OBJECT,NODECK',
//         PARM.LKED='XREF,LET,LIST,NCAL'
//ASM.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//           DD DSN=A030.GEO.COPYLIB,DISP=SHR
//           DD DSN=SYS1.MACLIB,DISP=SHR
//ASM.SYSIN  DD *
ASMF2SRC TITLE 'SAMPLE GEOSUPPORT ASSEMBLER PROGRAM 2 - MSW FORMAT'
ASMF2SRC CSECT
*****************************************************************
\* THIS PROGRAM MAKES FUNCTION 2 AND D CALLS TO GEOSUPPORT USING  *
\* TWO BOROS AND TWO STREET NAMES SUPPLIED BY AN INSTREAM FILE.   *
\* FUNCTION 2 RETURNS GEOGRAPHIC INFORMATION FOR AN INTERSECTION. *
\* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.   *
\* - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - -  *
\* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE          *
\*       ORIGINAL CALL TO FUNCTION 2, ALL THE CROSS STREET NAMES  *
\*       WOULD HAVE BEEN RETURNED BY FUNCTION 2.                  *
*****************************************************************
*
*********************************************************************
\*                                                                   *
\*  This program will do the following:                              *
\*     * Read an instream record containing 2 borough codes          *
\*       and two street names                                         *
\*                                                                   *
\*     * Build Work Area 1 for a Function 2 call                      *
\*                                                                   *
\*     * Call Function 2                                              *
\*                                                                   *
\*     * Get ZIP code, community district, police precinct, school    *
\*       district, and lists of intersecting street codes.            *
\*       These will be displayed along with the input intersection    *
\*       which consists of 2 borough codes, and 2 street names.       *
\*                                                                   *
\*     * Call Function D to get the street names of all intersecting  *
\*       streets.                                                     *
\*                                                                   *
\*      If it is greater than 01, an error message is printed, and    *
\*      the next input record, if any, is read.                      *
```

```
\*      If it is 01, a warning message is printed, the input record is *
\*      processed, and the next record is read.                        *
\*      If it is zero, the input record is processed, and the next     *
\*      record is read.                                                 *
\*                                                                      *
************************************************************************
 SPACE
         STM   R14,R12,12(R13)   Save caller's registers
         LR    R3,R15
         LA    R12,4095(,R3)     (second base register
         LA    R12,1(,R12)        to accommodate Work Areas 1 and 2)
         USING ASMF2SRC,R3,R12
\* Chain save areas
         LA    R4,MYSAVE
         ST    R13,4(,R4)    Save caller's savearea address
         ST    R4,8(,R13)    Save pgm's savearea adr in caller savearea
         LR    R13,R4        Ensure that R13 points to pgm's savearea
         SPACE 2
         XR    R15,R15                 (set OS return code to zero)
\* Open input and output files
         OPEN  (INFILE,,OUTFILE,(OUTPUT))
         TM    INFILE+48,X'10'   Did input file open successfully?
         BNO   INOPNERR             (no..)
         TM    OUTFILE+48,X'10'  Did output file open successfully?
         BNO   OUTOPNER             (no..)
\* Print report header lines
         SPACE
         PUT   OUTFILE,HDR1
         PUT   OUTFILE,HDR2
         PUT   OUTFILE,HDR3
         PUT   OUTFILE,HDR4
         B     NEXTREC
         SPACE 2
         TITLE 'READ IN-STREAM INPUT AND PREPARE FUNCTION 2 CALL'
\* Read (next) input record
NEXTREC  DS    0H
         GET   INFILE,INREC
\* Move input data to output record for display
         MVC   DBORO1,INBORO1          First borough code
         MVC   DSTRT1,INSTRT1          First street name
         MVC   DBORO2,INBORO2          Second borough code
         MVC   DSTRT2,INSTRT2          Second street name
         SPACE
*****************************************************************
\* TO MAKE A FUNCTION 2 CALL:                                    *
```

```
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                          *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO 2                       *
\*   (3) MOVE THE 1ST INPUT BORO TO WA1'S INPUT BORO CODE FIELD   *
\*   (4) MOVE THE 1ST INPUT STREET TO WA1'S INPUT STREET NAME     *
\*   (5) MOVE THE 2ND INPUT BORO TO WA1'S INPUT BORO CODE 2 FIELD *
\*   (6) MOVE THE 2ND INPUT STREET TO WA1'S INPUT STREET NAME 2   *
\*   (7) CALL GBI WITH 2 WORKAREAS                                *
\*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS                *
*****************************************************************
\* Clear WA1 to blanks
         LA    R8,W1BAL    "To" address for MVCL
         LA    R9,W1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
\* and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         SPACE
\* Prime Work Area 1 for Function 2 call
         MVC   W1IFUNC,=CL2'2 '              Get function code
         MVC   W1IBORO1,INBORO1                  borough code 1
         MVC   W1ISTRT1,INSTRT1                  street name  1
         MVC   W1IBORO2,INBORO2                  borough code 2
         MVC   W1ISTRT2,INSTRT2                  street name  2
         MVC   W1ISNL(L'W1ISNL),=C'25'    Normalized street name length
\* Call Function 2 (2-Work-Area call)
         CALL  GBI,(W1BAL,W2BAL),VL
\* Check Return code
         CLC   W1ORC(2),=C'00'         Good return?
         BE    PROCESS                     Yes, process returned data
\* Handle errors and warnings
ERREXIT  DS    0H
         CLC   W1ORC(2),=C'01'         Warning condition?
         BE    PUTWARN                    Yes, process warning
\*                                             and then process input;
\*                                         otherwise, process error
         MVC   ERFUNC,W1IFUNC              function code
         MVC   ERRET(L'W1ORC),W1ORC        return code
         MVC   ERREAS(L'W1OREASN),W1OREASN reason code
         MVC   ERRMSG(L'W1OERROR),W1OERROR Geosupport error message
         PUT   OUTFILE,ERR1            Print error message 1
         MVC   ERINPUT,DSPLYIN    2 boro codes and 2 street names
         PUT   OUTFILE,ERR2            Print error message 2
         B     NEXTREC
```

```
PUTWARN  DS    0H
         MVC   WRFUNC,W1IFUNC              function code
         MVC   WRRET(L'W1ORC),W1ORC        return code
         MVC   WRREAS(L'W1OREASN),W1OREASN reason code
         MVC   WRNMSG(L'W1OERROR),W1OERROR Geosupport warning message
         PUT   OUTFILE,WARN            Print warning message
         SPACE
\* Handle successful Geosupport calls (Return Code <= 01)
PROCESS  DS    0H
         MVI   OUTFIXED,C'0'      Init. carriage control to dbl-space
         CLC   W1ORC(2),=C'01'    Was a warning issued?
         BNE   MOVEOUT               No..
         MVI   OUTFIXED,C' '         Yes, single-space output instead
MOVEOUT  DS    0H
         MVC   OINPUT,DSPLYIN    Pair of boro codes and street names
         MVC   OZIP,W2F2ZIP      ZIP code
         MVC   OCOMM,W2F2CDN     community district number
         MVC   OPCT,W2F2POP      police precinct
         MVC   OSCHL,W2F2SCH     school district
***** At this point, clear WA1 again, call Function D, and move ******
***** all reported Intersecting Street Names to output          ******
         TITLE 'GET INTERSECTING STREET NAMES, USING FUNCTION D'
         SPACE 2
*************************************************************
\* TO GET THE STREET NAMES FOR INTERSECTING STREET CODES     *
\* MAKE A FUNCTION D CALL:                                   *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                     *
\*   (2) SET THE WA1'S FUNCTION CODE FIELD TO D              *
\*   (3) USE THE COMPACT STREET NAMES OPTION TO OBTAIN       *
\*       STREET NAMES FORMATTED FOR DISPLAY                  *
\*   (4) MOVE THE PACKED BORO AND STREET CODE TO             *
\*       WA1'S INPUT STREET CODE 1 FIELD                     *
\*   (5) CALL GBI WITH 1 WORKAREA                            *
\*   (6) CHECK RETURN CODES FOR ERRORS OR WARNINGS           *
*************************************************************
         SPACE
\* For each street code of intersecting streets, including those input,
\* call Function D to get the corresponding street name
         XR    R4,R4
         MVC   INTWK,W2F2#INT   get count of intersecting streets.
         NI    INTWK,X'0F'      remove zone, leaving numeric
         IC    R4,INTWK         count of intersecting streets.
         LA    R5,W2F2CODE      point to street code(s).
         SPACE
INTRLOOP DS    0H
```

```
\* Clear WA1 to blanks
         LA    R8,W1BAL     "To" address for MVCL
         LA    R9,W1LENGTH      "To" length
         XR    R11,R11        for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
\* and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
         SPACE
         MVC   W1IFUNC(2),=CL2'D '
         MVC   W1ISNL(L'W1ISNL),=C'25'    normalized street name length
         MVI   W1ICMPCT,C'C'              streets to be compacted
         MVC   W1ICDE1(L'W1ICDE1),0(R5)   Intersecting street code
         CALL  GBI,W1BAL,VL   Call Function D
\* Check Return code
         CLC   W1ORC(2),=C'00'         Good return?
         BNE   ERREXIT                     No, error or warning
\*                                          Yes, complete the record
\*                                               and write it out
PFIX     NOP   PVAR
         OI    PFIX+1,X'F0'
         MVC   OINTRSC1,W1OSTRT1
\*  put out the initial output including the first intersecting street
         PUT   OUTFILE,OUTFIXED
         B     NEXTSC     Now get the rest of the street codes, if any
PVAR     DS    0H
        MVC   OINTRSCN,W1OSTRT1
\* Print an output record and get the next intersecting street, if any
         PUT   OUTFILE,OUTVAR
NEXTSC   DS    0H
         LA    R5,4(,R5)    point to next intersecting street code
         BCT   R4,INTRLOOP  if any, and process it;
         NI    PFIX+1,X'0F'    reset 1st-time (fixed/variable) switch
         B     NEXTREC      then, process next input record, if any
         SPACE
EXIT     DS    0H
OUTOPNER DS    0H
         CLOSE (INFILE)
         TM    OUTFILE+48,X'10'   Did OUTFILE open successfully?
         BNO   INOPNERR              No, bypass closing it
         CLOSE (OUTFILE)
INOPNERR DS    0H
         L     R13,4(,R13)
         L     R14,12(,R13)
```

```
         LM    R0,R12,20(R13)
         BR    R14
SPACE 2
PARAMERR DS    0H       parameter error, missing or invalid
         LA    R15,8    rc=8
         B     EXIT
         TITLE 'DATA SECTION - REGISTER ASSIGNMENTS'
R0       EQU   0
R1       EQU   1
R2       EQU   2
R3       EQU   3
R4       EQU   4
R5       EQU   5
R6       EQU   6
R7       EQU   7
R8       EQU   8
R9       EQU   9
R10      EQU   10
R11      EQU   11
R12      EQU   12
R13      EQU   13
R14      EQU   14
R15      EQU   15
         TITLE 'FILE AND RECORD DEFINITIONS'
         PUSH  PRINT
         PRINT NOGEN
INFILE   DCB   DSORG=PS,MACRF=(GM),DDNAME=INFILE,                    *
               RECFM=FB,LRECL=80,BLKSIZE=400,EODAD=EXIT
         SPACE
OUTFILE  DCB   DSORG=PS,MACRF=(PM),DDNAME=SYSPRINT,                  *
               RECFM=FBA,LRECL=133,BLKSIZE=1330
*
         POP PRINT
         SPACE
INREC    DS    0CL80              Input record
INBORO1  DS    CL1                    First borough code
INSTRT1  DS    CL32                   First street name
INBORO2  DS    CL1                    Second borough code
INSTRT2  DS    CL32                   Second street name
         DC    14C' '                 filler
         SPACE
\* Output records: header, normal, warning, and error

         SPACE
\* header records
```

```
HDR1     DC    CL133'1SAMPLE ASSEMBLER \#2 EXECUTION OUTPUT            *
                                                                      *
                                        '
HDR2     DC    CL133'0*****---------------- INPUT INTERSECTION -------C
               --------------***** *****--------------- SELECTED OUTPUT*
                ITEMS ---------------*****'
HDR3     DC    CL133'0B IN-STREET-NAME-1                B IN-STREET-NA*
               ME-2                  ZIP CD NYPD-PCT SCHLDST INTERSECTI*
               NG STREET NAMES            '
HDR4     DC    CL133' - ------------------------------- - ------------*
               ------------------- ----- -- -------- ------- ----------*
               ---------------------------'
         SPACE
\* normal records, i.e., output for valid data
OUTFIXED DS    0CL133                Fixed output
\* Borough codes and street names for each of 2 streets are from input
         DC    C'0'
OINPUT   DS    CL69
OZIP     DS    CL5
         DC    C' '
OCOMM    DS    CL2
         DC    C' '
OPCT     DS    CL3
         DC    6C' '
OSCHL    DS    CL2
         DC    6C' '
OINTRSC1 DS    CL25  Normalized name of first intersecting street
         SPACE
OUTVAR   DS    0CL133 Output line repeated per No. of Intersecting Sts.
         DC    C' '
         DC    95C' '
OINTRSCN DS    CL25  Normalized name of additional intersecting street
         DC    (133-121)C' '
         SPACE
\* warning record
WARN     DS    0CL133
         DC    C'0'
         DC    C'**** FUNCTION '
WRFUNC   DS    CL2
         DC    C' WARNING, GRC = '
WRRET    DS    CL2
         DC    C' REASON CODE = '
WRREAS   DS    CL1
         DC    C'. '
WRNMSG   DS    CL80            Warning message
```

```
         SPACE
\* error records
ERR1     DS    0CL133
         DC    C'0'
         DC    C'***** FUNCTION '
ERFUNC   DS    CL2
         DC    C' GRC = '
ERRET    DS    CL2
         DC    C' REASON = '
ERREAS   DS    CL1
         DC    C'. '
ERRMSG   DS    CL80            Error message
         DC    CL(133-120)' '
         SPACE
ERR2     DS    0CL133
         DC    C' '
ERINPUT  DS    CL69
         DC    CL(133-70)' '
         TITLE 'WORKING VARIABLES, VALUES, ETC.'
#INTER   DS    D        Working field for no. of intersecting streets
MYSAVE   DC    18F'0'
***********************************************************************
***** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     ***
***** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                      ***
***********************************************************************
         COPY  W1BAL              COPY WORK AREA 1
         EJECT
         COPY  W2BAL              COPY WORK AREA 2
         EJECT
         SPACE 2
DSPLYIN  DS    0CL69
DBORO1   DS    CL1
         DC    C' '
DSTRT1   DS    CL32
         DC    C' '
DBORO2   DS    CL1
         DC    C' '
DSTRT2   DS    CL32
         SPACE 2
INTWK    DS    XL1      work field for number of intersecting streets
         TITLE 'CONSTANTS AND LITERAL POOL'
         SPACE 2
         LTORG
         END   ASMF2SRC
//LKED.SYSIN  DD  *
```

```
 INCLUDE INCLIB(GBI)
/*
//LKED.INCLIB   DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*                                                          \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                          \*//
//*  AS OF GEOSUPPORT VERSION 10.0,                          \*//
//*  THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP   \*//
//*  MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:      \*//
//*       A030.GEO.SUPPORT.PDSE.LOADLIB                      \*//
//*       A030.GEO.SUPPORT.LOADLIB                           \*//
//*                                                          \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//GO.STEPLIB DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//           DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                          \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                         \*//
//*   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD,  \*//
//*   ETC) ARE NO LONGER NEEDED AND ARE IGNORED. GEOSUPPORT     \*//
//*   IS TAILORED TO USE STANDARD GEOSUPPORT DATA SET NAMES.    \*//
//*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.   \*//
//*                                                          \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*
//SYSUDUMP DD  SYSOUT=\*,OUTLIM=2000
//SYSPRINT DD  SYSOUT=*
//INFILE   DD  *
1CHAMBERS ST                    1HUDSON ST
1SIXTH AVE                      1W. 8 ST
1DUANE ST                       1READE ST
/*
//
```

ASSEMBLER SAMPLE PROGRAM #2- Job Stream - COW

```
//ASMC2SRC JOB   YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//**  ASSEMBLER SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#2 **
//**                          COW FORMAT                          **
//*******************************************************************
//STEP1  EXEC  ASMACLG,
//         PARM.ASM='OBJECT,NODECK',
```

```
//         PARM.LKED='XREF,LET,LIST,NCAL'
//ASM.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//           DD DSN=A030.GEO.COPYLIB,DISP=SHR
//           DD DSN=SYS1.MACLIB,DISP=SHR
//ASM.SYSIN  DD *
ASMC2SRC TITLE 'SAMPLE GEOSUPPORT ASSEMBLER PROGRAM 2 - COW FORMAT'
ASMC2SRC CSECT
*****************************************************************
\* THIS PROGRAM MAKES FUNCTION 2 AND D CALLS TO GEOSUPPORT USING  *
\* TWO BOROS AND TWO STREET NAMES SUPPLIED BY AN INSTREAM FILE.   *
\* FUNCTION 2 RETURNS GEOGRAPHIC INFORMATION FOR AN INTERSECTION. *
\* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.   *
\* - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - - -  *
\* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE          *
\*       ORIGINAL CALL TO FUNCTION 2, ALL THE CROSS STREET NAMES  *
\*       WOULD HAVE BEEN RETURNED BY FUNCTION 2.                  *
*****************************************************************
*
*********************************************************************
\*                                                                   *
\*  This program will do the following:                              *
\*     * Read an instream record containing 2 borough codes         *
\*       and two street names                                        *
\*                                                                   *
\*     * Build Work Area 1 for a Function 2 call                     *
\*                                                                   *
\*     * Call Function 2                                             *
\*                                                                   *
\*     * Get ZIP code, community district, police precinct, school   *
\*       district, and lists of intersecting street codes.           *
\*       These will be displayed along with the input intersection   *
\*       which consists of 2 borough codes, and 2 street names.      *
\*                                                                   *
\*     * Call Function D to get the street names of all intersecting *
\*       streets.                                                    *
\*                                                                   *
\*      If it is greater than 01, an error message is printed, and   *
\*      the next input record, if any, is read.                      *
\*      If it is 01, a warning message is printed, the input record is *
\*      processed, and the next record is read.                      *
\*      If it is zero, the input record is processed, and the next   *
\*      record is read.                                              *
\*                                                                   *
*********************************************************************
SPACE
```

```
         STM   R14,R12,12(R13)   Save caller's registers
         LR    R3,R15
         LA    R12,4095(,R3)     (second base register
         LA    R12,1(,R12)        to accommodate Work Areas 1 and 2)
         USING ASMC2SRC,R3,R12
\* Chain save areas
         LA    R4,MYSAVE
         ST    R13,4(,R4)    Save caller's savearea address
         ST    R4,8(,R13)    Save pgm's savearea adr in caller savearea
         LR    R13,R4        Ensure that R13 points to pgm's savearea
         SPACE 2
         XR    R15,R15                 (set OS return code to zero)
\* Open input and output files
         OPEN  (INFILE,,OUTFILE,(OUTPUT))
         TM    INFILE+48,X'10'   Did input file open successfully?
         BNO   INOPNERR             (no..)
         TM    OUTFILE+48,X'10'  Did output file open successfully?
         BNO   OUTOPNER             (no..)
\* Print report header lines
         SPACE
         PUT   OUTFILE,HDR1
         PUT   OUTFILE,HDR2
         PUT   OUTFILE,HDR3
         PUT   OUTFILE,HDR4
         B     NEXTREC
         SPACE 2
         TITLE 'READ IN-STREAM INPUT AND PREPARE FUNCTION 2 CALL'
\* Read (next) input record
NEXTREC  DS    0H
         GET   INFILE,INREC
\* Move input data to output record for display
         MVC   DBORO1,INBORO1          First borough code
         MVC   DSTRT1,INSTRT1          First street name
         MVC   DBORO2,INBORO2          Second borough code
         MVC   DSTRT2,INSTRT2          Second street name
         SPACE
*****************************************************************
\* TO MAKE A COW FORMAT FUNCTION 2 CALL:                         *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                         *
\*       AND SET WORK AREA FORMAT FLAG TO 'C'                    *
\*   (2) SET WA1'S FUNCTION CODE FIELD TO 2                      *
\*   (3) MOVE THE 1ST INPUT BORO TO WA1'S INPUT BORO CODE FIELD  *
\*   (4) MOVE THE 1ST INPUT STREET TO WA1'S INPUT STREET NAME    *
\*   (5) MOVE THE 2ND INPUT BORO TO WA1'S INPUT BORO CODE 2 FIELD *
\*   (6) MOVE THE 2ND INPUT STREET TO WA1'S INPUT STREET NAME 2  *
```

```
\*   (7) CALL GBI WITH 2 WORKAREAS                                *
\*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS                *
*****************************************************************
\* Clear WA1 to blanks
         LA    R8,P1BAL    "To" address for MVCL
         LA    R9,P1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
\* and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
*
         MVI   P1IPLIND,C'C'  set work area format indicator to COW
*
         SPACE
\* Prime Work Area 1 for Function 2 call
         MVC   P1IFUNC,=CL2'2 '              Get function code
         MVC   P1IBORO1,INBORO1                  borough code 1
         MVC   P1ISTRT1,INSTRT1                  street name  1
         MVC   P1IBORO2,INBORO2                  borough code 2
         MVC   P1ISTRT2,INSTRT2                  street name  2
         MVC   P1ISNL(L'P1ISNL),=C'25'    Normalized street name length
\* Call Function 2 (2-Work-Area call)
         CALL  GBI,(P1BAL,P2BAL),VL
\* Check Return code
         CLC   P1ORC(2),=C'00'         Good return?
         BE    PROCESS                     Yes, process returned data
\* Handle errors and warnings
ERREXIT  DS    0H
         CLC   P1ORC(2),=C'01'         Warning condition?
         BE    PUTWARN                    Yes, process warning
\*                                             and then process input;
\*                                         otherwise, process error
         MVC   ERFUNC,P1IFUNC              function code
         MVC   ERRET(L'P1ORC),P1ORC        return code
         MVC   ERREAS(L'P1OREASN),P1OREASN reason code
         MVC   ERRMSG(L'P1OERROR),P1OERROR Geosupport error message
         PUT   OUTFILE,ERR1            Print error message 1
         MVC   ERINPUT,DSPLYIN    2 boro codes and 2 street names
         PUT   OUTFILE,ERR2            Print error message 2
         B     NEXTREC
PUTWARN  DS    0H
         MVC   WRFUNC,P1IFUNC              function code
         MVC   WRRET(L'P1ORC),P1ORC        return code
```

```
         MVC   WRREAS(L'P1OREASN),P1OREASN reason code
         MVC   WRNMSG(L'P1OERROR),P1OERROR Geosupport warning message
         PUT   OUTFILE,WARN            Print warning message
         SPACE
\* Handle successful Geosupport calls (Return Code <= 01)
PROCESS  DS    0H
         MVI   OUTFIXED,C'0'      Init. carriage control to dbl-space
         CLC   P1ORC(2),=C'01'    Was a warning issued?
         BNE   MOVEOUT               No..
         MVI   OUTFIXED,C' '         Yes, single-space output instead
MOVEOUT  DS    0H
         MVC   OINPUT,DSPLYIN    Pair of boro codes and street names
         MVC   OZIP,P2F2ZIP      ZIP code
 MVC   OCOMM,P2F2CDN     community district number
         MVC   OPCT,P2F2POP      police precinct
         MVC   OSCHL,P2F2SCH     school district
***** At this point, clear WA1 again, call Function D, and move ******
***** all reported Intersecting Street Names to output          ******
         TITLE 'GET INTERSECTING STREET NAMES, USING FUNCTION D'
         SPACE 2
*************************************************************
\* TO GET THE STREET NAMES FOR INTERSECTING STREET CODES     *
\* MAKE A FUNCTION D CALL:                                   *
\*   (1) INITIALIZE WORKAREA 1 TO SPACES                     *
\*       AND SET WORK AREA FORMAT FLAG TO 'C'                *
\*   (2) SET THE WA1'S FUNCTION CODE FIELD TO D              *
\*   (3) USE THE COMPACT STREET NAMES OPTION TO OBTAIN       *
\*       STREET NAMES FORMATTED FOR DISPLAY                  *
\*   (4) MOVE THE PACKED BORO AND STREET CODE TO             *
\*       WA1'S INPUT STREET CODE 1 FIELD                     *
\*   (5) CALL GBI WITH 1 WORKAREA                            *
\*   (6) CHECK RETURN CODES FOR ERRORS OR WARNINGS           *
*************************************************************
         SPACE
\* For each street code of intersecting streets, including those input,
\* call Function D to get the corresponding street name
         XR    R4,R4
         MVC   INTWK,P2F2#INT   get count of intersecting streets.
         NI    INTWK,X'0F'      remove zone, leaving numeric
         IC    R4,INTWK         count of intersecting streets.
         LA    R5,P2F2CODE      point to street code(s).
         SPACE
INTRLOOP DS    0H
\* Clear WA1 to blanks
         LA    R8,P1BAL    "To" address for MVCL
```

```
         LA    R9,P1LENGTH     "To" length
         XR    R11,R11       for blanking out std WA1,
         ICM   R11,B'1000',=C' '  rather than moving data
\* ...since if the "from" length reg. has lo-order zeroes, MVCL will
\* pad the target area with the pad character of the "from" register
\* and do nothing else (the "from" address register is not used).
         MVCL  R8,R10
*
         MVI   P1IPLIND,C'C'  set work area format indicator to COW
*
         SPACE
         MVC   P1IFUNC(2),=CL2'D '
         MVC   P1ISNL(L'P1ISNL),=C'25'    normalized street name length
         MVI   P1ICMPCT,C'C'              streets to be compacted
*
\* Note  COW - MSW: P1ICDEx is the 10-digit street code (no boro)
\*                  P1IBCDx is the Boro and 10-digit street code
\*                  W1ICDEx is the packed Boro and 5-digit street code
\*                  P2F2CODE is Boro and 5-digit street code list
\*                  W2F2CODE is packed Boro and 5-digit street code list
*
         MVC   P1IBCD1(LB5SC),0(R5)   Intersecting boro and street code
         CALL  GBI,P1BAL,VL   Call Function D
\* Check Return code
         CLC   P1ORC(2),=C'00'         Good return?
         BNE   ERREXIT                     No, error or warning
\*                                          Yes, complete the record
\*                                               and write it out
PFIX     NOP   PVAR
         OI    PFIX+1,X'F0'
         MVC   OINTRSC1,P1OSTRT1
\*  put out the initial output including the first intersecting street
         PUT   OUTFILE,OUTFIXED
         B     NEXTSC     Now get the rest of the street codes, if any
PVAR     DS    0H
         MVC   OINTRSCN,P1OSTRT1
\* Print an output record and get the next intersecting street, if any
         PUT   OUTFILE,OUTVAR
NEXTSC   DS    0H
         LA    R5,LB5SC(,R5) point to next intersecting street code
         BCT   R4,INTRLOOP  if any, and process it;
         NI    PFIX+1,X'0F'    reset 1st-time (fixed/variable) switch
         B     NEXTREC      then, process next input record, if any
         SPACE
EXIT     DS    0H
```

```
OUTOPNER DS    0H
         CLOSE (INFILE)
         TM    OUTFILE+48,X'10'   Did OUTFILE open successfully?
         BNO   INOPNERR              No, bypass closing it
         CLOSE (OUTFILE)
INOPNERR DS    0H
         L     R13,4(,R13)
         L     R14,12(,R13)
         LM    R0,R12,20(R13)
         BR    R14
         SPACE 2
PARAMERR DS    0H       parameter error, missing or invalid
         LA    R15,8    rc=8
         B     EXIT
         TITLE 'DATA SECTION - REGISTER ASSIGNMENTS'
R0       EQU   0
R1       EQU   1
R2       EQU   2
R3       EQU   3
R4       EQU   4
R5       EQU   5
R6       EQU   6
R7       EQU   7
R8       EQU   8
R9       EQU   9
R10      EQU   10
R11      EQU   11
R12      EQU   12
R13      EQU   13
R14      EQU   14
R15      EQU   15
         TITLE 'FILE AND RECORD DEFINITIONS'
         PUSH  PRINT
         PRINT NOGEN
INFILE   DCB   DSORG=PS,MACRF=(GM),DDNAME=INFILE,                    *
               RECFM=FB,LRECL=80,BLKSIZE=400,EODAD=EXIT
         SPACE
OUTFILE  DCB   DSORG=PS,MACRF=(PM),DDNAME=SYSPRINT,                  *
               RECFM=FBA,LRECL=133,BLKSIZE=1330
*
         POP PRINT
         SPACE
INREC    DS    0CL80              Input record
INBORO1  DS    CL1                    First borough code
INSTRT1  DS    CL32                   First street name
```

```
INBORO2  DS    CL1                    Second borough code
INSTRT2  DS    CL32                   Second street name
         DC    14C' '                 filler
         SPACE
\* Output records: header, normal, warning, and error
         SPACE
\* header records
HDR1     DC    CL133'1SAMPLE ASSEMBLER \#2 EXECUTION OUTPUT            *
                                                                      *
                                          '
HDR2     DC    CL133'0*****---------------- INPUT INTERSECTION -------C
               --------------***** *****--------------- SELECTED OUTPUT*
                ITEMS ---------------*****'
HDR3     DC    CL133'0B IN-STREET-NAME-1                B IN-STREET-NA*
               ME-2                  ZIP CD NYPD-PCT SCHLDST INTERSECTI*
               NG STREET NAMES            '
HDR4     DC    CL133' - ------------------------------- - ------------*
               ------------------- ----- -- -------- ------- ----------*
               ---------------------------'
         SPACE
\* normal records, i.e., output for valid data
OUTFIXED DS    0CL133                Fixed output
\* Borough codes and street names for each of 2 streets are from input
         DC    C'0'
OINPUT   DS    CL69
OZIP     DS    CL5
         DC    C' '
OCOMM    DS    CL2
         DC    C' '
OPCT     DS    CL3
         DC    6C' '
OSCHL    DS    CL2
                   DC    6C' '
OINTRSC1 DS    CL25  Normalized name of first intersecting street
         SPACE
OUTVAR   DS    0CL133 Output line repeated per No. of Intersecting Sts.
         DC    C' '
         DC    95C' '
OINTRSCN DS    CL25  Normalized name of additional intersecting street
         DC    (133-121)C' '
         SPACE
\* warning record
WARN     DS    0CL133
         DC    C'0'
         DC    C'**** FUNCTION '
```

```
WRFUNC   DS    CL2
         DC    C' WARNING, GRC = '
WRRET    DS    CL2
         DC    C' REASON CODE = '
WRREAS   DS    CL1
         DC    C'. '
WRNMSG   DS    CL80            Warning message
         SPACE
\* error records
ERR1     DS    0CL133
         DC    C'0'
         DC    C'***** FUNCTION '
ERFUNC   DS    CL2
         DC    C' GRC = '
ERRET    DS    CL2
         DC    C' REASON = '
ERREAS   DS    CL1
         DC    C'. '
ERRMSG   DS    CL80            Error message
         DC    CL(133-120)' '
         SPACE
ERR2     DS    0CL133
         DC    C' '
ERINPUT  DS    CL69
         DC    CL(133-70)' '
         TITLE 'WORKING VARIABLES, VALUES, ETC.'
#INTER   DS    D        Working field for no. of intersecting streets
MYSAVE   DC    18F'0'
***********************************************************************
***** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     ***
***** COPY STATEMENTS) IS STRONGLY ENCOURAGED.                      ***
***********************************************************************
         COPY  P1BAL              COPY WORK AREA 1
         EJECT
         COPY  P2BAL              COPY WORK AREA 2
         EJECT
         SPACE 2
DSPLYIN  DS    0CL69
DBORO1   DS    CL1
         DC    C' '
DSTRT1   DS    CL32
         DC    C' '
DBORO2   DS    CL1
         DC    C' '
DSTRT2   DS    CL32
```

```
         SPACE 2
INTWK    DS    XL1      work field for number of intersecting streets
LB5SC    EQU   6        length of Boro and 5-digit street code
         TITLE 'CONSTANTS AND LITERAL POOL'
         SPACE 2
         LTORG
         END   ASMC2SRC
//LKED.SYSIN  DD  *
 INCLUDE INCLIB(GBI)
/*
//LKED.INCLIB   DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*                                                          \*//


//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                            \*//
//*  AS OF GEOSUPPORT VERSION 10.0,                            \*//
//*  THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP  \*//
//*  MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:     \*//
//*       A030.GEO.SUPPORT.PDSE.LOADLIB                        \*//
//*       A030.GEO.SUPPORT.LOADLIB                             \*//
//*                                                            \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//GO.STEPLIB DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//           DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                            \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                           \*//
//*   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD, \*//
//*   ETC) ARE NO LONGER NEEDED AND ARE IGNORED. GEOSUPPORT    \*//
//*   IS TAILORED TO USE STANDARD GEOSUPPORT DATA SET NAMES.   \*//
//*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.  \*//
//*                                                            \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*
//SYSUDUMP DD  SYSOUT=\*,OUTLIM=2000
//SYSPRINT DD  SYSOUT=*
//INFILE   DD  *
1CHAMBERS ST                    1HUDSON ST
1SIXTH AVE                      1W. 8 ST
1DUANE ST                       1READE ST
/*
//
```

SAMPLE ASSEMBLER #2 EXECUTION OUTPUT

```
          *****----------------- INPUT INTERSECTION ---------------------***** *****----------
----- SELECTED OUTPUT ITEMS ---------------*****

          B IN-STREET-NAME-1                B IN-STREET-NAME-2                 ZIP CD NYPD-
PCT SCHLDST INTERSECTING STREET NAMES
          \- ------------------------------ - ------------------------------ ----- -- -----
--- ------- -------------------------------------

          1 CHAMBERS ST                     1 HUDSON ST                      10007 01 001
02      CHAMBERS STREET

HUDSON STREET

WEST BROADWAY

          1 SIXTH AVE                       1 W. 8 ST                        10014 02 006
02      6 AVENUE

GREENWICH AVENUE

WEST 8 STREET

          ***** FUNCTION 2  GRC = 62 REASON =  . READE STREET & DUANE STREET DO NOT INTERSECT
          1 DUANE ST                        1 READE ST
```

PL/1 SAMPLE PROGRAM #1

- Input Job Stream - MSW

- Input Job Stream - COW

- Output Report

PL/1 SAMPLE PROGRAM #1 – Job Stream - MSW

```
        //PL1F1BAT  JOB YOUR-JOB-CARD-INFORMATION
        //*
        //*******************************************************************
        //***  PL1 SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1. ******
        //***                  (MSW FORMAT)                            ******
        //*******************************************************************
        //STEP1      EXEC IBMZCPLG,REGION=0M,GOPGM='PL1F1SC',
        //           PARM.PLI='S,GS,INCLUDE',
```

```
//          PARM.LKED='AMODE(31)'
//PLI.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//          DD DSN=A030.GEO.COPYLIB,DISP=SHR
//SYSIN     DD *
 PL1F1SC:    PROC OPTIONS(MAIN);
   /*****************************************************************/
   /* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING \*/
   /* BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.\*/
   /* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     \*/
   /* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  \*/
   /* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
   /* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE         \*/
   /*       ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET       \*/
   /*       NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 1.           \*/
   /*****************************************************************/

 DCL EOF                      BIT(1)  INIT('0'B),
     YES                      BIT(1)  INIT('1'B),
     NO                       BIT(1)  INIT('0'B),
     ADDR                     BUILTIN,
     (I,J)                    FIXED BIN(15) INIT(0);

 /*****************************************************************/
 /**************   GBI DECLARATION BELOW IS REQUIRED   **************/
 /*** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE *****/
 /*** %INCLUDE STATEMENTS) IS STRONGLY ENCOURAGED.           *******/
 /*****************************************************************/
 DCL GBI                      ENTRY OPTIONS(ASM,INTER);
 %INCLUDE W1PL1;
 %INCLUDE W2PL1;

 /***** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DECLARATION *****/
 DCL INFILE FILE STREAM INPUT;
 DCL IN_BORO                  CHAR(01),
     IN_HOUSENUM              CHAR(12),
     IN_STREET_NAME           CHAR(32);

 /******** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT *********/
 DCL SYSPRINT FILE STREAM OUTPUT PRINT;
 ON ENDPAGE(SYSPRINT)
   PUT EDIT('SAMPLE PL1 PROGRAM \#1 EXECUTION OUTPUT',
      '*****---------- INPUT ADDRESS ------------***** '||
      '*****---------------------'||
      ' SELECTED OUTPUT ITEMS -----------------------*****',
      'B HOUSE NUMBER IN-STREET-NAME                   '||
```

```
      '  ZIP CD NYPD-PCT SCHLDST '||
      'LOW CROSS STREET          HIGH CROSS STREET        ',
      '_ ____________ '||(32)'_'||' '||
      '_____ __ ________ _______ '||
      (25)'_'||' '||(25)'_')
     (PAGE,COL(1),A,SKIP(2),COL(1),A,COL(1),A,SKIP(0),COL(1),A);
 OPEN FILE(SYSPRINT) LINESIZE(133);
 SIGNAL ENDPAGE(SYSPRINT);
 /*****************************************************************/


ON ENDFILE(INFILE)  BEGIN; EOF=YES; GOTO ENDLOOP;  END;
 OPEN FILE(INFILE);

 DO WHILE (EOF = NO);

   /********** REPLACE CODE BELOW WITH YOUR OWN INPUT *************/
   GET FILE(INFILE) EDIT(IN_BORO,IN_HOUSENUM,IN_STREET_NAME)
                       (COL(1),A(1),X(1),A(12),X(1),A(32));

   /*****************************************************************/
   /* TO MAKE A FUNCTION 1 CALL:                                    \*/
   /*   (1) INITIALIZE WORKAREA 1 TO SPACES                         \*/
   /*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                      \*/
   /*   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD      \*/
   /*   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER \*/
   /*       FIELD                                                   \*/
   /*   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  \*/
   /*   (6) CALL GBI WITH 2 WORKAREAS                               \*/
   /*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS               \*/
   /*****************************************************************/
   WORK1PL1 = ' ';
   GEO_WA1_IN_FUNCTION_1 = '1';
   GEO_WA1_IN_BORO       = IN_BORO;
   GEO_WA1_IN_HOUSENUM   = IN_HOUSENUM;
   GEO_WA1_IN_STREET_1   = IN_STREET_NAME;

   CALL GBI(W1PL1,W2PL1);

   IF GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 ¬= '00' &
      GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 ¬= '01'
   THEN DO;
          /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
          PUT EDIT(IN_BORO,IN_HOUSENUM,IN_STREET_NAME,
                   '*** FUNCTION 1 GRC =',
```

```
                GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2,
                'REASON CODE =',GEO_WA1_OUT_REASON_CODE,
                '*** ',GEO_WA1_OUT_ERROR_MESSAGE)
               (SKIP(2),COL(1),(7)(A,X(1)),SKIP(1),COL(49),A,A);
     END;
ELSE DO;
       PUT EDIT(IN_BORO,IN_HOUSENUM,IN_STREET_NAME)
               (SKIP(2),COL(1),(3)(A,X(1)));
       IF GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 = '01'
       THEN DO;
              /** INSERT YOUR OWN WARNING HANDLING ROUTINE HERE \**/
              PUT EDIT('*** FUNCTION 1 WARNING, GRC =',
                       GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2,
                       'REASON CODE =',GEO_WA1_OUT_REASON_CODE,
                       '*** ',GEO_WA1_OUT_ERROR_MESSAGE)
                      (COL(49),(4)(A,X(1)),SKIP(1),COL(49),A,A);
            END;
       /*****************************************************/
       /***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ****/
       /***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS    ****/
       /*****************************************************/
       PUT EDIT(GEO_WA2_FN1_ZIP,GEO_WA2_FN1_COMDIST_NUMBER,
                GEO_WA2_FN1_POL_PRECINCT,GEO_WA2_FN1_SCHOOLDIST)
               (COL(49),(3)(A,X(1)),X(5),A);
       /*************************************************************/
       /* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND \*/


/* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE   \*/
       /* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS    \*/
       /* FROM THE HIGH AND LOW STREET CODE LISTS CALL            \*/
       /* FUNCTION D:                                             \*/
       /*   (1) INITIALIZE WORKAREA 1 TO SPACES                   \*/
       /*   (2) SET WA1'S FUNCTION CODE FIELD TO D                \*/
       /*   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED     \*/
       /*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE    \*/
       /*              HAS SPACE FOR ONLY 25 CHARACTERS)          \*/
       /*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN     \*/
       /*       STREET NAMES FORMATTED FOR DISPLAY                \*/
       /*   (5) MOVE WA2'S LOW PBSC FIELD TO WA1'S INPUT STREET   \*/
       /*       CODE 1 FIELD                                      \*/
       /*   (6) MOVE WA2'S HIGH PBSC FIELD TO WA1'S INPUT STREET  \*/
       /*       CODE 2 FIELD                                      \*/
       /*   (7) CALL GBI WITH 1 WORKAREA                          \*/
       /*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS         \*/
```

```
          /*********************************************************/
          WORK1PL1 = ' ';
          GEO_WA1_IN_FUNCTION_1        = 'D';
          GEO_WA1_IN_SNL               = '25';
          GEO_WA1_IN_COMPACT_NAME_FLAG = 'C';
          GEO_WA1_IN_STREETCODE_1      = GEO_WA2_FN1_LOW_PBSC(1);
          GEO_WA1_IN_STREETCODE_2      = GEO_WA2_FN1_HI_PBSC(1);
          CALL GBI(W1PL1);
          IF GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 = '00'
          THEN DO;
                 /******** INSERT YOUR OWN CODE HERE *******/
                 PUT EDIT(GEO_WA1_OUT_STREET_1,GEO_WA1_OUT_STREET_2)
                         (COL(75),A(25),X(1),A(25));
               END;
          ELSE DO;
                 /*** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE \***/
                 PUT EDIT(IN_BORO,IN_HOUSENUM,IN_STREET_NAME,
                          '*** FUNCTION D GRC =',
                          GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2,
                          'REASON CODE =',GEO_WA1_OUT_REASON_CODE,',',
                          '*** ',GEO_WA1_OUT_ERROR_MESSAGE)
                         (SKIP(2),COL(1),(8)(A,X(1)),
                          SKIP(1),COL(49),A,A);
               END;
        END;
 ENDLOOP:  END;
 CLOSE FILE(INFILE);
 END PL1F1SC;
/*
//LKED.SYSIN  DD *
  INCLUDE INCLIB(GBI)
/*
//INCLIB      DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                              \*//
//*   THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP    \*//
//*   MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:       \*//
//*        A030.GEO.SUPPORT.PDSE.LOADLIB                          \*//
//*        A030.GEO.SUPPORT.LOADLIB                               \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//GO.STEPLIB  DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//GO.SYSLMOD  DD DSN=&&GOSET,DISP=(OLD,DELETE)
```

```
//*
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                              \*//
//*   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD,  \*//
//*   ETC) ARE NO LONGER NEEDED AND ARE IGNORED. GEOSUPPORT     \*//
//*   IS TAILORD TO USE STANDARD GEOSUPPORT DATA SET NAMES.     \*//
//*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.   \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*
//GO.SYSPRINT DD SYSOUT=A
//GO.INFILE   DD *
1 22           READE ST
1 500          DUANE ST
1 2-4          BROADWAY
4 165-100      BAISLEY BLVD
4 165-1000     BAISLEY BLVD
/*
//
```

PL/1 SAMPLE PROGRAM #1 – Job Stream - COW

```
//PL1C1SRC  JOB YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//***  PL1 SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1. ******
//***                   (COW FORMAT)                          ******
//*******************************************************************
//STEP1      EXEC IBMZCPLG,REGION=0M,GOPGM='PL1C1SC',
//           PARM.PLI='S,GS,INCLUDE',
//           PARM.LKED='AMODE(31),LIST'
//PLI.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//           DD DSN=A030.GEO.COPYLIB,DISP=SHR
//SYSIN      DD *
 PL1C1SC:   PROC OPTIONS(MAIN);
   /*****************************************************************/
   /* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING \*/
   /* BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.\*/
   /* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     \*/
   /* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  \*/
   /* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
   /* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE         \*/
   /*       ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET       \*/
   /*       NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 1.           \*/
   /*****************************************************************/
```

```
DCL EOF                     BIT(1)  INIT('0'B),
    YES                     BIT(1)  INIT('1'B),
    NO                      BIT(1)  INIT('0'B),
    ADDR                    BUILTIN,
    (I,J)                   FIXED BIN(15) INIT(0);

/*******************************************************************/
/**************   GBI DECLARATION BELOW IS REQUIRED   **************/
/*** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE *****/
/*** %INCLUDE STATEMENTS) IS STRONGLY ENCOURAGED.           *******/
/*******************************************************************/
DCL GBI                     ENTRY OPTIONS(ASM,INTER);
%INCLUDE P1PL1;
%INCLUDE P2PL1;

/***** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DECLARATION *****/
DCL INFILE FILE STREAM INPUT;
DCL IN_BORO                 CHAR(01),
    IN_HOUSENUM             CHAR(12),
    IN_STREET_NAME          CHAR(32);

/******** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT *********/
DCL SYSPRINT FILE STREAM OUTPUT PRINT;
ON ENDPAGE(SYSPRINT)
  PUT EDIT('SAMPLE PL1 PROGRAM \#1 EXECUTION OUTPUT',
     '*****---------- INPUT ADDRESS ------------***** '||
     '*****--------------------'||
     ' SELECTED OUTPUT ITEMS -----------------------*****',
     'B HOUSE NUMBER IN-STREET-NAME                   '||
     '  ZIP CD NYPD-PCT SCHLDST '||
     'LOW CROSS STREET          HIGH CROSS STREET        ',
     '_ ____________ '||(32)'_'||' '||
     '_____ __ ________ _______ '||
     (25)'_'||' '||(25)'_')
    (PAGE,COL(1),A,SKIP(2),COL(1),A,COL(1),A,SKIP(0),COL(1),A);
OPEN FILE(SYSPRINT) LINESIZE(133);
SIGNAL ENDPAGE(SYSPRINT);


*******************************************************************/

ON ENDFILE(INFILE)  BEGIN; EOF=YES; GOTO ENDLOOP;  END;
OPEN FILE(INFILE);
```

```
DO WHILE (EOF = NO);

  /********** REPLACE CODE BELOW WITH YOUR OWN INPUT *************/
  GET FILE(INFILE) EDIT(IN_BORO,IN_HOUSENUM,IN_STREET_NAME)
                      (COL(1),A(1),X(1),A(12),X(1),A(32));

  /*****************************************************************/
  /* TO MAKE A FUNCTION 1 CALL:                                    \*/
  /*   (1) INITIALIZE WORKAREA 1 TO SPACES                         \*/
  /*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                      \*/
  /*   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD      \*/
  /*   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER \*/
  /*       FIELD                                                   \*/
  /*   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  \*/
  /*   (6) CALL GBI WITH 2 WORKAREAS                               \*/
  /*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS               \*/
  /*****************************************************************/
  WORK1PL1 = ' ';
  PIWA1_IN_FUNCTION_1 = '1';
  PIWA1_IN_BORO_1     = IN_BORO;
   /* for cow format the field house_number has length=16 \*/
  PIWA1_IN_HOUSENUM_DISPLAY  = IN_HOUSENUM;
  PIWA1_IN_STREET_1   = IN_STREET_NAME;
  PIWA1_IN_PLATFORM_INDICATOR = 'C';
  /*****************************************************************/
  /*****************************************************************/
  /* AS OF GEOSUPPORT 10.1,                                       \*/
  /* TO RECEIVE ROADBED-SPECIFIC INFORMATION,                     \*/
  /* SET THE ROADBED REQUEST SWITCH TO 'R', AS FOLLOWS:           \*/
  /* PIWA1_IN_ROADBED_REQ_SWITCH = 'R';                           \*/
  /*****************************************************************/

  CALL GBI(P1PL1,P2PL1);

  IF PIWA1_OUT_RETURN_CODE ¬= '00' & PIWA1_OUT_RETURN_CODE ¬= '01'
  THEN DO;
         /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
         PUT EDIT(IN_BORO,IN_HOUSENUM,IN_STREET_NAME,
                  '*** FUNCTION 1 GRC =',PIWA1_OUT_RETURN_CODE,
                  'REASON CODE =',PIWA1_OUT_REASON_CODE,
                  '*** ',PIWA1_OUT_ERROR_MESSAGE)
                 (SKIP(2),COL(1),(7)(A,X(1)),SKIP(1),COL(49),A,A);
       END;
  ELSE DO;
         PUT EDIT(IN_BORO,IN_HOUSENUM,IN_STREET_NAME)
```

```
        (SKIP(2),COL(1),(3)(A,X(1)));
IF PIWA1_OUT_RETURN_CODE = '01'
THEN DO;
       /** INSERT YOUR OWN WARNING HANDLING ROUTINE HERE \**/
       PUT EDIT('*** FUNCTION 1 WARNING, GRC =',
                PIWA1_OUT_RETURN_CODE,
                'REASON CODE =',PIWA1_OUT_REASON_CODE,
                '*** ',PIWA1_OUT_ERROR_MESSAGE)
               (COL(49),(4)(A,X(1)),SKIP(1),COL(49),A,A);
     END;

/*****************************************************/
/***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ****/
/***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS    ****/
/*****************************************************/
PUT EDIT(PIWA2_FN1_ZIP,PIWA2_FN1_COM_DIST_NUM,
         PIWA2_FN1_POL_PRECINCT,PIWA2_FN1_SCHL_DIST)
        (COL(49),(3)(A,X(1)),X(5),A);
/*************************************************************/
/* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND \*/
/* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE   \*/
/* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS    \*/
/* FROM THE HIGH AND LOW STREET CODE LISTS CALL            \*/
/* FUNCTION D:                                             \*/
/*   (1) INITIALIZE WORKAREA 1 TO SPACES                   \*/
/*   (2) SET WA1'S FUNCTION CODE FIELD TO D                \*/
/*   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED     \*/
/*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE    \*/
/*              HAS SPACE FOR ONLY 25 CHARACTERS)          \*/
/*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN     \*/
/*       STREET NAMES FORMATTED FOR DISPLAY                \*/
/*   (5) MOVE WA2'S LOW B5SC FIELD TO WA1'S INPUT STREET   \*/
/*       CODE 1 FIELD                                      \*/
/*   (6) MOVE WA2'S HIGH B5SC FIELD TO WA1'S INPUT STREET  \*/
/*       CODE 2 FIELD                                      \*/
/*   (7) CALL GBI WITH 1 WORKAREA                          \*/
/*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS         \*/
/*************************************************************/
WORK1PL1 = ' ';
PIWA1_IN_PLATFORM_INDICATOR = 'C';
PIWA1_IN_FUNCTION_1        = 'D';
PIWA1_IN_SNL               = '25';
PIWA1_IN_SN_NORM_FORMAT    = 'C';

PIWA1_IN_BORO_1  = SUBSTR(PIWA2_FN1_LOW_B5SC(1),1,1);
```

```
          PIWA1_IN_10SC_1  = SUBSTR(PIWA2_FN1_LOW_B5SC(1),2,5);
          PIWA1_IN_BORO_2  = SUBSTR(PIWA2_FN1_HI_B5SC(1),1,1);
          PIWA1_IN_10SC_2  = SUBSTR(PIWA2_FN1_HI_B5SC(1),2,5);


          CALL GBI(P1PL1);
          IF PIWA1_OUT_RETURN_CODE = '00'
          THEN DO;
                 /******** INSERT YOUR OWN CODE HERE *******/
                 PUT EDIT(PIWA1_OUT_STREET_1,PIWA1_OUT_STREET_2)
                         (COL(75),A(25),X(1),A(25));
               END;
          ELSE DO;
                 /*** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE \***/
                 PUT EDIT(IN_BORO,IN_HOUSENUM,IN_STREET_NAME,
                          '*** FUNCTION D GRC =',
                          PIWA1_OUT_RETURN_CODE,
                          'REASON CODE =',PIWA1_OUT_REASON_CODE,',',
                          '*** ',PIWA1_OUT_ERROR_MESSAGE)
                         (SKIP(2),COL(1),(8)(A,X(1)),
                          SKIP(1),COL(49),A,A);
               END;
        END;
 ENDLOOP:  END;
 CLOSE FILE(INFILE);
 END PL1C1SC;
/*
//LKED.SYSIN  DD *
INCLUDE INCLIB(GBI)
/*
//INCLIB      DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                                \*//
//*   THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP  \*//
//*   MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:     \*//
//*        A030.GEO.SUPPORT.PDSE.LOADLIB                        \*//
//*        A030.GEO.SUPPORT.LOADLIB                             \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//GO.STEPLIB  DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//GO.SYSLMOD  DD DSN=&&GOSET,DISP=(OLD,DELETE)
//*
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                                \*//
```

```
//*   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD,  \*//
//*   ETC) ARE NO LONGER NEEDED AND ARE IGNORED. GEOSUPPORT     \*//
//*   IS TAILORD TO USE STANDARD GEOSUPPORT DATA SET NAMES.     \*//
//*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.   \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*
//GO.SYSPRINT DD SYSOUT=A
//GO.INFILE   DD *
1 22           READE ST
1 500          DUANE ST
1 2-4          BROADWAY
4 165-100      BAISLEY BLVD
4 165-1000     BAISLEY BLVD
/*
//
```

SAMPLE PL/1 PROGRAM #1 EXECUTION OUTPUT

```
        *****---------- INPUT ADDRESS ------------***** *****--------------------- SELECTED
OUTPUT ITEMS -----------------------*****

         B HOUSE NUMBER IN-STREET-NAME                     ZIP CD NYPD-PCT SCHLDST LOW CROSS
STREET          HIGH CROSS STREET
         - ------------ ------------------------------- ----- -- -------- ------- ------------
------------- -------------------------

         1 22           READE ST                         10007 01 005      02      ELK STREET
BROADWAY

         1 500          DUANE ST                         *** FUNCTION 1 GRC = 42 REASON CODE =
                                                         *** ADDRESS NUMBER OUT OF RANGE

         1 2-4          BROADWAY                         *** FUNCTION 1 WARNING, GRC = 01
REASON CODE = 1
                                                         *** ADDR NUMBER ALTERED: RANGE
ASSUMED. USING DIGITS BEFORE DASH ONLY
                                                         10004 01 001      02      STONE STREET
BOWLING GREEN

         4 165-100      BAISLEY BLVD                     11434 12 113      28      GUY R BREWER
BOULEVARD    BEDELL STREET

         4 165-1000     BAISLEY BLVD                     *** FUNCTION 1 GRC = 13 REASON CODE =
2
                                                         *** ADDRESS NBR 165-1000  HAS MORE
THAN 3 DIGITS AFTER THE DASH.
```

PL/1 SAMPLE PROGRAM #2

- Input Job Stream - MSW

- Input Job Stream - COW

- Output Report

PL/1 SAMPLE PROGRAM #2 –Job Stream - MSW

```
          //PL1F2SRC  JOB YOUR-JOB-CARD-INFORMATION
          //*
          //*******************************************************************
          //***  PL1 SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#2. ******
          //***                   (MSW FORMAT)                            ******
          //*******************************************************************
```

```
//STEP1      EXEC IBMZCPLG,REGION=0M,GOPGM='PL1F2SR',
//           PARM.PLI='S,GS,INCLUDE',
//           PARM.LKED='AMODE(31)'
//PLI.SYSLIB DD DSN=A030.GEO.COPYLIB2,DISP=SHR
//           DD DSN=A030.GEO.COPYLIB,DISP=SHR
//SYSIN      DD *
 PL1F2SR:    PROC OPTIONS(MAIN);
   /*****************************************************************/
   /* THIS PROGRAM MAKES FUNCTION 2 AND D CALLS TO GEOSUPPORT USING  \*/
   /* TWO BOROS AND TWO STREET NAMES SUPPLIED BY AN INSTREAM FILE.   \*/
   /* FUNCTION 2 RETURNS GEOGRAPHIC INFORMATION FOR AN INTERSECTION. \*/
   /* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.   \*/
   /* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *  \*/
   /* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE          \*/
   /*       ORIGINAL CALL TO FUNCTION 2, ALL THE CROSS STREET        \*/
   /*       NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 2.            \*/
   /*****************************************************************/

 DCL EOF                      BIT(1)  INIT('0'B),
     YES                      BIT(1)  INIT('1'B),
     NO                       BIT(1)  INIT('0'B),
     ADDR                     BUILTIN,
     (I,J)                    FIXED BIN(15) INIT(0);

 /**************** GBI DECLARATION BELOW IS REQUIRED ****************/
 DCL GBI                      ENTRY OPTIONS(ASM,INTER);

 /*****************************************************************/
 /** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BY THE %INCLUDE  \**/
 /** STATEMENTS) IS STRONGLY ENCOURAGED                            \**/
 /*****************************************************************/
 %INCLUDE W1PL1;
 %INCLUDE W2PL1;

 /***** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DECLARATION *****/
 DCL INFILE FILE STREAM INPUT;
 DCL IN_BORO1                 CHAR(01),
     IN_STREET_NAME1          CHAR(32),
     IN_BORO2                 CHAR(01),
     IN_STREET_NAME2          CHAR(32);

 /******** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT *********/
 DCL SYSPRINT FILE STREAM OUTPUT PRINT;
 ON ENDPAGE(SYSPRINT)
   PUT EDIT('SAMPLE PL1 PROGRAM \#2 EXECUTION OUTPUT',
```

```
      '*****----------------- INPUT INTERSECTION '||(22)'-'||'***** '||
      '*****------------ SELECTED OUTPUT ITEMS -------------*****',
      'B IN-STREET-NAME-1'||(17)' '||'B IN-STREET-NAME-2'||(17)' '||
      '  ZIP CD NYPD-PCT SCHLDST INTERSECTING STREET NAMES        ',
      '_ '||(32)'\_'||' _ '||(32)'\_'||' '||
      '_____ __ ________ _______ '||(32)'\_')
    (PAGE,COL(1),A,SKIP(2),COL(1),A,COL(1),A,SKIP(0),COL(1),A);
OPEN FILE(SYSPRINT) LINESIZE(133);
SIGNAL ENDPAGE(SYSPRINT);
/*****************************************************************/
ON ENDFILE(INFILE)  BEGIN; EOF=YES; GOTO ENDLOOP;  END;
OPEN FILE(INFILE);

DO WHILE (EOF = NO);

  /********** REPLACE CODE BELOW WITH YOUR OWN INPUT *************/
  GET FILE(INFILE) EDIT(IN_BORO1,IN_STREET_NAME1,
                        IN_BORO2,IN_STREET_NAME2)
                       (COL(1),A(1),X(1),A(32),X(1),A(1),X(1),A(32));

  /*****************************************************************/
  /* TO MAKE A FUNCTION 2 CALL:                                    \*/
  /*   (1) INITIALIZE WORKAREA 1 TO SPACES                         \*/
  /*   (2) SET WA1'S FUNCTION-CODE TO 2                            \*/
  /*   (3) MOVE THE 1ST INPUT BORO TO WA1'S INPUT BORO CODE FIELD  \*/
  /*   (4) MOVE THE 1ST INPUT STREET TO WA1'S INPUT STREET NAME    \*/
  /*       FIELD                                                   \*/
  /*   (5) MOVE THE 2ND INPUT BORO TO WA1'S INPUT BORO CODE 2 FIELD \*/
  /*   (6) MOVE THE 2ND INPUT STREET TO WA1'S INPUT STREET NAME 2  \*/
  /*       FIELD                                                   \*/
  /*   (7) CALL GBI WITH 2 WORKAREAS                               \*/
  /*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS               \*/
  /*****************************************************************/
  WORK1PL1 = ' ';
  GEO_WA1_IN_FUNCTION_1 = '2';
  GEO_WA1_IN_BORO       = IN_BORO1;
  GEO_WA1_IN_STREET_1   = IN_STREET_NAME1;
  GEO_WA1_IN_BORO_2     = IN_BORO2;
  GEO_WA1_IN_STREET_2   = IN_STREET_NAME2;

  CALL GBI(W1PL1,W2PL1);

  IF GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 ¬= '00' &
     GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 ¬= '01'
  THEN DO;
```

```
        /****** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *******/
        PUT EDIT('***** FUNCTION 2 GRC =',
                 GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2,
                 'REASON =',GEO_WA1_OUT_REASON_CODE,',',
                 GEO_WA1_OUT_ERROR_MESSAGE,
                 IN_BORO1,IN_STREET_NAME1,IN_BORO2,IN_STREET_NAME2)
                (SKIP(2),COL(1),(3)(A,X(1)),A,A,X(1),A,
                 SKIP(1),(4)(A,X(1)));
     END;
 ELSE
     IF GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 = '01'
     THEN DO;
            /*** INSERT YOUR OWN WARNING HANDLING ROUTINE HERE ****/
            PUT EDIT('***** FUNCTION 2 WARNING, GRC = '||
                     GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2||', '||
                     'REASON CODE = '||GEO_WA1_OUT_REASON_CODE||
                     ', '||GEO_WA1_OUT_ERROR_MESSAGE,
                     IN_BORO1,IN_STREET_NAME1,
                     IN_BORO2,IN_STREET_NAME2)
                    (SKIP(2),COL(1),A,SKIP(1),(4)(A,X(1)));
          END;

 IF GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 = '00'|
    GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 = '01'
 THEN DO;
        /*************************************************************/
/***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ***********/
        /***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS.         *****/
        /*************************************************************/
        PUT EDIT(IN_BORO1,IN_STREET_NAME1,IN_BORO2,IN_STREET_NAME2,
                 GEO_WA2_FN2_ZIP,GEO_WA2_FN2_COMDIST_NUMBER,
                 GEO_WA2_FN2_POL_PRECINCT,GEO_WA2_FN2_SCHOOLDIST)
                (SKIP(2),COL(1),(7)(A,X(1)),X(5),A);
        DO J = 1 TO GEO_WA2_FN2_NUM_OF_INTERSECTS;
          /*********************************************************/
          /* TO GET STREET NAMES FOR INTERSECTING STREET CODES   \*/
          /* MAKE A FUNCTION D CALL:                             \*/
          /*   (1) INITIALIZE WORKAREA 1 TO SPACES               \*/
          /*   (2) SET THE WA1'S FUNCTION CODE FIELD TO D        \*/
          /*   (3) USE THE COMPACT STREET NAMES OPTION TO OBTAIN \*/
          /*       STREET NAMES FORMATTED FOR DISPLAY            \*/
          /*   (4) MOVE THE PACKED BORO AND STREET CODE TO       \*/
          /*       WA1'S INPUT STREET CODE 1 FIELD               \*/
          /*   (5) CALL GBI WITH 1 WORKAREA                      \*/
          /*   (6) CHECK RETURN CODES FOR ERRORS OR WARNINGS     \*/
```

```
            /*****************************************************/
            WORK1PL1 = ' ';
            GEO_WA1_IN_FUNCTION_1        = 'D';
            GEO_WA1_IN_COMPACT_NAME_FLAG = 'C';
            GEO_WA1_IN_STREETCODE_1 = GEO_WA2_FN2_INTERSECT_PBSC(J);
            CALL GBI(W1PL1);
            IF GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2 = '00'
            THEN DO;
                   /******** INSERT YOUR OWN CODE HERE *******/
                   PUT EDIT(GEO_WA1_OUT_STREET_1)  (COL(97),A);
                 END;
            ELSE DO;
                   /** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE \**/
                   PUT EDIT('***** FUNCTION D GRC =',
                            GEO_WA1_OUT_RC_1||GEO_WA1_OUT_RC_2,
                            'REASON =',GEO_WA1_OUT_REASON_CODE,',',
                            GEO_WA1_OUT_ERROR_MESSAGE)
                           (SKIP(2),COL(1),(6)(A,X(1)));
                 END;
          END;
        END;
 ENDLOOP:  END;
 CLOSE FILE(INFILE);
 END PL1F2SR;
/*
//LKED.SYSIN  DD *
  INCLUDE INCLIB(GBI)
/*
//INCLIB      DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                              \*//
//*   THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP    \*//
//*   MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:       \*//
//*        A030.GEO.SUPPORT.PDSE.LOADLIB                          \*//
//*        A030.GEO.SUPPORT.LOADLIB                               \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//GO.STEPLIB  DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//GO.SYSLMOD  DD DSN=&&GOSET,DISP=(OLD,DELETE)
//*
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*   AS OF GEOSUPPORT VERSION 10.0,                              \*//
//*   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD,    \*//
//*   ETC) ARE NO LONGER NEEDED AND ARE IGNORED. GEOSUPPORT       \*//
```

```
//*   IS TAILORD TO USE STANDARD GEOSUPPORT DATA SET NAMES.     \*//
//*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.   \*//
//* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*
//GO.SYSPRINT DD SYSOUT=A
//GO.INFILE   DD *
1 CHAMBERS ST                      1 HUDSON ST
1 SIXTH AVE                        1 W. 8 ST
1 DUANE ST                         1 READE ST
/*
//
```

SAMPLE PL1 PROGRAM #2 EXECUTION OUTPUT

```
*****---------------- INPUT INTERSECTION ----------------------***** *****----------
-- SELECTED OUTPUT ITEMS -------------*****

 B IN-STREET-NAME-1                B IN-STREET-NAME-2                  ZIP CD NYPD-
PCT SCHLDST INTERSECTING STREET NAMES
 \- ------------------------------- - ------------------------------- ----- -- ----
---- -------- -------------------------------

 1 CHAMBERS ST                     1 HUDSON ST                       10007 01 001
02       CHAMBERS STREET

HUDSON STREET

WEST BROADWAY

 1 SIXTH AVE                       1 W. 8 ST                         10014 02 006
02       6 AVENUE

GREENWICH AVENUE

WEST 8 STREET

 ***** FUNCTION 2 GRC = 62 REASON =  , READE STREET & DUANE STREET DO NOT INTERSECT
 1 DUANE ST                        1 READE ST
```

C SAMPLE PROGRAM #1

- Input Job Stream - MSW

- Input Job Stream - COW

- Output Report

C SAMPLE PROGRAM #1 – Job Stream -MSW

```
//CCCF1SRC JOB YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//***  C SAMPLE MSW BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1  ****
//*******************************************************************
//STEP1 EXEC EDCCLG,
//      CPARM='SS,OPT,OFFSET,SOURCE,XREF,LIST'
//COMPILE.SYSPRINT DD SYSOUT=A
//COMPILE.SYSLIB   DD
//                 DD
//                 DD  DSNAME=A030.GEO.COPYLIB,DISP=SHR
//COMPILE.SYSIN    DD *
   /*****************************************************************/
   /* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING \*/
   /* BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.\*/
   /* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     \*/
   /* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  \*/
   /* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
   /* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE         \*/
   /*       ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET       \*/
   /*       NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 1.           \*/
   /*****************************************************************/

#include <stdio.h>
#include <string.h>

 /*******************************************************************/
 /*** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     \***/
 /*** #INCLUDE STATEMENTS) IS STRONGLY ENCOURAGED.                  \***/
 /*******************************************************************/
#include <wac.h>

 /**************   GBI OS LINKAGE BELOW IS REQUIRED   **************/
   #pragma linkage (GBI,OS)
   long GBI(void \*, ...);

 /***** THE WORK AREA LAYOUTS MUST BE DECLARED USING THE TYPEDEFS \***/
 /***** IN THE GEOSUPPORT COPY FILE.                             \***/
   C_WA1 wa1;
   C_WA2_F1 wa2_f1;
```

```
void main ()
 {
/***** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DECLARATION *****/
    FILE \*inpdat;
    struct tag
      {
       char in_boro;
       char filler1;
       char in_housenum         [12];
       char filler2;
       char in_street_name      [32];
       char filler3             [33];
      } recin ;

    inpdat = fopen("DD:INPDAT","rb");
    if (inpdat ==  NULL)
        {printf("INPDAT Data Set did not open.\n");
         return;}
 /***** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT  *****/
      printf("\fSAMPLE C PROGRAM \#1 EXECUTION OUTPUT  ");
      printf("\n\n*****---------- INPUT ADDRESS ------------***** \***");
      printf("\**--------------------- SELECTED OUTPUT ITEMS ---------");
      printf("--------------*****");
      printf("\n\nB HOUSE NUMBER IN-STREET-NAME              ");
      printf("       ZIP CD NYPD-PCT SCHLDST LOW CROSS STREET ");
      printf("         HIGH CROSS STREET       ");
      printf("\r_ ____________ ____________________________");
      printf("____ _____ __ ________ _______ _________________");
      printf("________ _________________________");

  /*** REPLACE CODE BELOW WITH YOUR OWN INPUT \***/
  while (fread(&recin,1,sizeof(recin),inpdat))
   {

   /*****************************************************************/
   /* TO MAKE A FUNCTION 1 CALL:                                    \*/
   /*   (1) INITIALIZE WORKAREA 1 TO SPACES                         \*/
   /*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                      \*/
   /*   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD      \*/
   /*   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER \*/
   /*       FIELD                                                   \*/
   /*   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  \*/
   /*   (6) CALL GBI WITH 2 WORKAREAS                               \*/
   /*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS               \*/
   /*****************************************************************/
```

```
    memset(&wa1,' ',sizeof(wa1));
    memcpy(wa1.input.func_code,"1 ",2);
    wa1.input.boro_1 = recin.in_boro ;
    memcpy(wa1.input.street_name_1,recin.in_street_name,32);
    memcpy(wa1.input.hse_nbr_disp,recin.in_housenum,12);
/*
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
/*     As of Geosupport Version 10.1,                                  \*/
/*     to receive roadbed-specific information,                        \*/
/*     set the Roadbed Request Switch to 'R', as follows:              \*/
/*     wa1.input.roadbedreq = 'R';                                     \*/
/*                                                                     \*/
/* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
/*                                                                     \*/
    GBI(&wa1,&wa2_f1);

    if ( (memcmp(wa1.output.ret_code,"01",2)) > 0
    ||   (memcmp(wa1.output.ret_code,"00",2)) < 0 )
         /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
     {
       printf("\n\n%c %.12s %.32s *** FUNCTION 1 GRC = %.2s"
              " REASON CODE = %c",
           recin.in_boro,recin.in_housenum,recin.in_street_name,
           wa1.output.ret_code,wa1.output.reject_reason_code) ;
       printf ("\n%51.5s %.80s", "\***", wa1.output.msg) ;
     }

    if ( (memcmp(wa1.output.ret_code,"01",2)) == 0 )
         /******** INSERT YOUR OWN WARNING HANDLING ROUTINE HERE *****/
     {
       printf("\n\n%c %.12s %.32s *** FUNCTION 1 WARNING, GRC = %.2s"
              " REASON CODE = %c",
           recin.in_boro,recin.in_housenum,recin.in_street_name,

       wa1.output.ret_code,wa1.output.reject_reason_code) ;
       printf ("\n%51.5s %.80s", "\***", wa1.output.msg) ;
       printf("\n%47.1s %.5s %.2s %.3s      %.2s",
           " ",wa2_f1.zip_code,
           wa2_f1.com_dist+1,wa2_f1.police_pre,wa2_f1.com_schl_dist) ;
     }

    if ( (memcmp(wa1.output.ret_code,"00",2)) == 0 )
         /*********************************************************/
         /***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ***********/
         /***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS         *****/
```

```
      /*************************************************************/
      printf("\n\n%c %.12s %.31s  %.5s %.2s %.3s      %.2s",
        recin.in_boro,recin.in_housenum,recin.in_street_name,
        wa2_f1.zip_code,
        wa2_f1.com_dist+1,wa2_f1.police_pre,wa2_f1.com_schl_dist) ;

    /*************************************************************/
    /* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND  \*/
    /* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE    \*/
    /* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS     \*/
    /* FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D: \*/
    /*   (1) INITIALIZE WORKAREA 1 TO SPACES                    \*/
    /*   (2) SET WA1'S FUNCTION CODE FIELD TO D                 \*/
    /*   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED      \*/
    /*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE     \*/
    /*              HAS SPACE FOR ONLY 25 CHARACTERS)           \*/
    /*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN      \*/
    /*       STREET NAMES FORMATTED FOR DISPLAY                 \*/
    /*   (5) MOVE WA2'S LOW PBSC FIELD TO WA1'S INPUT STREET    \*/
    /*       CODE 1 FIELD                                       \*/
    /*   (6) MOVE WA2'S HIGH PBSC FIELD TO WA1'S INPUT STREET   \*/
    /*       CODE 2 FIELD                                       \*/
    /*   (7) CALL GBI WITH 1 WORKAREA                           \*/
    /*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS          \*/
    /*************************************************************/
  if ( (memcmp(wa1.output.ret_code,"00",2)) == 0
  ||   (memcmp(wa1.output.ret_code,"01",2)) == 0 )
   {
    memset(&wa1,' ',sizeof(wa1));  /* Clear Work area 1 \*/
    wa1.input.func_code[0] = 'D' ;
    wa1.input.compact_flag = 'C' ;
    memcpy(wa1.input.snl,"25",2) ;
    memcpy(wa1.input.PB5SC_1,wa2_f1.l_x_sts[0],4) ;
    memcpy(wa1.input.PB5SC_2,wa2_f1.h_x_sts[0],4) ;
    GBI(&wa1);
    if ( (memcmp(wa1.output.ret_code,"00",2)) == 0 )
      /***** INSERT YOUR OWN CODE HERE ***********/
      printf("      %.25s %.25s",wa1.output.street_name_1,
             wa1.output.street_name_2) ;
    else
      /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
     {
      printf("\n\n%c %.12s %.32s *** FUNCTION D GRC = %.2s"
             " REASON CODE = %c",
          recin.in_boro,recin.in_housenum,recin.in_street_name,
```

```
                wa1.output.ret_code,wa1.output.reject_reason_code) ;
            printf ("\n%51.5s %.80s", "\***", wa1.output.msg) ;
           }

       }
   }

  }
/*
//LKED.SYSIN   DD *
    INCLUDE DD1(GBI)
/*
//LKED.DD1  DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************
//*
//*  AS OF GEOSUPPORT VERSION 10.0, THE STEPLIB OR JOBLIB
//*  STATEMENTS OF THE GEOSUPPORT EXECUTION STEP MUST INCLUDE
//*  THE FOLLOWING TWO CONCATENATED DATA SETS IN THE SPECIFIED
//*  ORDER:
//*                A030.GEO.SUPPORT.PDSE.LOADLIB
//*                A030.GEO.SUPPORT.LOADLIB
//*
//*****************************************************************
//GO.STEPLIB  DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************
//*
//*  AS OF GEOSUPPORT VERSION 10.0, DD STATEMENTS FOR GEOSUPPORT
//*  DATA FILES (E.G. GRID, PAD, ETC) ARE NO LONGER NEEDED AND
//*  ARE IGNORED.  GEOSUPPORT IS TAILORED TO USE STANDARD
//*  GEOSUPPORT DATA SETS.  TO USE NON-STANDARD FILES, SEE YOUR
//*  SYSTEMS PROGRAMMER.
//*
//*****************************************************************
//GO.SYSPRINT DD SYSOUT=A
//GO.INPDAT DD \*,DCB=LRECL=80
1 22           READE ST
1 500          DUANE ST
1 2-4          BROADWAY
4 165-100      BAISLEY BLVD
4 165-1000     BAISLEY BLVD
/*
//
```

C SAMPLE PROGRAM #1 –Job Stream - COW

```
//CCCC1SRC JOB YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//***  C SAMPLE COW BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1  ****
//*******************************************************************
//*
//STEP1 EXEC EDCCLG,
//      CPARM='SS,OPT,OFFSET,SOURCE,XREF,LIST'
//COMPILE.SYSPRINT DD SYSOUT=A
//COMPILE.SYSLIB   DD
//                 DD
//                 DD  DSNAME=A030.GEO.COPYLIB,DISP=SHR
//COMPILE.SYSIN    DD *
   /*****************************************************************/
   /* THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING \*/
   /* BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.\*/
   /* FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.     \*/
   /* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  \*/
   /* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
   /* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE         \*/
   /*       ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET       \*/
   /*       NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 1.           \*/
   /*****************************************************************/

#include <stdio.h>
#include <string.h>

 /*********************************************************************/
 /*** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     \***/
 /*** #INCLUDE STATEMENTS) IS STRONGLY ENCOURAGED.                  \***/
 /*********************************************************************/
#include <pac.h>

 /**************   GBI OS LINKAGE BELOW IS REQUIRED   **************/
#pragma linkage (GBI,OS)
long GBI(void \*, ...);

 /***** THE WORK AREA LAYOUTS MUST BE DECLARED USING THE TYPEDEFS \***/
 /***** IN THE GEOSUPPORT COPY FILE.                             \***/
   C_WA1 wa1;
   C_WA2_F1 wa2_f1;

void main ()

 /***** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DECLARATION *****/
```

```
   FILE \*inpdat;
   struct tag
     {
      char in_boro;
      char filler1;
      char in_housenum         [12];
      char filler2;
      char in_street_name      [32];
      char filler3             [33];
     } recin ;

   inpdat = fopen("DD:INPDAT","rb");
   if (inpdat ==  NULL)
       {printf("INPDAT Data Set did not open.\n");
        return;}
/***** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT  *****/
     printf("\fSAMPLE C PROGRAM \#1 EXECUTION OUTPUT  ");
     printf("\n\n*****---------- INPUT ADDRESS ------------***** \***");
     printf("\**--------------------- SELECTED OUTPUT ITEMS ---------");
     printf("--------------*****");
     printf("\n\nB HOUSE NUMBER IN-STREET-NAME              ");
     printf("       ZIP CD NYPD-PCT SCHLDST LOW CROSS STREET ");
     printf("         HIGH CROSS STREET       ");
     printf("\r_ ____________ ____________________________");
     printf("____ _____ __ ________ _______ _________________");
     printf("________ _________________________");

 /*** REPLACE CODE BELOW WITH YOUR OWN INPUT \***/
 while (fread(&recin,1,sizeof(recin),inpdat))
  {

  /*****************************************************************/
  /* TO MAKE A FUNCTION 1 CALL:                                    \*/
  /*   (1) INITIALIZE WORKAREA 1 TO SPACES                         \*/
  /*   (2) SET WA1'S FUNCTION CODE FIELD TO 1                      \*/
  /*   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD      \*/
  /*   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER \*/
  /*       FIELD                                                   \*/
  /*   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD  \*/
  /*   (6) CALL GBI WITH 2 WORKAREAS                               \*/
  /*   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS               \*/
  /*****************************************************************/

    memset(&wa1,' ',sizeof(wa1));
    memcpy(wa1.input.func_code,"1 ",2);
```

```
     wa1.input.sti??(0??).boro = recin.in_boro ;
     memcpy(wa1.input.sti??(0??).Street_name,recin.in_street_name,32);
            /* Please note that the house number field is actually \*/
            /* 16 bytes.  If you are only using 12 bytes, it is    \*/
            /* critical that you blank out the work area before    \*/
            /* you move in the house number                        \*/
     memcpy(wa1.input.hse_nbr_disp,recin.in_housenum,12);
     wa1.input.platform_ind = 'C';    /* Tells Geosupport that you \*/
                                      /* are using the character   \*/
 /*
 /* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
 /*     As of Geosupport Version 10.1,                               \*/
 /*     to receive roadbed-specific information,                     \*/
 /*     set the Roadbed Request Switch to 'R', as follows:           \*/
 /*     wa1.input.roadbedrequest = 'R';                              \*/
 /*                                                                  \*/
 /* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
 /*  \*/


     GBI(&wa1,&wa2_f1);

     if ( (memcmp(wa1.output.ret_code,"01",2)) > 0
     ||   (memcmp(wa1.output.ret_code,"00",2)) < 0 )
          /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
      {
        printf("\n\n%c %.12s %.32s *** FUNCTION 1 GRC = %.2s"
               " REASON CODE = %c",
            recin.in_boro,recin.in_housenum,recin.in_street_name,
            wa1.output.ret_code,wa1.output.reason_code) ;
        printf ("\n%51.5s %.80s", "\***", wa1.output.msg) ;
      }
     if ( (memcmp(wa1.output.ret_code,"01",2)) == 0 )
          /******** INSERT YOUR OWN WARNING HANDLING ROUTINE HERE *****/
      {
        printf("\n\n%c %.12s %.32s *** FUNCTION 1 WARNING, GRC = %.2s"
               " REASON CODE = %c",
            recin.in_boro,recin.in_housenum,recin.in_street_name,
wa1.output.ret_code,wa1.output.reason_code) ;
        printf ("\n%51.5s %.80s", "\***", wa1.output.msg) ;
        printf("\n%47.1s %.5s %.2s %.3s      %.2s",
            " ",wa2_f1.zip_code,
            wa2_f1.com_dist+1,wa2_f1.police_pre,wa2_f1.com_schl_dist) ;
      }
```

```
    if ( (memcmp(wa1.output.ret_code,"00",2)) == 0 )
         /*************************************************************/
         /***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ***********/
         /***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS          *****/
         /*************************************************************/
       printf("\n\n%c %.12s %.31s  %.5s %.2s %.3s      %.2s",
           recin.in_boro,recin.in_housenum,recin.in_street_name,
           wa2_f1.zip_code,
           wa2_f1.com_dist+1,wa2_f1.police_pre,wa2_f1.com_schl_dist) ;

       /*************************************************************/
       /* THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND  \*/
       /* ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE    \*/
       /* FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS     \*/
       /* FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D: \*/
       /*   (1) INITIALIZE WORKAREA 1 TO SPACES                    \*/
       /*   (2) SET WA1'S FUNCTION CODE FIELD TO D                 \*/
       /*   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED      \*/
       /*       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE     \*/
       /*              HAS SPACE FOR ONLY 25 CHARACTERS)           \*/
       /*   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN      \*/
       /*       STREET NAMES FORMATTED FOR DISPLAY                 \*/
       /*   (5) MOVE WA2'S LOW PBSC FIELD TO WA1'S INPUT STREET    \*/
       /*       CODE 1 FIELD                                       \*/
       /*   (6) MOVE WA2'S HIGH PBSC FIELD TO WA1'S INPUT STREET   \*/
       /*       CODE 2 FIELD                                       \*/
       /*   (7) CALL GBI WITH 1 WORKAREA                           \*/
       /*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS          \*/
       /*************************************************************/
    if ( (memcmp(wa1.output.ret_code,"00",2)) == 0
    ||   (memcmp(wa1.output.ret_code,"01",2)) == 0 )
     {
       memset(&wa1,' ',sizeof(wa1));  /* Clear Work area 1 \*/
       wa1.input.func_code[0] = 'D' ;
       wa1.input.st_name_norm = 'C' ;
       memcpy(wa1.input.snl,"25",2) ;
wa1.input.platform_ind = 'C';
       wa1.input.sti??(0??).boro=wa2_f1.st??(0??).B5SC??(0??)??(0??);
       memcpy(wa1.input.sti??(0??).SC10,
              wa2_f1.st??(0??).B5SC??(0??)+1,5);
       wa1.input.sti??(1??).boro=wa2_f1.st??(1??).B5SC??(0??)??(0??);
       memcpy(wa1.input.sti??(1??).SC10,
              wa2_f1.st??(1??).B5SC??(0??)+1,5);
       GBI(&wa1);
       if ( (memcmp(wa1.output.ret_code,"00",2)) == 0 )
```

```
          /***** INSERT YOUR OWN CODE HERE ***********/
            printf("      %.25s %.25s",wa1.output.sto??(0??).Street_name,
                 wa1.output.sto??(1??).Street_name) ;
        else
          /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
         {
          printf("\n\n%c %.12s %.32s *** FUNCTION D GRC = %.2s"
                 " REASON CODE = %c",
              recin.in_boro,recin.in_housenum,recin.in_street_name,
              wa1.output.ret_code,wa1.output.reason_code) ;
          printf ("\n%51.5s %.80s", "\***", wa1.output.msg) ;
         }

      }

   }

 }
/*
//LKED.SYSIN   DD *
    INCLUDE DD1(GBI)
/*
//LKED.DD1  DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************
//*
//*  AS OF GEOSUPPORT VERSION 10.0, THE STEPLIB OR JOBLIB
//*  STATEMENTS OF THE GEOSUPPORT EXECUTION STEP MUST INCLUDE
//*  THE FOLLOWING TWO CONCATENATED DATA SETS IN THE SPECIFIED
//*  ORDER:
//*                A030.GEO.SUPPORT.PDSE.LOADLIB
//*                A030.GEO.SUPPORT.LOADLIB
//*
//*****************************************************************
//GO.STEPLIB  DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************
//*
//*  AS OF GEOSUPPORT VERSION 10.0, DD STATEMENTS FOR GEOSUPPORT
//*  DATA FILES (E.G. GRID, PAD, ETC) ARE NO LONGER NEEDED AND
//*  ARE IGNORED.  GEOSUPPORT IS TAILORED TO USE STANDARD
//*  GEOSUPPORT DATA SETS.  TO USE NON-STANDARD FILES, SEE YOUR
//*  SYSTEMS PROGRAMMER.
//*
//*****************************************************************
//GO.SYSPRINT DD SYSOUT=A
```

```
//GO.INPDAT DD \*,DCB=LRECL=80
1 22           READE ST
1 500          DUANE ST
1 2-4          BROADWAY
4 165-100      BAISLEY BLVD
4 165-1000     BAISLEY BLVD
/*
//
```

C SAMPLE PROGRAM #1 – Output Report

```
     *****---------- INPUT ADDRESS ------------***** *****--------------------- SELECTED OUTPUT
ITEMS -----------------------*****

     B HOUSE NUMBER IN-STREET-NAME                     ZIP CD NYPD-PCT SCHLDST LOW CROSS STREET
HIGH CROSS STREET
     \- ------------ ------------------------------- ----- -- -------- ------- ---------------
---------- -------------------------

     1 22           READE ST                        10007 01 005      02      ELK STREET
BROADWAY

     1 500          DUANE ST                        *** FUNCTION 1 GRC = 42 REASON CODE =
                                                    *** ADDRESS NUMBER OUT OF RANGE

     1 2-4          BROADWAY                        *** FUNCTION 1 WARNING, GRC = 01 REASON
CODE = 1
                                                    *** ADDR NUMBER ALTERED: RANGE ASSUMED.
USING DIGITS BEFORE DASH ONLY
                                                    10004 01 001      02      STONE STREET
BOWLING GREEN

     4 165-100      BAISLEY BLVD                    11434 12 113      28      GUY R BREWER
BOULEVARD    BEDELL STREET

     4 165-1000     BAISLEY BLVD                    *** FUNCTION 1 GRC = 13 REASON CODE = 2
                                                    *** ADDRESS NBR 165-1000  HAS MORE THAN 3
DIGITS AFTER THE DASH.
```

C SAMPLE PROGRAM #2

- Input Job Stream - MSW

- Input Job Stream - COW

- Output Report

C SAMPLE PROGRAM #2 – Job Stream - MSW

```
//CCCF2SRC JOB YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//***  C SAMPLE MSW BATCH GEOSUPPORT USER APPLICATION PROGRAM \#2  ****
//*******************************************************************
//*
//STEP1 EXEC EDCCLG,
//      CPARM='SS,OPT,OFFSET,SOURCE,XREF,LIST'
//COMPILE.SYSPRINT DD SYSOUT=A
//COMPILE.SYSLIB   DD
//                 DD
//                 DD  DSNAME=A030.GEO.COPYLIB,DISP=SHR
//COMPILE.SYSIN    DD *
   /*****************************************************************/
   /* THIS PROGRAM MAKES FUNCTION 2 AND D CALLS TO GEOSUPPORT USING \*/
   /* TWO BOROS AND TWO STREET NAMES SUPPLIED BY AN INSTREAM FILE.  \*/
   /* FUNCTION 2 RETURNS GEOGRAPHIC INFORMATION FOR AN INTERSECTION.\*/
   /* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  \*/
   /* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
   /* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE         \*/
   /*       ORIGINAL CALL TO FUNCTION 2, ALL THE CROSS STREET       \*/
   /*       NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 2.           \*/
   /*****************************************************************/

#include <stdio.h>
#include <stdlib.h>
#include <string.h>

 /*********************************************************************/
 /*** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     \***/
 /*** #INCLUDE STATEMENTS) IS STRONGLY ENCOURAGED.                  \***/
 /*********************************************************************/
#include <wac.h>

 /**************   GBI DECLARATION BELOW IS REQUIRED   **************/
   #pragma linkage (GBI,OS)
   long GBI(void \*, ...);

 /***** THE WORK AREA LAYOUTS MUST BE DECLARED USING THE TYPEDEFS \***/
 /***** IN THE GEOSUPPORT COPY FILE.                             \***/
   C_WA1 wa1;
```

```
    C_WA2_F2 wa2_f2;

void main ()
 {

 /***** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DECLARATION *****/
    FILE \*infile;
    struct tag
      {
       char in_boro1;
       char filler1;
       char in_street_name1     [32];
       char filler2;
       char in_boro2;
       char filler3;
       char in_street_name2     [32];
       char filler4             [11];
      } recin ;
   short int j, i;
   char temp [2];
    if ((infile = fopen("DD:INFILE","rb")) ==  NULL)

{printf("INFILE Data Set did not open.\n");
         return;}

 /***** REPLACE CODE BELOW WITH YOUR OWN REPRORT LAYOUT  *****/
      printf("\fSAMPLE C PROGRAM \#2 EXECUTION OUTPUT  ");
      printf("\n\n*****----------------- INPUT INTERSECTION ---------");
      printf("-------------***** *****------------ SELECTED OUTPUT ");
      printf("ITEMS -------------*****");
      printf("\n\nB IN-STREET-NAME-1            ");
      printf("     B IN-STREET-NAME-2                   ZIP CD");
      printf(" NYPD-PCT SCHLDST INTERSECTING STREET NAMES");
      printf(  "\r_ ____________________________");
      printf("____ _ ________________________________ _____ \__");
      printf(" ________ _______ ___________________________________");

  /*** REPLACE CODE BELOW WITH YOUR OWN INPUT \***/
  while (fread(&recin,1,sizeof(recin),infile))
   {

   /*****************************************************************/
   /* TO MAKE A FUNCTION 2 CALL:                                    \*/
   /*   (1) INITIALIZE WORKAREA 1 TO SPACES                         \*/
   /*   (2) SET WA1'S FUNCTION-CODE TO 2                            \*/
```

```
/*   (3) MOVE THE 1ST INPUT BORO TO WA1'S INPUT BORO CODE FIELD   \*/
/*   (4) MOVE THE 1ST INPUT STREET TO WA1'S INPUT STREET NAME     \*/
/*       FIELD                                                    \*/
/*   (5) MOVE THE 2ND INPUT BORO TO WA1'S INPUT BORO CODE 2 FIELD \*/
/*   (6) MOVE THE 2ND INPUT STREET TO WA1'S INPUT STREET NAME 2   \*/
/*       FIELD                                                    \*/
/*   (7) CALL GBI WITH 2 WORKAREAS                                \*/
/*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS                \*/
/*****************************************************************/

  memset(&wa1,' ',sizeof(wa1));
  memcpy(wa1.input.func_code,"2 ",2);
  wa1.input.boro_1 = recin.in_boro1 ;
  memcpy(wa1.input.street_name_1,recin.in_street_name1,32);
  wa1.input.boro_2 = recin.in_boro2 ;
  memcpy(wa1.input.street_name_2,recin.in_street_name2,32);
  GBI(&wa1,&wa2_f2);

  if ( (memcmp(wa1.output.ret_code,"01",2)) > 0
  ||   (memcmp(wa1.output.ret_code,"00",2)) < 0 )
       /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
   {
     printf("\n\n***** FUNCTION 2 GRC = %.2s"
            " REASON CODE = %c. %.80s",
         wa1.output.ret_code,wa1.output.reject_reason_code,
         wa1.output.msg) ;
     printf
     ("\n%c %.32s %c %.32s ",
         recin.in_boro1,recin.in_street_name1,recin.in_boro2,
         recin.in_street_name2) ;
   }

  if ( (memcmp(wa1.output.ret_code,"01",2)) == 0 )
       /******** INSERT YOUR OWN WARNING HANDLING ROUTINE HERE *****/
   {
     printf("\n\n***** FUNCTION 2 WARNING GRC = %.2s"
            " REASON CODE = %c. %.80s",
         wa1.output.ret_code,wa1.output.reject_reason_code,

wa1.output.msg) ;
     printf
     ("\n%c %.32s %c %.32s ",
         recin.in_boro1,recin.in_street_name1,recin.in_boro2,
         recin.in_street_name2) ;
   }
```

```
if ( (memcmp(wa1.output.ret_code,"00",2)) == 0
||   (memcmp(wa1.output.ret_code,"01",2)) == 0 )
     /*********************************************************/
     /***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ***********/
     /***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS          *****/
     /*********************************************************/
 {
  printf("\n\n%c %.32s %c %.32s %.5s %.2s %.3s      %.2s     ",
       recin.in_boro1,recin.in_street_name1,recin.in_boro2,
       recin.in_street_name2,wa2_f2.zip_code,
       wa2_f2.com_dist+1,wa2_f2.police_pre,wa2_f2.com_schl_dist) ;

  temp [0] = wa2_f2.nbr_x_sts ;
  temp [1] = 0;
  i = atoi(temp) ;
  for (j=0; j<i; j++)
  {
       /*******************************************************/
       /* TO GET STREET NAMES FOR INTERSECTING STREET CODES   \*/
       /* MAKE A FUNCTION D CALL:                             \*/
       /*   (1) INITIALIZE WORKAREA 1 TO SPACES               \*/
       /*   (2) SET THE WA1'S FUNCTION CODE FIELD TO D        \*/
       /*   (3) USE THE COMPACT STREET NAMES OPTION TO OBTAIN \*/
       /*       STREET NAMES FORMATTED FOR DISPLAY            \*/
       /*   (4) MOVE THE PACKED BORO AND STREET CODE TO       \*/
       /*       WA1'S INPUT STREET CODE 1 FIELD               \*/
       /*   (5) CALL GBI WITH 1 WORKAREA                      \*/
       /*   (6) CHECK RETURN CODES FOR ERRORS OR WARNINGS     \*/
       /*******************************************************/
   memset(&wa1,' ',sizeof(wa1));
   wa1.input.func_code[0] = 'D' ;
   wa1.input.compact_flag = 'C' ;
   memcpy(wa1.input.PB5SC_1,wa2_f2.x_sts[j],4) ;
   GBI(&wa1);
   if ( (memcmp(wa1.output.ret_code,"00",2)) == 0 )
    {
     /***** INSERT YOUR OWN CODE HERE ***********/
     if (j==0)
       printf(" %.32s",wa1.output.street_name_1);
     else
       printf("\n%128.32s",wa1.output.street_name_1);
    }
   else
     /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
```

```
          printf("\n\n***** FUNCTION D GRC = %.2s"
               " REASON CODE = %c. %.80s",
            wa1.output.ret_code,wa1.output.reject_reason_code,
            wa1.output.msg) ;
       }

      }

   }

 }

/*
//LKED.SYSIN   DD *
    INCLUDE DD1(GBI)
/*
//LKED.DD1  DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************
//*
//*  AS OF GEOSUPPORT VERSION 10.0, THE STEPLIB OR JOBLIB
//*  STATEMENTS OF THE GEOSUPPORT EXECUTION STEP MUST INCLUDE
//*  THE FOLLOWING TWO CONCATENATED DATA SETS IN THE SPECIFIED
//*  ORDER:
//*                A030.GEO.SUPPORT.PDSE.LOADLIB
//*                A030.GEO.SUPPORT.LOADLIB
//*
//*****************************************************************
//GO.STEPLIB  DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************
//*
//*  AS OF GEOSUPPORT VERSION 10.0, DD STATEMENTS FOR GEOSUPPORT
//*  DATA FILES (E.G. GRID, PAD, ETC) ARE NO LONGER NEEDED AND
//*  ARE IGNORED.  GEOSUPPORT IS TAILORED TO USE STANDARD
//*  GEOSUPPORT DATA SETS.  TO USE NON-STANDARD FILES, SEE YOUR
//*  SYSTEMS PROGRAMMER.
//*
//*****************************************************************
//GO.SYSPRINT DD SYSOUT=A
//GO.INFILE DD *
1 CHAMBERS ST                      1 HUDSON ST
1 SIXTH AVE                        1 W. 8 ST
1 DUANE ST                         1 READE ST
/*
//
```

C SAMPLE PROGRAM #2 – Job Stream - COW

```
//CCCC2SRC JOB   YOUR-JOB-CARD-INFORMATION
//*
//*******************************************************************
//***  C SAMPLE COW BATCH GEOSUPPORT USER APPLICATION PROGRAM \#2  ****
//*******************************************************************
//*
//STEP1 EXEC EDCCLG,
//      CPARM='SS,OPT,OFFSET,SOURCE,XREF,LIST'
//COMPILE.SYSPRINT DD SYSOUT=A
//COMPILE.SYSLIB   DD
//                 DD
//                 DD  DSNAME=A030.GEO.COPYLIB,DISP=SHR
//COMPILE.SYSIN    DD *
   /*****************************************************************/
   /* THIS PROGRAM MAKES FUNCTION 2 AND D CALLS TO GEOSUPPORT USING \*/
   /* TWO BOROS AND TWO STREET NAMES SUPPLIED BY AN INSTREAM FILE.  \*/
   /* FUNCTION 2 RETURNS GEOGRAPHIC INFORMATION FOR AN INTERSECTION.\*/
   /* FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.  \*/
   /* * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * \*/
   /* NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE        \*/
   /*       ORIGINAL CALL TO FUNCTION 2, ALL THE CROSS STREET      \*/
   /*       NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 2.          \*/
   /*****************************************************************/

#include <stdio.h>
#include <stdlib.h>
#include <string.h>

 /*********************************************************************/
 /*** USE OF GEOSUPPORT COPY LIBRARIES (REFERENCED BELOW BY THE     \***/
 /*** #INCLUDE STATEMENTS) IS STRONGLY ENCOURAGED.                  \***/
 /*********************************************************************/
#include <pac.h>

 /**************   GBI DECLARATION BELOW IS REQUIRED   **************/
   #pragma linkage (GBI,OS)
   long GBI(void \*, ...);

 /***** THE WORK AREA LAYOUTS MUST BE DECLARED USING THE TYPEDEFS \***/
 /***** IN THE GEOSUPPORT COPY FILE.                             \***/
   C_WA1 wa1;
   C_WA2_F2 wa2_f2;
```

```
void main ()
 {

 /***** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DECLARATION *****/
    FILE \*infile;
    struct tag
      {
       char in_boro1;
       char filler1;
       char in_street_name1     [32];
       char filler2;
       char in_boro2;
       char filler3;
       char in_street_name2     [32];
       char filler4             [11];
      } recin ;
   short int j, i;
   char temp [2];
    if ((infile = fopen("DD:INFILE","rb")) ==  NULL)
{printf("INFILE Data Set did not open.\n");
         return;}

 /***** REPLACE CODE BELOW WITH YOUR OWN REPRORT LAYOUT  *****/
      printf("\fSAMPLE C PROGRAM \#2 EXECUTION OUTPUT  ");
      printf("\n\n*****---------------- INPUT INTERSECTION ---------");
      printf("-------------***** *****------------ SELECTED OUTPUT ");
      printf("ITEMS -------------*****");
      printf("\n\nB IN-STREET-NAME-1            ");
      printf("     B IN-STREET-NAME-2                   ZIP CD");
      printf(" NYPD-PCT SCHLDST INTERSECTING STREET NAMES");
      printf(  "\r_ ____________________________");
      printf("____ _ ________________________________ _____ \__");
      printf(" ________ _______ ________________________________");

  /*** REPLACE CODE BELOW WITH YOUR OWN INPUT \***/
  while (fread(&recin,1,sizeof(recin),infile))
   {

   /*****************************************************************/
   /* TO MAKE A FUNCTION 2 CALL:                                    \*/
   /*   (1) INITIALIZE WORKAREA 1 TO SPACES                         \*/
   /*   (2) SET WA1'S FUNCTION-CODE TO 2                            \*/
   /*   (3) MOVE THE 1ST INPUT BORO TO WA1'S INPUT BORO CODE FIELD  \*/
   /*   (4) MOVE THE 1ST INPUT STREET TO WA1'S INPUT STREET NAME    \*/
   /*       FIELD                                                   \*/
```

```
/*   (5) MOVE THE 2ND INPUT BORO TO WA1'S INPUT BORO CODE 2 FIELD \*/
/*   (6) MOVE THE 2ND INPUT STREET TO WA1'S INPUT STREET NAME 2   \*/
/*       FIELD                                                    \*/
/*   (7) CALL GBI WITH 2 WORKAREAS                                \*/
/*   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS                \*/
/*****************************************************************/

  memset(&wa1,' ',sizeof(wa1));
  memcpy(wa1.input.func_code,"2 ",2);
  wa1.input.sti??(0??).boro = recin.in_boro1 ;
  memcpy(wa1.input.sti??(0??).Street_name,recin.in_street_name1,32);
  wa1.input.sti??(1??).boro = recin.in_boro2 ;
  memcpy(wa1.input.sti??(1??).Street_name,recin.in_street_name2,32);
  wa1.input.platform_ind = 'C';    /* Tells Geosupport that you \*/
                                   /* are using the character   \*/
                                   /* only work areas           \*/
  GBI(&wa1,&wa2_f2);

  if ( (memcmp(wa1.output.ret_code,"01",2)) > 0
  ||   (memcmp(wa1.output.ret_code,"00",2)) < 0 )
       /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
   {
     printf("\n\n***** FUNCTION 2 GRC = %.2s"
            " REASON CODE = %c. %.80s",
         wa1.output.ret_code,wa1.output.reason_code,
         wa1.output.msg) ;
     printf
     ("\n%c %.32s %c %.32s ",
         recin.in_boro1,recin.in_street_name1,recin.in_boro2,
         recin.in_street_name2) ;
   }

  if ( (memcmp(wa1.output.ret_code,"01",2)) == 0 )
       /******** INSERT YOUR OWN WARNING HANDLING ROUTINE HERE *****/
   {
     printf("\n\n***** FUNCTION 2 WARNING GRC = %.2s"


       " REASON CODE = %c. %.80s",
         wa1.output.ret_code,wa1.output.reason_code,
         wa1.output.msg) ;
     printf
     ("\n%c %.32s %c %.32s ",
         recin.in_boro1,recin.in_street_name1,recin.in_boro2,
         recin.in_street_name2) ;
```

```
 }

if ( (memcmp(wa1.output.ret_code,"00",2)) == 0
||   (memcmp(wa1.output.ret_code,"01",2)) == 0 )
     /*********************************************************/
     /***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR ***********/
     /***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS          *****/
     /*********************************************************/
 {
  printf("\n\n%c %.32s %c %.32s %.5s %.2s %.3s      %.2s     ",
       recin.in_boro1,recin.in_street_name1,recin.in_boro2,
       recin.in_street_name2,wa2_f2.zip_code,
       wa2_f2.com_dist+1,wa2_f2.police_pre,wa2_f2.com_schl_dist) ;

  temp [0] = wa2_f2.inter.nbr_sts ;
  temp [1] = 0;
  i = atoi(temp) ;
  for (j=0; j<i; j++)
  {
       /*******************************************************/
       /* TO GET STREET NAMES FOR INTERSECTING STREET CODES   \*/
       /* MAKE A FUNCTION D CALL:                             \*/
       /*   (1) INITIALIZE WORKAREA 1 TO SPACES               \*/
       /*   (2) SET THE WA1'S FUNCTION CODE FIELD TO D        \*/
       /*   (3) USE THE COMPACT STREET NAMES OPTION TO OBTAIN \*/
       /*       STREET NAMES FORMATTED FOR DISPLAY            \*/
       /*   (4) MOVE THE PACKED BORO AND STREET CODE TO       \*/
       /*       WA1'S INPUT STREET CODE 1 FIELD               \*/
       /*   (5) CALL GBI WITH 1 WORKAREA                      \*/
       /*   (6) CHECK RETURN CODES FOR ERRORS OR WARNINGS     \*/
       /*******************************************************/
   memset(&wa1,' ',sizeof(wa1));
   wa1.input.func_code[0] = 'D' ;
   wa1.input.st_name_norm = 'C' ;
   wa1.input.platform_ind = 'C';
   wa1.input.sti??(0??).boro = wa2_f2.inter.B5SC??(j??)??(0??);
   memcpy(wa1.input.sti??(0??).SC10,wa2_f2.inter.B5SC??(j??)+1,5);
   GBI(&wa1);
   if ( (memcmp(wa1.output.ret_code,"00",2)) == 0 )
    {
     /***** INSERT YOUR OWN CODE HERE ***********/
     if (j==0)
       printf(" %.32s",wa1.output.sto??(0??).Street_name);
     else
       printf("\n%128.32s",wa1.output.sto??(0??).Street_name);
```

```
          }
         else
           /******** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE *****/
           printf("\n\n***** FUNCTION D GRC = %.2s"
                " REASON CODE = %c. %.80s",
             wa1.output.ret_code,wa1.output.reason_code,
             wa1.output.msg) ;
        }


      }

    }

  }
/*
//LKED.SYSIN   DD *
    INCLUDE DD1(GBI)
/*
//LKED.DD1  DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************
//*
//*  AS OF GEOSUPPORT VERSION 10.0, THE STEPLIB OR JOBLIB
//*  STATEMENTS OF THE GEOSUPPORT EXECUTION STEP MUST INCLUDE
//*  THE FOLLOWING TWO CONCATENATED DATA SETS IN THE SPECIFIED
//*  ORDER:
//*                A030.GEO.SUPPORT.PDSE.LOADLIB
//*                A030.GEO.SUPPORT.LOADLIB
//*
//*****************************************************************
//GO.STEPLIB  DD  DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD  DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//*****************************************************************
//*
//*  AS OF GEOSUPPORT VERSION 10.0, DD STATEMENTS FOR GEOSUPPORT
//*  DATA FILES (E.G. GRID, PAD, ETC) ARE NO LONGER NEEDED AND
//*  ARE IGNORED.  GEOSUPPORT IS TAILORED TO USE STANDARD
//*  GEOSUPPORT DATA SETS.  TO USE NON-STANDARD FILES, SEE YOUR
//*  SYSTEMS PROGRAMMER.
//*
//*****************************************************************
//GO.SYSPRINT DD SYSOUT=A
//GO.INFILE DD *
1 CHAMBERS ST                      1 HUDSON ST
1 SIXTH AVE                        1 W. 8 ST
```

```
      1 DUANE ST                          1 READE ST
      /*
      //
```

SAMPLE C PROGRAM #2 EXECUTION OUTPUT

```
       *****----------------- INPUT INTERSECTION ----------------------***** *****------------
SELECTED OUTPUT ITEMS -------------*****

       B IN-STREET-NAME-1                 B IN-STREET-NAME-2                   ZIP CD NYPD-PCT
SCHLDST INTERSECTING STREET NAMES
       \- ------------------------------- - ------------------------------- ----- -- --------
------- ---------------------------------

       1 CHAMBERS ST                      1 HUDSON ST                        10007 01 001
02      CHAMBERS STREET

HUDSON STREET

WEST BROADWAY

       1 SIXTH AVE                        1 W. 8 ST                          10014 02 006
02      6 AVENUE

GREENWICH AVENUE

WEST 8 STREET

       ***** FUNCTION 2 GRC = 62 REASON CODE =  . READE STREET & DUANE STREET DO NOT INTERSECT
       1 DUANE ST                         1 READE ST
```

NATURAL SAMPLE PROGRAM #1

– Program Source Code - MSW

- Program Source Code - COW

- Input Job Stream

- Output Report

NATURAL SAMPLE PROGRAM #1 – Program Source- MSW

```
         0010 ************************************************************************
          0020 * PGM NAME: GEOBUPG1    DATE: 08-18-98                                *
```

```
0030 *                                                                    *
0040 * THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING      *
0050 * BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.     *
0060 * FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.          *
0070 * FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.       *
0080 * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *  *
0090 *          NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE      *
0100 *                ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET    *
0110 *                NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 1.        *
0120 ************************************************************************
0130 *                                                                    *
0140 ************************************************************************
0150 * USE OF GEOSUPPORT LDA (REFERENCED BELOW BY THE LOCAL USING STATEMENT)*
0160 * IS STRONGLY ENCOURAGED.                                            *
0170 ************************************************************************
0180 DEFINE DATA
0190  LOCAL USING GEOLW1
0200  LOCAL USING GEOLW2
0210 *
0220 ***** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DECLARATION      *****
0230  LOCAL
0240   01 #USER-INPUT
0250      02 #USER-BORO                    (A1)
0260      02 #FILLER1                      (A1)
0270      02 #USER-HSE-NUM                 (A12)
0280      02 #FILLER2                      (A1)
0290      02 #USER-STRT-NAME               (A32)
0300      02 #FILLER3                      (A33)
0310 *
0320   01 #SAVE-RET-CODE                   (A2)
0330   01 #OUT-STREET-1-SNL25              (A25)
0340   01 #OUT-STREET-2-SNL25              (A25)
0350   01 #OUT-ERROR-MESSAGE-77            (A77)
0360 *
0370 END-DEFINE
0380 *
0390 FORMAT LS=133 PS=65
0400 *
0410 ***** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT               *****
0420 WRITE NOTITLE
0430  1T'SAMPLE NATURAL PROGRAM #1 EXECUTION OUTPUT'//
0440  1T'*****---------- INPUT ADDRESS ------------*****'
0450  49T'*****--------------------- SELECTED OUTPUT'
0460  92T'ITEMS -----------------------*****'//
0470  1T'B HOUSE NUMBER IN-STREET-NAME                    ZIP CD'
```

```
0480  58T'NYPD-PCT SCHLDST LOW CROSS STREET         '
0490  101T'HIGH CROSS STREET        '/
0500  1T'- ------------ ------------------------------ ----- --'
0510  58T'-------- ------- -------------------------'
0520  101T'-------------------------'/
0530 *
0540 READ WORK FILE 01 #USER-INPUT
0550  PERFORM FN1-PROCESS
0560 END-WORK
0570 *
0580 DEFINE SUBROUTINE FN1-PROCESS
0590 ************************************************************************
0600 * TO MAKE A FUNCTION 1 CALL:                                          *
0610 *   (1) INITIALIZE WORKAREA 1 TO SPACES                                *
0620 *   (2) SET WA1'S FUNCTION CODE FIELD TO 1                             *
0630 *   (3) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD             *
0640 *   (4) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER FIELD  *
0650 *   (5) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD         *
0660 *   (6) CALL GBI WITH 2 WORKAREAS                                      *
0670 *   (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS                      *
0680 ************************************************************************
0690 ************************************************************************
0700 * AS OF GEOSUPPORT 10.1,                                              *
0710 *    TO RECEIVE ROADBED-SPECIFIC INFORMATION,                         *
0720 *    SET THE ROADBED REQUEST SWITCH TO 'R', AS FOLLOWS:               *
0730 *        MOVE 'R' TO GEO-WA1-IN-ROADBED-REQ-SWITCH.                   *
0740 ************************************************************************
0750  RESET GEOLW1
0760  MOVE '1 ' TO GEO-WA1-IN-FUNCTION-CODE
0770  MOVE #USER-BORO TO GEO-WA1-IN-BORO
0780  MOVE #USER-HSE-NUM TO GEO-WA1-IN-HOUSENUM
0790  MOVE #USER-STRT-NAME TO GEO-WA1-IN-STREET-1
0800 *
0810  CALL 'GBI' W1NAT W2NAT
0820 *
0830  IF GEO-WA1-OUT-RETURN-CODE NOT = '00' AND
0840     GEO-WA1-OUT-RETURN-CODE NOT = '01'
0850 *
0860 ***** REPLACE YOUR OWN ERROR HANDLING ROUTINE HERE                *****
0870 *
0880   MOVE GEO-WA1-OUT-ERROR-MESSAGE TO #OUT-ERROR-MESSAGE-77
0890   WRITE NOTITLE
0900    1T #USER-BORO 3T #USER-HSE-NUM 16T #USER-STRT-NAME
0910    49T '*** FUNCTION 1 GRC =' GEO-WA1-OUT-RETURN-CODE
0920    73T 'REASON CODE =' GEO-WA1-OUT-REASON-CODE /
```

```
0930    49T '\***' #OUT-ERROR-MESSAGE-77 /
0940  ELSE
0950   IF GEO-WA1-OUT-RETURN-CODE = '01'
0960 *
0970 ***** REPLACE YOUR OWN WARNING HANDLING ROUTINE HERE              *****
0980 *
0990    MOVE GEO-WA1-OUT-ERROR-MESSAGE TO #OUT-ERROR-MESSAGE-77
1000    WRITE NOTITLE
1010     1T #USER-BORO 3T #USER-HSE-NUM 16T #USER-STRT-NAME
1020     49T '*** FUNCTION 1 WARNING, GRC =' GEO-WA1-OUT-RETURN-CODE
1030     82T 'REASON CODE =' GEO-WA1-OUT-REASON-CODE /
1040     49T '\***' #OUT-ERROR-MESSAGE-77
1050   END-IF
1060  END-IF
1070 *
1080  IF GEO-WA1-OUT-RETURN-CODE = '00' OR
1090     GEO-WA1-OUT-RETURN-CODE = '01'
1100   MOVE GEO-WA1-OUT-RETURN-CODE TO #SAVE-RET-CODE
1110 *
1120 ***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR                   *****
1130 ***** PROCESSING SUCCESSFUL GEOSUPPORT FUNCTION 1 CALL            *****
1140 *
1150 ************************************************************************
1160 * THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND             *
1170 * ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE               *
1180 * FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS                *
1190 * FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D:            *
1200 *   (1) INITIALIZE WORKAREA 1 TO SPACES                               *
1210 *   (2) SET WA1'S FUNCTION CODE FIELD TO D                            *
1220 *   (3) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED                 *
1230 *       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE                *
1240 *              HAS SPACE FOR ONLY 25 CHARACTERS)                      *
1250 *   (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN                 *
1260 *       STREET NAMES FORMATTED FOR DISPLAY                            *
1270 *   (5) MOVE WA2'S LOW PBSC FIELD TO WA1'S INPUT STREET CODE 1 FIELD  *
1280 *   (6) MOVE WA2'S HIGH PBSC FIELD TO WA1'S INPUT STREET CODE 2 FIELD *
1290 *   (7) CALL GBI WITH 1 WORKAREA                                      *
1300 *   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS                     *
1310 ************************************************************************
1320   RESET GEOLW1
1330   MOVE 'D ' TO GEO-WA1-IN-FUNCTION-CODE
1340   MOVE 'C' TO GEO-WA1-IN-COMPACT-NAME-FLAG
1350   MOVE '25' TO GEO-WA1-IN-SNL
1360   MOVE GEO-WA2-FN1-LOW-PBSC(1) TO GEO-WA1-IN-STREETCODE-1
1370   MOVE GEO-WA2-FN1-HI-PBSC(1) TO GEO-WA1-IN-STREETCODE-2
```

```
1380 *
1390   CALL 'GBI' W1NAT
1400 *
1410   IF GEO-WA1-OUT-RETURN-CODE = '00'
1420    MOVE GEO-WA1-OUT-STREET-1 TO #OUT-STREET-1-SNL25
1430    MOVE GEO-WA1-OUT-STREET-2 TO #OUT-STREET-2-SNL25
1440 *
1450 ***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR                    *****
1460 ***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS                       *****
1470 *
1480    IF #SAVE-RET-CODE = '01' RESET #USER-BORO
1490     #USER-HSE-NUM #USER-STRT-NAME
1500    END-IF
1510    WRITE NOTITLE
1520     1T #USER-BORO 3T #USER-HSE-NUM 16T #USER-STRT-NAME
1530     49T GEO-WA2-FN1-ZIP 55T GEO-WA2-FN1-COMDIST-NUM
1540     58T GEO-WA2-FN1-POL-PRECINCT 67T GEO-WA2-FN1-SCHOOLDIST
1550     75T #OUT-STREET-1-SNL25 101T #OUT-STREET-2-SNL25 /
1560   ELSE
1570 *
1580 ***** REPLACE YOUR OWN ERROR HANDLING ROUTINE HERE                 *****
1590 *
1600    MOVE GEO-WA1-OUT-ERROR-MESSAGE TO #OUT-ERROR-MESSAGE-77
1610    WRITE NOTITLE
1620     1T #USER-BORO 3T #USER-HSE-NUM 16T #USER-STRT-NAME
1630     49T '*** FUNCTION D GRC =' GEO-WA1-OUT-RETURN-CODE
1640     73T 'REASON CODE =' GEO-WA1-OUT-REASON-CODE /
1650     49T '\***' #OUT-ERROR-MESSAGE-77 /
1660   END-IF
1670  END-IF
1680 *
1690  END-SUBROUTINE
1700  END
```

NATURAL SAMPLE PROGRAM #1 – Program Source code - COW

```
0010 ************************************************************************
0020 * PGM NAME: GEOBUPGA    DATE: 08-18-98         MODIFIED : 08-28-06     *
0030 *                                                                      *
0040 * THIS PROGRAM MAKES FUNCTION 1 AND D CALLS TO GEOSUPPORT USING        *
0050 * BORO, HOUSENUMBER, & STREET NAME SUPPLIED BY AN INSTREAM FILE.       *
0060 * FUNCTION 1 RETURNS GEOGRAPHIC INFORMATION FOR AN ADDRESS.            *
0070 * FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.         *
0080 * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * * *  *
0090 *          NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE       *
```

```
0100 *                ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET     *
0110 *                NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 1.         *
0120 ************************************************************************
0130 *                                                                      *
0140 ************************************************************************
0150 * USE OF GEOSUPPORT LDA (REFERENCED BELOW BY THE LOCAL USING STATEMENT)*
0160 * IS STRONGLY ENCOURAGED.                                              *
0170 ************************************************************************
0180 DEFINE DATA
0190  LOCAL USING GEOLP1
0200  LOCAL USING GEOLP2
0210 *
0220 ***** REPLACE CODE BELOW WITH YOUR OWN INPUT FILE DECLARATION      *****
0230  LOCAL
0240   01 #USER-INPUT
0250      02 #USER-BORO                    (A1)
0260      02 #FILLER1                      (A1)
0270      02 #USER-HSE-NUM                 (A12)
0280      02 #FILLER2                      (A1)
0290      02 #USER-STRT-NAME               (A32)
0300      02 #FILLER3                      (A33)
0310 *
0320   01 #SAVE-RET-CODE                   (A2)
0330   01 #OUT-STREET-1-SNL25              (A25)
0340   01 #OUT-STREET-2-SNL25              (A25)
0350   01 #OUT-ERROR-MESSAGE-77            (A77)
0360 *
0370   01 #B5SC (A6)
0380   01 REDEFINE #B5SC
0390      02 #B5SC-BORO (A1)
0400      02 #B5SC-5SC (A5)
0410 *
0420 END-DEFINE
0430 *
0440 FORMAT LS=133 PS=65
0450 *
0460 ***** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT               *****
0470 WRITE NOTITLE
0480  1T'SAMPLE NATURAL PROGRAM \#1 EXECUTION OUTPUT'//
0490  1T'*****---------- INPUT ADDRESS ------------*****'
0500  49T'*****--------------------- SELECTED OUTPUT'
0510  92T'ITEMS -----------------------*****'//
0520  1T'B HOUSE NUMBER IN-STREET-NAME                    ZIP CD'
0530  58T'NYPD-PCT SCHLDST LOW CROSS STREET         '
0540  101T'HIGH CROSS STREET        '/
```

```
0550  1T'- ------------ ------------------------------- ----- --'
0560  58T'-------- ------- -------------------------'
0570  101T'-------------------------'/
0580 *
0590 READ WORK FILE 01 #USER-INPUT 0600  PERFORM FN1-PROCESS
0610 END-WORK
0620 *
0630 DEFINE SUBROUTINE FN1-PROCESS
0640 ************************************************************************
0650 * TO MAKE A FUNCTION 1 CALL:                                          *
0660 *   (1) INITIALIZE WORKAREA 1 TO SPACES                                *
0670 *   (2) SET WA1'S FUNCTION CODE FIELD TO 1                             *
0680 *   (3) SET THE PLATFORM INDICATOR SWITCH (NON-IBM-MAINFRAME)          *
0690 *       TO USE CHARACTER-ONLY WORK AREA (COWS)                         *
0700 *   (4) MOVE THE INPUT BORO TO WA1'S INPUT BORO CODE FIELD             *
0710 *   (5) MOVE THE INPUT HOUSE NUMBER TO WA1'S INPUT HOUSE NUMBER FIELD  *
0720 *   (6) MOVE THE INPUT STREET TO WA1'S INPUT STREET NAME FIELD         *
0730 *   (7) CALL GBI WITH 2 WORKAREAS                                      *
0740 *   (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS                      *
0750 ************************************************************************
0760 ************************************************************************
0770 * AS OF GEOSUPPORT 10.1,                                               *
0780 *    TO RECEIVE ROADBED-SPECIFIC INFORMATION,                          *
0790 *    SET THE ROADBED REQUEST SWITCH TO 'R', AS FOLLOWS:                *
0800 *        MOVE 'R' TO PIWA1-IN-ROADBED-REQ-SWITCH.                      *
0810 ************************************************************************
0820  RESET GEOLP1
0830  MOVE '1 ' TO PIWA1-IN-FUNCTION-CODE
0840  MOVE 'C' TO PIWA1-IN-PLATFORM-INDICATOR
0850  MOVE #USER-BORO TO PIWA1-IN-BORO-1
0860  MOVE #USER-HSE-NUM TO PIWA1-IN-HOUSENUM-DISPLAY
0870  MOVE #USER-STRT-NAME TO PIWA1-IN-STREET-1
0880 *
0890  CALL 'GBI' P1NAT P2NAT
0900 *
0910  IF PIWA1-OUT-RETURN-CODE NOT = '00' AND
0920     PIWA1-OUT-RETURN-CODE NOT = '01'
0930 *
0940 ***** REPLACE YOUR OWN ERROR HANDLING ROUTINE HERE                 *****
0950 *
0960   MOVE PIWA1-OUT-ERROR-MESSAGE TO #OUT-ERROR-MESSAGE-77
0970   WRITE NOTITLE
0980    1T #USER-BORO 3T #USER-HSE-NUM 16T #USER-STRT-NAME
0990    49T '*** FUNCTION 1 GRC =' PIWA1-OUT-RETURN-CODE
1000    73T 'REASON CODE =' PIWA1-OUT-REASON-CODE /
```

```
1010    49T '\***' #OUT-ERROR-MESSAGE-77 /
1020  ELSE
1030   IF PIWA1-OUT-RETURN-CODE = '01'
1040 *
1050 ***** REPLACE YOUR OWN WARNING HANDLING ROUTINE HERE              *****
1060 *
1070    MOVE PIWA1-OUT-ERROR-MESSAGE TO #OUT-ERROR-MESSAGE-77
1080    WRITE NOTITLE
1090     1T #USER-BORO 3T #USER-HSE-NUM 16T #USER-STRT-NAME
1100     49T '*** FUNCTION 1 WARNING, GRC =' PIWA1-OUT-RETURN-CODE
1110     82T 'REASON CODE =' PIWA1-OUT-REASON-CODE /
1120     49T '\***' #OUT-ERROR-MESSAGE-77
1130   END-IF
1140  END-IF
1150 *

1160  IF PIWA1-OUT-RETURN-CODE = '00' OR
1170     PIWA1-OUT-RETURN-CODE = '01'
1180   MOVE PIWA1-OUT-RETURN-CODE TO #SAVE-RET-CODE
1190 *
1200 ***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR                   *****
1210 ***** PROCESSING SUCCESSFUL GEOSUPPORT FUNCTION 1 CALL            *****
1220 *
1230 ************************************************************************
1240 * THIS PROGRAM ASSUMES THERE EXISTS AT LEAST ONE HIGH AND              *
1250 * ONE LOW CROSS STREET.  TO GET THE STREET NAMES OF THE                *
1260 * FIRST-LISTED HIGH AND FIRST-LISTED LOW CROSS STREETS                 *
1270 * FROM THE HIGH AND LOW STREET CODE LISTS CALL FUNCTION D:             *
1280 *   (1) INITIALIZE WORKAREA 1 TO SPACES                                *
1290 *   (2) SET WA1'S FUNCTION CODE FIELD TO D                             *
1300 *   (3) SET THE PLATFORM INDICATOR SWITCH (NON-IBM-MAINFRAME)          *
1310 *       TO USE CHARACTER-ONLY WORK AREA (COWS)                         *
1320 *   (4) SET WA1'S STREET NAME LENGTH FIELD TO DESIRED                  *
1330 *       VALUE (IN THIS CASE 25 BECAUSE THE REPORT LINE                 *
1340 *              HAS SPACE FOR ONLY 25 CHARACTERS)                       *
1350 *   (5) USE THE COMPACT STREET NAMES OPTION TO OBTAIN                  *
1360 *       STREET NAMES FORMATTED FOR DISPLAY                             *
1370 *   (6) MOVE WA2'S LOW B5SC FIELD TO WA1'S INPUT STREET CODE 1 FIELD   *
1380 *   (7) MOVE WA2'S HIGH B5SC FIELD TO WA1'S INPUT STREET CODE 2 FIELD  *
1390 *   (8) CALL GBI WITH 1 WORKAREA                                       *
1400 *   (9) CHECK RETURN CODES FOR ERRORS OR WARNINGS                      *
1410 ************************************************************************
1420   RESET GEOLP1
1430   MOVE 'C' TO PIWA1-IN-PLATFORM-INDICATOR
1440   MOVE 'D ' TO PIWA1-IN-FUNCTION-CODE
```

```
1450   MOVE '25' TO PIWA1-IN-SNL
1460   MOVE 'C' TO PIWA1-IN-SN-NORM-FORMAT
1470   MOVE PIWA2-FN1-LOW-B5SC(1) TO #B5SC
1480   MOVE #B5SC-BORO TO PIWA1-IN-BORO-1
1490   MOVE #B5SC-5SC TO PIWA1-IN-10SC-1
1500   MOVE PIWA2-FN1-HI-B5SC(1) TO #B5SC
1510   MOVE #B5SC-BORO TO PIWA1-IN-BORO-2
1520   MOVE #B5SC-5SC TO PIWA1-IN-10SC-2
1530 *
1540   CALL 'GBI' P1NAT
1550 *
1560   IF PIWA1-OUT-RETURN-CODE = '00'
1570    MOVE PIWA1-OUT-STREET-1 TO #OUT-STREET-1-SNL25
1580    MOVE PIWA1-OUT-STREET-2 TO #OUT-STREET-2-SNL25
1590 *
1600 ***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR                    *****
1610 ***** PROCESSING SUCCESSFUL GEOSUPPORT CALLS                       *****
1620 *
1630    IF #SAVE-RET-CODE = '01' RESET #USER-BORO
1640     #USER-HSE-NUM #USER-STRT-NAME
1650    END-IF
1660    WRITE NOTITLE
1670     1T #USER-BORO 3T #USER-HSE-NUM 16T #USER-STRT-NAME
1680     49T PIWA2-FN1-ZIP 55T PIWA2-FN1-COM-DIST-NUM
1690     58T PIWA2-FN1-POL-PRECINCT 67T PIWA2-FN1-SCHL-DIST
1700     75T #OUT-STREET-1-SNL25 101T #OUT-STREET-2-SNL25 /
1710   ELSE
1720 *
1730 ***** REPLACE YOUR OWN ERROR HANDLING ROUTINE HERE                 *****
1740 *
1750    MOVE PIWA1-OUT-ERROR-MESSAGE TO #OUT-ERROR-MESSAGE-77
1760    WRITE NOTITLE
1770     1T #USER-BORO 3T #USER-HSE-NUM 16T #USER-STRT-NAME
1780     49T '*** FUNCTION D GRC =' PIWA1-OUT-RETURN-CODE
1790     73T 'REASON CODE =' PIWA1-OUT-REASON-CODE /
1800     49T '\***' #OUT-ERROR-MESSAGE-77 /
1810   END-IF
1820  END-IF
1830 *
1840  END-SUBROUTINE
1850  END
```

NATURAL SAMPLE PROGRAM #1- Job Stream

```
//GEOBUPG1 JOB    YOUR-JOB-CARD-INFORMATION
```

```
//*
//*******************************************************************
//***  NATURAL SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#1   ***
//***                       MSW FORMAT                              ***
//*******************************************************************
//S1  EXEC NT3MPM1M,REGION=7000K
//* * * * * * *  * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                                  \*//
//*  AS OF GEOSUPPORT VERSION 10.0,                                  \*//
//*  THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP        \*//
//*  MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATSETS:            \*//
//*       A030.GEO.SUPPORT.PDSE.LOADLIB                              \*//
//*       A030.GEO.SUPPORT.LOADLIB                                   \*//
//*                                                                  \*//
//* * * * * * *  * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//NAT.STEPLIB DD
//            DD
//            DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//SYSPRINT    DD SYSOUT=A
//SYSOUT      DD SYSOUT=A,DCB=(LRECL=132)
//CMPRINT     DD SYSOUT=A,DCB=(LRECL=132)
//CMWKF01     DD *
1,22          ,READE ST
1,500         ,DUANE ST
1,2-4         ,BROADWAY
4,165-100     ,BAISLEY BLVD
4,165-1000    ,BAISLEY BLVD
//CMSYNIN     DD *
Your_Application_ID,Your-User_ID
%*
Your-Password
L L GEOLW1     [For COW: GEOLP1]
L L GEOLW2     [For COW: GEOLP2]
L P GEOBUPG1   [For COW Sample:  GEOBUPGA]
GEOBUPG1       [For COW Sample:  GEOBUPGA}
FIN
//INCLIB      DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//* * * * * * *  * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                                  \*//
//*  AS OF GEOSUPPORT VERSION 10.0,                                  \*//
//*  DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD,        \*//
//*  ETC) ARE NO LONGER NEEDED AND ARE IGNORED. GEOSUPPORT           \*//
//*  IS TAILORED TO USE STANDARD GEOSUPPORT DATA SET NAMES.          \*//
//*  TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.         \*//
```

```
//*                                                                  \*//
//* * * * * * *  * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//SYSUDUMP    DD DUMMY
//
```

SAMPLE NATURAL PROGRAM #1 EXECUTION OUTPUT

```
            *****---------- INPUT ADDRESS ------------***** *****---------------------
SELECTED OUTPUT ITEMS -----------------------*****

            B HOUSE NUMBER IN-STREET-NAME                    ZIP CD NYPD-PCT SCHLDST LOW
CROSS STREET          HIGH CROSS STREET
            \- ------------ ------------------------------- ----- -- -------- ------- -------
------------------ ------------------------

            1 22           READE ST                        10007 01 005      02      ELK
STREET                BROADWAY

            1 500          DUANE ST                        *** FUNCTION 1 GRC = 42 REASON
CODE =
                                                           *** ADDRESS NUMBER OUT OF RANGE

            1 2-4          BROADWAY                        *** FUNCTION 1 WARNING, GRC = 01
REASON CODE = 1
                                                           *** ADDR NUMBER ALTERED: RANGE
ASSUMED. USING DIGITS BEFORE DASH ONLY
                                                           10004 01 001      02      STONE
STREET              BOWLING GREEN

            4 165-100      BAISLEY BLVD                    11434 12 113      28      GUY R
BREWER BOULEVARD    BEDELL STREET

            4 165-1000     BAISLEY BLVD                    *** FUNCTION 1 GRC = 13 REASON
CODE = 2
                                                           *** ADDRESS NBR 165-1000  HAS MORE
THAN 3 DIGITS AFTER THE DASH.
```

NATURAL SAMPLE PROGRAM #2

– Program Source Code - MSW

- Program Source Code - COW

- Input Job Stream

- Output Report

NATURAL SAMPLE PROGRAM #2 – Program Source Code - MSW

```
0010************************************************************************
0020 * PGM NAME: GEOBUPG2    DATE: 08-18-98                                 *
0030 *                                                                      *
0040 * THIS PROGRAM MAKES FUNCTION 2 AND D CALLS TO GEOSUPPORT USING TWO    *
0050 * BOROS AND TWO STREET NAMES SUPPLIED BY AN INSTREAM FILE.             *
0060 * FUNCTION 2 RETURNS GEOGRAPHIC INFORMATION FOR AN INTERSECTION.       *
0070 * FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.         *
0080 ************************************************************************
0090 *          NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE       *
0100 *                ORIGINAL CALL TO FUNCTION 1, ALL THE CROSS STREET     *
0110 *                NAMES WOULD HAVE BEEN RETURNED BY FUNCTION 1.         *
0120 ************************************************************************
0130 *
0140 ************************************************************************
0150 * USE OF GEOSUPPORT LDA (REFERENCED BELOW BY THE LOCAL USING STATEMENT)*
0160 * IS STRONGLY ENCOURAGED.                                              *
0170 ************************************************************************
0180 *
0190 DEFINE DATA
0200  LOCAL USING GEOLW1
0210  LOCAL USING GEOLW2
0220 *
0230 ***** REPLACE CODE BELOW WITH YOUR OWN INPUT DATA DECLARATION      *****
0240 *
0250  LOCAL
0260   01 #USER-INPUT
0270      02 #USER-BORO1                  (A1)
0280      02 #FILLER1                     (A1)
0290      02 #USER-STRT-NAME1             (A32)
0300      02 #FILLER2                     (A1)
0310      02 #USER-BORO2                  (A1)
0320      02 #FILLER3                     (A1)
0330      02 #USER-STRT-NAME2             (A32)
0340      02 #FILLER4                     (A11)
0350 *
0360   01 #INDEX                          (I1)
0370 *
0380 END-DEFINE
0390 *
0400 FORMAT LS=133 PS=65
0410 *
```

```
0420 ***** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT              *****
0430 *
0440 WRITE NOTITLE
0450  1T'SAMPLE NATURAL PROGRAM \#2 EXECUTION OUTPUT'//
0460  1T'*****---------------- INPUT INTERSECTION'
0470  43T'----------------------*****'
0480  71T'*****------------ SELECTED OUTPUT ITEMS -------------*****'//
0490  1T 'B IN-STREET-NAME-1                '
0500  36T'B IN-STREET-NAME-2                '
0510  71T'  ZIP CD NYPD-PCT SCHLDST INTERSECTING STREET NAMES'/
0520  1T '- -------------------------------'
0530  36T'- -------------------------------'
0540  71T'----- -- -------- ------- -------------------------------'
0550 *
0560 READ WORK FILE 01 #USER-INPUT
0570  PERFORM FN2-PROCESS
0580 END-WORK
0590 *
0600 DEFINE SUBROUTINE FN2-PROCESS
0610 ************************************************************************
0620 * TO MAKE A FUNCTION 2 CALL:                                          *
0630 *    (1) INITIALIZE WORKAREA 1 TO SPACES                               *
0640 *    (2) SET WA1'S FUNCTION-CODE TO 2                                  *
0650 *    (3) MOVE THE 1ST INPUT BORO TO WA1'S INPUT BORO CODE FIELD        *
0660 *    (4) MOVE THE 1ST INPUT STREET TO WA1'S INPUT STREET NAME FIELD    *
0670 *    (5) MOVE THE 2ND INPUT BORO TO WA1'S INPUT BORO CODE 2 FIELD      *
0680 *    (6) MOVE THE 2ND INPUT STREET TO WA1'S INPUT STREET NAME 2 FIELD  *
0690 *    (7) CALL GBI WITH 2 WORKAREAS                                     *
0700 *    (8) CHECK RETURN CODES FOR ERRORS OR WARNINGS                     *
0710 ************************************************************************
0720  RESET GEOLW1
0730  MOVE '2 ' TO GEO-WA1-IN-FUNCTION-CODE
0740  MOVE #USER-BORO1 TO GEO-WA1-IN-BORO
0750  MOVE #USER-STRT-NAME1 TO GEO-WA1-IN-STREET-1
0760  MOVE #USER-BORO2 TO GEO-WA1-IN-BORO-2
0770  MOVE #USER-STRT-NAME2 TO GEO-WA1-IN-STREET-2
0780 *
0790  CALL 'GBI' W1NAT W2NAT
0800 *
0810  IF GEO-WA1-OUT-RETURN-CODE NOT = '00' AND
0820     GEO-WA1-OUT-RETURN-CODE NOT = '01'
0830 *
0840 ***** REPLACE CODE BELOW WITH YOUR OWN ERROR HANDLING ROUTINE HERE *****
0850 *
0860   WRITE NOTITLE /
```

```
0870    1T '***** FUNCTION 2 GRC =' GEO-WA1-OUT-RETURN-CODE
0880    27T 'REASON CODE ='GEO-WA1-OUT-REASON-CODE
0890    43T ','GEO-WA1-OUT-ERROR-MESSAGE /
0900    1T #USER-BORO1 3T #USER-STRT-NAME1
0910    36T #USER-BORO2 38T #USER-STRT-NAME2
0920  ELSE
0930   IF GEO-WA1-OUT-RETURN-CODE = '01'
0940 *
0950 *** REPLACE CODE BELOW WITH YOUR OWN WARNING HANDLING ROUTINE HERE   ***
0960 *
0970    WRITE NOTITLE /
0980     1T '***** FUNCTION 2 WARNING, GRC =' GEO-WA1-OUT-RETURN-CODE
0990     37T 'REASON CODE =' GEO-WA1-OUT-REASON-CODE
1000     53T ','GEO-WA1-OUT-ERROR-MESSAGE /
1010     1T #USER-BORO1 3T #USER-STRT-NAME1
1020     36T #USER-BORO2 38T #USER-STRT-NAME2
1030   END-IF
1040  END-IF
1050 *
1060   IF GEO-WA1-OUT-RETURN-CODE = '00' OR
1070      GEO-WA1-OUT-RETURN-CODE = '01'
1080 *
1090 ***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR                  *****
1100 ***** PROCESSING SUCCESSFUL GEOSUPPORT FUNCTION 2 CALL           *****
1110 *
1120    FOR #INDEX 1 TO GEO-WA2-FN2-NUM-OF-INTERSECTS
1130 ************************************************************************
1140 * TO GET STREET NAMES FOR INTERSECTING STREET CODES                   *
1150 * MAKE A FUNCTION D CALL:                                              *
1160 *    (1) INITIALIZE WORKAREA 1 TO SPACES                               *
1170 *    (2) SET THE WA1'S FUNCTION CODE FIELD TO D                        *
1180 *    (3) USE THE COMPACT STREET NAMES OPTION TO OBTAIN                 *
1190 *        STREET NAMES FORMATTED FOR DISPLAY                            *
1200 *    (4) MOVE THE PACKED BORO AND STREET CODE TO                       *
1210 *        WA1'S INPUT STREET CODE 1 FIELD                               *
1220 *    (5) CALL GBI WITH 1 WORKAREA                                      *
1230 *    (6) CHECK RETURN CODES FOR ERRORS OR WARNINGS                     *
1240 ************************************************************************
1250     RESET GEOLW1
1260     MOVE 'D ' TO GEO-WA1-IN-FUNCTION-CODE
1270     MOVE 'C ' TO GEO-WA1-IN-COMPACT-NAME-FLAG
1280     MOVE '25' TO GEO-WA1-IN-SNL
1290     MOVE GEO-WA2-FN2-INTERSECT-PBSC(#INDEX) TO GEO-WA1-IN-STREETCODE-1
1300 *
1310     CALL 'GBI' W1NAT
```

```
1320 *
1330     IF GEO-WA1-OUT-RETURN-CODE = '00'
1340 *
1350 ***** INSERT YOUR OWN CODE HERE FOR                                *****
1360 ***** PROCESSING SUCCESSFUL FUNCTION D CALLS                       *****
1370 *
1380      IF #INDEX = 1
1390       WRITE NOTITLE /
1400        1T #USER-BORO1 3T #USER-STRT-NAME1
1410        36T #USER-BORO2 38T #USER-STRT-NAME2
1420        71T GEO-WA2-FN2-ZIP 77T GEO-WA2-FN2-COMDIST-NUM
1430        80T GEO-WA2-FN2-POL-PRECINCT 89T GEO-WA2-FN2-SCHOOLDIST
1440        97T GEO-WA1-OUT-STREET-1
1450      ELSE
1460       WRITE NOTITLE
1470        97T GEO-WA1-OUT-STREET-1
1480      END-IF
1490     ELSE IF GEO-WA1-OUT-RETURN-CODE NOT = '00'
1500 *
1510 ***** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE                  *****
1520 *
1530      WRITE NOTITLE /
1540       1T '***** FUNCTION D GRC =' GEO-WA1-OUT-RETURN-CODE
1550       27T 'REASON CODE =' GEO-WA1-OUT-REASON-CODE
1560       43T ','GEO-WA1-OUT-ERROR-MESSAGE /
1570       1T #USER-BORO1 3T #USER-STRT-NAME1
1580       36T #USER-BORO2 38T #USER-STRT-NAME2
1590     END-IF
1600     END-IF
1610    END-FOR
1620  END-IF
1630 *
1640 END-SUBROUTINE
1650 END
```

NATURAL SAMPLE PROGRAM #2 – Program Source Code - COW

```
0010 ************************************************************************
0020 * PGM NAME: GEOBUPGB    DATE: 08-18-98     MODIFIED : 08-28-06         *
0030 *                                                                      *
0040 * THIS PROGRAM MAKES FUNCTION 2 AND D CALLS TO GEOSUPPORT USING TWO    *
0050 * BOROS AND TWO STREET NAMES SUPPLIED BY AN INSTREAM FILE.             *
0060 * FUNCTION 2 RETURNS GEOGRAPHIC INFORMATION FOR AN INTERSECTION.       *
0070 * FUNCTION D TRANSLATES AN INPUT STREET CODE TO A STREET NAME.         *
0080 ************************************************************************
```

```
0090 *          NOTE: IF THE CROSS STREET NAMES FLAG WERE USED IN THE       *
0100 *                ORIGINAL CALL TO FUNCTION 2, ALL THE CROSS STREET     *
0110 *                NAMES WOULD HAVE BEEN REUTRNED BY FUNCTION 2.         *
0120 ************************************************************************
0130 *                                                                      *
0140 ************************************************************************
0150 * USE OF GEOSUPPORT LDA (REFERENCED BELOW BY THE LOCAL USING STATEMENT)*
0160 * IS STRONGLY ENCOURAGED.                                              *
0170 ************************************************************************
0180 *
0190 DEFINE DATA
0200  LOCAL USING GEOLP1
0210  LOCAL USING GEOLP2
0220 *
0230 ***** REPLACE CODE BELOW WITH YOUR OWN INPUT DATA DECLARATION      *****
0240 *
0250  LOCAL
0260   01 #USER-INPUT
0270      02 #USER-BORO1                  (A1)
0280      02 #FILLER1                     (A1)
0290      02 #USER-STRT-NAME1             (A32)
0300      02 #FILLER2                     (A1)
0310      02 #USER-BORO2                  (A1)
0320      02 #FILLER3                     (A1)
0330      02 #USER-STRT-NAME2             (A32)
0340      02 #FILLER4                     (A11)
0350 *
0360   01 #INDEX                          (I1)
0370 *
0380   01 #B5SC (A6)
0390   01 REDEFINE #B5SC
0400      02 #B5SC-BORO (A1)
0410      02 #B5SC-5SC (A5)
0420 *
0430   01 #NUM-INTERSECT-A (A1)
0440   01 REDEFINE #NUM-INTERSECT-A
0450      02 #NUM-INTERSECT-N (N1)
0460 *
0470 END-DEFINE
0480 *
0490 FORMAT LS=133 PS=60
0500 *
0510 ***** REPLACE CODE BELOW WITH YOUR OWN REPORT LAYOUT              *****
0520 *
0530 WRITE NOTITLE
```

```
0540  1T'SAMPLE NATURAL PROGRAM \#2 EXECUTION OUTPUT'//
0550  1T'*****----------------- INPUT INTERSECTION'
0560  43T'----------------------*****'
0570  71T'*****------------ SELECTED OUTPUT ITEMS -------------*****'//
0580  1T 'B IN-STREET-NAME-1                '
0590  36T'B IN-STREET-NAME-2                '
0600  71T'  ZIP CD NYPD-PCT SCHLDST INTERSECTING STREET NAMES'/
0610  1T '- -------------------------------'
0620  36T'- -------------------------------'
0630  71T'----- -- -------- ------- -------------------------------'
0640 *
0650 READ WORK FILE 01 #USER-INPUT
0660  PERFORM FN2-PROCESS
0670 END-WORK
0680 *
0690 DEFINE SUBROUTINE FN2-PROCESS
0700 ************************************************************************
0710 * TO MAKE A FUNCTION 2 CALL:                                          *
0720 *    (1) INITIALIZE WORKAREA 1 TO SPACES                               *
0730 *    (2) SET WA1'S FUNCTION-CODE TO 2                                  *
0740 *    (3) SET THE PLATFORM INDICATOR SWITCH (NON-IBM-MAIN-FRAME)        *
0750 *        TO USE CHARACTER ONLY WORK AREAS (COWS)
0760 *    (4) MOVE THE 1ST INPUT BORO TO WA1'S INPUT BORO CODE FIELD        *
0770 *    (5) MOVE THE 1ST INPUT STREET TO WA1'S INPUT STREET NAME FIELD    *
0780 *    (6) MOVE THE 2ND INPUT BORO TO WA1'S INPUT BORO CODE 2 FIELD      *
0790 *    (7) MOVE THE 2ND INPUT STREET TO WA1'S INPUT STREET NAME 2 FIELD  *
0800 *    (8) CALL GBI WITH 2 WORKAREAS                                     *
0810 *    (9) CHECK RETURN CODES FOR ERRORS OR WARNINGS                     *
0820 ************************************************************************
0830  RESET GEOLP1
0840  MOVE '2 ' TO PIWA1-IN-FUNCTION-CODE
0850  MOVE 'C' TO PIWA1-IN-PLATFORM-INDICATOR
0860  MOVE #USER-BORO1 TO PIWA1-IN-BORO-1
0870  MOVE #USER-STRT-NAME1 TO PIWA1-IN-STREET-1
0880  MOVE #USER-BORO2 TO PIWA1-IN-BORO-2
0890  MOVE #USER-STRT-NAME2 TO PIWA1-IN-STREET-2
0900 *
0910  CALL 'GBI' P1NAT P2NAT
0920 *
0930  IF PIWA1-OUT-RETURN-CODE NOT = '00' AND
0940     PIWA1-OUT-RETURN-CODE NOT = '01'
0950 *
0960 ***** REPLACE CODE BELOW WITH YOUR OWN ERROR HANDLING ROUTINE HERE *****
0970 *
0980   WRITE NOTITLE /
```

```
0990    1T '***** FUNCTION 2 GRC =' PIWA1-OUT-RETURN-CODE
1000    27T 'REASON CODE ='PIWA1-OUT-REASON-CODE
1010    43T ','PIWA1-OUT-ERROR-MESSAGE /
1020    1T #USER-BORO1 3T #USER-STRT-NAME1
1030    36T #USER-BORO2 38T #USER-STRT-NAME2
1040  ELSE
1050   IF PIWA1-OUT-RETURN-CODE = '01'
1060 *
1070 *** REPLACE CODE BELOW WITH YOUR OWN WARNING HANDLING ROUTINE HERE   ***
1080 *
1090    WRITE NOTITLE /
1100     1T '***** FUNCTION 2 WARNING, GRC =' PIWA1-OUT-RETURN-CODE
1110     37T 'REASON CODE =' PIWA1-OUT-REASON-CODE
1120     53T ','PIWA1-OUT-ERROR-MESSAGE /
1130     1T #USER-BORO1 3T #USER-STRT-NAME1
1140     36T #USER-BORO2 38T #USER-STRT-NAME2
1150   END-IF
1160  END-IF
1170 *
1180   IF PIWA1-OUT-RETURN-CODE = '00' OR
1190      PIWA1-OUT-RETURN-CODE = '01'
1200 *
1210 ***** REPLACE CODE BELOW WITH YOUR OWN CODE FOR                  *****
1220 ***** PROCESSING SUCCESSFUL GEOSUPPORT FUNCTION 2 CALL           *****
1230 *
1240   MOVE PIWA2-FN2-NUM-OF-INTERSECTS TO #NUM-INTERSECT-A
1250   FOR #INDEX 1 TO #NUM-INTERSECT-N
1260 ************************************************************************
1270 * TO GET STREET NAMES FOR INTERSECTING STREET CODES                   *
1280 * MAKE A FUNCTION D CALL:                                              *
1290 *    (1) INITIALIZE WORKAREA 1 TO SPACES                               *
1300 *    (2) SET THE WA1'S FUNCTION CODE FIELD TO D                        *
1310 *    (3) SET THE PLATFORM INDICATOR SWITCH (NON-IBM-MAIN-FRAME)        *
1320 *        TO USE CHARACTER ONLY WORK AREAS (COWS)                       *
1330 *    (4) USE THE COMPACT STREET NAMES OPTION TO OBTAIN                 *
1340 *        STREET NAMES FORMATTED FOR DISPLAY                            *
1350 *    (5) MOVE THE PACKED BORO AND STREET CODE TO                       *
1360 *        WA1'S INPUT STREET CODE 1 FIELD                               *
1370 *    (6) CALL GBI WITH 1 WORKAREA                                      *
1380 *    (7) CHECK RETURN CODES FOR ERRORS OR WARNINGS                     *
1390 ************************************************************************
1400     RESET GEOLP1
1410     MOVE 'D ' TO PIWA1-IN-FUNCTION-CODE
1420     MOVE 'C' TO PIWA1-IN-PLATFORM-INDICATOR
1430     MOVE 'C' TO PIWA1-IN-SN-NORM-FORMAT
```

```
1440 *   MOVE PIWA2-FN2-INTERSECT-B5SC(#INDEX) TO PIWA1-IN-10SC-1
1450     MOVE PIWA2-FN2-INTERSECT-B5SC(#INDEX) TO #B5SC
1460     MOVE #B5SC-BORO TO PIWA1-IN-BORO-1
1470     MOVE #B5SC-5SC TO PIWA1-IN-10SC-1
1480 *
1490     CALL 'GBI' P1NAT
1500 *
1510     IF PIWA1-OUT-RETURN-CODE = '00'
1520 *
1530 ***** INSERT YOUR OWN CODE HERE FOR                              *****
1540 ***** PROCESSING SUCCESSFUL FUNCTION D CALLS                     *****
1550 *
1560      IF #INDEX = 1
1570       WRITE NOTITLE /
1580        1T #USER-BORO1 3T #USER-STRT-NAME1
1590        36T #USER-BORO2 38T #USER-STRT-NAME2
1600        71T PIWA2-FN2-ZIP 77T PIWA2-FN2-COM-DIST-NUM
1610        80T PIWA2-FN2-POL-PRECINCT 89T PIWA2-FN2-SCHL-DIST
1620        97T PIWA1-OUT-STREET-1
1630      ELSE
1640       WRITE NOTITLE
1650        97T PIWA1-OUT-STREET-1
1660      END-IF
1670     ELSE IF PIWA1-OUT-RETURN-CODE NOT = '00'
1680 *
1690 ***** INSERT YOUR OWN ERROR HANDLING ROUTINE HERE                *****
1700 *
1710      WRITE NOTITLE /
1720       1T '***** FUNCTION D GRC =' PIWA1-OUT-RETURN-CODE
1730       27T 'REASON CODE =' PIWA1-OUT-REASON-CODE
1740       43T ','PIWA1-OUT-ERROR-MESSAGE /
1750       1T #USER-BORO1 3T #USER-STRT-NAME1
1760       36T #USER-BORO2 38T #USER-STRT-NAME2
1770     END-IF
1780     END-IF
1790    END-FOR
1800  END-IF
1810 *
1820 END-SUBROUTINE
1830 END
```

NATURAL SAMPLE PROGRAM #2 – Job stream

```
//GEOBUPG2 JOB    YOUR-JOB-CARD-INFORMATION
//*
```

```
//*******************************************************************
//***  NATURAL SAMPLE BATCH GEOSUPPORT USER APPLICATION PROGRAM \#2   ***
//***                        MSW FORMAT                              ***
//*******************************************************************
//S1  EXEC NT3MPM1M,REGION=7000K
//* * * * * * *  * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                                   \*//
//*  AS OF GEOSUPPORT VERSION 10.0,                                   \*//
//*  THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP         \*//
//*  MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATSETS:             \*//
//*       A030.GEO.SUPPORT.PDSE.LOADLIB                               \*//
//*       A030.GEO.SUPPORT.LOADLIB                                    \*//
//*                                                                   \*//
//* * * * * * *  * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//NAT.STEPLIB DD
//            DD
//            DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR
//            DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//SYSPRINT    DD SYSOUT=A
//SYSOUT      DD SYSOUT=A,DCB=(LRECL=132)
//CMPRINT     DD SYSOUT=A,DCB=(LRECL=132)
//CMWKF01     DD *
1,CHAMBERS ST                     ,1,HUDSON ST
1,SIXTH AV                        ,1,W. 8 ST
1,DUANE ST                        ,1,READE ST
//CMSYNIN     DD *
Your-Application-ID,Your-User-ID
%*
Your-Password
L L GEOLW1         [For COW: GEOLP1]
L L GEOLW2         [For COW: GEOLP2]
L P GEOBUPG2       [For COW Sample:  GEOBUPGB]
GEOBUPG2           [For COW Sample:  GEOBUPGB]
FIN
//INCLIB      DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR
//* * * * * * *  * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//*                                                                   \*//
//*  AS OF GEOSUPPORT VERSION 10.0,                                   \*//
//*  DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD,         \*//
//*  ETC) ARE NO LONGER NEEDED AND ARE IGNORED. GEOSUPPORT            \*//
//*  IS TAILORED TO USE STANDARD GEOSUPPORT DATA SET NAMES.           \*//
//*  TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.          \*//
//*                                                                   \*//
//* * * * * * *  * * * * * * * * * * * * * * * * * * * * * * * * * * * \*//
//SYSUDUMP    DD DUMMY
```

SAMPLE NATURAL PROGRAM #2 EXECUTION OUTPUT

```
            *****---------------- INPUT INTERSECTION ----------------------***** *****-------
----- SELECTED OUTPUT ITEMS -------------*****

            B IN-STREET-NAME-1                B IN-STREET-NAME-2                  ZIP CD
NYPD-PCT SCHLDST INTERSECTING STREET NAMES
            - ------------------------------- - ------------------------------- ----- -- ---
----- ------- ------------------------------

            1 CHAMBERS ST                     1 HUDSON ST                       10007 01 001
02      CHAMBERS STREET

HUDSON STREET

WEST BROADWAY

            1 SIXTH AV                        1 W. 8 ST                         10014 02 006
02      6 AVENUE

GREENWICH AVENUE

WEST 8 STREET

            ***** FUNCTION 2 GRC = 62 REASON CODE =   , READE STREET & DUANE STREET DO NOT
INTERSECT
            1 DUANE ST                        1 READE ST
```

APPENDIX 9: GBAT REFERENCE TABLES

Table A9-1: GBAT Control Entry Descriptions by Keyword

This table lists all of the control entries alphabetically by keyword. Each control entry's coding format is indicated, and its purpose and usage are described. Control entry variables are indicated using 'S' and 'L' to represent the starting position and length, respectively, of a field in the input data records, and 'V' to represent other types of variables. Certain control entries do not have full table entries of their own but are cross-referenced to closely related control entries.

Control Entry	Description
ALIASES=V	Specifies whether an input alias file is to be used during this GBAT run. If so, during the processing of the input data file, the user-defined street name aliases in the alias file supplement the set of street names that Geosupport recognizes ([see ChapterIX.6] (/chapters/chapterIX/section06/)). This control entry is optional; if it is not coded, the default value is NO. The valid variable values are NO, YES and VAL. ALIASES=NO directs GBAT not to perform any alias processing. If there is an ALIASES DD statement in the JCL, it is ignored. ALIASES=YES directs GBAT to validate the ALIASES file, and then to process the input data file whether or not there are any invalid records in the alias file. An ALIASES DD statement referring to the alias file is required to be in the JCL. ALIASES=VAL directs GBAT to validate the alias file, and then to process the input data file only if there are no invalid records in the alias file. An ALIASES DD statement referring to the alias file is required to be in the JCL.
AUXSEG=V	Specifies whether the Work Area 2 to be used to form the records written into the output file of accepted data (OUTFILE) is the regular WA2 or the auxiliary segment WA2 ([see Chapter II.6] (/chapters/chapterII/section06/)). The valid variable values are YES and NO and are self-explanatory. Currently, the Auxiliary Segment WA2 option is only available for COW format Functions 3 and 3C; this control entry is invalid for all other functions. For the functions that have the Auxiliary Segment WA2 option, this control entry is invalid when GEOCODE=NO or VAL; it is optional when GEOCODE=YES or ALL, and the default value is

	NO.
BBL=S,10	Specifies the starting position and length of the input BBL field in the input data records. This control entry is valid only for Function BL. This control entry can be used in place of the three control entries BORO, BLOCK and LOT whenever the input data records contain those three items in adjacent positions so that they can be treated collectively as a BBL field. The length value must be explicitly coded as '10'.
BIN=S or BIN=S,7	Specifies the starting position and length of the input Building Identification Number (BIN) field in the input data records. This control entry is valid only for Function BN. An input BIN field must always have a length of seven bytes, which may be coded explicitly as '7' in this control entry or it may be left uncoded, in which case it defaults to that value.
BLOCK=S or BLOCK=S,5	Specifies the starting position and length of the input tax block field in the input data records. This control entry is valid only for Function BL. Either all three control entries BORO, BLOCK and LOT must be specified, or the control entry BBL must be specified. An input tax block field must always have a length of five bytes, which may be coded explicitly as '5' in this control entry, or it may be left uncoded, in which case it defaults to that value.
BORO=S,L	Specifies the starting position and length of the input borough code field in the input data records. This control entry is valid for all functions except Function BN. It is mandatory for functions that require an input borough code field. BORO is optional if ZIPCODE is specified for Function 1, 1A, 1B or 1E. For Functions 2, 3, 3C, 3S and D, which accept multiple input street fields, the field specified by BORO serves as the input borough code field for the input street field specified by the control entry ONSTREET or STRTCODE; in addition, if the control entries CROSSBORO1 and CROSSBORO2 are not coded, it also serves as the input borough code field for the other input street fields. The maximum permissible length value of BORO is L=12. Note: The input borough code field specified by BORO may contain user-defined, non-standard borough code values - see discussion at table entry for BRONX.
BRONX=V **BROOKLYN=V** **MANHATTAN=V** **QUEENS=V** **STATEN=V**	GBAT can accept non-standard, user-defined borough code values in the input borough code fields specified by the control entries BORO, CROSSBORO1 and CROSSBORO2. (If there is more than one input borough code field, the same borough code values must be used in all of them.) The five control entries BRONX, BROOKLYN, MANHATTAN, QUEENS and STATEN are used

	to specify the character strings that represent each borough in those input borough code fields. (Note: these control entries do not pertain to the borough code sub-fields that are embedded within larger data items such as BBL, BIN and B7SC, which must always contain the standard Geosupport borough code values.) The five borough code values may be specified as any strings of non-blank characters the lengths of which do not exceed the length value specified in the BORO control entry (which has a maximum permissible length value of 12). Embedded blanks should not be included in user-defined borough code values, since the first blank that GBAT encounters when scanning a borough code value terminates the scan. For example, coding STATEN=STATEN ISLAND would cause GBAT to interpret the control entry as STATEN=STATEN and to interpret ISLAND as the next keyword in the control file. Since ISLAND is an invalid control keyword, GBAT would terminate abnormally. However, coding STATEN=STATENISLAND (without the embedded blank) is acceptable. These five control entries are optional, but if any of them is coded, all five must be coded. If these control entries are not coded, the default values are the standard Geosupport borough codes, as follows: MANHATTAN=1 BRONX=2 BROOKLYN=3 QUEENS=4 STATEN=5
BROOKLYN	See BRONX.
BROWSEFLAG=V	Specifies whether the Browse Flag request (described in [Chapter III.7](/chapters/chapterIII/section07/) and [III.8] (/chapters/chapterIII/section08/)) is in effect. This control entry is valid only for COW functions that return normalized street name output. For such functions, this control entry is optional. BROWSEFLAG=P specifies that the Browse Flag is set to ‘P’. Only the primary name and street code of the input street names will be returned to the user.

	BROWSEFLAG=F specifies that the Browse Flag is set to ‘F’. Only principal street name and street code of the input street names will be returned to the user. BROWSEFLAG=R specifies that the Browse Flag is set to ‘R’. Only the DCP or BOE preferred street name and street code of the input street names will be returned to the user. The value of ‘R’ is valid only for ‘GEOCODE=YES’ or ‘GEOCODE=ALL’.
B7SC1=S **or B7SC1=S,8** **B7SC1=S,8** **B7SC1=S,8** **B7SC3=S or** **B7SC3=S,8**	Specify the starting positions of up to three input Borough-and-7-digit Street Code (B7SC) fields for input to Function DG. An input B7SC field must always have a length of 8, which may be coded explicitly in these control entries, or it may be left uncoded, in which case it defaults to 8.
B10SC1=S or **B10SC1=S or** **B10SC2=S or** **B10SC2=S,11** **B10SC3=S or** **B10SC3=S,11**	Specify the starting positions of up to three input Borough-and-10-digit Street Code (B10SC) fields for input to Function DN. An input B10SC field must always have a length of 11, which may be coded explicitly in these control entries, or it may be left uncoded, in which case it defaults to 11.
COMPACT=V	Specifies whether the Compact Names option (described in [Chapter III.3](/chapters/chapterIII/section03/)) is in effect. This control entry is valid only for functions that return normalized street name output. For such functions, this control entry is optional, and NO is the default value. COMPACT=YES specifies that the Compact Names option is in effect. Street names with numeric components are normalized into the compact format. COMPACT=NO specifies that the Compact Names option is not in effect. Street names with numeric components are normalized into the sort format.
COMPASS=S	Specifies the position of an input compass direction field in the input data records. This control entry is never coded with a length variable; GBAT always assumes an input compass direction field to be one byte long. This control entry is valid only for Functions 2, 3C and 3S. For Function 2: this control entry is required only if the input data file contains at least one input street intersection defined by a pair of streets that intersect at two distinct locations (see Chapter VII.2). In such input data records, the input compass direction field

	must contain a valid non-blank compass direction value, ‘N’, ‘S’, ‘E’ or ‘W’, which serves to designate which of the two intersections of the given pair of streets is to be processed. In other input data records, the input compass direction field should be blank. For Function 3C: this control entry is mandatory. The input data field that this control entry specifies contains the compass direction designating the side of the street. This field must contain a valid non-blank compass direction value, ‘N’, ‘S’, ‘E’ or ‘W’, in every input data record. For Function 3S: this control entry corresponds to the ‘first input intersection’, that is, the input intersection defined either by ONSTREET and CROSS1 or by STRTCODE and CRSCOD1. (The control entry COMPASS2 corresponds to the second input intersection.) The COMPASS control entry is required only if the input data file contains at least one first input intersection that is defined by a pair of streets that intersect in two locations (see Chapter VII.2). In such input data records, the input data field that this control entry specifies must contain a valid compass direction value identifying which of the two locations is the intended first input intersection. In other input data records, this field should contain a blank.
COMPASS2=S	Specifies the position of the input compass direction field in the input data records that corresponds to the second input intersection, that is, the input intersection defined either by ONSTREET and CROSS2 or by STRTCODE and CRSCOD2. The COMPASS2 control entry is never coded with a length variable; GBAT always assumes an input compass direction field to be one byte long. The COMPASS2 control entry is valid only for Function 3S. It is required only if the input data file contains at least one second input intersection that is defined by a pair of streets that intersect at two distinct locations ([see Chapter VII.2](/chapters/chapterVII/section02/)). In such input data records, the input data field that this control entry specifies must contain a valid compass direction value identifying which of the two locations is the intended second input intersection. In other input data records, this field should contain a blank.
CROSSBORO1=S,L	Specifies the starting position and length of the input borough code field corresponding to the input street field specified by the control entry CROSS1 or CRSCOD1.

	CROSSBORO1 is coded only if the input data records have separate borough code fields corresponding to each of the input street fields. Such separate input borough code fields enable GBAT to process input data files containing borough boundary locations that are defined by streets in different boroughs (see discussion of Geosupports borough boundary processing feature in Chapter VII.7). CROSSBORO1 is valid for Functions 2, 3, 3C, 3S and D, and is optional for those functions. If CROSSBORO1 is not coded, then the field specified by BORO is used as the input borough code field for the input street field specified by CROSS1 or CRSCOD1. If CROSSBORO1 is coded, then whenever the field it specifies contains a blank, the contents of the field specified by BORO is used as the input borough code for the input street field specified by CROSS1 or CRSCOD1. If CROSSBORO1 is coded, and the input street field it applies to is specified by CRSCOD1 rather than CROSS1 (i.e., if that field contains street codes rather than street names), and the length of CRSCOD1 is specified as 4 or 6 (i.e., the input street code field is in one of the formats that contain their own borough code), then CROSSBORO1 is ignored, and the input borough code field it specifies is not used. Note: The input borough code field specified by CROSSBORO1 may contain user-defined, non-standard borough code values - see discussion at table entry for BRONX.
CROSSBORO2=S,L	Specifies the starting position and length of the input borough code field corresponding to the input street field specified by the control entry CROSS2 or CRSCOD2. CROSSBORO2 is coded only if the input data records have separate borough code fields corresponding to each of the input street fields. Such separate input borough code fields enable GBAT to process input data files containing borough boundary locations that are defined by streets in different boroughs (see discussion of Geosupport's borough boundary processing feature in Chapter VII.7. CROSSBORO2 is valid for Functions 3, 3C, 3S and D, and is optional for those functions. If CROSSBORO2 is not coded, then the field specified by BORO is used as the input borough code field for the input street field specified by CROSS2 or CRSCOD2. If CROSSBORO2 is coded, then whenever the field it specifies contains a blank, the contents of the field specified by BORO is used as the input borough code for the input street field specified by CROSS2 or CRSCOD2. If CROSSBORO2 is coded, and the input street field it applies to is specified by CRSCOD2

	rather than CROSS2 (i.e., if that field contains street codes rather than street names), and the length of CRSCOD2 is specified as 4 or 6 (i.e., the input street code field is in one of the formats that contain their own borough code), then CROSSBORO2 is ignored, and the input borough code field it specifies is not used. Note: The input borough code field specified by CROSSBORO2 may contain user-defined, non-standard borough code values - see discussion at table entry for BRONX.
CROSSSTNAMES=V	Specifies whether a list of street names of the cross streets or intersecting streets is to be included in the appended output data. Note: the CROSSSTNAMES feature incurs processing overhead, and should only be used when necessary. Note that CROSSSTNAMES may no longer be necessary with certain COW functions since MODE=X (Extended Mode) and Function 1B Work Areas are now supported, and they contain the cross street B7SCs and the corresponding Principal cross street names. CROSSSTNAMES=YES specifies that the street names of the cross streets (RECTYPE=1, 1E, 2, 3 or 3C) or intersecting streets (RECTYTPE=2) are to be appended. This causes a 320-byte block of data to be included in the appended data containing those street names, laid out as described in the Appendix 3 entry for the List of Street Names (see paragraph on List of Cross Street Names). CROSSSTNAMES=YES is valid only when GEOCODE=ALL and RECTYPE=1, 1E, 2, 3 or 3C have been specified. CROSSSTNAMES=NO specifies that the street names of cross streets or intersecting streets are not to be appended. The default value is NO. This control entry is optional; if it is not coded, the default value is NO.
CROSS1, CROSS2	See ONSTREET.
CRSCOD1, CRSCOD2	See STRTCODE.
GEOCODE=V	Specifies whether GBAT will issue one-work-area or two-work-area calls (see Chapter II.4; whether OUTFILE will be produced; and if so, what information GBAT will append to the user input records in forming the OUTFILE records (see Chapter XI.7. The valid variable values for this control entry are NO, YES, ALL and

	VAL. For COW Functions 1, 1E, 1A and 1B, see also keyword GEOUNIT. GEOCODE=NO specifies a one-work-area call. Only selected information from Work Area 1 is appended. For Function BL, the BBL is appended; for Function BN, the BIN is appended; for the other functions, normalized house numbers, normalized street names and street codes are appended. For a detailed layout of the appended information for GEOCODE=NO, see Table A9-4 for MSW format, and see Table A12-2 for COW format. In addition, for COW Functions 1, 1E, 1A and 1B, if GEOUNIT=YES is specified, the Normalized Display Format Unit output field is also appended, in the form of a 70-byte block of data, the first 14 bytes of which are the Unit output field. For a description of the Unit fields, see Chapter V.15. OUTFILE is produced. GEOCODE=YES specifies a two−work−area call. Only a copy of Work Area 2 for the given function is appended. OUTFILE is produced. GEOCODE=ALL specifies a two−work−area call. Both the GEOCODE=NO information (including the GEOUNIT=YES information, as described above with GEOCODE=NO) and the GEOCODE=YES information are appended. In addition, if CROSSSTNAMES=YES is specified, a list of street names of the cross streets or intersecting streets is also appended, in the form of a 320-byte block of data, between the GEOCODE=NO data and the GEOCODE=YES data. OUTFILE is produced. GEOCODE=VAL specifies a two−work−area call. OUTFILE is not produced. This control entry is optional. The default value depends on the function: it is NO for Functions 1, 1N, 2, 3, D, DG and DN, and it is YES for all other functions. The values YES, ALL and VAL are invalid for functions that can only be called using one work area (currently, Functions 1N, D, DG and DN).
GEOUNIT=V	Specifies whether GBAT will append the Normalized Display Format Unit Output field. This control entry is valid only for COW Functions 1, 1E, 1A and 1B and only when GEOCODE=NO or GEOCODE=ALL is specified. The Normalized Display Format Unit output field is appended, in the form of a 70-byte block of data, the first 14 bytes of which are the Unit output field. See the description of GEOCODE=V above. The GEOUNIT control entry is optional. The valid values are YES and NO. The default is

	GEOUNIT=NO. For a description of the Unit fields, see Chapter V.15.
HNI=V	Specifies whether the input house number fields specified by the HOUSENUM and HOUSENUM2 control entries are House Numbers in Internal format (HNIs) (see Chapter V.2) or are in character format, indicated by the variable values YES and NO respectively. The HNI control entry is optional only for MSW Functions 1, 1A, 1E, D, DG and DN, and is invalid for other functions and for the COW format. The default value depends on the function. For MSW Functions 1, 1A and 1E, NO is the default, and YES is also valid. For MSW Functions D, DG and DN, YES is the default and is the only valid value.
HNS=V	Specifies whether the input house number field specified by the HOUSENUM and HOUSENUM2 control entries are House Numbers in Sort format (HNSs) (see Chapter V.2) or are in character format, indicated by the variable values YES and NO respectively. The HNS control entry is optional for COW Functions 1, 1A, 1E, D, DG and DN, and is invalid for other functions and for the MSW format. The default value depends on the function. For COW Functions 1, 1A and 1E, NO is the default, and YES is also valid. For COW Functions D, DG and DN, YES is the default and is the only valid value.
HOUSENUM=S or HOUSENUM=S,L	Specifies the starting position and length of an input house number field. This control entry is optional. It is valid for Functions 1, 1A, 1B, 1E, D, DG and DN. For Functions 1, 1A, 1B and 1E, if HOUSENUM is not coded, Geosupport assumes that the input street name field (specified by the control entry ONSTREET) contains a free−form address (see ChapterV.3). If HOUSENUM is coded, the input data field it specifies may contain either a House Number in Internal format (HNI - for MSW format only - see ChapterV.2), a House Number in Sort Format (HNS - for COW format only - see ChapterV.2), or a house number in character format. If it contains an HNI, then the control entry HNI=YES must be in effect (either by explicitly coding it or by default), and HOUSENUM's length variable must either be coded with the value '6' or not coded (in which case it defaults to '6' by virtue of HNI=YES). If it contains an HNS, then the control entry HNS=YES must be in effect (either by explicitly coding it or by default), and HOUSENUM's length variable must either be coded with the value '11' or not coded (in which case it defaults to '11' by virtue of HNS=YES). If HOUSENUM is not an HNI or an HNS, its length variable must be a number between 5 and 12.

	For Functions D, DG and DN, if HOUSENUM is coded, for MSW format, the input data field it specifies must contain an HNI, and the length variable must either be coded with the value ‘6’ or not coded (in which case it defaults to ‘6’). For COW format, the input data field it specifies must contain an HNS, and the length variable must either be coded with the value ‘11’ or not coded (in which case it defaults to ‘11’).
HOUSENUM2=S or HOUSENUM2=S,L	Specifies the starting position and length of an input house number field containing an HNI for the MSW format, or an HNS for the COW format. HOUSENUM2 is valid for Functions D, DG and DN, for which it is optional. Those functions can accept two input HNI or HNS fields per call. Coding both HOUSENUM and HOUSENUM2 enables two input HNI or HNS fields to be processed through Functions D, DG or DN in a single GBAT pass. For the MSW format, when HOUSENUM2 is coded, the OUTFILE records include a corresponding 12-byte field (identified as HND-2 in Table A9-4) in the appended data for a House Number in Display format (HND), and the total length of the appended data is 120 bytes. When HOUSENUM2 is not coded using the MSW format, no corresponding HND-2 field is included in the OUTFILE records, and the total length of the appended data is 108 bytes. For the COW format, the OUTFILE record length is always 128 bytes, and has space for two 16-byte output House Numbers in Display format (HNDs), each of which would either have data or be blank, dependent on the input..
LONGWA2=V	Specifies whether the Work Area 2 to be used to form the records written into the output file of accepted data (OUTFILE) is the regular WA2 or the long WA2 (see ChapterII.5). The valid variable values are YES and NO and are self-explanatory. Currently, the long WA2 option is only available for MSW format Functions 1, 1E, and 3, and for both MSW and COW formats for Functions 1A and BL; this control entry is invalid for all other functions. For the functions that have the long WA2 option, this control entry is invalid when GEOCODE=NO or VAL; it is optional when GEOCODE=YES or ALL, and the default value is NO.
LOT=S,L	Specifies the starting position and length of the input tax lot field. This control entry is valid only for Function BL. The Function BL user must specify either all three control entries BORO, BLOCK and LOT, or the control entry BBL. The length value of LOT must be explicitly coded as ‘4’. There is no default.

MANHATTAN	See BRONX.
MAXREJECTS=V	Specifies how many rejects (including warnings, if REJECTWARNINGS=YES has been specified) occurring at the beginning of the input data file, other than any records rejected for an invalid borough code, are to cause a 'MAXREJECTS termination', that is, would cause GBAT to terminate execution abnormally and exit with Condition Code 20 (see ChapterXI.3). The variable value must be either a positive integer specifying the number of such rejects that are to cause a MAXREJECTS termination, or the value NOMAX. If MAXREJECTS=NOMAX is coded, the entire input data file is processed, regardless of the number of rejects occurring at the beginning of the file. The MAXREJECTS control entry is optional, and the default value is MAXREJECTS=200.
MODE=V	Specifies whether the Work Area 2 to be used to form the records written into the output file of accepted data (OUTFILE) is the regular WA2 or the Extended WA2 (see ChapterII.7). The valid variable values are X or NO. X requests the Extended Work Area 2. Currently, the extended WA2 option is available only for COW format (WORKAREA=COW) Functions 1, 1E, 1A, 3, 3C, BL, and BN; this control entry is invalid for all other functions. When MODE=X, LONGWA2 cannot be set to YES for Function 1A or BL. All other control cards are the same for each of the Functions 1, 1E, 1A, 3, 3C, BL or BN. For the functions that have the extended WA2 option, this control entry (MODE=X) is invalid when GEOCODE=NO or VAL; it is optional when GEOCODE=YES or ALL, and the default value of MODE is NO.
NODE=S or NODE=S,7	Specifies the starting position and length of the input node ID field. This NODE=S,7 control entry is valid only for COW Functions 2 and 2W. An input node ID field must always have a length of seven bytes, which may be coded explicitly as '7' in this control entry or it may be left uncoded, in which case it defaults to that value. This entry must be coded if you have node input instead of two intersecting streets or an intersection name. Since node input stands on its own and does not require a borough code, the GBAT statistical report will not include groupings by borough. It is therefore recommended that the user not mix street name/street code input with node input.
ONSTREET=S,L **CROSS1=S,L** **CROSS2=S,L**	Specify the starting positions and lengths of input street name fields for Functions 1, 1A, 1B, 1E, 1N, 2, 3, 3C, 3S. (For functions 1, 1A, 1B, 1E, those fields may contain free-form addresses.) The

appropriate combination of these control entries for the function being called must be coded, as follows:

Functions	Field(s) Specified	Control Entries Used to Specify These Fields
1, 1A, 1B, 1E, 1N	‘On’ Street	ONSTREET
2	Two Intersecting Streets in Either Order	ONSTREET and CROSS1
3, 3C, 3S	‘On’ Street and , Two Cross Streets in Either Order	ONSTREET, CROSS1 and CROSS2 (Note: For Function 3S, input cross street fields are optional.)

Whenever input street name fields are specified by coding any of the three control entries ONSTREET, CROSS1 and CROSS2, an input borough code field (or fields) must also be specified, by coding the control entry BORO (and optionally CROSSBORO1 and CROSSBORO2, as appropriate).

Note: for Functions 1, 1A, 1B, 1E, 2, 3, 3C and 3S, but not function 1N, input street data may be provided either in the form of street name fields, specified using the control entries ONSTREET, CROSS1 and CROSS2, or alternatively, in the form of five-digit street code fields (see ChapterIV.8), specified using the control entries STRTCODE, CRSCOD1 and CRSCOD2. For those of the aforementioned functions that accept multiple input streets, either all of those input streets must take the form of street names or all must take the form of street codes; a mixture of names and codes is not permitted. For Function 1N, street name input fields are mandatory.

QUEENS	See BRONX.
REALSTREETONLY=V	Specifies whether the Real Street Only request (described in Chapter VII.6) is in effect. This control entry is valid only for COW function 3S. This control entry is optional. REALSTREETONLY=YES specifies that the Real Street Only flag is set to ‘R’. Only real streets (not bends or non-street features) will be returned to the user.

	REALSTREETONLY=NO specifies that the Real Street Only flag is set to blank. All intersections, including bends and non-street features, will be returned to the user. If this control entry is not coded, the default value is NO.
RECTYPE=V	Specifies the Geosupport function to be executed. This control entry is mandatory. The valid variable values are the valid Geosupport function codes. As of this writing, these are 1, 1A, 1B, 1E, 1N, 2, 3, 3C, 3S, AP, BL, BN, D, DG, DN.
REJECTWARNINGS=V	Specifies whether input data records that result in warnings are to be treated as accepted records or as rejects (see discussion of REJECTWARNINGS in Section XI.7). The valid variable values are YES and NO. This control entry is optional, and the default value is NO. If REJECTWARNINGS=YES is coded, records resulting in warnings (GRC=01) are treated as rejects; that is, they are written into ERRFILE (or ERRFIL2) rather than OUTFILE, they are counted as rejects in the report of run statistics, and they are considered to be rejects for the purpose of determining whether a MAXREJECTS termination is to be triggered. If REJECTWARNINGS=NO is coded or is in effect by default, warnings are treated as accepted records; that is, they are written into OUTFILE rather than ERRFILE (or ERRFIL2), they are counted as accepted records in the report of run statistics, and they are considered to be accepted records for the purpose of determining whether a MAXREJECTS termination is to be triggered.
RELATEDNODES=V	If COW Function 2 results in a 'many-node case' (GRC 03 with Reason Code A), this control entry specifies if GBAT should return the Nodes and B7SCs for the streets at those nodes (up to 20 nodes). This control entry is valid only with WORKAREA=COW, RECTYPE=2 and GEOCODE=YES or ALL. ERRFIL3 will contain this output. The variable values are YES and NO and are self-explanatory. If these If this control entry is not coded, the default value is NO.
ROADBED=V	Specifies whether the output of a multi-Roadbed street should contain Roadbed information or information based on the center line of the street. This control entry is valid only for Functions 1, 1E, 1B and 3S for which it is optional. The variable values are YES and NO and are self-explanatory. If this control entry is not coded, the default value is NO.

SNL=V	Specifies a value for the Street Name Normalization Length Limit (SNL) parameter (see ChapterIII.2). The variable value must be a number between 4 and 32, inclusive. This control entry is valid only for functions that return normalized street names, for which it is optional. The default value is 32.
STATEN	See BRONX.
STRTCODE=S,L **CRSCOD1=S,L** **CRSCOD2=S,L**	Specify the starting positions and lengths of input five-digit street code fields for Functions 1, 1A, 1B, 1E, 2, 3, 3C, 3S and D. The appropriate combination of these control entries for the function being called must be coded, as follows:

Functions	Street Input Fields Required	Control Entries Used to Specify These Fields
1, 1A, 1B, 1E	‘On’ Street	STRTCODE
2	Two Intersecting Streets in Either Order	STRTCODE and CRSCOD1
3, 3C, 3S	‘On’ Street and Two Cross Streets in Either Order	STRTCODE, CRSCOD1 and CRSCOD2 (Note: For Function 3S, input cross street fields are optional.)
D	Up to Three 5-Digit Street Codes	CRSCOD1 if necessary, CRSCOD2 if necessary

Each of the input street code fields specified by STRTCODE, CRSCOD1 and CRSCOD2 must contain a five-digit street code in one of four formats: P5SC (which has a length of 3 bytes, valid only with MSW format), PB5SC (length = 4, valid only with MSW format), 5SC (length = 5) or B5SC (length = 6). For Functions 2, 3, 3C, 3S and D, which can have multiple input five-digit street code fields, it is allowable for those fields to have different formats; for example, for MSW Function 3, it is permissible for the input ‘on’ street field to contain a PB5SC while one input cross street field contains a 5SC and the other input cross street field contains a B5SC. The user must code the length variable value in each of these control entries so that it accords with the street code format of the corresponding input street code field. GBAT uses that length value to determine which five-digit street code format to expect in that input field.

If any input street code fields are in the form of P5SCs or 5SCs, which do not contain their own borough code sub-field, the input data file must also have a separate input borough code field or

	fields, which must be specified by coding the control entry BORO, and if needed, the control entries CROSSBORO1 and CROSSBORO2. Note: for Functions 1, 1A, 1B, 1E, 2, 3, 3C and 3S, but not Function D, input street data may be provided either in the form of five-digit street code fields, specified using the control entries STRTCODE, CRSCOD1 and CRSCOD2, or alternatively, in the form of street name fields, specified using the control entries ONSTREET, CROSS1 and CROSS2. For those of the aforementioned functions that accept multiple input streets, either all of those input streets must take the form of street codes or all must take the form of street names; a mixture of codes and names is not permitted. For Function D, input street data must be in the form of street codes.
TITLE=V	Specifies a title to appear on the top of the SYSPRINT output report of summary run statistics. A valid variable value is any character string of up to 73 bytes ending in a semicolon. This control entry is optional. If it is not coded, the report is generated without a title. If it is coded, it is mandatory to terminate the title character string with a semicolon, which does not appear in the actual report.
TPADDATA=V	Specifies whether TPAD processing should be performed for functions 1A, 1B, BL, and BN Work Area 2 giving more up-to-date property-level information. (see ChapterVI.11).The valid variable values are YES and NO. Y requests the TPAD processing. The TPADDATA option is available only for COW format (WORKAREA=COW) Functions 1A, 1B, BL, and BN; this control entry is invalid for all other functions. All other control cards are the same for each of the Functions 1A, 1B, BL or BN. For the functions that have the TPAD option, this control entry (TPADDATA=YES) is invalid/ignored when GEOCODE=NO or VAL; it is optional when GEOCODE=YES or ALL, and the default value of TPADDATA= NO.
UNIT=S,L	Specify the starting position and length for the input Unit field. This control entry is valid only for COW Functions 1, 1E, 1A and 1B. This control entry is optional and there is no default. To have GBAT append the Normalized Display Format Unit Output field (in OUTFILE) also specify GEOUNIT=YES and either GEOCODE=NO or GEOCODE=ALL. See the description of those control entries. For a description of the Unit fields, see ChapterV.15.
VSAM=V	Specifies whether the input data file is a VSAM file or a sequential

	file. The valid variable values are YES and NO, specifying that the file is a VSAM file or a sequential file, respectively. This control entry is optional, and NO is the default value. If NO is specified or is in effect by default, then in the JCL, the DD statement for the input data file must contain the DDname INFILE. If YES is specified, the DDname must be coded as INVSAM.
WORKAREA=V	Specifies whether the work areas should be in MSW or COW format. The WORKAREA control entry is valid for all functions. The valid variable values are COW (Character Only Work Area) and MSW (Mainframe Specific Work Area), and are self-explanatory. If this control entry is not coded, the default value is MSW.
WORKAREA1=V	Specifies whether Work Area 1 is to be included at the end of each record written to the Output File of Rejected Records. The valid variable values are YES or NO. YES requests that Work Area 1 be included in the output records. NO requests that Work Area 1 not be included in the output records. When WORKAREA1=YES the records are written to ERRFIL4 and ERRFIL5; when WORKAREA1=NO, the records are written to ERRFILE and ERRFIL2 (see Chapter IX.8). WORKAREA1 is optional and is valid only when the format is COW (WORKAREA=COW). The default value of WORKAREA1 is NO.
ZIPCODE=S or ZIPCODE=S,5	Specifies the starting position and length of the input ZIP code field. This control entry is valid only for Functions 1, 1A, 1B and 1E. An input ZIP code field must always have a length of five bytes, which may be coded explicitly as ‘5’ in this control entry or it may be left uncoded, in which case it defaults to that value.
1ABLVERSION=V	Specifies that standard processing is to be performed for Functions 1A and BL (see ChapterVI.8). The 1ABLVERSION control entry is valid only for Functions 1A and BL, and is required for the MSW format. The only valid variable value for this control entry is STANDARD or S, and is self-explanatory. Note: Legacy has been discontinued..

Table A9-2: Summary of GBAT Control Entries by Keyword

This table lists all of the control entries alphabetically by keyword, indicates their coding formats, their allowable and default variable values, and the Geosupport functions for which each control entry or combination of control entry and variable value is valid. Control entry variables are indicated using ‘S’ and ‘L’ to represent the starting position and length of a field in the input data records, respectively, and ‘V’ to represent variables of other types.

Table A9-2: Summary of GBAT Control Entries by Keyword			
Control Entry	**Valid Variable Values**	**Default**	**Functions**
ALIASES=V	NO, YES, VAL	NO	1, 1A, 1B, 1E, 1N, 2, 3, 3C, 3S, AP
AUXSEG=V	YES, NO	NO	COW only: 3, 3C
BBL=S,10	1 <=S <=(LRECL-1)-10	None	BL
BIN=S or BIN=S,7	1 <=S <=(LRECL+1)-7	L=7	BN
BLOCK=S or BLOCK=S,5	1 <=S <=(LRECL+1)-5	L=5	BL
BORO=S,L	1 <=S <=(LRECL+1)-L 1 <=L <=1 2	None	All but BN, DG, DN
BRONX=V	Any character string that fits BORO	2	All but BN, DG, DN
BROOKLYN=V	Any character string that fits BORO	3	All but BN, DG, DN
BROWSEFLAG=V	P, F, R	None	1, 1A, 1B, 1E,1N, 2, 3, 3C, AP
B7SC1=S or B7SC1=S,8	1 <=S <=(LRECL+1)-8	L=8	DG
B7SC2=S or B7SC2=S,8	1 <=S <=(LRECL+1)-8	L=8	DG
B7SC3=S or B7SC3=S,8	1 <=S <=(LRECL+1)-8	L=8	DG
B10SC1=S or B10SC1=S,11	1 <=S <=(LRECL+1)-11	L=11	DN
B10SC2=S or B10SC2=S,11	1 <=S <=(LRECL+1)-11	L=11	DN
B10SC3=S or B10SC3=S,11	1 <=S <=(LRECL+1)-11	L=11	DN
COMPACT=V	YES, NO	NO	All but BL, BN
COMPASS=S	1 <=S <=L RECL	None	2, 3C, 3S
COMPASS2=S	1 <=S <=L RECL	None	3S
CROSSBORO1=S,L	1 <=S <=(LRECL+1)-L 1 <=L <=1 2	None	2, 3, 3C, 3S, D
	1 <=S <=(LRECL+1)-		

CROSSBORO2=S,L	L 1 <=L <=1 2	None	3, 3C, 3S, D
CROSSSTNAMES=V	YES, NO (YES is valid only for GEOCODE=ALL)	NO	1, 1B, 1E, 2, 3, 3C
CROSS1=S,L	1 <=S <=(LRECL+1)-L 4 <=L <=3 2	None	2, 3, 3C, 3S
CROSS2=S,L	1 <=S <=(LRECL+1)-L 4 <=L <=3 2	None	3, 3C, 3S
CRSCOD1=S,L	1 <=S <=(LRECL+1)-L 1 <=L <=1 2	None	3, 3C, 3S, D
CROSS1=S,L	1 <=S <=(LRECL+1)-L 4 <=L <=3 2	None	2, 3, 3C, 3S
CROSS2=S,L	1 <=S <=(LRECL+1)-L 4 <=L <=3 2	None	3, 3C, 3S
CRSCOD1=S,L	1 <=S <=(LRECL+1)-L L=3 if field contains P5SC (MSW) L=4 if field contains PB5SC (MSW) L=5 if field contains 5SC L=6 if field contains B5SC	None	2, 3, 3C, 3S, D
CRSCOD2=S,L	1 <=S <=(LRECL+1)-L L=3 if field contains P5SC (MSW) L=4 if field contains PB5SC (MSW) L=5 if field contains 5SC L=6 if field contains B5SC	None	3, 3C, 3S, D
GEOCODE=V	NO, YES, ALL, VAL YES and ALL are invalid for Functions	NO	1, 1N, 2, 3, D, DG, DN

	1N, D, DG, DN)	YES	1A, 1B, 1E, 3C, 3S, AP, BL, BN
GEOUNIT=V	YES, NO (YES is valid only for GEOCODE=NO or GEOCODE=ALL)	NO	COW only: 1, 1E, 1A, 1B
HNI=V	YES, NO (MSW format only) (NO is invalid for MSW Fns D, DG, DN)	YES	D, DG, DN
		NO	1, 1A, 1E
HNS=V	YES, NO (COW format only) (NO is invalid for COW Fns D, DG, DN)	YES	D, DG, DN
		NO	1, 1A, 1B, 1E, AP
HOUSENUM=S or HOUSENUM=S,L	1 <=S <=(LRECL+1)-L 5 <=L <=1 2 if field contains house number in character format L= 6 if field contains HNI L=11 if field contains HNS	L=6 when HNI=YES;L=11 when HNS= YES else no length default	1, 1A, 1B, 1E, AP, D, DG, DN
HOUSENUM2=S or HOUSENUM2=S,L	1 <=S <=(LRECL+1)-L L= 6 if field contains HNI L=11 if field contains HNS	L=6 when HNI=YES; L=11 when HNS=YES	D, DG, DN
LONGWA2=V	YES, NO	NO	MSW and COW: 1A, BL MSW only: 1, 1E, 3
LOT=S,4	1 <=S <=(LRECL+1)-4	None	BL
MANHATTAN=V	Any character string that fits BORO	1	All but BN, DG, DN
MAXREJECTS=V	Any positive integer or NOMAX	200	All
MODE=V	X, NO	NO	COW and GEOCODE=ALL or YES:

			1,1E,1A,3,3C, BL,BN
ONSTREET=S,L	1 <=S <=(LRECL+1)-L 4 <=L <=3 2	None	1, 1A, 1B, 1E, 1N, AP, 2, 3, 3C, 3S
QUEENS=V	Any character string that fits BORO	4	All but BN, DG, DN
RECTYPE=V	1, 1A, 1B, 1E, 1N, 2, 3, 3C, 3S, AP, BL, BN, D, DG, DN	None	All (Note 1B and AP are COW only
REALSTREETONLY=V	YES, NO	NO	COW only: 3S
REJECTWARNINGS=V	YES, NO	NO	All
ROADBED	YES, NO	NO	1, 1B, 1E, 3S
SNL=V	4 <=V <=3 2	32	All but BL, BN
STATEN=V	Any character string that fits BORO	5	All but BN, DG, DN
STRTCODE=S,L	1 <=S <=(LRECL+1)-L L=3 if contains P5SC (MSW L=4 if contains PB5SC (MSW) L=5 if contains 5SC L=6 if contains B5SC	None	1, 1A, 1B, 1E, 2, 3, 3C, 3S, AP, D
TITLE=V	Any character string of up to 73 bytes ending in a semicolon	No title	All
TPADDATA=V	YES, NO	NO	1A, 1B, BL, BN
UNIT=S,L	1 <=S <=(LRECL+1)-L 1 <=L <=1 4	None	COW only: 1, 1E, 1A, 1B
VSAM=V	YES, NO	NO	All
WORKAREA=V	COW, MSW	MSW	All
WORKAREA1=V	YES, NO	NO	COW only: All
ZIPCODE=S or ZIPCODE=S,5	1 <=S <=(LRECL+1)-5	L=5	1, 1A, 1B, 1E, AP
1ABLVERSION=V	STANDARD, S	None	1A, BL

Table A9-3: Summary of GBAT Control Entry Usage by Function

This table lists, by Geosupport function, which control entries are allowable and which of those are mandatory. Control entries are represented in this table by their keywords. Some combinations of control entries are mandatory or prohibited; such conditions are indicated in this table by using the logical connectors “and”, “or” (inclusive or) and “xor” (exclusive or) and by using underlining, as follows:

- A table entry of the form “A and B” signifies that if either A or B is coded, then both must be coded. Similarly, “A and B and C” signifies that if any of A, B or C is coded, then all three must be coded.
- A table entry of the form “A or B” signifies that A may be coded without B, B may be coded without A, and A and B may both be coded. Similarly, “A or B or C” signifies that any combination of these three items may be coded.”
- A table entry of the form “A xor B” signifies that if either A or B is coded, then the other one must not be coded.
- If a table entry is underlined, that control entry or combination of control entries is mandatory for the given function. All table entries not underlined are optional.
- Square brackets (“ [.....]”) are sometimes used for logical grouping to increase clarity.

  Thus, a table entry of the form “A or B” signifies that it is mandatory to code A or B; that is, it is mandatory to code at least one of A and B and it is permissible to code both A and B. “A xor B” signifies that it is mandatory to code A xor B; that is, it is mandatory to code either A or B but prohibited (because of the exclusive or) to code both A and B. A table entry of the form “ [A and B] xor [C and D]” signifies that it is mandatory to code either both A and B or both C and D but prohibited to code all four of them.

Function	**Control Entries**
1	ALIASES, <u>BORO or ZIPCODE</u>, BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, BROWSEFLAG (valid only if WORKAREA=COW),COMPACT, CROSSSTNAMES, GEOCODE, GEOUNIT (requires WORKAREA=COW and [GEOCODE=NO or GEOCODE=ALL]), HNI xor HNS (see Note 1), HOUSENUM (see Note 2), LONGWA2 xor WORKAREA=COW, MAXREJECTS, MODE=X (valid only if WORKAREA=COW and GEOCODE=ALL or YES), <u>ONSTREET xor STRTCODE, RECTYPE</u>, REJECTWARNINGS, ROADBED, SNL, TITLE, UNIT (requires WORKAREA=COW), WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM <u>Note 1</u>: HNI is a valid entry only if WORKAREA defaults to MSW or is set to MSW. HNS is a valid entry only if WORKAREA=COW <u>Note 2</u>: For Functions 1, 1A 1B and 1E, HOUSENUM is optional in the sense that coding it is either mandatory or prohibited, depending, respectively, on whether the input data file contains free-form addresses (in which a single field contains the house number followed by the street name in non-fixed positions; see ChapterV.3) or parsed-form addresses (in which the house number and street name are in separate fields). When HOUSENUM is not coded, the input street must be in the

	form of street names rather than street codes, the input street name field must be specified by the control entry ONSTREET, and in every input data record, that field must contain either a free-form address or a Non-Addressable Place name (NAP). When HOUSENUM is coded, and the input street is in the form of street names, GBAT assumes that the input street name field contains street names and NAPs only, not free-form addresses.
1 Extended	Same as Function 1, except [GEOCODE=ALL] xor [GEOCODE=YES], MODE=X, WORKAREA=COW
1A	ALIASES, BORO or ZIPCODE, BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, BROWSEFLAG (valid only if WORKAREA=COW), COMPACT, GEOCODE, GEOUNIT (requires WORKAREA=COW and [GEOCODE=NO or GEOCODE=ALL]), HNI xor HNS (see Note 1 following Function 1 entry), HOUSENUM (see Note 2 following Function 1 entry), LONGWA2, MAXREJECTS, ONSTREET xor STRTCODE, RECTYPE, REJECTWARNINGS, ROADBED, SNL, TITLE, TPADDATA (requires WORKAREA=COW), UNIT (requires WORKAREA=COW), WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM, 1ABLVERSION
1A Extended	Same as Function 1A, except [GEOCODE=ALL] xor [GEOCODE=YES], LONGWA2=NO (specified or by default), MODE=X, WORKAREA=COW
1B	ALIASES, BORO or ZIPCODE , BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, BROWSEFLAG , COMPACT, CROSSSTNAMES, [GEOCODE=ALL] xor [GEOCODE=YES], GEOUNIT (requires GEOCODE=ALL), HNS, HOUSENUM (see Note 2 following Function 1 entry), MAXREJECTS, ONSTREET xor STRTCODE, RECTYPE, REJECTWARNINGS, ROADBED, SNL, TITLE, TPADDATA, UNIT, WORKAREA=COW, WORKAREA1, VSAM
1E	ALIASES, BORO or ZIPCODE , BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, BROWSEFLAG (valid only if WORKAREA=COW), COMPACT, CROSSSTNAMES, GEOCODE, GEOUNIT (requires WORKAREA=COW and [GEOCODE=NO or GEOCODE=ALL]), HNI xor HNS (see Note 1 following Function 1 entry), HOUSENUM (see Note 2 following Function 1 entry), LONGWA2 xor WORKAREA=COW, MAXREJECTS, ONSTREET xor STRTCODE, RECTYPE, REJECTWARNINGS, ROADBED, SNL, TITLE, UNIT (requires WORKAREA=COW), WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM
1E Extended	Same as Function 1E, except [GEOCODE=ALL] xor [GEOCODE=YES], MODE=X, WORKAREA=COW
1N	ALIASES, BORO, BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, BROWSEFLAG (valid only if WORKAREA=COW), COMPACT, GEOCODE, MAXREJECTS, ONSTREET, RECTYPE, REJECTWARNINGS, SNL, TITLE, WORKAREA, VSAM
	ALIASES, BORO, BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, BROWSEFLAG (valid only if WORKAREA=COW), COMPACT, COMPASS, CROSSBORO1, CROSSSTNAMES, GEOCODE, MAXREJECTS,

2	[ONSTREET and CROSS1] xor [STRTCODE and CRSCOD1], RECTYPE, REJECTWARNINGS, SNL, TITLE, WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM
3	ALIASES, AUXSEG (see Note 3), BORO, BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, BROWSEFLAG (valid only if WORKAREA=COW), COMPACT, CROSSBORO1, CROSSBORO2, CROSSSTNAMES, GEOCODE, LONGWA2 xor WORKAREA=COW, MAXREJECTS, [ONSTREET and CROSS1 and CROSS2] xor [STRTCODE and CRSCOD1 and CRSCOD2], RECTYPE, REJECTWARNINGS, SNL, TITLE, WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM Note 3: AUXSEG is a valid entry only if WORKAREA=COW
3C	ALIASES, AUXSEG (see Note 3 following Function 3 entry), BORO, BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, BROWSEFLAG (valid only if WORKAREA=COW), COMPACT, COMPASS, CROSSBORO1, CROSSBORO2, CROSSSTNAMES, GEOCODE, MAXREJECTS, [ONSTREET and CROSS1 and CROSS2] xor [STRTCODE and CRSCOD1 and CRSCOD2], RECTYPE, REJECTWARNINGS, SNL, TITLE, WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM
3/3C (extended)	
3S	ALIASES, BORO, BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, COMPACT, COMPASS, COMPASS2, CROSSBORO1, CROSSBORO2, [CROSS1 and CROSS2] xor STRTCODE, [CRSCOD1 and CRSCOD2] xor ONSTREET, GEOCODE, MAXREJECTS, ONSTREET xor STRTCODE, REALSTREETONLY (see Note 4), RECTYPE, REJECTWARNINGS, ROADBED, SNL, TITLE, WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM Note 4: REALSTREETONLY is a valid entry only if WORKAREA=COW
AP	ALIASES, BORO or ZIPCODE, BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, BROWSEFLAG , COMPACT, GEOCODE, HNS, HOUSENUM (see Note 2 following Function 1 entry), MAXREJECTS, ONSTREET xor STRTCODE, RECTYPE, REJECTWARNINGS, SNL, TITLE, WORKAREA=COW, WORKAREA1, VSAM
AP Extended	Same as Function AP, except [GEOCODE=ALL] xor [GEOCODE=YES], MODE=X
BL	BORO and BLOCK and LOT xor BBL, BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, LONGWA2, MAXREJECTS, RECTYPE, REJECTWARNINGS, TITLE, TPADDATA (requires WORKAREA=COW), VSAM, WORKAREA, WORKAREA1 (requires WORKAREA=COW), 1ABLVERSION
BL Extended	Same as Function BL, except [GEOCODE=ALL] xor [GEOCODE=YES], LONGWA2=NO (specified or by default), MODE=X, WORKAREA=COW
	BIN, GEOCODE, MAXREJECTS, RECTYPE, REJECTWARNINGS, TITLE,

BN	TPADDATA (requires WORKAREA=COW), WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM
BN Extended	Same as Function BN, except [GEOCODE=ALL] xor [GEOCODE=YES], MODE=X, WORKAREA=COW
D	BRONX and BROOKLYN and MANHATTAN and QUEENS and STATEN, COMPACT, CROSSBORO1, CROSSBORO2, GEOCODE, HNI xor HNS, HOUSENUM or HOUSENUM2 or [BORO and STRTCODE] or [BORO and STRTCODE and CRSCOD1] or [BORO and STRTCODE and CRSCOD1 and CRSCOD2], MAXREJECTS, RECTYPE, REJECTWARNINGS, SNL, TITLE, WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM
DG	COMPACT, GEOCODE, HNI xor HNS, HOUSENUM or HOUSENUM2 or B7SC1 or [B7SC1 and B7SC2] or [B7SC1 and B7SC2 and B7SC3], MAXREJECTS, RECTYPE, REJECTWARNINGS, SNL, TITLE, WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM
DN	COMPACT, GEOCODE, HNI xor HNS, HOUSENUM or HOUSENUM2 or B10SC1 or [B10SC1 and B10SC2] or [B10SC1 and B10SC2 and B10SC3], MAXREJECTS, RECTYPE, REJECTWARNINGS, SNL, TITLE, WORKAREA, WORKAREA1 (requires WORKAREA=COW), VSAM

<span id=""appendix09-tblA9-4"

Table A9-4: MSW Appended Items for GEOCODE=NO

NOTE: For COW Appended Items for GEOCODE=NO see TABLE 12.2
This table contains, by function or combination of function and option, a layout of the data that GBAT appends to the input data record to form the OUTFILE record for the MSW format when GEOCODE=NO has been specified.

Function(s)	Option	Appended Items	Length
1, 1A, 1E		HND HNHPD Normalized Street Name 10SC	12 8 32 10
		Total Length:	62
1N		Normalized Street Name 10SC	32 10
		Total Length:	42
2		Normalized Street Name-1 10SC-1 Normalized Street Name-2 10SC-2	32 10 32 10
		Total Length:	84
3, 3C, 3S		Normalized Street Name-1 10SC-1 Normalized Street Name-2 10SC-2 Normalized Street Name-3 10SC-3	32 10 32 10 32 10
		Total Length:	126
		BBL (Standard Format): Borough Code	

BL	1ABLVERSION=STANDARD	Tax Block Tax Lot	1 5 4
		Total Length:	10
	1ABLVERSION=LEGACY	No longer supported	
BN		BIN Filler	73
		Total Length:	10
D, DG, DN	HOUSENUM2 control entry not coded	HND Normalized Street Name-1 Normalized Street Name-2 Normalized Street Name-3	12 32 32 32
		Total Length:	108
D, DG,DN (cont.)	HOUSENUM2 control entry coded	HND-1 Normalized Street Name-1 Normalized Street Name-2 Normalized Street Name-3 HND-2	12 32 32 32 12
		Total Length:	120

Table A9-5: MSW Format- Length of GBAT−Appended Data

This table lists, by function and GEOCODE value, the length in bytes of the data that GBAT appends to an input data record that has been accepted by Geosupport to form the corresponding OUTFILE record. The LRECL value that the user must specify in the OUTFILE DD statement in the JCL is computed by adding the length of the appended data as indicated in this table to the LRECL of the input data file.

Note: For Functions 1, 1E, 2, 3 and 3C, when GEOCODE=ALL and CROSSSTNAMES=YES, the appended data consist of the concatenation of the GEOCODE=NO data, followed by a 320-byte block of data containing cross street names, followed by the GEOCODE=YES data. For further information about the layout of the appended CROSSSTNAMES data, refer to the Appendix 3 entry for the List of Street Names (see paragraph on List of Cross Street Names).

MSW Functions Options		GEOCODE Value		
		NO	YES	ALL
		62		
	LONGWA2=NO, CROSSSTNAMES=NO		200	262
1, 1E	LONGWA2=YES, CROSSSTNAMES=NO		300	362
	LONGWA2=NO, CROSSSTNAMES=YES			582
	LONGWA2=YES, CROSSSTNAMES=YES			682
	1ABLVERSION=STANDARD	62		
1A	1ABLVERSION=STANDARD, LONGWA2=NO		939	1001
	1ABLVERSION=STANDARD,LONGWA2=YES		17683	17745
1N		42	Invalid	Invalid

2	CROSSSTNAMES=NO	84	200	284
	CROSSSTNAMES=YES			604
		126		
	LONGWA2=NO, CROSSSTNAMES=NO		200	326
3	LONGWA2=YES, CROSSSTNAMES=NO		300	426
	LONGWA2=NO, CROSSSTNAMES=YES			646
	LONGWA2=YES, CROSSSTNAMES=YES			746
3C	CROSSSTNAMES=NO	126	200	326
	CROSSSTNAMES=YES			646
3S		126	4224	4350
BL	1ABLVERSION=STANDARD	10		
	1ABLVERSION=STANDARD, LONGWA2=NO		939	949
	1ABLVERSION=STANDARD, LONGWA2=YES		17683	17693
BN		10	939	949
D, DG, DN	HOUSENUM2 not coded	108	Invalid	Invalid
	HOUSENUM2 coded	120	Invalid	Invalid

APPENDIX 10: SAMPLE GBAT JOBS

This appendix contains printouts of two sample GBAT jobs, referred to as Sample Job 1 and Sample Job 2. Sample Job 1 executes Function 1A. Sample Job 2 executes Function 2.

For each sample job, this appendix contains a description of the control file, followed by listings of the job-stream input and the job output. The job-stream input listing contains the JCL, the in-stream control file, the in-stream data input file, and for Sample Job 2 only, the in-stream ALIASES input file. An ALIASES file is not used in Sample Job 1. The job output listing contains the system job-stream output, the GBAT output report of messages and run statistics, and the output file of GBAT rejects.

GSS developed and ran the sample jobs on the DoITT/Computer Service Center mainframe. Some variations from the JCL shown herein may be necessary for users running on other computers. In addition, the JCL shown has been modified to remove account-specific references.

Please note that the GBAT samples are not guaranteed to run exactly as shown in this appendix. The samples are here as an aid in developing GBAT runs.

Note: The GBAT samples are MSW format samples. To run using the COW format, add the GBAT control entry WORKAREA=COW to the in-stream control files and update the LRECL of the OUTFILE DD card appropriately.

SAMPLE GBAT JOB #1

SAMPLE GBAT JOB 1: DESCRIPTION

The control file for Sample GBAT Job 1 is as follows:

```
BORO=9,1   RECTYPE=1A    ONSTREET=15,20    1ABLVERSION=S
 TITLE=THIS IS GBAT CONTROL FILE EXAMPLE 1;
```

In this example, the user has chosen to code several control entries in a single control record, followed by a second control record containing a heading for the SYSPRINT output file. In the first control record, the order in which the control entries are coded, their precise positioning within the control record and the amount of spacing between them are immaterial.

The control file in this example contains the following control entries. (See Table A9-1 for Control Entry Descriptions)

- BORO specifies that the input borough code field is in position 9 of the INFILE records and is one byte long.
- RECTYPE specifies Function 1A.

- ONSTREET specifies that the input street name field starts in position 15 of the INFILE records and is 20 bytes long.
- 1ABLVERSION specifies that the standard version of Function 1A is to be executed. This control entry is required with the MSW format. The Legacy version of Function 1A is no longer supported.
- TITLE specifies a title for the SYSPRINT output report. Notice that the text of the title is terminated with a semicolon character, as required. (The semicolon does not appear in the actual report.)

The user has chosen not to code the following control entries, the default values for which are therefore in effect: (See Table A9-2 for Control Entry default values.)

- Since the control entry VSAM has not been coded, GBAT will assume that the user input data file is a sequential file. Consequently, GBAT will access the input data file via the DDname INFILE, and the corresponding DD statement in the JCL must be coded accordingly.
    - Since the control entry GEOCODE has not been coded, and Function 1A is being executed, the default value of YES is in effect. This causes GBAT to issue a two−work−area call and to append Work Area 2 for Function 1A to the successfully processed INFILE records in forming the OUTFILE records.
- Since the control entry ALIASES has not been coded, the default value of NO is in effect. Therefore, GBAT will not use temporary user-defined aliases when processing input street names; if an ALIASES DD statement has been included in the JCL, it will be ignored.
- Since the control entries MANHATTAN, BRONX etc. have not been coded, GBAT will assume that the input borough code field contains the default borough code values, which are the standard Geosupport borough codes (‘1’ for Manhattan, ‘2’ for the Bronx, etc.).
- Since HNI (or HNS for COW) has not been coded, GBAT will assume that input house numbers are not necessarily normalized and are in display format rather than in the HNI (or HNS for COW) format.
- Since HOUSENUM has not been coded, GBAT will assume that the input street name field specified by ONSTREET contains a free−form address (a house number followed by a street name). Note that since in this GBAT run input addresses are free-form, partial street names (see Chapter III.4) will be rejected.
- Since COMPACT has not been coded, GBAT will return normalized street names in a format suitable for sorting, rather than in the compact format.

- Since REJECTWARNINGS has not been coded, the default value of NO is in effect, so warnings will be treated as successfully processed records: they will be written to OUTFILE, they will be counted as successfully processed records in the SYSPRINT report, and they will not be counted as rejects towards the MAXREJECTS termination limit.
- Since MAXREJECTS has not been coded, the default value of '200' is in effect, so that GBAT will terminate with an MVS Return Code of '20' if the first 200 INFILE records all result in rejects for any reason other than an invalid borough code.
- Since the SNL control entry has not been coded, GBAT will assume the default value of SNL=32 when normalizing street names.
- Since LONGWA2=YES has not been coded, GBAT will return the regular WA2 for Function 1A.
- Since the WORKAREA control entry has not been coded, GBAT will assume the default value of MSW (Mainframe Specific Work Area).

SAMPLE GBAT JOB 1: JOB-STREAM INPUT

```
//EXAMPLE1 JOB YOUR-JOB-CARD-INFORMATION
//*
//*
//*******************************************************************
//************     THIS JOB IS GBAT MSW EXAMPLE 1     ***************
//*******************************************************************
//*********   THIS STEP INVOKES THE STANDARD CATALOGUED      ********
//*********   PROCEDURE FOR GBAT EXECUTION, CALLED GBAT2     ********
//*******************************************************************
//S1 EXEC GBAT2
//*******************************************************************
//*********   CARDIN IS THE USER-PROVIDED CONTROL FILE       ********
//*******************************************************************
//CARDIN DD *
BORO=9,1  RECTYPE=1A ONSTREET=15,20 1ABLVERSION=S
TITLE=THIS IS GBAT CONTROL FILE MSW EXAMPLE 1;
/*
//*******************************************************************
//*********   INFILE IS THE USER-PROVIDED INPUT DATA.          ******
//*********   IN THIS EXAMPLE, IT IS PROVIDED AS INSTREAM DATA.******
//*******************************************************************
//INFILE DD *
      1     100 GARAGE CENTRE ST
      1     22  READE ST
      1     36  READE ST
```

```
      1     60  READE             ** PARTIAL STREET NAMES NOT ALLOWED
      1     12  ELK               ** IN FREE-FORM ADDRESSES
      1     12  ELK ST
      1     310   BWY
      1     99 W 3 ST
      2     709 E 165 ST
      2     187C  EDGEWATER PK
      4     229-16 87 AVE
      2     1475  LONGFELLOW AV
      1     2053 ADAM POWELL BL
      1     310   1 AVE
      /*
//*******************************************************************
//*********   OUTFILE IS THE UT FILE OF SUCCESSFULLY     ********
//*********   PROCESSED INFILE RECORDS.                     ********
//*******************************************************************
//OUTFILE DD DSN=&&OUT1A,DISP=(NEW,PASS),
//        UNIT=SYSDA,SPACE=(TRK,(80,20),RLSE),
//        DCB=(RECFM=FB,LRECL=1019)
//*******************************************************************
//*** ERRFILE IS THE OUTPUT FILE OF REJECTED INFILE RECORDS.      ***
//*********   INFILE RECORDS.                                ********
//ERRFILE DD SYSOUT=A,DCB=(RECFM=FB,LRECL=84)
//*******************************************************************
//*** AS OF GEOSUPPORT VERSION 10.0, DD STATEMENTS FOR GEOSUPPORT ***
//*** DATA FILES (E.G. GRID, PAD, ETC) ARE NO LONGER NEEDED       ***
//*** AND ARE IGNORED.  GEOSUPPORT IS TAILORED TO USE STANDARD    ***
//*** GEOSUPPORT DATA SET NAMES.                                  ***
//*** TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.     ***
//*******************************************************************
//
```

SAMPLE GBAT JOB 1: OUTPUT

```
J E S 2  J O B  L O G  --  S Y S T E M  M V S P  --  N O D E  C S C B A T C H
10.29.19 JOB17476 ---- FRIDAY,    DD MMMM YYYY ----
10.29.19 JOB17476  IRR010I  USERID YOURUID  IS ASSIGNED TO THIS JOB.
10.29.19 JOB17476  ICH70001I YOURUID  LAST ACCESS AT 10:27:49 ON FRIDAY, MMMM DD, YYYY
10.29.19 JOB17476  $HASP373 EXAMPLE1 STARTED - INIT 84   - CLASS X - SYS MVSP
10.29.19 JOB17476  IEF403I EXAMPLE1 - STARTED - TIME=10.29.19
10.29.19 JOB17476  +GBI SUCCESSFULLY LOADED GBIDRV
10.29.20 JOB17476  +GBIDRV (VERSION VV.V) INVOKED
10.29.20 JOB17476  +GEO (VERSION VV.V) INVOKED
10.29.20 JOB17476  +snd NNN  OPENED SUCCESSFULLY
10.29.20 JOB17476  +PAD NNN  'B030.GEO.COW.BLDGS.CITY' OPENED SUCCESSFULLY
```

```
        10.29.20 JOB17476  -                                          --TIMINGS (MINS.)--
----PAGING COUNTS---
        10.29.20 JOB17476  -JOBNAME  STEPNAME PROCSTEP    RC   EXCP   CONN    TCB    SRB  CLOCK
SERV  PG  PAGE  SWAP   VIO
        10.29.20 JOB17476  -EXAMPLE1 S1       GBAT2       00    787    142    .00    .00     .0
1198   0     0     0     0
        10.29.20 JOB17476  IEF404I EXAMPLE1 - ENDED - TIME=10.29.20
        10.29.20 JOB17476  -EXAMPLE1 ENDED.  NAME-YOURUID             TOTAL TCB CPU TIME=
.00  TOTAL ELAPSED TIME=    .0
        10.29.20 JOB17476  $HASP395 EXAMPLE1 ENDED

        ------ JES2 JOB STATISTICS ------

        DD MMMM YYYY JOB EXECUTION DATE

               60 CARDS READ

              208 SYSOUT PRINT RECORDS

                0 SYSOUT PUNCH RECORDS

               15 SYSOUT SPOOL KBYTES


             0.01 MINUTES EXECUTION TIME

             1 //EXAMPLE1 JOB YOUR-JOB-CARD-INFORMATION
               //*
               //*
               //*******************************************************************
               //************     THIS JOB IS GBAT MSW EXAMPLE 1     ***************
               //*******************************************************************
               //*******************************************************************
               //*********   THIS STEP INVOKES THE STANDARD CATALOGUED      ********
               //*********   PROCEDURE FOR GBAT EXECUTION, CALLED GBAT2     ********
               //*******************************************************************
             3 //S1 EXEC GBAT2
             4 XXGBAT2 PROC                                                          00000100
               XX**                          /* IN CSC.TEST.PROCLIB * /
00000200
               XX**                          /* MODIFIED 06/30/06  BY MEB   * /
00000315
               XX**                          /* ADDED SUPPORT.PDSE.LOADLIB  * /
00000415
               XX**                          /* REMOVED DD CARDS            * /
```

```
00000515
              XX**                          /* MODIFIED 05/11/06  BY MEB   * /
00000615
              XX**                          /* ADDED GRID1R FILE           * /
00000715
              XX**                          /* MODIFIED 07/25/05  BY MEB   * /
00000815
              XX**                          /* PEDFILE BECOMES DUMMY FILE  * /
00000915
              XX**                          /* MODIFIED 03/26/02  BY MEB   * /
00001015
              XX**                                                          00001115
              XX**** WARNING: DO NOT OVERRIDE THE REGION PARAMETER  **************    00001215
              XX**                                                          00001315
            5 XXGBAT2 EXEC PGM=GBATIO2,REGION=9M,PARM='ISASIZE(40K)'        00001415
              XX*                                                           00001516
              XX*************************************************************/    00001616
              XX*                                                       * /
00001716
              XX*   AS OF GEOSUPPORT VERSION 10.0,                      * /
00001816
              XX*   THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP   * /
00001916
              XX*   MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:      * /
00002016
              XX*               A030.GEO.SUPPORT.PDSE.LOADLIB               * /
00002116
              XX*               A030.GEO.SUPPORT.LOADLIB                    * /
00002216
              XX*                                                       * /
00002316
              XX*************************************************************/    00002416
              XX*                                                           00002516
              XX*                                                           00002616
            6 XXSTEPLIB DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR       00002716
            7 XX        DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR            00002816
              XX*                                                           00002916
              XX*                                                           00003016
              XX*************************************************************/    00003116
              XX*                                                       * /
00003216
              XX*   AS OF GEOSUPPORT VERSION 10.0,                      * /
00003316
              XX*   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD    * /
00003416
```

```
              XX*   ETC) ARE NO LONGER NEEDED AND ARE IGNORED.  GEOSUPPORT     * /
00003516
              XX*   IS TAILORED TO USE STANDARD GEOSUPPORT DATA SET NAMES.     * /
00003616
              XX*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.    * /
00003716
              XX*                                                             * /
00003816
              XX*************************************************************/     00003916
              XX*                                                             * /
00004016
              XX*                                                             * /
00004116
            8 XXSYSPRINT DD SYSOUT=A,DCB=(LRECL=133,RECFM=FBA,BLKSIZE=1330)           00004216
              XX** SYSPRINT FILE CONTAINS RUN STATISTICS AND MESSAGES                 00004316
            9 XXSYSTERM  DD SYSOUT=A,DCB=(LRECL=133,RECFM=FBA,BLKSIZE=1330)           00004416
              XX** SYSTERM FILE CONTAINS SYSTEM WARNINGS AND ERRORS                   00004516
           10 //CARDIN DD *
              X/CARDIN DD DDNAME=CARDIN                                               00004616
              XX** CARDIN IS THE FILE OF GBAT CONTROL RECORDS                         00004716
           11 //INFILE DD *
              X/INFILE DD DDNAME=INFILE                                               00004816
              XX** INFILE CONTAINS THE USERS DATA INPUT RECORDS                       00004916
           12 //OUTFILE DD DSN=&&OUT1A,DISP=(NEW,PASS),
              //        UNIT=SYSDA,SPACE=(TRK,(80,20),RLSE),
              //        DCB=(RECFM=FB,LRECL=1019)
              X/OUTFILE DD DDNAME=OUTFILE                                             00005016
              XX** OUTFILE CONTAINS THE VALID OUTPUT RECORDS                          00005116
           13 //ERRFILE DD SYSOUT=A,DCB=(RECFM=FB,LRECL=84)
              X/ERRFILE DD DDNAME=ERRFILE                                             00005216
              XX** ERRFILE CONTAINS THE REJECTS                                       00005316
           14 XXALIASES  DD DUMMY                                                     00005416
              XX** ALIASES IS THE OPTIONAL INPUT FILE OF USER-DEFINED ST NAME ALIASES 00006015
              //*******************************************************************
              //*********   CARDIN IS THE USER-PROVIDED CONTROL FILE       ********
              //*******************************************************************
              //*******************************************************************
              //*********   INFILE IS THE USER-PROVIDED INPUT DATA.          ******
              //*********   IN THIS EXAMPLE, IT IS PROVIDED AS INSTREAM DATA.******
              //*******************************************************************
              //*******************************************************************
              //*********   OUTFILE IS THE OUTPUT FILE OF SUCCESSFULLY     ********
              //*********   PROCESSED INFILE RECORDS.                      ********
              //*******************************************************************
              //*******************************************************************
```

```
   //*********   ERRFILE IS THE OUTPUT FILE OF REJECTED        ********
   //*********   INFILE RECORDS.                               ********
   //*******************************************************************
  //*******************************************************************
   //*********   AS OF GEOSUPPORT VERSION 10.0,                ********
   //*********   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. ********
   //*********   GRID, PAD, TABFILE ETC) ARE NO LONGER NEEDED  ********
   //*********   AND ARE IGNORED.  GEOSUPPORT IS TAILORED TO   ********
   //*********   USE STANDARD GEOSUPPORT DATA SET NAMES.       ********
   //*********   TO USE NON-STANDARD FILES, PLEASE SEE YOUR    ********
   //*********   SYSTEMS PROGRAMMER.                           ********
   //*******************************************************************
   //*******************************************************************
   STMT NO. MESSAGE
3 IEFC001I PROCEDURE GBAT2 WAS EXPANDED USING PRIVATE LIBRARY CSC.TEST.PROCLIB
ICH70001I YOURUID  LAST ACCESS AT 10:27:49 ON FRIDAY, MMMM DD, YYYY
IEF236I ALLOC. FOR EXAMPLE1 GBAT2 S1
IGD103I SMS ALLOCATED TO DDNAME STEPLIB
IGD103I SMS ALLOCATED TO DDNAME
IEF237I JES2 ALLOCATED TO SYSPRINT
IEF237I JES2 ALLOCATED TO SYSTERM
IEF237I JES2 ALLOCATED TO CARDIN
IEF237I JES2 ALLOCATED TO INFILE
IGD101I SMS ALLOCATED TO DDNAME (OUTFILE )
  DSN (SYS06195.T102919.RA000.EXAMPLE1.OUT1A.H01   )
  STORCLAS (PRIMARY) MGMTCLAS (        ) DATACLAS (        )
  VOL SER NOS= SMST01
IEF237I JES2 ALLOCATED TO ERRFILE
IEF237I DMY  ALLOCATED TO ALIASES
GBI SUCCESSFULLY LOADED GBIDRV
GBIDRV (VERSION VV.V) INVOKED
GEO (VERSION VV.V) INVOKED
snd NNN  OPENED SUCCESSFULLY
IGD103I SMS ALLOCATED TO DDNAME SYS00001
PAD NNN  'B030.GEO.COW.BLDGS.CITY' OPENED SUCCESSFULLY
IEF142I EXAMPLE1 GBAT2 S1 - STEP WAS EXECUTED - COND CODE 0000
IGD104I A030.GEO.SUPPORT.PDSE.LOADLIB                RETAINED,  DDNAME=STEPLIB
IGD104I A030.GEO.SUPPORT.LOADLIB                     RETAINED,  DDNAME=
IEF285I   YOURUID.EXAMPLE1.JOB17476.D0000103.?         SYSOUT
IEF285I   YOURUID.EXAMPLE1.JOB17476.D0000104.?         SYSOUT
IEF285I   YOURUID.EXAMPLE1.JOB17476.D0000101.?         SYSIN
IEF285I   YOURUID.EXAMPLE1.JOB17476.D0000102.?         SYSIN
IEF285I   YOURUID.EXAMPLE1.JOB17476.D0000105.?         SYSOUT
IGD104I B030.GEO.COW.BLDGS.CITY                      RETAINED,  DDNAME=SYS00001
IEF373I STEP/GBAT2   /START 2006195.1029
```

```
            IEF374I STEP/GBAT2   /STOP  2006195.1029 CPU    0MIN 00.06SEC SRB    0MIN 00.00SEC
VIRT   928K SYS   308K EXT    8768K SYS   11284K
            IEF237I E001 ALLOCATED TO SYS00002
            IEF285I   SYS06195.T102920.RA000.EXAMPLE1.R0170302     KEPT
            IEF285I   VOL SER NOS= SMST01.
            IGD105I SYS06195.T102919.RA000.EXAMPLE1.OUT1A.H01    DELETED,   DDNAME=OUTFILE
            IEF375I  JOB/EXAMPLE1/START 2006195.1029
            IEF376I  JOB/EXAMPLE1/STOP  2006195.1029 CPU    0MIN 00.06SEC SRB    0MIN 00.00SEC

            ************************************************************************
            *****  NOTE:  THIS IS PART OF THE SYSPRINT OUTPUT
            ************************************************************************
            0USER CONTROL CARDS:

            BORO=9,1  RECTYPE=1A ONSTREET=15,20 1ABLVERSION=S
            TITLE=THIS IS GBAT CONTROL FILE MSW EXAMPLE 1;

            WARNING: CONTROL ENTRIES FOR BOROUGH CODES ARE MISSING - ASSUMED VALUES FOLLOW.
            WARNING: GEOCODE IS MISSING. A DEFAULT VALUE OF YES IS IN EFFECT.
            WARNING: HNI IS MISSING OR UNDEFINED. A DEFAULT VALUE OF NO  IS IN EFFECT.
            WARNING: SNL IS MISSING. A DEFAULT VALUE OF 32 IS IN EFFECT.
            WARNING: MAXREJECTS IS MISSING. A DEFAULT VALUE OF 200 IS IN EFFECT.
            WARNING: REJECTWARNINGS IS MISSING. A DEFAULT VALUE OF NO IS IN EFFECT.
            WARNING: ALIASES IS MISSING. A DEFAULT VALUE OF NO IS IN EFFECT.

            PARAMETERS BEING USED:
            BOROUGH STARTS IN               9               FOR A LENGTH OF                 1
            STREET 1 STARTS IN             15               FOR A LENGTH OF                20
            NORMALIZED STREET LENGTH:                               32
            THE VALUE OF 1ABLVERSION IS:                    S
            RECORD TYPE SPECIFIED: FUNCTION 1A
            THE VALUE OF GEOCODE IS:                        YES
            THE VALUE OF ALIASES IS:                        NO
            THE VALUE OF HNI IS:    NO
            BOROUGH CODE FOR MANHATTAN IS:                  1
            BOROUGH CODE FOR THE BRONX IS:                  2
            BOROUGH CODE FOR BROOKLYN IS:                   3
            BOROUGH CODE FOR QUEENS IS:                     4
            BOROUGH CODE FOR STATEN ISLAND IS:              5

            ************************************************************************
            *****  NOTE:  THIS IS PART OF THE SYSPRINT OUTPUT
            ************************************************************************

            **********************    STATISTICS  ********************************
```

```
            THIS IS GBAT CONTROL FILE MSW EXAMPLE 1
MM/DD/YY

                                                GEOSUPPORT BATCH ADDRESS TRANSLATOR

                                        MANHATTAN          BRONX       BROOKLYN         QUEENS
STATEN IS.           TOTAL

            INPUT RECORDS                10                  3             0              1
0              14(* )

            ACCEPTED RECORDS             8                   2             0              1
0              11

            REJECTED RECORDS:

            28 - A PARTIAL STREET NAME MAY NOT BE USED IN A
            FREE-FORM ADDRESS:           2                   0             0              0
0                2

            42 - ADDRESS NUMBER OUT OF RANGE
                                         0                   1             0              0
0                1

            TOTAL REJECTED RECORDS EXCEPT CODES 17 AND 99:
                                         2                   1             0              0
0                3

            17+99 - BLANK AND INVALID BOROUGH CODES
0

            TOTAL REJECTED RECORDS
3

            (* ) NOTE  - THIS TOTAL INCLUDES RECORDS WITH INVALID BOROUGH CODES


*************************************************************************************************
************
            *****  NOTE:  THIS IS A PRINTOUT OF ERRFILE.  THE FIRST FOUR BYTES CONSIST OF THE
TWO-BYTE GEOSUPPORT RETURN CODE (GRC)
            *****      FOLLOWED BY A DASH ('-'), FOLLOWED BY A ONE-BYTE REASON CODE, IF ANY.
IN THIS EXAMPLE, THERE ARE 3 REJECTED
            *****      RECORDS. TWO HAVE A GRC VALUE OF '28' AND NO REASON CODE VALUE. THE
```

```
THIRD REJECT HAS A GRC VALUE OF '42' AND
            *****      NO REASON CODE VALUE. REFER TO THE GBAT STATISTICS REPORT OR TO
[APPENDIX 4](/appendices/appendix04) FOR THE MESSAGES CORRESPONDING TO
            *****      THE OCCURRING GRC'S.  AFTER THE FIRST FOUR BYTES, THE REST OF THE
ERRFILE RECORD CONSISTS OF A COPY OF THE
            *****      REJECTED INFILE RECORD.

*****************************************************************************************
************

            28-         1     60  READE             ** PARTIAL STREET NAMES NOT ALLOWED
            28-         1     12  ELK               ** IN FREE-FORM ADDRESSES
            42-         2     709 E 165 ST
```

SAMPLE GBAT JOB #2

SAMPLE GBAT JOB 2: DESCRIPTION

The control file for Sample GBAT Job 2 is as follows:

ALIASES=YES

TITLE=THIS IS GBAT CONTROL FILE EXAMPLE 2;

RECTYPE=2

BORO=5,2

MANHATTAN=MN

BRONX=BX

BROOKLYN=BK

QUEENS=QN

STATEN=SI

ONSTREET=8,25

CROSS1=33,25

GEOCODE=ALL

COMPASS=65,1

COMPACT=YES

REJECTWARNINGS=YES

MAXREJECTS=75

In this example, the user has chosen to code each control entry in a separate control record. The user has chosen to align the control entries vertically for aesthetic reasons, although the positioning of each control entry within its control record and the order in which the control entries is codes are immaterial.

The control file in this example contains the following control entries. (See Table A9-1 for Control Entry Descriptions.)

- Since ALIASES=YES has been coded, the user must provide an ALIASES file in the required format (described in Chapter XI .6), and must provide a DD statement in the JCL referring to that file. GBAT will validate the user's ALIASES file, and will then use the valid street name aliases it contains when processing INFILE. Any invalid aliases will be ignored when processing INFILE, but will be reported in SYSPRINT.

- The TITLE control entry specifies a title for the SYSPRINT output report. Notice that the text of the title is terminated with a semicolon character, as required. (The semicolon does not appear in the actual report.)

- The control entry RECTYPE specifies Function 2.

- The control entry BORO specifies that the input borough code field is in position 5 of the INFILE records and is two bytes long. The input borough code values in this example are not the standard Geosupport borough codes, but are specified as user-defined two-character alphabetic borough codes, 'MN', 'BX', etc., as shown.

- Function 2 requires two input street fields, which in this example are in the form of street names rather than street codes. These fields are specified using the control entries ONSTREET and CROSS1, which state that these fields begin in positions 8 and 33 of the INFILE records, and that each field is 25 bytes long.

- GEOCODE=ALL has been specified, so GBAT will issue a two−work−area call to Function 2 and will form the OUTFILE records by appending the normalized street names and street codes, as well as Work Area 2, to the successfully processed INFILE records.

- The control entry COMPASS specifies an INFILE field for an input compass direction. (Function 2 requires an input compass direction for intersections that are specified in terms of a pair of streets that intersect twice (see Chapter VII.2). If INFILE contains no such intersections, the control entry COMPASS is not required.)

- COMPACT=YES has been specified, directing GBAT to return all normalized street names in the compact format, which is suitable for display but not for use in sorting.
- REJECTWARNINGS=YES directs GBAT to treat warnings as rejects: they will be written to ERRFILE instead of OUTFILE, they will be counted as errors in the SYSPRINT report, and they will count towards the MAXREJECTS termination limit.
- Since MAXREJECTS=75 has been coded, GBAT will terminate with an MVS Return Code of '20' if the first 75 INFILE records all result in rejects or warnings for any reason other than an invalid borough code.

The user has chosen not to code the following control entries, the default values for which are therefore in effect: (See Table A9-2 for Control Entry default values.)

- Since the control entry VSAM has not been coded, GBAT will assume that the user input data file is a sequential file. Consequently, GBAT will access the input data file via the DDname INFILE, and the corresponding DD statement in the JCL must be coded accordingly.
- Since the SNL control entry has not been coded, GBAT will assume the default value of SNL=32 when normalizing street names.
- Since the WORKAREA control entry has not been coded, GBAT will assume the default value of MSW (Mainframe Specific Work Area).

SAMPLE GBAT JOB 2: JOB-STREAM INPUT

```
//EXAMPLE2 JOB YOUR-JOB-CARD-INFORMATION
//*
//*
//*******************************************************************
//************     THIS JOB IS GBAT MSW EXAMPLE 2     ***************
//*******************************************************************
//*******************************************************************
//*********   THIS STEP INVOKES THE STANDARD CATALOGUED     *********
//*********   PROCEDURE FOR GBAT EXECUTION, CALLED GBAT2    *********
//*******************************************************************
//S1 EXEC GBAT2
//*******************************************************************
//*********   CARDIN IS THE USER-PROVIDED CONTROL FILE       ********
//*******************************************************************
//CARDIN DD *
ALIASES=YES
TITLE=THIS IS GBAT CONTROL FILE MSW EXAMPLE 2;
BORO=5,2
RECTYPE=2
```

```
MANHATTAN=MN
BRONX=BX
BROOKLYN=BK
QUEENS=QN
STATEN=SI
ONSTREET=8,25
CROSS1=33,25
GEOCODE=ALL
COMPASS=65,1
COMPACT=YES
REJECTWARNINGS=YES
MAXREJECTS=75
/*
//*****************************************************************
//*********   INFILE IS THE USER-PROVIDED INPUT DATA.         ******
//*********   IN THIS EXAMPLE, IT IS PROVIDED AS INSTREAM DATA.******
//*****************************************************************
//INFILE DD *
  MN READE ST                 BROADWAY
  MN REED ST                  BROADWAY
  MN CANAL ST                 ALLEN ST                       E
  MN CANEL ST                 ALLEN ST                       E
  MN CANAL ST                 ALEN ST                        E
  MN CANEL ST                 ALEN ST                        S
  BK ASSEMBLY RD              GEE AV
  BK ASEMBLY RD               GEE AV
  BK ASSEMBLY RD              GE AV
  BK ASEMBLY RD               GE AV
  MN MAIN ST                  RIVER RD                       S
  MN MAN ST                   RIVER RD                       S
  MN MAIN ST                  RIVE RD                        S
  MN MAN ST                   RIVE RD
  SI HAVEN ESPLN              SILVER LAKE RD
  SI HAVEN ESPLN              SILVER LAKE RD                 N
  QN 116 ST                   CURZON RD                      S
  BX MARINE ST                CITY ISLAND AV                 N
  BX MARINE ST                CITY ISLAND AV
  BX PAULDING AV              SACKET AV                      N
  BK FLATBUSH AV              BEVERLEY RD                    S
  QN QUEENS BL                64 ST                          S
  QN ALDERTON ST              CROMWELL CR                    E
  QN BURDEN CR                84 DR                          N
  BX SHERIF S BYRD PL         JESUP AV
  BX FR MARTIN DOLAN PL       GLEBE AV
/*
```

```
//*****************************************************************
//*********   OUTFILE IS THE OUTPUT FILE OF SUCCESSFULLY     ********
//*********   PROCESSED INFILE RECORDS.                      ********
//*****************************************************************
//OUTFILE DD DSN=&&OUT,DISP=(NEW,PASS),UNIT=SYSDA,
//        SPACE=(TRK,(80,20),RLSE),
//        DCB=(RECFM=FM,LRECL=364)
//*****************************************************************
//*********   ERRFILE IS THE OUTPUT FILE OF REJECTED         ********
//*********   INFILE RECORDS.                                ********
//*****************************************************************
//ERRFILE DD SYSOUT=A,DCB=(RECFM=FB,LRECL=84)
//*****************************************************************
//*********   ALIASES IS THE OPTIONAL FILE OF USER-PROVIDED  ********
//*********   TEMPORARY STREET NAME ALIASES.                 ********
//*****************************************************************
//ALIASES DD *
  1REED ST                        READE ST
  1E ST                           ELK ST
  1CANEL ST                       CANAL ST
  1ALEN ST                        ALLEN ST
  3ASEMBLY RD                     ASSEMBLY RD
  3GE AV                          GEE AV
  1MAN ST                         MAIN ST
  1DUANE ST                       DUANE ST
  1RIVE RD                        RIVER RD
  1RIV RD                         RIVAR RD
  1FASHION AVE                    7 AVE
/*
//*****************************************************************
//*********   AS OF GEOSUPPORT VERSION 10.0,                 ********
//*********   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G.  ********
//*********   GRID, PAD, TABFILE ETC) ARE NO LONGER NEEDED   ********
//*********   AND ARE IGNORED.  GEOSUPPORT IS TAILORED TO    ********
//*********   USE STANDARD GEOSUPPORT DATA SET NAMES.        ********
//*********   TO USE NON-STANDARD FILES, PLEASE SEE YOUR     ********
//*********   SYSTEMS PROGRAMMER.                            ********
//*****************************************************************
//
```

SAMPLE GBAT JOB 2: OUTPUT

```
J E S 2  J O B  L O G  --  S Y S T E M  M V S P  --  N O D E  C S C B A T C H      0
10.31.18 JOB17538 ---- FRIDAY,    DD MMMM YYYY ----
10.31.18 JOB17538  IRR010I  USERID YOURUID  IS ASSIGNED TO THIS JOB.
```

```
10.31.18 JOB17538  ICH70001I YOURUID  LAST ACCESS AT 10:30:31 ON FRIDAY, MMMM DD, YYYY
10.31.18 JOB17538  $HASP373 EXAMPLE2 STARTED - INIT 84   - CLASS X - SYS MVSP
10.31.18 JOB17538  IEF403I EXAMPLE2 - STARTED - TIME=10.31.18
10.31.18 JOB17538  +GBI SUCCESSFULLY LOADED GBIDRV
10.31.18 JOB17538  +GBIDRV (VERSION VV.V) INVOKED
10.31.18 JOB17538  +GEO (VERSION VV.V) INVOKED
10.31.18 JOB17538  +snd NNN  OPENED SUCCESSFULLY
10.31.19 JOB17538  +GRID2 NNN  'B030.GEO.COW.GRID2' OPENED SUCCESSFULLY
10.31.19 JOB17538  -                                            --TIMINGS (MINS.)--
----PAGING COUNTS---
10.31.19 JOB17538  -JOBNAME  STEPNAME PROCSTEP    RC   EXCP   CONN    TCB    SRB  CLOCK   SERV
PG  PAGE  SWAP   VIO SWAPS
10.31.19 JOB17538  -EXAMPLE2 S1       GBAT2       00   1142    180    .00    .00     .0   1264
0     0     0     0     0
10.31.19 JOB17538  IEF404I EXAMPLE2 - ENDED - TIME=10.31.19
10.31.19 JOB17538  -EXAMPLE2 ENDED.  NAME-YOURUID             TOTAL TCB CPU TIME=   .00  TOTAL
ELAPSED TIME=    .0
10.31.19 JOB17538  $HASP395 EXAMPLE2 ENDED
0------ JES2 JOB STATISTICS ------
-  DD MMMM YYYY JOB EXECUTION DATE
-          102 CARDS READ
-          242 SYSOUT PRINT RECORDS
-            0 SYSOUT PUNCH RECORDS
-           17 SYSOUT SPOOL KBYTES
-         0.01 MINUTES EXECUTION TIME
     1 //EXAMPLE2 JOB YOUR-JOB-CARD-INFORMATION
       //*
       //*
       //*******************************************************************
       //************     THIS JOB IS MSW GBAT EXAMPLE 2     ***************
       //*******************************************************************
       //*******************************************************************
       //*********   THIS STEP INVOKES THE STANDARD CATALOGUED     *********
       //*********   PROCEDURE FOR GBAT EXECUTION, CALLED GBAT2    *********
       //*******************************************************************
     3 //S1 EXEC GBAT2
     4 XXGBAT2 PROC                                                        00000100
       XX**                        /* IN CSC.TEST.PROCLIB * /              00000200
       XX**                        /* MODIFIED 06/30/06  BY MEB   * /      00000315
       XX**                        /* ADDED SUPPORT.PDSE.LOADLIB  * /      00000415
       XX**                        /* REMOVED DD CARDS            * /      00000515
       XX**                        /* MODIFIED 05/11/06  BY MEB   * /      00000615
       XX**                        /* ADDED GRID1R FILE           * /      00000715
       XX**                        /* MODIFIED 07/25/05  BY MEB   * /      00000815
       XX**                        /* PEDFILE BECOMES DUMMY FILE  * /      00000915
```

```
   XX**                          /* MODIFIED 03/26/02  BY MEB   * /        00001015
   XX**                                                                    00001115
   XX**** WARNING: DO NOT OVERRIDE THE REGION PARAMETER  **************    00001215
   XX**                                                                    00001315
 5 XXGBAT2 EXEC PGM=GBATIO2,REGION=9M,PARM='ISASIZE(40K)'                  00001415
   XX*                                                                     00001516
   XX*************************************************************/        00001616
   XX*                                                          * /        00001716
   XX*   AS OF GEOSUPPORT VERSION 10.0,                          * /        00001816
   XX*   THE STEPLIB (OR JOBLIB) OF THE GEOSUPPORT EXECUTION STEP  * /      00001916
   XX*   MUST INCLUDE THE FOLLOWING TWO CONCATENATED DATASETS:    * /        00002016
   XX*              A030.GEO.SUPPORT.PDSE.LOADLIB               * /        00002116
   XX*              A030.GEO.SUPPORT.LOADLIB                    * /        00002216
   XX*                                                          * /        00002316
   XX*************************************************************/        00002416
   XX*                                                                     00002516
   XX*                                                                     00002616
 6 XXSTEPLIB DD DSN=A030.GEO.SUPPORT.PDSE.LOADLIB,DISP=SHR                 00002716
 7 XX        DD DSN=A030.GEO.SUPPORT.LOADLIB,DISP=SHR                      00002816
   XX*                                                                     00002916
   XX*                                                                     00003016
   XX*************************************************************/        00003116
   XX*                                                          * /        00003216
   XX*   AS OF GEOSUPPORT VERSION 10.0,                          * /        00003316
   XX*   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G. GRID, PAD   * /      00003416
   XX*   ETC) ARE NO LONGER NEEDED AND ARE IGNORED.  GEOSUPPORT   * /       00003516
   XX*   IS TAILORED TO USE STANDARD GEOSUPPORT DATA SET NAMES.   * /       00003616
   XX*   TO USE NON-STANDARD FILES, SEE YOUR SYSTEMS PROGRAMMER.  * /       00003716
   XX*                                                          * /        00003816
   XX*************************************************************/        00003916
   XX*                                                          * /        00004016
   XX*                                                          * /        00004116
 8 XXSYSPRINT DD SYSOUT=A,DCB=(LRECL=133,RECFM=FBA,BLKSIZE=1330)           00004216
   XX** SYSPRINT FILE CONTAINS RUN STATISTICS AND MESSAGES                 00004316
 9 XXSYSTERM  DD SYSOUT=A,DCB=(LRECL=133,RECFM=FBA,BLKSIZE=1330)           00004416
   XX** SYSTERM FILE CONTAINS SYSTEM WARNINGS AND ERRORS                  00004516
10 //CARDIN DD *
   X/CARDIN DD DDNAME=CARDIN                                              00004616
   XX** CARDIN IS THE FILE OF GBAT CONTROL RECORDS                        00004716
11 //INFILE DD *
   X/INFILE DD DDNAME=INFILE                                              00004816
   XX** INFILE CONTAINS THE USERS DATA INPUT RECORDS                      00004916
12 //OUTFILE DD DSN=&&OUT,DISP=(NEW,PASS),UNIT=SYSDA,
   //        SPACE=(TRK,(80,20),RLSE),
   //        DCB=(RECFM=FM,LRECL=364)
```

```
      X/OUTFILE DD DDNAME=OUTFILE                                       00005016
      XX** OUTFILE CONTAINS THE VALID OUTPUT RECORDS                    00005116
   13 //ERRFILE DD SYSOUT=A,DCB=(RECFM=FB,LRECL=84)
      X/ERRFILE DD DDNAME=ERRFILE                                       00005216
      XX** ERRFILE CONTAINS THE REJECTS                                 00005316
   14 //ALIASES DD *
      X/ALIASES  DD DUMMY                                               00005416
      XX** ALIASES IS THE OPTIONAL INPUT FILE OF USER-DEFINED ST NAME ALIASES 00006015
      //*******************************************************************
      //*********   CARDIN IS THE USER-PROVIDED CONTROL FILE       ********
      //*******************************************************************
      //*******************************************************************
      //*********   INFILE IS THE USER-PROVIDED INPUT DATA.          ******
      //*********   IN THIS EXAMPLE, IT IS PROVIDED AS INSTREAM DATA.******
      //*******************************************************************
      //*******************************************************************
      //*********   OUTFILE IS THE OUTPUT FILE OF SUCCESSFULLY     ********
      //*********   PROCESSED INFILE RECORDS.                      ********
      //*******************************************************************
      //*******************************************************************
      //*********   ERRFILE IS THE OUTPUT FILE OF REJECTED         ********
      //*********   INFILE RECORDS.                                ********
      //*******************************************************************
      //*******************************************************************
      //*********   ALIASES IS THE OPTIONAL FILE OF USER-PROVIDED  ********
      //*********   TEMPORARY STREET NAME ALIASES.                 ********
      //*******************************************************************
      //*******************************************************************
      //*********   AS OF GEOSUPPORT VERSION 10.0,                 ********
      //*********   DD STATEMENTS FOR GEOSUPPORT DATA FILES (E.G.  ********
      //*********   GRID, PAD, TABFILE ETC) ARE NO LONGER NEEDED   ********
      //*********   AND ARE IGNORED.  GEOSUPPORT IS TAILORED TO    ********
      //*********   USE STANDARD GEOSUPPORT DATA SET NAMES.        ********
      //*********   TO USE NON-STANDARD FILES, PLEASE SEE YOUR     ********
      //*********   SYSTEMS PROGRAMMER.                            ********
      //*******************************************************************

 STMT NO. MESSAGE
     3 IEFC001I PROCEDURE GBAT2 WAS EXPANDED USING PRIVATE LIBRARY CSC.TEST.PROCLIB
ICH70001I YOURUID  LAST ACCESS AT 10:30:31 ON FRIDAY, MMMM DD, YYYY
IEF236I ALLOC. FOR EXAMPLE2 GBAT2 S1
IGD103I SMS ALLOCATED TO DDNAME STEPLIB
IGD103I SMS ALLOCATED TO DDNAME
IEF237I JES2 ALLOCATED TO SYSPRINT
IEF237I JES2 ALLOCATED TO SYSTERM
```

```
IEF237I JES2 ALLOCATED TO CARDIN
IEF237I JES2 ALLOCATED TO INFILE
IGD101I SMS ALLOCATED TO DDNAME (OUTFILE )
     DSN (SYS06195.T103118.RA000.EXAMPLE2.OUT.H01     )
     STORCLAS (PRIMARY) MGMTCLAS (        ) DATACLAS (        )
     VOL SER NOS= SMST07
IEF237I JES2 ALLOCATED TO ERRFILE
IEF237I JES2 ALLOCATED TO ALIASES
GBI SUCCESSFULLY LOADED GBIDRV
GBIDRV (VERSION VV.V) INVOKED
GEO (VERSION VV.V) INVOKED
snd NNN  OPENED SUCCESSFULLY
IGD103I SMS ALLOCATED TO DDNAME SYS00001
GRID2 NNN  'B030.GEO.COW.GRID2' OPENED SUCCESSFULLY
IEF142I EXAMPLE2 GBAT2 S1 - STEP WAS EXECUTED - COND CODE 0000
IGD104I A030.GEO.SUPPORT.PDSE.LOADLIB                RETAINED,  DDNAME=STEPLIB
IGD104I A030.GEO.SUPPORT.LOADLIB                     RETAINED,  DDNAME=
IEF285I   YOURUID.EXAMPLE2.JOB17538.D0000104.?         SYSOUT
IEF285I   YOURUID.EXAMPLE2.JOB17538.D0000105.?         SYSOUT
IEF285I   YOURUID.EXAMPLE2.JOB17538.D0000101.?         SYSIN
IEF285I   YOURUID.EXAMPLE2.JOB17538.D0000102.?         SYSIN
IEF285I   YOURUID.EXAMPLE2.JOB17538.D0000106.?         SYSOUT
IEF285I   YOURUID.EXAMPLE2.JOB17538.D0000103.?         SYSIN
IGD104I B030.GEO.COW.GRID2                           RETAINED,  DDNAME=SYS00001
IEF373I STEP/GBAT2   /START 2006195.1031
IEF374I STEP/GBAT2   /STOP  2006195.1031 CPU    0MIN 00.06SEC SRB    0MIN 00.00SEC VIRT  1020K
SYS   300K EXT    8748K SYS   11384K
IEF237I E901 ALLOCATED TO SYS00002
IEF285I   SYS06195.T103119.RA000.EXAMPLE2.R0170325     KEPT
IEF285I   VOL SER NOS= SMST07.
IGD105I SYS06195.T103118.RA000.EXAMPLE2.OUT.H01      DELETED,   DDNAME=OUTFILE
IEF375I  JOB/EXAMPLE2/START 2006195.1031
IEF376I  JOB/EXAMPLE2/STOP  2006195.1031 CPU    0MIN 00.06SEC SRB    0MIN 00.00SEC
*************************************************************************************
*********************************
***** NOTE:  THIS IS PART OF THE SYSPRINT OUTPUT
*************************************************************************************
*********************************
0USER CONTROL CARDS:

  ALIASES=YES
  TITLE=THIS IS GBAT CONTROL FILE MSW EXAMPLE 2;
  BORO=5,2
  RECTYPE=2
  MANHATTAN=MN
```

```
  BRONX=BX
  BROOKLYN=BK
  QUEENS=QN
  STATEN=SI
  ONSTREET=8,25
  CROSS1=33,25
  GEOCODE=ALL
  COMPASS=65,1
  COMPACT=YES
  REJECTWARNINGS=YES
  MAXREJECTS=75

WARNING: SNL IS MISSING. A DEFAULT VALUE OF 32 IS IN EFFECT.

PARAMETERS BEING USED:
BOROUGH STARTS IN               5               FOR A LENGTH OF                 2
STREET 1 STARTS IN              8               FOR A LENGTH OF                25
STREET 2 STARTS IN             33               FOR A LENGTH OF                25
NORMALIZED STREET LENGTH:                              32
COMPASS STARTS IN              65               FOR A LENGTH OF                 1
COMPACT OPTION   WAS SPECIFIED
RECORD TYPE SPECIFIED: FUNCTION 2
THE VALUE OF GEOCODE IS:                        ALL
WARNINGS ARE TREATED AS REJECTS
MAXIMUM NUMBER OF REJECTS ALLOWED IS                        75
THE VALUE OF ALIASES IS:                        YES
BOROUGH CODE FOR MANHATTAN IS:                  MN
BOROUGH CODE FOR THE BRONX IS:                  BX
BOROUGH CODE FOR BROOKLYN IS:                   BK
BOROUGH CODE FOR QUEENS IS:                     QN
BOROUGH CODE FOR STATEN ISLAND IS:              SI
ERROR: ALIASES INPUT RECORD NUMBER 0008 HAS BEEN REJECTED.
ALIAS STREET NAME AND STREET NAME RECOGNIZED BY GEOSUPPORT ARE INDENTICAL - DUANE ST
.

ERROR: ALIASES INPUT RECORD NUMBER 0010 HAS BEEN REJECTED:
RETURN CODE = EE FOR STNAME RIVAR RD                        .
ERROR: ALIASES INPUT RECORD NUMBER 0011 HAS BEEN REJECTED.
FASHION AVE                     AND 7 AVE                           HAVE DIFFERENT 7 DIGIT
STCODES (11061002 AND 11061004).

NOTE:  ALIAS TABLE HAS ERRORS AND ALIASES=YES HAS BEEN SPECIFIED-PROCESSING CONTINUED.

 ******************************************************************************************
*********************************
```

```
 ***** NOTE:  THIS IS PART OF THE SYSPRINT OUTPUT
 ******************************************************************************************
*********************************
 0*****************************************************    STATISTICS
*************************************************************
 0 THIS IS GBAT CONTROL FILE MSW EXAMPLE 2
MM/DD/YY
 0                                            GEOSUPPORT BATCH ADDRESS TRANSLATOR
 0                                             MANHATTAN       BRONX    BROOKLYN      QUEENS
STATEN IS.    BOROUGH        TOTAL

BOUNDARY
 0INPUT RECORDS                                        10           5           5           4
2           0          26(* )
 0ACCEPTED RECORDS                                      8           4           5           2
0           0          19
 0REJECTED RECORDS:
 0  01 - WARNING MESSAGES                               0           0           0           1
0           0           1
 0  02 - THESE STREETS INTERSECT TWICE-COMPASS
    DIRECTION REQUIRED:                                 1           1           0           0
0           0           2
 0  03 - THESE STREETS INTERSECT MORE THAN
    TWICE-CANNOT BE PROCESSED:                          0           0           0           1
2           0           3
 0  40 - COMPASS DIRECTION VALUE IS INVALID FOR THIS
    INPUT LOCATION:                                     1           0           0           0
0           0           1
 0TOTAL REJECTED RECORDS EXCEPT CODES 17 AND 99:
                                                        2           1           0           2
2           0           7
 0  17+99 - BLANK AND INVALID BOROUGH CODES
0
 0TOTAL REJECTED RECORDS
7
 0  (* ) NOTE  - THIS TOTAL INCLUDES RECORDS WITH INVALID BOROUGH CODES
 1******************************************************************************************
***********************************
 ***** NOTE:  THIS IS A PRINTOUT OF ERRFILE.  THE FIRST FOUR BYTES CONSIST OF THE TWO-BYTE
GEOSUPPORT RETURN CODE (GRC),
 *****        FOLLOWED BY A DASH ('-'), FOLLOWED BY A ONE-BYTE REASON CODE, IF ANY.  IN THIS
EXAMPLE, THERE ARE SEVEN REJECTED
 *****        RECORDS.  TWO HAVE A GRC VALUE OF '02' AND NO REASON CODE VALUE.  TWO HAVE A GRC
VALUE OF '03' AND A REASON CODE
 *****        VALUE OF '3'.  ONE HAS A GRC VALUE OF '01' (WARNING) AND A REASON CODE VALUE OF
```

```
'H', ETC.  REFER TO THE GBAT
 *****        STATISTICS REPORT OR TO [APPENDIX 4](/appendices/appendix04) FOR THE MESSAGES
CORRESPONDING TO THE OCCURRING GRC'S AND REASON CODES.  AFTER
 *****        THE FIRST FOUR BYTES, THE REST OF THE ERRFILE RECORD CONSISTS OF A COPY OF THE
REJECTED INFILE RECORD.
 ******************************************************************************************
**********************************

 40-     MN CANEL ST                 ALEN ST                         S
 02-     MN MAN ST                   RIVE RD
 03-3    SI HAVEN ESPLN              SILVER LAKE RD
 03-3    SI HAVEN ESPLN              SILVER LAKE RD                  N
 01-H    QN 116 ST                   CURZON RD                       S
 02-     BX MARINE ST                CITY ISLAND AV
 03-4    QN QUEENS BL                64 ST                           S
```

APPENDIX 11: GUIDELINES FOR APPLICATION DESIGN

This appendix contains guidelines for application designers, listed in no particular order. These guidelines are intended only to be a limited selection of helpful suggestions, not a comprehensive set of instructions for application design. Terms highlighted in bold typeface have entries in the Glossary.

1. DESIGN PROCEDURES TO REVIEW AND (WHEN APPROPRIATE) TO REPORT REJECTS TO GSS: As an integral part of the application, set up procedures to examine geographic data that have been rejected by Geosupport, and to report appropriate rejects to GSS. Only those rejected data that, after examination, do not appear attributable to user errors should be reported to GSS. In addition, users should also report cases in which the input information was not rejected, but the output data that Geosupport has returned to the application appear to be erroneous for the given location (such as an incorrect ZIP code or incorrect cross streets). User feedback is essential to GSS's efforts to keep Geosupport accurate and up to date.

2. USE THE GEOSUPPORT COPY LIBRARIES: : If the application is being written in a programming language supported by Geosupport's **COPY facility** (currently, COBOL, PL/1, IBM Mainframe Assembler Language, C or NATURAL), do not code layouts of the Geosupport work areas directly into the application program source code. Instead, write the program to access the Geosupport **COPY facility.** This will cause the program to automatically obtain the most current standard source code work area layouts at compile time. This approach eliminates tedious and error-prone line-by-line coding of the Geosupport work area layouts by the application programmer, insures the use of the most current layouts, and facilitates trouble-shooting by insuring the use of standard data names for Geosupport data items.

3. DESIGN FOR GEOGRAPHIC RETRIEVAL CONSISTENCY: If an application is required to retrieve data from the application's own files by geographic location, it should be designed so that it performs such retrieval consistently, that is, independently of variations in specifying geographic locations. This is accomplished by obtaining certain items from Geosupport, storing them in the application file, and using them as part of the retrieval key. For example, for retrievals by address, use B5SCs instead of street names in the retrieval key. For building-level retrievals, store **BINs** in the application file and use them rather than addresses or tax lot identifiers as the retrieval key.

4. DESIGN BATCH PROCEDURES TO RE-SYNCHRONIZE APPLICATION FILES WITH NEW GEOSUPPORT RELEASES: Geographic information changes over time. For example, changes are possible in the election districts, tax lot identifiers or police precincts associated with addresses, in the **street codes** assigned to street names, in the streets incident upon intersections, etc. During application design, consider which data

items obtained from Geosupport and stored in application files should be updated to reflect changes in new Geosupport **releases**, and design procedures to perform such updating. In particular, if street codes are to be stored in an application file, store them in the form of B10SCs (but use only the B5SC portions for geographic retrieval), and develop a fully automated batch **resynchronization** procedure utilizing the Street Code Change File (see Chapter IV.4).

5. (1) USE THE APPROPRIATE STREET NAME FOR THE TASK: To sort a file by geographic location, always use **street names normalized in sort format** (see Chapter III.3). For display purposes, obtain **preferred street names** (see Chapter IV.6), and display them **normalized** in **compact format** (see Chapter III.3).

6. WHENEVER POSSIBLE, ALLOCATE 32 BYTES FOR STREET NAME FIELDS; DO NOT SPECIFY AN **SNL** VALUE UNLESS THE APPLICATION SPECIFICALLY REQUIRES SHORTER STREET NAME FIELDS (for example, to fit within a limited amount of space in a report, screen or transparent envelope window). The default SNL value, 32, insures that all valid input street names can be successfully normalized.

7. TO VALIDATE ADDRESSES, USE FUNCTION 1A RATHER THAN FUNCTION 1 OR 1E. Function 1A does a far better job of validating whether a building having a given address actually exists.

8. TO IMPROVE EXECUTION EFFICIENCY, use Function 1 instead of Function1E unless the application requires the political district geography that only Function 1E provides. (Function 1 performs fewer I/O operations.)

9. NEVER DESIGN NEW APPLICATIONS TO USE **VESTIGIAL FEATURES** OF GEOSUPPORT (see Chapter I.5).

10. ESCHEW **FREE-FORM ADDRESS** PROCESSING (see Chapter V.3) UNLESS IT IS UNAVOIDABLE. Whenever possible, pass the house number and the street name of an address to Geosupport in the separate **WA1** input fields for those items. Design application files so that the house number and street name of an address are stored in separate fields.

11. REVIEW THE SET OF **WARNING** AND **REJECT** CONDITIONS THAT CAN BE ISSUED BY EACH FUNCTION THE APPLICATION WILL BE CALLING. Determine whether any of these conditions warrant custom handling in your application. Appendices 1 and 4 of this document are useful in this regard.

12. DESIGN INTERACTIVE APPLICATIONS TO USE THE SIMILAR NAMES FEATURE. (See Chapter III.5.) Whenever Geosupport rejects an input street name and returns similar names, display the list of similar names on the screen and allow (but do not require) the operator to select one of them using the cursor. If the operator selects a

similar name, re-submit the Geosupport call automatically using the similar name in place of the rejected input name.

APPENDIX 12: CHARACTER-ONLY WORK AREAS (COW)

Introduction

This appendix is based on Geosupport System Technical Bulletin 02-01 (dated 15 November 2002) and Geosupport Technical Bulletin 02-01 Addendum (dated 22 November 2002). It contains information needed to create Geosupport applications using the Character-Only Work Areas (COWs). Included are the following topics:

- Comparison of COWs and Mainframe-Specific Work Areas (MSWs)
- Considerations when using COWs
- Work Area Lengths
- Specifying the Work Area Format
- GBAT Considerations
- COW COPY Files

Notes:

1. There are two versions of the sample programs in Appendix 5 of this User Programming Guide. One version is for MSWs and the other is for COWs. When coding, bear in mind the differences between COWs and MSWs.

2. The Work Area Layouts in Appendix 2 of this User Programming Guide are the layouts of the MSWs. For the COW layouts, see Appendix 13.

3. The COPY files that are printed in Appendix 5 of this User Programming Guide are for the Mainframe-Specific Work Areas (MSWs). For the COW COPY files, see Appendix 14.

Overview

Standard work areas with pre-defined layouts are used to pass data between the Geosupport System and user-developed application programs. The same work areas are also used by GBAT, the Geosupport batch utility program, to pass data to and from Geosupport.

The Geosupport work areas that have long been in use are called the Mainframe-Specific Work Areas (MSWs). Most of the MSWs contain one or more packed decimal fields, a data encoding schema unique to IBM mainframes. This appendix discusses an alternative set of Geosupport work areas called the Character-Only Work Areas (COWs) which, as the name implies, contain character fields only. The introduction of the COW is an essential part of a long-term effort to port the Geosupport System to other platforms.

Each specific Geosupport work area (for example, Work Area 2 for Function 3S) has both a COW version and an MSW version. User-written application programs running on mainframes now have the option to use either set of work areas when making calls to Geosupport. GBAT users can also specify the use of either set of work areas.

From now on, all new applications should be designed to use the COWs. We also recommend that **all existing applications be converted to use the COWs.** Although the MSWs will continue to be supported, as of some future date (not yet determined), only the COWs will be enhanced with new data items and functionality. Eventually, the MSWs may be de-supported.

Comparison of COWs and MSWs

Each non-character field in an MSW has a character field counterpart in the corresponding COW. Except for an item called the HND (discussed below in the sub-section on house number fields), each character field in an MSW appears in identical form in the corresponding COW. However, corresponding fields do not necessarily occupy the same byte positions or occur in the same order in the corresponding MSW and COW. In designing the COWs, the opportunity has been taken to reorganize the layouts to situate related fields near each other and to increase the amount of filler space available for adding new data items in the future.

The data items for which the MSWs contain non-character fields are house numbers, street codes, segment lengths, and count fields. Each of these is discussed in detail below.

House Number Fields. The Geosupport System uses three different formats for standardized or 'normalized' house numbers: the House Number in Display format (HND), the House Number in Internal format (HNI), and the new House Number in Sort format (HNS).

- The **HND** is a character item that is present in both the COWs and the MSWs, but it has a different length in each: 16 bytes in the COWs and 12 bytes in the MSWs. The length of the HND was increased in the COWs to insure that house numbers having suffixes fit within the HND field without the suffix having to be abbreviated. (House number suffixes are certain character strings that occur at the ends of some New York City house numbers, such as 1/2, 1/4, REAR, GARAGE.) For compatibility with MSW, by default Geosupport uses only the first 12 characters of the 16-byte COW HND. The remaining 4 characters are blank. To use all 16 characters, the user can specify an HNL (House Number Length) of 16.

- The **HNI** is a six-byte data item with a hybrid format: the first five bytes are in packed decimal format, and the sixth byte contains a binary value. HNIs occur only in the MSW.

- The **HNS** is a new 11-byte item that is the character equivalent of the HNI in the COWs.

The HND is the appropriate format for displaying house numbers on application screens, reports and computer-generated maps, and is specifically designed for that purpose. In particular, the HND is left-justified and space-filled. However, the HND renders unsatisfactory results when used as a field to sort addresses. For example, it would, inappropriately, cause 102 MAIN STREET to sort ahead of 98 MAIN STREET.

In contrast to the HND, both the HNI and the HNS are suitable to use as fields to sort addresses. For example, both would, appropriately, cause 98 MAIN STREET to sort ahead of 102 MAIN STREET. However, neither the HNI nor the HNS is suitable for display:

- The HNI is not a character item and so cannot be displayed as intelligible data unless first converted to character format. Any of the Geosupport display functions (Functions D, DG and DN) can be used with the MSWs to convert an HNI to an HND.

- The HNS, although it is a character item, is unsuitable for display. In particular, the HNS is in an internal format with a unique layout and flags. If the house number has a suffix, the HNS does not contain the suffix itself, but instead, contains a code for the suffix meaningful only to the Geosupport software. Any of the Geosupport display functions (Function D, DG and DN) can be used with the COWs to convert an HNS to an HND.

To reiterate, **the HND should be used for display, and the HNI (in MSWs) or the HNS (in COWs) should be used for sorting.**

Street Code Fields. A notable feature of the Geosupport System is its set of numeric street codes assigned to the names of New York City streets and selected non-street geographic features. The street code feature provides specialized capabilities that are essential for certain types of applications.

Street codes appear in several forms in the Geosupport work areas. In many of the MSWs, there are four-byte fields for a packed decimal data item called the Packed Borough and 5-Digit Street Code (PB5SC). The COW counterparts of PB5SC fields can take one of the following three forms:

- A six-byte field for an item called the Borough and 5-Digit Street Code (B5SC). This is simply the unpacked version of the PB5SC

- The first six bytes (constituting the B5SC) of an eight-byte field for an item called the Borough and 7-Digit Street Code (B7SC)

- The first six bytes (constituting the B5SC) of an 11-byte field for an item called the Borough and 10-Digit Street Code (B10SC)

Segment Length Fields. Both Work Area 2 for Function 3 and Work Area 2 for Function 3C contain fields for the segment length expressed in feet. In the MSW format, these are 3-byte packed decimal fields. In the COW format, they are 5-byte character fields.

Count Fields. Some count fields, e.g. Number of Street Names in List, are packed decimal fields in the MSW format, and character fields in the COW format.

Consideration When Using the COWs

The Long Work Area 2 option that is available when using the MSWs is occasionally not needed or not supported when using the COWs, as follows:

- When using the COWs, Functions 1, 1E and 3 do not have the long Work Area 2 option. This option is unnecessary in these cases, since the COW versions of the regular Work Area 2s for these functions already accommodate all the requisite fields. However, Functions 1A and BL continue to have the long Work Area 2 option when COWs are used. (See Chapter II.5 for a general discussion of the long Work Area 2 option.)

Work Area Lengths (COWs and MSWs)

The following table lists the lengths of the members of both sets of work areas. Note that the lengths of corresponding members from the two sets differ in most cases.

Table A12-1: Lengths of Work Areas (COWs and MSWs)		
Work Area	**Length of COW**	**Length of MSW**
Work Area 1 (used with all functions)	1200	884
Regular WA2 for Functions 1, 1E	300	200
Long WA2 for Functions 1, 1E	N/A	300
Extended WA2 for Functions 1, 1E	1500	NA
Regular WA2 for Functions 1A, BL, BN	1363	939
Long WA2 for Functions 1A, BL	17750	17683
Extended WA2 for Functions 1A	2800	NA
WA2 for Function 1B	4300	N/A
WA2 for Function 2	200	200
Regular WA2 for Function 3	450	200
Long WA2 for Function 3	N/A	300
Extended WA2 for Function 3	1000	N/A
Auxiliary Segment WA2 for Function 3	950	N/A
Extended WA2 with Auxiliary Segment for Function 3	1500	N/A
WA2 for Function 3C	300	200
Auxiliary Segment WA2 for Function 3C	800	N/A
Extended WA2 with Auxiliary Segment for Function 3C	1350	N/A
Regular WA2 for Function AP	1363	N/A

Extended WA2 for Functions AP	2800	N/A
WA2 for Function 3S	19274	4224

Specifying a Work Area Format (COW or MSW)

To indicate which set of work areas is being used in a call to Geosupport, an application program uses a new field called the Work Area Format Indicator. This field is one byte long and is located at position 213 of both the COW Work Area 1 and the MSW Work Area 1.

- The value 'C' in the Work Area Format Indicator indicates to Geosupport that COWs are being used for the given call.
- A blank in the Work Area Format Indicator indicates that MSWs are being used.
- If the Work Area Format Indicator is invalid, the call is rejected with a Geosupport Return Code of 27 and an appropriate message.

Since every call to Geosupport is an independent event, application programs must insure that the Work Area Format Indicator is appropriately set for each call; Geosupport doesn't 'remember' previous calls.

Note that the MSWs are the default work areas, that is, the work areas that Geosupport expects when the Work Area Format Indicator is blank. Therefore, **existing applications that use the MSWs will continue to execute properly without modification, provided Work Area 1 is being passed to Geosupport with position 213 containing a blank.** (As a matter of course, every application program should be designed so that, each time a call to Geosupport is to be made, the program clears Work Area 1 entirely to blanks prior to moving the input data for that call into the requisite Work Area 1 fields. This insures that Work Area 1 will not be 'polluted' by stray input data lingering from a previous call.)

GBAT Considerations for COWs

When executing GBAT, the set of work areas that are used affects the length and format of the records written into OUTFILE (the output file of successfully processed data records).

To specify the set of work areas GBAT is to use, the user codes a control entry in CARDIN (the input control file) containing the keyword WORKAREA, as follows:

- WORKAREA=COW specifies the COWs.
- WORKAREA=MSW specifies the MSWs.
- (Default:) If no WORKAREA control entry is coded, GBAT uses the MSWs.

Since the MSWs are GBAT's default set of work areas, existing GBAT jobs will continue to execute properly without modification.

When COWs are used, GBAT options that involve processing packed decimal input data are, of course, invalid. Specifically, the following control entries or control entry variable values are invalid when COWs are being used:

- HNI=YES is invalid.
- In the control entries STRTCODE, CRSCOD1 and CRSCOD2, the values 3 and 4 are invalid for the length variable.
- If MSWs are being used, the default is 1ABLVERSION=L (or 1ABLVERSION=LEGACY), which results in an error, since Legacy is no longer supported.

GBAT forms each OUTFILE record by appending Geosupport information to a copy of the data input record. The information that is appended is determined by three factors: the set of work areas being used, the function being executed and the value of the GEOCODE control entry that is in effect. The GEOCODE value affects the appended information as follows:

- When GEOCODE=NO, the appended items consist only of selected output items from Work Area 1 (and, in case of MSW Functions 1, 1A, and 1E, an item created by GBAT called the HNHPD). See Table A12-2 below for lists of the appended COW items and their lengths by function and set of work areas. For MSW format, see Table 9-4 and Table 9-5.

  When GEOCODE =YES the appended information consists only of work area 2 in its entirety. Table A12-1 above lists the lengths of these work areas by function and work area format. Appendix 2 contains the MSW Work Area Layouts and Appendix 13 contains the COW Work Area layouts.

- When GEOCODE=ALL, the appended information consists of the data for GEOCODE=NO followed by the data appended for GEOCODE=YES. Table A12-3 lists the lengths of the appended information by function and set of work areas. These lengths typically are the sums of the corresponding lengths listed in Table A12-1 and Table A12-2(and A12-2A if GEOUNIT=YES).

YES and ALL are invalid GEOCODE options for Functions 1N, D, DG and DN, since these functions do not have a Work Area 2.

The information appended for GEOCODE=NO is as follows.

- <u>For the functions that allow an input house number other than the display functions (viz. Functions 1, 1A, 1B and 1E):</u> the appended information includes normalized house number items as follows:
  - If COWs are being used, the HND and the HNS are appended.

    - If MSWs are being used, the HND and an 8-byte item called the HNHPD are appended. The HNHPD is a normalized house number created by GBAT in a special format for use only by the Department of Housing Preservation and Development.

- For the display functions (Functions D, DG and DN), which allow input house numbers in the form of HNIs when using MSWs: the appended information includes the normalized house numbers only in the HND format for a length of 12.

- For the display functions (Functions D, DG and DN), which allow input house numbers in the form of HNSs when using COWs: the appended information includes the normalized house numbers only in the HND format for a length of between 12 and 16.

- For the functions that involve input street names (Functions 1, 1A, 1B, 1E, 1N, 2, 3, 3C, 3S, D, DG and DN): the appended information includes normalized street name(s) and street codes, as follows:

    - Regardless of which set of work areas is being used, normalized street names are provided in 32−byte fields, left-justified and blank−filled.

    - If COWs are being used, street codes are provided as B10SCs, an 11-byte item.

- If MSWs are being used, street codes are provided as 10SCs (ten−digit street codes without a borough code), a 10-byte item.

- For Function BL: the appended information when 1ABLVERSION=STANDARD is specified consists of the standard 10-byte BBL, which is composed of the one-byte borough code followed by the five-byte tax block followed by the four-byte tax lot. Note: STANDARD is the only valid value for 1ABLVERSION.

- For Function BN: the appended information consists of ten bytes containing the seven-byte Building Identification Number (BIN) followed by a three-byte filler.

Table A12-2 below lists the appended items when GEOCODE=NO, itemized by function and set of work areas. When an item of appended data has no value for a particular record (such as a house number item, when the input location is a non-addressable place name), the given field is still present in the appended data but it contains all blanks. The only exception to this involves the display functions (D, DG and DN) when using MSWs, where there is no field for the second house number unless it is provided as an input datum by the user.

Table A12-2A, which follows Table A12-2, lists the additional appended items when GEOUNIT=YES. Note that that the GEOUNIT option is for COW only. The GEOUNIT items are appended in the output file record immediately after the GEOCODE=NO items (when GEOCODE=NO or GEOCODE=ALL).

Table A12-2: GBAT-Appended Items when GEOCODE=NO (COWs and MSWs)

See Table A12-2A for additional GBAT-Appended Items when GEOUNIT=YES(COW Only)

Functions [Options]	COWs		MSWs	
	Appended Items	**Length**	**Appended Items**	**Length**
1, 1A, 1B[15], 1E, AP[16]	HND	16	HND	12
	HNS	11	HNHPD	8
	Normalized Street Name	32	Normalized Street Name	32
	B10SC	11	10SC	10
	Total Length:	70	Total Length:	62
1N	Normalized Street Name	32	Normalized Street Name	32
	B10SC	11	10SC	10
	Total Length:	43	Total Length:	42
2	Normalized Street Name-1	32	Normalized Street Name-1	32
	B10SC-1	11	10SC-1	10
	Normalized Street Name-2	32	Normalized Street Name-2	32
	B10SC-2	11	10SC-2	10
	Total Length:	86	Total Length:	84
2 - NODE input	Filler	86	Invalid	
	Total Length:	86		
3, 3C, 3S	Normalized Street Name-1	32	Normalized Street Name-1	32
	B10SC-1	11	10SC-1	10
	Normalized Street Name-2	32	Normalized Street Name-2	32
	B10SC-2	11	10SC-2	10
	Normalized Street Name-3	32	Normalized Street Name-3	32
	B10SC-3	11	10SC-3	10
	Total Length:	129	Total Length:	126
AP	See 1, 1A, 1E, 1B, AP above	70	Invalid	
	Total Length:	70		
	BBL:		BBL:	
	Borough Code	1	Borough Code	1

BL (Standard)	Tax Block	5	Tax Block	5
	Tax Lot	4	Tax Lot	4
	Total Length:	10	Total Length:	10
BL (Legacy)	Invalid		Invalid	
BN	BIN	7	BIN	7
	Filler	3	Filler	3
	Total Length:	10	Total Length:	10
D, DG, DN [HOUSENUM2 control entry not coded]	HND-1	16	HND	12
	Normalized Street Name-1	32	Normalized Street Name-1	32
	Normalized Street Name-2	32	Normalized Street Name-2	32
	Normalized Street Name-3	32	Normalized Street Name-3	32
	HND-2	16		
	Total Length:	128	Total Length:	108
D, DG, DN [HOUSENUM2 control entry coded]	HND-1	16	HND-1	12
	Normalized Street Name-1	32	Normalized Street Name-1	32
	Normalized Street Name-2	32	Normalized Street Name-2	32
	Normalized Street Name-3	32	Normalized Street Name-3	32
	HND-2	16	HND-2	12
	Total Length:	128	Total Length:	120

Table A12-2A: Additional GBAT-Appended Items when GEOUNIT=YES (COW only)

Functions [Options]	COWs	
	Appended Items	**Length**
1, 1E, 1A, 1B	Normalized Display-Format Unit Output	14
	Filler	56
	Total Length:	70

Table A12-3 lists the length of the data appended by GBAT, itemized by function and option within function, GEOCODE value and set of work areas being used.

Note: CROSSSTNAMES=YES

For Functions 1, 1E, 1B, 2, 3 and 3C, when GEOCODE=ALL (and, optionally, GEOUNIT=YES) and CROSSSTNAMES=YES, the appended data consist of the concatenation of the GEOCODE=NO data, (followed, optionally, by GEOUNIT=YES data,)

followed by a 320-byte block of data containing cross street names, followed by the GEOCODE=YES data. For further information about the layout of the appended CROSSSTNAMES data, refer to the Appendix 3 entry for the List of Street Names (see paragraph on List of Cross Street Names).

Table A12-3: Length of GBAT−Appended Data (COWs and MSWs)

Note: The data is appended to the user's input record

Functions	Options [17]	GEOCODE=NO		GEOCODE=YES		GEOCODE=ALL	
		COWs	MSWs	COWs	MSWs	COWs	MSWs
1, 1E	LONGWA2=NO	70	62	300	200	370	262
	LONGWA2=NO GEOUNIT=YES	140	Invalid	Invalid	Invalid	440	Invalid
	LONGWA2=YES	Invalid	Invalid	Invalid	300	Invalid	362
	MODE=X	Invalid	Invalid	1500	Invalid	1570	Invalid
	MODE=X GEOUNIT=YES	Invalid	Invalid	Invalid	Invalid	1640	Invalid
1A	LONGWA2=NO	70	62	1363	939	1433	1001
	LONGWA2=NO, GEOUNIT=YES	140	Invalid	Invalid	Invalid	1503	Invalid
	LONGWA2=YES	Invalid	Invalid	17750	17683	17820	17745
	LONGWA2=YES, GEOUNIT=YES	Invalid	Invalid	Invalid	Invalid	17890	Invalid
	MODE=X, LONGWA2=NO	Invalid	Invalid	2800	Invalid	2870	Invalid
	MODE=X, LONGWA2=NO, GEOUNIT=YES	Invalid	Invalid	Invalid	Invalid	2940	Invalid
1B		Invalid	Invalid	4300	Invalid	4370	Invalid
	GEOUNIT=YES	Invalid	Invalid	Invalid	Invalid	4440	Invalid
1N		43	42	Invalid	Invalid	Invalid	Invalid
2		86	84	200	200	286	284
	RELATEDNODES = YES (ERRFIL3)	Invalid	Invalid	3352	Invalid	3352	Invalid
3	LONGWA2=NO with AUXSEG=NO	129	126	450	200	579	326
	LONGWA2=YES	Invalid	Invalid	Invalid	300	Invalid	426
	AUXSEG=YES	Invalid	Invalid	950	Invalid	1079	Invalid
	MODE=X	Invalid	Invalid	1000	Invalid	1129	Invalid
	MODE=X with						

	AUXSEG=YES	Invalid	Invalid	1500	Invalid	1629	Invalid
3C	AUXSEG=NO	129	126	300	200	429	326
	AUXSEG=YES	Invalid	Invalid	800	Invalid	929	Invalid
	MODE=X	Invalid	Invalid	850	Invalid	979	Invalid
	MODE=X with AUXSEG=YES	Invalid	Invalid	1350	Invalid	1479	Invalid
3S		129	126	19274	4224	19403	4350
AP		70	Invalid	1363	Invalid	1433	Invalid
	MODE=X	Invalid	Invalid	2800	Invalid	2870	Invalid
BL	LONGWA2=NO	10	10	1363	939	1373	949
	LONGWA2=YES	Invalid	Invalid	17750	17683	17760	17693
	MODE=X, LONGWA2=NO	Invalid	Invalid	2800	Invalid	2810	Invalid
BN	10	10	1363	939	1373	949	
	MODE=X	Invalid	Invalid	2800	Invalid	2810	Invalid
D, DG, DN	HOUSENUM2 not coded	128	128	128	Invalid	Invalid	Invalid
	HOUSENUM2 coded	128	120	Invalid	Invalid	Invalid	Invalid

COPY Files for COWs

For COBOL, PL/1, BAL and C programmers, copy files have been created to enable you to easily use the new work areas (COWs) in your programming work. Local Data Areas will be available for Natural programmers. If you use the MVSP LPAR at DoITT, these items will be found in library ‘A030.GEO.COPYLIB’. If you use any other LPAR at DoITT or if you work at a different data center, contact your system programming staff to learn the name of the library in which these members are stored. The following table shows you the copy file name by language and Geosupport Function.

Table A12-4: List of COPY Files for COWs

Language	COW Work Area	Copy File
COBOL	Work Area 1 (used with all Functions)	P1COB
	Regular Work Area 2 for Functions 1 and 1E	P2COB
	Extended Work Area 2 for Functions 1 and 1E	P2COB1AL
	Regular Work Area 2 for Functions 1A, BL, BN	P2COB1A
	Long Work Area 2 for Functions 1A and BL	P2COB1AL
	Work Area 2 for Function 2	P2COB
	Regular Work Area 2 for Function 3	P2COB
	Auxiliary Segment Work Area 2 for Function 3	P2COB
	Regular Work Area 2 for Function 3C	P2COB

	Auxiliary Segment Work Area 2 for Function 3C	P2COB
	Work Area 2 for Function 3S	P2COB3S
	Regular Work Area 2 for Function AP	P2COBAP
	Extended Work Area 2 for Function AP	P2COBAP
PL/1	Work Area 1 (used with all Functions)	P1PL1
	Regular Work Area 2 for Functions 1 and 1E	P2PL1
	Extended Work Area 2 for Functions 1 and 1E	P2PL11AL
	Regular Work Area 2 for Functions 1A, BL, BN	P2PL11A
	Long Work Area 2 for Functions 1A and BL	P2PL11AL
	Work Area 2 for Function 2	P2PL1
	Regular Work Area 2 for Function 3	P2PL1
	Auxiliary Segment Work Area 2 for Function 3	P2PL1
	Regular Work Area 2 for Function 3C	P2PL1
	Auxiliary Segment Work Area 2 for Function 3C	P2PL1
	Work Area 2 for Function 3S	P2PL13S
	Regular Work Area 2 for Function AP	P2PLIAP
	Extended Work Area 2 for Function AP	P2PLIAP
NATURAL	Work Area 1 (used with all Functions)	GEOLP1
	Regular Work Area 2 for Functions 1 and 1E	GEOLP2
	Extended Work Area 2 for Functions 1 and 1E	GEOLP2AL
	Regular Work Area 2 for Functions 1A, BL, BN	GEOLP21A
	Long Work Area 2 for Functions 1A and BL	GEOLP2AL
	Work Area 2 for Function 2	GEOLP2
	Regular Work Area 2 for Function 3	GEOLP2
	Auxiliary Segment Work Area 2 for Function 3	GEOLP2
	Regular Work Area 2 for Function 3C	GEOLP2
	Auxiliary Segment Work Area 2 for Function 3C	GEOLP2
	Work Area 2 for Function 3S	GEOLP23S
	Regular Work Area 2 for Function AP	GEOL2AP
	Extended Work Area 2 for Function AP	GEOL2APX
BAL	Work Area 1 (used with all Functions)	P1BAL
	Regular Work Area 2 for Functions 1 and 1E	P2BAL
	Extended Work Area 2 for Functions 1 and 1E	P2BAL1A
	Regular Work Area 2 for Functions 1A, BL, BN	P2BAL1A
	Long Work Area 2 for Functions 1A and BL	P2BAL1A
	Work Area 2 for Function 2	P2BAL
	Regular Work Area 2 for Function 3	P2BAL
	Auxiliary Segment Work Area 2 for Function 3	P2BAL
	Regular Work Area 2 for Function 3C	P2BAL
	Auxiliary Segment Work Area 2 for Function 3C	P2BAL
	Work Area 2 for Function 3S	P2BAL3S
	Regular Work Area 2 for Function AP	P2PLIAP
	Extended Work Area 2 for Function AP	P2PLIAP
C	All Work Areas for all Functions	PAC

[15] GEOCODE=NO is invalid for Function 1B, but the 70 bytes are appended when GEOCODE=ALL. [16] Functions 1B and AP are valid for COW only

APPENDIX 13: CHARACTER-ONLY WORK AREA LAYOUTS (COW)

(as of Geosupport System Software Version 18.4 - unchanged since **V18.1)**

This appendix contains layouts of all of the COW work areas used with the Geosupport System's API. These layouts are current as of the Geosupport software version indicated above. The layouts are in the Character-Only Work Area (COW) format.[18]

Some Geosupport functions can only be called using one work area, Work Area 1 (WA1). Other functions can be called using two work areas, WA1 and Work Area 2 (WA2). WA1 contains both input fields (fields used to pass data from the application to Geosupport) and output fields (fields used to pass data from Geosupport to the application). WA1 is organized so that all the input fields occur first, followed by all the output fields. WA2 contains output fields only.

All functions use the same WA1 layout, but the set of WA1 fields that are used depends on the function. In the layout of WA1 in this appendix, the column labeled 'Functions' indicates which functions use each field.

The functions that can be called using two work areas use various WA2 layouts of various lengths. In some cases, several functions share a single WA2 layout. For functions 1A and BL, the user has a choice of two WA2 layouts, a 'regular' WA2 and a 'long' WA2.

The majority of the COW fields are identical to the MSW (Mainframe-Specific Work Area) fields.

Appendix 3 consists of a data item dictionary describing the fields that occur in the work areas.

Appendix 12 describes the differences between the COWs and MSWs.

The Geosupport Character-Only work areas (COWs) contain no packed decimal or binary fields; all fields are character. The work areas are divided into logical groups. For example work area 1 is divided into three parts; namely,

- Input information from user
- Input flags set by user
- Output information supplied by Geosupport

For precise information on work areas, refer to the appropriate section below.

NOTE: The notation *"Not Implemented"* in the comments column of the work area layout means the field is blank, its contents are not reliable or the functionality has not yet been implemented. Only items that we intend to implement and/or correct at a later date are listed in this fashion.

The following is a list of all of the Geosupport COW work areas, indicating the length of each in bytes. Functions that are listed together share a single Work Area 2 layout.

---

[18]The mainframe version of Geosupport supports both the Character-Only Work Area (COW) format and the Mainframe-Specific Work Area (MSW (a.k.a. MFS)) format. The layout of the MSWs is in [Appendix 2](/appendices/appendix02/).

The following is a list of all of the Geosupport COW work areas, indicating the length of each in bytes. Functions that are listed together share a single Work Area 2 layout.

Character-Only Work Area (COW)	**Length**
WA1, All Functions	1,200
WA2, Functions 1, 1E Regular	300
WA2, Functions 1, 1E Extended	1,500
WA2, Functions 1A, BL, BN Regular	1,363
Long WA2, Functions 1A, BL	17,750
TPAD Long WA2, Functions 1A, BL	17,750
WA2, Functions 1A, BL, BN Extended	2,800
WA2, Function 1B	4,300
WA2, Function AP Regular	1,363
WA2, Function AP Extended	2,800
WA2, Function 2	200
WA2, Function 2W (Wide)	4000
WA2, Function 3 Regular	450
WA2, Function 3 with Auxiliary Segment	950
WA2, Function 3 Extended	1,000
WA2, Function 3 Extended with Auxiliary Segment	1,500
WA2, Function 3C Regular	300
WA2, Function 3C with Auxiliary Segment	800
WA2, Function 3C Extended	850
WA2, Function 3C Extended with Auxiliary Segment	1,350
WA2, Function 3S	19,274

Notes:

1. When a group of fields are listed together in a layout, the name of the group appears in UPPER CASE and is followed by a colon (:). The fields within the group appear in mixed case and are indented under the group name. The ‘FROM’ and ‘TO’ POSITIONS are listed for the group and for the individual fields within the group.

   Example:

(Field Name)	(Size)	(From)	(To)	(Function)
BOROUGH BLOCK LOT (BBL):	10	186	195	BL
Borough Code	1	186	186	BL
Tax Block	5	187	191	BL
Tax Lot	4	192	195	BL

2. If there is a multi-field entry that may be repeated a variable number of times in the work area, then the relative positions of the fields within the entry are published and those relative positions appear in parentheses '( )'.

   Example:

(Field Name)	(Size)	(From)	(To)	(Comment)
LIST OF GEOGRAPHIC IDENTIFIERS: Variable length list of up to 21 entries; each is 53 bytes long, structured as follows:	1113	251	1363	Maximum of 21 entries, each 53 bytes long: 21x53 = 1,113
Low House Number	(16)	(1)	(16)	
High House Number	(16)	(17)	32)	
✶ ✶ ✶				
TPAD BIN Status	(1)	(50)	(50)	TPAD Request
Filler	(3)	(51)	(53)	
* End of 53-byte entry *				

Character-Only Work Area 1 (COW) – All Functions

INPUT FIELDS	SIZE	POSITION		FUNCTIONS[19]
		FROM	TO	
Geosupport Function Code	2	1	2	All
House Number - Display Format	16	3	18	1, 1A, 1B, 1E, AP
House Number - Sort Format	11	19	29	1, 1A, 1B, 1E, AP, D*
Low House Number - Display Format[20]	16	30	45	Internal Use
Low House Number – Sort Format	11	46	56	D*, Internal Use
B10SC-1 (includes Borough Code 1, B5SC-1 and B7SC-1):	11	57	67	See next 2 entries

Borough Code-1	1	57	57	Required for All Functions but BL, BN. Ignored if Fn 2 has Node Number input
10SC[21]-1	10	58	67	All but 1N, B*
Street Name-1	32	68	99	All but BL, BN, D*
B10SC-2 (includes Borough Code 2, B5SC-2 and B7SC-2):	11	100	110	2, 3*, D*
Borough Code[22]-2	1	100	100	2, 3*, D*
10SC-2	10	101	110	2, 3*, D*
Street Name-2	32	111	142	2, 3*
B10SC-3 (includes Borough Code 3, B5SC-3 and B7SC-3):	11	143	153	3*, D*
Borough Code-3	1	143	143	3*, D*
10SC-3	10	144	153	3*, D*
Street Name-3	32	154	185	3*
BOROUGH BLOCK LOT (BBL):	10	186	195	BL
Borough Code	1	186	186	BL
Tax Block	5	187	191	BL
Tax Lot	4	192	195	BL
Filler for Tax Lot Version Number	1	196	196	Not Implemented
Building Identification Number (BIN)	7	197	203	BN
Compass Direction	1	204	204	2, 3C, 3S
Compass Direction for 2nd Intersection	1	205	205	3S
Node Number	7	206	212	2, 2W
Work Area Format Indicator[23]	1	213	213	All
ZIP Code Input	5	214	218	1*, AP
Unit Input	14	219	232	1*
Filler	82	233	314	
Input Flags				
Long Work Area 2 Flag	1	315	315	1A, BL
House Number Justification Flag[24]	1	316	316	Not Implemented
House Number Normalization Length[25]	2	317	318	Not Implemented
House Number Normalization Override Flag	1	319	319	Internal Use
Street Name Normalization Length				

Limit (SNL)	2	320	321	All but B*
Street Name Normalization Format Flag[26]	1	322	322	All but B*
Cross Street Names Flag[27] a.k.a. Expanded Format Flag	1	323	323	1, 1A, 1B, 1E, 2, 3, 3C
Roadbed Request Switch	1	324	324	1, 1B, 1E, 3S (Limited)
Reserved for Internal Use	1	325	325	Internal GRC Flag
Auxiliary Segment Switch	1	326	326	3, 3C
Browse Flag	1	327	327	1*, 2, 3, 3C, BB, BF
Real Streets Only Flag	1	328	328	3S
TPAD Switch	1	329	329	1A, 1B, BL, BN
Mode Switch	1	330	330	1, 1E, 1A, 3, 3C, AP
WTO Switch	1	331	331	All
Filler	29	332	360	
OUTPUT Fields				
First Borough Name	9	361	369	All but D*
House Number - Display Format	16	370	385	1, 1A, 1B, 1E, AP, D*
House Number - Sort Format	11	386	396	1, 1A, 1B, 1E, AP, D*
B10SC - First Borough and Street Code	11	397	407	All but BL, BN
First Street Name Normalized	32	408	439	439
B10SC - Second Borough and Street Code	11	440	450	2, 3*, D*
Second Street Name Normalized	32	451	482	2, 3*, D*
B10SC - Third Borough and Street Code	11	483	493	3*, D*
Third Street Name Normalized	32	494	525	3*, D*
BOROUGH BLOCK LOT (BBL):	10	526	535	BL (Also 1, 1A, 1B, 1E if Cross Street Names Flag is ‘E’; Also 1, 1E if Mode Switch is ‘X’)
Borough Code	1	526	526	BL (see BL comment above)
Tax Block	5	527	531	BL (see BL comment above)
Tax Lot	4	532	535	BL (see BL comment above)
Filler for Tax Lot Version Number	1	536	536	*Not Implemented*
Low House Number - Display Format	16	537	552	Internal Use, D*
Low House Number - Sort Format	11	553	563	Internal Use, D*
Building Identification Number (BIN)	7	564	570	BN (see BBL functions list above)

Street Attribute Indicators	3	571	573	Internal Use
Reason Code 2	1	574	574	1B - reflects 1A Extended
Reason Code Qualifier 2	1	575	575	1B (See Reason Code 2)
Warning Code 2	2	576	577	1B (not used)
Geosupport Return Code 2 (GRC 2)	2	578	579	1B (See Reason Code 2)
Message 2	80	580	659	1B (See Reason Code 2)
Node Number	7	660	666	2, 2W
UNIT – SORT FORMAT	14	667	680	1*
Unit – Type	4	667	670	1*
Unit – Identifier	10	671	680	1*
Unit – Display Format	14	681	694	1*
Filler	11	695	705	
NIN[28]	6	706	711	*Not Implemented*
Street Attribute Indicator	1	712	712	Internal Use
Reason Code	1	713	713	All
Reason Code Qualifier	1	714	714	1A, BL, BN
Warning Code	2	715	716	All (not used)
Geosupport Return Code (GRC)	2	717	718	All
Message	80	719	798	All
Number of Street Codes and Street Names in List (up to 10)	2	799	800	1*, 2, 3*, BB, BF
List of Street Codes (10 B7SC's)	80	801	880	1*, 2, 3*, BB, BF
List of Street Names (10 Street Name Fields, 32 Bytes Each)	320	881	1200	1*, 2, 3*, BB, BF

---

[19] Note: An asterisk in the second position of a function code is used as a shorthand notation to represent all function codes having the indicated value in the first position, as follows:

```
1* = 1, 1A, 1B, 1E, 1N, AP
3* = 3, 3C, 3S
B* = BB, BF, BL, BN
D* = D, DG, DN
```

Typically, any function listed with an asterisk also includes the various forms of the function, e.g. Extended, Long, Auxiliary Segments etc.

[20] The Low House Number fields are for Internal Use (Fn 5). In addition the low House Number in Sort Format can be used with Functions D*.

[21] The user may supply either a 5-Digit, 7-Digit or 10-Digit Street code in this field. The contents are to be left-justified and blank-filled.

[22] When using street name input, the second and third borough codes are required only if they differ from the first.

[23] When this indicator, also known as the Platform Indicator, is set to C or P, the Character-Only formats of the work areas (i.e., the formats documented herein) are used. A blank in this indicator means that the IBM mainframe specific work areas, known as MSW (a.k.a. MFS), are used.

[24] If the house number is to be right justified, the House Number Justification Flag is set to R and if the house number is to be left justified, the House Number Justification Flag is set to L or left blank.

[25] The House Number Normalization Length field is used to achieve compatibility between the Main Frame Specific (MSW) work areas and the COWs. In the COWs, the House Number is permitted to be 16 characters, but, in the MSW, it is limited to 12 characters. It is not anticipated that users will make use of this field.

[26] This field, Street Name Normalization Format Flag, was formerly known as the Compact Option. If the Street Name Normalization Format Flag is set to S or blank, then the street name is returned in sort format. If it is set to C, then the street name is returned in compact format.

[27] The Cross Street Names Flag (a.k.a. Expanded Format Flag), if set to E, will return the Cross Street Names and Cross Street Codes in the List of Street Names and List of Street Codes fields respectively for Functions 1, 1E, 2, 3, 3C. These lists are in the output section of Work Area 1. These lists are also used for Similar Names processing and the Browse function. (The cross street names and codes lists are not returned for Functions 1A and 1B.) The BBL and BIN are returned in the output area of Work Area 1 where possible for Functions 1, 1A, 1B, 1E.

[28] NAP Identification Number

Work Area 2 (COW) - Functions 1, 1E

Block Face Defined by Address Range Along a Street

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Internal Use	21	1	21	
Continuous Parity Indicator/Duplicate Address Indicator	1	22	22	
Low House Number of Block Face	11	23	33	Sort Format
High House Number of Block Face	11	34	44	Sort Format
DCP Preferred LGC (For Function 1E,				For Function 1E, the BOE

See comment)				preferred LGC is provided.
No. of Cross Streets at Low Address End	1	47	47	
List of Cross Streets at Low Address End (Up to 5 B5SCs)	30	48	77	B5SC - Blank-Filled
No. of Cross Streets at High Address End	1	78	78	
List of Cross Streets at High Address End (Up to 5 B5SCs)	30	79	108	B5SC - Blank-Filled
LION KEY:	10	109	118	
Borough Code	1	109	109	
Face Code	4	110	113	
Sequence Number	5	114	118	
Special Address Generated Record Flag	1	119	119	
Side of Street Indicator	1	120	120	
Segment Length in Feet	5	121	125	
SPATIAL X-Y COORDINATES OF ADDRESS:	14	126	139	
X Coordinate	7	126	132	
Y Coordinate	7	133	139	
Reserved for Possible Z Coordinate	7	140	146	
Community Development Eligibility Indicator	1	147	147	
Marble Hill/Rikers Island Alternative Borough Flag	1	148	148	
DOT Street Light Contractor Area	1	149	149	
COMMUNITY DISTRICT:	3	150	152	
Community District Borough Code	1	150	150	
Community District Number	2	151	152	
ZIP Code	5	153	157	
FUNCTION 1E ITEMS:	14	158	171	**Use ONLY for Function 1E**
Election District	3	158	160	Invalid for Fn 1
Assembly District	2	161	162	Invalid for Fn 1
Split Election District Flag	1	163	163	Invalid for Fn 1
Congressional District	2	164	165	Invalid for Fn 1
State Senatorial District	2	166	167	Invalid for Fn 1
Civil Court District	2	168	169	Invalid for Fn 1
City Council District	2	170	171	Invalid for Fn 1
Health Center District	2	172	173	
Health Area	4	174	177	

Sanitation District	3	178	180	
Sanitation Collection Scheduling Section and Subsection	2	181	182	
Sanitation Regular Collection Schedule	5	183	187	
Sanitation Recycling Collection Schedule	3	188	190	
Police Patrol Borough Command	1	191	191	
Police Precinct	3	192	194	
Fire Division	2	195	196	
Fire Battalion	2	197	198	
Fire Company Type	1	199	199	
Fire Company Number	3	200	202	
Filler	1	203	203	Was Split Comm School Dist Flag
Community School District	2	204	205	
Atomic Polygon	3	206	208	Was Dynamic Block
Police Patrol Borough	2	209	210	
Feature Type Code	1	211	211	
Segment Type Code	1	212	212	
Alley or Cross Street List Flag	1	213	213	A - Alley Split X - Cross Street List Modified
Coincidence Segment Count	1	214	214	
Filler	2	215	216	
Borough of Census Tract	1	217	217	Internal
1990 Census Tract	6	218	223	
2010 Census Tract	6	224	229	
2010 Census Block	4	230	233	
2010 Census Block Suffix	1	234	234	*Not Implemented*
2000 Census Tract	6	235	240	
2000 Census Block	4	241	244	
2000 Census Block Suffix	1	245	245	
Neighborhood Tabulation Area (NTA)	4	246	249	
DSNY Snow Priority Code	1	250	250	Dept. of Sanitation
DSNY Organic Recycling Schedule	5	251	255	Dept. of Sanitation
DSNY Bulk Pickup Schedule	5	256	260	Dept. of Sanitation
Hurricane Evacuation Zone (HEZ)	2	261	262	
Filler	11	263	273	
Underlying Address Number on True Street				

(for NAPs, Vanity, etc)	11	274	284	Sort Format
Underlying B7SC of True Street (NAPs etc)	8	285	292	
Segment Identifier	7	293	299	
Curve Flag	1	300	300	

Work Area 2 (COW) - Functions 1, 1E Extended

Block Face Defined by Address Range Along a Street

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as Regular Work Area 2 for Functions 1, 1E	300	1	300	
List of 4 LGC's	8	301	308	
BOE LGC Pointer	1	309	309	
Segment Azimuth	3	310	312	
Segment Orientation	1	313	313	
SPATIAL COORDINATES OF SEGMENT:	42	314	355	
X Coordinate, Low Address End	7	314	320	From Node
Y Coordinate, Low Address End	7	321	327	
Z Coordinate, Low Address End	7	328	334	*Not Implemented*
X Coordinate, High Address End	7	335	341	To Node
Y Coordinate, High Address End	7	342	348	
Z Coordinate, High Address End	7	349	355	*Not Implemented*
SPATIAL COORDINATES OF CENTER OF CURVATURE:	21	356	376	
X Coordinate	7	356	362	
Y Coordinate	7	363	369	
Z Coordinate	7	370	376	*Not Implemented*
Radius of Circle	7	377	383	
Secant Location Related to Curve	1	384	384	L - Left, R - Right
Angle to From Node – Beta Value	5	385	389	Beta & Alpha Used to Calculate Coordinates
Angle to To Node – Alpha Value	5	390	394	
From LION Node ID	7	395	401	From Node
To LION Node ID	7	402	408	To Node
LION KEY FOR VANITY ADDRESS:	10	409	418	
Borough Code	1	409	409	
Face Code	4	410	413	

Sequence Number	5	414	418	
Side of Street of Vanity Address	1	419	419	
Split Low House Number	11	420	430	
Traffic Direction	1	431	431	
Turn Restrictions	10	432	441	*Not Implemented*
Fraction for Curve Calculation	3	442	444	Internal Use
Roadway Type	2	445	446	
Physical ID	7	447	453	
Generic ID	7	454	460	
NYPD ID	7	461	467	
FDNY ID	7	468	474	
Bike Lane 2	2	475	476	
Bike Traffic Direction	2	477	478	
Filler	3	479	481	Was Blockface ID, See bytes 730-739
Street Status	1	482	482	
Street Width	3	483	485	
Street Width Irregular	1	486	486	
Bike Lane	1	487	487	Will be retired. See Bike Lane 2
Federal Classification Code	2	488	489	
Right Of Way Type	1	490	490	
List of Second Set of 5 LGCs	10	491	500	
Legacy Segment ID	7	501	507	
From Preferred LGCs First Set of 5	10	508	517	
To Preferred LGCs First Set of 5	10	518	527	
From Preferred LGCs Second Set of 5	10	528	537	
To Preferred LGCs Second Set of 5	10	538	547	
No Cross Street Calculation Flag	1	548	548	
Individual Segment Length	5	549	553	
NTA Name	75	554	628	
USPS Preferred City Name	25	629	653	
Latitude	9	654	662	
Longitude	11	663	673	
From Actual Segment Node ID	7	674	680	
To Actual Segment Node ID	7	681	687	
SPATIAL COORDINATES OF ACTUAL SEGMENT:	42	688	729	

X Coordinate, Low Address End	7	688	694	Actual From Node
Y Coordinate, Low Address End	7	695	701	
Z Coordinate, Low Address End	7	702	708	*Not Implemented*
X Coordinate, High Address End	7	709	715	Actual To Node
Y Coordinate, High Address End	7	716	722	
Z Coordinate, High Address End	7	723	729	*Not Implemented*
Blockface ID	10	730	739	Previously 7 bytes
Number of Travel Lanes on the Street	2	740	741	
Number of Parking Lanes on the Street	2	742	743	
Number of Total Lanes on the Street	2	744	745	
Street Width Maximum	3	746	748	
Speed Limit	2	749	750	
PUMA Code	5	751	755	
Filler	245	756	1000	
Reason Code	1	1001	1001	
Reason Code Qualifier	1	1002	1002	
Warning Code Filler	2	1003	1004	
Return Code	2	1005	1006	
Number of Cross Streets at Low Address End	1	1007	1007	
List of Cross Streets at Low Address End (Up to 5 B7SCs)	40	1008	1047	B7SC-Blank-Filled
Number of Cross Streets at High Address End	1	1048	1048	
List of Cross Streets at High Address End (Up to 5 B7SCs)	40	1049	1088	B7SC-Blank-Filled
List of Cross Street Names at Low Address End	160	1089	1248	5 x 32 = 160 Up to 5 Street Names
List of Cross Street Names at High Address End	160	1249	1408	5 x 32 = 160 Up to 5 Street Names
BOE Preferred B7SC	8	1409	1416	
BOE Preferred Street Name	32	1417	1448	
Filler	52	1449	1500	

Work Area 2 (COW) - Functions 1A, BL, BN

Property Level Information Defined by Address, BBL or BIN

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Internal Use	21	1	21	

Continuous Parity Indicator /Duplicate Address Indicator	1	22	22	
Low House Number of Defining Address Range	11	23	33	Sort Format
BOROUGH BLOCK LOT (BBL):	10	34	43	Billing BBL if Condo
Borough Code	1	34	34	
Tax Block	5	35	39	
Tax Lot	4	40	43	
Filler for Tax Lot Version Number	1	44	44	*Not Implemented*
RPAD Self-Check Code (SCC) for BBL	1	45	45	
Filler	1	46	46	
RPAD Building Classification Code	2	47	48	
Corner Code	2	49	50	
Number of Existing Structures on Lot	4	51	54	
Number of Street Frontages of Lot	2	55	56	
Interior Lot Flag	1	57	57	
Vacant Lot Flag	1	58	58	
Irregularly-Shaped Lot Flag	1	59	59	
Marble Hill/Rikers Island Alternate Borough Flag	1	60	60	
List of Geographic Identifiers (LGI) Overflow Flag	1	61	61	When = 'E', there are more than 21 addrs for Fns 1A and BL.
STROLLING KEY:	19	62	80	*Not Implemented*
Borough	1	62	62	*Not Implemented*
5-Digit Street Code of ‘On’ Street	5	63	67	*Not Implemented*
Side of Street Indicator	1	68	68	*Not Implemented*
High House Number – Sort Format	11	69	79	*Not Implemented*
Filler	1	80	80	*Not Implemented*
Reserved for Internal Use	1	81	81	
Building Identification Number (BIN) of Input Address or NAP	7	82	88	
Condominium Flag	1	89	89	If condo, = 'C';
Filler	1	90	90	
DOF Condominium Identification Number	4	91	94	
Condominium Unit ID Number	7	95	101	*Not Implemented*
Condominium Billing BBL	10	102	111	
Filler - Tax Lot Version No. for Billing BBL	1	112	112	*Not Implemented*

Self-Check Code (SCC) of Billing BBL	1	113	113	
LOW BBL OF THIS BUILDING'S CONDOMINIUM UNITS:	10	114	123	
Borough Code	1	114	114	Condo
Tax Block	5	115	119	
Tax Lot	4	120	123	
Filler for Tax Lot Version No. of Low BBL	1	124	124	*Not Implemented*
HIGH BBL OF THIS BUILDING'S CONDOMINIUM UNITS:	10	125	134	
Borough Code	1	125	125	Condo
Tax Block	5	126	130	
Tax Lot	4	131	134	
Filler for Tax Lot Version No. of High BBL	1	135	135	*Not Implemented*
Filler	15	136	150	
Cooperative ID Number	4	151	154	
SBVP (SANBORN MAP IDENTIFIER):	8	155	162	
Sanborn Borough Code	1	155	155	
Volume Number	2	156	157	
Volume Number Suffix	1	158	158	
Page Number	3	159	161	
Page Number Suffix	1	162	162	
DCP Commercial Study Area	5	163	167	
Tax Map Number Section & Volume	5	168	172	
Reserved for Tax Map Page Number	4	173	176	*Not Implemented*
Filler	3	177	179	
Latitude	9	180	188	
Longitude	11	189	199	
X-Y Coordinates of Tax Lot Centroid (Internal to Lot)	14	200	213	Previously X-Y Coordinates of COGIS Annotation Point
Business Improvement District (BID)	6	214	219	
TPAD BIN Status (for DM job)	1	220	220	TPAD request
TPAD New BIN	7	221	227	TPAD request
TPAD New BIN Status	1	228	228	TPAD request
TPAD Conflict Flag	1	229	229	TPAD request
DCP Zoning Map	3	230	232	
Filler	6	233	238	

List of 4 LGCs	8	239	246	Internal Use
Number of Entries in List of Geographic Identifiers	4	247	250	Maximum of 21 entries
LIST OF GEOGRAPHIC IDENTIFIERS: Variable length list of up to 21 entries, each 53-bytes long, structured as follows:	1113	251	1363	Maximum of 21 entries, each 53 bytes long: 21x53 = 1,113
Low House Number	(16)	(1)	(16)	Display format
High House Number	(16)	(17)	(32)	Display format
Borough Code	(1)	(33)	(33)	Start of B7SC
5-Digit Street Code	(5)	(34)	(38)	Part of B7SC
DCP-Preferred Local Group Code (LGC)	(2)	(39)	(40)	End of B7SC
Building Identification Number (BIN)	(7)	(41)	(47)	
Side of Street Indicator	(1)	(48)	(48)	L - Left, R - Right
Geographic Identifier Entry Type Code	(1)	(49)	(49)	N - NAP (Simplex) G - Complex NAP X - Constituent entity of Complex NAP B - NAUB F - Frontage W - Blank Wall Q - Pseudo Addr T - Tunnel U - Misc. Structure V - Vanity Address O - Out-of Sequence Address Blank - Normal
TPAD BIN Status	(1)	(50)	(50)	TPAD Request
Filler	(3)	(51)	(53)	
* End of 53-byte entry *				
*** End of Work Area *** (1,363 bytes)				

Long Work Area 2 (COW) - Functions 1A, BL

Property Level Information (BIN Number) Defined by Address, BBL

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as Regular Work Area 2 – Functions 1A, BL, BN	246	1	246	
Number of Buildings on Tax Lot	4	247	250	Maximum of 2,500
LIST OF BUILDINGS ON TAX LOT: Variable length list of up to 2,500 entries; each is 7 bytes long structured as follows:	17500	251	17750	Maximum of 2,500 entries, each 7 bytes long. 7 x 2,500 = 17,500
Building Identification Number (BIN)	-7	-1	-7	
* End of 7-byte entry *				
*** End of Work Area *** (17,750 bytes)"				

TPAD Long Work Area 2 (COW) - Functions 1A, BL

Property Level Information Defined by Address/BBL

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as Regular Work Area 2 – Functions 1A, BL, BN	246	1	246	
Number of Buildings on Tax Lot	4	247	250	Maximum is 2,187
LIST OF BUILDINGS ON TAX LOT: Variable length list of up to 2,187 entries; each is 8 bytes long, structured as follows:	17496	251	17746	Maximum of 2,187 entries, each 8 bytes long. 8 x 2,187 = 17,496
TPAD BIN	(7)	(1)	(7)	
TPAD BIN Status	(1)	(8)	(8)	
* End of 8-byte entry *				
Filler	4	17747	17750	

Work Area 2 (COW) - Functions 1A, BL, BN Extended

Property Level Information Defined by Address, BBL or BIN

FIELD	SIZE	POSITION		COMMENT
		TO	FROM	
Same as Regular Work Area 2 – Functions 1A, BL, BN	246	1	246	
Reason Code	1	247	247	Same as Work Area 1
Reason Code Qualifier	1	248	248	Same as Work Area 1
Warning Code	2	249	250	Not used
Return Code (GRC)	2	251	252	Same as Work Area 1
Filler	108	253	360	
Number of Entries in List of Geographic Identifiers	4	361	364	Maximum number is 21
LIST OF GEOGRAPHIC IDENTIFIERS: Variable length list of up to 21 entries; each is 116 bytes long, structured as follows:	2436	365	2800	Maximum of 21 entries, each 116 bytes long: 116 x 21 = 2,436
Low House Number	(16)	(1)	(16)	Display format
High House Number	(16)	(17)	(32)	Display format
Borough Code	(1)	(33)	(33)	Start of B7SC
5-Digit Street Code	(5)	(34)	(38)	Part of B7SC
DCP-Preferred Local Group Code (LGC)	(2)	(39)	(40)	End of B7SC
Building Identification Number (BIN)	(7)	(41)	(47)	
Side of Street Indicator	(1)	(48)	(48)	L - Left, R - Right
Geographic Identifier Entry Type Code	(1)	(49)	(49)	N - NAP (Simplex) G - Complex NAP X - Constituent Entity of Complex NAP B - NAUB F - Frontage W - Blank Wall Q - Pseudo Address T - Tunnel U - Misc Structure V - Vanity Address

				O - Out-of-Sequence Addr Blank - Normal
TPAD BIN Status	(1)	(50)	(50)	TPAD Request
Street Name (Principal Street Name)	(32)	(51)	(82)	Based on B7SCin Address List
Filler	(34)	(83)	(116)	
* End of 116-byte entry *				
*** End of Work Area *** (2,800 bytes)				

Work Area 2 (COW) - Function 1B

Block Face Information Defined by Address Range Along a Street &

Property Level Information Defined by Address

FIELD	SIZE	POSITION		COMMENT
		TO	FROM	
BLOCK FACE INFORMATION (Based On Function 1E Extended)				
Internal Use	21	1	21	
Continuous Parity Indicator/Duplicate Address Indicator	1	22	22	
Low House Number of Block Face	11	23	33	Sort Format
High House Number of Block Face	11	34	44	Sort Format
DCP Preferred LGC	2	45	46	
Number of Cross Streets at Low Address End	1	47	47	
List of Cross Streets at Low Address End (Up to 5 B5SCs)	30	48	77	B5SC - Blank-Filled
Number of Cross Streets at High Address End	1	78	78	
List of Cross Streets at High Address End (Up to 5 B5SCs)	30	79	108	B5SC - Blank-Filled
LION KEY:	10	109	118	
Borough Code	1	109	109	
Face Code	4	110	113	
Sequence Number	5	114	118	
Special Address Generated Record Flag	1	119	119	
Side of Street Indicator	1	120	120	
Segment Length in Feet	5	121	125	

Spatial X-Y Coordinates of Address	14	126	139	
Reserved for Possible Z Coordinate	7	140	146	
Community Development Eligibility Indicator	1	147	147	
Marble Hill/Rikers Island Alternative Borough Flag	1	148	148	
DOT Street Light Contractor Area	1	149	149	
COMMUNITY DISTRICT:	3	150	152	
Community District Borough Code	1	150	150	
Community District Number	2	151	152	
ZIP Code	5	153	157	
Election District	3	158	160	
Assembly District	2	161	162	
Split Election District Flag	1	163	163	
Congressional District	2	164	165	
State Senatorial District	2	166	167	
Civil Court District	2	168	169	
City Council District	2	170	171	
Health Center District	2	172	173	
Health Area	4	174	177	
Sanitation District	3	178	180	
Sanitation Collection Scheduling Section and Subsection	2	181	182	
Sanitation Regular Collection Schedule	5	183	187	
Sanitation Recycling Collection Schedule	3	188	190	
Police Patrol Borough Command	1	191	191	
Police Precinct	3	192	194	
Fire Division	2	195	196	
Fire Battalion	2	197	198	
Fire Company Type	1	199	199	
Fire Company Number	3	200	202	
Filler	1	203	203	Was Split Community School District Flag
Community School District	2	204	205	
Atomic Polygon	3	206	208	Was Dynamic Block
Police Patrol Borough	2	209	210	
Feature Type Code	1	211	211	

Segment Type Code	1	212	212	
Alley or Cross Street List Flag	1	213	213	A - Alley Split X - Cross Street List Modified
Coincidence Segment Count	1	214	214	
Filler	3	215	217	
1990 Census Tract	6	218	223	
2010 Census Tract	6	224	229	
2010 Census Block	4	230	233	
2010 Census Block Suffix	1	234	234	Not Implemented
2000 Census Tract	6	235	240	
2000 Census Block	4	241	244	
2000 Census Block Suffix	1	245	245	
Neighborhood Tabulation Area (NTA)	4	246	249	
DSNY Snow Priority Code	1	250	250	Dept. of Sanitation
DSNY Organic Recycling Schedule	5	251	255	Dept. of Sanitation
DSNY Bulk Pickup Schedule	5	256	260	Dept. of Sanitation
Hurricane Evacuation Zone (HEZ)	2	261	262	
Filler	11	263	273	
Underlying Address Number for NAPs	11	274	284	Sort Format
Underlying B7SC	8	285	292	
Segment Identifier	7	293	299	
Curve Flag	1	300	300	
List of 4 LGC's	8	301	308	
BOE LGC Pointer	1	309	309	
Segment Azimuth	3	310	312	
Segment Orientation	1	313	313	
SPATIAL COORDINATES OF SEGMENT:	42	314	355	
X Coordinate, Low Address End	7	314	320	
Y Coordinate, Low Address End	7	321	327	
Z Coordinate, Low Address End	7	328	334	Not Implemented
X Coordinate, High Address End	7	335	341	
Y Coordinate, High Address End	7	342	348	
Z Coordinate, High Address End	7	349	355	Not Implemented
SPATIAL COORDINATES OF CENTER OF				

CURVATURE:	21	356	376	
X Coordinate	7	356	362	
Y Coordinate	7	363	369	
Z Coordinate	7	370	376	Not Implemented
Radius of Circle	7	377	383	
Secant Location Related to Curve	1	384	384	L - Left, R - Right
Angle to From Node – Beta Value	5	385	389	Beta & Alpha Used to Calculate Coordinates
Angle to To Node – Alpha Value	5	390	394	
From LION Node ID	7	395	401	
To LION Node ID	7	402	408	
LION Key for Vanity Address	10	409	418	
Side of Street of Vanity Address	1	419	419	
Split Low House Number	11	420	430	
Traffic Direction	1	431	431	
Turn Restrictions	10	432	441	
Fraction for Curve Calculation	3	442	444	
Roadway Type	2	445	446	
Physical ID	7	447	453	
Generic ID	7	454	460	
NYPD ID	7	461	467	
FDNY ID	7	468	474	
Bike Lane 2	2	475	476	
Bike Traffic Direction	2	477	478	
Filler	3	479	481	Was Blockface ID See bytes 730-739
Street Status	1	482	482	
Street Width	3	483	485	
Street Width Irregular	1	486	486	
Bike Lane	1	487	487	Will be retired. See Bike Lane 2
Federal Classification Code	2	488	489	
Right Of Way Type	1	490	490	
List of Second Set of 5 LGCs	10	491	500	
Legacy Segment ID	7	501	507	
From Preferred LGCs First Set of 5	10	508	517	
To Preferred LGCs First Set of 5	10	518	527	

From Preferred LGCs Second Set of 5	10	528	537	
To Preferred LGCs Second Set of 5	10	538	547	
No Cross Street Calculation Flag	1	548	548	
Individual Segment Length	5	549	553	
NTA Name	75	554	628	
USPS Preferred City Name	25	629	653	
Latitude	9	654	662	
Longitude	11	663	673	
From Actual Segment Node ID	7	674	680	
To Actual Segment Node ID	7	681	687	
SPATIAL COORDINATES OF ACTUAL SEGMENT:	42	688	729	
X Coordinate, Low Address End	7	688	694	Actual From Node
Y Coordinate, Low Address End	7	695	701	
Z Coordinate, Low Address End	7	702	708	Not Implemented
X Coordinate, High Address End	7	709	715	Actual To Node
Y Coordinate, High Address End	7	716	722	
Z Coordinate, High Address End	7	723	729	Not Implemented
Blockface ID	10	730	739	
Number of Travel Lanes on the Street	2	740	741	
Number of Parking Lanes on the Street	2	742	743	
Number of Total Lanes on the Street	2	744	745	
Street Width Maximum	3	746	748	
Speed Limit	2	749	750	
PUMA Code	5	751	755	
Filler	245	756	1000	
Reason Code	1	1001	1001	
Reason Code Qualifier	1	1002	1002	
Warning Code	2	1003	1004	
Return Code	2	1005	1006	
Number of Cross Streets at Low Address End	1	1007	1007	
List of Cross Streets at Low Address End (Up to 5 B7SCs)	40	1008	1047	B7SC - Blank Filled
No. of Cross Streets at High Address End	1	1048	1048	
List of Cross Streets at High Address End (Up to 5 B7SCs)	40	1049	1088	B7SC - Blank Filled
List of Cross Street Names at Low Address End	160	1089	1248	5 x 32 = 160 Up to 5 Street Names

List of Cross Street Names at High Address End	160	1249	1408	5 x 32 = 160 Up to 5 Street Names
BOE Preferred B7SC	8	1409	1416	
BOE Preferred Street Name	32	1417	1448	
Filler	52	1449	1500	
PROPERTY LEVEL INFORMATION (Based On Functions 1A, BL, BN Extended)				
Internal Use	21	1501	1521	
Continuous Parity Indicator / Duplicate Address Indicator	1	1522	1522	
Low House Number of Defining Address Range	11	1523	1533	Sort Format
BOROUGH BLOCK LOT (BBL):	10	1534	1543	Billing BBL if Condo
Borough Code	1	1534	1534	
Tax Block	5	1535	1539	
Tax Lot	4	1540	1543	
Filler for Tax Lot Version Number	1	1544	1544	Not Implemented
RPAD Self-Check Code (SCC) for BBL	1	1545	1545	
Filler	1	1546	1546	
RPAD Building Classification Code	2	1547	1548	
Corner Code	2	1549	1550	
Number of Existing Structures on Lot	4	1551	1554	
Number of Street Frontages of Lot	2	1555	1556	
Interior Lot Flag	1	1557	1557	
Vacant Lot Flag	1	1558	1558	
Irregularly-Shaped Lot Flag	1	1559	1559	
Marble Hill/Rikers Island Alternate Borough Flag	1	1560	1560	
List of Geographic Identifiers Overflow Flag	1	1561	1561	When = 'E', there are more than 21 addrs for Fn 1B (based on Fn 1A)
STROLLING KEY:	19	1562	1580	Not Implemented
Borough	1	1562	1562	
5-Digit Street Code of ON- Street	5	1563	1567	
Side of Street Indicator	1	1568	1568	
High House Number	11	1569	1579	Sort Format
Filler	1	1580	1580	
Reserved for Internal Use	1	1581	1581	

Building Identification Number (BIN) of Input Address or NAP	7	1582	1588	
Condominium Flag	1	1589	1589	If condo, = ‘C’
Filler	1	1590	1590	
DOF Condominium Identification Number	4	1591	1594	
Condominium Unit ID Number	7	1595	1601	Not Implemented
Condominium Billing BBL	10	1602	1611	
Filler - Tax Lot Version No. Billing BBL	1	1612	1612	Not Implemented
Self-Check Code (SCC) of Billing BBL	1	1613	1613	
Low BBL of this Building’s Condominium Units	10	1614	1623	
Filler - Tax Lot Version No. of Low BBL	1	1624	1624	Not Implemented
High BBL of this Building’s Condominium Units	10	1625	1634	
Filler - Tax Log Version No. of High BBL	1	1635	1635	Not Implemented
Filler	15	1636	1650	
Cooperative ID Number	4	1651	1654	
SBVP (SANBORN MAP IDENTIFIER):	8	1655	1662	
Sanborn Borough Code	1	1655	1655	
Volume Number	2	1656	1657	
Volume Number Suffix	1	1658	1658	
Page Number	3	1659	1661	
Page Number Suffix	1	1662	1662	
DCP Commercial Study Area	5	1663	1667	
Tax Map Number Section & Volume	5	1668	1672	
Reserved for Tax Map Page Number	4	1673	1676	Not Implemented
Filler	3	1677	1679	
Latitude	9	1680	1688	
Longitude	11	1689	1699	
X-Y Coordinates of Lot Centroid	14	1700	1713	
Business Improvement District (BID)	6	1714	1719	
TPAD BIN Status	1	1720	1720	TPAD Request
TPAD New BIN	7	1721	1727	TPAD Request
TPAD New BIN Status	1	1728	1728	TPAD Request
TPAD Conflict Flag	1	1729	1729	TPAD Request
DCP Zoning Map	3	1730	1732	
Filler	6	1733	1738	
Internal Use	8	1739	1746	
Reason Code	1	1747	1747	

Reason Code Qualifier	1	1748	1748	
Warning Code	2	1749	1750	
Return Code	2	1751	1752	
Filler	108	1753	1860	
Number of Entries in List of Geographic Identifiers	4	1861	1864	Maximum is 21
LIST OF GEOGRAPHIC IDENTIFIERS: Variable length list of up to 21 entries; each is 116 bytes long, structured as follows:	2436	1865	4300	Maximum is 21 entries. 21 x 116 = 2436
Low House Number	16	(1)	(16)	Display format
High House Number	16	(17)	(32)	Display format
Borough Code	1	(33)	(33)	Start of B7SC
5-Digit Street Code	5	(34)	(38)	
DCP-Preferred Local Group Code (LGC)	2	(39)	(40)	
Building Identification Number	7	(41)	(47)	
Side of Street Indicator	1	(48)	(48)	L - Left, R - Right
Geographic Identifier Entry Type Code	1	(49)	(49)	N - NAP (Simplex) G - Complex NAP X - Constituent Entity of Complex NAP B - NAUB F - Frontage W - Blank Wall Q - Pseudo Address T - Tunnel U - Misc. Structure V - Vanity Address O - Out-of-Sequence Address Blank – Normal
TPAD BIN Status	1	(50)	(50)	TPAD Request
Street Name	32	(51)	(82)	
Filler	34	(83)	(116)	
* End of 116-byte entry *				
*** End of Work Area *** (4,300 bytes)				

Work Area 2 (COW) - Function AP

Address Point Information Defined by Address

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Internal Use	21	1	21	
Continuous Parity Indicator /Duplicate Address Indicator	1	22	22	
Low House Number of Defining Address Range	11	23	33	Sort Format
BOROUGH BLOCK LOT (BBL):	10	34	43	Billing BBL if Condo
Borough Code	1	34	34	
Tax Block	5	35	39	
Tax Lot	4	40	43	
Filler	7	44	50	
Number of Existing Structures on Lot	4	51	54	
Filler	26	55	80	
Reserved for Internal Use	1	81	81	
Building Identification Number (BIN) of Input Address or NAP	7	82	88	
Condominium Flag	1	89	89	If condo, = 'C'
Filler	1	90	90	
DOF Condominium Identification Number	4	91	94	
Filler	7	95	101	
Condominium Billing BBL	10	102	111	
Filler - Tax Lot Version No. for Billing BBL	1	112	112	Not Implemented
Filler	1	113	113	
LOW BBL OF THIS BUILDING⁇S CONDOMINIUM UNITS:	10	114	123	
Borough Code	1	114	114	Condo
Tax Block	5	115	119	
Tax Lot	4	120	123	
Filler for Tax Lot Version No. of Low BBL	1	124	124	Not Implemented
HIGH BBL OF THIS BUILDING⁇S CONDOMINIUM UNITS:	10	125	134	
Borough Code	1	125	125	Condo

Tax Block	5	126	130	
Tax Lot	4	131	134	
Filler for Tax Lot Version No. of High BBL	1	135	135	Not Implemented
Filler	15	136	150	
Cooperative ID Number	4	151	154	
Filler	22	155	176	
Filler	3	177	179	
Latitude	9	180	188	
Longitude	11	189	199	
X-Y Coordinates of Address Point	14	200	213	
Filler	16	214	229	
Address Point ID	9	230	238	
List of 4 LGCs - Internal Use	8	239	246	Internal Use
Number of Entries in List of Geographic Identifiers	4	247	250	For Fn AP # is '0001'. Always '0001'
LIST OF GEOGRAPHIC IDENTIFIERS: For Function AP, the list contains one entry. Variable length list of up to 21 entries, each is 53 bytes long, structured as follows:	1113	251	1363	For Function AP - there is only 1 entry. (Potential Max of 21) 21x53 = 1,113
Low House Number	(16)	(1)	(16)	Display format
High House Number	(16)	(17)	(32)	Display format
Borough Code	(1)	(33)	(33)	Start of B7SC
5-Digit Street Code	(5)	(34)	(38)	Part of B7SC
DCP-Preferred Local Group Code (LGC)	(2)	(39)	(40)	End of B7SC
Building Identification Number (BIN)	(7)	(41)	(47)	
Side of Street Indicator	(1)	(48)	(48)	L - Left, R - Right
Geographic Identifier Entry Type Code	(1)	(49)	(49)	V - Vanity Address Blank - Normal
Filler	(4)	(50)	(53)	
* End of 53-byte entry *				

*** End of Work Area *** (1,363 bytes)	

Work Area 2 (COW) - Function AP Extended

Address Point Information Defined by Address

FIELD	SIZE	FROM		COMMENT
		FROM	TO	
Same as Regular Work Area 2 – Function AP	1	1	246	
Reason Code	1	247	247	Same as Work Area 1
Reason Code Qualifier	1	248	248	Same as Work Area 1
Warning Code	2	249	250	Not used
Return Code (GRC)	2	251	252	Same as Work Area 1
Filler	108	253	360	
Number of Entries in List of Geographic Identifiers	4	361	364	Fn APX # is '0001' Always '0001'
LIST OF GEOGRAPHIC IDENTIFIERS: For Function APX, the list contains one entry Variable length list of up to 21 entries; there is only 1 entry. each is 116 bytes long, structured as follows:	2436	365	2800	For Function APX – 21 x 116 = 2,436
Low House Number	(16)	(1)	(16)	Display format
High House Number	(16)	(17)	(32)	Display format
Borough Code	(1)	(33)	(33)	Start of B7SC
5-Digit Street Code	(5)	(34)	(38)	Part of B7SC
DCP-Preferred Local Group Code (LGC)	(2)	(39)	(40)	End of B7SC
Building Identification Number (BIN)	(7)	(41)	(47)	
Side of Street Indicator	(1)	(48)	(48)	L - Left, R - Right
Geographic Identifier Entry Type Code	(1)	(49)	(49)	V - Vanity Address Blank - Normal

Filler	(1)	(50)	(50)	
Street Name (Principal Street Name)	(32)	(51)	(82)	Based on B7SC in Address List
Filler	(34)	(83)	(116)	
* End of 116-byte entry *				
*** End of Work Area *** (2,800 bytes)				

Work Area 2 (COW) - Function 2

Intersection Defined by Two Intersecting Streets

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Internal Use	21	1	21	
Intersection Replication Counter	1	22	22	
DCP-Preferred LGC for Street 1	2	23	24	
DCP-Preferred LGC for Street 2	2	25	26	
Number of Intersecting Streets	1	27	27	
List of Intersecting Streets (Up to five B5SCs, 6 bytes each)	30	28	57	
Compass Direction for Intersection Key or Counter for Multiple Intersections	1	58	58	
Atomic Polygon	3	59	61	Was Dynamic Block
Filler	2	62	63	
LION Node Number	7	64	70	
SPATIAL COORDINATES:	21	71	91	
X Coordinate	7	71	77	
Y Coordinate	7	78	84	
Reserved for possible Z Coordinate	7	85	91	
SBVP1 (SANBORN MAP IDENTIFIER):	8	92	99	
Borough Code	1	92	92	
Volume Number	2	93	94	
Volume Number Suffix	1	95	95	
Page Number	3	96	98	
Page Number Suffix	1	99	99	
SBVP2 (SANBORN MAP IDENTIFIER):	8	100	107	
Borough Code	1	100	100	

Volume Number	2	101	102	
Volume Number Suffix	1	103	103	
Page Number	3	104	106	
Page Number Suffix	1	107	107	
Marble Hill/Rikers Island Alternative Borough Flag	1	108	108	
DOT Street Light Contractor Area	1	109	109	
COMMUNITY DISTRICT:	3	110	112	
Community District Borough Code	1	110	110	
Community District Number	2	111	112	
ZIP Code	5	113	117	
Health Area	4	118	121	
Police Patrol Borough Command	1	122	122	
Police Precinct	3	123	125	
Fire Division	2	126	127	
Fire Battalion	2	128	129	
Fire Company Type	1	130	130	
Fire Company Number	3	131	133	
Community School District	2	134	135	
2010 Census Tract	6	136	141	
1990 Census Tract	6	142	147	
List of Pairs of Level Codes	10	148	157	Not Implemented
Police Patrol Borough	2	158	159	
Assembly District	2	160	161	
Congressional District	2	162	163	
State Senatorial District	2	164	165	
Civil Court District	2	166	167	
City Council District	2	168	169	
CD Eligibility	1	170	170	
Distance Between Duplicate Intersections	5	171	175	
2000 Census Tract	6	176	181	
Health Center District	2	182	183	
Sanitation District	3	184	186	
Sanitation Section/Subsection	2	187	188	
Filler	12	189	200	

Work Area 2 (COW) - Function 2W (Wide)

Intersection Defined by Two Intersecting Streets

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as regular work area 2 for Function 2	200	1	200	
Filler	22	201	222	
LGC List for Street 1	8	223	230	
LGC List for Street 2	8	231	238	
Turn Restrictions	10	239	248	
Preferred LGCs for Intersecting B5SCs	10	249	258	
True Replication Counter	2	259	260	
List of Up To 20 7-Byte Nodes	140	261	400	GRC 03 / Reason B
B7SCs For The Above 20 Nodes – List of intersecting streets (B7SCs) for node list (8 byte street code * 4 LGCs * 5 streets * 20 nodes) - See table below for detail	3200	401	3600	GRC 03/ B See detail layout below.
Reason Code	1	3601	3601	
Reason Code Qualifier	1	3602	3602	
Warning Code	2	3603	3604	
Return Code	2	3605	3606	
Latitude	9	3607	3615	
Longitude	11	3616	3626	
Filler	374	3627	4000	

Detail of List of intersecting streets for node list (bytes 401-3600)

LIST OF B7SCS FOR EACH NODE IN NODE LIST (Up to 20 nodes, Up to 5 streets per node, Up to 4 LGCs per street, 8 bytes per B7SC) Each node is structured as follows:	3200	401	3600	GRC 03 /B generates bytes 261-400 & 401-3600 20x5x4x8=3,200
NODE 1 (entire node entry repeats 20 times) STREET 1 (entire street entry repeats 5 times) B7SC for LGC1 B7SC for LGC2 B7SC for LGC3 B7SC for LGC4 Note: The first 2 streets may have up to four LGCs defined. As of this release, the remaining 3 streets at each node may have only 1 LGC defined (resulting in 1 B7SC) and the remaining 3 blank.	 (160) (32) (8) (8) (8) (8)	 (1) (1) (1) (9) (17) (25)	 (160) (32) (8) (16) (24) (32)	Each street has up to 4 B7SCs. (8x4=32 byte) Each node has up to 5 streets (32x5=160) Each situation has up to 20 nodes (160x20=3200)

Work Area 2 (COW) - Function 3

Street Segment Defined By 'On' and Two Cross Streets

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Internal Use	21	1	21	
Duplicate Key Flag or Continuous Parity	1	22	22	
Locational Status of Segment	1	23	23	
County Boundary Indicator	1	24	24	
DCP-Preferred LGC for Street 1	2	25	26	‘On’ Street
DCP-Preferred LGC for Street 2	2	27	28	Input Cross Street with Lower B5SC value
DCP-Preferred LGC for Street 3	2	29	30	Input Cross Street with Higher B5SC value
Number of Cross Streets at Low Address End	1	31	31	
List of Cross Streets at Low Address End (Up to five B5SCs, 6 bytes each)	30	32	61	Blank Filled
Number of Cross Streets at High Address End	1	62	62	
List of Cross Streets at High Address End (Up to five B5SCs, 6 bytes each)	30	63	92	Blank Filled
Cross Street Reversal Flag	1	93	93	
LION KEY	10	94	103	
LION Borough Code	1	94	94	
LION Face Code	4	95	98	
LION Sequence Number	5	99	103	
Generated Record Flag	1	104	104	
Length of Segment in Feet	5	105	109	
Segment Azimuth	3	110	112	
Segment Orientation	1	113	113	
Marble Hill/Rikers Island Alternative Borough Flag	1	114	114	
From Node	7	115	121	
To Node	7	122	128	
DSNY Snow Priority Code	1	129	129	Dept. of Sanitation
Filler	4	130	133	
Segment Identifier	7	134	140	
DOT Street Light Contractor Area	1	141	141	
Curve Flag	1	142	142	

Dog Leg Flag	1	143	143	
Feature Type Code	1	144	144	
Segment Type Code	1	145	145	
Coincident Segment Count	1	146	146	
Filler	4	147	150	
LEFT SIDE:				
COMMUNITY DISTRICT:	3	151	153	
Community District Borough Code	1	151	151	
Community District Number	2	152	153	
Low House Number	16	154	169	Display Format
High House Number	16	170	185	Display Format
Future Use	32	186	217	
Community Development Eligibility Indicator	1	218	218	
ZIP Code	5	219	223	
Health Area	4	224	227	
Police Patrol Borough Command	1	228	228	
Police Precinct	3	229	231	
Fire Division	2	232	233	
Fire Battalion	2	234	235	
Fire Company Type	1	236	236	
Fire Company Number	3	237	239	
Community School District	2	240	241	
Atomic Polygon	3	242	244	Was Dynamic Block
Election District (ED)	3	245	247	
Assembly District (AD)	2	248	249	
Police Patrol Borough	2	250	251	
Filler	1	252	252	
Borough Code	1	253	253	
1990 Census Tract	6	254	259	
2010 Census Tract	6	260	265	
2010 Census Block	4	266	269	
2010 Census Block Suffix	1	270	270	*Not Implemented*
2000 Census Tract	6	271	276	
2000 Census Block Suffix	1	281	281	
Filler	7	282	288	Was Blockface ID. See Function 3 Extended
Neighborhood Tabulation Area (NTA)	4	289	292	

Filler	8	293	300	
RIGHT SIDE:				
COMMUNITY DISTRICT:	3	301	303	
Community District Borough Code	1	301	301	
Community District Number	2	302	303	
Low House Number	16	304	319	Display Format
High House Number	16	320	335	Display Format
Future Use	32	336	367	
Community Development Eligibility Indicator	1	368	368	
ZIP Code	5	369	373	
Health Area	4	374	377	
Police Patrol Borough Command	1	378	378	
Police Precinct	3	379	381	
Fire Division	2	382	383	
Fire Battalion	2	384	385	
Fire Company Type	1	386	386	
Fire Company Number	3	387	389	
Community School District	2	390	391	
Atomic Polygon	3	392	394	Was Dynamic Block
Election District (ED)	3	395	397	
Assembly District (AD)	2	398	399	
Police Patrol Borough	2	400	401	
Filler	1	402	402	
Borough Code	1	403	403	Internal Use
1990 Census Tract	6	404	409	
2010 Census Tract	6	410	415	
2010 Census Block	4	416	419	
2010 Census Block Suffix	1	420	420	*Not Implemented*
2000 Census Tract	6	421	426	
2000 Census Block	4	427	430	
2000 Census Block Suffix	1	431	431	
Filler	7	432	438	Was Blockface ID See Function 3 Extended
Neighborhood Tabulation Area (NTA)	4	439	442	
Filler	8	443	450	

Work Area 2 (COW) - Function 3 with Auxiliary Segment List

Street Segment Defined By 'On' and Two Cross Streets (List of Segment IDs)

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as Regular Work Area 2 for Function 3	450	1	450	
Filler	6	451	456	
Segment Count	4	457	460	Number of Segments
Segment IDs	490	461	950	Up to 70 Segment IDs 7 bytes each; 7 x 70 = 490

Work Area 2 (COW) - Function 3 Extended

Street Segment Defined By 'On' and Two Cross Streets

```
<tr>
  <td>Bike Traffic Direction</td>
  <td>2</td>
  <td>786</td>
  <td>787</td>
  <td></td>
</tr>
<tr>
  <td>Speed Limit</td>
  <td>2</td>
  <td>788</td>
  <td>789</td>
  <td></td>
</tr>
<tr>
  <td>Left PUMA Code</td>
  <td>2</td>
  <td>790</td>
  <td>794</td>
  <td></td>
</tr>
<tr>
  <td>Right PUMA Code</td>
  <td>2</td>
  <td>795</td>
  <td>799</td>
  <td></td>
</tr>
<tr>
  <td>Filler</td>
  <td>201</td>
  <td>800</td>
  <td>1000</td>
  <td></td>
</tr>
```


FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as Regular Work Area 2 Function 3	450	1	450	
List of 4 LGCs for Street 1	8	451	458	‘On’ Street
List of 4 LGCs for Street 2	8	459	466	Input Cross Street with Lower B5SC
List of 4 LGCs for Street 3	8	467	474	Input Cross Street with Higher

				B5SC
Left Health Center District	2	475	476	
Right Health Center District	2	477	478	
Filler	1	479	479	Was Split Comm Schl District Flag
Traffic Direction	1	480	480	
Roadway Type	2	481	482	
Physical ID	7	483	489	
Generic ID	7	490	496	
NYPD ID	7	497	503	
FDNY ID	7	504	510	
Street Status	1	511	511	
Street Width	3	512	514	
Street Width Irregular	1	515	515	*Not Implemented*
Bike Lane	1	516	516	Will be retired. See Bike Lane 2
Federal Classification Code	2	517	518	*Not Implemented*
Right of Way Type	1	519	519	
List of 5 Additional LGCs for Street 1	10	520	529	*Not Implemented*
Legacy ID	7	530	536	
Left NTA Name	75	537	611	
Right NTA Name	75	612	686	
FROM SPATIAL COORDINATES:	14	687	700	From Node
From X Coordinate	7	687	693	
From Y Coordinate	7	694	700	
TO SPATIAL COORDINATES:	14	701	714	To Node
To X Coordinate	7	701	707	
To Y Coordinate	7	708	714	
Latitude of From Intersection	9	715	713	
Longitude of From Intersection	11	724	734	
Latitude of To Intersection	9	735	743	
Longitude of To Intersection	11	744	754	
Left Blockface ID	10	755	764	
Right Blockface ID	10	765	774	
Number of Travel Lanes on the Street	2	775	776	
Number of Parking Lanes on the Street	2	777	778	
Number of Total Lanes on the Street	2	779	780	
Bike Lane 2	2	781	782	
Street Width Maximum	3	783	785	

Work Area 2 (COW) - Function 3 Extended with Auxiliary Segment List

Street Segment Defined by 'On' and Two Cross Streets

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as Work Area 2 for Function 3 Extended	1000	1	1000	
Filler	6	1001	1006	
Segment Count	4	1007	1010	Number of Segments
Segment IDs	490	1011	1500	Up to 70 Segment IDs 7 bytes each; 7 x 70 = 490

Work Area 2 (COW) - Function 3C

Block Face Defined by 'On' and Two Cross Streets and Compass Direction

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Internal Use	21	1	21	
Duplicate Key Flag or Continuous Parity	1	22	22	
Locational Status of Segment	1	23	23	
County Boundary Indicator	1	24	24	
DCP-Preferred LGC for Street 1	2	25	26	‘On’ Street
DCP-Preferred LGC for Street 2	2	27	28	Input Cross Street with Lower B5SC value
DCP-Preferred LGC for Street 3	2	29	30	Input Cross Street with Higher B5SC value
No. of Cross Streets at Low Addr End	1	31	31	
List of Cross Streets at Low Address End (Up to five B5SCs, 6 bytes each)	30	32	61	Blank Filled
No. of Cross Streets at High Addr End	1	62	62	
List of Cross Streets at High Address End (Up to five B5SCs, 6 bytes each)	30	63	92	Blank Filled
Cross Street Reversal Flag	1	93	93	
LION KEY	10	94	103	
LION Borough Code	1	94	94	
LION Face Code	4	95	98	

LION Sequence Number	5	99	103	
Generated Record Flag	1	104	104	
Length of Segment in Feet	5	105	109	
Segment Azimuth	3	110	112	
Segment Orientation	1	113	113	
Marble Hill/Rikers Island Alternative Borough Flag	1	114	114	
From Node	7	115	121	
To Node	7	122	128	
DSNY Snow Priority Code	1	129	129	Dept. of Sanitation
Filler	4	130	133	
Segment Identifier	7	134	140	
DOT Street Light Contractor Area	1	141	141	
Side-of-Street Indicator	1	142	142	
Curve Flag	1	143	143	
Feature Type Code	1	144	144	
Segment Type Code	1	145	145	
Coincident Segment Count	1	146	146	
Filler	4	147	150	
COMMUNITY DISTRICT:	3	151	153	
Community District Borough Code	1	151	151	
Community District Number	2	152	153	
Low House Number	16	154	169	Display Format
High House Number	16	170	185	Display Format
Future Use	32	186	217	
Community Development Eligibility Indicator	1	218	218	
ZIP Code	5	219	223	
Health Area	4	224	227	
Police Patrol Borough Command	1	228	228	
Police Precinct	3	229	231	
Fire Division	2	232	233	
Fire Battalion	2	234	235	
Fire Company Type	1	236	236	
Fire Company Number	3	237	239	
Community School District	2	240	241	
Atomic Polygon	3	242	244	Was Dynamic Block
Election District (ED)	3	245	247	
Assembly District (AD)	2	248	249	

Police Patrol Borough	2	250	251	
Filler	1	252	252	
Borough Code	1	253	253	Internal Use
1990 Census Tract	6	254	259	
2010 Census Tract	6	260	265	
2010 Census Block	4	266	269	
2010 Census Block Suffix	1	270	270	Not Implemented
2000 Census Tract	6	271	276	
2000 Census Block	4	277	280	
2000 Census Block Suffix	1	281	281	
Filler	7	282	288	Was Blockface ID See Function 3C Extended
Neighborhood Tabulation Area (NTA)	4	289	292	
Filler	8	293	300	

Work Area 2 (COW) - Function 3C with Auxiliary Segment List

Block Face Defined by 'On' and Two Cross Streets and Compass Direction

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as Regular Work Area 2 for Function 3C	**300**	**1**	**300**	
Filler	6	301	306	
Segment Count	4	307	310	Number of Segments
Segment IDs	490	311	800	Up to 70 Segment IDs; 7 bytes each 7 x 70 = 490

Work Area 2 (COW) - Function 3C Extended

Block Face Defined by 'On' Street, Two Cross Streets and Compass Direction

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as Regular Work Area 2 Function 3C	300	1	300	
List of 4 LGCs for Street 1	8	301	308	‘On’ Street
				Input Cross Street with Lower

List of 4 LGCs for Street 2	8	309	316	B5SC
List of 4 LGCs for Street 3	8	317	324	Input Cross Street with Higher B5SC
Left Health Center District	2	325	326	
Right Health Center District	2	327	328	
Filler	1	329	329	Was Split Community School District Flag
Traffic Direction	1	330	330	
Roadway Type	2	331	332	
Physical ID	7	333	339	
Generic ID	7	340	346	
NYPD ID	7	347	353	
FDNY ID	7	354	360	
Street Status	1	361	361	
Street Width	3	362	364	
Street Width Irregular	1	365	365	Not Implemented
Bike Lane	1	366	366	Will be retired See Bike Lane 2
Federal Classification Code	2	367	368	Not Implemented
Right Of Way Type	1	369	369	
List of 5 Additional LGCs for Street 1	10	370	379	Not Implemented
Legacy ID	7	380	386	
NTA Name	75	387	461	
FROM SPATIAL COORDINATES:	14	462	475	From Node
From X Coordinate	7	462	468	
From Y Coordinate	7	469	475	
TO SPATIAL COORDINATES:	14	476	489	To Node
To X Coordinate	7	476	482	
To Y Coordinate	7	483	489	
Latitude of From Intersection	9	490	498	From Node
Longitude of From Intersection	11	499	509	
Latitude of To Intersection	9	510	518	To Node
Longitude of To Intersection	11	519	529	
Blockface ID	10	530	539	
Number of Travel Lanes on the Street	2	540	541	
Number of Parking Lanes on the Street	2	542	543	
Number of Total Lanes on the Street	2	544	545	

Bike Lane 2	2	546	547	
Street Width Maximum	3	548	550	
Bike Traffic Direction	2	551	552	
Speed Limit	2	553	554	
PUMA Code	5	555	559	
Filler	291	560	850	

Work Area 2 (COW) - Function 3C Extended with Auxiliary Segment List

Street Segment Defined By 'On' Street and Two Cross Streets

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Same as Work Area 2 for Function 3C Extended	850	1	850	
Filler	6	851	856	
Segment Count	4	857	860	Number of Segments
Segment IDs	490	861	1350	Up to 70 Segment IDs 7 bytes each 7 x 70 = 490

Work Area 2 (COW) - Function 3S

Street Stretch Defined by 'On' Street and Optionally Two Cross Streets

FIELD	SIZE	POSITION		COMMENT
		FROM	TO	
Internal Use	2	1	2	
Generic/Roadbed Street Name Indicator	1	3	3	G - Generic R - Roadbed
Borough Code	1	4	4	
5-Digit Street Code of 'On' Street	5	5	9	
LGC	2	10	11	
Filler	10	12	21	Always Blank
Number of Intersections	3	22	24	Maximum of 350
LIST OF INTERSECTIONS: Variable length list of up to 350 entries; each is 55 bytes long, structured as follows:	19250	25	19274	Max. of 350 entries, each 55 bytes long: 350 x 55 = 19,250

Marble Hill/Rikers Island Flag	(1)	(1)	(1)	
Distance from previous intersection in list	(5)	(2)	(60)	
Gap Flag	(1)	(7)	(7)	
Node Number	(7)	(8)	(14)	
Number of streets at this intersection	(1)	(15)	(15)	
List of Cross Streets at this Intersection (Up to 5 B7SCs)	(40)	(16)	(55)	B7SC = B5SC + DCP Preferred LGC
* End of 55-byte entry *				
*** End of Work Area *** (19,274 bytes)				

APPENDIX 14: GEOSUPPORT COPY FILES (COW)

This appendix contains printouts of the Geosupport COW COPY files for COBOL, Assembler, PL/1, C and NATURAL. (For C, COPY files take the form of header files. For NATURAL, COPY files take the form of Local Data Areas.)

The Geosupport COPY files contain source code layouts of the Geosupport work areas. These files are stored in a COPY library that can be accessed by user application programs at compile time. Each supported programming language has an appropriate declarative statement for referencing COPY files at compile time. The Geosupport COPY files are listed in the following table.

GEOSUPPORT SYSTEM WORK AREA COPY FILES (COW)

Table 14-1: COW COPY Files for COBOL, Assembler, PL/1, C and NATURAL

COW WORK AREA	FUNCTION(S)	LENGTH (bytes)	- - - - - - - - - - - COPY File Name - - - - - - - - - - -				
			COBOL	ASSEMBLER	PL/1	C	NATURAL
WA1	All	1,200	P1COB	P1BAL	P1PL1	PAC	GEOLP1
WA2	1 & 1E (Regular WA2), 3C (Regular WA2)	300	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	2	200	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3 (Regular WA2)	450	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3 (WA2 with AUXSEG option)	950	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3C (WA2 with AUXSEG option)	800	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3 (Extended WA2)	1,000	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3C (Extended WA2)	850	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3 (Extended WA2 w/AUXSEG)	1,500	P2COB	P2BAL	P2PL1	PAC	GEOLP2
WA2	3C (Extended WA2 w/AUXSEG)	1,350	P2COB	P2BAL	P2PL1	PAC	GEOLP2

WA2	1A & BL (Regular WA2), BN (✶)	1,363	P2COB1A	P2BAL1A	P2PL11A	PAC	GEOLP21A
WA2	1A & BL (Long WA2) (✶✶) 1A & BL (TPAD Long WA2) (✶✶✶)	17,750	P2COB1AL	P2BAL1A	P2PL11AL	PAC	GEOLP2A
WA2	1A & BL & BN (Extended WA2) (✶✶✶✶)	2,800	P2COB1AL	P2BAL1A	P2PL11AL	PAC	GEOLP2A
WA2	1 & 1E (Extended WA2)	1,500	P2COB1AL	P2BAL1A	P2PL11AL	PAC	GEOLP2A
WA2	1B	4,300	P2COB1AL	P2BAL1A	P2PL11AL	PAC	GEOLP2A
WA2	3S	19,274	P2COB3S	P2BAL3S	P2PL13S	PAC	GEOLP23S
WA2	AP	1,363	P2COBAP	P2BALAP	P2PL1AP	PAC	GEOL2AP
WA2	AP (Extended WA2)	2,800	P2COBAP	P2BALAP	P2PL1AP	PAC	GEOL2AP

(✶) Functions 1A, BL and BN share a single regular WA2 layout.
(✶✶) Functions 1A and BL share a single long WA2 layout. (Function BN has no long WA2 option.).
(✶✶✶) Functions 1A and BL share a single TPAD long WA2 layout. (Function BN has no TPAD long WA2 option.).
(✶✶✶✶) Functions 1A, BL and BN share a single extended WA2 layout.

See Chapter VIII.4 for a detailed discussion of the Geosupport COPY feature.

COBOL COPY Files (COW)

P1COB COPY File

```
*****************************************************************  00010010
**** LAST UPDATED OCTOBER 2016                                 ***  00020021
**** OCT. 2016 ADDED UNIT IN INPUT AND OUTPUT V16.4            ***  00020121
**** THIS IS THE COBOL STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM ***  00021021
**** INDEPENDENT WORK AREA 1.                                  ***  00030010
**** COPY FILE - P1COB.                            04/07/98   ***  00040010
*****************************************************************  00050010
****               INPUT FIELDS                               ****  00060010
*****************************************************************  00070010
        05  PIWA1-IN-FUNC-CODE                PIC X(2).           00080010
```

```
      05  GEO-WA1-IN-FUNCTION-CODE REDEFINES PIWA1-IN-FUNC-CODE.  00090010
         10  GEO-WA1-IN-FUNCTION-1           PIC X.               00100010
         10  GEO-WA1-IN-FUNCTION-2           PIC X.               00110010
      05  PIWA1-IN-HOUSENUM-DISPLAY          PIC X(16).           00120010
      05  GEO-WA1-IN-HOUSENUM-DISPLAY REDEFINES                   00130010
          PIWA1-IN-HOUSENUM-DISPLAY.                               00140010
        10  GEO-WA1-IN-HOUSENUM              PIC X(12).           00150010
        10  FILLER                           PIC X(4).            00160010
      05  PIWA1-IN-HOUSENUM-SORT             PIC X(11).           00170010
      05  PIWA1-IN-LOW-HOUSENUM-DISPLAY      PIC X(16).           00180010
      05  GEO-WA1-IN-LO-HOUSENUM-DISPLAY REDEFINES                00190010
          PIWA1-IN-LOW-HOUSENUM-DISPLAY.                           00200010
        10  GEO-WA1-IN-LOW-HOUSENUM          PIC X(12).           00210010
        10  FILLER                           PIC X(4).            00220010
      05  PIWA1-IN-LOW-HOUSENUM-SORT         PIC X(11).           00230010
      05  GEO-WA1-IN-10SC-1.                                      00240010
        10  GEO-WA1-IN-BORO                  PIC X.               00250010
        10  PIWA1-IN-10SC-1                  PIC X(10).           00260010
      05  GEO-WA1-IN-STREET-1                PIC X(32).           00270010
      05  GEO-WA1-IN-10SC-2.                                      00280010
        10  GEO-WA1-IN-BORO-2                PIC X.               00290010
        10  PIWA1-IN-10SC-2                  PIC X(10).           00300010
      05  GEO-WA1-IN-STREET-2                PIC X(32).           00310010
      05  GEO-WA1-IN-10SC-3.                                      00320010
        10  GEO-WA1-IN-BORO-3                PIC X.               00330010
        10  PIWA1-IN-10SC-3                  PIC X(10).           00340010
      05  GEO-WA1-IN-STREET-3                PIC X(32).           00350010
      05  GEO-WA1-IN-BBL.                                         00360010
         10  GEO-WA1-IN-BL-BORO              PIC X.               00370010
         10  GEO-WA1-IN-BLOCKNUM             PIC X(5).            00380010
         10  GEO-WA1-IN-LOTNUM               PIC X(5).            00390010
      05  PIWA1-IN-BIN                       PIC X(7).            00400010
      05  GEO-WA1-IN-COMPASS.                                     00410010
        10  PIWA1-IN-COMPASS1                PIC X.               00420010
        10  PIWA1-IN-COMPASS2                PIC X.               00430010
      05  PIWA1-IN-NODE                      PIC X(7).            00440018
      05  GEO-WA1-IN-NON-IBM-MAIN-FRAME      PIC X(1).            00450010
      05  GEO-WA1-IN-ZIPIN                   PIC X(5).            00460010
      05  GEO-WA1-IN-UNIT                    PIC X(14).           00471021
      05  FILLER                             PIC X(82).           00471121
***** 05  FILLER   V16.4                     PIC X(96).           00472021
      05  GEO-WA1-IN-LONG-WORKAREA2-FLAG     PIC X.               00480010
      05  PIWA1-IN-HSE-NBR-JUSTIFY           PIC X.               00490010
      05  PIWA1-IN-HNL                       PIC X(2).            00500010
      05  PIWA1-IN-HSE-NBR-OVER-FLAG         PIC X.               00510010
```

```
        05  GEO-WA1-IN-SNL                     PIC X(2).           00520010
        05  GEO-WA1-IN-COMPACT-NAME-FLAG       PIC X.              00530010
        05  GEO-WA1-IN-XSTREET-FLAG            PIC X.              00540010
        05  PIWA1-IN-ROADBED-REQ-SWITCH        PIC X.              00550010
        05  PIWA1-IN-INTERNAL-USE-LEGACY       PIC X.              00560010
        05  PIWA1-IN-SEGAUX-SWITCH             PIC X.              00570010
        05  PIWA1-IN-BROWSE-FLAG               PIC X.              00580010
        05  PIWA1-IN-REAL-STREET-ONLY          PIC X.              00590010
        05  PIWA1-IN-TPAD-SWITCH               PIC X.              00600010
        05  PIWA1-IN-MODE-SWITCH               PIC X.              00601013
        05  PIWA1-IN-WTO-SWITCH                PIC X.              00602016
        05  FILLER                             PIC X(29).          00610017
*********************************************************************** 00620010
*****               OUTPUT FIELDS                            ***** 00630010
*********************************************************************** 00640010
        05  GEO-WA1-OUT-BORONAME               PIC X(9).           00650010
        05  PIWA1-OUT-HOUSENUM-DISPLAY         PIC X(16).          00660010
        05  GEO-WA1-OUT-HOUSENUM-DISPLAY REDEFINES                 00670010
            PIWA1-OUT-HOUSENUM-DISPLAY.                             00680010
          10  GEO-WA1-OUT-HOUSENUM             PIC X(12).          00690010
          10  FILLER                           PIC X(4).           00700010
        05  PIWA1-OUT-HOUSENUM-SORT            PIC X(11).          00710010
        05  GEO-WA1-OUT-10SC-1                 PIC X(11).          00720010
        05  GEO-WA1-OUT-STREET-1               PIC X(32).          00730010
        05  GEO-WA1-OUT-10SC-2                 PIC X(11).          00740010
        05  GEO-WA1-OUT-STREET-2               PIC X(32).          00750010
        05  GEO-WA1-OUT-10SC-3                 PIC X(11).          00760010
        05  GEO-WA1-OUT-STREET-3               PIC X(32).          00770010
        05  GEO-WA1-OUT-BBL.                                       00780010
           10  GEO-WA1-OUT-BBL-BORO            PIC X.              00790010
           10  GEO-WA1-OUT-BLOCKNUM            PIC X(5).           00800010
           10  GEO-WA1-OUT-LOTNUM              PIC X(5).           00810010
        05  PIWA1-OUT-LOW-HN-DISPLAY           PIC X(16).          00820010
        05  GEO-WA1-OUT-LOW-HN-DISPLAY REDEFINES                   00830010
            PIWA1-OUT-LOW-HN-DISPLAY.                               00840010
          10  GEO-WA1-OUT-LOW-HOUSENUM         PIC X(12).          00850012
          10  FILLER                           PIC X(4).           00860010
        05  PIWA1-OUT-LOW-HN-SORT              PIC X(11).          00870010
        05  GEO-WA1-OUT-BIN                    PIC X(7).           00880010
        05  GEO-WA1-OUT-STREET-ATTR OCCURS 3 TIMES PIC X.          00890010
        05  GEO-WA1-OUT-REASON-CODE2           PIC X.              00891013
        05  GEO-WA1-OUT-REASON-CODE-QUAL-2     PIC X.              00891115
        05  GEO-WA1-OUT-WARNING-CODE2          PIC XX.             00893013
        05  GEO-WA1-OUT-RETURN-CODE2.                              00894013
           10  GEO-WA1-OUT-RC2-1               PIC X.              00895013
```

```
          10  GEO-WA1-OUT-RC2-2              PIC X.              00896013
       05  GEO-WA1-OUT-ERROR-MESSAGE2        PIC X(80).          00897013
       05  PIWA1-OUT-NODE                    PIC X(7).           00899019
       05  PIWA1-OUT-UNIT-SORT.                                  00899122
          10  PIWA1-OUT-UNIT-TYPE            PIC X(4).           00899221
          10  PIWA1-OUT-UNIT-ID              PIC X(10).          00899321
       05  PIWA1-OUT-UNIT-DISP               PIC X(14).          00899421
       05  FILLER                            PIC X(17).          00900021
  ***** 05  FILLER   V16.4                   PIC X(45).          00901021
       05  GEO-WA1-OUT-SND-ATTR              PIC X.              00910010
       05  GEO-WA1-OUT-REASON-CODE           PIC X.              00920010
       05  GEO-WA1-OUT-REASON-CODE-QUAL      PIC X.              00921014
       05  GEO-WA1-OUT-WARNING-CODE          PIC XX.             00940010
       05  GEO-WA1-OUT-RETURN-CODE.                              00950010
          10  GEO-WA1-OUT-RC-1               PIC X.              00960010
          10  GEO-WA1-OUT-RC-2               PIC X.              00970010
       05  GEO-WA1-OUT-ERROR-MESSAGE         PIC X(80).          00980010
       05  PIWA1-OUT-NUM-SIMILAR-STRS        PIC X(2).           00990010
       05  PIWA1-OUT-SIMILAR-B7SC            PIC X(8)            01000010
                        OCCURS 10 TIMES.                       01010010
       05  GEO-WA1-OUT-SIMILAR-NAMES         PIC X(32)           01020010
                        OCCURS 10 TIMES.                       01030010
```

P2COB COPY File

```
*****************************************************************  00010032
****                    P2COB                                 **  00011082
****          LAST MODIFIED DECEMBER 2016                     **  00012082
**** ADD NEW 5 BYTE PUMA CODE                YNL 12/17 V18,1   **  00014085
**** ADD NEW 2 BYTE SPEED LIMIT              YNL 09/17 V17,4   **  00014185
**** ADD NEW 2 BYTE BIKE TRAFFIC DIRECTION   YNL 12/16 V17,1   **  00015084
**** THIS IS THE COBOL- STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM**  00020032
**** INDEPENDENT WORK AREA 2 FOR FUNCTIONS: 1, 1E, 2, 2C, 3,    **  00030032
**** 3C, AND 5.                                                 **  00040032
****                                                            **  00050032
**** COPY FILE - P2COB.                                         **  00060032
**** PLEASE NOTE THAT FUNCTIONS 1 AND 1E SHARE A SINGLE         **  00070032
**** WORK AREA 2 LAYOUT, AND FUNCTIONS 2 AND 2C ALSO            **  00080032
**** SHARE A SINGLE WORK AREA 2 LAYOUT.             04/03/01    **  00090032
*****************************************************************  00100032
****              LAST MODIFIED FEBRUARY 2016                   **  00110078
*****************************************************************  00120032
                                                                   00130032
       05  PIWA2                             PIC X(7000).        00140066
```

```
                                                                  00150032
*****************************************************************  00160032
****     FOR: FUNCTIONS 1 & 1E      ******************************  00170032
                                                                  00180032
       05  PIWA2-FUNCTION1   REDEFINES PIWA2.                     00190032
          10  GEO-WA2-FN1-ACCESS-KEY          PIC X(21).          00200032
          10  GEO-WA2-FN1-CONT-PARITY         PIC X.              00210032
          10  PIWA2-FN1-LOW-HOUSENUM-SORT     PIC X(11).          00220032
          10  PIWA2-FN1-HI-HOUSENUM-SORT      PIC X(11).          00230032
          10  GEO-WA2-FN1-PREFERRED-LGC       PIC X(2).           00240032
          10  GEO-WA2-FN1-NUM-X-ST-LOW-END    PIC X.              00250032
          10  PIWA2-FN1-LOW-B5SC              PIC X(6)            00260032
                                                OCCURS 5 TIMES.    00270032
          10  GEO-WA2-FN1-NUM-X-ST-HI-END      PIC X.             00280032
          10  PIWA2-FN1-HI-B5SC               PIC X(6)            00290032
                                                OCCURS 5 TIMES.    00300032
          10  PIWA2-FN1-LIONKEY.                                  00310032
              15  PIWA2-FN1-LION-BORO         PIC X.              00320032
              15  GEO-WA2-FN1-LIONFACECODE    PIC X(4).           00330032
              15  GEO-WA2-FN1-LIONSEQ         PIC X(5).           00340032
          10  GEO-WA2-FN1-SPECIAL-ADDR-FLAG   PIC X(1).           00350032
          10  PIWA2-FN1-SIDE-OF-STR           PIC X.              00360032
          10  GEO-WA2-FN1-SEGMENTLENGTH       PIC X(5).           00370032
          10  GEO-WA2-FN1-XCOORD              PIC X(7).           00380032
          10  GEO-WA2-FN1-YCOORD              PIC X(7).           00390032
          10  FILLER-GSS                      PIC X(8).           00400032
          10  GEO-WA2-FN1-MARBLE-RIKER-FLAG   PIC X(1).           00410032
          10  GEO-WA2-FN1-SLA                 PIC X.              00420032
          10  GEO-WA2-FN1-COMDIST.                                00430032
              15  GEO-WA2-FN1-COMDIST-BORO    PIC X(1).           00440032
              15  GEO-WA2-FN1-COMDIST-NUMBER  PIC X(2).           00450032
          10  GEO-WA2-FN1-ZIP                 PIC X(5).           00460032
                                                                  00470032
 ***  THE FN1E FIELDS ARE VALID ONLY FOR FUNCTION 1E, NOT FUNC 1.** 00480032
          10  GEO-WA2-FN1E-ELECTDIST          PIC X(3).           00490032
          10  GEO-WA2-FN1E-ASSEMDIST          PIC X(2).           00500032
          10  GEO-WA2-FN1E-SPLIT-ED-FLAG      PIC X(1).           00510032
          10  GEO-WA2-FN1E-CONGDIST           PIC X(2).           00520032
          10  GEO-WA2-FN1E-SENATEDIST         PIC X(2).           00530032
          10  GEO-WA2-FN1E-COURTDIST          PIC X(2).           00540032
          10  GEO-WA2-FN1E-COUNCILDIST        PIC X(2).           00550032
                                                                  00560032
          10  GEO-WA2-FN1-HCD                 PIC X(2).           00570053
          10  GEO-WA2-FN1-HEALTHAREA          PIC X(4).           00580053
          10  GEO-WA2-FN1-SANIDIST.                               00590032
```

```
            15  GEO-WA2-FN1-SANIDIST-BORO   PIC X(1).            00600032
            15  GEO-WA2-FN1-SANIDIST-NUMBER PIC X(2).            00610032
        10  GEO-WA2-FN1-SANITATION-SUBSEC   PIC X(2).            00620032
        10  GEO-WA2-FN1-SANI-REG            PIC X(5).            00630032
        10  GEO-WA2-FN1-SANI-REC            PIC X(3).            00640032
        10  GEO-WA2-FN1-POLICEDIST.                              00650032
           15 GEO-WA2-FN1-POL-PATR-BORO-CMD PIC X(1).            00660032
           15 GEO-WA2-FN1-POL-PRECINCT      PIC X(3).            00670032
** NOTE:10  GEO-WA2-FN1-FIRESEC ==> FIRE DIVISION **             00680032
        10  GEO-WA2-FN1-FIRESEC             PIC X(2).            00690032
        10  GEO-WA2-FN1-FIREBAT             PIC X(2).            00700032
        10  GEO-WA2-FN1-FIRECO.                                  00710032
            15  GEO-WA2-FN1-FIRECO-TYPE     PIC X(1).            00720032
            15  GEO-WA2-FN1-FIRECO-NUM      PIC X(3).            00730032
***     NEXT LINE WAS PREVIOUSLY SPLIT SCHOOL FLAG               00731044
        10  GEO-WA2-FN1-FILL-SCHOOL-FLAG    PIC X.               00740044
        10  GEO-WA2-FN1-SCHOOLDIST          PIC X(2).            00750032
        10  GEO-WA2-FN1-DYN-BLOCK           PIC X(3).            00760032
        10  PIWA2-FN1-POLICE-PAT-BORO       PIC X(2).            00770073
        10  GEO-WA2-FN1-FEATURE-TYPE        PIC X.               00790032
        10  GEO-WA2-FN1-SEGMENT-TYPE        PIC X.               00800032
        10  GEO-WA2-FN1-ALX                 PIC X.               00810032
        10  GEO-WA2-FN1-COINCIDENT-CNT      PIC X.               00820032
        10  FILLER                          PIC X(2).            00830058
        10  PIWA2-FN1-CENS-TRCT-BORO        PIC X.               00840158
        10  GEO-WA2-FN1-1990-CENSUSTRACT    PIC X(6).            00841058
        10  GEO-WA2-FN1-2010-CENS-TRCT      PIC X(6).            00850035
        10  GEO-WA2-FN1-2010-CENS-BLK       PIC X(4).            00860035
        10  GEO-WA2-FN1-2010-CENS-BLK-SFX   PIC X.               00870035
        10  GEO-WA2-FN1-2000-CENS-TRACT     PIC X(6).            00890035
        10  GEO-WA2-FN1-2000-CENS-BLOCK     PIC X(4).            00900035
        10  GEO-WA2-FN1-2000-CENS-BLK-SUF   PIC X.               00910035
        10  GEO-WA2-FN1-NTA                 PIC X(4).            00911050
        10  GEO-WA2-FN1-SANIT-SNOW-PRRTY    PIC X.               00912050
        10  PIWA2-FN1-SANIT-ORGANICS        PIC X(5).            00922061
        10  PIWA2-FN1-SANIT-BULK-PICK-UP    PIC X(5).            00924080
**V16.4 10  PIWA2-FN1-SANIT-RESERVED        PIC X(5).            00924180
        10  PIWA2-FN1-HURRICANE-ZONE        PIC XX.              00925072
        10  FILLER                          PIC X(11).           00926072
        10  GEO-WA2-FN1-TRUE-HNS            PIC X(11).           00930032
        10  GEO-WA2-FN1-TRUE-B7SC           PIC X(8).            00940032
        10  GEO-WA2-FN1-SEG-ID              PIC X(7).            00950032
        10  GEO-WA2-FN1-CURVE-FLAG          PIC X(1).            00960032
                                                                  00970032
*****************************************************************  00980032
```

```
****     FOR: FUNCTIONS 2       **********************************   00990032
                                                                     01000032
       05  PIWA2-FUNCTION2   REDEFINES PIWA2.                        01010032
          10  PIWA2-FN2-ACCESS-KEY            PIC X(21).            01020032
          10  GEO-WA2-FN2-DUPINTERFLAG        PIC X.                01030032
          10  GEO-WA2-FN2-PREFERRED-LGC1      PIC X(2).             01040032
          10  GEO-WA2-FN2-PREFERRED-LGC2      PIC X(2).             01050032
          10  GEO-WA2-FN2-NUM-OF-INTERSECTS   PIC X.                01060032
          10  PIWA2-FN2-INTERSECT-B5SC        PIC X(6)              01070032
                                               OCCURS 5 TIMES.       01080032
          10  GEO-WA2-FN2-COMPDIR             PIC X.                01090032
          10  GEO-WA2-FN2-ATOMIC-POLYGON      PIC X(3).             01091064
          10  FILLER                          PIC X(2).             01100057
          10  GEO-WA2-FN2-NODE-NUM            PIC X(7).             01110032
          10  GEO-WA2-FN2-XCOORD              PIC X(7).             01120032
          10  GEO-WA2-FN2-YCOORD              PIC X(7).             01130032
          10  FILLER-GSS                      PIC X(7).             01140032
          10  GEO-WA2-FN2-SANBORN1-BVOLPAGE.                        01150032
             15 GEO-WA2-FN2-SANBORN1-BORO     PIC X(1).             01160032
             15 GEO-WA2-FN2-SANBORN1-VOL-NUM  PIC X(3).             01170032
             15 GEO-WA2-FN2-SANBORN1-PAGE-NUM PIC X(4).             01180032
          10  GEO-WA2-FN2-SANBORN2-BVOLPAGE.                        01190032
             15 GEO-WA2-FN2-SANBORN2-BORO     PIC X(1).             01200032
             15 GEO-WA2-FN2-SANBORN2-VOL-NUM  PIC X(3).             01210032
             15 GEO-WA2-FN2-SANBORN2-PAGE-NUM PIC X(4).             01220032
          10  GEO-WA2-FN2-MARBLE-RIKER-FLAG   PIC X(1).             01230032
          10  GEO-WA2-FN2-SLA                   PIC X.              01240032
          10  GEO-WA2-FN2-COMDIST.                                  01250032
              15  GEO-WA2-FN2-COMDIST-BORO    PIC X(1).             01260032
              15  GEO-WA2-FN2-COMDIST-NUMBER  PIC X(2).             01270032
          10  GEO-WA2-FN2-ZIP                 PIC X(5).             01280032
          10  GEO-WA2-FN2-HEALTHAREA          PIC X(4).             01290053
          10  GEO-WA2-FN2-POLICEDIST.                               01300032
             15 GEO-WA2-FN2-POL-PATR-BORO-CMD PIC X(1).             01310032
             15 GEO-WA2-FN2-POL-PRECINCT      PIC X(3).             01320032
   ** NOTE:10  GEO-WA2-FN2-FIRESEC ==> FIRE DIVISION **              01330032
          10  GEO-WA2-FN2-FIRESEC             PIC X(2).             01340032
          10  GEO-WA2-FN2-FIREBAT             PIC X(2).             01350032
          10  GEO-WA2-FN2-FIRECO.                                   01360032
              15  GEO-WA2-FN2-FIRECO-TYPE     PIC X(1).             01370032
              15  GEO-WA2-FN2-FIRECO-NUM      PIC X(3).             01380032
          10  GEO-WA2-FN2-SCHOOLDIST          PIC X(2).             01390032
          10  GEO-WA2-FN2-2010-CENS-TRCT      PIC X(6).             01400035
          10  GEO-WA2-FN2-1990-CENSUSTRACT    PIC X(6).             01410032
          10  GEO-WA2-FN2-LEVEL-LIST OCCURS 5 TIMES.                01420032
```

```
            15 GEO-WA2-FN2-LEVEL-CODES                          01430032
               OCCURS 2 TIMES              PIC X.                01440032
         10  PIWA2-FN2-POLICE-PAT-BORO      PIC X(2).            01470073
         10  GEO-WA2-FN2-ASSEMDIST          PIC X(2).            01471073
         10  GEO-WA2-FN2-CONGDIST           PIC X(2).            01480032
         10  GEO-WA2-FN2-SENATEDIST         PIC X(2).            01490032
         10  GEO-WA2-FN2-COURTDIST          PIC X(2).            01500032
         10  GEO-WA2-FN2-COUNCILDIST        PIC X(2).            01510032
         10  GEO-WA2-FN2-CDELIG             PIC X(1).            01520032
         10  GEO-WA2-FN2-DUP-INT-DISTANCE   PIC X(5).            01530032
         10  GEO-WA2-FN2-2000-CENS-TRACT    PIC X(6).            01550035
         10  PIWA2-FN2-HCD                  PIC X(2).            01551053
         10  PIWA2-FN2-SANITATION-DIST      PIC X(3).            01552045
         10  PIWA2-FN2-SANITATION-SUBSEC    PIC X(2).            01553047
         10  FILLER                         PIC X(12).           01560047
                                                                  01561059
*****************************************************************  01562059
****     FOR: FUNCTIONS 2W      ********************************  01563065
                                                                  01564059
       05  PIWA2-FUNCTION2W  REDEFINES PIWA2.                     01565065
         10  PIWA2-2W-ACCESS-KEY            PIC X(21).           01566065
         10  GEO-WA2-2W-DUPINTERFLAG        PIC X.               01567065
         10  GEO-WA2-2W-PREFERRED-LGC1      PIC X(2).            01568065
         10  GEO-WA2-2W-PREFERRED-LGC2      PIC X(2).            01569065
         10  GEO-WA2-2W-NUM-OF-INTERSECTS   PIC X.               01569165
         10  PIWA2-2W-INTERSECT-B5SC        PIC X(6)             01569265
                                            OCCURS 5 TIMES.      01569359
         10  GEO-WA2-2W-COMPDIR             PIC X.               01569465
         10  GEO-WA2-2W-ATOMIC-POLYGON      PIC X(3).            01569565
         10  FILLER                         PIC X(2).            01569659
         10  GEO-WA2-2W-NODE-NUM            PIC X(7).            01569765
         10  GEO-WA2-2W-XCOORD              PIC X(7).            01569865
         10  GEO-WA2-2W-YCOORD              PIC X(7).            01569965
         10  FILLER-GSS                     PIC X(7).            01570059
         10  GEO-WA2-2W-SANBORN1-BVOLPAGE.                       01570165
            15 GEO-WA2-2W-SANBORN1-BORO     PIC X(1).            01570265
            15 GEO-WA2-2W-SANBORN1-VOL-NUM  PIC X(3).            01570365
            15 GEO-WA2-2W-SANBORN1-PAGE-NUM PIC X(4).            01570465
         10  GEO-WA2-2W-SANBORN2-BVOLPAGE.                       01570565
            15 GEO-WA2-2W-SANBORN2-BORO     PIC X(1).            01570665
            15 GEO-WA2-2W-SANBORN2-VOL-NUM  PIC X(3).            01570765
            15 GEO-WA2-2W-SANBORN2-PAGE-NUM PIC X(4).            01570865
         10  GEO-WA2-2W-MARBLE-RIKER-FLAG   PIC X(1).            01570965
         10  GEO-WA2-2W-SLA                   PIC X.             01571065
         10  GEO-WA2-2W-COMDIST.                                 01571165
```

```
            15  GEO-WA2-2W-COMDIST-BORO     PIC X(1).            01571265
            15  GEO-WA2-2W-COMDIST-NUMBER   PIC X(2).            01571365
        10  GEO-WA2-2W-ZIP                  PIC X(5).            01571465
        10  GEO-WA2-2W-HEALTHAREA           PIC X(4).            01571565
        10  GEO-WA2-2W-POLICEDIST.                               01571665
           15 GEO-WA2-2W-POL-PATR-BORO-CMD PIC X(1).             01571765
           15 GEO-WA2-2W-POL-PRECINCT       PIC X(3).            01571865
** NOTE:10  GEO-WA2-2W-FIRESEC ==> FIRE DIVISION **               01571965
        10  GEO-WA2-2W-FIRESEC              PIC X(2).            01572065
        10  GEO-WA2-2W-FIREBAT              PIC X(2).            01572165
        10  GEO-WA2-2W-FIRECO.                                   01572265
            15  GEO-WA2-2W-FIRECO-TYPE      PIC X(1).            01572365
            15  GEO-WA2-2W-FIRECO-NUM       PIC X(3).            01572465
        10  GEO-WA2-2W-SCHOOLDIST           PIC X(2).            01572565
        10  GEO-WA2-2W-2010-CENS-TRCT       PIC X(6).            01572665
        10  GEO-WA2-2W-1990-CENSUSTRACT     PIC X(6).            01572765
        10  GEO-WA2-2W-LEVEL-LIST OCCURS 5 TIMES.                01572865
            15 GEO-WA2-2W-LEVEL-CODES                            01572965
               OCCURS 2 TIMES               PIC X.               01573059
        10  PIWA2-2W-POLICE-PAT-BORO        PIC X(2).            01573373
        10  GEO-WA2-2W-ASSEMDIST            PIC X(2).            01573473
        10  GEO-WA2-2W-CONGDIST             PIC X(2).            01573573
        10  GEO-WA2-2W-SENATEDIST           PIC X(2).            01573673
        10  GEO-WA2-2W-COURTDIST            PIC X(2).            01573773
        10  GEO-WA2-2W-COUNCILDIST          PIC X(2).            01573873
        10  GEO-WA2-2W-CDELIG               PIC X(1).            01573973
        10  GEO-WA2-2W-DUP-INT-DISTANCE     PIC X(5).            01574073
        10  GEO-WA2-2W-2000-CENS-TRACT      PIC X(6).            01574173
        10  PIWA2-2W-HCD                    PIC X(2).            01574273
        10  PIWA2-2W-SANITATION-DIST        PIC X(3).            01574373
        10  PIWA2-2W-SANITATION-SUBSEC      PIC X(2).            01574473
        10  FILLER                          PIC X(12).           01574573
        10  FILLER                          PIC X(22).           01574673
        10  PIWA2-2W-LGCS-1                 PIC X(8).            01574773
        10  PIWA2-2W-LGCS-2                 PIC X(8).            01574873
        10  PIWA2-2W-TURN-RESTRICTIONS      PIC X(10).           01574965
        10  PIWA2-2W-LGCS-FOR-B5SCS         PIC X(2)             01575065
                                             OCCURS 5 TIMES.      01575160
        10  PIWA2-2W-TRUE-REP-COUNTER       PIC XX.              01575265
        10  PIWA2-2W-NODE-LIST              PIC X(7)             01575365
                                             OCCURS 20 TIMES.     01575463
        10 PIWA2-2W-NODE-LIST-B7SCS-LIST     OCCURS 20 TIMES.     01575771
         15 PIWA2-2W-NODE-LIST-B7SCS         OCCURS 5  TIMES.     01575871
          20 PIWA2-2W-NODE-LIST-B7SC         PIC X(8)             01575971
                                             OCCURS 4 TIMES.      01576067
```

```
          10  PIWA2-2W-REASON-CODE            PIC X.                01585471
          10  PIWA2-2W-REASON-CODE-QUAL       PIC X.                01585571
          10  PIWA2-2W-WARN-CODE              PIC XX.               01585671
          10  PIWA2-2W-RETURN-CODE            PIC XX.               01585771
          10  PIWA2-2W-LATITUDE               PIC X(9).             01585874
          10  PIWA2-2W-LONGITUDE              PIC X(11).            01585974
          10  FILLER                          PIC X(374).           01586474
   ****   10  FILLER  V15.3                   PIC X(394).           01586574
                                                                     01586674
*****************************************************************   01587065
****     FOR: FUNCTION  3           ******************************   01590032
                                                                     01600032
       05  PIWA2-FUNCTION3   REDEFINES PIWA2.                        01610032
          10  GEO-WA2-FN3-ACCESS-KEY          PIC X(21).            01620032
          10  GEO-WA2-FN3-DUP-KEY-FLAG        PIC X.                01630032
          10  GEO-WA2-FN3-LOCATION-STATUS     PIC X.                01640032
          10  GEO-WA2-FN3-COUNTY-BOUNDARY     PIC X.                01650032
          10  GEO-WA2-FN3-PREFERRED-LGC1      PIC X(2).             01660032
          10  GEO-WA2-FN3-PREFERRED-LGC2      PIC X(2).             01670032
          10  GEO-WA2-FN3-PREFERRED-LGC3      PIC X(2).             01680032
          10  GEO-WA2-FN3-NUM-X-ST-LOW-END    PIC X.                01690032
          10  PIWA2-FN3-LOW-B5SC              PIC X(6)              01700032
                                                OCCURS 5 TIMES.      01710032
          10  GEO-WA2-FN3-NUM-X-ST-HI-END     PIC X.                01720032
          10  PIWA2-FN3-HI-B5SC               PIC X(6)              01730032
                                                OCCURS 5 TIMES.      01740032
          10  GEO-WA2-FN3-REVERSALFLAG        PIC X.                01750032
          10  PIWA2-FN3-LIONKEY.                                    01760032
              15  PIWA2-FN3-LION-BORO         PIC X.                01770032
              15  GEO-WA2-FN3-LIONFACECODE    PIC X(4).             01780032
              15  GEO-WA2-FN3-LIONSEQ         PIC X(5).             01790032
          10  GEO-WA2-FN3-GENRECFLAG          PIC X.                01800032
          10  PIWA2-FN3-SEG-LEN               PIC X(5).             01810032
          10  GEO-WA2-FN3-SEGMENTSLOPE        PIC X(3).             01820032
          10  GEO-WA2-FN3-SEGMENTORIENT       PIC X.                01830032
          10  GEO-WA2-FN3-MARBLE-RIKER-FLAG   PIC X(1).             01840032
          10  GEO-WA2-FN3-FROM-NODE           PIC X(7).             01850032
          10  GEO-WA2-FN3-TO-NODE             PIC X(7).             01860032
          10  GEO-WA2-FN3-SANIT-SNOW-PRRTY    PIC X.                01861050
          10  FILLER                          PIC X(4).             01870050
          10  GEO-WA2-FN3-SEG-ID              PIC X(7).             01880032
          10  GEO-WA2-FN3-SLA                 PIC X.                01890032
          10  GEO-WA2-FN3-CURVE-FLAG          PIC X.                01900032
          10  GEO-WA2-FN3-DOG-LEG             PIC X.                01910032
          10  GEO-WA2-FN3-FEATURE-TYPE        PIC X.                01920032
```

```
        10  GEO-WA2-FN3-SEGMENT-TYPE        PIC X.                01930032
        10  GEO-WA2-FN3-COINCIDENT-CNT      PIC X.                01940032
        10  FILLER                          PIC X(4).             01950032
        10  PIWA2-FN3-LEFT-SIDE-OF-STR.                           01960032
            15  GEO-WA2-FN3-LEFT-COMDIST.                         01970032
              20  GEO-WA2-FN3-LEFT-COMDIST-BORO PIC X(1).         01980032
              20  GEO-WA2-FN3-LEFT-COMDIST-NUM  PIC X(2).         01990032
            15  PIWA2-FN3-L-LOW-HOUSENUM        PIC X(16).        02000032
            15  PIWA2-FN3-L-HI-HOUSENUM         PIC X(16).        02010032
            15  FILLER-GSS                      PIC X(33).        02020032
            15  GEO-WA2-FN3-LEFT-ZIP            PIC X(5).         02030032
            15  GEO-WA2-FN3-LEFT-HEALTHAREA     PIC X(4).         02040053
            15  GEO-WA2-FN3-LEFT-POLDIST.                         02050032
             20  GEO-WA2-FN3-L-POL-PATR-BOR-CMD PIC X(1).         02060032
             20  GEO-WA2-FN3-L-POL-PRECINCT     PIC X(3).         02070032
** NOTE:10  GEO-WA2-3L-R-FIRESEC ==> FIRE DIV **                   02080032
            15  GEO-WA2-3L-L-FIRESEC            PIC X(2).         02090032
            15  GEO-WA2-3L-L-FIREBAT            PIC X(2).         02100032
            15  GEO-WA2-3L-L-FIRECO.                              02110032
                20  GEO-WA2-3L-L-FIRECO-TYPE    PIC X(1).         02120032
                20  GEO-WA2-3L-L-FIRECO-NUM     PIC X(3).         02130032
            15  GEO-WA2-FN3-LEFT-SCHLDIST       PIC X(2).         02140032
            15  GEO-WA2-3L-L-DYN-BLOCK          PIC X(3).         02150032
            15  PIWA2-FN3-L-ED                  PIC X(3).         02161036
            15  PIWA2-FN3-L-AD                  PIC X(2).         02162036
            15  PIWA2-FN3-L-POLICE-PAT-BORO     PIC X(2).         02163073
            15  FILLER                          PIC X.            02170073
            15  GEO-WA2-3L-L-BORO               PIC X .           02190051
            15  GEO-WA2-3L-L-1990-CENSUSTRACT   PIC X(6) .        02191051
            15  GEO-WA2-3L-L-2010-CENS-TRCT     PIC X(6).         02200035
            15  GEO-WA2-3L-L-2010-CENS-BLK      PIC X(4).         02210035
            15  GEO-WA2-3L-L-2010-CENS-BLK-SFX  PIC X.            02220035
            15  GEO-WA2-3L-L-2000-CENS-TRACT    PIC X(6).         02240035
            15  GEO-WA2-3L-L-2000-CENS-BLOCK    PIC X(4).         02250035
            15  GEO-WA2-3L-L-2000-CENS-BLK-SUF  PIC X.            02260035
            15  FILLER                          PIC X(7).         02260176
****        15  PIWA2-FN3-L-BLOCKFACE-ID *V16.1*PIC X(7)**        02261076
            15  PIWA2-FN3-L-NTA                 PIC X(4).         02261150
            15  FILLER                          PIC X(8).         02270050
        10  PIWA2-FN3-RIGHT-SIDE-OF-STR.                           02280032
            15  GEO-WA2-FN3-RIGHT-COMDIST.                        02290032
              20 GEO-WA2-FN3-RIGHT-COMDIST-BORO PIC X(1).         02300032
              20 GEO-WA2-FN3-RIGHT-COMDIST-NUM  PIC X(2).         02310032
            15  PIWA2-FN3-R-LOW-HOUSENUM        PIC X(16).        02320032
            15  PIWA2-FN3-R-HI-HOUSENUM         PIC X(16).        02330032
```

```
            15  FILLER-GSS                      PIC X(33).        02340032
            15  GEO-WA2-FN3-RIGHT-ZIP           PIC X(5).         02350032
            15  GEO-WA2-FN3-RIGHT-HEALTHAREA    PIC X(4).         02360053
            15  GEO-WA2-FN3-RIGHT-POLDIST.                        02370032
             20 GEO-WA2-FN3-R-POL-PATR-BOR-CMD  PIC X(1).         02380032
             20 GEO-WA2-FN3-R-POL-PRECINCT      PIC X(3).         02390032
            15  GEO-WA2-3L-R-FIRESEC            PIC X(2).         02400032
            15  GEO-WA2-3L-R-FIREBAT            PIC X(2).         02410032
            15  GEO-WA2-3L-R-FIRECO.                              02420032
                20  GEO-WA2-3L-R-FIRECO-TYPE    PIC X(1).         02430032
                20  GEO-WA2-3L-R-FIRECO-NUM     PIC X(3).         02440032
            15  GEO-WA2-FN3-RIGHT-SCHLDIST      PIC X(2).         02450032
            15  GEO-WA2-3L-R-DYN-BLOCK          PIC X(3).         02460032
            15  PIWA2-FN3-R-ED                  PIC X(3).         02471036
            15  PIWA2-FN3-R-AD                  PIC X(2).         02472036
            15  PIWA2-FN3-R-POLICE-PAT-BORO     PIC X(2).         02473073
            15  FILLER                          PIC X.            02490073
            15  GEO-WA2-3L-R-BORO               PIC X.            02500051
            15  GEO-WA2-3L-R-1990-CENSUSTRACT   PIC X(6).         02501051
            15  GEO-WA2-3L-R-2010-CENS-TRCT     PIC X(6).         02510035
            15  GEO-WA2-3L-R-2010-CENS-BLK      PIC X(4).         02520035
            15  GEO-WA2-3L-R-2010-CENS-BLK-SFX  PIC X.            02530035
            15  GEO-WA2-3L-R-2000-CENS-TRACT    PIC X(6).         02550035
            15  GEO-WA2-3L-R-2000-CENS-BLOCK    PIC X(4).         02560035
            15  GEO-WA2-3L-R-2000-CENS-BLK-SUF  PIC X.            02570035
            15  FILLER                          PIC X(7).         02570176
  ****      15  PIWA2-FN3-R-BLOCKFACE-ID *V16.1*PIC X(7)**        02570276
            15  PIWA2-FN3-R-NTA                 PIC X(4).         02572050
            15  FILLER                          PIC X(8).         02580050
                                                                   02590032
      05  PIWA2-AUX-FUNCTION3 REDEFINES PIWA2.                     02600032
         10  FILLER                             PIC X(450).       02610032
         10  PIWA2-FN3-SEGAUX.                                     02620032
            15  PIWA2-FN3-SEGAUX-FILL           PIC X(6).         02630032
            15  PIWA2-FN3-SEGAUX-CTR            PIC X(4).         02640032
            15  PIWA2-FN3-SEGAUX-SEGS OCCURS 70 TIMES             02650032
                                                PIC X(7).         02660032
                                                                   02670032
*****************************************************************  02670136
****     FOR: FUNCTION  3 EXTENDED  ****************************   02671036
                                                                   02672036
      05  PIWA2-FUNCTION3X  REDEFINES PIWA2.                       02673036
         10  PIWA2-3X-ACCESS-KEY            PIC X(21).             02674042
         10  PIWA2-3X-DUP-KEY-FLAG          PIC X.                 02675042
         10  PIWA2-3X-LOCATION-STATUS       PIC X.                 02676042
```

```
        10  PIWA2-3X-COUNTY-BOUNDARY        PIC X.                 02677042
        10  PIWA2-3X-PREFERRED-LGC1         PIC X(2).              02678042
        10  PIWA2-3X-PREFERRED-LGC2         PIC X(2).              02679042
        10  PIWA2-3X-PREFERRED-LGC3         PIC X(2).              02679142
        10  PIWA2-3X-NUM-X-ST-LOW-END       PIC X.                 02679242
        10  PIWA2-3X-LOW-B5SC               PIC X(6)               02679338
                                              OCCURS 5 TIMES.       02679436
        10  PIWA2-3X-NUM-X-ST-HI-END        PIC X.                 02679542
        10  PIWA2-3X-HI-B5SC                PIC X(6)               02679638
                                              OCCURS 5 TIMES.       02679736
        10  PIWA2-3X-REVERSALFLAG           PIC X.                 02679842
        10  PIWA2-3X-LIONKEY.                                      02679938
            15  PIWA2-3X-LION-BORO          PIC X.                 02680038
            15  PIWA2-3X-LIONFACECODE       PIC X(4).              02680142
            15  PIWA2-3X-LIONSEQ            PIC X(5).              02680242
        10  PIWA2-3X-GENRECFLAG             PIC X.                 02680342
        10  PIWA2-3X-SEG-LEN                PIC X(5).              02680438
        10  PIWA2-3X-SEGMENTSLOPE           PIC X(3).              02680542
        10  PIWA2-3X-SEGMENTORIENT          PIC X.                 02680642
        10  PIWA2-3X-MARBLE-RIKER-FLAG      PIC X(1).              02680742
        10  PIWA2-3X-FROM-NODE              PIC X(7).              02680842
        10  PIWA2-3X-TO-NODE                PIC X(7).              02680942
        10  PIWA2-3X-SANIT-SNOW-PRRTY       PIC X.                 02681050
        10  FILLER                          PIC X(4).              02681150
        10  PIWA2-3X-SEG-ID                 PIC X(7).              02681250
        10  PIWA2-3X-SLA                    PIC X.                 02681350
        10  PIWA2-3X-CURVE-FLAG             PIC X.                 02681450
        10  PIWA2-3X-DOG-LEG                PIC X.                 02681550
        10  PIWA2-3X-FEATURE-TYPE           PIC X.                 02681650
        10  PIWA2-3X-SEGMENT-TYPE           PIC X.                 02681750
        10  PIWA2-3X-COINCIDENT-CNT         PIC X.                 02681850
        10  FILLER                          PIC X(4).              02681950
        10  PIWA2-3X-LEFT-SIDE-OF-STR.                             02682050
            15  PIWA2-3X-LEFT-COMDIST.                             02682150
              20  PIWA2-3X-LEFT-COMDIST-BORO    PIC X(1).          02682250
              20  PIWA2-3X-LEFT-COMDIST-NUM     PIC  X(2).         02682350
            15  PIWA2-3X-L-LOW-HOUSENUM         PIC X(16).         02682450
            15  PIWA2-3X-L-HI-HOUSENUM          PIC X(16).         02682550
            15  FILLER-GSS                      PIC X(33).         02682650
            15  PIWA2-3X-LEFT-ZIP               PIC X(5).          02682750
            15  PIWA2-3X-LEFT-HEALTHAREA        PIC X(4).          02682853
            15  PIWA2-3X-LEFT-POLDIST.                             02682950
             20  PIWA2-3X-L-POL-PATR-BOR-CMD    PIC X(1).          02683050
             20  PIWA2-3X-L-POL-PRECINCT        PIC X(3).          02683150
** NOTE:10  PIWA2-3XL-R-FIRESEC ==> FIRE DIV **                    02683250
```

```
            15  PIWA2-3X-L-FIRESEC              PIC X(2).         02683350
            15  PIWA2-3X-L-FIREBAT              PIC X(2).         02683450
            15  PIWA2-3X-L-FIRECO.                                02683550
                20  PIWA2-3X-L-FIRECO-TYPE      PIC X(1).         02683650
                20  PIWA2-3X-L-FIRECO-NUM       PIC X(3).         02683750
            15  PIWA2-3X-LEFT-SCHLDIST          PIC X(2).         02683850
            15  PIWA2-3X-L-DYN-BLOCK            PIC X(3).         02683950
            15  PIWA2-3X-L-ED                   PIC X(3).         02684138
            15  PIWA2-3X-L-AD                   PIC X(2).         02684238
            15  PIWA2-3X-L-POLICE-PAT-BORO      PIC X(2).         02684373
            15  FILLER                          PIC X.            02684473
            15  PIWA2-3X-L-BORO                 PIC X .           02684551
            15  PIWA2-3X-L-1990-CENSUSTRACT     PIC X(6) .        02684651
            15  PIWA2-3X-L-2010-CENS-TRCT       PIC X(6).         02684751
            15  PIWA2-3X-L-2010-CENS-BLK        PIC X(4).         02684851
            15  PIWA2-3X-L-2010-CENS-BLK-SFX    PIC X.            02684951
            15  PIWA2-3X-L-2000-CENS-TRACT      PIC X(6).         02685051
            15  GIWA2-3X-L-2000-CENS-BLOCK      PIC X(4).         02685151
            15  PIWA2-3X-L-2000-CENS-BLK-SUF    PIC X.            02685251
            15  FILLER                          PIC X(7).         02685376
****        15  PIWA2-3X-L-BLOCKFACE-ID *V16.1* PIC X(7)***       02685476
            15  PIWA2-3X-L-NTA                  PIC X(4).         02685551
            15  FILLER                          PIC X(8).         02685651
        10  PIWA2-3X-RIGHT-SIDE-OF-STR.                           02685751
            15  PIWA2-3X-RIGHT-COMDIST.                           02685851
              20 PIWA2-3X-RIGHT-COMDIST-BORO    PIC X(1).         02685951
              20 PIWA2-3X-RIGHT-COMDIST-NUM     PIC X(2).         02686051
            15  PIWA2-3X-R-LOW-HOUSENUM         PIC X(16).        02686151
            15  PIWA2-3X-R-HI-HOUSENUM          PIC X(16).        02686251
            15  FILLER-GSS                      PIC X(33).        02686351
            15  PIWA2-3X-RIGHT-ZIP              PIC X(5).         02686451
            15  PIWA2-3X-RIGHT-HEALTHAREA       PIC X(4).         02686553
            15  PIWA2-3X-RIGHT-POLDIST.                           02686651
             20 PIWA2-3X-R-POL-PATR-BOR-CMD     PIC X(1).         02686751
             20 PIWA2-3X-R-POL-PRECINCT         PIC X(3).         02686851
            15  PIWA2-3X-R-FIRESEC              PIC X(2).         02686951
            15  PIWA2-3X-R-FIREBAT              PIC X(2).         02687051
            15  PIWA2-3X-R-FIRECO.                                02687151
                20  PIWA2-3X-R-FIRECO-TYPE      PIC X(1).         02687251
                20  PIWA2-3X-R-FIRECO-NUM       PIC X(3).         02687351
            15  PIWA2-3X-RIGHT-SCHLDIST         PIC X(2).         02687451
            15  PIWA2-3X-R-DYN-BLOCK            PIC X(3).         02687551
***     NEXT LINE WAS PREVIOUSLY INSTRUC-DIV                       02687651
            15  PIWA2-3X-R-ED                   PIC X(3).         02687751
            15  PIWA2-3X-R-AD                   PIC X(2).         02687851
```

```
            15  PIWA2-3X-R-POLICE-PAT-BORO      PIC X(2).         02687973
            15  FILLER                          PIC X.            02688073
            15  PIWA2-3X-R-BORO                 PIC X.            02688173
            15  PIWA2-3X-R-1990-CENSUSTRACT     PIC X(6).         02688273
            15  PIWA2-3X-R-2010-CENS-TRCT       PIC X(6).         02688373
            15  PIWA2-3X-R-2010-CENS-BLK        PIC X(4).         02688473
            15  PIWA2-3X-R-2010-CENS-BLK-SFX    PIC X.            02688573
            15  PIWA2-3X-R-2000-CENS-TRACT      PIC X(6).         02688673
            15  PIWA2-3X-R-2000-CENS-BLOCK      PIC X(4).         02688773
            15  PIWA2-3X-R-2000-CENS-BLK-SUF    PIC X.            02688873
            15  FILLER                          PIC X(7).         02688976
****        15  PIWA2-3X-R-BLOCKFACE-ID *V16.1* PIC X(7)***       02689076
            15  PIWA2-3X-R-NTA                  PIC X(4).         02689273
            15  FILLER                          PIC X(8).         02689373
            15  PIWA2-3X-LGCS                   PIC X(8).         02689473
            15  PIWA2-3X-LGCS-FROM              PIC X(8).         02689573
            15  PIWA2-3X-LGCS-TO                PIC X(8).         02689673
            15  PIWA2-3X-L-HCD                  PIC X(2).         02689773
            15  PIWA2-3X-R-HCD                  PIC X(2).         02689873
            15  FILLER                          PIC X(1).         02689973
            15  PIWA2-3X-TRAFFIC-DIR            PIC X(1).         02690073
            15  PIWA2-3X-ROADWAY-TYPE           PIC X(2).         02690173
            15  PIWA2-3X-PHYSICAL-ID            PIC X(7).         02690273
            15  PIWA2-3X-GENERIC-ID             PIC X(7).         02690373
            15  PIWA2-3X-INTP-ID-INT-USE        PIC X(7).         02690473
            15  PIWA2-3X-INFD-ID-INT-USE        PIC X(7).         02690573
            15  PIWA2-3X-STR-STATUS             PIC X(1).         02690673
            15  PIWA2-3X-STR-WIDTH              PIC X(3).         02690773
            15  PIWA2-3X-STR-WIDTH-IRREG        PIC X(1).         02690873
            15  PIWA2-3X-BIKE-LANE              PIC X(1).         02690973
            15  PIWA2-3X-FED-CLASS-CODE         PIC X(2).         02691073
            15  PIWA2-3X-ROW-TYPE               PIC X(1).         02691173
            15  PIWA2-3X-LGC-LIST               PIC X(10).        02691273
            15  PIWA2-3X-LEGACY-ID              PIC X(7).         02691373
            15  PIWA2-3X-L-NTA-NAME             PIC X(75).        02691473
            15  PIWA2-3X-R-NTA-NAME             PIC X(75).        02691573
            15  PIWA2-3X-FROM-XCOORD            PIC X(7).         02691673
            15  PIWA2-3X-FROM-YCOORD            PIC X(7).         02691773
            15  PIWA2-3X-TO-XCOORD              PIC X(7).         02691873
            15  PIWA2-3X-TO-YCOORD              PIC X(7).         02691973
            15  PIWA2-3X-FROM-LATITUDE          PIC X(9).         02692075
            15  PIWA2-3X-FROM-LONGITUDE         PIC X(11).        02692175
            15  PIWA2-3X-TO-LATITUDE            PIC X(9).         02692275
            15  PIWA2-3X-TO-LONGITUDE           PIC X(11).        02692375
            15  PIWA2-3X-L-BLOCKFACE-ID         PIC X(10).        02692476
```

```
            15  PIWA2-3X-R-BLOCKFACE-ID         PIC X(10).        02692576
            15  PIWA2-3X-NBR-TRAVEL-LANES       PIC X(2).         02692676
            15  PIWA2-3X-NBR-PARK-LANES         PIC X(2).         02692776
            15  PIWA2-3X-NBR-TOTAL-LANES        PIC X(2).         02692876
            15  PIWA2-3X-BIKE-LANE-2            PIC X(2).         02692979
            15  PIWA2-3X-STR-WIDTH-MAX          PIC X(3).         02693079
            15  PIWA2-3X-BIKE-TRAFFIC-DIR       PIC X(2).         02693181
            15  PIWA2-3X-SPEED-LIMIT            PIC X(2).         02693283
            15  PIWA2-3X-LEFT-PUMA-CODE         PIC X(5).         02693386
            15  PIWA2-3X-RIGHT-PUMA-CODE        PIC X(5).         02693486
            15  FILLER                          PIC X(201).       02693586
  ****      15  FILLER   V18.1                  PIC X(211).       02693686
  ****      15  FILLER   V17.4                  PIC X(213).       02693786
  ****      15  FILLER   V17.1                  PIC X(215).       02693886
  ****      15  FILLER   V16.4                  PIC X(220).       02693986
  ****      15  FILLER   V16.1                  PIC X(246).       02694086
  ****      15  FILLER   V15.3                  PIC X(286).       02694186
                                                                   02694286
      05  PIWA2-AUX-FUNCTION3X REDEFINES PIWA2.                    02694386
         10  FILLER                             PIC X(1000).      02694486
         10  PIWA2-3X-SEGAUX.                                     02694586
            15  PIWA2-3X-SEGAUX-FILL            PIC X(6).         02694686
            15  PIWA2-3X-SEGAUX-CTR             PIC X(4).         02694786
            15  PIWA2-3X-SEGAUX-SEGS OCCURS 70 TIMES              02694886
                                                PIC X(7).         02694986
                                                                   02695086
*****************************************************************  02695186
****     FOR: FUNCTION  3C          ******************************  02696085
                                                                   02700032
      05  PIWA2-FUNCTION3C  REDEFINES PIWA2.                       02710032
         10  GEO-WA2-FN3C-ACCESS-KEY          PIC X(21).           02720032
         10  PIWA2-FN3C-DUP-KEY-FLAG          PIC X.               02730032
         10  GEO-WA2-FN3C-LOCATION-STATUS     PIC X.               02740032
         10  GEO-WA2-FN3C-COUNTY-BOUNDARY     PIC X.               02750032
         10  GEO-WA2-FN3C-PREFERRED-LGC1      PIC X(2).            02760032
         10  GEO-WA2-FN3C-PREFERRED-LGC2      PIC X(2).            02770032
         10  GEO-WA2-FN3C-PREFERRED-LGC3      PIC X(2).            02780032
         10  GEO-WA2-FN3C-NUM-X-ST-LOW-END    PIC X.               02790032
         10  PIWA2-FN3C-LOW-B5SC              PIC X(6)             02800032
                                               OCCURS 5 TIMES.      02810032
         10  GEO-WA2-FN3C-NUM-X-ST-HI-END     PIC X.               02820032
         10  PIWA2-FN3C-HI-B5SC               PIC X(6)             02830032
                                               OCCURS 5 TIMES.      02840032
         10  GEO-WA2-FN3C-REVERSALFLAG        PIC X.               02850032
         10  PIWA2-FN3C-LIONKEY.                                   02860032
```

```
            15  PIWA2-FN3C-LION-BORO         PIC X.              02870032
            15  GEO-WA2-FN3C-LIONFACECODE    PIC X(4).           02880032
            15  GEO-WA2-FN3C-LIONSEQ         PIC X(5).           02890032
        10  GEO-WA2-FN3C-GENRECFLAG          PIC X.              02900032
        10  PIWA2-FN3C-SEG-LEN               PIC X(5).           02910032
        10  GEO-WA2-FN3C-SEGMENTSLOPE        PIC X(3).           02920032
        10  GEO-WA2-FN3C-SEGMENTORIENT       PIC X.              02930032
        10  GEO-WA2-FN3C-MARBLE-RIKER-FLAG   PIC X(1).           02940032
        10  GEO-WA2-FN3C-FROM-NODE           PIC X(7).           02950032
        10  GEO-WA2-FN3C-TO-NODE             PIC X(7).           02960032
        10  GEO-WA2-FN3C-SANIT-SNOW-PRRTY    PIC X.              02961050
        10  FILLER                           PIC X(4).           02970050
        10  GEO-WA2-FN3C-SEG-ID              PIC X(7).           02980032
        10  GEO-WA2-FN3C-SLA                 PIC X.              02990032
        10  PIWA2-FN3C-SIDE-OF-STR           PIC X.              03000032
        10  GEO-WA2-FN3C-CURVE-FLAG          PIC X.              03010032
        10  GEO-WA2-FN3C-FEATURE-TYPE        PIC X.              03020032
        10  GEO-WA2-FN3C-SEGMENT-TYPE        PIC X.              03030032
        10  GEO-WA2-FN3C-COINCIDENT-CNT      PIC X.              03040032
        10  FILLER                           PIC X(4).           03050032
        10  PIWA2-FN3C-BLOCKFACE-INFO.                           03060032
            15  GEO-WA2-FN3C-COMDIST.                            03070032
               20  GEO-WA2-FN3C-COMDIST-BORO   PIC X(1).         03080032
               20  GEO-WA2-FN3C-COMDIST-NUMBER PIC X(2).         03090032
            15  PIWA2-FN3C-LOW-HOUSENUM        PIC X(16).        03100032
            15  PIWA2-FN3C-HI-HOUSENUM         PIC X(16).        03110032
            15  PIWA2-FN3C-LOW-HOUSENUM2       PIC X(16).        03120032
            15  PIWA2-FN3C-HI-HOUSENUM2        PIC X(16).        03130032
            15  FILLER-GSS                     PIC X.            03140032
            15  GEO-WA2-FN3C-ZIP               PIC X(5).         03150032
            15  GEO-WA2-FN3C-HEALTHAREA        PIC X(4).         03160053
            15  GEO-WA2-FN3C-POLICEDIST.                         03170032
             20 GEO-WA2-FN3C-POL-PATR-BORO-CMD PIC X(1).         03180032
             20 GEO-WA2-FN3C-POL-PRECINCT      PIC X(3).         03190032
** NOTE:10  GEO-WA2-FN3C-FIRESEC ==> FIRE DIVISION **             03200032
            15  GEO-WA2-FN3C-FIRESEC           PIC X(2).         03210032
            15  GEO-WA2-FN3C-FIREBAT           PIC X(2).         03220032
            15  GEO-WA2-FN3C-FIRECO.                             03230032
                20  GEO-WA2-FN3C-FIRECO-TYPE   PIC X(1).         03240032
                20  GEO-WA2-FN3C-FIRECO-NUM    PIC X(3).         03250032
            15  GEO-WA2-FN3C-SCHOOLDIST        PIC X(2).         03260032
            15  GEO-WA2-FN3C-DYN-BLOCK         PIC X(3).         03270032
            15  PIWA2-FN3C-ED                  PIC X(3).         03281041
            15  PIWA2-FN3C-AD                  PIC X(2).         03282041
            15  PIWA2-FN3C-POLICE-PAT-BORO     PIC X(2).         03282173
```

```
            15  FILLER                        PIC X.            03283073
            15  GEO-WA2-FN3C-BORO             PIC X.            03310051
            15  GEO-WA2-FN3C-1990-CENSUSTRACT  PIC X(6).        03311051
            15  GEO-WA2-FN3C-2010-CENS-TRCT    PIC X(6).        03320035
            15  GEO-WA2-FN3C-2010-CENS-BLK     PIC X(4).        03330035
            15  GEO-WA2-FN3C-2010-CENS-BLK-SFX PIC X.           03340035
            15  GEO-WA2-FN3C-2000-CENS-TRACT   PIC X(6).        03360035
            15  GEO-WA2-FN3C-2000-CENS-BLOCK   PIC X(4).        03370035
            15  GEO-WA2-FN3C-2000-CENS-BLK-SUF PIC X.           03380035
            15  FILLER                        PIC X(7).         03380177
  ******    15  PIWA2-FN3C-BLOCKFACE-ID  V16.1 PIC X(7)***       03381077
            15  PIWA2-FN3C-NTA                PIC X(4).         03382050
            15  FILLER                        PIC X(8).         03390050
                                                                 03400032
      05  PIWA2-AUX-FUNCTION3C REDEFINES PIWA2.                  03410032
         10  FILLER                           PIC X(300).       03420037
         10  PIWA2-FN3C-SEGAUX.                                  03430032
            15  PIWA2-FN3C-SEGAUX-FILL        PIC X(4).         03440032
            15  PIWA2-FN3C-SEGAUX-CTR         PIC X(4).         03450032
            15  PIWA2-FN3C-SEGAUX-SEGS OCCURS 70 TIMES          03460032
                                              PIC X(7).          03470032
                                                                 03480032
*****************************************************************  03481036
****     FOR: FUNCTION  3C EXTENDED ****************************  03482036
                                                                 03483036
      05  PIWA2-FUNCTION3CX REDEFINES PIWA2.                     03484036
         10  PIWA2-3CX-ACCESS-KEY            PIC X(21).          03485042
         10  PIWA2-3CX-DUP-KEY-FLAG          PIC X.              03486039
         10  PIWA2-3CX-LOCATION-STATUS       PIC X.              03487042
         10  PIWA2-3CX-COUNTY-BOUNDARY       PIC X.              03488042
         10  PIWA2-3CX-PREFERRED-LGC1        PIC X(2).           03489042
         10  PIWA2-3CX-PREFERRED-LGC2        PIC X(2).           03489142
         10  PIWA2-3CX-PREFERRED-LGC3        PIC X(2).           03489242
         10  PIWA2-3CX-NUM-X-ST-LOW-END      PIC X.              03489342
         10  PIWA2-3CX-LOW-B5SC              PIC X(6)            03489439
                                             OCCURS 5 TIMES.     03489536
         10  PIWA2-3CX-NUM-X-ST-HI-END       PIC X.              03489642
         10  PIWA2-3CX-HI-B5SC               PIC X(6)            03489739
                                             OCCURS 5 TIMES.     03489836
         10  PIWA2-3CX-REVERSALFLAG          PIC X.              03489942
         10  PIWA2-3CX-LIONKEY.                                  03490039
            15  PIWA2-3CX-LION-BORO          PIC X.              03490139
            15  PIWA2-3CX-LIONFACECODE       PIC X(4).           03490242
            15  PIWA2-3CX-LIONSEQ            PIC X(5).           03490342
         10  PIWA2-3CX-GENRECFLAG            PIC X.              03490442
```

```
        10  PIWA2-3CX-SEG-LEN                PIC X(5).           03490539
        10  PIWA2-3CX-SEGMENTSLOPE           PIC X(3).           03490642
        10  PIWA2-3CX-SEGMENTORIENT          PIC X.              03490742
        10  PIWA2-3CX-MARBLE-RIKER-FLAG      PIC X(1).           03490842
        10  PIWA2-3CX-FROM-NODE              PIC X(7).           03490942
        10  PIWA2-3CX-TO-NODE                PIC X(7).           03491042
        10  PIWA2-3CX-SANIT-SNOW-PRRTY       PIC X.              03491150
        10  FILLER                           PIC X(4).           03491250
        10  PIWA2-3CX-SEG-ID                 PIC X(7).           03491342
        10  PIWA2-3CX-SLA                    PIC X.              03491442
        10  PIWA2-3CX-SIDE-OF-STR            PIC X.              03491539
        10  PIWA2-3CX-CURVE-FLAG             PIC X.              03491642
        10  PIWA2-3CX-FEATURE-TYPE           PIC X.              03491742
        10  PIWA2-3CX-SEGMENT-TYPE           PIC X.              03491842
        10  PIWA2-3CX-COINCIDENT-CNT         PIC X.              03491942
        10  FILLER                           PIC X(4).           03492036
        10  PIWA2-3CX-BLOCKFACE-INFO.                            03492139
            15  PIWA2-3CX-COMDIST.                               03492242
               20  PIWA2-3CX-COMDIST-BORO    PIC X(1).           03492342
               20  PIWA2-3CX-COMDIST-NUMBER  PIC X(2).           03492442
            15  PIWA2-3CX-LOW-HOUSENUM         PIC X(16).        03492539
            15  PIWA2-3CX-HI-HOUSENUM          PIC X(16).        03492639
            15  PIWA2-3CX-LOW-HOUSENUM2        PIC X(16).        03492739
            15  PIWA2-3CX-HI-HOUSENUM2         PIC X(16).        03492839
            15  FILLER-GSS                     PIC X.            03492936
            15  PIWA2-3CX-ZIP                  PIC X(5).         03493042
            15  PIWA2-3CX-HEALTHAREA           PIC X(4).         03493153
            15  PIWA2-3CX-POLICEDIST.                            03493242
             20 PIWA2-3CX-POL-PATR-BORO-CMD    PIC X(1).         03493342
             20 PIWA2-3CX-POL-PRECINCT         PIC X(3).         03493442
** NOTE:10  PIWA2-3CX-FIRESEC ==> FIRE DIVISION **               03493542
            15  PIWA2-3CX-FIRESEC              PIC X(2).         03493642
            15  PIWA2-3CX-FIREBAT              PIC X(2).         03493742
            15  PIWA2-3CX-FIRECO.                                03493842
                20  PIWA2-3CX-FIRECO-TYPE      PIC X(1).         03493942
                20  PIWA2-3CX-FIRECO-NUM       PIC X(3).         03494042
            15  PIWA2-3CX-SCHOOLDIST           PIC X(2).         03494142
            15  PIWA2-3CX-DYN-BLOCK            PIC X(3).         03494242
            15  PIWA2-3CX-ED                   PIC X(3).         03494439
            15  PIWA2-3CX-AD                   PIC X(2).         03494539
            15  PIWA2-3CX-POLICE-PAT-BORO      PIC X(2).         03494673
            15  FILLER                         PIC X.            03494773
            15  PIWA2-3CX-BORO                 PIC X.            03494851
            15  PIWA2-3CX-1990-CENSUSTRACT     PIC X(6).         03494951
            15  PIWA2-3CX-2010-CENS-TRCT       PIC X(6).         03495051
```

```
            15  PIWA2-3CX-2010-CENS-BLK        PIC X(4).          03495151
            15  PIWA2-3CX-2010-CENS-BLK-SFX    PIC X.             03495251
            15  PIWA2-3CX-2000-CENS-TRACT      PIC X(6).          03495351
            15  PIWA2-3CX-2000-CENS-BLOCK      PIC X(4).          03495451
            15  PIWA2-3CX-2000-CENS-BLK-SUF    PIC X.             03495551
            15  FILLER                         PIC X(7).          03495677
*****       15  PIWA2-3CX-BLOCKFACE-ID V16.1   PIC X(7)***        03495777
            15  PIWA2-3CX-NTA                  PIC X(4).          03495851
            15  FILLER                         PIC X(8).          03495951
            15  PIWA2-3CX-LGCS                 PIC X(8).          03496051
            15  PIWA2-3CX-LGCS-FROM            PIC X(8).          03496151
            15  PIWA2-3CX-LGCS-TO              PIC X(8).          03496251
            15  PIWA2-3CX-L-HCD                PIC X(2).          03496353
            15  PIWA2-3CX-R-HCD                PIC X(2).          03496453
            15  FILLER                         PIC X(1).          03496551
            15  PIWA2-3CX-TRAFFIC-DIR          PIC X(1).          03496651
            15  PIWA2-3CX-ROADWAY-TYPE         PIC X(2).          03496751
            15  PIWA2-3CX-PHYSICAL-ID          PIC X(7).          03496851
            15  PIWA2-3CX-GENERIC-ID           PIC X(7).          03496951
            15  PIWA2-3CX-INTP-ID              PIC X(7).          03497051
            15  PIWA2-3CX-INFD-ID              PIC X(7).          03497151
            15  PIWA2-3CX-STR-STATUS           PIC X(1).          03497251
            15  PIWA2-3CX-STR-WIDTH            PIC X(3).          03497351
            15  PIWA2-3CX-STR-WIDTH-IRREF      PIC X(1).          03497451
            15  PIWA2-3CX-BIKE-LANE            PIC X(1).          03497551
            15  PIWA2-3CX-FED-CLASS-CODE       PIC X(2).          03497651
            15  PIWA2-3CX-ROW-TYPE             PIC X(1).          03497751
            15  PIWA2-3CX-LGC-LIST             PIC X(10).         03497851
            15  PIWA2-3CX-LEGACY-ID            PIC X(7).          03497951
            15  PIWA2-3CX-NTA-NAME             PIC X(75).         03498052
            15  PIWA2-3CX-FROM-XCOORD          PIC X(7).          03498156
            15  PIWA2-3CX-FROM-YCOORD          PIC X(7).          03498256
            15  PIWA2-3CX-TO-XCOORD            PIC X(7).          03498356
            15  PIWA2-3CX-TO-YCOORD            PIC X(7).          03498456
            15  PIWA2-3CX-FROM-LATITUDE        PIC X(9).          03498575
            15  PIWA2-3CX-FROM-LONGITUDE       PIC X(11).         03498675
            15  PIWA2-3CX-TO-LATITUDE          PIC X(9).          03498775
            15  PIWA2-3CX-TO-LONGITUDE         PIC X(11).         03498875
            15  PIWA2-3CX-BLOCKFACE-ID         PIC X(10).         03498977
            15  PIWA2-3CX-NBR-TRAVEL-LANES     PIC X(2).          03499077
            15  PIWA2-3CX-NBR-PARK-LANES       PIC X(2).          03499177
            15  PIWA2-3CX-NBR-TOTAL-LANES      PIC X(2).          03499277
            15  PIWA2-3CX-BIKE-LANE-2          PIC X(2).          03499379
            15  PIWA2-3CX-STR-WIDTH-MAX        PIC X(3).          03499479
            15  PIWA2-3CX-BIKE-TRAFFIC-DIR     PIC X(2).          03499581
```

```
            15  PIWA2-3CX-SPEED-LIMIT         PIC X(2).         03499683
            15  PIWA2-3CX-PUMA-CODE           PIC X(5).         03499785
            15  FILLER                        PIC X(291).       03499985
  ****      15  FILLER   V18.1                PIC X(296).       03500085
  ****      15  FILLER   V17.4                PIC X(298).       03500185
  ****      15  FILLER   V17.1                PIC X(300).       03500285
  ****      15  FILLER   V16.4                PIC X(305).       03500385
  ****      15  FILLER   V16.1                PIC X(321).       03500485
  ****      15  FILLER   V15.3                PIC X(361).       03500585
                                                                03500685
      05  PIWA2-AUX-FUNCTION3CX REDEFINES PIWA2.                 03500785
        10  FILLER                          PIC X(850).        03500885
        10  PIWA2-3CX-SEGAUX.                                   03500985
            15  PIWA2-3CX-SEGAUX-FILL        PIC X(4).         03501085
            15  PIWA2-3CX-SEGAUX-CTR         PIC X(4).         03501185
            15  PIWA2-3CX-SEGAUX-SEGS OCCURS 70 TIMES          03501285
                                              PIC X(7).         03501385
                                                                03501485
*****************************************************************03501585
****     FOR: FUNCTION 5            ******************************03502081
                                                                03510032
      05  PIWA2-FUNCTION5   REDEFINES PIWA2.                    03520032
        10  GEO-WA2-FN5-ADDR-MATCHING-KEY     PIC X(33).        03530034
```

P2COB1A COPY File

```
*****************************************************************00010007
**  YL 9/27/2017 ADDED DCP ZONE MAP FIELD                     **00020011
**  THIS IS THE COBOL STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM **00021011
**  INDEPENDENT REGULAR WORK AREA 2 FOR FUNCTIONS: 1A, BL, AND **00030007
**  BN.  THESE THREE FUNCTIONS SHARE A SINGLE WORK AREA 2      **00040007
**  LAYOUT.  COPY FILE - P2COB1A.                 10/10/97     **00050007
*****************************************************************00060007
                                                                00070007
     05  GEO-WA2-1A-ACCESS-KEY             PIC X(21).          00080007
     05  GEO-WA2-1A-CONT-PARITY            PIC X.              00090007
     05  PIWA2-1A-LOW-HOUSENUM             PIC X(11).          00100007
     05  GEO-WA2-1A-ALTKEY-1.                                  00110007
       10 GEO-WA2-1A-ALTKEY-1-BORO         PIC X.              00120007
       10 GEO-WA2-1A-ALTKEY-1-TAXBLOCK     PIC X(5).           00130007
       10 GEO-WA2-1A-ALTKEY-1-TAXLOT       PIC X(4).           00140007
     05  FILLER                            PIC X.              00150007
     05  GEO-WA2-1A-SCC                    PIC X(1).           00160007
     05  FILLER                            PIC X.              00170007
```

```
05  GEO-WA2-1A-GENERAL-LOT-INFO.                                00180007
   10 GEO-WA2-1A-RPAD-BLDG-CLASS       PIC X(2).               00190007
   10 GEO-WA2-1A-CORNER-CODE           PIC X(2).               00200007
   10 GEO-WA2-1A-TOT-NBR-BLDG          PIC X(4).               00210007
   10 GEO-WA2-1A-NUM-OF-BLOCKFACES     PIC X(2).               00220007
   10 GEO-WA2-1A-INTERIOR-FLAG         PIC X.                  00230007
   10 GEO-WA2-1A-VACANT-FLAG           PIC X.                  00240007
   10 GEO-WA2-1A-IRREG-FLAG            PIC X.                  00250007
05  GEO-WA2-1A-ALT-BORO-FLAG           PIC X.                  00260007
05  GEO-WA2-1A-OVERFLOW-FLAG           PIC X(1).               00270007
05  PIWA2-1A-STROLL-KEY                PIC X(19).              00280007
05  FILLER-GSS                         PIC X.                  00290007
05  GEO-WA2-1A-BLDG-ID-NUM             PIC X(7).               00300007
05  GEO-WA2-1A-CONDO-LOT-FLAG          PIC X.                  00310007
05  FILLER                             PIC X.                  00320007
05  GEO-WA2-1A-RPAD-COND-NUM           PIC X(4).               00330007
05  FILLER                             PIC X(7).               00340007
05  GEO-WA2-1A-CONDO-BILLING-BBL       PIC X(10).              00350007
05  FILLER                             PIC X.                  00360007
05  GEO-WA2-1A-CONDO-BILL-BBL-SCC      PIC X(1).               00370007
05  GEO-WA2-1A-CONDO-LOW-BBL           PIC X(10).              00380007
05  FILLER                             PIC X.                  00390007
05  GEO-WA2-1A-CONDO-HIGH-BBL          PIC X(10).              00400007
05  FILLER                             PIC X.                  00410007
05  FILLER                             PIC X(15).              00420007
05  GEO-WA2-1A-CO-OP-NBR               PIC X(4).               00430007
05  GEO-WA2-1A-SANBORN-BVOLPAGE.                               00440007
    10  GEO-WA2-1A-SANBORN-BORO        PIC X(1).               00450007
    10  GEO-WA2-1A-SANBORN-VOL-PAGE.                           00460007
      15  GEO-WA2-1A-SANBORN-VOL-NUM   PIC X(3).               00470007
      15  GEO-WA2-1A-SANBORN-PAGE-NUM  PIC X(4).               00480007
05  GEO-WA2-1A-COMMERC-DIST            PIC X(5).               00490007
05  GEO-WA2-1A-DOF-MAP-BOROUGH         PIC X.                  00500007
05  GEO-WA2-1A-TAX-MAP-NBR             PIC X(4).               00510007
05  FILLER-FOR-TAX-MAP-PAGE            PIC X(4).               00520007
05  FILLER                             PIC X(3).               00530009
05  PIWA2-1A-LATITUDE                  PIC X(9).               00540009
05  PIWA2-1A-LONGITUDE                 PIC X(11).              00540110
05  PIWA2-1A-X-COORD                   PIC X(7).               00541009
05  PIWA2-1A-Y-COORD                   PIC X(7).               00550007
05  PIWA2-1A-BID                       PIC X(6).               00560007
05  PIWA2-1A-TPAD-BIN-ST               PIC X.                  00570007
05  PIWA2-1A-TPAD-NEW-BIN              PIC X(7).               00580007
05  PIWA2-1A-TPAD-NEW-BIN-ST           PIC X.                  00590007
05  PIWA2-1A-TPAD-CONFLICT             PIC X.                  00600007
```

```
     05  PIWA2-1A-DCP-ZONE-MAP             PIC X(3).            00601011
     05  FILLER                            PIC X(6).            00610011
     05  FILLER-GSS                        PIC X(8).            00620007
     05  PIWA2-1A-NUM-OF-ADDR              PIC X(4).            00630007
     05  PIWA2-1A-ADDR-LIST                OCCURS 21 TIMES.     00640007
        10  PIWA2-1A-LIST-LOW-HOUSENUM     PIC X(16).           00650007
        10  PIWA2-1A-LIST-HI-HOUSENUM      PIC X(16).           00660007
        10  PIWA2-1A-LIST-BORO             PIC X.               00670007
        10  PIWA2-1A-LIST-5SC              PIC X(5).            00680007
        10  PIWA2-1A-LIST-LGC              PIC X(2).            00690007
        10  GEO-WA2-1A-LIST-BIN            PIC X(7).            00700007
        10  GEO-WA2-1A-LIST-SOS            PIC X.               00710007
        10  GEO-WA2-1A-ADDR-TYPE           PIC X.               00720007
        10  PIWA2-1A-TPAD-STATUS           PIC X.               00730007
        10  FILLER                         PIC X(3).            00740007
```

P2COB1AL COPY File

```
*****************************************************************  00010006
**                    P2COBIAL                                 **  00020034
**          LAST MODIFIED DECEMBER 2016                        **  00030034
** ADD NEW 5 BYTE PUMA CODE                YNL 12/17 V18,1     **  00031039
**  YL 9/27/2017 ADDED DCP ZONE MAP FIELD                      **  00040037
** ADD NEW 2 BYTE SPEED LIMIT              YNL 09/17 V17,4     **  00050036
** ADD NEW 2 BYTE BIKE TRAFFIC DIRECTION   YNL 12/16 V17,1     **  00060036
**  THIS IS THE COBOL STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM **  00070006
**  INDEPENDENT LONG WORK AREA 2 FOR FUNCTIONS: 1A, AND BL.    **  00080006
**  THESE TWO FUNCTIONS SHARE A SINGLE LONG WORK AREA 2 LAYOU. **  00090006
**  COPY FILE - P2COB1AL.                        11/06/97      **  00100006
*****************************************************************  00110006
**              LAST MODIFIED OCTOBER  2016                    **  00120030
*****************************************************************  00130027
**  JANUARY 2011 YNL ADDED THREE WORK AREAS:                   **  00140006
**  1. P2COB1EX - FUNCTION 1E EXTENDED.                        **  00150007
**  2. P2COB1AX - FUNCTION 1A   EXTENDED.                      **  00160006
**  2. P2COB1B  - P2COB1EX COMBINED WITH P2COB1AX              **  00170016
*****************************************************************  00180006
     03  PIWA2                              PIC X(17750).       00190006
*****************************************************************   00200006
****     FOR: FUNCTION 1A LONG      ******************************   00210006
                                                                   00220006
     03  PIWA2-FUNCTION1AL  REDEFINES PIWA2.                       00230006
                                                                   00240006
      05 GEO-WA2-1AL-ACCESS-KEY             PIC X(21).           00250006
```

```
      05 GEO-WA2-1AL-CONT-PARITY            PIC X.              00260006
      05 PIWA2-1AL-LOW-HOUSENUM             PIC X(11).          00270006
      05 GEO-WA2-1AL-ALTKEY-1.                                  00280006
        10 GEO-WA2-1AL-ALTKEY-1-BORO        PIC X.              00290006
        10 GEO-WA2-1AL-ALTKEY-1-TAXBLOCK    PIC X(5).           00300006
        10 GEO-WA2-1AL-ALTKEY-1-TAXLOT      PIC X(4).           00310006
      05 FILLER                              PIC X.              00320006
      05 GEO-WA2-1AL-SCC                     PIC X.              00330006
      05 FILLER                              PIC X.              00340006
      05 GEO-WA2-1AL-GENERAL-LOT-INFO.                           00350006
        10 GEO-WA2-1AL-RPAD-BLDG-CLASS       PIC X(2).           00360006
        10 GEO-WA2-1AL-CORNER-CODE           PIC X(2).           00370006
        10 GEO-WA2-1AL-NUM-OF-STRUCTURES     PIC X(4).           00380006
        10 GEO-WA2-1AL-NUM-OF-BLOCKFACES     PIC X(2).           00390006
        10 GEO-WA2-1AL-INTERIOR-FLAG         PIC X.              00400006
        10 GEO-WA2-1AL-VACANT-FLAG           PIC X.              00410006
        10 GEO-WA2-1AL-IRREG-FLAG            PIC X.              00420006
      05 GEO-WA2-1AL-ALT-BORO-FLAG           PIC X.              00430006
      05 FILLER                              PIC X.              00440006
      05 PIWA2-1AL-STROLL-KEY                PIC X(19).          00450006
      05 FILLER-GSS                          PIC X.              00460006
      05 GEO-WA2-1AL-BLDG-ID-NUM             PIC X(7).           00470006
      05 GEO-WA2-1AL-CONDO-LOT-FLAG          PIC X.              00480006
      05 FILLER                              PIC X.              00490006
      05 GEO-WA2-1AL-RPAD-COND-NUM           PIC X(4).           00500006
      05 FILLER                              PIC X(7).           00510006
      05 GEO-WA2-1AL-CONDO-BILLING-BBL       PIC X(10).          00520006
      05 FILLER                              PIC X.              00530006
      05 GEO-WA2-1AL-CONDO-BILL-BBL-SCC      PIC X.              00540006
      05 GEO-WA2-1AL-CONDO-LOW-BBL           PIC X(10).          00550006
      05 FILLER                              PIC X.              00560006
      05 GEO-WA2-1AL-CONDO-HIGH-BBL          PIC X(10).          00570006
      05 FILLER                              PIC X.              00580006
      05 FILLER                              PIC X(15).          00590006
      05 GEO-WA2-1AL-CO-OP-NBR               PIC X(4).           00600006
      05 GEO-WA2-1AL-SANBORN-BVOLPAGE.                           00610006
         10  GEO-WA2-1AL-SANBORN-BORO        PIC X(1).           00620006
         10  GEO-WA2-1AL-SANBORN-VOL-PAGE.                       00630006
           15  GEO-WA2-1AL-SANBORN-VOL-NUM   PIC X(3).           00640006
           15  GEO-WA2-1AL-SANBORN-PAGE-NUM  PIC X(4).           00650006
      05 GEO-WA2-1AL-COMMERC-DIST            PIC X(5).           00660006
      05 PIWA2-1AL-DOF-MAP-BORO              PIC X.              00670006
      05 PIWA2-1AL-DOF-MAP-SECVOL            PIC X(4).           00680006
*******  PIWA2-1AL-DOF-MAP-PAGE  NOT IMPLEMENTED                  00690006
      05 PIWA2-1AL-DOF-MAP-PAGE              PIC X(4).           00700006
```

```
      05 FILLER                              PIC X(3).           00710019
      05 PIWA2-1AL-LATITUDE                  PIC X(9).           00720019
      05 PIWA2-1AL-LONGITUDE                 PIC X(11).          00730019
      05 PIWA2-1AL-X-COORD                   PIC X(7).           00740019
      05 PIWA2-1AL-Y-COORD                   PIC X(7).           00750019
      05 PIWA2-1AL-BID                       PIC X(6).           00760019
      05 PIWA2-1AL-TPAD-BIN-ST               PIC X.              00770019
      05 PIWA2-1AL-TPAD-NEW-BIN              PIC X(7).           00780019
      05 PIWA2-1AL-TPAD-NEW-BIN-ST           PIC X.              00790019
      05 PIWA2-1AL-TPAD-CONFLICT             PIC X.              00800019
      05 PIWA2-1AL-DCP-ZONE-MAP              PIC X(3).           00810037
      05 FILLER                              PIC X(6).           00820037
      05 FILLER-GSS                          PIC X(8).           00830037
      05 GEO-WA2-1AL-NUM-OF-BINS             PIC X(4).           00840037
      05 PIWA2-1AL-TPAD-BINLIST.                                 00850037
         10 PIWA2-1AL-TPAD-BINS OCCURS 2187 TIMES.               00860037
           15 PIWA2-1AL-TPAD-BINS-BIN         PIC X(7).          00870037
           15 PIWA2-1AL-TPAD-BINS-STAT        PIC X.             00880037
         10 PIWA2-1AL-TPAD-FILL               PIC X(4).          00890037
      05 GEO-WA2-1AL-BINS REDEFINES PIWA2-1AL-TPAD-BINLIST       00900037
         PIC X(7)  OCCURS 2500 TIMES.                           00910037
                                                                00920037
*************************************************************   00930037
***   FOR: FUNCTION 1/1E EXTENDED  ****************3**********   00940037
                                                                00950037
     03  PIWA2-FUNCTION1EX   REDEFINES PIWA2.                   00960037
                                                                00970037
      05 PIWA2-FN1EX-ACCESS-KEY              PIC X(21).          00980037
      05 PIWA2-FN1EX-CONT-PARITY              PIC X.              00990037
      05 PIWA2-FN1EX-LOW-HOUSENUM-SORT        PIC X(11).          01000037
      05 PIWA2-FN1EX-HI-HOUSENUM-SORT         PIC X(11).          01010037
      05 PIWA2-FN1EX-PREFERRED-LGC            PIC X(2).           01020037
      05 PIWA2-FN1EX-NUM-X-ST-LOW-END         PIC X.              01030037
      05 PIWA2-FN1EX-LOW-B5SC                 PIC X(6)            01040037
                                              OCCURS 5 TIMES.     01050037
      05 PIWA2-FN1EX-NUM-X-ST-HI-END          PIC X.              01060037
      05 PIWA2-FN1EX-HI-B5SC                  PIC X(6)            01070037
                                              OCCURS 5 TIMES.     01080037
      05 PIWA2-FN1EX-LIONKEY.                                    01090037
          10  PIWA2-FN1EX-LION-BORO           PIC X.              01100037
          10  PIWA2-FN1EX-LIONFACECODE        PIC X(4).           01110037
          10  PIWA2-FN1EX-LIONSEQ             PIC X(5).           01120037
      05 PIWA2-FN1EX-SPECIAL-ADDR-FLAG        PIC X(1).           01130037
      05 PIWA2-FN1EX-SIDE-OF-STR              PIC X.              01140037
      05 PIWA2-FN1EX-SEGMENTLENGTH            PIC X(5).           01150037
```

```
      05 PIWA2-FN1EX-XCOORD                  PIC X(7).            01160037
      05 PIWA2-FN1EX-YCOORD                  PIC X(7).            01170037
      05 FILLER-GSS                          PIC X(8).            01180037
      05 PIWA2-FN1EX-MARBLE-RIKER-FLAG       PIC X(1).            01190037
      05 PIWA2-FN1EX-SLA                     PIC X.               01200037
      05 PIWA2-FN1EX-COMDIST.                                     01210037
          10  PIWA2-FN1EX-COMDIST-BORO       PIC X(1).            01220037
          10  PIWA2-FN1EX-COMDIST-NUMBER     PIC X(2).            01230037
      05 PIWA2-FN1EX-ZIP                     PIC X(5).            01240037
                                                                   01250037
      05 PIWA2-FN1EX-ELECTDIST               PIC X(3).            01260037
      05 PIWA2-FN1EX-ASSEMDIST               PIC X(2).            01270037
      05 PIWA2-FN1EX-SPLIT-ED-FLAG           PIC X(1).            01280037
      05 PIWA2-FN1EX-CONGDIST                PIC X(2).            01290037
      05 PIWA2-FN1EX-SENATEDIST              PIC X(2).            01300037
      05 PIWA2-FN1EX-COURTDIST               PIC X(2).            01310037
      05 PIWA2-FN1EX-COUNCILDIST             PIC X(2).            01320037
                                                                   01330037
      05 PIWA2-FN1EX-HCD                     PIC X(2).            01340037
      05 PIWA2-FN1EX-HEALTHAREA              PIC X(4).            01350037
      05 PIWA2-FN1EX-SANIDIST.                                    01360037
          10  PIWA2-FN1EX-SANIDIST-BORO      PIC X(1).            01370037
          10  PIWA2-FN1EX-SANIDIST-NUMBER    PIC X(2).            01380037
      05 PIWA2-FN1EX-SANITATION-SUBSEC       PIC X(2).            01390037
      05 PIWA2-FN1EX-SANI-REG                PIC X(5).            01400037
      05 PIWA2-FN1EX-SANI-REC                PIC X(3).            01410037
      05 PIWA2-FN1EX-POLICEDIST.                                  01420037
           15 PIWA2-FN1EX-POL-PATR-BORO-CMD PIC X(1).             01430037
           15 PIWA2-FN1EX-POL-PRECINCT       PIC X(3).            01440037
** NOTE:10  PIWA2-FN1EX-FIRESEC ==> FIRE DIVISION **               01450037
      05 PIWA2-FN1EX-FIRESEC                 PIC X(2).            01460037
      05 PIWA2-FN1EX-FIREBAT                 PIC X(2).            01470037
      05 PIWA2-FN1EX-FIRECO.                                      01480037
          10  PIWA2-FN1EX-FIRECO-TYPE        PIC X(1).            01490037
          10  PIWA2-FN1EX-FIRECO-NUM         PIC X(3).            01500037
      05 PIWA2-FN1EX-SPLIT-SCHOOL-FLAG       PIC X.               01510037
      05 PIWA2-FN1EX-SCHOOLDIST              PIC X(2).            01520037
      05 PIWA2-FN1EX-DYN-BLOCK               PIC X(3).            01530037
      05 PIWA2-FN1EX-POLICE-PAT-BORO         PIC X(2).            01540037
      05 PIWA2-FN1EX-FEATURE-TYPE            PIC X.               01550037
      05 PIWA2-FN1EX-SEGMENT-TYPE            PIC X.               01560037
      05 PIWA2-FN1EX-ALX                     PIC X.               01570037
      05 PIWA2-FN1EX-COINCIDENT-CNT          PIC X.               01580037
      05 FILLER                              PIC X(3).            01590037
      05 PIWA2-FN1EX-1990-CENSUSTRACT        PIC X(6).            01600037
```

```
     05 PIWA2-FN1EX-2010-CENS-TRCT          PIC X(6).           01610037
     05 PIWA2-FN1EX-2010-CENS-BLK           PIC X(4).           01620037
     05 PIWA2-FN1EX-2010-CENS-BLK-SFX       PIC X.              01630037
     05 PIWA2-FN1EX-2000-CENS-TRCT          PIC X(6).           01640037
     05 PIWA2-FN1EX-2000-CENS-BLK           PIC X(4).           01650037
     05 PIWA2-FN1EX-2000-CENS-BLK-SFX       PIC X.              01660037
     05 PIWA2-FN1EX-NTA                     PIC X(4).           01670037
     05 PIWA2-FN1EX-SANIT-SNOW-PRRTY        PIC X.              01680037
     05 PIWA2-FN1EX-SANIT-ORGANICS          PIC X(5).           01690037
     05 PIWA2-FN1EX-SANIT-BULK-PICK-UP      PIC X(5).           01700037
**** 05 PIWA2-FN1EX-SANIT-RESERVED V16.4    PIC X(5).           01710037
     05 PIWA2-FN1EX-HURRICANE-ZONE          PIC XX.             01720037
     05 FILLER                              PIC X(11).          01730037
     05 PIWA2-FN1EX-TRUE-HNS                PIC X(11).          01740037
     05 PIWA2-FN1EX-TRUE-B7SC               PIC X(8).           01750037
     05 PIWA2-FN1EX-SEG-ID                  PIC X(7).           01760037
     05 PIWA2-FN1EX-CURVE-FLAG              PIC X(1).           01770037
     05 PIWA2-FN1EX-LGCS                    PIC X(8).           01780037
     05 PIWA2-FN1EX-BOE-PTR                 PIC X(1).           01790037
     05 PIWA2-FN1EX-AZIMUTH                 PIC X(3).           01800037
     05 PIWA2-FN1EX-ORIENT                  PIC X(1).           01810037
     05 PIWA2-FN1EX-X-LOW                   PIC X(7).           01820037
     05 PIWA2-FN1EX-Y-LOW                   PIC X(7).           01830037
     05 PIWA2-FN1EX-Z-LOW                   PIC X(7).           01840037
     05 PIWA2-FN1EX-X-HI                    PIC X(7).           01850037
     05 PIWA2-FN1EX-Y-HI                    PIC X(7).           01860037
     05 PIWA2-FN1EX-Z-HI                    PIC X(7).           01870037
     05 PIWA2-FN1EX-X-CC                    PIC X(7).           01880037
     05 PIWA2-FN1EX-Y-CC                    PIC X(7).           01890037
     05 PIWA2-FN1EX-Z-CC                    PIC X(7).           01900037
     05 PIWA2-FN1EX-RADIUS                  PIC X(7).           01910037
     05 PIWA2-FN1EX-SECANT                  PIC X(1).           01920037
     05 PIWA2-FN1EX-ANGLE-FROM              PIC X(5).           01930037
     05 PIWA2-FN1EX-ANGLE-TO                PIC X(5).           01940037
     05 PIWA2-FN1EX-NODE-FROM               PIC X(7).           01950037
     05 PIWA2-FN1EX-NODE-TO                 PIC X(7).           01960037
     05 PIWA2-FN1EX-VANITY-LION             PIC X(10).          01970037
     05 PIWA2-FN1EX-SOS                     PIC X(1).           01980037
     05 PIWA2-FN1EX-SPLIT-LOHSN             PIC X(11).          01990037
     05 PIWA2-FN1EX-TD                      PIC X(1).           02000037
     05 PIWA2-FN1EX-TR                      PIC X(10).          02010037
     05 PIWA2-FN1EX-CURVE-FRACTION          PIC X(3).           02020037
     05 PIWA2-FN1EX-ROADWAY-TYPE            PIC X(2).           02030037
     05 PIWA2-FN1EX-PHYICAL-ID              PIC X(7).           02040037
     05 PIWA2-FN1EX-GENERIC-ID              PIC X(7).           02050037
```

```
     05 PIWA2-FN1EX-NYPD-ID-FILL            PIC X(7).           02060037
     05 PIWA2-FN1EX-FDNY-ID-FILL            PIC X(7).           02070037
     05 PIWA2-FN1EX-BIKE-LANE-2             PIC X(2).           02080037
     05 PIWA2-FN1EX-BIKE-TRAFFIC-DIR        PIC X(2).           02090037
     05 FILLER                              PIC X(3).           02100037
****  05 FILLER              ******V17.1 **  PIC X(5).           02110033
****  05 FILLER              ******V16.4 **  PIC X(7).           02120033
****  05 PIWA2-FN1EX-BLOCKFACE-ID *V16.1 **  PIC X(7) ***        02130033
     05 PIWA2-FN1EX-STREET-STATUS           PIC X(1).           02140033
     05 PIWA2-FN1EX-STREET-WIDTH            PIC X(3).           02150033
     05 PIWA2-FN1EX-STREET-WIDTH-IRR        PIC X(1).           02160033
     05 PIWA2-FN1EX-BIKE-LANE               PIC X(1).           02170033
     05 PIWA2-FN1EX-FED-CLASS-CODE          PIC X(2).           02180033
     05 PIWA2-FN1EX-ROW-TYPE                PIC X(1).           02190033
     05 PIWA2-FN1EX-LGC-LIST-2              PIC X(10).          02200033
     05 PIWA2-FN1EX-LEGACY-SEG-ID           PIC X(7).           02210033
     05 PIWA2-FN1EX-LGC-LIST-FROM-1         PIC X(10).          02220033
     05 PIWA2-FN1EX-LGC-LIST-TO-1           PIC X(10).          02230033
     05 PIWA2-FN1EX-LGC-LIST-FROM-2         PIC X(10).          02240033
     05 PIWA2-FN1EX-LGC-LIST-TO-2           PIC X(10).          02250033
     05 PIWA2-FN1EX-NOCROSS-FLG             PIC X(1).           02260033
     05 PIWA2-FN1EX-IND-SEG-LEN             PIC X(5).           02270033
     05 PIWA2-FN1EX-NTA-NAME                PIC X(75).          02280033
     05 PIWA2-FN1EX-USPS-CITY-NAME          PIC X(25).          02290033
     05 PIWA2-FN1EX-LATITUDE                PIC X(9).           02300033
     05 PIWA2-FN1EX-LONGITUDE               PIC X(11).          02310033
     05 PIWA2-FN1EX-SEG-FROM-NODE           PIC X(7).           02320033
     05 PIWA2-FN1EX-SEG-TO-NODE             PIC X(7).           02330033
     05 PIWA2-FN1EX-SEG-FROM-XYZ            PIC X(21).          02340033
     05 PIWA2-FN1EX-SEG-TO-XYZ              PIC X(21).          02350033
     05 PIWA2-FN1EX-BLOCKFACE-ID            PIC X(10).          02360033
     05 PIWA2-FN1EX-NBR-TRAVEL-LANES        PIC X(2).           02370033
     05 PIWA2-FN1EX-NBR-PARK-LANES          PIC X(2).           02380033
     05 PIWA2-FN1EX-NBR-TOTAL-LANES         PIC X(2).           02390033
     05 PIWA2-FN1EX-STREET-WIDTH-MAX        PIC X(3).           02400033
     05 PIWA2-FN1EX-SPEED-LIMIT             PIC X(2).           02410036
     05 PIWA2-FN1EX-PUMA-CODE               PIC X(5).           02411039
     05 PIWA2-FN1EX-FILL500                 PIC X(245).         02420039
****  05 PIWA2-FN1EX-FILL500   ** V18.1 **   PIC X(250).         02430039
****  05 PIWA2-FN1EX-FILL500   ** V17.4 **   PIC X(252).         02431039
****  05 PIWA2-FN1EX-FILL500   ** V16.4 **   PIC X(255).         02440036
****  05 PIWA2-FN1EX-FILL500   ** V16.1 **   PIC X(271) ***      02450036
****  05 PIWA2-FN1EX-FILL500   ** V15.3 **   PIC X(327) ***      02460036
*************************************************************/ 02470036
*                                                        ***/ 02480036
```

```
*THE FOLLOWING FIELDS ARE AN ADDITION TO GRID1              ***/ 02490036
*****************************************************************/ 02500036
      05 PIWA2-FN1EX-REASON-CODE            PIC X(1).            02510036
      05 PIWA2-FN1EX-REASON-CODE-QUAL       PIC X(1).            02520036
      05 PIWA2-FN1EX-WARN-CODE              PIC X(2).            02530036
      05 PIWA2-FN1EX-RETURN-CODE            PIC X(2).            02540036
      05 PIWA2-FN1EX-NUM-X-STS-LO-END       PIC X(1).            02550036
      05 PIWA2-FN1EX-LO-B7SC OCCURS 5 TIMES  PIC X(8).           02560036
      05 PIWA2-FN1EX-NUM-X-STS-HI-END       PIC X(1).            02570036
      05 PIWA2-FN1EX-HI-B7SC OCCURS 5 TIMES  PIC X(8).           02580036
      05 PIWA2-FN1EX-LO-ST-NAME OCCURS 5 TIMES PIC X(32).        02590036
      05 PIWA2-FN1EX-HI-ST-NAME OCCURS 5 TIMES PIC X(32).        02600036
      05 PIWA2-FN1EX-BOE-B7SC               PIC X(8).            02610036
      05 PIWA2-FN1EX-BOE-ST-NAME            PIC X(32).           02620036
      05 PIWA2-FN1EX-FILL600                PIC X(52).           02630036
                                                                 02640036
*************************************************************   02650036
***   FOR: FUNCTION 1A   EXTENDED  ***************************   02660036
                                                                 02670036
     03  PIWA2-FUNCTION1AX  REDEFINES PIWA2.                      02680036
      05 PIWA2-1AX-ACCESS-KEY               PIC X(21).           02690036
      05 PIWA2-1AX-CONT-PARITY              PIC X.               02700036
      05 PIWA2-1AX-LOW-HOUSENUM             PIC X(11).           02710036
      05 PIWA2-1AX-ALTKEY-1.                                     02720036
        10 PIWA2-1AX-ALTKEY-1-BORO          PIC X.               02730036
        10 PIWA2-1AX-ALTKEY-1-TAXBLOCK      PIC X(5).            02740036
        10 PIWA2-1AX-ALTKEY-1-TAXLOT        PIC X(4).            02750036
      05 FILLER                             PIC X.               02760036
      05 PIWA2-1AX-SCC                      PIC X(1).            02770036
      05 FILLER                             PIC X.               02780036
      05 PIWA2-1AX-GENERAL-LOT-INFO.                             02790036
        10 PIWA2-1AX-RPAD-BLDG-CLASS        PIC X(2).            02800036
        10 PIWA2-1AX-CORNER-CODE            PIC X(2).            02810036
        10 PIWA2-1AX-TOT-NBR-BLDG           PIC X(4).            02820036
        10 PIWA2-1AX-NUM-OF-BLOCKFACES      PIC X(2).            02830036
        10 PIWA2-1AX-INTERIOR-FLAG          PIC X.               02840036
        10 PIWA2-1AX-VACANT-FLAG            PIC X.               02850036
        10 PIWA2-1AX-IRREG-FLAG             PIC X.               02860036
      05 PIWA2-1AX-ALT-BORO-FLAG            PIC X.               02870036
      05 PIWA2-1AX-OVERFLOW-FLAG            PIC X(1).            02880036
      05 PIWA2-1AX-STROLL-KEY               PIC X(19).           02890036
      05 FILLER-GSS                         PIC X.               02900036
      05 PIWA2-1AX-BLDG-ID-NUM              PIC X(7).            02910036
      05 PIWA2-1AX-CONDO-LOT-FLAG           PIC X.               02920036
      05 FILLER                             PIC X.               02930036
```

```
05 PIWA2-1AX-RPAD-COND-NUM            PIC X(4).            02940036
05 FILLER                             PIC X(7).            02950036
05 PIWA2-1AX-CONDO-BILLING-BBL        PIC X(10).           02960036
05 FILLER                             PIC X.               02970036
05 PIWA2-1AX-CONDO-BILL-BBL-SCC       PIC X(1).            02980036
05 PIWA2-1AX-CONDO-LOW-BBL            PIC X(10).           02990036
05 FILLER                             PIC X.               03000036
05 PIWA2-1AX-CONDO-HIGH-BBL           PIC X(10).           03010036
05 FILLER                             PIC X.               03020036
05 FILLER                             PIC X(15).           03030036
05 PIWA2-1AX-CO-OP-NBR                PIC X(4).            03040036
05 PIWA2-1AX-SANBORN-BVOLPAGE.                              03050036
   10  PIWA2-1AX-SANBORN-BORO         PIC X(1).            03060036
   10  PIWA2-1AX-SANBORN-VOL-PAGE.                         03070036
     15  PIWA2-1AX-SANBORN-VOL-NUM    PIC X(3).            03080036
     15  PIWA2-1AX-SANBORN-PAGE-NUM   PIC X(4).            03090036
05 PIWA2-1AX-COMMERC-DIST             PIC X(5).            03100036
05 PIWA2-1AX-DOF-MAP-BOROUGH          PIC X.               03110036
05 PIWA2-1AX-TAX-MAP-NBR              PIC X(4).            03120036
05 FILLER-FOR-TAX-MAP-PAGE            PIC X(4).            03130036
05 FILLER                             PIC X(3).            03140036
05 PIWA2-1AX-LATITUDE                 PIC X(9).            03150036
05 PIWA2-1AX-LONGITUDE                PIC X(11).           03160036
05 PIWA2-1AX-X-COORD                  PIC X(7).            03170036
05 PIWA2-1AX-Y-COORD                  PIC X(7).            03180036
05 PIWA2-1AX-BID                      PIC X(6).            03190036
05 PIWA2-1AX-TPAD-BIN-ST              PIC X.               03200036
05 PIWA2-1AX-TPAD-NEW-BIN             PIC X(7).            03210036
05 PIWA2-1AX-TPAD-NEW-BIN-ST          PIC X.               03220036
05 PIWA2-1AX-TPAD-CONFLICT            PIC X.               03230036
05 PIWA2-1AX-DCP-ZONE-MAP             PIC X(3).            03240038
05 FILLER                             PIC X(6).            03250038
05 FILLER-GSS                         PIC X(8).            03260036
05 PIWA2-1AX-REASON-CODE              PIC X(1).            03270036
05 PIWA2-1AX-REASON-CODE-QUAL         PIC X(1).            03280036
05 PIWA2-1AX-WARN-CODE                PIC X(2).            03290036
05 PIWA2-1AX-RETURN-CODE              PIC X(2).            03300036
05 PIWA2-1AX-FILLER                   PIC X(108).          03310036
05 PIWA2-1AX-NUM-OF-ADDR              PIC X(4).            03320036
05 PIWA2-1AX-ADDR-LIST               OCCURS 21 TIMES.      03330036
  10  PIWA2-1AX-LIST-LOW-HOUSENUM     PIC X(16).           03340036
  10  PIWA2-1AX-LIST-HI-HOUSENUM      PIC X(16).           03350036
  10  PIWA2-1AX-LIST-BORO             PIC X.               03360036
  10  PIWA2-1AX-LIST-5SC              PIC X(5).            03370036
  10  PIWA2-1AX-LIST-LGC              PIC X(2).            03380036
```

```
        10  PIWA2-1AX-LIST-BIN              PIC X(7).           03390036
        10  PIWA2-1AX-LIST-SOS              PIC X.              03400036
        10  PIWA2-1AX-ADDR-TYPE             PIC X.              03410036
        10  PIWA2-1AX-TPAD-STATUS           PIC X.              03420036
        10  PIWA2-1AX-ST-NAME               PIC X(32).          03430036
        10  FILLER                          PIC X(34).          03440036
                                                                 03450036
*****************************************************************  03460036
***   FOR: FUNCTION 1B             ****************************   03470036
                                                                 03480036
     03  PIWA2-FUNCTION1B   REDEFINES PIWA2.                     03490036
                                                                 03500036
      05 PIWA2-1B-1-ACCESS-KEY              PIC X(21).          03510036
      05 PIWA2-1B-1-CONT-PARITY             PIC X.              03520036
      05 PIWA2-1B-1-LOW-HOUSENUM-SORT       PIC X(11).          03530036
      05 PIWA2-1B-1-HI-HOUSENUM-SORT        PIC X(11).          03540036
      05 PIWA2-1B-1-PREFERRED-LGC           PIC X(2).           03550036
      05 PIWA2-1B-1-NUM-X-ST-LOW-END        PIC X.              03560036
      05 PIWA2-1B-1-LOW-B5SC                PIC X(6)            03570036
                                            OCCURS 5 TIMES.     03580036
      05 PIWA2-1B-1-NUM-X-ST-HI-END         PIC X.              03590036
      05 PIWA2-1B-1-HI-B5SC                 PIC X(6)            03600036
                                            OCCURS 5 TIMES.     03610036
      05 PIWA2-1B-1-LIONKEY.                                    03620036
          10  PIWA2-1B-1-LION-BORO          PIC X.              03630036
          10  PIWA2-1B-1-LIONFACECODE       PIC X(4).           03640036
          10  PIWA2-1B-1-LIONSEQ            PIC X(5).           03650036
      05 PIWA2-1B-1-SPECIAL-ADDR-FLAG       PIC X(1).           03660036
      05 PIWA2-1B-1-SIDE-OF-STR             PIC X.              03670036
      05 PIWA2-1B-1-SEGMENTLENGTH           PIC X(5).           03680036
      05 PIWA2-1B-1-XCOORD                  PIC X(7).           03690036
      05 PIWA2-1B-1-YCOORD                  PIC X(7).           03700036
      05 FILLER-GSS                         PIC X(8).           03710036
      05 PIWA2-1B-1-MARBLE-RIKER-FLAG       PIC X(1).           03720036
      05 PIWA2-1B-1-SLA                     PIC X.              03730036
      05 PIWA2-1B-1-COMDIST.                                    03740036
          10  PIWA2-1B-1-COMDIST-BORO       PIC X(1).           03750036
          10  PIWA2-1B-1-COMDIST-NUMBER     PIC X(2).           03760036
      05 PIWA2-1B-1-ZIP                     PIC X(5).           03770036
                                                                 03780036
      05 PIWA2-1B-1-ELECTDIST               PIC X(3).           03790036
      05 PIWA2-1B-1-ASSEMDIST               PIC X(2).           03800036
      05 PIWA2-1B-1-SPLIT-ED-FLAG           PIC X(1).           03810036
      05 PIWA2-1B-1-CONGDIST                PIC X(2).           03820036
      05 PIWA2-1B-1-SENATEDIST              PIC X(2).           03830036
```

```
      05 PIWA2-1B-1-COURTDIST                PIC X(2).            03840036
      05 PIWA2-1B-1-COUNCILDIST              PIC X(2).            03850036
                                                                  03860036
      05 PIWA2-1B-1-HCD                      PIC X(2).            03870036
      05 PIWA2-1B-1-HEALTHAREA               PIC X(4).            03880036
      05 PIWA2-1B-1-SANIDIST.                                     03890036
          10  PIWA2-1B-1-SANIDIST-BORO       PIC X(1).            03900036
          10  PIWA2-1B-1-SANIDIST-NUMBER     PIC X(2).            03910036
      05 PIWA2-1B-1-SANITATION-SUBSEC        PIC X(2).            03920036
      05 PIWA2-1B-1-SANI-REG                 PIC X(5).            03930036
      05 PIWA2-1B-1-SANI-REC                 PIC X(3).            03940036
      05 PIWA2-1B-1-POLICEDIST.                                   03950036
           15 PIWA2-1B-1-POL-PATR-BORO-CMD PIC X(1).              03960036
           15 PIWA2-1B-1-POL-PRECINCT        PIC X(3).            03970036
** NOTE:10  PIWA2-1B-1-FIRESEC ==> FIRE DIVISION **               03980036
      05 PIWA2-1B-1-FIRESEC                  PIC X(2).            03990036
      05 PIWA2-1B-1-FIREBAT                  PIC X(2).            04000036
      05 PIWA2-1B-1-FIRECO.                                       04010036
          10  PIWA2-1B-1-FIRECO-TYPE         PIC X(1).            04020036
          10  PIWA2-1B-1-FIRECO-NUM          PIC X(3).            04030036
      05 PIWA2-1B-1-SPLIT-SCHOOL-FLAG        PIC X.               04040036
      05 PIWA2-1B-1-SCHOOLDIST               PIC X(2).            04050036
      05 PIWA2-1B-1-DYN-BLOCK                PIC X(3).            04060036
      05 PIWA2-1B-1-POLICE-PAT-BORO          PIC X(2).            04070036
      05 PIWA2-1B-1-FEATURE-TYPE             PIC X.               04080036
      05 PIWA2-1B-1-SEGMENT-TYPE             PIC X.               04090036
      05 PIWA2-1B-1-ALX                      PIC X.               04100036
      05 PIWA2-1B-1-COINCIDENT-CNT           PIC X.               04110036
      05 FILLER                              PIC X(3).            04120036
      05 PIWA2-1B-1-1990-CENSUSTRACT         PIC X(6).            04130036
      05 PIWA2-1B-1-2010-CENS-TRCT           PIC X(6).            04140036
      05 PIWA2-1B-1-2010-CENS-BLK            PIC X(4).            04150036
      05 PIWA2-1B-1-2010-CENS-BLK-SFX        PIC X.               04160036
      05 PIWA2-1B-1-2000-CENS-TRCT           PIC X(6).            04170036
      05 PIWA2-1B-1-2000-CENS-BLK            PIC X(4).            04180036
      05 PIWA2-1B-1-2000-CENS-BLK-SFX        PIC X.               04190036
      05 PIWA2-1B-1-NTA                      PIC X(4).            04200036
      05 PIWA2-1B-1-SANIT-SNOW-PRRTY         PIC X.               04210036
      05 PIWA2-1B-1-SANIT-ORGANICS           PIC X(5).            04220036
      05 PIWA2-1B-1-SANIT-BULK-PICK-UP       PIC X(5).            04230036
****  05 PIWA2-1B-1-SANIT-RESERVED V16.4     PIC X(5).            04240036
      05 PIWA2-1B-1-HURRICANE-ZONE           PIC XX.              04250036
      05 FILLER                              PIC X(11).           04260036
      05 PIWA2-1B-1-TRUE-HNS                 PIC X(11).           04270036
      05 PIWA2-1B-1-TRUE-B7SC                PIC X(8).            04280036
```

```
     05 PIWA2-1B-1-SEG-ID                  PIC X(7).           04290036
     05 PIWA2-1B-1-CURVE-FLAG              PIC X(1).           04300036
     05 PIWA2-1B-1-LGCS                    PIC X(8).           04310036
     05 PIWA2-1B-1-BOE-PTR                 PIC X(1).           04320036
     05 PIWA2-1B-1-AZIMUTH                 PIC X(3).           04330036
     05 PIWA2-1B-1-ORIENT                  PIC X(1).           04340036
     05 PIWA2-1B-1-X-LOW                   PIC X(7).           04350036
     05 PIWA2-1B-1-Y-LOW                   PIC X(7).           04360036
     05 PIWA2-1B-1-Z-LOW                   PIC X(7).           04370036
     05 PIWA2-1B-1-X-HI                    PIC X(7).           04380036
     05 PIWA2-1B-1-Y-HI                    PIC X(7).           04390036
     05 PIWA2-1B-1-Z-HI                    PIC X(7).           04400036
     05 PIWA2-1B-1-X-CC                    PIC X(7).           04410036
     05 PIWA2-1B-1-Y-CC                    PIC X(7).           04420036
     05 PIWA2-1B-1-Z-CC                    PIC X(7).           04430036
     05 PIWA2-1B-1-RADIUS                  PIC X(7).           04440036
     05 PIWA2-1B-1-SECANT                  PIC X(1).           04450036
     05 PIWA2-1B-1-ANGLE-FROM              PIC X(5).           04460036
     05 PIWA2-1B-1-ANGLE-TO                PIC X(5).           04470036
     05 PIWA2-1B-1-NODE-FROM               PIC X(7).           04480036
     05 PIWA2-1B-1-NODE-TO                 PIC X(7).           04490036
     05 PIWA2-1B-1-VANITY-LION             PIC X(10).          04500036
     05 PIWA2-1B-1-SOS                     PIC X(1).           04510036
     05 PIWA2-1B-1-SPLIT-LOHSN             PIC X(11).          04520036
     05 PIWA2-1B-1-TD                      PIC X(1).           04530036
     05 PIWA2-1B-1-TR                      PIC X(10).          04540036
     05 PIWA2-1B-1-CURVE-FRACTION          PIC X(3).           04550036
     05 PIWA2-1B-1-ROADWAY-TYPE            PIC X(2).           04560036
     05 PIWA2-1B-1-PHYICAL-ID              PIC X(7).           04570036
     05 PIWA2-1B-1-GENERIC-ID              PIC X(7).           04580036
     05 PIWA2-1B-1-NYPD-ID-FILL            PIC X(7).           04590036
     05 PIWA2-1B-1-FDNY-ID-FILL            PIC X(7).           04600036
     05 PIWA2-1B-1-BIKE-LANE-2             PIC X(2).           04610036
     05 PIWA2-1B-1-BIKE-TRAFFIC-DIR        PIC X(2).           04620036
     05 FILLER                             PIC X(3).           04630036
****  05 FILLER                 ** V17.1 ** PIC X(5) ***        04640036
****  05 FILLER                 ** V16.4 ** PIC X(7) ***        04650036
****  05 PIWA2-FN-1-BLOCKFACE-ID ** V16.1 ** PIC X(7) ***       04660036
     05 PIWA2-1B-1-STREET-STATUS           PIC X(1).           04670036
     05 PIWA2-1B-1-STREET-WIDTH            PIC X(3).           04680036
     05 PIWA2-1B-1-STREET-WIDTH-IRR        PIC X(1).           04690036
     05 PIWA2-1B-1-BIKE-LANE               PIC X(1).           04700036
     05 PIWA2-1B-1-FED-CLASS-CODE          PIC X(2).           04710036
     05 PIWA2-1B-1-ROW-TYPE                PIC X(1).           04720036
     05 PIWA2-1B-1-LGC-LIST-2              PIC X(10).          04730036
```

```
      05 PIWA2-1B-1-LEGACY-SEG-ID           PIC X(7).           04740036
      05 PIWA2-1B-1-LGC-LIST-FROM-1         PIC X(10).          04750036
      05 PIWA2-1B-1-LGC-LIST-TO-1           PIC X(10).          04760036
      05 PIWA2-1B-1-LGC-LIST-FROM-2         PIC X(10).          04770036
      05 PIWA2-1B-1-LGC-LIST-TO-2           PIC X(10).          04780036
      05 PIWA2-1B-1-NOCROSS-FLG             PIC X(1).           04790036
      05 PIWA2-1B-1-IND-SEG-LEN             PIC X(5).           04800036
      05 PIWA2-1B-1-NTA-NAME                PIC X(75).          04810036
      05 PIWA2-1B-1-USPS-CITY-NAME          PIC X(25).          04820036
      05 PIWA2-1B-1-LATITUDE                PIC X(9).           04830036
      05 PIWA2-1B-1-LONGITUDE               PIC X(11).          04840036
      05 PIWA2-1B-1-SEG-FROM-NODE           PIC X(7).           04850036
      05 PIWA2-1B-1-SEG-TO-NODE             PIC X(7).           04860036
      05 PIWA2-1B-1-SEG-FROM-XYZ            PIC X(21).          04870036
      05 PIWA2-1B-1-SEG-TO-XYZ              PIC X(21).          04880036
      05 PIWA2-1B-1-BLOCKFACE-ID            PIC X(10).          04890036
      05 PIWA2-1B-1-NBR-TRAVEL-LANES        PIC X(2).           04900036
      05 PIWA2-1B-1-NBR-PARK-LANES          PIC X(2).           04910036
      05 PIWA2-1B-1-NBR-TOTAL-LANES         PIC X(2).           04920036
      05 PIWA2-1B-1-STREET-WIDTH-MAX        PIC X(3).           04930036
      05 PIWA2-1B-1-SPEED-LIMIT             PIC X(2).           04940036
      05 PIWA2-1B-1-PUMA-CODE               PIC X(5).           04941039
      05 PIWA2-1B-1-FILL500                 PIC X(245).         04950039
****  05 PIWA2-1B-1-FILL500   ** V18.1 **   PIC X(250).         04960039
****  05 PIWA2-1B-1-FILL500   ** V17.4 **   PIC X(252).         04961039
****  05 PIWA2-1B-1-FILL500   ** V16.4 **   PIC X(255).         04970036
****  05 PIWA2-1B-1-FILL500   ** V16.1 **   PIC X(271) **       04980036
****  05 PIWA2-1B-1-FILL500   ** V15,3 **   PIC X(327) **       04990036
*****************************************************************/ 05000036
*                                                          ***/ 05010036
*THE FOLLOWING FIELDS ARE AN ADDITION TO 1/1E               ***/ 05020036
*****************************************************************/ 05030036
      05 PIWA2-1B-1-REASON-CODE             PIC X(1).           05040036
      05 PIWA2-1B-1-REASON-CODE-QUAL        PIC X(1).           05050036
      05 PIWA2-1B-1-WARN-CODE               PIC X(2).           05060036
      05 PIWA2-1B-1-RETURN-CODE             PIC X(2).           05070036
      05 PIWA2-1B-1-NUM-X-STS-LO-END        PIC X(1).           05080036
      05 PIWA2-1B-1-LO-B7SC OCCURS 5 TIMES  PIC X(8).           05090036
      05 PIWA2-1B-1-NUM-X-STS-HI-END        PIC X(1).           05100036
      05 PIWA2-1B-1-HI-B7SC OCCURS 5 TIMES  PIC X(8).           05110036
      05 PIWA2-1B-1-LO-ST-NAME OCCURS 5 TIMES PIC X(32).        05120036
      05 PIWA2-1B-1-HI-ST-NAME OCCURS 5 TIMES PIC X(32).        05130036
      05 PIWA2-1B-1-BOE-B7SC                PIC X(8).           05140036
      05 PIWA2-1B-1-BOE-ST-NAME             PIC X(32).          05150036
      05 PIWA2-1B-1-FILL600                 PIC X(52).          05160036
```

```
                                                          05170036
05 PIWA2-1B-1A-ACCESS-KEY              PIC X(21).         05180036
05 PIWA2-1B-1A-CONT-PARITY             PIC X.             05190036
05 PIWA2-1B-1A-LOW-HOUSENUM            PIC X(11).         05200036
05 PIWA2-1B-1A-ALTKEY-1.                                  05210036
  10 PIWA2-1B-1A-ALTKEY-1-BORO         PIC X.             05220036
  10 PIWA2-1B-1A-ALTKEY-1-TAXBLOCK     PIC X(5).          05230036
  10 PIWA2-1B-1A-ALTKEY-1-TAXLOT       PIC X(4).          05240036
05 FILLER                              PIC X.             05250036
05 PIWA2-1B-1A-SCC                     PIC X(1).          05260036
05 FILLER                              PIC X.             05270036
05 PIWA2-1B-1A-GENERAL-LOT-INFO.                          05280036
  10 PIWA2-1B-1A-RPAD-BLDG-CLASS       PIC X(2).          05290036
  10 PIWA2-1B-1A-CORNER-CODE           PIC X(2).          05300036
  10 PIWA2-1B-1A-TOT-NBR-BLDG          PIC X(4).          05310036
  10 PIWA2-1B-1A-NUM-OF-BLOCKFACES     PIC X(2).          05320036
  10 PIWA2-1B-1A-INTERIOR-FLAG         PIC X.             05330036
  10 PIWA2-1B-1A-VACANT-FLAG           PIC X.             05340036
  10 PIWA2-1B-1A-IRREG-FLAG            PIC X.             05350036
05 PIWA2-1B-1A-ALT-BORO-FLAG           PIC X.             05360036
05 PIWA2-1B-1A-OVERFLOW-FLAG           PIC X(1).          05370036
05 PIWA2-1B-1A-STROLL-KEY              PIC X(19).         05380036
05 FILLER-GSS                          PIC X.             05390036
05 PIWA2-1B-1A-BLDG-ID-NUM             PIC X(7).          05400036
05 PIWA2-1B-1A-CONDO-LOT-FLAG          PIC X.             05410036
05 FILLER                              PIC X.             05420036
05 PIWA2-1B-1A-RPAD-COND-NUM           PIC X(4).          05430036
05 FILLER                              PIC X(7).          05440036
05 PIWA2-1B-1A-CONDO-BILLING-BBL       PIC X(10).         05450036
05 FILLER                              PIC X.             05460036
05 PIWA2-1B-1A-CONDO-BILL-BBL-SCC      PIC X(1).          05470036
05 PIWA2-1B-1A-CONDO-LOW-BBL           PIC X(10).         05480036
05 FILLER                              PIC X.             05490036
05 PIWA2-1B-1A-CONDO-HIGH-BBL          PIC X(10).         05500036
05 FILLER                              PIC X.             05510036
05 FILLER                              PIC X(15).         05520036
05 PIWA2-1B-1A-CO-OP-NBR               PIC X(4).          05530036
05 PIWA2-1B-1A-SANBORN-BVOLPAGE.                          05540036
   10  PIWA2-1B-1A-SANBORN-BORO        PIC X(1).          05550036
   10  PIWA2-1B-1A-SANBORN-VOL-PAGE.                      05560036
     15  PIWA2-1B-1A-SANBORN-VOL-NUM   PIC X(3).          05570036
     15  PIWA2-1B-1A-SANBORN-PAGE-NUM  PIC X(4).          05580036
05 PIWA2-1B-1A-COMMERC-DIST            PIC X(5).          05590036
05 PIWA2-1B-1A-DOF-MAP-BOROUGH         PIC X.             05600036
05 PIWA2-1B-1A-TAX-MAP-NBR             PIC X(4).          05610036
```

```
05 FILLER-FOR-TAX-MAP-PAGE            PIC X(4).           05620036
05 FILLER                             PIC X(3).           05630036
05 PIWA2-1B-1A-LATITUDE               PIC X(9).           05640036
05 PIWA2-1B-1A-LONGITUDE              PIC X(11).          05650036
05 PIWA2-1B-1A-X-COORD                PIC X(7).           05660036
05 PIWA2-1B-1A-Y-COORD                PIC X(7).           05670036
05 PIWA2-1B-1A-BID                    PIC X(6).           05680036
05 PIWA2-1B-1A-TPAD-BIN-ST            PIC X.              05690036
05 PIWA2-1B-1A-TPAD-NEW-BIN           PIC X(7).           05700036
05 PIWA2-1B-1A-TPAD-NEW-BIN-ST        PIC X.              05710036
05 PIWA2-1B-1A-TPAD-CONFLICT          PIC X.              05720036
05 PIWA2-1B-1A-DCP-ZONE-MAP           PIC X(3).           05721038
05 FILLER                             PIC X(6).           05722038
05 FILLER-GSS                         PIC X(8).           05740036
05 PIWA2-1B-1A-REASON-CODE            PIC X(1).           05750036
05 PIWA2-1B-1A-REASON-CODE-QUAL       PIC X(1).           05760036
05 PIWA2-1B-1A-WARN-CODE              PIC X(2).           05770036
05 PIWA2-1B-1A-RETURN-CODE            PIC X(2).           05780036
05 FILLER                             PIC X(108).         05790036
05 PIWA2-1B-1A-NUM-OF-ADDR            PIC X(4).           05800036
05 PIWA2-1B-1A-ADDR-LIST             OCCURS 21 TIMES.     05810036
  10  PIWA2-1B-1A-LIST-LOW-HOUSENUM   PIC X(16).          05820036
  10  PIWA2-1B-1A-LIST-HI-HOUSENUM    PIC X(16).          05830036
  10  PIWA2-1B-1A-LIST-BORO           PIC X.              05840036
  10  PIWA2-1B-1A-LIST-5SC            PIC X(5).           05850036
  10  PIWA2-1B-1A-LIST-LGC            PIC X(2).           05860036
  10  PIWA2-1B-1A-LIST-BIN            PIC X(7).           05870036
  10  PIWA2-1B-1A-LIST-SOS            PIC X.              05880036
  10  PIWA2-1B-1A-ADDR-TYPE           PIC X.              05890036
  10  PIWA2-1B-1A-TPAD-STATUS         PIC X.              05900036
  10  PIWA2-1B-1A-ST-NAME             PIC X(32).          05910036
  10  FILLER                          PIC X(34).          05920028
                                                          05930010
```

P2COB3S COPY File

```
*****************************************************************  00000100
***  THIS IS THE COBOL STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM **  00000200
***  INDEPENDENT WORK AREA 2 FOR FUNCTION 3S.                   **  00000300
***  COPY FILE - P2COB3S.                        09/17/97       **  00000400
*****************************************************************  00000500
      05  PIWA2-3S-ACCESS-KEY.                                     00000600
         10 FILLER-GSS                      PIC X(2).             00000700
         10 PIWA2-3S-PORS-STNAME-IND        PIC X.                00000800
         10 PIWA2-3S-BORO                   PIC X.                00000900
         10 PIWA2-3S-5SC                    PIC X(5).             00001000
         10 PIWA2-3S-LGC                    PIC X(2).             00001100
         10 FILLER                          PIC X(10).            00001200
      05  PIWA2-3S-NUM-OF-INTERSECTS        PIC X(3).             00001300
      05  PIWA2-3S-LIST-OFINTERSECTS        OCCURS 350 TIMES.     00001400
         10 PIWA2-3S-MARBLE-RIKERS-FLAG     PIC X.                00001500
         10 PIWA2-3S-DISTANCE               PIC X(5).             00001600
         10 PIWA2-3S-GAP-FLAG               PIC X.                00001700
         10 FILLER                          PIC X(7).             00001800
         10 PIWA2-3S-NUM-OF-STR             PIC X.                00001900
         10 PIWA2-3S-B7SC                   PIC X(8)              00002000
                                           OCCURS 5 TIMES.       00002100
```

P2COBAP COPY File

```
*****************************************************************  00010006
**  MARCH   2015 YNL                - COPYLIB AP / APX    V15.2**  00020028
**  THIS IS THE COBOL STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM **  00030006
**  INDEPENDENT WORK AREA 2 FOR FUNCTION: AP.                  **  00040028
*****************************************************************  00050006
*****************************************************************  00060006
                                                                   00070006
      03  PIWA2                              PIC X(2800).         00080024
                                                                   00090006
 ***************************************************************   00100023
 ***   FOR: FUNCTION AP             ******** ADDAP  V15.2 ******   00110024
                                                                   00120023
      03  PIWA2-FUNCTIONAP   REDEFINES PIWA2.                      00130024
       05 PIWA2-AP-ACCESS-KEY               PIC X(21).            00140024
       05 PIWA2-AP-CONT-PARITY              PIC X.                00150024
       05 PIWA2-AP-LOW-HOUSENUM             PIC X(11).            00160024
       05 PIWA2-AP-ALTKEY-1.                                      00170024
         10 PIWA2-AP-ALTKEY-1-BORO          PIC X.                00180024
         10 PIWA2-AP-ALTKEY-1-TAXBLOCK      PIC X(5).             00190024
         10 PIWA2-AP-ALTKEY-1-TAXLOT        PIC X(4).             00200024
```

```
      05 FILLER                              PIC X(7).            00210025
      05 PIWA2-AP-TOT-NBR-BLDG               PIC X(4).            00220024
      05 FILLER                              PIC X(26).           00230023
      05 FILLER-GSS                          PIC X.               00240023
      05 PIWA2-AP-BLDG-ID-NUM                PIC X(7).            00250024
      05 PIWA2-AP-CONDO-LOT-FLAG             PIC X.               00260024
      05 FILLER                              PIC X.               00270023
      05 PIWA2-AP-RPAD-COND-NUM              PIC X(4).            00280024
      05 FILLER                              PIC X(7).            00290023
      05 PIWA2-AP-CONDO-BILLING-BBL          PIC X(10).           00300024
      05 FILLER                              PIC X(2).            00310025
      05 PIWA2-AP-CONDO-LOW-BBL              PIC X(10).           00320024
      05 FILLER                              PIC X.               00330023
      05 PIWA2-AP-CONDO-HIGH-BBL             PIC X(10).           00340024
      05 FILLER                              PIC X(16).           00350025
      05 PIWA2-AP-CO-OP-NBR                  PIC X(4).            00360024
      05 FILLER                              PIC X(22).           00370031
      05 PIWA2-AP-RESERVED                   PIC X(3).            00380031
      05 PIWA2-AP-LATITUDE                   PIC X(9).            00400024
      05 PIWA2-AP-LONGITUDE                  PIC X(11).           00410024
      05 PIWA2-AP-X-COORD                    PIC X(7).            00420024
      05 PIWA2-AP-Y-COORD                    PIC X(7).            00430024
      05 FILLER                              PIC X(16).           00440029
      05 PIWA2-AP-AP-ID                      PIC X(9).            00450029
      05 FILLER-GSS                          PIC X(8).            00460023
      05 PIWA2-AP-NUM-OF-ADDR                PIC X(4).            00470024
      05 PIWA2-AP-ADDR-LIST                 OCCURS 21 TIMES.      00480024
        10  PIWA2-AP-LIST-LOW-HOUSENUM      PIC X(16).           00490024
        10  PIWA2-AP-LIST-HI-HOUSENUM       PIC X(16).           00500024
        10  PIWA2-AP-LIST-BORO              PIC X.               00510024
        10  PIWA2-AP-LIST-5SC               PIC X(5).            00520024
        10  PIWA2-AP-LIST-LGC               PIC X(2).            00530024
        10  PIWA2-AP-LIST-BIN               PIC X(7).            00540024
        10  PIWA2-AP-LIST-SOS               PIC X.               00550024
        10  PIWA2-AP-ADDR-TYPE              PIC X.               00560024
        10  FILLER                          PIC X(4).            00570024
                                                                  00580024
*************************************************************      00590024
***   FOR: FUNCTION AP EXTENDED  ******** ADDAP  V15.2 ********   00600026
                                                                  00610024
     03  PIWA2-FUNCTIONAPX  REDEFINES PIWA2.                      00620024
      05 PIWA2-APX-ACCESS-KEY               PIC X(21).           00630024
      05 PIWA2-APX-CONT-PARITY               PIC X.               00640024
      05 PIWA2-APX-LOW-HOUSENUM              PIC X(11).           00650024
      05 PIWA2-APX-ALTKEY-1.                                      00660024
```

```
  10 PIWA2-APX-ALTKEY-1-BORO          PIC X.              00670024
  10 PIWA2-APX-ALTKEY-1-TAXBLOCK      PIC X(5).           00680024
  10 PIWA2-APX-ALTKEY-1-TAXLOT        PIC X(4).           00690024
05 FILLER                             PIC X(7).           00700025
05 PIWA2-APX-TOT-NBR-BLDG             PIC X(4).           00710024
05 FILLER                             PIC X(26).          00720024
05 FILLER-GSS                         PIC X.              00730024
05 PIWA2-APX-BLDG-ID-NUM               PIC X(7).           00740024
05 PIWA2-APX-CONDO-LOT-FLAG            PIC X.              00750024
05 FILLER                             PIC X.              00760024
05 PIWA2-APX-RPAD-COND-NUM             PIC X(4).           00770024
05 FILLER                             PIC X(7).           00780024
05 PIWA2-APX-CONDO-BILLING-BBL         PIC X(10).          00790024
05 FILLER                             PIC X(2).           00800025
05 PIWA2-APX-CONDO-LOW-BBL             PIC X(10).          00810024
05 FILLER                             PIC X.              00820024
05 PIWA2-APX-CONDO-HIGH-BBL            PIC X(10).          00830024
05 FILLER                             PIC X(16).          00840025
05 PIWA2-APX-CO-OP-NBR                 PIC X(4).           00850024
05 FILLER                             PIC X(18).          00860024
05 FILLER-FOR-TAX-MAP-PAGE             PIC X(4).           00870024
05 FILLER                             PIC X(3).           00880024
05 PIWA2-APX-LATITUDE                  PIC X(9).           00890024
05 PIWA2-APX-LONGITUDE                 PIC X(11).          00900024
05 PIWA2-APX-X-COORD                   PIC X(7).           00910024
05 PIWA2-APX-Y-COORD                   PIC X(7).           00920024
05 FILLER                             PIC X(16).          00930029
05 PIWA2-APX-AP-ID                     PIC X(9).           00940029
05 FILLER-GSS                         PIC X(8).           00950024
05 PIWA2-APX-REASON-CODE               PIC X(1).           00960024
05 PIWA2-APX-REASON-CODE-QUAL          PIC X(1).           00970024
05 PIWA2-APX-WARN-CODE                 PIC X(2).           00980024
05 PIWA2-APX-RETURN-CODE               PIC X(2).           00990024
05 PIWA2-APX-FILLER                    PIC X(108).         01000024
05 PIWA2-APX-NUM-OF-ADDR               PIC X(4).           01010024
05 PIWA2-APX-ADDR-LIST                OCCURS 21 TIMES.     01020024
  10  PIWA2-APX-LIST-LOW-HOUSENUM     PIC X(16).          01030024
  10  PIWA2-APX-LIST-HI-HOUSENUM      PIC X(16).          01040024
  10  PIWA2-APX-LIST-BORO             PIC X.              01050024
  10  PIWA2-APX-LIST-5SC              PIC X(5).           01060024
  10  PIWA2-APX-LIST-LGC              PIC X(2).           01070024
  10  PIWA2-APX-LIST-BIN              PIC X(7).           01080024
  10  PIWA2-APX-LIST-SOS              PIC X.              01090024
  10  PIWA2-APX-ADDR-TYPE             PIC X.              01100024
  10  FILLER                          PIC X.              01110024
```

```
        10  PIWA2-APX-ST-NAME                PIC X(32).          01120024
        10  FILLER                           PIC X(34).          01130024
                                                                 01140024
```

ASSEMBLER COPY Files (COW)

```
*/*******************************************************************/ 00010000
*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE P1BAL,    ***/ 00020000
*/*****  CONTAINING THE Platform Independent LAYOUT OF WORK AREA 1 ***/ 00030000
*/*******************************************************************/ 00040000
*/*****        Last Updated:  August 2016  - Unit added by meb     ***/ 00040136
*/*****        Last Updated:  December 2013                        ***/ 00040336
*/*******************************************************************/ 00041014
P1BAL    DS   0H                                                       00050000
*/****************************                                         00060000
*/*****  INPUT FIELDS  *******                                         00070000
*/****************************                                         00080000
P1IFUNC  DS   0CL2      FUNCTION CODE                                  00090000
P1IFUNC1 DS    CL1      FUNCTION CODE, BYTE 1                          00100000
P1IFUNC2 DS    CL1      FUNCTION CODE, BYTE 2                          00110000
         SPACE                                                         00120000
P1IHSE#  DS    CL16      UNFORMATED HSNUM FOR FUNCTION: 1; 1A; 1E.     00130001
P1IHSE#S DS    CL11      HOUSE NUMBER (SORT FORMAT)                    00140005
*                        The Following two fields are for Fn 5         00150001
P1ILHS#  DS    CL16      UNFORMATED HSNUM                              00160001
P1ILHS#S DS    CL11      HOUSE NUMBER (SORT FORMAT)                    00170005
         SPACE                                                         00180001
P1IBCD1  DS   0CL11       11 Digit Street Code for Street one            00190000
P1IBORO1 DS    CL1      BORO CODE  (1=MN;2=BX;3=BK;4=QN;5=SI)          00200000
P1ICDE1  DS    CL10      STREET CODE FOR STREET ONE                    00210000
P1ISTRT1 DS    CL32      STREET NAME 1                                 00220000
         SPACE                                                         00230000
P1IBCD2  DS   0CL11     11 Digit Street Code for Street two            00240000
P1IBORO2 DS    CL1       BORO CODE OF CROSS ST. 1                      00250000
P1ICDE2  DS    CL10      STREET CODE FOR STREET TWO                    00260000
P1ISTRT2 DS    CL32      STREET NAME 2                                 00270000
         SPACE                                                         00280000
P1IBCD3  DS   0CL11     11 Digit Street Code for Street Three          00290001
P1IBORO3 DS    CL1       BORO CODE OF CROSS ST. 2                      00300000
P1ICDE3  DS    CL10      STREET CODE FOR STREET THREE                  00310000
P1ISTRT3 DS    CL32      STREET NAME 3                                 00320000
         SPACE                                                         00330000
P1IBBL   DS   0CL10     BORO,BLOCK,LOT FOR "BL" FUNCTION               00340002
P1IBLBOR DS    CL1      BORO FOR FUNCTION "BL"                         00350000
```

```
P1IBLOCK DS    CL5      TAX BLOCK - FOR  FUNCTION "BL"                 00360000
P1ILOT   DS    CL4      TAX LOT   - FOR  FUNCTION "BL"                 00370000
P1ITLV#  DS    CL1       Tax Lot Version Number (Not Implemented)      00380000
P1IBIN   DS    CL7       BUILDING ID NUMBER                            00390000
P1ICOMP  DS    CL1       COMPASS DIRECTION (TYPES 2, 3C & 3S)          00400010
P1ICOMP2 DS    CL1       COMPASS DIRECTION (TYPE 3S)                   00401010
P1INODE  DS    CL7       Node as inpur for Fn 2                        00410032
P1IPLIND DS    CL1       Platform Indicator                            00420003
*                        Blank = St'd Mainframe                        00430000
*                        P = Platform Independent                      00440000
P1IZIPIN DS    CL5       Input Zip Code                                00450036
P1IUNIT  DS    CL14      Input Unit V16.4                              00451036
         DS    CL82      Filler                                        00460036
         SPACE                                                         00470000
*/****************************                                         00480000
*/*****      FLAGS     *******                                         00490000
*/****************************                                         00500000
         SPACE                                                         00510000
P1ILONG  DS    CL1       'L' IF LONG WORKAREA 2 FOR FUNC 1A/BL         00520000
P1IJUST  DS    CL1       HOUSE NUMBER JUSTIFICATION FLAG               00520109
P1IHNL   DS    CL2       House Number Length                           00521009
P1IHNBRF DS    CL1       House Number Override Flag - *, $ or blank    00522009
P1ISNL   DS    CL2       LENGTH STREET NAME IS TO BE NORMALIZED TO     00523009
P1ICMPCT DS    CL1       'C' IF STREET NAMES ARE TO BE COMPACTED       00524009
P1IEXPND DS    CL1       EXPANDED FORMAT FLAG                          00530009
P1IRBRQS DS    CL1       ROADBED REQUEST SWITCH                        00550013
P1IRES01 DS    CL1       RESERVED FOR INTERNAL USE                     00581015
P1ISEGAX DS    CL1       Segment Auxiliary Switch                      00582018
P1IBRFLG DS    CL1       BROWSE FLAG P=PRIMARY ONLY F=PRINCIPAL ONLY   00583020
P1IRSTON DS    CL1       Real Street Only Flag used with Function 3S   00584021
P1ITPADS DS    CL1       Read TPAD for PAD Processing                  00585023
P1IMODES DS    CL1       Mode Switch                                   00586027
*                        X = Extended                                  00586131
P1IWTOS  DS    CL1       WTO Switch  N=No WTO                          00586231
         DS    CL29      FILLER                                        00590031
         SPACE                                                         00600000
*/****************************                                         00610000
*/*****  OUTPUT FIELDS  *******                                        00620000
*/****************************                                         00630000
         SPACE                                                         00640000
P1OBORO  DS    CL9       BORO NAME                                     00650000
P1OHSE#  DS    CL16      HOUSE NUMBER, NORMALIZED, DISPLAY FORMAT      00660000
P1OHSE#S DS    CL11      HOUSE NUMBER (SORT FORMAT)                    00670005
P1OBCD1  DS   0CL11     11 Digit Street Code for Street one            00680000
P1OBORO1 DS    CL1      BORO CODE  (1=MN;2=BX;3=BK;4=QN;5=SI)          00690000
```

```
P1OCDE1  DS    CL10      STREET CODE FOR STREET ONE                    00700000
P1OSTRT1 DS    CL32      STREET 1 NAME, NORMALIZED                     00710004
         SPACE                                                         00720000
P1OBCD2  DS   0CL11     11 Digit Street Code for Street two            00730000
P1OBORO2 DS    CL1       BORO CODE OF CROSS ST. 1                      00740000
P1OCDE2  DS    CL10      STREET CODE FOR STREET TWO                    00750000
P1OSTRT2 DS    CL32      STREET 2 NAME, NORMALIZED                     00760004
         SPACE                                                         00770000
P1OBCD3  DS   0CL11     11 Digit Street Code for Street three          00780000
P1OBORO3 DS    CL1       BORO CODE OF street 3                         00790000
P1OCDE3  DS    CL10      STREET CODE FOR STREET THREE                  00800000
P1OSTRT3 DS    CL32      STREET 3 NAME, NORMALIZED                     00810004
         SPACE                                                         00820000
P1OBBL   DS   0CL11     BORO,BLOCK,LOT FOR "BL" FUNCTION               00830000
P1OBLBOR DS    CL1      BORO FOR FUNCTION "BL"                         00840000
P1OBLOCK DS    CL5      TAX BLOCK - FOR  FUNCTION "BL"                 00850000
P1OLOT   DS    CL4      TAX LOT   - FOR  FUNCTION "BL"                 00860000
P1OTLV#  DS    CL1       Tax Lot Version Number (Not Implemented)      00870000
P1OLHSE  DS    CL16      LOW HOUSE NUMBER DISPLAY FORM                 00880006
P1OLHSES DS    CL11      LOW HOUSE NUMBER SORT FORM                    00881006
P1OBIN   DS    CL7       Output Building Identification Number         00882011
P1OATTR3 DS    CL3       Attribute Bytes - Internal Use                00883011
         SPACE                                                         00890000
P1OREAS2 DS    CL1       2ND REASON CODE                               00891024
P10RCQ2  DS    CL1       2ND REASON CODE TPAD QUALIFIER                00892130
P1OWARN2 DS    CL2       2ND WARNING RETURN CODE-NOT IMPL              00892226
P1ORC2   DS    CL2       2ND GEOSUPPORT RETURN CODE                    00893025
P1OERR2  DS    CL80      2ND ERROR MESSAGE                             00894024
P1ONODE  DS    CL7       NODE NORMALIZED FOR FN 2                      00895032
P1OUNITS DS   0CL14      UNIT IN SORT FORMAT                           00896037
P1OUNITT DS    CL4       UNIT TYPE                                     00897036
P1OUNITI DS    CL10      UNIT IDENTIFIER                               00898036
P1OUNITD DS    CL14      UNIT IN DISPLAY FORMAT                        00899036
         DS    CL11      FILLER                                        00900036
P1ONIN   DS    CL6       NAP IDENTIFICATION NUMBER                     00900107
P1OATTRB DS    CL1       ATTRIBUTE BYTE FROM SND                       00901006
P1OREASN DS    CL1       REASON CODE                                   00910000
P10RCQ   DS    CL1       REASON CODE TPAD QUALIFIER                    00920030
P1OWARNC DS    CL2       WARNING RETURN CODE                           00930025
P1ORC    DS    CL2       GEOSUPPORT RETURN CODE                        00940025
P1OERROR DS    CL80      ERROR MESSAGE                                 00950000
P1O#NAME DS    CL2       NUMBER OF STREET NAMES                        00960002
P1OBRWSE DS    CL80      10 B7SC'S                                     00970002
P1ONAMES DS  10CL32      UP TO 10 STREET NAMES                         00980002
P1END    EQU   *                                                       00990000
```

```
P1LENGTH EQU   P1END-P1BAL    LENGTH OF P1BAL                          01000000
```

P2BAL COPY File

```
*/*********************************************************************/ 00010092
*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE P2BAL,    ***/ 00020092
*/*****  CONTAINING THE LAYOUT OF WORK AREA 2 FOR FUNCTIONS       ***/ 00030092
*/*****  1, 1E, 2, 2C, 3, 3C. PLEASE NOTE THAT FUNCTIONS 2 AND 2C  ***/ 00040092
*/*****  SHARE A SINGLE WORK AREA 2 LAYOUT.                       ***/ 00050092
*/*****  ADDED 3 EXTENDED (MODE OF X)                    6/2011   ***/ 00060092
*/*****  ADDED 2 WIDE     (2W       )                    2/2014   ***/ 00070092
*/*****  ADDED 2 byte field "Police Patrol Borough" for functions: ***/ 00080092
*/*****  1/1E; 2/2W; 3/3X-left side;3/3X-right side; 3C/3CX.      ***/ 00090092
*/*****                                                  8/2014   ***/ 00100092
*/*****  ADDED 2 fields: "Bike Lane 2" and "Street Width Maximum"  ***/ 00110092
*/*****  for functions 3X/3CX                            9/2016   ***/ 00120092
*/*****  Replaced "Sanitation Reserved" with "Sanitation Bulk      ***/ 00130098
*/*****  Pick Up" for function 1                         10/2016  ***/ 00140092
*/*****  ADDED 2 bytes field "Bike Traffic Direction" for          ***/ 00150092
*/*****  for functions 1/1E (extended),1B,3X,3CX         12/2016  ***/ 00160093
*/*****  ADDED 2 bytes field "Speed Limit"               09/2017  ***/ 00161093
*/*****  for functions 3,3C (extended).                           ***/ 00162094
*/*****  ADDED 5 bytes field "PUMA Code" for functions:           ***/ 00163097
*/*****  3/3C (extended).                                12/2017  ***/ 00164097
*/*********************************************************************/ 00170092
*/*****        Last Date Modified -   FEBRUARY 2016               ***/ 00180092
*/*********************************************************************/ 00190092
P2BAL    DS   0H                                                      00200092
P2ACCKEY DS    CL21          ACCESS KEY                               00210092
P2LAYOUT DS   0CL279                                                  00220092
P2F1CPAR DS    CL1           CONTINUOUS PARITY INDICATOR              00230092
P2F1LHNS DS    CL11          LOW HOUSE NUMBER                         00240092
P2F1HHNS DS    CL11          HIGH HOUSE NUMBER                        00250092
P2F1LGC  DS    CL2           DCP Prefered LGC (Fn 1) - BOE (Fn 1E)    00260092
P2F1#STL DS    CL1           NUMBER OF CROSS STREETS AT LOW END       00270092
P2F1CDEL DS    CL30          UP TO FIVEPB5SC'S FOR LOW END            00280092
P2F1#STH DS    CL1           NUMBER OF CROSS STREETS AT HIGH END      00290092
P2F1CDEH DS    CL30          UP TO FIVE B5SC'S FOR HIGH END           00300092
P2F1LBOR DS    CL1           LION BOROUGH CODE                        00310092
P2F1FACE DS    CL4           LION FACE CODE                           00320092
P2F1SEQ  DS    CL5           LION SEQUENCE NUMBER                     00330092
P2F1SPAD DS    CL1           SPECIAL ADDRESS FLAG                     00340092
P2F1SOS  DS    CL1           SIDE OF STREET INDICATOR                 00350092
P2F1SEGL DS    CL5           SEGMENT LEGNTH                           00360092
```

```
P2F1XCOR DS    CL7          X COORDINATE                              00370092
P2F1YCOR DS    CL7          Y COORDINATE                              00380092
P2F1ZCOR DS    CL7          Z Coordinate - Not Impl.                  00390092
P2F1RES1 DS    CL1          RESERVED FOR DCP/GSS USE                  00400092
P2F1MHRI DS    CL1          MARBLE HILL/RIKERS ISLAND FLAG            00410092
P2F1SLA  DS    CL1          STREET LIGHT AREA                         00420092
P2F1CD   DS   0CL3          COMMUNITY DISTRICT                        00430092
P2F1CDB  DS    CL1          COMMUNITY DISTRICT BORO                   00440092
P2F1CDN  DS    CL2          COMMUNITY DISTRICT NUMBER                 00450092
P2F1ZIP  DS    CL5          ZIP CODE                                  00460092
P2F1EED  DS    CL3          ELECTION DISTRICT                         00470092
P2F1EAD  DS    CL2          ASSEMBLY DISTRICT                         00480092
P2F1ESED DS    CL1          SPLIT E.D. FLAG                           00490092
*                 Next four fields are valid only for Fn 1E           00500092
P2F1ECON DS    CL2          CONGRESSIONAL DISTRICT                    00510092
P2F1ESEN DS    CL2          SENATORIAL DISTRICT                       00520092
P2F1ECIV DS    CL2          CIVIL COURT DISTRICT                      00530092
P2F1ECOU DS    CL2          CITY COUNCIL DISTRICT                     00540092
*                                                                      00550092
P2F1HCD  DS    CL2          HEALTH CODE DISTRICT                      00560092
P2F1HA   DS    CL4          HEALTH AREA                               00570092
P2F1SAND DS    CL3          SANITATION DISTRICT                       00580092
P2F1SANT DS    CL2          SANITATION DEPT SUBSECTION                00590092
P2F1SREG DS    CL5          SANITATION REGULAR PICK-UP                00600092
P2F1SREC DS    CL3          SANITATION RECYCLE PICK-UP                00610092
P2F1POL  DS    0CL4         POLICE DISTRICT                           00620092
P2F1PBC  DS    CL1          POLICE PATROL BORO COMMAND                00630092
P2F1POP  DS    CL3          POLICE PRECINCT                           00640092
P2F1FS   DS    CL2          FIRE DIVISION                             00650092
P2F1FB   DS    CL2          FIRE BATTALION                            00660092
P2F1FC   DS   0CL4          FIRE COMPANY                              00670092
P2F1FCT  DS    CL1          FIRE COMPANY TYPE                         00680092
P2F1FCN  DS    CL3          FIRE COMPANY NUMBER                       00690092
P2F1FILS DS    CL1          FILLER_WAS SPLIT SCHOOL DISTRICT FLAG     00700092
P2F1SCH  DS    CL2          SCHOOL DISTRICT                           00710092
P2F1CPB  DS    CL3          DYNAMIC  BLOCK/ATOMIC POLYGON             00720092
P2F1PPB  DS    CL2          Police Patrol Borough                     00730092
P2F1FEAT DS    CL1          Feature Type Code                         00740092
P2F1STC  DS    CL1          SEGMENT TYPE CODE                         00750092
P2F1ALX  DS    CL1          A=Segment split by Alley                  00760092
*                           X=Cross Streets modified                  00770092
P2F1CSC  DS    CL1          Coincident Segment Count                  00780092
         DS    CL2          Filler                                    00790092
P2F1CTB  DS    CL1          CENSUS TRACT BOROUGH                      00800092
P2F1CT90 DS    CL6          1990 CENSUS TRACT                         00810092
```

```
P2F1CT10 DS    CL6           2010 CENSUS TRACT                          00820092
P2F1BL10 DS    CL4           2010 CENSUS BLOCK                          00830092
P2F1BLS1 DS    CL1           2010 CENSUS BLOCK SUFFIX NOT IMPLEMENTED   00840092
P2F1T00  DS    CL6           2000 CENSUS TRACT                          00850092
P2F1B00  DS    CL4           2000 CENSUS BLOCK                          00860092
P2F1S00  DS    CL1           2000 CENSUS BLOCK SUFFIX                   00870092
P2F1NTA  DS    CL4           Neighborhood Tabulation Area               00880092
P2F1SP   DS    CL1           Sanitation Street Snow Priority            00890092
P2F1SORG DS    CL5           Sanitation Organics Pick Up                00900092
P2F1SBLK DS    CL5           Sanitation Bulk Pick Up                    00910092
*        DS    CL5           Sanitation Reserved                        00920092
P2F1HZ   DS    CL2           Hurricane Evacuation Zone                  00930092
         DS    CL11          Filler                                     00940092
P2F1UHNS DS    CL11          Underlying HNS                             00950092
P2F1B7SC DS    CL8           "True" Borough 7 Digit Street Code         00960092
P2F1SEGT DS    CL7           Segment Identifier                         00970092
P2F1CURV DS    CL1           Curve Flag                                 00980092
P2F1END  EQU   *                                                        00990092
P2F1LEN  EQU   P2F1END-P2BAL      Length of WA 2 for Fn 1               01000092
*                                                                       01010092
*********************************************************************   01020092
         ORG   P2LAYOUT      RESET LOCATION COUNTER FOR FUNCTION 2      01030092
*********************************************************************   01040092
*                                                                       01050092
P2F2DUPI DS    CL1           DUPLICATE INTERSECT FLAG                   01060092
P2F2LGC1 DS    CL2           STREET 1 PREFERRED LGC                     01070092
P2F2LGC2 DS    CL2           STREET 2 PREFERRED LGC                     01080092
P2F2#INT DS    CL1           NUMBER OF INTERSECTING STREETS             01090092
P2F2CODE DS    CL30          INTERSECTING B5SC'S                        01100092
P2F2CDUP DS    CL1           COMPASS DIRECTION FOR TWO LOWEST           01110092
P2F2AP   DS    CL3           ATOMIC POLYGON                             01120092
         DS    CL2           FILLER                                     01130092
P2F2NDNB DS    CL7           LION NODE NUMBER                           01140092
P2F2XCOR DS    CL7           X COORDINATE                               01150092
P2F2YCOR DS    CL7           Y COORDINATE                               01160092
P2F2ZCOR DS    CL7           Z Coordinate - Not Impl.                   01170092
P2F2SVP1 DS   0CL8           FIRST SANBORN BOROUGH, PAGE, VOLUME        01180092
P2F2SB1  DS    CL1           FIRST SANBORN BOROUGH CODE                 01190092
P2F2SP1  DS    CL3           FIRST SANBORN PAGE                         01200092
P2F2SV1  DS    CL4           FIRST SANBORN VOLUME                       01210092
P2F2SVP2 DS   0CL8           SECOND SANBORN BOROUGH, PAGE, VOLUME       01220092
P2F2SB2  DS    CL1           SECOND SANBORN BOROUGH CODE                01230092
P2F2SP2  DS    CL3           SECOND SANBORN PAGE                        01240092
P2F2SV2  DS    CL4           SECOND SANBORN VOLUME                      01250092
P2F2MHRI DS    CL1           MARBLE HILL/RIKERS ISLAND FLAG             01260092
```

```
P2F2SLA  DS    CL1          STREET LIGHT AREA                        01270092
P2F2CD   DS   0CL3          COMMUNITY DISTRICT                       01280092
P2F2CDB  DS    CL1          COMMUNITY DISTRICT BORO                  01290092
P2F2CDN  DS    CL2          COMMUNITY DISTRICT NUMBER                01300092
P2F2ZIP  DS    CL5          ZIP CODE                                 01310092
P2F2HA   DS    CL4          HEALTH AREA                              01320092
P2F2POL  DS   0CL4          POLICE DISTRICT                          01330092
P2F2PBC  DS    CL1          POLICE PATROL BORO COMMAND               01340092
P2F2POP  DS    CL3          POLICE PRECINCT                          01350092
P2F2FS   DS    CL2          FIRE DIVISION                            01360092
P2F2FB   DS    CL2          FIRE BATTALION                           01370092
P2F2FC   DS   0CL4          FIRE COMPANY                             01380092
P2F2FCT  DS    CL1          FIRE COMPANY TYPE                        01390092
P2F2FCN  DS    CL3          FIRE COMPANY NUMBER                      01400092
P2F2SCH  DS    CL2          SCHOOL DISTRICT                          01410092
P2F2CT10 DS    CL6          2010 CENSUS TRACT                        01420092
P2F2CT90 DS    CL6          1990 CENSUS TRACT                        01430092
P2F2LEVC DS    CL10         Level Codes                              01440092
P2F2PPB  DS    CL2          Police Patrol Borough                    01450092
P2F2AD   DS    CL2          ASSEMBLY DISTRICT                        01460092
P2F2CON  DS    CL2          CONGRESSIONAL DISTRICT                   01470092
P2F2SEN  DS    CL2          SENATORIAL DISTRICT                      01480092
P2F2CIV  DS    CL2          CIVIL COURT DISTRICT                     01490092
P2F2COU  DS    CL2          CITY COUNCIL DISTRICT                    01500092
P2F2RES1 DS    CL1          CD ELIGIBILITY                           01510092
P2F2DDST DS    CL5          DUPLICATE INTERSECTION DISTANCE          01520092
P2F2T00  DS    CL6          2000 CENSUS TRACT                        01530092
P2F2HCD  DS    CL2          HEALTH CENTER DISTRICT                   01540092
P2F2SD   DS    CL3          SANITATION DISTRICT                      01550092
P2F2SANT DS    CL2          SANITATION DEPT SECTION/SUBSECTION       01560092
         DS    CL12         FILLER                                   01570092
P2F2END  EQU   *                                                     01580092
P2F2LEN  EQU   P2F2END-P2BAL      Length of WA 2 for Fn 2/2C         01590092
*                                                                    01600092
*********************************************************************01610092
         ORG   P2LAYOUT      RESET LOCATION COUNTER FOR FUNCTION 2W  01620092
*********************************************************************01630092
*                                                                    01640092
P22WDUPI DS    CL1          DUPLICATE INTERSECT FLAG                 01650092
P22WLGC1 DS    CL2          STREET 1 PREFERRED LGC                   01660092
P22WLGC2 DS    CL2          STREET 2 PREFERRED LGC                   01670092
P22W#INT DS    CL1          NUMBER OF INTERSECTING STREETS           01680092
P22WCODE DS    CL30         INTERSECTING B5SC'S                      01690092
P22WCDUP DS    CL1          COMPASS DIRECTION FOR TWO LOWEST         01700092
P22WAP   DS    CL3          ATOMIC POLYGON                           01710092
```

```
         DS    CL2          FILLER                                  01720092
P22WNDNB DS    CL7          LION NODE NUMBER                        01730092
P22WXCOR DS    CL7          X COORDINATE                            01740092
P22WYCOR DS    CL7          Y COORDINATE                            01750092
P22WZCOR DS    CL7          Z Coordinate - Not Impl.                01760092
P22WSVP1 DS   0CL8          FIRST SANBORN BOROUGH, PAGE, VOLUME     01770092
P22WSB1  DS    CL1          FIRST SANBORN BOROUGH CODE              01780092
P22WSP1  DS    CL3          FIRST SANBORN PAGE                      01790092
P22WSV1  DS    CL4          FIRST SANBORN VOLUME                    01800092
P22WSVP2 DS   0CL8          SECOND SANBORN BOROUGH, PAGE, VOLUME    01810092
P22WSB2  DS    CL1          SECOND SANBORN BOROUGH CODE             01820092
P22WSP2  DS    CL3          SECOND SANBORN PAGE                     01830092
P22WSV2  DS    CL4          SECOND SANBORN VOLUME                   01840092
P22WMHRI DS    CL1          MARBLE HILL/RIKERS ISLAND FLAG          01850092
P22WSLA  DS    CL1          STREET LIGHT AREA                       01860092
P22WCD   DS   0CL3          COMMUNITY DISTRICT                      01870092
P22WCDB  DS    CL1          COMMUNITY DISTRICT BORO                 01880092
P22WCDN  DS    CL2          COMMUNITY DISTRICT NUMBER               01890092
P22WZIP  DS    CL5          ZIP CODE                                01900092
P22WHA   DS    CL4          HEALTH AREA                             01910092
P22WPOL  DS   0CL4          POLICE DISTRICT                         01920092
P22WPBC  DS    CL1          POLICE PATROL BORO COMMAND              01930092
P22WPOP  DS    CL3          POLICE PRECINCT                         01940092
P22WFS   DS    CL2          FIRE DIVISION                           01950092
P22WFB   DS    CL2          FIRE BATTALION                          01960092
P22WFC   DS   0CL4          FIRE COMPANY                            01970092
P22WFCT  DS    CL1          FIRE COMPANY TYPE                       01980092
P22WFCN  DS    CL3          FIRE COMPANY NUMBER                     01990092
P22WSCH  DS    CL2          SCHOOL DISTRICT                         02000092
P22WCT10 DS    CL6          2010 CENSUS TRACT                       02010092
P22WCT90 DS    CL6          1990 CENSUS TRACT                       02020092
P22WLEVC DS    CL10         Level Codes                             02030092
P22WPPB  DS    CL2          Police Patrol Borough                   02040092
*        DS    CL2          FILLER                                  02050092
P22WAD   DS    CL2          ASSEMBLY DISTRICT                       02060092
P22WCON  DS    CL2          CONGRESSIONAL DISTRICT                  02070092
P22WSEN  DS    CL2          SENATORIAL DISTRICT                     02080092
P22WCIV  DS    CL2          CIVIL COURT DISTRICT                    02090092
P22WCOU  DS    CL2          CITY COUNCIL DISTRICT                   02100092
P22WRES1 DS    CL1          CD ELIGIBILITY                          02110092
P22WDDST DS    CL5          DUPLICATE INTERSECTION DISTANCE         02120092
P22WT00  DS    CL6          2000 CENSUS TRACT                       02130092
P22WHCD  DS    CL2          HEALTH CENTER DISTRICT                  02140092
P22WSD   DS    CL3          SANITATION DISTRICT                     02150092
P22WSANT DS    CL2          SANITATION DEPT SECTION/SUBSECTION      02160092
```

```
         DS    CL12          FILLER                                    02170092
P22WGFIL DS    CL22          FILLER FOR GRID GENERATION                02180092
P22WLGCF DS    CL8           UP TO 4 LGCS FOR FIRST INTERSECTING STR   02190092
P22WLGCS DS    CL8           UP TO 4 LGCS FOR SECOND INTERSECTING STR  02200092
P22WTR   DS    CL10          TURN RESTRICTIONS                         02210092
P22WPLGC DS    CL10          PREFERRED LGCS FOR 5 STS IN ST LIST       02220092
P22WTRC  DS    CL2           TRUE REPLICATION COUNTER                  02230092
P22WDNOD DS    20CL7         LIST OF 20 7-BYTE DUPLICATE NODES         02240092
P22WS7SC DS    CL3200        B7SCS FOR NODE LIST(20*5*4*8)             02250092
P22WRC   DS    CL1           REASON CODE                               02260092
P22WRCQ  DS    CL1           REASON CODE QUALIFIER                     02270092
P22WWC   DS    CL2           WARNING CODE                              02280092
P22WGRC  DS    CL2           RETURN CODE                               02290092
P22WLAT  DS    CL9           LATITUDE CALC FROM X-Y                    02300092
P22WLON  DS    CL11          LONGITUDE CALC FROM X-Y                   02310092
         DS    CL374         FILLER                                    02320092
P22WEND  EQU   *                                                       02330092
P22WLEN  EQU   P22WEND-P2BAL      Length of WA 2 for Fn 2W             02340092
*********************************************************************   02350092
         ORG   P2LAYOUT      RESET LOCATION COUNTER FOR FUNCTION 3     02360092
*********************************************************************   02370092
*                                                                      02380092
P2F3DUPF DS   0CL1           DUPLICATE KEY FLAG                        02390092
P2F3PAR  DS    CL1           CONTINUOUS PARITY INDICATOR               02400092
P2F3LST  DS    CL1           Locational Status of Segment              02410092
P2F3CBI  DS    CL1           County Boundary Indicator                 02420092
P2F3LGC1 DS    CL2           STREET 1 PREFERRED LGC                    02430092
P2F3LGC2 DS    CL2           STREET 2 PREFERRED LGC                    02440092
P2F3LGC3 DS    CL2           STREET 3 PREFERRED LGC                    02450092
P2F3#STL DS    CL1           NUMBER OF CROSS STREETS AT LOW END        02460092
P2F3CDEL DS    CL30          CROSS STREET B5SC'S AT LOW END            02470092
P2F3#STH DS    CL1           NUMBER OF CROSS STREETS AT HIGH END       02480092
P2F3CDEH DS    CL30          CROSS STREET B5SC'S AT HIGH END           02490092
P2F3REVF DS    CL1           REVERSAL FLAG                             02500092
P2F3KEY  DS   0CL10          LION KEY                                  02510092
P2F3BOR  DS    CL1           LION BOROUGH CODE                         02520092
P2F3FACE DS    CL4           LION FACE CODE                            02530092
P2F3SEQ  DS    CL5           LION SEQUENCE NUMBER                      02540092
P2F3GEN  DS    CL1           GENERATED RECORD FLAG                     02550092
P2F3SEGL DS    CL5           SEGMENT LENGTH IN FEET                    02560092
P2F3SLOP DS    CL3           SEGMENT SLOPE IN DEGREES                  02570092
P2F3ORNT DS    CL1           SEGMENT ORIENTATION                       02580092
P2F3MHRI DS    CL1           MARBLE HILL/RIKERS ISLAND FLAG            02590092
P2F3FROM DS    CL7           FROM NODE                                 02600092
P2F3TO   DS    CL7           TO NODE                                   02610092
```

```
P2F3SP   DS    CL1          SANITATION STREET SNOW PRIORITY          02620092
         DS    CL4          Future Use                               02630092
*                                                                    02640092
*                           Apply to both sides of street            02650092
*                                                                    02660092
P2F3SEGT DS    CL7          Segment Identifier                       02670092
P2F3SLA  DS    CL1          STREET LIGHT AREA                        02680092
P2F3CURV DS    CL1          Curve Flag                               02690092
P2F3DGLG DS    CL1          Dog Leg Flag                             02700092
P2F3FEAT DS    CL1          Feature Type Code                        02710092
P2F3STC  DS    CL1          Segment Type Code                        02720092
P2F3CSC  DS    CL1          Coincident Segment Count                 02730092
         DS    CL4          Future Use                               02740092
*                                                                    02750092
*                           Left Side of Street                      02760092
*                                                                    02770092
P2F3CDL  DS   0CL3          LEFT COMMUNITY DISTRICT                  02780092
P2F3CDBL DS    CL1          LEFT COMMUNITY DISTRICT BORO             02790092
P2F3CDNL DS    CL2          LEFT COMMUNITY DISTRICT NUMBER           02800092
P2F3LO#L DS    CL16         LEFT LOW HOUSE NUMBER                    02810092
P2F3HI#L DS    CL16         LEFT HIGH HOUSE NUMBER                   02820092
         DS    CL32              Future Use                          02830092
P2F3RS2L DS    CL1          RESERVED FOR DCP/GSS USE                 02840092
P2F3ZIPL DS    CL5          LEFT ZIP CODE                            02850092
P2F3HAL  DS    CL4          LEFT HEALTH AREA                         02860092
P2F3POLL DS   0CL4          LEFT POLICE DISTRICT                     02870092
P2F3PBCL DS    CL1          LEFT POLICE PATROL BORO COMMAND          02880092
P2F3POPL DS    CL3          LEFT POLICE PRECINCT                     02890092
P2F3FSL  DS    CL2          LEFT FIRE DIVISION                       02900092
P2F3FBL  DS    CL2          LEFT FIRE BATTALION                      02910092
P2F3FCL  DS   0CL4          LEFT FIRE COMPANY                        02920092
P2F3FCTL DS    CL1          LEFT FIRE COMPANY TYPE                   02930092
P2F3FCNL DS    CL3          LEFT FIRE COMPANY NUMBER                 02940092
P2F3SCHL DS    CL2          LEFT SCHOOL DISTRICT                     02950092
P2F3CPBL DS    CL3          LEFT DYNAMIC BLOCK/ATOMIC POLYGON        02960092
P2F3EDL  DS    CL3          LEFT ED                                  02970092
P2F3ADL  DS    CL2          LEFT AD                                  02980092
P2F3PPBL DS    CL2          Left Police Patrol Borough               02990092
         DS    CL1          Filler                                   03000092
P2F3BROL DS    CL1          Left BOROUGH CODE                        03010092
P2F3TR9L DS    CL6          Left 1990 CENSUS TRACT                   03020092
P2F3C10L DS    CL6          Left 2010 CENSUS TRACT                   03030092
P2F3B10L DS    CL4          Left 2010 CENSUS BLOCK NUMBER            03040092
P2F3BS1L DS    CL1          Left 2010 CENSUS BLOCK SUFFIX-NOT IMPLEMNT 03050092
P2F3T00L DS    CL6          Left 2000 CENSUS TRACT                   03060092
```

```
P2F3B00L DS    CL4          Left 2000 CENSUS BLOCK NUMBER             03070092
P2F3S00L DS    CL1          Left 2000 CENSUS BLOCK SUFFIX             03080092
         DS    CL7          Filler                                    03090092
*P2F3BIDL DS    CL7          Left BLOCKFACE ID                        03100092
P2F3NTAL DS    CL4          Left NEIGHBORHOOD TABULATION AREA         03110092
         DS    CL8          Future Use                                03120092
*                                                                     03130092
*                           Right Side of Street                      03140092
*                                                                     03150092
P2F3CDR  DS   0CL3          RIGHT COMMUNITY DISTRICT                  03160092
P2F3CDBR DS    CL1          RIGHT COMMUNITY DISTRICT BORO             03170092
P2F3CDNR DS    CL2          RIGHT COMMUNITY DISTRICT NUMBER           03180092
P2F3LO#R DS    CL16         RIGHT LOW HOUSE NUMBER                    03190092
P2F3HI#R DS    CL16         RIGHT HIGH HOUSE NUMBER                   03200092
         DS    CL32               Future Use                          03210092
P2F3RS2R DS    CL1          RESERVED FOR DCP/GSS USE                  03220092
P2F3ZIPR DS    CL5          RIGHT ZIP CODE                            03230092
P2F3HAR  DS    CL4          RIGHT HEALTH AREA                         03240092
P2F3POLR DS   0CL4          RIGHT POLICE DISTRICT                     03250092
P2F3PBCR DS    CL1          RIGHT POLICE PATROL BORO COMMAND          03260092
P2F3POPR DS    CL3          RIGHT POLICE PRECINCT                     03270092
P2F3FSR  DS    CL2          RIGHT FIRE DIVISION                       03280092
P2F3FBR  DS    CL2          RIGHT FIRE BATTALION                      03290092
P2F3FCR  DS   0CL4          RIGHT FIRE COMPANY                        03300092
P2F3FCTR DS    CL1          RIGHT FIRE COMPANY TYPE                   03310092
P2F3FCNR DS    CL3          RIGHT FIRE COMPANY NUMBER                 03320092
P2F3SCHR DS    CL2          RIGHT SCHOOL DISTRICT                     03330092
P2F3CPBR DS    CL3          RIGHT DYNAMIC BLOCK/ATOMIC POLYGON        03340092
P2F3EDR  DS    CL3          RIGHT ED                                  03350092
P2F3ADR  DS    CL2          RIGHT AD                                  03360092
P2F3PPBR DS    CL2          Right Police Patrol Borough               03370092
         DS    CL1          Filler                                    03380092
P2F3BROR DS    CL1          Right BOROUGH CODE                        03390092
P2F3TR9R DS    CL6          Right 1990 CENSUS TRACT                   03400092
P2F3C10R DS    CL6          Right 2010 CENSUS TRACT                   03410092
P2F3B10R DS    CL4          Right 2010 CENSUS BLOCK                   03420092
P2F3BS1R DS    CL1          Right 2010 CENSUS BLOCK SUFFIX NOT IMPLM  03430092
P2F3T00R DS    CL6          Right 2000 CENSUS TRACT                   03440092
P2F3B00R DS    CL4          Right 2000 CENSUS BLOCK                   03450092
P2F3S00R DS    CL1          Right 2000 CENSUS BLOCK SUFFIX            03460092
*P2F3BIDR DS    CL7          RIGHT BLOCKFACE ID                       03470092
         DS    CL7          Filler V16.1                              03480092
P2F3NTAR DS    CL4          RIGHT NEIGHBORHOOD TABULATION AREA        03490092
         DS    CL8          Future Use                                03500092
P2F3END  EQU   *                                                      03510092
```

```
P2F3LEN  EQU   P2F3END-P2BAL      Length of WA 2 for Fn 3              03520092
*                                                                     03530092
*********************************************************************  03540092
         ORG   P2F3END       Auxiliary Segment Overlay - FUNCTION 3   03550092
*********************************************************************  03560092
*                                                                     03570092
P2F3FILR DS    CL6           Future Use                               03580092
P2F3SCNT DS    CL4           Number of segment ids                    03590092
P2F3SGID DS    CL490         up to 70 Seven Byte Segment IDS          03600092
P2F3SEND EQU   *                                                      03610092
P2F3SLEN EQU   P2F3SEND-P2BAL  Length of WA 2 for Fn 3 w/segments     03620092
*                                                                     03630092
*********************************************************************  03640092
         ORG   P2LAYOUT  RESET LOCATION COUNTER-FUNCTION 3 EXTENDED   03650092
*********************************************************************  03660092
*                                                                     03670092
P23XDUPF DS   0CL1           DUPLICATE KEY FLAG                       03680092
P23XPAR  DS    CL1           CONTINUOUS PARITY INDICATOR              03690092
P23XLST  DS    CL1           Locational Status of Segment             03700092
P23XCBI  DS    CL1           County Boundary Indicator                03710092
P23XLGC1 DS    CL2           STREET 1 PREFERRED LGC                   03720092
P23XLGC2 DS    CL2           STREET 2 PREFERRED LGC                   03730092
P23XLGC3 DS    CL2           STREET 3 PREFERRED LGC                   03740092
P23X#STL DS    CL1           NUMBER OF CROSS STREETS AT LOW END       03750092
P23XCDEL DS    CL30          CROSS STREET B5SC'S AT LOW END           03760092
P23X#STH DS    CL1           NUMBER OF CROSS STREETS AT HIGH END      03770092
P23XCDEH DS    CL30          CROSS STREET B5SC'S AT HIGH END          03780092
P23XREVF DS    CL1           REVERSAL FLAG                            03790092
P23XKEY  DS   0CL10          LION KEY                                 03800092
P23XBOR  DS    CL1           LION BOROUGH CODE                        03810092
P23XFACE DS    CL4           LION FACE CODE                           03820092
P23XSEQ  DS    CL5           LION SEQUENCE NUMBER                     03830092
P23XGEN  DS    CL1           GENERATED RECORD FLAG                    03840092
P23XSEGL DS    CL5           SEGMENT LENGTH IN FEET                   03850092
P23XSLOP DS    CL3           SEGMENT SLOPE IN DEGREES                 03860092
P23XORNT DS    CL1           SEGMENT ORIENTATION                      03870092
P23XMHRI DS    CL1           MARBLE HILL/RIKERS ISLAND FLAG           03880092
P23XFROM DS    CL7           FROM NODE                                03890092
P23XTO   DS    CL7           TO NODE                                  03900092
P23XSP   DS    CL1           SANITATION STREET SNOW PRIORITY          03910092
         DS    CL4           Future Use                               03920092
*                                                                     03930092
*                            Apply to both sides of street            03940092
*                                                                     03950092
P23XSEGT DS    CL7           Segment Identifier                       03960092
```

```
P23XSLA  DS    CL1          STREET LIGHT AREA                        03970092
P23XCURV DS    CL1          Curve Flag                               03980092
P23XDGLG DS    CL1          Dog Leg Flag                             03990092
P23XFEAT DS    CL1          Feature Type Code                        04000092
P23XSTC  DS    CL1          Segment Type Code                        04010092
P23XCSC  DS    CL1          Coincident Segment Count                 04020092
         DS    CL4          Future Use                               04030092
*                                                                    04040092
*                           Left Side of Street                      04050092
*                                                                    04060092
P23XCDL  DS   0CL3          LEFT COMMUNITY DISTRICT                  04070092
P23XCDBL DS    CL1          LEFT COMMUNITY DISTRICT BORO             04080092
P23XCDNL DS    CL2          LEFT COMMUNITY DISTRICT NUMBER           04090092
P23XLO#L DS    CL16         LEFT LOW HOUSE NUMBER                    04100092
P23XHI#L DS    CL16         LEFT HIGH HOUSE NUMBER                   04110092
         DS    CL32              Future Use                          04120092
P23XRS2L DS    CL1          RESERVED FOR DCP/GSS USE                 04130092
P23XZIPL DS    CL5          LEFT ZIP CODE                            04140092
P23XHAL  DS    CL4          LEFT HEALTH AREA                         04150092
P23XPOLL DS   0CL4          LEFT POLICE DISTRICT                     04160092
P23XPBCL DS    CL1          LEFT POLICE PATROL BORO COMMAND          04170092
P23XPOPL DS    CL3          LEFT POLICE PRECINCT                     04180092
P23XFSL  DS    CL2          LEFT FIRE DIVISION                       04190092
P23XFBL  DS    CL2          LEFT FIRE BATTALION                      04200092
P23XFCL  DS   0CL4          LEFT FIRE COMPANY                        04210092
P23XFCTL DS    CL1          LEFT FIRE COMPANY TYPE                   04220092
P23XFCNL DS    CL3          LEFT FIRE COMPANY NUMBER                 04230092
P23XSCHL DS    CL2          LEFT SCHOOL DISTRICT                     04240092
P23XCPBL DS    CL3          LEFT DYNAMIC BLOCK/ATOMIC POLYGON        04250092
P23XEDL  DS    CL3          LEFT ED                                  04260092
P23XADL  DS    CL2          LEFT AD                                  04270092
P23XPPBL DS    CL2          Left Police Patrol Borough               04280092
         DS    CL1          Filler                                   04290092
P23XBROL DS    CL1          Left BOROUGH CODE                        04300092
P23XTR9L DS    CL6          Left 1990 CENSUS TRACT                   04310092
P23XC10L DS    CL6          Left 2010 CENSUS TRACT                   04320092
P23XB10L DS    CL4          Left 2010 CENSUS BLOCK NUMBER            04330092
P23XBS1L DS    CL1          Left 2010 CENSUS BLOCK SUFFIX-NOT IMPLEMNT 04340092
P23XT00L DS    CL6          Left 2000 CENSUS TRACT                   04350092
P23XB00L DS    CL4          Left 2000 CENSUS BLOCK NUMBER            04360092
P23XS00L DS    CL1          Left 2000 CENSUS BLOCK SUFFIX            04370092
*P23XBIDL DS    CL7          Left BLOCKFACE ID                       04380092
         DS    CL7          Filler                                   04390092
P23XNTAL DS    CL4          Left NEIGHBORHOOD TABULATION AREA        04400092
         DS    CL8          Future Use                               04410092
```

```
*                                                                  04420092
*                          Right Side of Street                    04430092
*                                                                  04440092
P23XCDR  DS   0CL3         RIGHT COMMUNITY DISTRICT                04450092
P23XCDBR DS    CL1         RIGHT COMMUNITY DISTRICT BORO           04460092
P23XCDNR DS    CL2         RIGHT COMMUNITY DISTRICT NUMBER         04470092
P23XLO#R DS    CL16        RIGHT LOW HOUSE NUMBER                  04480092
P23XHI#R DS    CL16        RIGHT HIGH HOUSE NUMBER                 04490092
         DS    CL32              Future Use                        04500092
P23XRS2R DS    CL1         RESERVED FOR DCP/GSS USE                04510092
P23XZIPR DS    CL5         RIGHT ZIP CODE                          04520092
P23XHAR  DS    CL4         RIGHT HEALTH AREA                       04530092
P23XPOLR DS   0CL4         RIGHT POLICE DISTRICT                   04540092
P23XPBCR DS    CL1         RIGHT POLICE PATROL BORO COMMAND        04550092
P23XPOPR DS    CL3         RIGHT POLICE PRECINCT                   04560092
P23XFSR  DS    CL2         RIGHT FIRE DIVISION                     04570092
P23XFBR  DS    CL2         RIGHT FIRE BATTALION                    04580092
P23XFCR  DS   0CL4         RIGHT FIRE COMPANY                      04590092
P23XFCTR DS    CL1         RIGHT FIRE COMPANY TYPE                 04600092
P23XFCNR DS    CL3         RIGHT FIRE COMPANY NUMBER               04610092
P23XSCHR DS    CL2         RIGHT SCHOOL DISTRICT                   04620092
P23XCPBR DS    CL3         RIGHT DYNAMIC BLOCK/ATOMIC POLYGON      04630092
P23XEDR  DS    CL3         RIGHT ED                                04640092
P23XADR  DS    CL2         RIGHT AD                                04650092
P23XPPBR DS    CL2         Right Police Patrol Borough             04660092
         DS    CL1         Filler                                  04670092
P23XBROR DS    CL1         Right BOROUGH CODE                      04680092
P23XTR9R DS    CL6         Right 1990 CENSUS TRACT                 04690092
P23XC10R DS    CL6         Right 2010 CENSUS TRACT                 04700092
P23XB10R DS    CL4         Right 2010 CENSUS BLOCK                 04710092
P23XBS1R DS    CL1         Right 2010 CENSUS BLOCK SUFFIX NOT IMPLM 04720092
P23XT00R DS    CL6         Right 2000 CENSUS TRACT                 04730092
P23XB00R DS    CL4         Right 2000 CENSUS BLOCK                 04740092
P23XS00R DS    CL1         Right 2000 CENSUS BLOCK SUFFIX          04750092
*P23XBIDR DS    CL7         RIGHT BLOCKFACE ID                     04760092
         DS    CL7         Filler                                  04770092
P23XNTAR DS    CL4         RIGHT NEIGHBORHOOD TABULATION AREA      04780092
         DS    CL8         Future Use                              04790092
P23XLGCS DS    CL8         List of 4 LGCs                          04800092
P23XLGCF DS    CL8         List of 4 From LGCs                     04810092
P23XLGCT DS    CL8         List of 4 To LGCs                       04820092
P23XLHCD DS    CL2         Left Health Center District             04830092
P23XRHCD DS    CL2         Right Health Center District            04840092
P23XFILS DS    CL1         Filler                                  04850092
P23XTD   DS    CL1         Traffic Direction                       04860092
```

```
P23XRTP  DS    CL2          Roadyway Type                          04870092
P23XPID  DS    CL7          Physical Id                            04880092
P23XGID  DS    CL7          Generic Id                             04890092
P23XPDID DS    CL7          For DCP Use Only                       04900092
P23XFDID DS    CL7          For DCP Use Only                       04910092
P23XSTST DS    CL1          Street Status                          04920092
P23XSTW  DS    CL3          Street Width                           04930092
P23XSTWI DS    CL1          Street Width Irregular                 04940092
P23XBL   DS    CL1          Bike Lane                              04950092
P23XFCC  DS    CL2          Federal Classification Code            04960092
P23XROW  DS    CL1          Row Type                               04970092
P23XLGC5 DS    CL10         List of 5 LGCs                         04980092
P23XLGID DS    CL7          Legacy Id                              04990092
P23XLNTA DS    CL75         Left NTA Name                          05000092
P23XRNTA DS    CL75         Right NTA Name                         05010092
P23XFXC  DS    CL7          From X Coordinate                      05020092
P23XFYC  DS    CL7          From Y Coordinate                      05030092
P23XTXC  DS    CL7          To X Coordinate                        05040092
P23XTYC  DS    CL7          To Y Coordinate                        05050092
P23XFLAT DS    CL9          LATITUDE OF FROM INTERSCT.             05060092
P23XFLON DS    CL11         LONGITUDE OF FROM INTERSCT.            05070092
P23XTLAT DS    CL9          LATITUDE OF TO INTERSCT.               05080092
P23XTLON DS    CL11         LONGITUDE OF TO INTERSCT.              05090092
P23XBIDL DS    CL10         NEW location Left Blockface Id V16.1   05100092
P23XBIDR DS    CL10         NEW location Right Blockface Id V16.1  05110092
P23X#TRL DS    CL2          nbr of traveling lanes                 05120092
P23X#PKL DS    CL2          nbr of parking lanes                   05130092
P23X#TLL DS    CL2          nbr of total lanes                     05140092
P23XBL2  DS    CL2          Bike Lane 2 (has 2 bytes numeric value) 05150092
P23XSTWX DS    CL3          Street Width Maximum                   05160092
P23XBTD  DS    CL2          Bike Traffic Direction                 05170092
P23XSPDL DS    CL2          Speed Limit                            05171094
P23XPUML DS    CL5          PUMA CODE (left)                       05172097
P23XPUMR DS    CL5          PUMA CODE (right)                      05173097
P23XFILL DS    CL201        FILLER                                 05180097
P23XEND  EQU   *                                                   05190092
P23XLEN  EQU   P23XEND-P2BAL      Length of WA 2 for Fn 3 Extended 05200092
*                                                                  05210092
*******************************************************************05220092
         ORG   P23XEND  Auxiliary Seg Overlay - FUNCTION 3 EXTENDED 05230092
*******************************************************************05240092
*                                                                  05250092
P23XFILR DS    CL6          Future Use                             05260092
P23XSCNT DS    CL4          Number of segment ids                  05270092
P23XSGID DS    CL490        up to 70 Seven Byte Segment IDS        05280092
```

```
P23XSEND EQU   *                                                       05290092
P23XSLEN EQU   P23XSEND-P2BAL  Len of WA2 for Fn3 MODE=X w/segments     05300092
*                                                                      05310092
*********************************************************************  05320092
         ORG   P2LAYOUT      RESET LOCATION COUNTER FOR FUNCTION 3C    05330092
*********************************************************************  05340092
*                                                                      05350092
P23CDUPF DS   0CL1           DUPLICATE KEY FLAG                        05360092
P23CPAR  DS    CL1           CONTINUOUS PARITY INDICATOR               05370092
P23CLST  DS    CL1           Locational Status of Segment              05380092
P23CCBI  DS    CL1           County Boundary Indicator                 05390092
P23CLGC1 DS    CL2           STREET 1 PREFERRED LGC                    05400092
P23CLGC2 DS    CL2           STREET 2 PREFERRED LGC                    05410092
P23CLGC3 DS    CL2           STREET 3 PREFERRED LGC                    05420092
P23C#STL DS    CL1           NUMBER OF CROSS STREETS AT LOW END        05430092
P23CCDEL DS    CL30          CROSS STREET B5SC'S AT LOW END            05440092
P23C#STH DS    CL1           NUMBER OF CROSS STREETS AT HIGH END       05450092
P23CCDEH DS    CL30          CROSS STREET B5SC'S AT HIGH END           05460092
P23CREVF DS    CL1           REVERSAL FLAG                             05470092
P23CKEY  DS   0CL10          LION KEY                                  05480092
P23CBOR  DS    CL1           LION BOROUGH CODE                         05490092
P23CFACE DS    CL4           LION FACE CODE                            05500092
P23CSEQ  DS    CL5           LION SEQUENCE NUMBER                      05510092
P23CGEN  DS    CL1           GENERATED RECORD FLAG                     05520092
P23CSEGL DS    CL5           SEGMENT LENGTH IN FEET                    05530092
P23CSLOP DS    CL3           SEGMENT SLOPE IN DEGREES                  05540092
P23CORNT DS    CL1           SEGMENT ORIENTATION                       05550092
P23CMHRI DS    CL1           MARBLE HILL/RIKERS ISLAND FLAG            05560092
P23CFROM DS    CL7           FROM NODE                                 05570092
P23CTO   DS    CL7           TO NODE                                   05580092
P23CSP   DS    CL1           SANITATION STREET SNOW PRIORITY           05590092
         DS    CL4           Future Use                                05600092
*                                                                      05610092
*                            Side of Street Information                05620092
*                                                                      05630092
P23CSEGT DS    CL7           Segment Identifier                        05640092
P23CSLA  DS    CL1           STREET LIGHT AREA                         05650092
P23CSOS  DS    CL1           Side of Street Indicator                  05660092
P23CCURV DS    CL1           Curve Flag                                05670092
P23CFEAT DS    CL1           Feature Type Code                         05680092
P23CSTC  DS    CL1           Segment Type Code                         05690092
P23CCSC  DS    CL1           COINCIDENT SEGMENT COUNT                  05700092
         DS    CL4           Future Use                                05710092
P23CCD   DS   0CL3           COMMUNITY DISTRICT                        05720092
P23CCDB  DS    CL1           COMMUNITY DISTRICT BORO                   05730092
```

```
P23CCDN  DS    CL2           COMMUNITY DISTRICT NUMBER                 05740092
P23CLO#  DS    CL16          LOW HOUSE NUMBER                          05750092
P23CHI#  DS    CL16          HIGH HOUSE NUMBER                         05760092
P23CHS2L DS    CL16          2ND LOW HSE # - USED IF ODD & EVEN RANGES 05770092
P23CHS2H DS    CL16          2ND HI HSE #    ARE ON SAME SIDE OF STREET 05780092
P23CRES2 DS    CL1           RESERVED FOR DCP/GSS USE                  05790092
P23CZIP  DS    CL5           ZIP CODE                                  05800092
P23CHAL  DS    CL4           HEALTH AREA                               05810092
P23CPOL  DS   0CL4           POLICE DISTRICT                           05820092
P23CPBC  DS    CL1           POLICE PATROL BORO COMMAND                05830092
P23CPOP  DS    CL3           POLICE PRECINCT                           05840092
P23CFS   DS    CL2           FIRE DIVISION                             05850092
P23CFB   DS    CL2           FIRE BATTALION                            05860092
P23CFC   DS   0CL4           FIRE COMPANY                              05870092
P23CFCT  DS    CL1           FIRE COMPANY TYPE                         05880092
P23CFCN  DS    CL3           FIRE COMPANY NUMBER                       05890092
P23CSCH  DS    CL2           SCHOOL DISTRICT                           05900092
P23CCPB  DS    CL3           DYNAMIC  BLOCK / ATOMIC POLYGON           05910092
P23CED   DS    CL3           ED                                        05920092
P23CAD   DS    CL2           AD                                        05930092
P23CPPB  DS    CL2           Police Patrol Borough                     05940092
         DS    CL1           Filler                                    05950092
P23CBRO  DS    CL1           BOROUGH CODE                              05960092
P23CTR9  DS    CL6           1990 CENSUS TRACT                         05970092
P23CCT10 DS    CL6           2010 CENSUS TRACT                         05980092
P23CBL10 DS    CL4           2010 CENSUS BLOCK                         05990092
P23CBL1S DS    CL1           2010 CENSUS BLOCK SUFFIX NOT IMPLEMENTED  06000092
P23CT00  DS    CL6           2000 CENSUS TRACT                         06010092
P23CB00  DS    CL4           2000 CENSUS BLOCK                         06020092
P23CS00  DS    CL1           2000 CENSUS BLOCK SUFFIX                  06030092
*P23CBID  DS    CL7          BLOCKFACE ID                              06040092
         DS    CL7           Filler V16.1                              06050092
P23CNTA  DS    CL4           NEIGHBORHOOD TABULATION AREA              06060092
         DS    CL8           Future Use                                06070092
P23CEND  EQU   *                                                       06080092
P23CLEN  EQU   P23CEND-P2BAL      Length of WA 2 for Fn 3C             06090092
*********************************************************************   06100092
         ORG   P23CEND       Auxiliary Segment Overlay - FUNCTION 3C   06110092
*********************************************************************   06120092
*                                                                      06130092
P23CFILR DS    CL6           FUTURE USE                                06140092
P23CSCNT DS    CL4           Number of segment ids                     06150092
P23CSGID DS    CL490         up to 70 Seven Byte Segment IDS           06160092
P23CSEND EQU   *                                                       06170092
P23CSLEN EQU   P23CSEND-P2BAL  Length of WA 2 for Fn 3C w/Segments     06180092
```

```
*                                                                       06190092
***********************************************************************  06200092
         ORG   P2LAYOUT RESET LOC COUNTER FOR FUNCTION 3C EXTENDED      06210092
***********************************************************************  06220092
*                                                                       06230092
P2CXDUPF DS   0CL1          DUPLICATE KEY FLAG                          06240092
P2CXPAR  DS    CL1          CONTINUOUS PARITY INDICATOR                 06250092
P2CXLST  DS    CL1          Locational Status of Segment                06260092
P2CXCBI  DS    CL1          County Boundary Indicator                   06270092
P2CXLGC1 DS    CL2          STREET 1 PREFERRED LGC                      06280092
P2CXLGC2 DS    CL2          STREET 2 PREFERRED LGC                      06290092
P2CCLGC3 DS    CL2          STREET 3 PREFERRED LGC                      06300092
P2CX#STL DS    CL1          NUMBER OF CROSS STREETS AT LOW END          06310092
P2CXCDEL DS    CL30         CROSS STREET B5SC'S AT LOW END              06320092
P2CX#STH DS    CL1          NUMBER OF CROSS STREETS AT HIGH END         06330092
P2CXCDEH DS    CL30         CROSS STREET B5SC'S AT HIGH END             06340092
P2CXREVF DS    CL1          REVERSAL FLAG                               06350092
P2CXKEY  DS   0CL10         LION KEY                                    06360092
P2CXBOR  DS    CL1          LION BOROUGH CODE                           06370092
P2CXFACE DS    CL4          LION FACE CODE                              06380092
P2CXSEQ  DS    CL5          LION SEQUENCE NUMBER                        06390092
P2CXGEN  DS    CL1          GENERATED RECORD FLAG                       06400092
P2CXSEGL DS    CL5          SEGMENT LENGTH IN FEET                      06410092
P2CXSLOP DS    CL3          SEGMENT SLOPE IN DEGREES                    06420092
P2CXORNT DS    CL1          SEGMENT ORIENTATION                         06430092
P2CXMHRI DS    CL1          MARBLE HILL/RIKERS ISLAND FLAG              06440092
P2CXFROM DS    CL7          FROM NODE                                   06450092
P2CXTO   DS    CL7          TO NODE                                     06460092
P2CXSP   DS    CL1          SANITATION STREET SNOW PRIORITY             06470092
         DS    CL4          Future Use                                  06480092
*                                                                       06490092
*                           Side of Street Information                  06500092
*                                                                       06510092
P2CXSEGT DS    CL7          Segment Identifier                          06520092
P2CXSLA  DS    CL1          STREET LIGHT AREA                           06530092
P2CXSOS  DS    CL1          Side of Street Indicator                    06540092
P2CXCURV DS    CL1          Curve Flag                                  06550092
P2CXFEAT DS    CL1          Feature Type Code                           06560092
P2CXSTC  DS    CL1          Segment Type Code                           06570092
P2CXCSC  DS    CL1          COINCIDENT SEGMENT COUNT                    06580092
         DS    CL4          Future Use                                  06590092
P2CXCD   DS   0CL3          COMMUNITY DISTRICT                          06600092
P2CXCDB  DS    CL1          COMMUNITY DISTRICT BORO                     06610092
P2CXCDN  DS    CL2          COMMUNITY DISTRICT NUMBER                   06620092
P2CXLO#  DS    CL16         LOW HOUSE NUMBER                            06630092
```

```
P2CXHI#  DS    CL16          HIGH HOUSE NUMBER                          06640092
P2CXHS2L DS    CL16          2ND LOW HSE # - USED IF ODD & EVEN RANGES  06650092
P2CXHS2H DS    CL16          2ND HI HSE #    ARE ON SAME SIDE OF STREET 06660092
P2CXRES2 DS    CL1           RESERVED FOR DCP/GSS USE                   06670092
P2CXZIP  DS    CL5           ZIP CODE                                   06680092
P2CXHAL  DS    CL4           HEALTH AREA                                06690092
P2CXPOL  DS   0CL4           POLICE DISTRICT                            06700092
P2CXPBC  DS    CL1           POLICE PATROL BORO COMMAND                 06710092
P2CXPOP  DS    CL3           POLICE PRECINCT                            06720092
P2CXFS   DS    CL2           FIRE DIVISION                              06730092
P2CXFB   DS    CL2           FIRE BATTALION                             06740092
P2CXFC   DS   0CL4           FIRE COMPANY                               06750092
P2CXFCT  DS    CL1           FIRE COMPANY TYPE                          06760092
P2CXFCN  DS    CL3           FIRE COMPANY NUMBER                        06770092
P2CXSCH  DS    CL2           SCHOOL DISTRICT                            06780092
P2CXCPB  DS    CL3           DYNAMIC  BLOCK / ATOMIC POLYGON            06790092
P2CXED   DS    CL3           ED                                         06800092
P2CXAD   DS    CL2           AD                                         06810092
P2CXPPB  DS    CL2           Police Patrol Borough                      06820092
         DS    CL1           Filler                                     06830092
P2CXBRO  DS    CL1           BOROUGH CODE                               06840092
P2CXTR9  DS    CL6           1990 CENSUS TRACT                          06850092
P2CXCT10 DS    CL6           2010 CENSUS TRACT                          06860092
P2CXBL10 DS    CL4           2010 CENSUS BLOCK                          06870092
P2CXBL1S DS    CL1           2010 CENSUS BLOCK SUFFIX NOT IMPLEMENTED   06880092
P2CXT00  DS    CL6           2000 CENSUS TRACT                          06890092
P2CXB00  DS    CL4           2000 CENSUS BLOCK                          06900092
P2CXS00  DS    CL1           2000 CENSUS BLOCK SUFFIX                   06910092
*P2CXBID  DS    CL7           BLOCKFACE ID                              06920092
         DS    CL7           Filler V16.1                               06930092
P2CXNTA  DS    CL4           NEIGHBORHOOD TABULATION AREA               06940092
         DS    CL8           Future Use                                 06950092
P2CXLGCS DS    CL8           List of 4 LGCs                             06960092
P2CXLGCF DS    CL8           List of 4 From LGCs                        06970092
P2CXLGCT DS    CL8           List of 4 To LGCs                          06980092
P2CXLHCD DS    CL2           Left Health Center District                06990092
P2CXRHCD DS    CL2           Right Health Center District               07000092
P2CXFILS DS    CL1           Filler                                     07010092
P2CXTD   DS    CL1           Traffic Direction                          07020092
P2CXRTP  DS    CL2           Roadyway Type                              07030092
P2CXPID  DS    CL7           Physical Id                                07040092
P2CXGID  DS    CL7           Generic Id                                 07050092
P2CXPDID DS    CL7           For DCP Use Only                           07060092
P2CXFDID DS    CL7           For DCP Use Only                           07070092
P2CXSTST DS    CL1           Street Status                              07080092
```

```
P2CXSTW  DS    CL3           Street Width                              07090092
P2CXSTWI DS    CL1           Street Width Irregular                    07100092
P2CXBL   DS    CL1           Bike Lane                                 07110092
P2CXFCC  DS    CL2           Federal Classification Code               07120092
P2CXROW  DS    CL1           Row Type                                  07130092
P2CXLGC5 DS    CL10          List of 5 LGCs                            07140092
P2CXLGID DS    CL7           Legacy Id                                 07150092
P2CXNTAN DS    CL75          NTA Name                                  07160092
P2CXFXC  DS    CL7           From X Coordinate                         07170092
P2CXFYC  DS    CL7           From Y Coordinate                         07180092
P2CXTXC  DS    CL7           To X Coordinate                           07190092
P2CXTYC  DS    CL7           To Y Coordinate                           07200092
P2CXFLAT DS    CL9           LATITUDE OF FROM INTERSCT.                07210092
P2CXFLON DS    CL11          LONGITUDE OF FROM INTERSCT.               07220092
P2CXTLAT DS    CL9           LATITUDE OF TO INTERSCT.                  07230092
P2CXTLON DS    CL11          LONGITUDE OF TO INTERSCT.                 07240092
P2CXBFID DS    CL10          NEW location Blockface Id V16.1           07250092
P2CX#TRL DS    CL2           nbr of traveling lanes                    07260092
P2CX#PKL DS    CL2           nbr of parking lanes                      07270092
P2CX#TLL DS    CL2           nbr of total lanes                        07280092
P2CXBL2  DS    CL2           Bike Lane2 (has 2bytes numeric value)     07290092
P2CXSTWX DS    CL3           Street Width Maximum                      07300092
P2CXBTD  DS    CL2           Bike Traffic Direction                    07310092
P2CXSPDL DS    CL2           Speed Limit                               07311094
P2CXPUMA DS    CL5           PUMA Code   V18.1                         07312098
P2CXFILL DS    CL291         FILLER                                    07320098
P2CXEND  EQU   *                                                       07330092
P2CXLEN  EQU   P2CXEND-P2BAL      Length of WA 2 for Fn 3C             07340092
*********************************************************************  07350092
         ORG   P2CXEND     Auxiliary Segment Overlay - FUNCTION 3C-X   07360092
*********************************************************************  07370092
*                                                                      07380092
P2CXFILR DS    CL6           FUTURE USE                                07390092
P2CXSCNT DS    CL4           Number of segment ids                     07400092
P2CXSGID DS    CL490         up to 70 Seven Byte Segment IDS           07410092
P2CXSEND EQU   *                                                       07420092
P2CXSLEN EQU   P2CXSEND-P2BAL  Length of WA 2 for Fn 3C-X w/Segments   07430092
*                                                                      07440092
*                                                                      07450092
*********************************************************************  07460092
         ORG   P2BAL         RESET LOCATION COUNTER FOR FUNCTION 5     07470092
*********************************************************************  07480092
*                                                                      07490092
P2F5AMK  DS    CL28          ACCESS MATCHING KEY                       07500092
         DS    CL172                                                   07510092
```

```
P2F5END  EQU   *                                                    07520092
P2F5LEN  EQU   P2F5END-P2BAL      Length of WA 2 for Fn 5            07530092
         ORG                                                        07540092
```

P2BAL1A COPY File

```
*/*********************************************************************/ 00010064
*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE P2BAL1A,  ***/ 00020064
*/*****  CONTAINING THE LAYOUT OF WORK AREA 2 FOR FUNCTION         ***/ 00030064
*/*****  1A, BL And BN WHICH SHARE A SINGLE WORK AREA 2 LAYOUT.    ***/ 00040064
*/*****  The Long Work Area only applies to Functions 1A and BL.   ***/ 00050064
*/*****  The long work area only exists if the Address Overflow    ***/ 00060064
*/*****  Flag has been set on.                                     ***/ 00070064
*/*****  As of 2011, Function 1/1E Extended, Function 1A Extended  ***/ 00080064
*/*****  and Function 1B have been added to this Copy File         ***/ 00090064
*/*****  ADDED 2 byte field "Police Patrol Borough" for functions: ***/ 00100064
*/*****  1X/1EX/1B.                                August 2014     ***/ 00110064
*/*****  ADDED 4 fields: "segment from node", "segment to node",   ***/ 00120064
*/*****  "segment from XYZ", "segment to XYZ" for func 1X/1EX/1B   ***/ 00130064
*/*****                                                 May 2015   ***/ 00140064
*/*****  ADDED 2 fields: "Bike Lane 2" and "Street Width Maximum"  ***/ 00141068
*/*****  for functions 1EX/1B                     September 2016   ***/ 00142068
*/*****  Replaced "Saniitation Reserved" with "Sanitation Bulk     ***/ 00143070
*/*****  Pick Up" for functions 1E,1B             October   2016   ***/ 00144070
*/*****  ADDED 2 bytes field "Bike Traffic Direction" for          ***/ 00145072
*/*****  for functions 1/1E (extended),1B,3X,3CX           12/2016 ***/ 00146071
*/*****  ADDED 2 bytes field "Speed Limit"                 09/2017 ***/ 00147073
*/*****  for functions 1/1E (extended),1B                          ***/ 00148074
*/*****  ADDED 3 bytes field "DCP Zoning Map"              09/2017 ***/ 00149075
*/*****  for functions 1A,BL,BN, 1A,BL,BN(extended) and 1B         ***/ 00149175
*/*****  ADDED 5 bytes field "PUMA Code" for functions:            ***/ 00149276
*/*****  1/1E (extended),1B.                              12/2017  ***/ 00149376
*/*********************************************************************/ 00150064
*/*****          LAST UPDATE -  February 2016                      ***/ 00160066
*/*********************************************************************/ 00170064
P2BAL1A  DS    0H                                                   00180064
         DS     CL21                                                00190064
P21ACPAR DS     CL1           CONTINUOUS PARITY INDICATOR           00200064
P21AHSEL DS     CL11          LOW HOUSE NUMBER ON BLOCK - HNS Form  00210064
P21AALT1 DS    0CL11          ALTERNATE KEY                         00220064
P21ABOR1 DS     CL1           ALTERNATE KEY - BORO                  00230064
P21ATXB1 DS     CL5           ALTERNATE KEY - TAX BLOCK             00240064
P21ATXL1 DS     CL4           ALTERNATE KEY - TAX LOT               00250064
         DS     CL1              Future Use                         00260064
```

```
P21ARSCC DS    CL1          RPAD SCC                                  00270064
         DS    CL1          FILLER                                    00280064
P21AGLI  DS   0CL13         GENERAL LOT INFO                          00290064
P21ARBLC DS    CL2          RPAD BUILDING CLASSIFICATION              00300064
P21ACORC DS    CL2          CORNER CODE                               00310064
P21A#STC DS    CL4          TOTAL NUMBER STRUCTURES                   00320064
P21A#BFA DS    CL2          TOTAL NUMBER BLOCKFACES                   00330064
P21AINTF DS    CL1          INTERIOR LOT FLAG                         00340064
P21AVACF DS    CL1          VACANT LOT FLAG                           00350064
P21AIRLF DS    CL1          IRREGULARLY-SHAPED LOT FLAG               00360064
*                                                                     00370064
P21AABFL DS    CL1          Marble Hill/ Rikers ALTERNATE BORO FLAG   00380064
P21AOVFL DS    CL1          Address Overflow Flag                     00390064
*                                                                     00400064
P21ASTRK DS    CL19         STROLLING KEY                             00410064
*                                                                     00420064
P21ARFIU DS    CL1          RESERVED FOR INTERNAL USE                 00430064
P21ABIN  DS    CL7          BUILDING IDENTIFICATION NUMBER (BIN)      00440064
*                          Condo Information                         00450064
P21ACONF DS    CL1          CONDO LOT FLAG                            00460064
         DS    CL1          Filler for Future Use                     00470064
P21ARCO# DS    CL4          RPAD CONDO NUMBER                         00480064
         DS    CL7          Future Use - Condo Unit Number            00490064
P21ACBBL DS    CL11         CONDO BILLING BBL                         00500064
P21ACBBS DS    CL1          CONDO BILLING BBL SCC                     00510064
P21ACLBL DS    CL11         CONDO LOW BBL                             00520064
P21ACHBL DS    CL11         CONDO HIGH BBL                            00530064
         DS    CL15         Filler                                    00540064
P21ACOOP DS    CL4          Co-op Number                              00550064
*                                                                     00560064
P21ASBVP DS    CL8          SANDBORN BOROUGH/VOLUME/PAGE              00570064
*                                                                     00580064
P21ABUSA DS    CL5          BUSINESS AREA                             00590064
P21ATAXM DS    CL5          Tax Map Number - Section and Volume       00600064
         DS    CL4          Reserved for Tax Map Page                 00610064
         DS    CL3             FILLER                                 00620064
P21ALAT  DS    CL9          LATITUDE                                  00630064
P21ALONG DS    CL11         LONGITUDE                                 00640064
P21AXCO  DS    CL7          X Coordinate of Annotation Point          00650064
P21AYCO  DS    CL7          Y Coordinate of Annotation Point          00660064
P21ABID  DS    CL6          Business Improvement District             00670064
P21ATPBS DS    CL1          TPAD BIN Status                           00680064
P21ATPNB DS    CL7          TPAD New BIN                              00690064
P21ATPNS DS    CL1          TPAD New BIN Status                       00700064
P21ATPCF DS    CL1          TPAD Conflict Flag                        00710064
```

```
P21AZMAP DS    CL3           DCP Zoning Map                          00711075
         DS    CL6           FILLER                                  00720075
         DS    CL8           Internal Use                            00730064
P21A#ADR DS    CL4           TOTAL ADDRESSES FOR LOT                 00740064
P21ALIST DS   0CL1113        LIST OF ADDRESSES, MAXIMUM OF 21        00750064
P21ALOW# DS    CL16          LOW HOUSE NUMBER-Display Form           00760064
P21AHI#  DS    CL16          HIGH HOUSE NUMBER-Display Form          00770064
P21ABCDE DS    CL1           Borough Code                            00780064
P21ACODE DS    CL5           STREET CODE                             00790064
P21APLGC DS    CL2           Preferred LGC                           00800064
P21ALBIN DS    CL7           BIN                                     00810064
P21ALSOS DS    CL1           Side of Street Indicator                00820064
P21AATP  DS    CL1           Address Type Flag                       00830064
P21AATPS DS    CL1           TPAD BIN Status                         00840064
         DS    CL3           FILLER                                  00850064
*  STORAGE IS RESERVED FOR THE REMAINING 20 ADDRESS STRUCTURES.       00860064
*  EACH STRUCTURE IS IDENTICAL TO THE ONE DEFINED ABOVE.              00870064
         DS    CL1060        REMAINING ADDRESSES                     00880064
P21ASEND EQU   *                                                     00890064
P21ASLEN EQU   P21ASEND-P2BAL1A    LENGTH OF Short P2BAL1A           00900064
*                                                                    00910064
*        Long Work Area Overlay                                      00920064
*                                                                    00930064
         ORG   P21A#ADR                                              00940064
P21A#BIN DS    CL4           Total Nbr of BINs for Lot               00950064
P21ABINS DS    2500CL7                                               00960064
P21ALEND EQU   *                                                     00970064
         ORG   P21ABINS      Redefine the list for TPAD              00980064
P21ATPL@ EQU   *             Start of TPAD List for Longwa2          00990064
P21ATPB  DS    (2187)CL8     2187 8-Byte Elements                    01000064
         DS    CL4           Filler                                  01010064
P21ATPL  EQU   P21ATPL@,*-P21ATPL@  Define Start and Length          01020064
         ORG   P21ATPB       Element Breakdown                       01030064
P21ATPBN DS    CL7           BIN                                     01040064
P21ATPST DS    CL1           BIN STATUS                              01050064
         ORG   P21ATPL+L'P21ATPL   Point To End of List               01060064
P21ALLEN EQU   P21ALEND-P2BAL1A    Length of Long P2BAL1A            01070064
P21ATPLN EQU   P21ALEND-P2BAL1A    Length of TPAD Long P2BAL1A       01080064
                                                                     01090064
*********************************************************************  01100064
******                                                               01110064
         ORG   P2BAL1A           RESET LOCATION FOR FN 1/1E EXTENDED 01120064
******                                                               01130064
*********************************************************************  01140064
                                                                     01150064
```

```
P2EXKEY  DS    CL21          ACCESS KEY                                01160064
P2EXCPAR DS    CL1           CONTINUOUS PARITY INDICATOR               01170064
P2EXLHNS DS    CL11          LOW HOUSE NUMBER                          01180064
P2EXHHNS DS    CL11          HIGH HOUSE NUMBER                         01190064
P2EXLGC  DS    CL2           DCP Prefered LGC                          01200064
P2EX#STL DS    CL1           NUMBER OF CROSS STREETS AT LOW END        01210064
P2EXCDEL DS    CL30          UP TO FIVEPB5SC'S FOR LOW END             01220064
P2EX#STH DS    CL1           NUMBER OF CROSS STREETS AT HIGH END       01230064
P2EXCDEH DS    CL30          UP TO FIVE B5SC'S FOR HIGH END            01240064
P2EXLBOR DS    CL1           LION BOROUGH CODE                         01250064
P2EXFACE DS    CL4           LION FACE CODE                            01260064
P2EXSEQ  DS    CL5           LION SEQUENCE NUMBER                      01270064
P2EXSPAD DS    CL1           SPECIAL ADDRESS FLAG                      01280064
P2EXSOS  DS    CL1           SIDE OF STREET INDICATOR                  01290064
P2EXSEGL DS    CL5           SEGMENT LEGNTH                            01300064
P2EXXCOR DS    CL7           X COORDINATE                              01310064
P2EXYCOR DS    CL7           Y COORDINATE                              01320064
P2EXZCOR DS    CL7           Z Coordinate - Not Impl.                  01330064
P2EXRES1 DS    CL1           RESERVED FOR DCP/GSS USE                  01340064
P2EXMHRI DS    CL1           MARBLE HILL/RIKERS ISLAND FLAG            01350064
P2EXSLA  DS    CL1           STREET LIGHT AREA                         01360064
P2EXCD   DS   0CL3           COMMUNITY DISTRICT                        01370064
P2EXCDB  DS    CL1           COMMUNITY DISTRICT BORO                   01380064
P2EXCDN  DS    CL2           COMMUNITY DISTRICT NUMBER                 01390064
P2EXZIP  DS    CL5           ZIP CODE                                  01400064
P2EXEED  DS    CL3           ELECTION DISTRICT                         01410064
P2EXEAD  DS    CL2           ASSEMBLY DISTRICT                         01420064
P2EXESED DS    CL1           SPLIT E.D. FLAG                           01430064
P2EXECON DS    CL2           CONGRESSIONAL DISTRICT                    01440064
P2EXESEN DS    CL2           SENATORIAL DISTRICT                       01450064
P2EXECIV DS    CL2           CIVIL COURT DISTRICT                      01460064
P2EXECOU DS    CL2           CITY COUNCIL DISTRICT                     01470064
*                                                                      01480064
P2EXHCD  DS    CL2           HEALTH CODE DISTRICT                      01490064
P2EXHA   DS    CL4           HEALTH AREA                               01500064
P2EXSAND DS    CL3           SANITATION DISTRICT                       01510064
P2EXSANT DS    CL2           SANITATION DEPT SUBSECTION                01520064
P2EXSREG DS    CL5           SANITATION REGULAR PICK-UP                01530064
P2EXSREC DS    CL3           SANITATION RECYCLE PICK-UP                01540064
P2EXPOL  DS   0CL4           POLICE DISTRICT                           01550064
P2EXPBC  DS    CL1           POLICE PATROL BORO COMMAND                01560064
P2EXPOP  DS    CL3           POLICE PRECINCT                           01570064
P2EXFS   DS    CL2           FIRE DIVISION                             01580064
P2EXFB   DS    CL2           FIRE BATTALION                            01590064
P2EXFC   DS   0CL4           FIRE COMPANY                              01600064
```

```
P2EXFCT  DS    CL1          FIRE COMPANY TYPE                        01610064
P2EXFCN  DS    CL3          FIRE COMPANY NUMBER                      01620064
         DS    CL1          FILLER-WAS SPLIT SCHOOL DIST             01630064
P2EXSCH  DS    CL2          SCHOOL DISTRICT                          01640064
P2EXCPB  DS    CL3          DYNAMIC BLOCK/ATOMIC POLYGON             01650064
P2EXPPB  DS    CL2          Police Patrol Borough                    01660064
P2EXFEAT DS    CL1          Feature Type Code                        01670064
P2EXSTC  DS    CL1          SEGMENT TYPE CODE                        01680064
P2EXALX  DS    CL1          A=Segment split by Alley                 01690064
*                           X=Cross Streets modified                 01700064
P2EXCSC  DS    CL1          Coincident Segment Count                 01710064
         DS    CL2          Filler                                   01720064
P2EXCTB  DS    CL1          CENSUS TRACT BORO USED FOR GRIDGEN       01730064
P2EXCT90 DS    CL6          1990 CENSUS TRACT                        01740064
P2EXCT10 DS    CL6          2010 CENSUS TRACT                        01750064
P2EXBL10 DS    CL4          2010 CENSUS BLOCK                        01760064
P2EXBLS1 DS    CL1          2010 CENSUS BLOCK SUFFIX NOT IMPLEMENTED 01770064
P2EXT00  DS    CL6          2000 CENSUS TRACT                        01780064
P2EXB00  DS    CL4          2000 CENSUS BLOCK                        01790064
P2EXS00  DS    CL1          2000 CENSUS BLOCK SUFFIX                 01800064
P2EXNTA  DS    CL4          NEIGHBORHOOD TABULATION AREA             01810064
P2EXSP   DS    CL1          SANITATION STREET SNOW PRIORITY          01820064
P2EXSORG DS    CL5          SANITATION ORGANIC PICK UP               01830064
P2EXSBLK DS    CL5          SANITATION BULK PICK UP                  01831069
*        DS    CL5          SANITATION RESERVED                      01840070
P2EXHZ   DS    CL2          HURRICANE EVACUATION ZONE-OEM            01850064
         DS    CL11         FILLER                                   01860064
P2EXUHNS DS    CL11         Underlying HNS                           01870064
P2EXB7SC DS    CL8          "True" Borough 7 Digit Street Code       01880064
P2EXSEGT DS    CL7          Segment Identifier                       01890064
P2EXCURV DS    CL1          Curve Flag                               01900064
P2EXLGCS DS    CL8          List of 4 LGCs                           01910064
P2EXBOEP DS    CL1          BOE LGC Pointer                          01920064
P2EXAZM  DS    CL3          Segment Azimuth                          01930064
P2EXORN  DS    CL1          Segment Orientation                      01940064
P2EXXCL  DS    CL7          X Coordinate, Low Address end            01950064
P2EXYCL  DS    CL7          Y Coordinate, Low Address end            01960064
P2EXZCL  DS    CL7          Z Coordinate, Low Address Not Impl       01970064
P2EXXCH  DS    CL7          X Coordinate, Hi Address end             01980064
P2EXYCH  DS    CL7          Y Coordinate, Hi Address end             01990064
P2EXZCH  DS    CL7          Z Coordinate, Hi Address Not Impl        02000064
P2EXXCC  DS    CL7          X Coordinate, Center Curve               02010064
P2EXYCC  DS    CL7          Y Coordinate, Center Curve               02020064
P2EXZCC  DS    CL7          Z Coordinate, Center Curve Not Impl      02030064
P2EXRAD  DS    CL7          Radius of Circle                         02040064
```

P2EXSEC	DS	CL1	Secant Location Related to Curve	02050064
P2EXBETA	DS	CL5	Angle to From Node	02060064
P2EXALFA	DS	CL5	Angle to To Node	02070064
P2EXFNOD	DS	CL7	From LION Node Id	02080064
P2EXTNOD	DS	CL7	To LION Node Id	02090064
P2EXLVA	DS	CL10	LION Key for Vanity Address	02100064
P2EXSVA	DS	CL1	Side of Street for Vanity Address	02110064
P2EXSLH	DS	CL11	Split Low House Number	02120064
P2EXTD	DS	CL1	Traffic Direction	02130064
P2EXTR	DS	CL10	Turn Restrictions	02140064
P2EXFRC	DS	CL3	Fraction for Curve Calculation	02150064
P2EXRT	DS	CL2	Roadway Type	02160064
P2EXPID	DS	CL7	Physical Id	02170064
P2EXGID	DS	CL7	Generic Id	02180064
P2EXPDID	DS	CL7	For DCP Use Only	02190064
P2EXFDID	DS	CL7	For DCP Use Only	02200064
P2EXBLN2	DS	CL2	Bike Lane 2 (has 2 byte numeric value)	02201068
P2EXBTD	DS	CL2	Bike Traffic Direction	02202072
	DS	CL3	filler	02210071
P2EXSTS	DS	CL1	Street Status	02220064
P2EXSTW	DS	CL3	Street Width	02230064
P2EXSTWI	DS	CL1	Street Width Irregular (Y/N)	02240064
P2EXBLN	DS	CL1	Bike Lane	02250064
P2EXFCC	DS	CL2	Federal Classification Code	02260064
P2EXROW	DS	CL1	Right of Way Type	02270064
P2EXSLGC	DS	CL10	Set of Second LGCs	02280064
P2EXLSID	DS	CL7	Legacy Segment ID	02290064
P2EXFPL1	DS	CL10	From Preferred LGCs First Set of 5	02300064
P2EXTPL1	DS	CL10	To Preferred LGCs First Set of 5	02310064
P2EXFPL2	DS	CL10	From Preferred LGCs Second Set of 5	02320064
P2EXTPL2	DS	CL10	To Preferred LGCs Second Set of 5	02330064
P2EXNCR	DS	CL1	No Cross Street Calc Flag	02340064
P2EXISL	DS	CL5	Individual Segment Length	02350064
P2EXNTAN	DS	CL75	NTA Name	02360064
P2EXUSPS	DS	CL25	USPS PREFERRED CITY NAME	02370064
P2EXLAT	DS	CL9	LATITUDE	02380064
P2EXLONG	DS	CL11	LONGITUDE	02390064
P2EXSFRN	DS	CL7	SEGMENT FROM NODE	02400064
P2EXSTON	DS	CL7	SEGMENT TO NODE	02410064
P2EXFXYZ	DS	CL21	XYZ COORD (SEGMENT FROM XYZ)	02420064
P2EXTXYZ	DS	CL21	XYZ COORD (SEGMENT TO XYZ)	02430064
P2EXBFID	DS	CL10	NEW location blockface_id because of	02460064
*			length changed V16.1	02470064
P2EX#TRL	DS	CL2	nbr of traveling lanes	02480064
P2EX#PKL	DS	CL2	nbr of parking lanes	02490064

```
P2EX#TLL DS    CL2           nbr of total lanes on street              02500067
P2EXSTWX DS    CL3           Street Width-Maximum                      02501068
P2EXSPDL DS    CL2           Speed Limit                               02502073
P2EXPUMA DS    CL5           PUMA Code V18.1                           02503076
         DS    CL245         Filler                                    02510076
P2EXRC   DS    CL1           REASON CODE                               02520064
P2EXRCQ  DS    CL1           REASON CODE QUALIFIER                     02530064
P2EXWC   DS    CL2           WARNING CODE FILLER                       02540064
P2EXGRC  DS    CL2           GEOSUPPORT RETURN CODE                    02550064
P2EX#SL  DS    CL1           NUMBER OF CROSS STREETS AT LOW END        02560064
P2EX7SL  DS    CL40          UP TO 5 B7SC'S FOR LOW END                02570064
P2EX#SH  DS    CL1           NUMBER OF CROSS STREETS AT HIGH END       02580064
P2EX7SH  DS    CL40          UP TO 5 B7SC'S FOR HIGH END               02590064
P2EXSNL  DS    CL160         UP TO 5 STREET NAMES FOR LOW END          02600064
P2EXSNH  DS    CL160         UP TO 5 STREET NAMES FOR HIGH END         02610064
P2EXBPC  DS    CL8           BOE PREFERRED B7SC STREET CODE            02620064
P2EXBPN  DS    CL32          BOE PREFERRED STREET NAME                 02630064
P2EXFIL  DS    CL52          Filler                                    02640064
*                                                                       02650064
P2EXEND  EQU   *                                                       02660064
P2EXLEN  EQU   P2EXEND-P2BAL1A  LENGTH OF P21EX WORKAREA 2             02670064
*                                                                       02680064
                                                                       02690064
************************************************************************ 02700064
******                                                                 02710064
         ORG   P2BAL1A            RESET LOCATION FOR FN 1A EXTENDED    02720064
******                                                                 02730064
************************************************************************ 02740064
                                                                       02750064
P2AXKEY  DS    CL21          Internal Use Only                         02760064
P2AXCPIN DS    CL1           CONTINUOUS PARITY INDICATOR               02770064
P2AXHSEL DS    CL11          LOW HOUSE NUMBER ON BLOCK - HNS Form      02780064
P2AXALT1 DS   0CL11          Alternate Key                             02790064
P2AXBOR1 DS    CL1           ALTERNATE KEY - BORO                      02800064
P2AXTXB1 DS    CL5           ALTERNATE KEY - TAX BLOCK                 02810064
P2AXTXL1 DS    CL4           ALTERNATE KEY - TAX LOT                   02820064
         DS    CL1              Future Use                             02830064
P2AXRSCC DS    CL1           RPAD SCC                                  02840064
         DS    CL1           FILLER                                    02850064
P2AXGLI  DS   0CL13          GENERAL LOT INFO                          02860064
P2AXRBLC DS    CL2           RPAD BUILDING CLASSIFICATION              02870064
P2AXCORC DS    CL2           CORNER CODE                               02880064
P2AX#STC DS    CL4           TOTAL NUMBER STRUCTURES                   02890064
P2AX#BFA DS    CL2           TOTAL NUMBER BLOCKFACES                   02900064
P2AXINTF DS    CL1           INTERIOR LOT FLAG                         02910064
```

```
P2AXVACF DS    CL1          VACANT LOT FLAG                          02920064
P2AXIRLF DS    CL1          IRREGULARLY-SHAPED LOT FLAG              02930064
*                                                                    02940064
P2AXABFL DS    CL1          Marble Hill/ Rikers ALTERNATE BORO FLAG  02950064
P2AXOVFL DS    CL1          Address Overflow Flag                    02960064
*                                                                    02970064
P2AXSTRK DS    CL19         STROLLING KEY - FILLER                   02980064
*                                                                    02990064
P2AXRFIU DS    CL1          RESERVED FOR INTERNAL USE                03000064
P2AXBIN  DS    CL7          BUILDING IDENTIFICATION NUMBER (BIN)     03010064
*                           Condo Information                        03020064
P2AXCONF DS    CL1          CONDO LOT FLAG                           03030064
         DS    CL1          Filler for Future Use                    03040064
P2AXRCO# DS    CL4          RPAD CONDO NUMBER                        03050064
         DS    CL7          Future Use - Condo Unit Number           03060064
P2AXCBBL DS    CL11         CONDO BILLING BBL                        03070064
P2AXCBBS DS    CL1          CONDO BILLING BBL SCC                    03080064
P2AXCLBL DS    CL11         CONDO LOW BBL                            03090064
P2AXCHBL DS    CL11         CONDO HIGH BBL                           03100064
         DS    CL15         Filler                                   03110064
P2AXCOOP DS    CL4          Co-op Number                             03120064
*                                                                    03130064
P2AXSBVP DS    CL8          SANDBORN BOROUGH/VOLUME/PAGE             03140064
*                                                                    03150064
P2AXBUSA DS    CL5          BUSINESS AREA                            03160064
P2AXTAXM DS    CL5          Tax Map Number - Section and Volume      03170064
         DS    CL4          Reserved for Tax Map Page                03180064
         DS    CL3             FILLER                                03190064
P2AXLAT  DS    CL9          LATITUDE                                 03200064
P2AXLONG DS    CL11         LONGITUDE                                03210064
P2AXXCO  DS    CL7          X Coordinate of Annotation Point         03220064
P2AXYCO  DS    CL7          Y Coordinate of Annotation Point         03230064
P2AXBID  DS    CL6          Business Improvement District            03240064
P2AXTPBS DS    CL1          TPAD BIN Status                          03250064
P2AXTPNB DS    CL7          TPAD New BIN                             03260064
P2AXTPNS DS    CL1          TPAD New BIN Status                      03270064
P2AXTPCF DS    CL1          TPAD Conflict Flag                       03280064
P2AXZMAP DS    CL3          DCP Zoning Map                           03281075
         DS    CL6          FILLER                                   03290075
         DS    CL8          Internal Use - LGCS                      03300064
P2AXRC   DS    CL1          REASON CODE                              03310064
P2AXRCQ  DS    CL1          REASON CODE QUALIFIER                    03320064
P2AXWC   DS    CL2          WARNING CODE FILLER                      03330064
P2AXGRC  DS    CL2          GEOSUPPORT RETURN CODE                   03340064
         DS    CL108        FILLER                                   03350064
```

```
P2AX#ADR DS    CL4           TOTAL ADDRESSES FOR LOT                    03360064
P2AXLIST DS   0CL116         LIST OF ADDRESSES, MAXIMUM OF 21           03370064
P2AXLOW# DS    CL16          LOW HOUSE NUMBER-Display Form              03380064
P2AXHI#  DS    CL16          HIGH HOUSE NUMBER-Display Form             03390064
P2AXBCDE DS    CL1           Borough Code                               03400064
P2AXCODE DS    CL5           STREET CODE                                03410064
P2AXPLGC DS    CL2           Preferred LGC                              03420064
P2AXLBIN DS    CL7           BIN                                        03430064
P2AXLSOS DS    CL1           Side of Street Indicator                   03440064
P2AXATP  DS    CL1           Address Type Flag                          03450064
P2AXATPS DS    CL1           TPAD BIN Status                            03460064
P2AXSTN  DS    CL32          STREET NAME                                03470064
         DS    CL34          FILLER                                     03480064
*  STORAGE IS RESERVED FOR THE REMAINING 20 ADDRESS STRUCTURES.         03490064
*  EACH STRUCTURE IS IDENTICAL TO THE ONE DEFINED ABOVE.                03500064
         DS    CL2320        REMAINING ADDRESSES                        03510064
P2AXEND  EQU   *                                                       03520064
P2AXLEN  EQU   P2AXEND-P2BAL1A  LENGTH OF P21A EXTEND WORKAREA 2       03530064
*                                                                      03540064
                                                                       03550064
************************************************************************ 03560064
******                                                                 03570064
         ORG   P2BAL1A             RESET LOCATION FOR FN 1B            03580064
******                                                                 03590064
************************************************************************ 03600064
P21BKEY  DS    CL21          ACCESS KEY                                 03610064
P21BCPAR DS    CL1           CONTINUOUS PARITY INDICATOR                03620064
P21BLHNS DS    CL11          LOW HOUSE NUMBER                           03630064
P21BHHNS DS    CL11          HIGH HOUSE NUMBER                          03640064
P21BLGC  DS    CL2           DCP PREFERRED LGC(FN 1) - BOE (FN 1E)      03650076
P21B#STL DS    CL1           NUMBER OF CROSS STREETS AT LOW END         03660064
P21BCDEL DS    CL30          UP TO FIVEPB5SC'S FOR LOW END              03670064
P21B#STH DS    CL1           NUMBER OF CROSS STREETS AT HIGH END        03680064
P21BCDEH DS    CL30          UP TO FIVE B5SC'S FOR HIGH END             03690064
P21BLBOR DS    CL1           LION BOROUGH CODE                          03700064
P21BFACE DS    CL4           LION FACE CODE                             03710064
P21BSEQ  DS    CL5           LION SEQUENCE NUMBER                       03720064
P21BSPAD DS    CL1           SPECIAL ADDRESS FLAG                       03730064
P21BSOS  DS    CL1           SIDE OF STREET INDICATOR                   03740064
P21BSEGL DS    CL5           SEGMENT LEGNTH                             03750064
P21BXCOR DS    CL7           X COORDINATE                               03760064
P21BYCOR DS    CL7           Y COORDINATE                               03770064
P21BZCOR DS    CL7           Z Coordinate - Not Impl.                   03780064
P21BRES1 DS    CL1           RESERVED FOR DCP/GSS USE                   03790064
P21BMHRI DS    CL1           MARBLE HILL/RIKERS ISLAND FLAG             03800064
```

```
P21BSLA  DS    CL1          STREET LIGHT AREA                        03810064
P21BCD   DS   0CL3          COMMUNITY DISTRICT                       03820064
P21BCDB  DS    CL1          COMMUNITY DISTRICT BORO                  03830064
P21BCDN  DS    CL2          COMMUNITY DISTRICT NUMBER                03840064
P21BZIP  DS    CL5          ZIP CODE                                 03850064
P21BEED  DS    CL3          ELECTION DISTRICT                        03860064
P21BEAD  DS    CL2          ASSEMBLY DISTRICT                        03870064
P21BESED DS    CL1          SPLIT E.D. FLAG                          03880064
*                 Next four fields are valid only for Fn 1E          03890064
P21BECON DS    CL2          CONGRESSIONAL DISTRICT                   03900064
P21BESEN DS    CL2          SENATORIAL DISTRICT                      03910064
P21BECIV DS    CL2          CIVIL COURT DISTRICT                     03920064
P21BECOU DS    CL2          CITY COUNCIL DISTRICT                    03930064
*                                                                    03940064
P21BHCD  DS    CL2          HEALTH CODE DISTRICT                     03950064
P21BHA   DS    CL4          HEALTH AREA                              03960064
P21BSAND DS    CL3          SANITATION DISTRICT                      03970064
P21BSANT DS    CL2          SANITATION DEPT SUBSECTION               03980064
P21BSREG DS    CL5          SANITATION REGULAR PICK-UP               03990064
P21BSREC DS    CL3          SANITATION RECYCLE PICK-UP               04000064
P21BPOL  DS    0CL4         POLICE DISTRICT                          04010064
P21BPBC  DS    CL1          POLICE PATROL BORO COMMAND               04020064
P21BPOP  DS    CL3          POLICE PRECINCT                          04030064
P21BFS   DS    CL2          FIRE DIVISION                            04040064
P21BFB   DS    CL2          FIRE BATTALION                           04050064
P21BFC   DS   0CL4          FIRE COMPANY                             04060064
P21BFCT  DS    CL1          FIRE COMPANY TYPE                        04070064
P21BFCN  DS    CL3          FIRE COMPANY NUMBER                      04080064
P21BFILS DS    CL1          FILLER_WAS SPLIT SCHOOL DISTRICT FLAG    04090064
P21BSCH  DS    CL2          SCHOOL DISTRICT                          04100064
P21BCPB  DS    CL3          DYNAMIC BLOCK/ATOMIC POLYGON             04110064
P21BPPB  DS    CL2          Police Patrol Borough                    04120064
P21BFEAT DS    CL1          FEATURE TYPE CODE                        04130064
P21BSTC  DS    CL1          SEGMENT TYPE CODE                        04140064
P21BALX  DS    CL1          A=Segment split by Alley                 04150064
*                           X=Cross Streets modified                 04160064
P21BCSC  DS    CL1          COINCIDENT SEGMENT COUNT                 04170064
         DS    CL2          Filler                                   04180064
P21BCTB  DS    CL1          CENSUS TRACT BORO USED FOR GRIDGEN       04190064
P21BCT90 DS    CL6          1990 CENSUS TRACT                        04200064
P21BCT10 DS    CL6          2010 CENSUS TRACT                        04210064
P21BBL10 DS    CL4          2010 CENSUS BLOCK                        04220064
P21BBLS1 DS    CL1          2010 CENSUS BLOCK SUFFIX NOT IMPLEMENTED 04230064
P21BT00  DS    CL6          2000 CENSUS TRACT                        04240064
P21BB00  DS    CL4          2000 CENSUS BLOCK                        04250064
```

P21BS00	DS	CL1	2000 CENSUS BLOCK SUFFIX	04260064
P21BNTA	DS	CL4	NEIGHBORHOOD TABULATION AREA	04270064
P21BSP	DS	CL1	SANITATION STREET SNOW PRIORITY	04280064
P21BSORG	DS	CL5	SANITATION ORGANIC PICK UP	04290064
P21BSBLK	DS	CL5	SANITATION BULK PICK UP	04291069
*	DS	CL5	SANITATION RESERVED	04300070
P21BHZ	DS	CL2	HURRICANE EVACUATION ZONE-OEM	04310064
	DS	CL11	FILLER	04320064
P21BUHNS	DS	CL11	Underlying HNS	04330064
P21BB7SC	DS	CL8	"True" Borough 7 Digit Street Code	04340064
P21BSEGT	DS	CL7	Segment Identifier	04350064
P21BCURV	DS	CL1	Curve Flag	04360064
P21BLGCS	DS	CL8	List of 4 LGCs	04370064
P21BBOEP	DS	CL1	BOE LGC Pointer	04380064
P21BAZM	DS	CL3	Segment Azimuth	04390064
P21BORN	DS	CL1	Segment Orientation	04400064
P21BXCL	DS	CL7	X Coordinate, Low Address end	04410064
P21BYCL	DS	CL7	Y Coordinate, Low Address end	04420064
P21BZCL	DS	CL7	Z Coordinate, Low Address Not Impl	04430064
P21BXCH	DS	CL7	X Coordinate, Hi Address end	04440064
P21BYCH	DS	CL7	Y Coordinate, Hi Address end	04450064
P21BZCH	DS	CL7	Z Coordinate, Hi Address Not Impl	04460064
P21BXCC	DS	CL7	X Coordinate, Center Curve	04470064
P21BYCC	DS	CL7	Y Coordinate, Center Curve	04480064
P21BZCC	DS	CL7	Z Coordinate, Center Curve Not Impl	04490064
P21BRAD	DS	CL7	Radius of Circle	04500064
P21BSEC	DS	CL1	Secant Location Related to Curve	04510064
P21BBETA	DS	CL5	Angle to From Node	04520064
P21BALFA	DS	CL5	Angle to To Node	04530064
P21BFNOD	DS	CL7	From LION Node Id	04540064
P21BTNOD	DS	CL7	To LION Node Id	04550064
P21BLVA	DS	CL10	LION Key for Vanity Address	04560064
P21BSVA	DS	CL1	Side of Street for Vanity Address	04570064
P21BSLH	DS	CL11	Split Low House Number	04580064
P21BTD	DS	CL1	Traffic Direction	04590064
P21BTR	DS	CL10	Turn Restrictions	04600064
P21BFRC	DS	CL3	Fraction for Curve Calculation	04610064
P21BRT	DS	CL2	Roadway Type	04620064
P21BPID	DS	CL7	Physical Id	04630064
P21BGID	DS	CL7	Generic Id	04640064
P21BPDID	DS	CL7	For DCP Use Only	04650064
P21BFDID	DS	CL7	For DCP Use Only	04660064
P21BBLN2	DS	CL2	Bike Lane 2 (has 2 bytes numeric value)	04661068
P21BBTD	DS	CL2	Bike Traffic Direction	04662072
	DS	CL3	Filler	04670071

```
P21BSTS  DS    CL1          Street Status                          04680064
P21BSTW  DS    CL3          Street Width                           04690064
P21BSTWI DS    CL1          Street Width Irregular (Y/N)           04700064
P21BBLN  DS    CL1          Bike Lane                              04710064
P21BFCC  DS    CL2          Federal Classification Code            04720064
P21BRTP  DS    CL1          Row Type                               04730064
P21BSLGC DS    CL10         Set of Second LGCs                     04740064
P21BLSID DS    CL7          Legacy Segment ID                      04750064
P21BFPL1 DS    CL10         From Preferred LGCs First Set of 5     04760064
P21BTPL1 DS    CL10         To Preferred LGCs First Set of 5       04770064
P21BFPL2 DS    CL10         From Preferred LGCs Second Set of 5    04780064
P21BTPL2 DS    CL10         To Preferred LGCs Second Set of 5      04790064
P21BNCR  DS    CL1          No Cross Street Calc Flag              04800064
P21BISL  DS    CL5          Individual Segment Length              04810064
P21BNTAN DS    CL75         NTA Name                               04820064
P21BUSPS DS    CL25         USPS PREFERRED CITY NAME               04830064
P21B1LAT DS    CL9          LATITUDE                               04840064
P21B1LON DS    CL11         LONGITUDE                              04850064
P21BSFRN DS    CL7          SEGMENT FROM NODE                      04860064
P21BSTON DS    CL7          SEGMENT TO NODE                        04870064
P21BFXYZ DS    CL21         XYZ COORD (SEGMENT FROM XYZ)           04880064
P21BTXYZ DS    CL21         XYZ COORD (SEGMENT TO XYZ)             04890064
P21BBFID DS    CL10         NEW location blockface_id because of   04891065
*                           length changed V16.1                   04892065
P21B#TRL DS    CL2          nbr of traveling lanes                 04893065
P21B#PKL DS    CL2          nbr of parking lanes                   04894065
P21B#TLL DS    CL2          nbr of total lanes                     04895065
P21BSTWX DS    CL3          Street Width Maximum                   04895168
P21BSPDL DS    CL2          Speed Limit                            04895274
P21BPUMA DS    CL5          PUMA Code  V18.1                       04895376
         DS    CL245        Filler                                 04895476
P21BRC   DS    CL1          REASON CODE                            04910064
P21BRC1  DS    CL1          REASON CODE QUALIFIER                  04920064
P21BWC   DS    CL2          WARNING CODE FILLER                    04930064
P21BGRC  DS    CL2          GEOSUPPORT RETURN CODE                 04940064
P21B#SL  DS    CL1          NUMBER OF CROSS STREETS AT LOW END     04950064
P21B7SL  DS    CL40         UP TO 5 B7SC'S FOR LOW END             04960064
P21B#SH  DS    CL1          NUMBER OF CROSS STREETS AT HIGH END    04970064
P21B7SH  DS    CL40         UP TO 5 B7SC'S FOR HIGH END            04980064
P21BSNL  DS    CL160        UP TO 5 STREET NAMES FOR LOW END       04990064
P21BSNH  DS    CL160        UP TO 5 STREET NAMES FOR HIGH END      05000064
P21BBP7  DS    CL8          BOE PREFERRED B7SC                     05010064
P21BBSN  DS    CL32         BOE PREFERRED STREET NAME              05020064
         DS    CL52         Filler                                 05030064
*                                                                   05040064
```

```
         DS    CL21          Internal Use Only                          05050064
P21BCPIN DS    CL1           CONTINUOUS PARITY INDICATOR                05060064
P21BHSEL DS    CL11          LOW HOUSE NUMBER ON BLOCK - HNS Form       05070064
P21BALT1 DS   0CL11          Alternate Key    Y                         05080064
P21BBOR1 DS    CL1           ALTERNATE KEY - BORO                       05090064
P21BTXB1 DS    CL5           ALTERNATE KEY - TAX BLOCK                  05100064
P21BTXL1 DS    CL4           ALTERNATE KEY - TAX LOT                    05110064
         DS    CL1              Future Use                              05120064
P21BRSCC DS    CL1           RPAD SCC                                   05130064
         DS    CL1           FILLER                                     05140064
P21BGLI  DS   0CL13          GENERAL LOT INFO                           05150064
P21BRBLC DS    CL2           RPAD BUILDING CLASSIFICATION               05160064
P21BCORC DS    CL2           CORNER CODE                                05170064
P21B#STC DS    CL4           TOTAL NUMBER STRUCTURES                    05180064
P21B#BFA DS    CL2           TOTAL NUMBER BLOCKFACES                    05190064
P21BINTF DS    CL1           INTERIOR LOT FLAG                          05200064
P21BVACF DS    CL1           VACANT LOT FLAG                            05210064
P21BIRLF DS    CL1           IRREGULARLY-SHAPED LOT FLAG                05220064
*                                                                       05230064
P21BABFL DS    CL1           Marble Hill/ Rikers ALTERNATE BORO FLAG    05240064
P21BOVFL DS    CL1           Address Overflow Flag                      05250064
*                                                                       05260064
P21BSTRK DS    CL19          STROLLING KEY - FILLER                     05270064
*                                                                       05280064
P21BRFIU DS    CL1           RESERVED FOR INTERNAL USE                  05290064
P21BBIN  DS    CL7           BUILDING IDENTIFICATION NUMBER (BIN)       05300064
*                            Condo Information                          05310064
P21BCONF DS    CL1           CONDO LOT FLAG                             05320064
         DS    CL1           Filler for Future Use                      05330064
P21BRCO# DS    CL4           RPAD CONDO NUMBER                          05340064
         DS    CL7           Future Use - Condo Unit Number             05350064
P21BCBBL DS    CL11          CONDO BILLING BBL                          05360064
P21BCBBS DS    CL1           CONDO BILLING BBL SCC                      05370064
P21BCLBL DS    CL11          CONDO LOW BBL                              05380064
P21BCHBL DS    CL11          CONDO HIGH BBL                             05390064
         DS    CL15          Filler                                     05400064
P21BCOOP DS    CL4           Co-op Number                               05410064
*                                                                       05420064
P21BSBVP DS    CL8           SANDBORN BOROUGH/VOLUME/PAGE               05430064
*                                                                       05440064
P21BBUSA DS    CL5           BUSINESS AREA                              05450064
P21BTAXM DS    CL5           Tax Map Number - Section and Volume        05460064
         DS    CL4           Reserved for Tax Map Page                  05470064
         DS    CL3              FILLER                                  05480064
P21BALAT DS    CL9           LATITUDE                                   05490064
```

```
P21BALON DS    CL11          LONGITUDE                                05500064
P21BXCO  DS    CL7           X Coordinate of Annotation Point         05510064
P21BYCO  DS    CL7           Y Coordinate of Annotation Point         05520064
P21BBID  DS    CL6           Business Improvement District            05530064
P21BTPBS DS    CL1           TPAD BIN Status                          05540064
P21BTPNB DS    CL7           TPAD New BIN                             05550064
P21BTPNS DS    CL1           TPAD New BIN Status                      05560064
P21BTPCF DS    CL1           TPAD Conflict Flag                       05570064
P21BZMAP DS    CL3           DCP Zoning Map                           05571075
         DS    CL6           FILLER                                   05580075
         DS    CL8           Internal Use - LGCS                      05590064
P21BRCS2 DS    CL1           REASON CODE                              05600064
P21BRCQ2 DS    CL1           REASON CODE QUALIFIER                    05610064
P21BWC2  DS    CL2           WARNING CODE FILLER                      05620064
P21BGRC2 DS    CL2           GEOSUPPORT RETURN CODE                   05630064
         DS    CL108         FILLER                                   05640064
P21B#ADR DS    CL4           TOTAL ADDRESSES FOR LOT                  05650064
P21BLIST DS   0CL116         LIST OF ADDRESSES, MAXIMUM OF 21         05660064
P21BLOW# DS    CL16          LOW HOUSE NUMBER-Display Form            05670064
P21BHI#  DS    CL16          HIGH HOUSE NUMBER-Display Form           05680064
P21BBCDE DS    CL1           Borough Code                             05690064
P21BCODE DS    CL5           STREET CODE                              05700064
P21BPLGC DS    CL2           Preferred LGC                            05710064
P21BLBIN DS    CL7           BIN                                      05720064
P21BLSOS DS    CL1           Side of Street Indicator                 05730064
P21BATP  DS    CL1           Address Type Flag                        05740064
P21BATPS DS    CL1           TPAD BIN Status                          05750064
P21BSTN  DS    CL32          STREET NAME                              05760064
         DS    CL34          FILLER                                   05770064
*  STORAGE IS RESERVED FOR THE REMAINING 20 ADDRESS STRUCTURES.        05780064
*  EACH STRUCTURE IS IDENTICAL TO THE ONE DEFINED ABOVE.               05790064
         DS    CL2320        REMAINING ADDRESSES                      05800064
P21BEND  EQU   *                                                      05810064
P21BLEN  EQU   P21BEND-P2BAL1A LENGTH OF P21B WORKAREA 2              05820064
*                                                                     05830064
         ORG   ,                                                      05840064
*********************************************************************** 05850064
```

P2BAL3S COPY File

```
*/*******************************************************************/ 00000100
*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE P2BAL3S,  ***/ 00000200
*/*****  CONTAINING THE LAYOUT OF WORK AREA 2 FOR FUNCTION 3S.     ***/ 00000300
*/*******************************************************************/ 00000400
*/******         Last Modified - 3 April 2002                      ***/ 00000502
*/*******************************************************************/ 00000602
P2BAL3S  DS   0H                                                      00000700
P23SAKEY DS   0CL21          ACCESS KEY                               00000800
         DS    CL2           Internal Use Only                        00000900
P23SPORS DS    CL1           P=Primary, S=Secondary                   00001000
P23SBORO DS    CL1           Borough Code                             00001100
P23S5SC  DS    CL5           Street Code                              00001200
P23SLGC  DS    CL2           Blank if P in P23SPORS                   00001300
         DS    CL10          Internal use Only                        00001400
P23S#INT DS    CL3           NUMBER OF INTERSECTIONS ON STRETCH       00001500
*                            Up to 350 Intersections                  00001600
*P23SINT  DS    0CL87        INTERSECTION LAYOUT                      00001700
P23SINT  DS    0CL55         INTERSECTION LAYOUT                      00001800
P23SMHRI DS    CL1           Marble Hill / Rikers Island Flag         00001900
P23SDIST DS    CL5           DISTANCE IN FEET FROM PREVIOUS INTERSECT. 00002000
P23SGAPF DS    CL1           GAP FLAG ("G" IF NO SEGMENT CONNECTS THIS 00002100
*                            INTERSECTION TO THE PREVIOUS ONE)        00002200
P23SNODE DS    CL7           Node Number                              00002301
P23S#ST  DS    CL1           Number of Streets intersecting (max 5)   00002400
P23SCDE1 DS    CL8           NUMERICALLY SMALLEST B7SC                00002503
P23SCDE2 DS    CL8           NUMERICALLY 2ND SMALLEST B7SC            00002603
P23SCDE3 DS    CL8           Remaining Street Codes in any order      00002700
P23SCDE4 DS    CL8                                                    00002800
P23SCDE5 DS    CL8                                                    00002900
P23SREST DS    CL19195      REMAINING INTERSECTIONS Assuming Max size 00003402
P23SEND  EQU   *                                                      00003500
P23SLEN  EQU   P23SEND-P2BAL3S     LENGTH OF P2BAL3S                  00003600
```

P2BALAP COPY File

```
*/*******************************************************************/ 00000100
*/*****  THIS IS GEOSUPPORT INFORMATION SYSTEM COPY FILE P2BALAP,  ***/ 00000260
*/*****  CONTAINING THE LAYOUT OF WORK AREA 2 FOR FUNCTION AP AND  ***/ 00000360
*/*****  APX (ADDRESS POINT AND AP EXTENDED).   TLV 3/2015  V15.2  ***/ 00001260
*/*******************************************************************/ 00001315
P2BALAP  DS   0H                                                      00001760
         DS    CL21                                                   00001815
P2APCPAR DS    CL1           CONTINUOUS PARITY INDICATOR              00001960
P2APHSEL DS    CL11          LOW HOUSE NUMBER ON BLOCK - HNS FORM     00002060
```

```
P2APALT1 DS   0CL11          ALTERNATE KEY                            00002160
P2APBOR1 DS    CL1           ALTERNATE KEY - BORO                     00002260
P2APTXB1 DS    CL5           ALTERNATE KEY - TAX BLOCK                00002360
P2APTXL1 DS    CL4           ALTERNATE KEY - TAX LOT                  00002460
         DS    CL1              Future Use                            00002515
         DS    CL1           FILLER FOR FUNC AP                       00002661
         DS    CL1           FILLER                                   00002715
P2APGLI  DS   0CL13          GENERAL LOT INFO                         00002860
P2APFL01 DS    CL2           FILLER FOR AP ?fields name for fillers ??  00002961
P2APFL02 DS    CL2           FILLER FOR FUNC AP                       00003061
P2AP#STC DS    CL4           TOTAL NUMBER STRUCTURES                  00003160
P2APFL03 DS    CL2           FILLER FOR FUNC AP ?                     00003261
P2APFL04 DS    CL1           FILLER FOR FUNC AP ?                     00003361
P2APFL05 DS    CL1           FILLER FOR FUNC AP ?                     00003461
P2APFL06 DS    CL1           FILLER FOR FUNC AP                       00003561
*                                                                     00003615
         DS    CL1           FILLER FOR FUNC AP                       00003761
         DS    CL1           FILLER FOR FUNC AP                       00003861
*                                                                     00003915
         DS    CL19          FILLER FOR FUNC AP                       00004061
*                                                                     00004115
P2APRFIU DS    CL1           RESERVED FOR INTERNAL USE                00004260
P2APBIN  DS    CL7           BUILDING IDENTIFICATION NUMBER (BIN)     00004360
*                          Condo Information                         00004463
P2APCONF DS    CL1           CONDO LOT FLAG                           00004560
         DS    CL1           Filler for Future Use                    00004615
P2APRCO# DS    CL4           RPAD CONDO NUMBER                        00004760
         DS    CL7           Future Use - Condo Unit Number           00004815
P2APCBBL DS    CL11          CONDO BILLING BBL                        00005063
         DS    CL1           FILLER FOR FUNC AP                       00005161
P2APCLBL DS    CL11          CONDO LOW BBL                            00005260
P2APCHBL DS    CL11          CONDO HIGH BBL                           00005360
         DS    CL15          Filler                                   00005415
P2APCOOP DS    CL4           CO-OP NUMBER                             00005560
*                                                                     00005615
         DS    CL8           FILLER FOR FUNC AP                       00005761
*                                                                     00005815
         DS    CL5           FILLER FOR FUNCTION AP                   00005961
         DS    CL5           FILLER FOR FUNCTION AP                   00006061
         DS    CL4           FILLER                                   00006161
         DS    CL3           FILLER                                   00006261
P2APLAT  DS    CL9           LATITUDE                                 00006360
P2APLONG DS    CL11          LONGITUDE                                00006460
P2APXCO  DS    CL7           X COORDINATE OF ANNOTATION POINT         00006560
P2APYCO  DS    CL7           Y COORDINATE OF ANNOTATION POINT         00006660
```

```
         DS    CL6           FILLER FOR FUNC AP                        00006761
         DS    CL1           FILLER FOR FUNC AP                        00006861
         DS    CL7           FILLER FOR FUNC AP                        00006961
         DS    CL1           FILLER FOR FUNC AP                        00007061
         DS    CL1           FILLER FOR FUNC AP                        00007162
P2APAPID DS    CL9           ADDRESS POINT ID                          00007367
         DS    CL8           Internal Use                              00007461
P2AP#ADR DS    CL4           TOTAL ADDRESSES FOR LOT                   00007561
P2APLIST DS   0CL1113        LIST OF ADDRESSES, MAXIMUM OF 21          00007661
P2APLOW# DS    CL16          LOW HOUSE NUMBER-Display Form             00007761
P2APHI#  DS    CL16          HIGH HOUSE NUMBER-DISPLAY FORM            00007863
P2APBCDE DS    CL1           Borough Code                              00007961
P2APCODE DS    CL5           STREET CODE                               00008061
P2APPLGC DS    CL2           Preferred LGC                             00008161
P2APLBIN DS    CL7           BIN                                       00008261
P2APLSOS DS    CL1           Side of Street Indicator                  00008361
P2APATP  DS    CL1           Address Type Flag                         00008461
         DS    CL1           FILLER FOR FUNC AP                        00008562
         DS    CL3           FILLER                                    00008661
*  STORAGE IS RESERVED FOR THE REMAINING 20 ADDRESS STRUCTURES.        00008761
*  EACH STRUCTURE IS IDENTICAL TO THE ONE DEFINED ABOVE.               00008861
         DS    CL1060        REMAINING ADDRESSES                       00008961
P2APSEND EQU   *                                                      00009061
P2APSLEN EQU   P2APSEND-P2BALAP    LENGTH OF P2BALAP                  00009162
                                                                      00021016
*********************************************************************** 01222016
******                                                                 01223016
         ORG   P2BALAP             RESET LOCATION FOR FN AP EXTENDED   01224062
******                                                                 01225016
*********************************************************************** 01226016
P2PXKEY  DS    CL21          INTERNAL USE ONLY                         01226166
P2PXCPAR DS    CL1           CONTINUOUS PARITY INDICATOR               01226366
P2PXHSEL DS    CL11          LOW HOUSE NUMBER ON BLOCK - HNS FORM      01226466
P2PXALT1 DS   0CL11          BBL                                       01226566
P2PXBOR1 DS    CL1           BORO                                      01226666
P2PXTXB1 DS    CL5           TAX BLOCK                                 01226766
P2PXTXL1 DS    CL4           TAX LOT                                   01226866
         DS    CL1              Future Use                             01226963
         DS    CL1           FILLER FOR FUNC AP                        01227063
         DS    CL1           FILLER                                    01227163
P2PXGLI  DS   0CL13          GENERAL LOT INFO                          01227266
P2PXFL01 DS    CL2           FILLER FOR AP ?FIELDS NAME FOR FILLERS ?? 01227366
P2PXFL02 DS    CL2           FILLER FOR FUNC AP                        01227466
P2PX#STC DS    CL4           TOTAL NUMBER STRUCTURES                   01227566
P2PXFL03 DS    CL2           FILLER FOR FUNC AP ?                      01227666
```

```
P2PXFL04 DS    CL1          FILLER FOR FUNC AP ?                      01227766
P2PXFL05 DS    CL1          FILLER FOR FUNC AP ?                      01227866
P2PXFL06 DS    CL1          FILLER FOR FUNC AP                        01227966
*                                                                      01228063
         DS    CL1          FILLER FOR FUNC AP                        01228163
         DS    CL1          FILLER FOR FUNC AP                        01228263
*                                                                      01228363
         DS    CL19         FILLER FOR FUNC AP                        01228463
*                                                                      01228563
P2PXRFIU DS    CL1          RESERVED FOR INTERNAL USE                 01228666
P2PXBIN  DS    CL7          BUILDING IDENTIFICATION NUMBER (BIN)      01228766
*                         Condo Information                            01228863
P2PXCONF DS    CL1          CONDO LOT FLAG                            01228966
         DS    CL1          Filler for Future Use                     01229063
P2PXRCO# DS    CL4          RPAD CONDO NUMBER                         01229166
         DS    CL7          Future Use - Condo Unit Number            01229263
P2PXCBBL DS    CL11         CONDO BILLING BBL                         01229366
         DS    CL1          FILLER FOR FUNC AP                        01229463
P2PXCLBL DS    CL11         CONDO LOW BBL                             01229566
P2PXCHBL DS    CL11         CONDO HIGH BBL                            01229666
         DS    CL15         Filler                                    01229763
P2PXCOOP DS    CL4          CO-OP NUMBER                              01229866
*                                                                      01229963
         DS    CL8          FILLER FOR FUNC AP                        01230063
*                                                                      01230163
         DS    CL5          FILLER FOR FUNCTION AP                    01230263
         DS    CL5          FILLER FOR FUNCTION AP                    01230363
         DS    CL4          FILLER                                    01230463
         DS    CL3          FILLER                                    01230563
P2PXLAT  DS    CL9          LATITUDE                                  01230666
P2PXLONG DS    CL11         LONGITUDE                                 01230766
P2PXXCO  DS    CL7          X COORDINATE OF ANNOTATION POINT          01230866
P2PXYCO  DS    CL7          Y COORDINATE OF ANNOTATION POINT          01230966
         DS    CL6          FILLER FOR FUNC AP                        01231063
         DS    CL1          FILLER FOR FUNC AP                        01231163
         DS    CL7          FILLER FOR FUNC AP                        01231263
         DS    CL1          FILLER FOR FUNC AP                        01231363
         DS    CL1          FILLER FOR FUNC AP                        01231463
P2PXAPID DS    CL9          ADDRESS POINT ID                          01231667
         DS    CL8          Internal Use - LGCs                       01231764
P2PXRC   DS    CL1          REASON CODE                               01231866
P2PXRCQ  DS    CL1          REASON CODE QUALIFIER                     01231966
P2PXWC   DS    CL2          WARNING CODE FILLER                       01232066
P2PXGRC  DS    CL2          GEOSUPPORT RETURN CODE                    01232166
         DS    CL108        FILLER                                    01232264
```

```
P2PX#ADR DS    CL4           TOTAL ADDRESSES FOR LOT                    01232966
P2PXLIST DS   0CL116         LIST OF ADDRESSES, MAXIMUM OF 21           01233066
P2PXLOW# DS    CL16          LOW HOUSE NUMBER-DISPLAY FORM              01233166
P2PXHI#  DS    CL16          HIGH HOUSE NUMBER-DISPLAY FORM             01233266
P2PXBCDE DS    CL1           BOROUGH CODE                               01233366
P2PXCODE DS    CL5           STREET CODE                                01233466
P2PXPLGC DS    CL2           PREFERRED LGC                              01233566
P2PXLBIN DS    CL7           BIN                                        01233666
P2PXLSOS DS    CL1           SIDE OF STREET INDICATOR                   01233766
P2PXATP  DS    CL1           ADDRESS TYPE FLAG                          01233866
         DS    CL1           FILLER FOR FUNC AP                         01233963
P2PXSTN  DS    CL32          STREET NAME                                01234066
         DS    CL34          FILLER                                     01234164
*  STORAGE IS RESERVED FOR THE REMAINING 20 ADDRESS STRUCTURES.         01234263
*  EACH STRUCTURE IS IDENTICAL TO THE ONE DEFINED ABOVE.                01234363
         DS    CL1060        REMAINING ADDRESSES                        01234463
P2PXSEND EQU   *                                                       01234566
P2PXSLEN EQU   P2APSEND-P2BALAP   LENGTH OF P2AP EXTEND WORKAREA 2      01234666
*                                                                      01234764
         ORG   ,                                                       01269362
*********************************************************************** 01269516
```

PL/1 COPY Files (COW)

P1PL1 COPY File

```
/*******************************************************************/ 00000100
/** ADDED 'UNIT' FIELDS TO WA1                  YNL 10/16  V16.4 ***/ 00000227
/***  THIS IS THE PL/1 STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM  ***/ 00000300
/***  INDEPENDENT WORK AREA 1.                                   ***/ 00000400
/***  COPY FILE - P1PL1.                                         ***/ 00000500
/***                                                 04/07/98   ***/ 00000600
/**                      LAST UPDATED OCTOBER  2016               **/ 00000729
/*******************************************************************/ 00000825
 DCL PP1 POINTER;                                                      00000925
 DCL                                                                   00001025
   1 P1PL1,                                                            00001125
     /*************************************************/               00001225
     /*****           INPUT  FIELDS             *****/                00001325
     /*************************************************/               00001425
     2 PIWA1_IN_FUNCTION_CODE,                                         00001525
       3 PIWA1_IN_FUNCTION_1            CHAR(1),                       00001625
       3 PIWA1_IN_FUNCTION_2            CHAR(1),                       00001725
     2 PIWA1_IN_HOUSENUM_DISPLAY        CHAR(16),                      00001825
```

```
    2 PIWA1_IN_HOUSENUM_SORT            CHAR(11),                   00001925
    2 PIWA1_IN_LOW_HOUSENUM_DISPLAY     CHAR(16),                   00002025
    2 PIWA1_IN_LOW_HOUSENUM_SORT        CHAR(11),                   00002125
    2 PIWA1_IN_BORO_1                   CHAR(1),                    00002225
    2 PIWA1_IN_10SC_1                   CHAR(10),                   00002325
    2 PIWA1_IN_STREET_1                 CHAR(32),                   00002425
    2 PIWA1_IN_BORO_2                   CHAR(1),                    00002525
    2 PIWA1_IN_10SC_2                   CHAR(10),                   00002625
    2 PIWA1_IN_STREET_2                 CHAR(32),                   00002725
    2 PIWA1_IN_BORO_3                   CHAR(1),                    00002825
    2 PIWA1_IN_10SC_3                   CHAR(10),                   00002925
    2 PIWA1_IN_STREET_3                 CHAR(32),                   00003025
    2 PIWA1_IN_BBL,                                                 00003125
      3 PIWA1_IN_BBL_BORO               CHAR(1),                    00003225
      3 PIWA1_IN_BLOCK                  CHAR(5),                    00003325
      3 PIWA1_IN_LOT                    CHAR(4),                    00003425
      3 PIWA1_IN_LOT_VER                CHAR(1),                    00003525
    2 PIWA1_IN_BIN                      CHAR(7),                    00003625
    2 PIWA1_IN_COMPASS                  CHAR(1),                    00003725
    2 PIWA1_IN_COMPASS2                 CHAR(1),                    00003825
    2 PIWA1_IN_NODE                     CHAR(7),  /*NODE INPUT FN 2*/00003923
    2 PIWA1_IN_PLATFORM_INDICATOR       CHAR(1),                    00004009
    2 PIWA1_IN_ZIPIN                    CHAR(5),                    00004112
    2 PIWA1_IN_UNIT                     CHAR(14),                   00004227
    2 FILLER_200                        CHAR(82),                   00004327
/** 2 FILLER_200  *** V16.4 ***        CHAR(96)  ****/             00004427
    2 PIWA1_IN_LONG_WORKAREA2_FLAG      CHAR(1), /*L=LONG */        00004527
    2 PIWA1_IN_HSE_NBR_JUSTIFY          CHAR(1),                    00004627
    2 PIWA1_IN_HNL                      CHAR(2), /* NI */           00004727
    2 PIWA1_IN_HSE_OVER_FLAG            CHAR(1),                    00004827
    2 PIWA1_IN_SNL                      CHAR(2),                    00004927
    2 PIWA1_IN_SN_NORM_FORMAT           CHAR(1), /*C=COMPACT */     00005027
                                                 /*S OR ' '=SORT*/  00005127
    2 PIWA1_IN_EXPANDED_FORMAT          CHAR(1),                    00005227
    2 PIWA1_IN_ROADBED_REQ_SWITCH       CHAR(1),                    00005327
    2 PIWA1_IN_INTERNAL_USE_LEGACY      CHAR(1),                    00005427
    2 PIWA1_IN_SEGAUX_SWITCH            CHAR(1),                    00005527
    2 PIWA1_IN_BROWSE_FLAG              CHAR(1),                    00005627
    2 PIWA1_IN_REAL_STREET_ONLY         CHAR(1),  /* FN 3S */       00005727
    2 PIWA1_IN_TPAD_SWITCH              CHAR(1),  /*FN 1A-BL-BN*/   00005827
    2 PIWA1_IN_MODE_SWITCH              CHAR(1),  /*FN 1-1E-1A-*/   00005927
                                                  /*FN BL-BN-3-3C*/ 00006027
                                                  /*X=EXTENDED */   00006127
    2 PIWA1_IN_WTO_SWITCH               CHAR(1),  /*N=NO WTO*/      00006227
    2 FILLER_400                        CHAR(29),                   00006327
```

```
    /*********************************************/                 00006427
    /*****            OUTPUT  FIELDS          *****/                 00006527
    /*********************************************/                 00006627
    2 PIWA1_OUT_BORONAME                CHAR(9),                     00006727
    2 PIWA1_OUT_HOUSENUM_DISPLAY        CHAR(16),                    00006827
    2 PIWA1_OUT_HOUSENUM_SORT           CHAR(11),                    00006927
    2 PIWA1_OUT_B10SC_1                 CHAR(11),                    00007027
    2 PIWA1_OUT_STREET_1                CHAR(32),                    00007127
    2 PIWA1_OUT_B10SC_2                 CHAR(11),                    00007227
    2 PIWA1_OUT_STREET_2                CHAR(32),                    00007327
    2 PIWA1_OUT_B10SC_3                 CHAR(11),                    00007427
    2 PIWA1_OUT_STREET_3                CHAR(32),                    00007527
    2 PIWA1_OUT_BBL,                                                 00007627
      3 PIWA1_OUT_BBL_BORO              CHAR(1),                     00007727
      3 PIWA1_OUT_BLOCK                 CHAR(5),                     00007827
      3 PIWA1_OUT_LOT                   CHAR(4),                     00007927
    2 PIWA1_OUT_LOT_VER                 CHAR(1),                     00008027
    2 PIWA1_OUT_LO_HOUSENUM_DISPLAY     CHAR(16),                    00008127
    2 PIWA1_OUT_LO_HOUSENUM_SORT        CHAR(11),                    00008227
    2 PIWA1_OUT_BIN                     CHAR(7),                     00008327
    2 PIWA1_OUT_STREET_ATTR(3)          CHAR(1),                     00008427
    2 PIWA1_OUT_REASON_CODE_2           CHAR(1),                     00008527
    2 PIWA1_OUT_REASON_CODE_QUAL_2      CHAR(1), /*TPAD 2ND REASON*/ 00008627
                                                 /*CODE QUALIFIER */ 00008727
    2 PIWA1_OUT_WARNING_CODE_2          CHAR(2),                     00008827
    2 PIWA1_OUT_RETURN_CODE_2           CHAR(2),                     00008927
    2 PIWA1_OUT_ERROR_MESSAGE_2         CHAR(80),                    00009027
    2 PIWA1_OUT_NODE                    CHAR(7),  /*NODE NORMALIZED*/00009127
    2 PIWA1_OUT_UNIT_SORT,                                           00009227
      3 PIWA1_OUT_UNIT_TYPE             CHAR(4),                     00009327
      3 PIWA1_OUT_UNIT_ID               CHAR(10),                    00009427
    2 PIWA1_OUT_UNIT_DISP               CHAR(14),                    00009527
    2 FILLER_550                        CHAR(17),                    00009728
/** 2 FILLER_550   *** V16.4  ***       CHAR(39)  ***/               00009827
/** 2 FILLER_555                        CHAR(6),  ***/               00009928
    2 PIWA1_OUT_SND_ATTR                CHAR(1),                     00010027
    2 PIWA1_OUT_REASON_CODE             CHAR(1),                     00010127
    2 PIWA1_OUT_REASON_CODE_QUAL        CHAR(1), /*TPAD REASON   */  00010227
                                                 /*CODE QUALIFIER*/  00010327
    2 PIWA1_OUT_WARNING_CODE            CHAR(2),                     00010427
    2 PIWA1_OUT_RETURN_CODE             CHAR(2),                     00010527
    2 PIWA1_OUT_ERROR_MESSAGE           CHAR(80),                    00010627
    2 PIWA1_OUT_NUM_SIMILAR_STRS        CHAR(2),                     00010727
    2 PIWA1_OUT_SIMILAR_B7SC(10)        CHAR(8),                     00010827
    2 PIWA1_OUT_SIMILAR_NAMES(10)       CHAR(32);                    00010927
```

```
                                                                    00011027
 DCL PIWA1_IN_FUNC_CODE                  CHAR(2)                    00011127
                BASED(ADDR(PIWA1_IN_FUNCTION_CODE));               00011227
                                                                    00011327
 DCL WORK1PL1   BASED(PP1)               CHAR(1200);                00012027
 PP1=ADDR(P1PL1);                                                   00020018
```

P2PL1 COPY File

```
/*******************************************************************/ 00010099
/***                      P2PL1                                  ***/ 00011099
/***            LAST MODIFIED DECEMBER 2017                      ***/ 00012099
/*  ADD NEW 5 BYTE PUMA CODE                        YNL 12/17 V18.1*/ 00013099
/*  ADD NEW 2 BYTE SPEED LIMIT                      TLV 09/17 V17.4*/ 00015099
/*  ADD NEW 2 BYTE BIKE TRAFFIC DIRECTION           YNL 12/16 V17,1*/ 00015199
/*  ADD NEW 2 BYTE BIKE LANE AND MAX STR WIDTH      YNL 10/16 V16.4*/ 00015299
/*                                                                  */ 00016099
/***  THIS IS THE PL/1 STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM  ***/ 00030099
/***  INDEPENDENT WORK AREA 2 FOR FUNCTIONS: 1, 1E, 2, 2C, 3,    ***/ 00040099
/***   AND 5.                                                    ***/ 00050099
/***  ADDED 3 EXTENDED AND 3C EXTENDED            MEB   6/11     ***/ 00060099
/***  ADDED 2 WIDE                                MEB   3/14     ***/ 00070099
/***                                                             ***/ 00080099
/***  COPY FILE - P2PL1.                                         ***/ 00090099
/***  PLEASE NOTE THAT FUNCTIONS 1 AND 1E SHARE A SINGLE         ***/ 00100099
/***  WORK AREA 2 LAYOUT, AND FUNCTIONS 2 AND 2C ALSO            ***/ 00110099
/***  SHARE A SINGLE WORK AREA 2 LAYOUT.              12/30/97   ***/ 00120099
/*******************************************************************/ 00130099
DCL PP2 POINTER;                                                     00140099
DCL P2PL1             CHAR(10000) INIT(' ');                         00150099
                                                                    00160099
                                                                    00170099
/*******************************************************************/ 00180099
/*******     FOR: FUNCTIONS 1 & 1E     ****************************/ 00190099
DCL                                                                  00200099
 1 PIWA2_FUNCTION1   BASED(PP2),                                    00210099
   2 PIWA2_FN1_ACCESS_KEY              CHAR(21),                    00220099
   2 PIWA2_FN1_CONT_PARITY             CHAR(1),/*(OR DUP ADDR IND)*/ 00230099
   2 PIWA2_FN1_LOW_HOUSENUM            CHAR(11),/* SORT FORMAT */    00240099
   2 PIWA2_FN1_HI_HOUSENUM             CHAR(11),/* SORT FORMAT */    00250099
   2 PIWA2_FN1_PREF_LGC                CHAR(2),                     00260099
   2 PIWA2_FN1_NUM_X_ST_LOW_END        CHAR(1),                     00270099
   2 PIWA2_FN1_LOW_B5SC(5)             CHAR(6),                     00280099
   2 PIWA2_FN1_NUM_X_ST_HI_END         CHAR(1),                     00290099
```

```
2 PIWA2_FN1_HI_B5SC(5)              CHAR(6),                     00300099
2 PIWA2_FN1_LIONKEY,                                             00310099
  3 PIWA2_FN1_LION_BORO             CHAR(1),                     00320099
  3 PIWA2_FN1_LION_FACECODE         CHAR(4),                     00330099
  3 PIWA2_FN1_LION_SEQ              CHAR(5),                     00340099
2 PIWA2_FN1_SPECIAL_ADDR_FLAG       CHAR(1),                     00350099
2 PIWA2_FN1_SIDE_OF_STR             CHAR(1),                     00360099
2 PIWA2_FN1_SEG_LEN                 CHAR(5),                     00370099
2 PIWA2_FN1_XCOORD                  CHAR(7),                     00380099
2 PIWA2_FN1_YCOORD                  CHAR(7),                     00390099
2 FILLER_100                        CHAR(7), /* FOR ZCOORD */    00400099
2 FILLER_200                        CHAR(1), /* FOR GSS USE*/    00410099
2 PIWA2_FN1_MARBLE_RIKERS_FLAG      CHAR(1),                     00420099
2 PIWA2_FN1_DOT_SLA                 CHAR(1),                     00430099
2 PIWA2_FN1_COM_DIST,                                            00440099
  3 PIWA2_FN1_COM_DIST_BORO         CHAR(1),                     00450099
  3 PIWA2_FN1_COM_DIST_NUM          CHAR(2),                     00460099
2 PIWA2_FN1_ZIP                     CHAR(5),                     00470099
                                                                 00480099
2 PIWA2_FN1E_ELECT_DIST             CHAR(3), /****************/  00490099
2 PIWA2_FN1E_ASSEM_DIST             CHAR(2), /* THE FNIE      */  00500099
2 PIWA2_FN1E_SPLIT_ED_FLAG          CHAR(1), /* FIELDS ARE    */  00510099
2 PIWA2_FN1E_CONG_DIST              CHAR(2), /* VALID ONLY FOR*/  00520099
2 PIWA2_FN1E_SENATE_DIST            CHAR(2), /* FUNCTION 1E,  */  00530099
2 PIWA2_FN1E_COURT_DIST             CHAR(2), /* NOT FUNC 1.   */  00540099
2 PIWA2_FN1E_COUNCIL_DIST           CHAR(2), /****************/  00550099
                                                                 00560099
2 PIWA2_FN1_HEALTH_CENTER_DIST      CHAR(2), /* HEALTH CENTR*/    00570099
2 PIWA2_FN1_HEALTH_AREA             CHAR(4), /* HEALTH AREA*/     00580099
2 PIWA2_FN1_SANI_DIST,                                           00590099
  3 PIWA2_FN1_SANI_DIST_BORO        CHAR(1),                     00600099
  3 PIWA2_FN1_SANI_DIST_NUM         CHAR(2),                     00610099
2 PIWA2_FN1_SANI_SUBSEC             CHAR(2),                     00620099
2 PIWA2_FN1_SANI_REG                CHAR(5),                     00630099
2 PIWA2_FN1_SANI_REC                CHAR(3),                     00640099
2 PIWA2_FN1_POLICE_DIST,                                         00650099
  3  PIWA2_FN1_POL_PAT_BORO_CMD     CHAR(1),                     00660099
  3  PIWA2_FN1_POL_PRECINCT         CHAR(3),                     00670099
2 PIWA2_FN1_FIRE_DIV                CHAR(2),                     00680099
2 PIWA2_FN1_FIRE_BAT                CHAR(2),                     00690099
2 PIWA2_FN1_FIRE_CO,                                             00700099
  3 PIWA2_FN1_FIRE_CO_TYPE          CHAR(1),                     00710099
  3 PIWA2_FN1_FIRE_CO_NUM           CHAR(3),                     00720099
2 PIWA2_FN1_FILL_DIST_SPLIT_FLAG    CHAR(1),  /*WAS SPLIT SC*/   00730099
2 PIWA2_FN1_SCHL_DIST               CHAR(2),                     00740099
```

```
   2 PIWA2_FN1_DYN_BLK                  CHAR(3),  /*ATOMIC POLYGON*/  00750099
   2 PIWA2_FN1_POLICE_PAT_BORO          CHAR(2),                      00760099
   2 PIWA2_FN1_FEATURE_TYPE             CHAR(1),                      00770099
   2 PIWA2_FN1_SEGMENT_TYPE             CHAR(1),                      00780099
   2 PIWA2_FN1_ALX                      CHAR(1),                      00790099
   2 PIWA2_FN1_COINCIDENT_SEG_CTR       CHAR(1),                      00800099
   2 FILLER_290                         CHAR(2),                      00810099
   2 PIWA2_FN1_CENS_TRCT_BORO           CHAR(1), /*USED FOR GRIDGEN*/ 00820099
   2 PIWA2_FN1_1990_CENS_TRCT           CHAR(6),                      00830099
   2 PIWA2_FN1_2010_CENSUS_TRACT        CHAR(6),                      00840099
   2 PIWA2_FN1_2010_CENSUS_BLOCK        CHAR(4),                      00850099
   2 PIWA2_FN1_2010_CENSUS_BLK_SF       CHAR(1), /*NOT IMPLEMENTED*/  00860099
   2 PIWA2_FN1_2000_CENS_TRACT          CHAR(6),                      00870099
   2 PIWA2_FN1_2000_CENS_BLOCK          CHAR(4),                      00880099
   2 PIWA2_FN1_2000_CENS_BLOCK_SUF      CHAR(1),                      00890099
   2 PIWA2_FN1_NTA                      CHAR(4), /*NEIGHBORHOOD    */ 00900099
                                                 /*TABULATION AREA */ 00910099
   2 PIWA2_FN1_SANIT_SNOW_PRIORITY      CHAR(1), /*SANITATION STRT */ 00920099
                                                 /*SNOW PRIORITY   */ 00930099
   2 PIWA2_FN1_SANIT_ORGANICS           CHAR(5), /*SANITATION      */ 00940099
                                                 /*ORGANIC PICKUP  */ 00950099
   2 PIWA2_FN1_SANIT_BULK_PICK_UP       CHAR(5), /*SANITATION BULK */ 00960099
/** 2 PIWA2_FN1_SANIT_RESERVED *V16.4*   CHAR(5), /*SANITATION RESRV*/ 00961099
   2 PIWA2_FN1_HURRICANE_ZONE           CHAR(2), /*OEM HURRICANE   */ 00970099
                                                 /*EVACUATION ZONE */ 00980099
   2 FILLER_300                         CHAR(11),                     00990099
   2 PIWA2_FN1_UHNS                     CHAR(11),                     01000099
   2 PIWA2_FN1_REAL_B7SC                CHAR(8),                      01010099
   2 PIWA2_FN1_SEGMENT_ID               CHAR(7),                      01020099
   2 PIWA2_FN1_CURVE_FLAG               CHAR(1);                      01030099
                                                                      01040099
DCL   PIWA2_FN1_COMDIST                  CHAR(3)                       01050099
       BASED(ADDR(PIWA2_FN1_COM_DIST));                               01060099
DCL   PIWA2_FN1_SANIDIST                 CHAR(3)                       01070099
       BASED(ADDR(PIWA2_FN1_SANI_DIST));                              01080099
DCL   PIWA2_FN1_POLDIST                  CHAR(4)                       01090099
       BASED(ADDR(PIWA2_FN1_POLICE_DIST));                            01100099
                                                                      01110099
                                                                      01120099
/*****************************************************************/ 01130099
/*******     FOR: FUNCTIONS 2 & 2C     ****************************/ 01140099
DCL                                                                   01150099
 1 PIWA2_FUNCTION2   BASED(PP2),                                      01160099
   2 PIWA2_FN2_ACCESS_KEY               CHAR(21),                     01170099
   2 PIWA2_FN2_DUP_INTERSECT_FLAG       CHAR(1),                      01180099
```

```
2 PIWA2_FN2_PREF_LGC1              CHAR(2),                      01190099
2 PIWA2_FN2_PREF_LGC2              CHAR(2),                      01200099
2 PIWA2_FN2_NUM_OF_INTERSECTS      CHAR(1),                      01210099
2 PIWA2_FN2_INTERSECT_B5SC(5)      CHAR(6),                      01220099
2 PIWA2_FN2_COMPDIR                CHAR(1),                      01230099
2 PIWA2_FN2_ATOMIC_POLYGON         CHAR(3),                      01240099
2 FILLER_350                       CHAR(2),                      01250099
2 PIWA2_FN2_LIONNODENUM            CHAR(7),                      01260099
2 PIWA2_FN2_XCOORD                 CHAR(7),                      01270099
2 PIWA2_FN2_YCOORD                 CHAR(7),                      01280099
2 FILLER_400                       CHAR(7), /* FOR ZCOORD */     01290099
2 PIWA2_FN2_SANBORN1,                                            01300099
  3 PIWA2_FN2_SANBORN1_BORO        CHAR(1),                      01310099
  3 PIWA2_FN2_SANBORN1_VOL         CHAR(3),                      01320099
  3 PIWA2_FN2_SANBORN1_PAGE        CHAR(4),                      01330099
2 PIWA2_FN2_SANBORN2,                                            01340099
  3 PIWA2_FN2_SANBORN2_BORO        CHAR(1),                      01350099
  3 PIWA2_FN2_SANBORN2_VOL         CHAR(3),                      01360099
  3 PIWA2_FN2_SANBORN2_PAGE        CHAR(4),                      01370099
2 PIWA2_FN2_MARBLE_RIKERS_FLAG     CHAR(1),                      01380099
2 PIWA2_FN2_DOT_SLA                CHAR(1),                      01390099
2 PIWA2_FN2_COM_DIST,                                            01400099
  3 PIWA2_FN2_COM_DIST_BORO        CHAR(1),                      01410099
  3 PIWA2_FN2_COM_DIST_NUM         CHAR(2),                      01420099
2 PIWA2_FN2_ZIP                    CHAR(5),                      01430099
2 PIWA2_FN2_HEALTH_AREA            CHAR(4),  /*HEALTH AREA*/     01440099
2 PIWA2_FN2_POLICE_DIST,                                         01450099
  3  PIWA2_FN2_POL_PAT_BORO_CMD    CHAR(1),                      01460099
  3  PIWA2_FN2_POL_PRECINCT        CHAR(3),                      01470099
2 PIWA2_FN2_FIRE_DIV               CHAR(2),                      01480099
2 PIWA2_FN2_FIRE_BAT               CHAR(2),                      01490099
2 PIWA2_FN2_FIRE_CO,                                             01500099
  3 PIWA2_FN2_FIRE_CO_TYPE         CHAR(1),                      01510099
  3 PIWA2_FN2_FIRE_CO_NUM          CHAR(3),                      01520099
2 PIWA2_FN2_SCHL_DIST              CHAR(2),                      01530099
2 PIWA2_FN2_2010_CENSUS_TRACT      CHAR(6),                      01540099
2 PIWA2_FN2_1990_CENS_TRCT         CHAR(6),                      01550099
2 PIWA2_FN2_LEVEL_CODES(5,2)       CHAR(1),                      01560099
2 PIWA2_FN2_POLICE_PAT_BORO        CHAR(2),                      01570099
2 PIWA2_FN2_ASSEM_DIST             CHAR(2),                      01580099
2 PIWA2_FN2_CONG_DIST              CHAR(2),                      01590099
2 PIWA2_FN2_SENATE_DIST            CHAR(2),                      01600099
2 PIWA2_FN2_COURT_DIST             CHAR(2),                      01610099
2 PIWA2_FN2_COUNCIL_DIST           CHAR(2),                      01620099
2 PIWA2_FN2_CD_ELIGIBLE            CHAR(1),                      01630099
```

```
   2 PIWA2_FN2_DUP_INTERSECT_DIST       CHAR(5),                      01640099
   2 PIWA2_FN2_2000_CENS_TRACT          CHAR(6),                      01650099
   2 PIWA2_FN2_HEALTH_CENTER_DIST       CHAR(2), /*HEALTH CENTER*/    01660099
   2 PIWA2_FN2_SANITATION_DIST          CHAR(3),                      01670099
   2 PIWA2_FN2_SANITATION_SUBSEC        CHAR(2),                      01680099
   2 FILLER_500                         CHAR(12);                     01690099
                                                                      01700099
DCL   PIWA2_FN2_COMDIST                  CHAR(3)                       01710099
       BASED(ADDR(PIWA2_FN2_COM_DIST));                               01720099
DCL   PIWA2_FN2_POLDIST                  CHAR(4)                       01730099
       BASED(ADDR(PIWA2_FN2_POLICE_DIST));                            01740099
DCL   PIWA2_FN2_SANBORN1_BVOLPAGE        CHAR(8)                       01750099
       BASED(ADDR(PIWA2_FN2_SANBORN1)),                               01760099
     PIWA2_FN2_SANBORN2_BVOLPAGE        CHAR(8)                       01770099
       BASED(ADDR(PIWA2_FN2_SANBORN2));                               01780099
                                                                      01790099
                                                                      01800099
/*******************************************************************/ 01810099
/*******     FOR: FUNCTIONS 2W         ****************************/ 01820099
DCL                                                                   01830099
 1 PIWA2_FUNCTION2W  BASED(PP2),                                      01840099
   2 PIWA2_FN2W_ACCESS_KEY              CHAR(21),                     01850099
   2 PIWA2_FN2W_DUP_INTERSECT_FLAG      CHAR(1),                      01860099
   2 PIWA2_FN2W_PREF_LGC1               CHAR(2),                      01870099
   2 PIWA2_FN2W_PREF_LGC2               CHAR(2),                      01880099
   2 PIWA2_FN2W_NUM_OF_INTERSECTS       CHAR(1),                      01890099
   2 PIWA2_FN2W_INTERSECT_B5SC(5)       CHAR(6),                      01900099
   2 PIWA2_FN2W_COMPDIR                 CHAR(1),                      01910099
   2 PIWA2_FN2W_ATOMIC_POLYGON          CHAR(3),                      01920099
   2 PIWA2_FN2W_FILLER_350              CHAR(2),                      01930099
   2 PIWA2_FN2W_LIONNODENUM             CHAR(7),                      01940099
   2 PIWA2_FN2W_XCOORD                  CHAR(7),                      01950099
   2 PIWA2_FN2W_YCOORD                  CHAR(7),                      01960099
   2 PIWA2_FN2W_FILLER_400              CHAR(7), /* FOR ZCOORD */     01970099
   2 PIWA2_FN2W_SANBORN1,                                             01980099
     3 PIWA2_FN2W_SANBORN1_BORO         CHAR(1),                      01990099
     3 PIWA2_FN2W_SANBORN1_VOL          CHAR(3),                      02000099
     3 PIWA2_FN2W_SANBORN1_PAGE         CHAR(4),                      02010099
   2 PIWA2_FN2W_SANBORN2,                                             02020099
     3 PIWA2_FN2W_SANBORN2_BORO         CHAR(1),                      02030099
     3 PIWA2_FN2W_SANBORN2_VOL          CHAR(3),                      02040099
     3 PIWA2_FN2W_SANBORN2_PAGE         CHAR(4),                      02050099
   2 PIWA2_FN2W_MARBLE_RIKERS_FLAG      CHAR(1),                      02060099
   2 PIWA2_FN2W_DOT_SLA                 CHAR(1),                      02070099
   2 PIWA2_FN2W_COM_DIST,                                             02080099
```

```
  3 PIWA2_FN2W_COM_DIST_BORO         CHAR(1),                      02090099
  3 PIWA2_FN2W_COM_DIST_NUM          CHAR(2),                      02100099
2 PIWA2_FN2W_ZIP                     CHAR(5),                      02110099
2 PIWA2_FN2W_HEALTH_AREA             CHAR(4),  /*HEALTH AREA*/     02120099
2 PIWA2_FN2W_POLICE_DIST,                                          02130099
  3  PIWA2_FN2W_POL_PAT_BORO_CMD     CHAR(1),                      02140099
  3  PIWA2_FN2W_POL_PRECINCT         CHAR(3),                      02150099
2 PIWA2_FN2W_FIRE_DIV                CHAR(2),                      02160099
2 PIWA2_FN2W_FIRE_BAT                CHAR(2),                      02170099
2 PIWA2_FN2W_FIRE_CO,                                              02180099
  3 PIWA2_FN2W_FIRE_CO_TYPE          CHAR(1),                      02190099
  3 PIWA2_FN2W_FIRE_CO_NUM           CHAR(3),                      02200099
2 PIWA2_FN2W_SCHL_DIST               CHAR(2),                      02210099
2 PIWA2_FN2W_2010_CENSUS_TRACT       CHAR(6),                      02220099
2 PIWA2_FN2W_1990_CENS_TRCT          CHAR(6),                      02230099
2 PIWA2_FN2W_LEVEL_CODES(5,2)        CHAR(1),                      02240099
2 PIWA2_FN2W_POLICE_PAT_BORO         CHAR(2),                      02250099
2 PIWA2_FN2W_ASSEM_DIST              CHAR(2),                      02260099
2 PIWA2_FN2W_CONG_DIST               CHAR(2),                      02270099
2 PIWA2_FN2W_SENATE_DIST             CHAR(2),                      02280099
2 PIWA2_FN2W_COURT_DIST              CHAR(2),                      02290099
2 PIWA2_FN2W_COUNCIL_DIST            CHAR(2),                      02300099
2 PIWA2_FN2W_CD_ELIGIBLE             CHAR(1),                      02310099
2 PIWA2_FN2W_DUP_INTERSECT_DIST      CHAR(5),                      02320099
2 PIWA2_FN2W_2000_CENS_TRACT         CHAR(6),                      02330099
2 PIWA2_FN2W_HEALTH_CENTER_DIST      CHAR(2),                      02340099
2 PIWA2_FN2W_SANITATION_DIST         CHAR(3),                      02350099
2 PIWA2_FN2W_SANITATION_SUBSEC       CHAR(2),                      02360099
2 PIWA2_FN2W_FILLER_500              CHAR(12),                     02370099
2 PIWA2_FN2W_FILLER_GRIDGEN          CHAR(22),                     02380099
2 PIWA2_FN2W_LGCS_FIRST_INTERSCT(4),          /*UP TO 4 LGCS FOR */02390099
  3 PIWA2_FN2W_LGC_FIRST_INTERSCT    CHAR(2), /*1ST INPUT STREET */02400099
                                              /*IN INTERSECTION  */02410099
2 PIWA2_FN2W_LGCS_SECOND_INTERSCT(4),         /*UP TO 4 LGCS FOR */02420099
  3 PIWA2_FN2W_LGC_SECOND_INTERSCT   CHAR(2), /*2ND INPUT STREET */02430099
                                              /*IN INTERSECTION  */02440099
2 PIWA2_FN2W_TURN_RESTRICTIONS(10),                                02450099
  3 PIWA2_FN2W_TURN_RESTRICTION      CHAR(1),                      02460099
2 PIWA2_FN2W_INTERSECT_B5SC_LGCS(5),                               02470099
  3 PIWA2_FN2W_INTERSECT_B5SC_LGC    CHAR(2),                      02480099
2 PIWA2_FN2W_TRUE_REP_COUNTER        CHAR(2),                      02490099
2 PIWA2_FN2W_NODE_LIST(20),                                        02500099
  3 PIWA2_FN2W_NODE_LIST_NODE        CHAR(7),                      02510099
2 PIWA2_FN2W_NODE_LIST_B7SCS_LIST(20),                             02520099
  3 PIWA2_FN2W_NODE_LIST_B7SCS(5),                                 02530099
```

```
      4 PIWA2_FN2W_NODE_LIST_B7SC(4)    CHAR(8),                      02540099
   2 PIWA2_FN2W_REASON_CODE             CHAR(1),                      02550099
   2 PIWA2_FN2W_REASON_CODE_QUAL        CHAR(1),                      02560099
   2 PIWA2_FN2W_WARN_CODE               CHAR(2),                      02570099
   2 PIWA2_FN2W_RETURN_CODE             CHAR(2),                      02580099
   2 PIWA2_FN2W_LATITUDE                CHAR(9),                      02590099
   2 PIWA2_FN2W_LONGITUDE               CHAR(11),                     02600099
   2 PIWA2_FN2W_FILLER6                 CHAR(374);                    02610099
/* 2 PIWA2_FN2W_FILLER6    V15.3       CHAR(394)  ***/               02620099
                                                                      02630099
DCL   PIWA2_FN2W_COMDIST                 CHAR(3)                       02640099
       BASED(ADDR(PIWA2_FN2W_COM_DIST));                              02650099
DCL   PIWA2_FN2W_POLDIST                 CHAR(4)                       02660099
       BASED(ADDR(PIWA2_FN2W_POLICE_DIST));                           02670099
DCL   PIWA2_FN2W_SANBORN1_BVOLPAGE       CHAR(8)                       02680099
       BASED(ADDR(PIWA2_FN2W_SANBORN1)),                              02690099
     PIWA2_FN2W_SANBORN2_BVOLPAGE       CHAR(8)                       02700099
       BASED(ADDR(PIWA2_FN2W_SANBORN2));                              02710099
                                                                      02720099
/*******************************************************************/ 02730099
/*******     FOR: FUNCTION 3          ****************************/ 02740099
DCL                                                                   02750099
 1 PIWA2_FUNCTION3   BASED(PP2),                                      02760099
   2 PIWA2_FN3_ACCESS_KEY               CHAR(21),                     02770099
   2 PIWA2_FN3_DUP_KEY_FLAG             CHAR(1),/*(OR CONT PARITY)*/  02780099
   2 PIWA2_FN3_LOCATION_STATUS          CHAR(1),                      02790099
   2 PIWA2_FN3_COUNTY_BOUNDARY          CHAR(1),                      02800099
   2 PIWA2_FN3_PREF_LGC1                CHAR(2),                      02810099
   2 PIWA2_FN3_PREF_LGC2                CHAR(2),                      02820099
   2 PIWA2_FN3_PREF_LGC3                CHAR(2),                      02830099
   2 PIWA2_FN3_NUM_X_ST_LOW_END         CHAR(1),                      02840099
   2 PIWA2_FN3_LOW_B5SC(5)              CHAR(6),                      02850099
   2 PIWA2_FN3_NUM_X_ST_HI_END          CHAR(1),                      02860099
   2 PIWA2_FN3_HI_B5SC(5)               CHAR(6),                      02870099
   2 PIWA2_FN3_REVERSAL_FLAG            CHAR(1),                      02880099
   2 PIWA2_FN3_LIONKEY,                                               02890099
     3 PIWA2_FN3_LION_BORO              CHAR(1),                      02900099
     3 PIWA2_FN3_LION_FACECODE          CHAR(4),                      02910099
     3 PIWA2_FN3_LION_SEQ               CHAR(5),                      02920099
   2 PIWA2_FN3_GENREC_FLAG              CHAR(1),                      02930099
   2 PIWA2_FN3_SEG_LEN                  CHAR(5),                      02940099
   2 PIWA2_FN3_SEG_SLOPE                CHAR(3),                      02950099
   2 PIWA2_FN3_SEG_ORIENT               CHAR(1),                      02960099
   2 PIWA2_FN3_MARBLE_RIKERS_FLAG       CHAR(1),                      02970099
   2 PIWA2_FN3_FROM_TO_NODES,                                         02980099
```

```
  3 PIWA2_FN3_FROM_NODE              CHAR(7),                      02990099
  3 PIWA2_FN3_TO_NODE                CHAR(7),                      03000099
2 PIWA2_FN3_SANIT_SNOW_PRIORITY      CHAR(1), /*SANITATION STRT */ 03010099
                                              /*SNOW PRIORITY   */ 03020099
2 FILLER_600                         CHAR(4),                      03030099
2 PIWA2_FN3_SEGMENT_ID               CHAR(7),                      03040099
2 PIWA2_FN3_DOT_SLA                  CHAR(1),                      03050099
2 PIWA2_FN3_CURVE_FLAG               CHAR(1),                      03060099
2 PIWA2_FN3_DOG_LEG                  CHAR(1),                      03070099
2 PIWA2_FN3_FEATURE_TYPE             CHAR(1),                      03080099
2 PIWA2_FN3_SEGMENT_TYPE             CHAR(1),                      03090099
2 PIWA2_FN3_COINCIDENT_SEG_CTR       CHAR(1),                      03100099
2 FILLER_700                         CHAR(4),                      03110099
2 PIWA2_FN3_LEFT_SIDE_OF_STR,                                      03120099
  3 PIWA2_FN3_L_COM_DIST,                                          03130099
    4 PIWA2_FN3_L_COM_DIST_BORO      CHAR(1),                      03140099
    4 PIWA2_FN3_L_COM_DIST_NUM       CHAR(2),                      03150099
  3 PIWA2_FN3_L_LOW_HOUSENUM         CHAR(16),/*DISPLAY FORMAT*/   03160099
  3 PIWA2_FN3_L_HI_HOUSENUM          CHAR(16),/*DISPLAY FORMAT*/   03170099
  3 FILLER_800                       CHAR(33),/* FOR GSS USE*/     03180099
  3 PIWA2_FN3_L_ZIP                  CHAR(5),                      03190099
  3 PIWA2_FN3_L_HEALTH_AREA          CHAR(4), /*HEALTH AREA*/      03200099
  3 PIWA2_FN3_L_POLICE_DIST,                                       03210099
    4  PIWA2_FN3_L_POL_PAT_BORO_CMD  CHAR(1),                      03220099
    4  PIWA2_FN3_L_POL_PRECINCT      CHAR(3),                      03230099
  3 PIWA2_FN3_L_FIRE_DIV             CHAR(2),                      03240099
  3 PIWA2_FN3_L_FIRE_BAT             CHAR(2),                      03250099
  3 PIWA2_FN3_L_FIRE_CO,                                           03260099
    4 PIWA2_FN3_L_FIRE_CO_TYPE       CHAR(1),                      03270099
    4 PIWA2_FN3_L_FIRE_CO_NUM        CHAR(3),                      03280099
  3 PIWA2_FN3_L_SCHL_DIST            CHAR(2),                      03290099
  3 PIWA2_FN3_L_DYN_BLK              CHAR(3), /*ATOMIC POLYGON*/   03300099
  3 PIWA2_FN3_L_ED                   CHAR(3),                      03310099
  3 PIWA2_FN3_L_AD                   CHAR(2),                      03320099
  3 PIWA2_FN3_L_POLICE_PAT_BORO      CHAR(2),                      03330099
  3 FILLER_880                       CHAR(1),                      03340099
  3 PIWA2_FN3_L_BORO                 CHAR(1),                      03350099
  3 PIWA2_FN3_L_1990_CENS_TRCT       CHAR(6),                      03360099
  3 PIWA2_FN3_L_2010_CENSUS_TRACT    CHAR(6),                      03370099
  3 PIWA2_FN3_L_2010_CENSUS_BLOCK    CHAR(4),                      03380099
  3 PIWA2_FN3_L_2010_CENSUS_BLK_SF   CHAR(1), /*NOT IMPLEMENTED*/  03390099
  3 PIWA2_FN3_L_2000_CENSUS_TRACT    CHAR(6),                      03400099
  3 PIWA2_FN3_L_2000_CENSUS_BLOCK    CHAR(4),                      03410099
  3 PIWA2_FN3_L_2000_CENSUS_BLK_SF   CHAR(1),                      03420099
  3 FILLER_890                       CHAR(7),                      03430099
```

```
/**  3 PIWA2_FN3_L_BLOCKFACE_ID *V16.1* CHAR(7)  **/                 03440099
     3 PIWA2_FN3_L_NTA                  CHAR(4), /*NEIGHBORHOOD    */ 03450099
                                                 /*TABULATION AREA */ 03460099
     3 FILLER_900                       CHAR(8),                     03470099
   2 PIWA2_FN3_RIGHT_SIDE_OF_STR,                                     03480099
     3 PIWA2_FN3_R_COM_DIST,                                          03490099
       4 PIWA2_FN3_R_COM_DIST_BORO      CHAR(1),                     03500099
       4 PIWA2_FN3_R_COM_DIST_NUM       CHAR(2),                     03510099
     3 PIWA2_FN3_R_LOW_HOUSENUM         CHAR(16),/*DISPLAY FORMAT*/  03520099
     3 PIWA2_FN3_R_HI_HOUSENUM          CHAR(16),/*DISPLAY FORMAT*/  03530099
     3 FILLER_1000                      CHAR(33),/*FOR GSS USE */    03540099
     3 PIWA2_FN3_R_ZIP                  CHAR(5),                     03550099
     3 PIWA2_FN3_R_HEALTH_AREA          CHAR(4), /*HEALTH AREA*/     03560099
     3 PIWA2_FN3_R_POLICE_DIST,                                       03570099
       4  PIWA2_FN3_R_POL_PAT_BORO_CMD  CHAR(1),                     03580099
       4  PIWA2_FN3_R_POL_PRECINCT      CHAR(3),                     03590099
     3 PIWA2_FN3_R_FIRE_DIV             CHAR(2),                     03600099
     3 PIWA2_FN3_R_FIRE_BAT             CHAR(2),                     03610099
     3 PIWA2_FN3_R_FIRE_CO,                                           03620099
       4 PIWA2_FN3_R_FIRE_CO_TYPE       CHAR(1),                     03630099
       4 PIWA2_FN3_R_FIRE_CO_NUM        CHAR(3),                     03640099
     3 PIWA2_FN3_R_SCHL_DIST            CHAR(2),                     03650099
     3 PIWA2_FN3_R_DYN_BLK              CHAR(3), /*ATOMIC POLYGON*/  03660099
     3 PIWA2_FN3_R_ED                   CHAR(3),                     03670099
     3 PIWA2_FN3_R_AD                   CHAR(2),                     03680099
     3 PIWA2_FN3_R_POLICE_PAT_BORO      CHAR(2),                     03690099
     3 FILLER_1080                      CHAR(1),                     03700099
     3 PIWA2_FN3_R_BORO                 CHAR(1),                     03710099
     3 PIWA2_FN3_R_1990_CENS_TRCT       CHAR(6),                     03720099
     3 PIWA2_FN3_R_2010_CENSUS_TRACT    CHAR(6),                     03730099
     3 PIWA2_FN3_R_2010_CENSUS_BLOCK    CHAR(4),                     03740099
     3 PIWA2_FN3_R_2010_CENSUS_BLK_SF   CHAR(1), /*NOT IMPLEMENTED*/ 03750099
     3 PIWA2_FN3_R_2000_CENS_TRACT      CHAR(6),                     03760099
     3 PIWA2_FN3_R_2000_CENS_BLOCK      CHAR(4),                     03770099
     3 PIWA2_FN3_R_2000_CENS_BLK_SUF    CHAR(1),                     03780099
     3 FILLER_1090                      CHAR(7),                     03790099
/**  3 PIWA2_FN3_R_BLOCKFACE_ID *V16.1* CHAR(7)  **/                 03800099
     3 PIWA2_FN3_R_NTA                  CHAR(4), /*NEIGHBORHOOD    */ 03810099
                                                 /*TABULATION AREA */ 03820099
     3 FILLER_1100                      CHAR(8),                     03830099
   2 PIWA2_FN3_SEGAUX,                                                03840099
     3 PIWA2_FN3_SEGAUX_FILL            CHAR(6),                     03850099
     3 PIWA2_FN3_SEGAUX_CTR             CHAR(4),                     03860099
     3 PIWA2_FN3_SEGAUX_SEGS(70)        CHAR(7);                     03870099
                                                                     03880099
```

```
DCL   PIWA2_FN3_L_COMDIST                CHAR(3)                      03890099
       BASED(ADDR(PIWA2_FN3_L_COM_DIST));                            03900099
DCL   PIWA2_FN3_L_POLDIST                CHAR(4)                      03910099
       BASED(ADDR(PIWA2_FN3_L_POLICE_DIST));                         03920099
DCL   PIWA2_FN3_R_COMDIST                CHAR(3)                      03930099
       BASED(ADDR(PIWA2_FN3_R_COM_DIST));                            03940099
DCL   PIWA2_FN3_R_POLDIST                CHAR(4)                      03950099
       BASED(ADDR(PIWA2_FN3_R_POLICE_DIST));                         03960099
                                                                     03970099
/*****************************************************************/ 03980099
/*******     FOR: FUNCTION 3 EXTENDED  ****************************/ 03990099
DCL                                                                   04000099
 1 PIWA2_FUNCTION3X  BASED(PP2),                                     04010099
   2 PIWA2_3X_ACCESS_KEY                CHAR(21),                    04020099
   2 PIWA2_3X_DUP_KEY_FLAG              CHAR(1),/*(OR CONT PARITY)*/ 04030099
   2 PIWA2_3X_LOCATION_STATUS           CHAR(1),                     04040099
   2 PIWA2_3X_COUNTY_BOUNDARY           CHAR(1),                     04050099
   2 PIWA2_3X_PREF_LGC1                 CHAR(2),                     04060099
   2 PIWA2_3X_PREF_LGC2                 CHAR(2),                     04070099
   2 PIWA2_3X_PREF_LGC3                 CHAR(2),                     04080099
   2 PIWA2_3X_NUM_X_ST_LOW_END          CHAR(1),                     04090099
   2 PIWA2_3X_LOW_B5SC(5)               CHAR(6),                     04100099
   2 PIWA2_3X_NUM_X_ST_HI_END           CHAR(1),                     04110099
   2 PIWA2_3X_HI_B5SC(5)                CHAR(6),                     04120099
   2 PIWA2_3X_REVERSAL_FLAG             CHAR(1),                     04130099
   2 PIWA2_3X_LIONKEY,                                               04140099
     3 PIWA2_3X_LION_BORO               CHAR(1),                     04150099
     3 PIWA2_3X_LION_FACECODE           CHAR(4),                     04160099
     3 PIWA2_3X_LION_SEQ                CHAR(5),                     04170099
   2 PIWA2_3X_GENREC_FLAG               CHAR(1),                     04180099
   2 PIWA2_3X_SEG_LEN                   CHAR(5),                     04190099
   2 PIWA2_3X_SEG_SLOPE                 CHAR(3),                     04200099
   2 PIWA2_3X_SEG_ORIENT                CHAR(1),                     04210099
   2 PIWA2_3X_MARBLE_RIKERS_FLAG        CHAR(1),                     04220099
   2 PIWA2_3X_FROM_TO_NODES,                                         04230099
     3 PIWA2_3X_FROM_NODE               CHAR(7),                     04240099
     3 PIWA2_3X_TO_NODE                 CHAR(7),                     04250099
   2 PIWA2_3X_SANIT_SNOW_PRIORITY       CHAR(1), /*SANITATION STRT */ 04260099
                                                 /*SNOW PRIORITY   */ 04270099
   2 FILLER3X_600                       CHAR(4),                     04280099
   2 PIWA2_3X_SEGMENT_ID                CHAR(7),                     04290099
   2 PIWA2_3X_DOT_SLA                   CHAR(1),                     04300099
   2 PIWA2_3X_CURVE_FLAG                CHAR(1),                     04310099
   2 PIWA2_3X_DOG_LEG                   CHAR(1),                     04320099
   2 PIWA2_3X_FEATURE_TYPE              CHAR(1),                     04330099
```

```
  2 PIWA2_3X_SEGMENT_TYPE              CHAR(1),                      04340099
  2 PIWA2_3X_COINCIDENT_SEG_CTR        CHAR(1),                      04350099
  2 FILLER3X_700                       CHAR(4),                      04360099
  2 PIWA2_3X_LEFT_SIDE_OF_STR,                                       04370099
    3 PIWA2_3X_L_COM_DIST,                                           04380099
      4 PIWA2_3X_L_COM_DIST_BORO       CHAR(1),                      04390099
      4 PIWA2_3X_L_COM_DIST_NUM        CHAR(2),                      04400099
    3 PIWA2_3X_L_LOW_HOUSENUM          CHAR(16),/*DISPLAY FORMAT*/   04410099
    3 PIWA2_3X_L_HI_HOUSENUM           CHAR(16),/*DISPLAY FORMAT*/   04420099
    3 FILLER3X_800                     CHAR(33),/* FOR GSS USE*/     04430099
    3 PIWA2_3X_L_ZIP                   CHAR(5),                      04440099
    3 PIWA2_3X_L_HEALTH_AREA           CHAR(4), /* HEALTH AREA*/     04450099
    3 PIWA2_3X_L_POLICE_DIST,                                        04460099
      4  PIWA2_3X_L_POL_PAT_BORO_CMD CHAR(1),                        04470099
      4  PIWA2_3X_L_POL_PRECINCT       CHAR(3),                      04480099
    3 PIWA2_3X_L_FIRE_DIV              CHAR(2),                      04490099
    3 PIWA2_3X_L_FIRE_BAT              CHAR(2),                      04500099
    3 PIWA2_3X_L_FIRE_CO,                                            04510099
      4 PIWA2_3X_L_FIRE_CO_TYPE        CHAR(1),                      04520099
      4 PIWA2_3X_L_FIRE_CO_NUM         CHAR(3),                      04530099
    3 PIWA2_3X_L_SCHL_DIST             CHAR(2),                      04540099
    3 PIWA2_3X_L_DYN_BLK               CHAR(3), /*ATOMIC POLYGON*/   04550099
    3 PIWA2_3X_L_ED                    CHAR(3),                      04560099
    3 PIWA2_3X_L_AD                    CHAR(2),                      04570099
    3 PIWA2_3X_L_POLICE_PAT_BORO       CHAR(2),                      04580099
    3 FILLER3X_880                     CHAR(1),                      04590099
    3 PIWA2_3X_L_BORO                  CHAR(1),                      04600099
    3 PIWA2_3X_L_1990_CENS_TRCT        CHAR(6),                      04610099
    3 PIWA2_3X_L_2010_CENSUS_TRACT     CHAR(6),                      04620099
    3 PIWA2_3X_L_2010_CENSUS_BLOCK     CHAR(4),                      04630099
    3 PIWA2_3X_L_2010_CENSUS_BLK_SF    CHAR(1), /*NOT IMPLEMENTED*/  04640099
    3 PIWA2_3X_L_2000_CENS_TRACT       CHAR(6),                      04650099
    3 PIWA2_3X_L_2000_CENS_BLOCK       CHAR(4),                      04660099
    3 PIWA2_3X_L_2000_CENS_BLK_SF      CHAR(1),                      04670099
    3 FILLER_3X_L_890                  CHAR(7),                      04680099
/** 3 PIWA2_3X_L_BLOCKFACE_ID *V16.1*  CHAR(7)  **/                  04690099
    3 PIWA2_3X_L_NTA                   CHAR(4), /*NEIGHBORHOOD    */ 04700099
                                                /*TABULATION AREA */ 04710099
    3 FILLER_3X_L_900                  CHAR(8),                      04720099
  2 PIWA2_3X_RIGHT_SIDE_OF_STR,                                      04730099
    3 PIWA2_3X_R_COM_DIST,                                           04740099
      4 PIWA2_3X_R_COM_DIST_BORO       CHAR(1),                      04750099
      4 PIWA2_3X_R_COM_DIST_NUM        CHAR(2),                      04760099
    3 PIWA2_3X_R_LOW_HOUSENUM          CHAR(16),/*DISPLAY FORMAT*/   04770099
    3 PIWA2_3X_R_HI_HOUSENUM           CHAR(16),/*DISPLAY FORMAT*/   04780099
```

```
    3 FILLER3X_R_1000                 CHAR(33),/*FOR GSS USE */     04790099
    3 PIWA2_3X_R_ZIP                  CHAR(5),                      04800099
    3 PIWA2_3X_R_HEALTH_AREA          CHAR(4), /*HEALTH AREA*/      04810099
    3 PIWA2_3X_R_POLICE_DIST,                                       04820099
      4  PIWA2_3X_R_POL_PAT_BORO_CMD  CHAR(1),                      04830099
      4  PIWA2_3X_R_POL_PRECINCT      CHAR(3),                      04840099
    3 PIWA2_3X_R_FIRE_DIV             CHAR(2),                      04850099
    3 PIWA2_3X_R_FIRE_BAT             CHAR(2),                      04860099
    3 PIWA2_3X_R_FIRE_CO,                                           04870099
      4 PIWA2_3X_R_FIRE_CO_TYPE       CHAR(1),                      04880099
      4 PIWA2_3X_R_FIRE_CO_NUM        CHAR(3),                      04890099
    3 PIWA2_3X_R_SCHL_DIST            CHAR(2),                      04900099
    3 PIWA2_3X_R_DYN_BLK              CHAR(3), /*ATOMIC POLYGON*/   04910099
    3 PIWA2_3X_R_ED                   CHAR(3),                      04920099
    3 PIWA2_3X_R_AD                   CHAR(2),                      04930099
    3 PIWA2_3X_R_POLICE_PAT_BORO      CHAR(2),                      04940099
    3 FILLER3X_R_1080                 CHAR(1),                      04950099
    3 PIWA2_3X_R_BORO                 CHAR(1),                      04960099
    3 PIWA2_3X_R_1990_CENS_TRCT       CHAR(6),                      04970099
    3 PIWA2_3X_R_2010_CENSUS_TRACT    CHAR(6),                      04980099
    3 PIWA2_3X_R_2010_CENSUS_BLOCK    CHAR(4),                      04990099
    3 PIWA2_3X_R_2010_CENSUS_BLK_SF   CHAR(1), /*NOT IMPLEMENTED*/  05000099
    3 PIWA2_3X_R_2000_CENS_TRACT      CHAR(6),                      05010099
    3 PIWA2_3X_R_2000_CENS_BLOCK      CHAR(4),                      05020099
    3 PIWA2_3X_R_2000_CENS_BLK_SF     CHAR(1),                      05030099
    3 FILLER3X_R_1090                 CHAR(7),                      05040099
/** 3 PIWA2_3X_R_BLOCKFACE_ID *V16.1* CHAR(7)  **/                  05050099
    3 PIWA2_3X_R_NTA                  CHAR(4), /*NEIGHBORHOOD    */ 05060099
                                               /*TABULATION AREA */ 05070099
    3 FILLER_3X_R_1100                CHAR(8),                      05080099
  2   PIWA2_3X_LGCS                   CHAR(8),                      05090099
  2   PIWA2_3X_LGCS_FROM              CHAR(8),                      05100099
  2   PIWA2_3X_LGCS_TO                CHAR(8),                      05110099
  2   PIWA2_3X_L_HEALTH_CTR_DIST      CHAR(2), /*HEALTH CENTER*/    05120099
  2   PIWA2_3X_R_HEALTH_CTR_DIST      CHAR(2), /*HEALTH CENTER*/    05130099
  2   PIWA2_3X_FILL1                  CHAR(1),                      05140099
  2   PIWA2_3X_TRAFFIC_DIR            CHAR(1),                      05150099
  2   PIWA2_3X_ROADWAY_TYPE           CHAR(2),                      05160099
  2   PIWA2_3X_PHYSICAL_ID            CHAR(7),                      05170099
  2   PIWA2_3X_GENERIC_ID             CHAR(7),                      05180099
  2   PIWA2_3X_INTP_ID                CHAR(7),  /*INTERNAL USE*/    05190099
  2   PIWA2_3X_INTF_ID                CHAR(7),  /*INTERNAL USE*/    05200099
  2   PIWA2_3X_STR_STATUS             CHAR(1),                      05210099
  2   PIWA2_3X_STR_WIDTH              CHAR(3),                      05220099
  2   PIWA2_3X_STR_WIDTH_IRREG        CHAR(1),                      05230099
```

```
   2   PIWA2_3X_BIKE_LANE              CHAR(1),                     05240099
   2   PIWA2_3X_FED_CLASS_CODE         CHAR(2),                     05250099
   2   PIWA2_3X_ROW_TYPE               CHAR(1),                     05260099
   2   PIWA2_3X_LGC_LIST               CHAR(10),                    05270099
   2   PIWA2_3X_LEGACY_ID              CHAR(7),                     05280099
   2   PIWA2_3X_L_NTA_NAME             CHAR(75),                    05290099
   2   PIWA2_3X_R_NTA_NAME             CHAR(75),                    05300099
   2   PIWA2_3X_FROM_XCOORD            CHAR(7),                     05310099
   2   PIWA2_3X_FROM_YCOORD            CHAR(7),                     05320099
   2   PIWA2_3X_TO_XCOORD              CHAR(7),                     05330099
   2   PIWA2_3X_TO_YCOORD              CHAR(7),                     05340099
   2   PIWA2_3X_FROM_LATITUDE          CHAR(9),                     05350099
   2   PIWA2_3X_FROM_LONGITUDE         CHAR(11),                    05360099
   2   PIWA2_3X_TO_LATITUDE            CHAR(9),                     05370099
   2   PIWA2_3X_TO_LONGITUDE           CHAR(11),                    05380099
   2   PIWA2_3X_L_BLOCKFACE_ID         CHAR(10),                    05390099
   2   PIWA2_3X_R_BLOCKFACE_ID         CHAR(10),                    05400099
   2   PIWA2_3X_NBR_TRAVEL_LANES       CHAR(2),                     05410099
   2   PIWA2_3X_NBR_PARK_LANES         CHAR(2),                     05420099
   2   PIWA2_3X_NBR_TOTAL_LANES        CHAR(2),                     05430099
   2   PIWA2_3X_BIKE_LANE_2            CHAR(2),                     05431099
   2   PIWA2_3X_STR_WIDTH_MAX          CHAR(3),                     05432099
   2   PIWA2_3X_BIKE_TRAFFIC_DIR       CHAR(2),                     05433099
   2   PIWA2_3X_SPEED_LIMIT            CHAR(2),                     05434099
   2   PIWA2_3X_LEFT_PUMA_CODE         CHAR(5),                     05435099
   2   PIWA2_3X_RIGHT_PUMA_CODE        CHAR(5),                     05436099
   2   PIWA2_3X_FILL2                  CHAR(201),                   05440099
/* 2   PIWA2_3X_FILL2 ** V18.1   ***   CHAR(211), **/               05440199
/* 2   PIWA2_3X_FILL2 ** V17.1   ***   CHAR(215), **/               05441099
/* 2   PIWA2_3X_FILL2 ** V16.4   ***   CHAR(220), **/               05442099
/* 2   PIWA2_3X_FILL2 ** V16.1   ***   CHAR(246)  **/               05450099
/* 2   PIWA2_3X_FILL2 ** V15.3   ***   CHAR(286)  **/               05460099
   2 PIWA2_3X_SEGAUX,                                               05470099
     3 PIWA2_3X_SEGAUX_FILL            CHAR(6),                     05480099
     3 PIWA2_3X_SEGAUX_CTR             CHAR(4),                     05490099
     3 PIWA2_3X_SEGAUX_SEGS(70)        CHAR(7);                     05500099
                                                                    05510099
/*****************************************************************/ 05520099
/*******     FOR: FUNCTION 3C          ****************************/ 05530099
DCL                                                                  05540099
 1 PIWA2_FUNCTION3C  BASED(PP2),                                     05550099
   2 PIWA2_FN3C_ACCESS_KEY           CHAR(21),                     05560099
   2 PIWA2_FN3C_DUP_KEY_FLAG         CHAR(1),/*(OR CONT PARITY)*/  05570099
   2 PIWA2_FN3C_LOCATION_STATUS      CHAR(1),                      05580099
   2 PIWA2_FN3C_COUNTY_BOUNDARY      CHAR(1),                      05590099
```

```
2 PIWA2_FN3C_PREF_LGC1              CHAR(2),                      05600099
2 PIWA2_FN3C_PREF_LGC2              CHAR(2),                      05610099
2 PIWA2_FN3C_PREF_LGC3              CHAR(2),                      05620099
2 PIWA2_FN3C_NUM_X_ST_LOW_END       CHAR(1),                      05630099
2 PIWA2_FN3C_LOW_B5SC(5)            CHAR(6),                      05640099
2 PIWA2_FN3C_NUM_X_ST_HI_END        CHAR(1),                      05650099
2 PIWA2_FN3C_HI_B5SC(5)             CHAR(6),                      05660099
2 PIWA2_FN3C_REVERSAL_FLAG          CHAR(1),                      05670099
2 PIWA2_FN3C_LIONKEY,                                             05680099
  3 PIWA2_FN3C_LION_BORO            CHAR(1),                      05690099
  3 PIWA2_FN3C_LION_FACECODE        CHAR(4),                      05700099
  3 PIWA2_FN3C_LION_SEQ             CHAR(5),                      05710099
2 PIWA2_FN3C_GENREC_FLAG            CHAR(1),                      05720099
2 PIWA2_FN3C_SEG_LEN                CHAR(5),                      05730099
2 PIWA2_FN3C_SEG_SLOPE              CHAR(3),                      05740099
2 PIWA2_FN3C_SEG_ORIENT             CHAR(1),                      05750099
2 PIWA2_FN3C_MARBLE_RIKERS_FLAG     CHAR(1),                      05760099
2 PIWA2_FN3C_FROM_TO_NODES,                                       05770099
  3 PIWA2_FN3C_FROM_NODE            CHAR(7),                      05780099
  3 PIWA2_FN3C_TO_NODE              CHAR(7),                      05790099
2 PIWA2_FN3C_SANIT_SNOW_PRIORITY    CHAR(1), /*SANITATION STRT */ 05800099
                                             /*SNOW PRIORITY   */ 05810099
2 FILLER_1200                       CHAR(4),                      05820099
2 PIWA2_FN3C_SEGMENT_ID             CHAR(7),                      05830099
2 PIWA2_FN3C_DOT_SLA                CHAR(1),                      05840099
2 PIWA2_FN3C_SIDE_OF_STR            CHAR(1),                      05850099
2 PIWA2_FN3C_CURVE_FLAG             CHAR(1),                      05860099
2 PIWA2_FN3C_FEATURE_TYPE           CHAR(1),                      05870099
2 PIWA2_FN3C_SEGMENT_TYPE           CHAR(1),                      05880099
2 PIWA2_FN3C_COINCIDENT_SEG_CTR     CHAR(1),                      05890099
2 FILLER_1300                       CHAR(4),                      05900099
2 PIWA2_FN3C_BLOCKFACE_INFO,                                      05910099
  3 PIWA2_FN3C_COM_DIST,                                          05920099
    4 PIWA2_FN3C_COM_DIST_BORO      CHAR(1),                      05930099
    4 PIWA2_FN3C_COM_DIST_NUM       CHAR(2),                      05940099
  3 PIWA2_FN3C_LOW_HOUSENUM         CHAR(16),/*DISPLAY FORMAT*/   05950099
  3 PIWA2_FN3C_HI_HOUSENUM          CHAR(16),/*DISPLAY FORMAT*/   05960099
  3 PIWA2_FN3C_LOW_HOUSENUM2        CHAR(16),/*DISPLAY FORMAT*/   05970099
  3 PIWA2_FN3C_HI_HOUSENUM2         CHAR(16),/*DISPLAY FORMAT*/   05980099
  3 FILLER_1400                     CHAR(1), /* FOR GSS USE */    05990099
  3 PIWA2_FN3C_ZIP                  CHAR(5),                      06000099
  3 PIWA2_FN3C_HEALTH_AREA          CHAR(4), /*HEALTH AREA*/      06010099
  3 PIWA2_FN3C_POLICE_DIST,                                       06020099
    4 PIWA2_FN3C_POL_PAT_BORO_CMD   CHAR(1),                      06030099
    4 PIWA2_FN3C_POL_PRECINCT       CHAR(3),                      06040099
```

```
     3 PIWA2_FN3C_FIRE_DIV              CHAR(2),                      06050099
     3 PIWA2_FN3C_FIRE_BAT              CHAR(2),                      06060099
     3 PIWA2_FN3C_FIRE_CO,                                            06070099
       4 PIWA2_FN3C_FIRE_CO_TYPE        CHAR(1),                      06080099
       4 PIWA2_FN3C_FIRE_CO_NUM         CHAR(3),                      06090099
     3 PIWA2_FN3C_SCHL_DIST             CHAR(2),                      06100099
     3 PIWA2_FN3C_DYN_BLK               CHAR(3), /*ATOMIC POLYGON*/   06110099
     3 PIWA2_FN3C_ED                    CHAR(3),                      06120099
     3 PIWA2_FN3C_AD                    CHAR(2),                      06130099
     3 PIWA2_FN3C_POLICE_PAT_BORO       CHAR(2),                      06140099
     3 FILLER_1480                      CHAR(1),                      06150099
     3 PIWA2_FN3C_BORO                  CHAR(1),                      06160099
     3 PIWA2_FN3C_1990_CENS_TRCT        CHAR(6),                      06170099
     3 PIWA2_FN3C_2010_CENSUS_TRACT     CHAR(6),                      06180099
     3 PIWA2_FN3C_2010_CENSUS_BLOCK     CHAR(4),                      06190099
     3 PIWA2_FN3C_2010_CENSUS_BLK_SF    CHAR(1), /*NOT IMPLEMENTED*/  06200099
     3 PIWA2_FN3C_2000_CENS_TRACT       CHAR(6),                      06210099
     3 PIWA2_FN3C_2000_CENS_BLOCK       CHAR(4),                      06220099
     3 PIWA2_FN3C_2000_CENS_BLK_SUF     CHAR(1),                      06230099
     3 FILLER_1490                      CHAR(7),                      06240099
/**  3 PIWA2_FN3C_BLOCKFACE_ID *V16.1*  CHAR(7)  **/                  06250099
     3 PIWA2_FN3C_NTA                   CHAR(4), /*NEIGHBORHOOD    */ 06260099
                                                 /*TABULATION AREA */ 06270099
     3 FILLER_1500                      CHAR(8),                      06280099
   2 PIWA2_FN3C_SEGAUX,                                               06290099
     3 PIWA2_FN3C_SEGAUX_FILL           CHAR(6),                      06300099
     3 PIWA2_FN3C_SEGAUX_CTR            CHAR(4),                      06310099
     3 PIWA2_FN3C_SEGAUX_SEGS(70)       CHAR(7);                      06320099
                                                                      06330099
DCL   PIWA2_FN3C_COMDIST                 CHAR(3)                       06340099
       BASED(ADDR(PIWA2_FN3C_COM_DIST));                              06350099
DCL   PIWA2_FN3C_POLDIST                 CHAR(4)                       06360099
       BASED(ADDR(PIWA2_FN3C_POLICE_DIST));                           06370099
                                                                      06380099
/*******************************************************************/ 06390099
/*******     FOR: FUNCTION 3CX (EXTENDED) *************************/ 06400099
DCL                                                                   06410099
 1 PIWA2_FUNCTION3CX BASED(PP2),                                      06420099
   2 PIWA2_3CX_ACCESS_KEY               CHAR(21),                     06430099
   2 PIWA2_3CX_DUP_KEY_FLAG             CHAR(1),/*(OR CONT PARITY)*/  06440099
   2 PIWA2_3CX_LOCATION_STATUS          CHAR(1),                      06450099
   2 PIWA2_3CX_COUNTY_BOUNDARY          CHAR(1),                      06460099
   2 PIWA2_3CX_PREF_LGC1                CHAR(2),                      06470099
   2 PIWA2_3CX_PREF_LGC2                CHAR(2),                      06480099
   2 PIWA2_3CX_PREF_LGC3                CHAR(2),                      06490099
```

```
2 PIWA2_3CX_NUM_X_ST_LOW_END        CHAR(1),                      06500099
2 PIWA2_3CX_LOW_B5SC(5)             CHAR(6),                      06510099
2 PIWA2_3CX_NUM_X_ST_HI_END         CHAR(1),                      06520099
2 PIWA2_3CX_HI_B5SC(5)              CHAR(6),                      06530099
2 PIWA2_3CX_REVERSAL_FLAG           CHAR(1),                      06540099
2 PIWA2_3CX_LIONKEY,                                              06550099
  3 PIWA2_3CX_LION_BORO             CHAR(1),                      06560099
  3 PIWA2_3CX_LION_FACECODE         CHAR(4),                      06570099
  3 PIWA2_3CX_LION_SEQ              CHAR(5),                      06580099
2 PIWA2_3CX_GENREC_FLAG             CHAR(1),                      06590099
2 PIWA2_3CX_SEG_LEN                 CHAR(5),                      06600099
2 PIWA2_3CX_SEG_SLOPE               CHAR(3),                      06610099
2 PIWA2_3CX_SEG_ORIENT              CHAR(1),                      06620099
2 PIWA2_3CX_MARBLE_RIKERS_FLAG      CHAR(1),                      06630099
2 PIWA2_3CX_FROM_TO_NODES,                                        06640099
  3 PIWA2_3CX_FROM_NODE             CHAR(7),                      06650099
  3 PIWA2_3CX_TO_NODE               CHAR(7),                      06660099
2 PIWA2_3CX_SANIT_SNOW_PRIORITY     CHAR(1), /*SANITATION STRT */ 06670099
                                             /*SNOW PRIORITY   */ 06680099
2 FILLER3CX_1200                    CHAR(4),                      06690099
2 PIWA2_3CX_SEGMENT_ID              CHAR(7),                      06700099
2 PIWA2_3CX_DOT_SLA                 CHAR(1),                      06710099
2 PIWA2_3CX_SIDE_OF_STR             CHAR(1),                      06720099
2 PIWA2_3CX_CURVE_FLAG              CHAR(1),                      06730099
2 PIWA2_3CX_FEATURE_TYPE            CHAR(1),                      06740099
2 PIWA2_3CX_SEGMENT_TYPE            CHAR(1),                      06750099
2 PIWA2_3CX_COINCIDENT_SEG_CTR      CHAR(1),                      06760099
2 FILLER3CX_1300                    CHAR(4),                      06770099
2 PIWA2_3CX_BLOCKFACE_INFO,                                       06780099
  3 PIWA2_3CX_COM_DIST,                                           06790099
    4 PIWA2_3CX_COM_DIST_BORO       CHAR(1),                      06800099
    4 PIWA2_3CX_COM_DIST_NUM        CHAR(2),                      06810099
  3 PIWA2_3CX_LOW_HOUSENUM          CHAR(16),/*DISPLAY FORMAT*/   06820099
  3 PIWA2_3CX_HI_HOUSENUM           CHAR(16),/*DISPLAY FORMAT*/   06830099
  3 PIWA2_3CX_LOW_HOUSENUM2         CHAR(16),/*DISPLAY FORMAT*/   06840099
  3 PIWA2_3CX_HI_HOUSENUM2          CHAR(16),/*DISPLAY FORMAT*/   06850099
  3 FILLER3CX_1400                  CHAR(1), /* FOR GSS USE */    06860099
  3 PIWA2_3CX_ZIP                   CHAR(5),                      06870099
  3 PIWA2_3CX_HEALTH_AREA           CHAR(4), /*HEALTH AREA*/      06880099
  3 PIWA2_3CX_POLICE_DIST,                                        06890099
    4 PIWA2_3CX_POL_PAT_BORO_CMD    CHAR(1),                      06900099
    4 PIWA2_3CX_POL_PRECINCT        CHAR(3),                      06910099
  3 PIWA2_3CX_FIRE_DIV              CHAR(2),                      06920099
  3 PIWA2_3CX_FIRE_BAT              CHAR(2),                      06930099
  3 PIWA2_3CX_FIRE_CO,                                            06940099
```

```
      4 PIWA2_3CX_FIRE_CO_TYPE         CHAR(1),                      06950099
      4 PIWA2_3CX_FIRE_CO_NUM          CHAR(3),                      06960099
    3 PIWA2_3CX_SCHL_DIST              CHAR(2),                      06970099
    3 PIWA2_3CX_DYN_BLK                CHAR(3), /*ATOMIC POLYGON*/   06980099
    3 PIWA2_3CX_ED                     CHAR(3),                      06990099
    3 PIWA2_3CX_AD                     CHAR(2),                      07000099
    3 PIWA2_3CX_POLICE_PAT_BORO        CHAR(2),                      07010099
    3 FILLER3CX_1480                   CHAR(1),                      07020099
    3 PIWA2_3CX_BORO                   CHAR(1),                      07030099
    3 PIWA2_3CX_1990_CENS_TRCT         CHAR(6),                      07040099
    3 PIWA2_3CX_2010_CENSUS_TRACT      CHAR(6),                      07050099
    3 PIWA2_3CX_2010_CENSUS_BLOCK      CHAR(4),                      07060099
    3 PIWA2_3CX_2010_CENSUS_BLK_SF     CHAR(1), /*NOT IMPLEMENTED*/  07070099
    3 PIWA2_3CX_2000_CENS_TRACT        CHAR(6),                      07080099
    3 PIWA2_3CX_2000_CENS_BLOCK        CHAR(4),                      07090099
    3 PIWA2_3CX_2000_CENS_BLK_S        CHAR(1),                      07100099
    3 FILLER3CX_1490                   CHAR(7),                      07110099
/** 3 PIWA2_3CX_BLOCKFACE_ID *V16.1*   CHAR(7)  **/                  07120099
    3 PIWA2_3CX_NTA                    CHAR(4), /*NEIGHBORHOOD    */ 07130099
                                                /*TABULATION AREA */ 07140099
    3 FILLER3CX_1500                   CHAR(8),                      07150099
                                                                     07160099
  2   PIWA2_3CX_LGCS                   CHAR(8),                      07170099
  2   PIWA2_3CX_LGCS_FROM              CHAR(8),                      07180099
  2   PIWA2_3CX_LGCS_TO                CHAR(8),                      07190099
  2   PIWA2_3CX_L_HEALTH_CTR_DIST      CHAR(2), /*HEALTH CENTER*/    07200099
  2   PIWA2_3CX_R_HEALTH_CTR_DIST      CHAR(2), /*HEALTH CENTER*/    07210099
  2   PIWA2_3CX_FILL1550               CHAR(1),                      07220099
  2   PIWA2_3CX_TRAFFIC_DIRECTN        CHAR(1),                      07230099
  2   PIWA2_3CX_ROADWAY_TYPE           CHAR(2),                      07240099
  2   PIWA2_3CX_PHYSICAL_ID            CHAR(7),                      07250099
  2   PIWA2_3CX_GENERIC_ID             CHAR(7),                      07260099
  2   PIWA2_3CX_INTP_ID                CHAR(7),  /*INTERNAL USE*/    07270099
  2   PIWA2_3CX_INTF_ID                CHAR(7),  /*INTERNAL USE*/    07280099
  2   PIWA2_3CX_STREET_STATUS          CHAR(1),                      07290099
  2   PIWA2_3CX_STREET_WIDTH           CHAR(3),                      07300099
  2   PIWA2_3CX_STREET_WIDTH_IRREG     CHAR(1),                      07310099
  2   PIWA2_3CX_BIKE_LANE              CHAR(1),                      07320099
  2   PIWA2_3CX_FED_CLASS_CODE         CHAR(2),                      07330099
  2   PIWA2_3CX_ROW_TYPE               CHAR(1),                      07340099
  2   PIWA2_3CX_LGC_LIST               CHAR(10),                     07350099
  2   PIWA2_3CX_LEGACY_ID              CHAR(7),                      07360099
  2   PIWA2_3CX_NTA_NAME               CHAR(75),                     07370099
  2   PIWA2_3CX_FROM_XCOORD            CHAR(7),                      07380099
  2   PIWA2_3CX_FROM_YCOORD            CHAR(7),                      07390099
```

```
   2   PIWA2_3CX_TO_XCOORD             CHAR(7),                    07400099
   2   PIWA2_3CX_TO_YCOORD             CHAR(7),                    07410099
   2   PIWA2_3CX_FROM_LATITUDE         CHAR(9),                    07420099
   2   PIWA2_3CX_FROM_LONGITUDE        CHAR(11),                   07430099
   2   PIWA2_3CX_TO_LATITUDE           CHAR(9),                    07440099
   2   PIWA2_3CX_TO_LONGITUDE          CHAR(11),                   07450099
   2   PIWA2_3CX_BLOCKFACE_ID          CHAR(10),                   07460099
   2   PIWA2_3CX_NBR_TRAVEL_LANES      CHAR(2),                    07470099
   2   PIWA2_3CX_NBR_PARK_LANES        CHAR(2),                    07480099
   2   PIWA2_3CX_NBR_TOTAL_LANES       CHAR(2),                    07490099
   2   PIWA2_3CX_BIKE_LANE_2           CHAR(2),                    07491099
   2   PIWA2_3CX_STREET_WIDTH_MAX      CHAR(3),                    07492099
   2   PIWA2_3CX_BIKE_TRAFFIC_DIR      CHAR(2),                    07493099
   2   PIWA2_3CX_SPEED_LIMIT           CHAR(2),                    07494099
   2   PIWA2_3CX_PUMA_CODE             CHAR(5),                    07494199
   2   PIWA2_3CX_FILL1560              CHAR(291),                  07495099
/* 2   PIWA2_3CX_FILL1560 ** V18.1 **  CHAR(296), **/              07500099
/* 2   PIWA2_3CX_FILL1560 ** V17.4 **  CHAR(298), **/              07500199
/* 2   PIWA2_3CX_FILL1560 ** V17.1 **  CHAR(300), **/              07501099
/* 2   PIWA2_3CX_FILL1560 ** V16.4 **  CHAR(305), **/              07502099
/* 2   PIWA2_3CX_FILL1560 ** V16.1 **  CHAR(321)  **/              07510099
/* 2   PIWA2_3CX_FILL1560 ** V15.3 **  CHAR(361)  **/              07520099
   2 PIWA2_3CX_SEGAUX,                                            07530099
     3 PIWA2_3CX_SEGAUX_FILL           CHAR(6),                    07540099
     3 PIWA2_3CX_SEGAUX_CTR            CHAR(4),                    07550099
     3 PIWA2_3CX_SEGAUX_SEGS(70)       CHAR(7);                    07560099
                                                                   07570099
/*******************************************************************/ 07580099
/*******     FOR: FUNCTION 5          ****************************/ 07590099
DCL                                                                 07600099
 1 PIWA2_FUNCTION5   BASED(PP2),                                   07610099
   2 PIWA2_FN5_ADDR_MATCHING_KEY     CHAR(33),                    07620099
   2 FILLER_1600                     CHAR(267);                   07630099
                                                                   07640099
PP2=ADDR(P2PL1);                                                    07650099
```

P2PL11A COPY File

```
/*******************************************************************/  00000100
/***  THIS IS THE PL/1 STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM  ***/  00000200
/***  INDEPENDENT REGULAR WORK AREA 2 FOR FUNCTIONS: 1A , BL,    ***/  00000300
/***  AND BN.                                                    ***/  00000400
/***  THESE THREE FUNCTIONS SHARE A SINGLE WORK AREA 2 LAYOUT.   ***/  00000500
/***                                                             ***/  00000600
```

```
/***  COPY FILE - P2PL11A.                          10/10/97     ***/  00000700
/*******************************************************************/  00000800
                                                                       00000900
DCL                                                                    00001000
 1 P2PL11A,                                                            00001100
   2 PIWA2_1A_ACCESS_KEY                CHAR(21),                      00001200
   2 PIWA2_1A_CONT_PARITY               CHAR(1), /*(OR DUP ADDR IND)*/ 00001300
   2 PIWA2_1A_LOW_HOUSENUM              CHAR(11), /* SORT FORMAT */   00001400
   2 PIWA2_1A_BBL,                                                     00001500
     3 PIWA2_1A_BBL_BORO                CHAR(1),                       00001600
     3 PIWA2_1A_BLOCK                   CHAR(5),                       00001700
     3 PIWA2_1A_LOT                     CHAR(4),                       00001800
   2 PIWA2_1A_LOT_VER                   CHAR(1),                       00001900
   2 PIWA2_1A_SCC                       CHAR(1),                       00002000
   2 FILLER_100                         CHAR(1),                       00002100
   2 PIWA2_1A_GENERAL_LOT_INFO,                                        00002200
     3 PIWA2_1A_RPAD_BLDG_CLASS         CHAR(2),                       00002300
     3 PIWA2_1A_CORNER_CODE             CHAR(2),                       00002400
     3 PIWA2_1A_NUM_OF_STRUCTURES       CHAR(4),                       00002502
     3 PIWA2_1A_NUM_OF_BLOCKFACES       CHAR(2),                       00002600
     3 PIWA2_1A_INTERIOR_FLAG           CHAR(1),                       00002700
     3 PIWA2_1A_VACANT_FLAG             CHAR(1),                       00002800
     3 PIWA2_1A_IRREG_LOT_FLAG          CHAR(1),                       00002900
   2 PIWA2_1A_MARBLE_RIKERS_FLAG        CHAR(1),                       00003000
   2 PIWA2_1A_ADDR_LIST_OVFLOW_FLAG     CHAR(1),                       00003100
   2 PIWA2_1A_STROLL_KEY,                                              00003200
     3 PIWA2_1A_STROLL_BORO             CHAR(1),                       00003300
     3 PIWA2_1A_STROLL_5SC              CHAR(5),                       00003400
     3 PIWA2_1A_STROLL_SIDE_OF_STR      CHAR(1),  /* L, R */           00003500
     3 PIWA2_1A_STROLL_HI_HOUSENUM      CHAR(11), /* SORT FORMAT */    00003600
     3 FILLER_200                       CHAR(1),                       00003700
   2 FILLER_300                         CHAR(1),  /* FOR GSS USE*/     00003800
   2 PIWA2_1A_BIN                       CHAR(7),                       00003900
   2 PIWA2_1A_CONDO_FLAG                CHAR(1),                       00004000
   2 FILLER_400                         CHAR(1),                       00004100
   2 PIWA2_1A_RPAD_CONDO_ID_NUM         CHAR(4),                       00004200
   2 PIWA2_1A_CONDO_UNIT_ID_NUM         CHAR(7),                       00004300
   2 PIWA2_1A_CONDO_BILL_BBL            CHAR(10),                      00004400
   2 PIWA2_1A_CONDO_BILL_BBL_VER        CHAR(1),                       00004500
   2 PIWA2_1A_CONDO_BILL_BBL_SCC        CHAR(1),                       00004600
   2 PIWA2_1A_CONDO_LOW_BBL             CHAR(10),                      00004700
   2 PIWA2_1A_CONDO_LOW_BBL_VER         CHAR(1),                       00004800
   2 PIWA2_1A_CONDO_HIGH_BBL            CHAR(10),                      00004900
   2 PIWA2_1A_CONDO_HIGH_BBL_VER        CHAR(1),                       00005000
   2 FILLER_500                         CHAR(15),                      00005100
```

```
  2 PIWA2_1A_COOP_NUM                CHAR(4),                      00005200
  2 PIWA2_1A_SANBORN,                                              00005300
    3 PIWA2_1A_SANBORN_BORO          CHAR(1),                      00005400
    3 PIWA2_1A_SANBORN_VOL           CHAR(3),                      00005500
    3 PIWA2_1A_SANBORN_PAGE          CHAR(4),                      00005600
  2 PIWA2_1A_COMMERC_DIST            CHAR(5),                      00005700
  2 PIWA2_1A_DOF_MAP_BORO            CHAR(1),                      00005803
  2 PIWA2_1A_DOF_MAP_SECVOL          CHAR(4),                      00005902
  2 PIWA2_1A_DOF_MAP_PAGE            CHAR(4),                      00006003
  2 RESERVED_DCP                     CHAR(3),                      00006110
  2 PIWA2_1A_LATITUDE                CHAR(09),                     00006210
  2 PIWA2_1A_LONGITUDE               CHAR(11),                     00006310
  2 PIWA2_1A_X_COORD                 CHAR(07),                     00006410
  2 PIWA2_1A_Y_COORD                 CHAR(07),                     00006510
  2 PIWA2_1A_BID                     CHAR(06),                     00006610
  2 PIWA2_1A_TPAD_BIN_ST             CHAR(01),  /*CURRENT STATUS*/ 00006710
  2 PIWA2_1A_TPAD_NEW_BIN            CHAR(07),  /*NEW BIN       */ 00006810
  2 PIWA2_1A_TPAD_NEW_BIN_ST         CHAR(01),  /*NEW BIN STATUS*/ 00006910
  2 PIWA2_1A_TPAD_CONFLICT           CHAR(01),  /*CONFLICT FLAG */ 00007010
  2 PIWA2_1A_DCP_ZONE_MAP            CHAR(03),  /*DCP ZONING MAP*/ 00007111
  2 FILLER_650                       CHAR(06),                     00007211
  2 FILLER_700                       CHAR(8),  /* LGC - GSS USE*/  00007311
  2 PIWA2_1A_NUM_OF_ADDR             CHAR(4),                      00007411
  2 PIWA2_1A_ADDR_LIST(21),                                        00007511
    3 PIWA2_1A_LIST_LOW_HOUSENUM     CHAR(16), /*DISPLAY FORMAT*/  00007611
    3 PIWA2_1A_LIST_HI_HOUSENUM      CHAR(16), /*DISPLAY FORMAT*/  00007711
    3 PIWA2_1A_LIST_BORO             CHAR(1),                      00007811
    3 PIWA2_1A_LIST_5SC              CHAR(5),                      00007911
    3 PIWA2_1A_LIST_LGC              CHAR(2),                      00008011
    3 PIWA2_1A_LIST_BIN              CHAR(7),                      00008111
    3 PIWA2_1A_LIST_SIDE_OF_STR      CHAR(1),  /* L, R */          00008211
    3 PIWA2_1A_ADDR_TYPE             CHAR(1),  /*              */  00008311
                                               /* BLANK = NORMAL*/ 00008411
    3 PIWA2_1A_TPAD_STATUS           CHAR(1),  /* 0 - 9        */  00008511
    3 FILLER_800                     CHAR(3);                      00008611
                                                                   00008711
DCL  PIWA2_1A_SANBORN_BVOLPAGE       CHAR(8)                       00008811
       BASED(ADDR(PIWA2_1A_SANBORN));                              00008911
DCL  PIWA2_1A_STROLLKEY              CHAR(19)                      00009011
       BASED(ADDR(PIWA2_1A_STROLL_KEY));                           00010011
```

P2PL11AL COPY File

```
/*****************************************************************/  00000100
```

```
/*******************************************************************/00000276
/*                                                                 */00000376
/***                      P2PL1AL                                ***/00000480
/*  ADD NEW 5 BYTE PUMA CODE                          YNL 12/17 V18.1*/00000584
/***           LAST MODIFIED DECEMBER 2016                       ***/00000680
/*  ADD NEW 2 BYTE SPEED LIMIT                        TLV 09/17 V17.4*/00000782
/*  ADD NEW 2 BYTE BIKE TRAFFIC DIRECTION             YNL 12/16 V17,1*/00000880
/*  REPLACED SANIT_RESERVED WITH SANIT_BULK_PICK_UP   YNL 10/16 V16.4*/00000982
/*  ADD NEW 2 BYTE BIKE LANE AND MAX STR WIDTH        YNL 10/16 V16.4*/00001082
/*                                                                 */00001176
/*******************************************************************/00001276
/***  THIS IS THE PL/1 STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM  ***/  00001300
/***  INDEPENDENT LONG WORK AREA 2 FOR FUNCTIONS: 1A , AND BL.   ***/  00001400
/***  THESE TWO FUNCTIONS SHARE A SINGLE LONG WORK AREA 2 LAYOUT.***/  00001500
/***  THIS IS ALSO THE PL/1 STRUCTURE FOR GEOSUPPORT SYSTEM      ***/  00001615
/***   PLATFORM INDEPENDENT EXTENDED WORK AREA 2 FOR             ***/  00001715
/***   FUNCTIONS 1E AND 1A, AND FOR FUNCTION 1B WHICH IS A       ***/  00001835
/***   COMBINATION OF EXTENDED 1/1E AND EXTENDED 1A)             ***/  00001926
/***                                                             ***/  00002000
/***                           LAST MODIFIED OCTOBER  2016       ***/  00002176
/***  COPY FILE - P2PL11AL.                          10/11/2000  ***/  00002226
/*******************************************************************/  00002326
                                                                        00002426
DCL                                                                     00002526
 1 P2PL11AL,                                                            00002626
   2 PIWA2_1AL_ACCESS_KEY              CHAR(21),                        00002726
   2 PIWA2_1AL_CONT_PARITY             CHAR(1), /*(OR DUP ADDR IND)*/ 00002826
   2 PIWA2_1AL_LOW_HOUSENUM            CHAR(11), /* SORT FORMAT */    00002926
   2 PIWA2_1AL_BBL,                                                     00003026
     3 PIWA2_1AL_BBL_BORO              CHAR(1),                         00003126
     3 PIWA2_1AL_BLOCK                 CHAR(5),                         00003226
     3 PIWA2_1AL_LOT                   CHAR(4),                         00003326
   2 PIWA2_1AL_LOT_VER                 CHAR(1),                         00003426
   2 PIWA2_1AL_SCC                     CHAR(1),                         00003526
   2 FILLER_100                        CHAR(1),                         00003626
   2 PIWA2_1AL_GENERAL_LOT_INFO,                                        00003726
     3 PIWA2_1AL_RPAD_BLDG_CLASS       CHAR(2),                         00003826
     3 PIWA2_1AL_CORNER_CODE           CHAR(2),                         00003926
     3 PIWA2_1AL_NUM_OF_STRUCTURES     CHAR(4),                         00004026
     3 PIWA2_1AL_NUM_OF_BLOCKFACES     CHAR(2),                         00004126
     3 PIWA2_1AL_INTERIOR_FLAG         CHAR(1),                         00004226
     3 PIWA2_1AL_VACANT_FLAG           CHAR(1),                         00004326
     3 PIWA2_1AL_IRREG_LOT_FLAG        CHAR(1),                         00004426
   2 PIWA2_1AL_MARBLE_RIKERS_FLAG      CHAR(1),                         00004526
   2 PIWA2_1AL_ADDR_LIST_OVFLOW_FLAG   CHAR(1),                         00004626
```

```
2 PIWA2_1AL_STROLL_KEY,                                          00004726
  3 PIWA2_1AL_STROLL_BORO            CHAR(1),                    00004826
  3 PIWA2_1AL_STROLL_5SC             CHAR(5),                    00004926
  3 PIWA2_1AL_STROLL_SIDE_OF_STR     CHAR(1),  /* L, R */        00005026
  3 PIWA2_1AL_STROLL_HI_HOUSENUM     CHAR(11), /* SORT FORMAT */ 00005126
  3 FILLER_200                       CHAR(1),                    00005226
2 FILLER_300                         CHAR(1),  /* FOR GSS USE*/  00005326
2 PIWA2_1AL_BIN                      CHAR(7),                    00005426
2 PIWA2_1AL_CONDO_FLAG               CHAR(1),                    00005526
2 FILLER_400                         CHAR(1),                    00005626
2 PIWA2_1AL_RPAD_CONDO_ID_NUM        CHAR(4),                    00005726
2 PIWA2_1AL_CONDO_UNIT_ID_NUM        CHAR(7),                    00005826
2 PIWA2_1AL_CONDO_BILL_BBL           CHAR(10),                   00005926
2 PIWA2_1AL_CONDO_BILL_BBL_VER       CHAR(1),                    00006026
2 PIWA2_1AL_CONDO_BILL_BBL_SCC       CHAR(1),                    00006126
2 PIWA2_1AL_CONDO_LOW_BBL            CHAR(10),                   00006226
2 PIWA2_1AL_CONDO_LOW_BBL_VER        CHAR(1),                    00006326
2 PIWA2_1AL_CONDO_HIGH_BBL           CHAR(10),                   00006426
2 PIWA2_1AL_CONDO_HIGH_BBL_VER       CHAR(1),                    00006526
2 FILLER_500                         CHAR(15),                   00006626
2 PIWA2_1AL_COOP_NUM                 CHAR(4),                    00006726
2 PIWA2_1AL_SANBORN,                                             00006826
  3 PIWA2_1AL_SANBORN_BORO           CHAR(1),                    00006926
  3 PIWA2_1AL_SANBORN_VOL            CHAR(3),                    00007026
  3 PIWA2_1AL_SANBORN_PAGE           CHAR(4),                    00007126
2 PIWA2_1AL_COMMERC_DIST             CHAR(5),                    00007226
2 PIWA2_1AL_DOF_MAP_BORO             CHAR(1),                    00007326
2 PIWA2_1AL_DOF_MAP_SECVOL           CHAR(4),                    00007426
2 PIWA2_1AL_DOF_MAP_PAGE             CHAR(4),                    00007526
2 FILLER_600                         CHAR(3),                    00007665
2 PIWA2_1AL_LATITUDE                 CHAR(9),                    00007765
2 PIWA2_1AL_LONGITUDE                CHAR(11),                   00007865
2 PIWA2_1AL_X_COORD                  CHAR(07),                   00007965
2 PIWA2_1AL_Y_COORD                  CHAR(07),                   00008065
2 PIWA2_1AL_BID                      CHAR(06),                   00008165
2 PIWA2_1AL_TPAD_BIN_ST              CHAR(01), /*CURRENT STATUS*/ 00008265
2 PIWA2_1AL_TPAD_NEW_BIN             CHAR(07), /*NEW BIN       */ 00008365
2 PIWA2_1AL_TPAD_NEW_BIN_ST          CHAR(01), /*NEW BIN STATUS*/ 00008465
2 PIWA2_1AL_TPAD_CONFLICT            CHAR(01), /*CONFLICT FLAG */ 00008565
2 PIWA2_1AL_DCP_ZONE_MAP             CHAR(03), /*DCP ZONING MAP*/ 00008683
2 FILLER_650                         CHAR(06),                   00008783
2 FILLER_700                         CHAR(8),  /*LGC -GSS USE*/  00008883
2 PIWA2_1AL_NUM_OF_BINS              CHAR(4),                    00008983
2 PIWA2_1AL_BINS(2500)               CHAR(7);                    00009083
                                                                 00009183
```

```
DCL 1 PIWA2_1AL_TPAD_BINLIST BASED(ADDR(PIWA2_1AL_BINS)),              00009283
      2 PIWA2_1AL_TPAD_BINS(2187),                                     00009383
        3 PIWA2_1AL_TPAD_BINS_BIN   CHAR (7),                          00009483
        3 PIWA2_1AL_TPAD_BINS_STAT  CHAR (1),                          00009583
      2 PIWA2_1AL_TPAD_FILL         CHAR (4);                          00009683
                                                                       00009783
DCL  PIWA2_1AL_SANBORN_BVOLPAGE         CHAR(8)                        00009883
        BASED(ADDR(PIWA2_1AL_SANBORN));                                00009983
DCL  PIWA2_1AL_STROLLKEY                CHAR(19)                       00010083
        BASED(ADDR(PIWA2_1AL_STROLL_KEY));                             00010183
                                                                       00010283
                                                                       00010383
DCL 1 PIWA2_1EX BASED(ADDR(P2PL11AL)),                                 00010483
                                                                       00010583
 /*******************************************************************/ 00010683
 /***              WORK AREA 2 FOR FUNCTION 1/1E EXTENDED         ***/ 00010783
 /***                                                             ***/ 00010883
 /*******************************************************************/ 00010983
 /*******************************************************************/ 00011083
                                                                       00011183
 /*******************************************************************/ 00011283
 /***                                                             ***/ 00011383
 /*** THE FOLLOWING FIELDS ARE FROM FUNCTION 1/1E                  ***/ 00011483
 /*******************************************************************/ 00011583
    2 PIWA2_1EX_ACCESS_KEY            CHAR(21),                        00011683
    2 PIWA2_1EX_CONT_PARITY           CHAR(1),/*(OR DUP ADDR IND)*/    00011783
    2 PIWA2_1EX_LOW_HOUSENUM          CHAR(11),/* SORT FORMAT */       00011883
    2 PIWA2_1EX_HI_HOUSENUM           CHAR(11),/* SORT FORMAT */       00011983
    2 PIWA2_1EX_DCP_PREF_LGC          CHAR(2),                         00012083
    2 PIWA2_1EX_NUM_X_ST_LOW_END      CHAR(1),                         00012183
    2 PIWA2_1EX_LOW_B5SC(5)           CHAR(6),                         00012283
    2 PIWA2_1EX_NUM_X_ST_HI_END       CHAR(1),                         00012383
    2 PIWA2_1EX_HI_B5SC(5)            CHAR(6),                         00012483
    2 PIWA2_1EX_LIONKEY,                                               00012583
      3 PIWA2_1EX_LION_BORO           CHAR(1),                         00012683
      3 PIWA2_1EX_LION_FACECODE       CHAR(4),                         00012783
      3 PIWA2_1EX_LION_SEQ            CHAR(5),                         00012883
    2 PIWA2_1EX_SPECIAL_ADDR_FLAG     CHAR(1),                         00012983
    2 PIWA2_1EX_SIDE_OF_STR           CHAR(1),                         00013083
    2 PIWA2_1EX_SEG_LEN               CHAR(5),                         00013183
    2 PIWA2_1EX_XCOORD                CHAR(7),                         00013283
    2 PIWA2_1EX_YCOORD                CHAR(7),                         00013383
    2 FILLER_1EX_100                  CHAR(7), /* FOR ZCOORD */        00013483
    2 FILLER_1EX_200                  CHAR(1), /* FOR GSS USE*/        00013583
    2 PIWA2_1EX_MARBLE_RIKERS_FLAG    CHAR(1),                         00013683
```

```
2 PIWA2_1EX_DOT_SLA              CHAR(1),                        00013783
2 PIWA2_1EX_COM_DIST,                                            00013883
  3 PIWA2_1EX_COM_DIST_BORO      CHAR(1),                        00013983
  3 PIWA2_1EX_COM_DIST_NUM       CHAR(2),                        00014083
2 PIWA2_1EX_ZIP                  CHAR(5),                        00014183
                                                                 00014283
2 PIWA2_1EX_ELECT_DIST           CHAR(3), /*****************/    00014383
2 PIWA2_1EX_ASSEM_DIST           CHAR(2), /* FUNCTION 1E   */    00014483
2 PIWA2_1EX_SPLIT_ED_FLAG        CHAR(1), /* FIELDS        */    00014583
2 PIWA2_1EX_CONG_DIST            CHAR(2), /*               */    00014683
2 PIWA2_1EX_SENATE_DIST          CHAR(2), /*               */    00014783
2 PIWA2_1EX_COURT_DIST           CHAR(2), /*               */    00014883
2 PIWA2_1EX_COUNCIL_DIST         CHAR(2), /*****************/    00014983
                                                                 00015083
2 PIWA2_1EX_HEALTH_CENTER_DIST   CHAR(2), /*HEALTH CENTER*/      00015183
2 PIWA2_1EX_HEALTH_AREA          CHAR(4), /*HEALTH AREA*/        00015283
2 PIWA2_1EX_SANI_DIST,                                           00015383
  3 PIWA2_1EX_SANI_DIST_BORO     CHAR(1),                        00015483
  3 PIWA2_1EX_SANI_DIST_NUM      CHAR(2),                        00015583
2 PIWA2_1EX_SANI_SUBSEC          CHAR(2),                        00015683
2 PIWA2_1EX_SANI_REG             CHAR(5),                        00015783
2 PIWA2_1EX_SANI_REC             CHAR(3),                        00015883
2 PIWA2_1EX_POLICE_DIST,                                         00015983
  3  PIWA2_1EX_POL_PAT_BORO_CMD  CHAR(1),                        00016083
  3  PIWA2_1EX_POL_PRECINCT      CHAR(3),                        00016183
2 PIWA2_1EX_FIRE_DIV             CHAR(2),                        00016283
2 PIWA2_1EX_FIRE_BAT             CHAR(2),                        00016383
2 PIWA2_1EX_FIRE_CO,                                             00016483
  3 PIWA2_1EX_FIRE_CO_TYPE       CHAR(1),                        00016583
  3 PIWA2_1EX_FIRE_CO_NUM        CHAR(3),                        00016683
2 PIWA2_1EX_FILL_DIST_SPLT_FLAG  CHAR(1),                        00016783
2 PIWA2_1EX_SCHL_DIST            CHAR(2),                        00016883
2 PIWA2_1EX_DYN_BLK              CHAR(3), /*ATOMIC POLYGON*/     00016983
2 PIWA2_1EX_POLICE_PAT_BORO      CHAR(2),                        00017083
2 PIWA2_1EX_FEATURE_TYPE         CHAR(1),                        00017183
2 PIWA2_1EX_SEGMENT_TYPE         CHAR(1),                        00017283
2 PIWA2_1EX_ALX                  CHAR(1),                        00017383
2 PIWA2_1EX_COINCIDENT_SEG_CTR   CHAR(1),                        00017483
2 FILLER_1EX_290                 CHAR(2),                        00017583
2 PIWA2_1EX_CENS_TRCT_BORO       CHAR(1),  /*USED FOR GRIDGEN*/  00017683
2 PIWA2_1EX_1990_CENS_TRCT       CHAR(6),                        00017783
2 PIWA2_1EX_2010_CENSUS_TRACT    CHAR(6),                        00017883
2 PIWA2_1EX_2010_CENSUS_BLOCK    CHAR(4),                        00017983
2 PIWA2_1EX_2010_CENSUS_BLK_SF   CHAR(1), /*NOT IMPLEMENTED*/    00018083
2 PIWA2_1EX_2000_CENS_TRACT      CHAR(6),                        00018183
```

```
   2 PIWA2_1EX_2000_CENS_BLOCK       CHAR(4),                        00018283
   2 PIWA2_1EX_2000_CENS_BLK_S       CHAR(1),                        00018383
   2 PIWA2_1EX_NTA                   CHAR(4), /*NEIGHBORHOOD     */  00018483
                                              /*TABULATION AREA  */  00018583
   2 PIWA2_1EX_SANIT_SNOW_PRIORITY   CHAR(1), /*SANITATION STRT  */  00018683
                                              /*SNOW PRIORITY    */  00018783
   2 PIWA2_1EX_SANIT_ORGANICS        CHAR(5), /*SANITATION       */  00018883
                                              /*ORGANIC PICK UP  */  00018983
   2 PIWA2_1EX_SANIT_BULK_PICK_UP    CHAR(5), /*SANITATION BULK  */  00019083
/* 2 PIWA2_1EX_SANIT_RESERVED *V16.4*CHAR(5),  *SANITATION RESERVE*/  00019183
   2 PIWA2_1EX_HURRICANE_ZONE        CHAR(2), /*OEM HURRICANE     */  00019283
                                              /*EVACUATION ZONE   */  00019383
   2 FILLER_1EX_400                  CHAR(11),                       00019483
   2 PIWA2_1EX_UHNS                  CHAR(11),                       00019583
   2 PIWA2_1EX_REAL_B7SC             CHAR(8),                        00019683
   2 PIWA2_1EX_SEGMENT_ID            CHAR(7),                        00019783
   2 PIWA2_1EX_CURVE_FLAG            CHAR(1),                        00019883
   2 PIWA2_1EX_LGCS                  CHAR(8),                        00019983
   2 PIWA2_1EX_BOE_PTR               CHAR(1),                        00020083
   2 PIWA2_1EX_AZIMUTH               CHAR(3),                        00020183
   2 PIWA2_1EX_ORIENT                CHAR(1),                        00020283
   2 PIWA2_1EX_X_LOW                 CHAR(7),                        00020383
   2 PIWA2_1EX_Y_LOW                 CHAR(7),                        00020483
   2 PIWA2_1EX_Z_LOW                 CHAR(7), /*NOT IMPLEMENTED*/    00020583
   2 PIWA2_1EX_X_HI                  CHAR(7),                        00020683
   2 PIWA2_1EX_Y_HI                  CHAR(7),                        00020783
   2 PIWA2_1EX_Z_HI                  CHAR(7), /*NOT IMPLEMENTED*/    00020883
   /* SPATIAL COORDINATES OF CENTER OF CURVATURE                 */  00020983
   2 PIWA2_1EX_X_CC                  CHAR(7),                        00021083
   2 PIWA2_1EX_Y_CC                  CHAR(7),                        00021183
   2 PIWA2_1EX_Z_CC                  CHAR(7), /*NOT IMPLEMENTED*/    00021283
   2 PIWA2_1EX_RADIUS                CHAR(7),                        00021383
   2 PIWA2_1EX_SECANT                CHAR(1),                        00021483
   2 PIWA2_1EX_ANGLE_FROM            CHAR(5),                        00021583
   2 PIWA2_1EX_ANGLE_TO              CHAR(5),                        00021683
   2 PIWA2_1EX_NODE_FROM             CHAR(7),                        00021783
   2 PIWA2_1EX_NODE_TO               CHAR(7),                        00021883
   2 PIWA2_1EX_VANITY_LION           CHAR(10),                       00021983
   2 PIWA2_1EX_SOS                   CHAR(1),                        00022083
   2 PIWA2_1EX_SPLIT_LOHSN           CHAR(11),                       00022183
   2 PIWA2_1EX_TD                    CHAR(1),                        00022283
   2 PIWA2_1EX_TR                    CHAR(10),                       00022383
   2 PIWA2_1EX_CURVE_FRACTION        CHAR(3),                        00022483
   2 PIWA2_1EX_ROADWAY_TYPE          CHAR(2),                        00022583
   2 PIWA2_1EX_PHYSICAL_ID           CHAR(7),                        00022683
```

```
   2 PIWA2_1EX_GENERIC_ID           CHAR(7),                        00022783
   2 PIWA2_1EX_INTP_ID              CHAR(7),  /*INTERNAL USE*/      00022883
   2 PIWA2_1EX_INTF_ID              CHAR(7),  /*INTERNAL USE*/      00022983
   2 PIWA2_1EX_BIKE_LANE_2          CHAR(2),                        00023083
   2 PIWA2_1EX_BIKE_TRAFFIC_DIR     CHAR(2),                        00023183
   2 PIWA2_1EX_FILL450              CHAR(3),                        00023283
/* 2 PIWA2_1EX_FILL450  * V17.1 *   CHAR(5),  **/                   00023383
/* 2 PIWA2_1EX_FILL450  * V16.4 *   CHAR(7),  **/                   00023483
/* 2 PIWA2_1EX_BLOCKFACE_ID * V16.1* CHAR(7),  **/                  00023583
   2 PIWA2_1EX_STREET_STATUS        CHAR(1),                        00023683
   2 PIWA2_1EX_STREET_WIDTH         CHAR(3),                        00023783
   2 PIWA2_1EX_STREET_WIDTH_IRR     CHAR(1),                        00023883
   2 PIWA2_1EX_BIKE_LANE            CHAR(1),                        00023983
   2 PIWA2_1EX_FED_CLASS_CODE       CHAR(2),                        00024083
   2 PIWA2_1EX_ROW_TYPE             CHAR(1),                        00024183
   2 PIWA2_1EX_LGC_LIST_2           CHAR(10),                       00024283
   2 PIWA2_1EX_LEGACY_SEG_ID        CHAR(7),                        00024383
   2 PIWA2_1EX_LGC_LIST_FROM_1      CHAR(10),                       00024483
   2 PIWA2_1EX_LGC_LIST_TO_1        CHAR(10),                       00024583
   2 PIWA2_1EX_LGC_LIST_FROM_2      CHAR(10),                       00024683
   2 PIWA2_1EX_LGC_LIST_TO_2        CHAR(10),                       00024783
   2 PIWA2_1EX_NOCROSS_FLG          CHAR(1),                        00024883
   2 PIWA2_1EX_IND_SEG_LEN          CHAR(5),                        00024983
   2 PIWA2_1EX_NTA_NAME             CHAR(75),                       00025083
   2 PIWA2_1EX_USPS_CITY_NAME       CHAR(25),                       00025183
   2 PIWA2_1EX_LATITUDE             CHAR(9),                        00025283
   2 PIWA2_1EX_LONGITUDE            CHAR(11),                       00025383
   2 PIWA2_1EX_SEG_FROM_NODE        CHAR(7),                        00025483
   2 PIWA2_1EX_SEG_TO_NODE          CHAR(7),                        00025583
   2 PIWA2_1EX_SEG_FROM_XYZ         CHAR(21),                       00025683
   2 PIWA2_1EX_SEG_TO_XYZ           CHAR(21),                       00025783
   2 PIWA2_1EX_BLOCKFACE_ID         CHAR(10),                       00025883
   2 PIWA2_1EX_NBR_TRAVEL_LANES     CHAR(2),                        00025983
   2 PIWA2_1EX_NBR_PARK_LANES       CHAR(2),                        00026083
   2 PIWA2_1EX_NBR_TOTAL_LANES      CHAR(2),                        00026183
   2 PIWA2_1EX_STR_WIDTH_MAX        CHAR(3),                        00026283
   2 PIWA2_1EX_SPEED_LIMIT          CHAR(2),                        00026383
   2 PIWA2_1EX_PUMA_CODE            CHAR(5),                        00026485
   2 PIWA2_1EX_FILL500              CHAR(245),                      00026584
/* 2 PIWA2_1EX_FILL500 ** V18.1 **  CHAR(250),**/                   00026684
/* 2 PIWA2_1EX_FILL500 ** V17.4 **  CHAR(252),**/                   00026784
/* 2 PIWA2_1EX_FILL500 ** V16.4 **  CHAR(255) **/                   00026884
/* 2 PIWA2_1EX_FILL500 ** V16.1 **  CHAR(271) **/                   00026984
/* 2 PIWA2_1EX_FILL500 ** V15.3 **  CHAR(327) **/                   00027084
/*******************************************************************/ 00027184
```

```
 /***                                                          ***/ 00027284
 /*** THE FOLLOWING FIELDS ARE AN ADDITION TO 1E                ***/ 00027384
 /*******************************************************************/ 00027484
    2 PIWA2_1EX_REASON_CODE           CHAR(1),                        00027584
    2 PIWA2_1EX_REASON_CODE_QUAL      CHAR(1),                        00027684
    2 PIWA2_1EX_WARN_CODE             CHAR(2),                        00027784
    2 PIWA2_1EX_RETURN_CODE           CHAR(2),                        00027884
    2 PIWA2_1EX_NUM_X_STS_LO_END      CHAR(1),                        00027984
    2 PIWA2_1EX_LO_B7SC(5)            CHAR(8),                        00028084
    2 PIWA2_1EX_NUM_X_STS_HI_END      CHAR(1),                        00028184
    2 PIWA2_1EX_HI_B7SC(5)            CHAR(8),                        00028284
    2 PIWA2_1EX_LO_ST_NAME(5)         CHAR(32),                       00028384
    2 PIWA2_1EX_HI_ST_NAME(5)         CHAR(32),                       00028484
    2 PIWA2_1EX_BOE_B7SC              CHAR(8),                        00028584
    2 PIWA2_1EX_BOE_ST_NAME           CHAR(32),                       00028684
    2 PIWA2_1EX_FILL600               CHAR(52);                       00028784
                                                                      00028884
                                                                      00028984
                                                                      00029084
DCL 1 PIWA2_FN1AX BASED(ADDR(P2PL11AL)),                              00029184
 /*******************************************************************/ 00029284
 /***              WORK AREA 2 FOR FUNCTION 1A EXTENDED          ***/ 00029384
 /***                                                          ***/ 00029484
 /*******************************************************************/ 00029584
                                                                      00029684
                                                                      00029784
   2 PIWA2_1AX_ACCESS_KEY              CHAR(21),                      00029884
   2 PIWA2_1AX_CONT_PARITY             CHAR(1), /*(OR DUP ADDR IND)*/ 00029984
   2 PIWA2_1AX_LOW_HOUSENUM            CHAR(11), /* SORT FORMAT */    00030084
   2 PIWA2_1AX_BBL,                                                   00030184
     3 PIWA2_1AX_BBL_BORO              CHAR(1),                       00030284
     3 PIWA2_1AX_BLOCK                 CHAR(5),                       00030384
     3 PIWA2_1AX_LOT                   CHAR(4),                       00030484
   2 PIWA2_1AX_LOT_VER                 CHAR(1),                       00030584
   2 PIWA2_1AX_SCC                     CHAR(1),                       00030684
   2 FILLER_1AX1                       CHAR(1),                       00030784
   2 PIWA2_1AX_GENERAL_LOT_INFO,                                      00030884
     3 PIWA2_1AX_RPAD_BLDG_CLASS       CHAR(2),                       00030984
     3 PIWA2_1AX_CORNER_CODE           CHAR(2),                       00031084
     3 PIWA2_1AX_NUM_OF_STRUCTURES     CHAR(4),                       00031184
     3 PIWA2_1AX_NUM_OF_BLOCKFACES     CHAR(2),                       00031284
     3 PIWA2_1AX_INTERIOR_FLAG         CHAR(1),                       00031384
     3 PIWA2_1AX_VACANT_FLAG           CHAR(1),                       00031484
     3 PIWA2_1AX_IRREG_LOT_FLAG        CHAR(1),                       00031584
   2 PIWA2_1AX_MARBLE_RIKERS_FLAG      CHAR(1),                       00031684
```

```
2 PIWA2_1AX_ADDR_LIST_OVFLOW_FLAG    CHAR(1),                        00031784
2 PIWA2_1AX_STROLL_KEY,                                              00031884
  3 PIWA2_1AX_STROLL_BORO            CHAR(1),                        00031984
  3 PIWA2_1AX_STROLL_5SC             CHAR(5),                        00032084
  3 PIWA2_1AX_STROLL_SIDE_OF_STR     CHAR(1),    /* L, R */          00032184
  3 PIWA2_1AX_STROLL_HI_HOUSENUM     CHAR(11), /* SORT FORMAT */     00032284
  3 FILLER_1AX2                      CHAR(1),                        00032384
2 FILLER_1AX3                        CHAR(1),  /* FOR GSS USE*/      00032484
2 PIWA2_1AX_BIN                      CHAR(7),                        00032584
2 PIWA2_1AX_CONDO_FLAG               CHAR(1),                        00032684
2 FILLER_1AX4                        CHAR(1),                        00032784
2 PIWA2_1AX_RPAD_CONDO_ID_NUM        CHAR(4),                        00032884
2 PIWA2_1AX_CONDO_UNIT_ID_NUM        CHAR(7),                        00032984
2 PIWA2_1AX_CONDO_BILL_BBL           CHAR(10),                       00033084
2 PIWA2_1AX_CONDO_BILL_BBL_VER       CHAR(1),                        00033184
2 PIWA2_1AX_CONDO_BILL_BBL_SCC       CHAR(1),                        00033284
2 PIWA2_1AX_CONDO_LOW_BBL            CHAR(10),                       00033384
2 PIWA2_1AX_CONDO_LOW_BBL_VER        CHAR(1),                        00033484
2 PIWA2_1AX_CONDO_HIGH_BBL           CHAR(10),                       00033584
2 PIWA2_1AX_CONDO_HIGH_BBL_VER       CHAR(1),                        00033684
2 FILLER_1AX5                        CHAR(15),                       00033784
2 PIWA2_1AX_COOP_NUM                 CHAR(4),                        00033884
2 PIWA2_1AX_SANBORN,                                                 00033984
  3 PIWA2_1AX_SANBORN_BORO           CHAR(1),                        00034084
  3 PIWA2_1AX_SANBORN_VOL            CHAR(3),                        00034184
  3 PIWA2_1AX_SANBORN_PAGE           CHAR(4),                        00034284
2 PIWA2_1AX_COMMERC_DIST             CHAR(5),                        00034384
2 PIWA2_1AX_DOF_MAP_BORO             CHAR(1),                        00034484
2 PIWA2_1AX_DOF_MAP_SECVOL           CHAR(4),                        00034584
2 PIWA2_1AX_DOF_MAP_PAGE             CHAR(4),                        00034684
2 PIWA2_1AX_RESERVED                 CHAR(03),                       00034784
2 PIWA2_1AX_LATITUDE                 CHAR(09),                       00034884
2 PIWA2_1AX_LONGITUDE                CHAR(11),                       00034984
2 PIWA2_1AX_X_COORD                  CHAR(07),                       00035084
2 PIWA2_1AX_Y_COORD                  CHAR(07),                       00035184
2 PIWA2_1AX_BID                      CHAR(06),                       00035284
2 PIWA2_1AX_TPAD_BIN_ST              CHAR(01),  /*CURRENT STATUS*/  00035384
2 PIWA2_1AX_TPAD_NEW_BIN             CHAR(07),  /*NEW BIN       */  00035484
2 PIWA2_1AX_TPAD_NEW_BIN_ST          CHAR(01),  /*NEW BIN STATUS*/  00035584
2 PIWA2_1AX_TPAD_CONFLICT            CHAR(01),  /*CONFLICT FLAG */  00035684
2 PIWA2_1AX_DCP_ZONE_MAP             CHAR(03),  /*DCP ZONING MAP*/  00035784
2 FILLER_1AX7                        CHAR(06),                       00035884
2 FILLER_1AX8                        CHAR(8),  /* LGC - GSS USE*/    00035984
2 PIWA2_1AX_REASON_CODE              CHAR(01),                       00036084
2 PIWA2_1AX_REASON_CODE_QUAL         CHAR(01),                       00036184
```

```
  2 PIWA2_1AX_WARN_CODE                CHAR(02),                      00036284
  2 PIWA2_1AX_RETURN_CODE              CHAR(02),                      00036384
  2 FILLER_1AX9                        CHAR(108),                     00036484
  2 PIWA2_1AX_NUM_OF_ADDR              CHAR(4),                       00036584
  2 PIWA2_1AX_ADDR_LIST(21),                                          00036684
    3 PIWA2_1AX_LIST_LOW_HOUSENUM      CHAR(16), /*DISPLAY FORMAT*/   00036784
    3 PIWA2_1AX_LIST_HI_HOUSENUM       CHAR(16), /*DISPLAY FORMAT*/   00036884
    3 PIWA2_1AX_LIST_BORO              CHAR(1),                       00036984
    3 PIWA2_1AX_LIST_5SC               CHAR(5),                       00037084
    3 PIWA2_1AX_LIST_LGC               CHAR(2),                       00037184
    3 PIWA2_1AX_LIST_BIN               CHAR(7),                       00037284
    3 PIWA2_1AX_LIST_SIDE_OF_STR       CHAR(1),  /* L, R */           00037384
    3 PIWA2_1AX_ADDR_TYPE              CHAR(1),  /*               */  00037484
                                                 /* BLANK = NORMAL*/  00037584
    3 PIWA2_1AX_TPAD_STATUS            CHAR(1),                       00037684
    3 PIWA2_1AX_ST_NAME                CHAR(32),                      00037784
    3 FILLER_1AX10                     CHAR(34);                      00037884
                                                                      00037984
                                                                      00038084
DCL 1 PIWA2_FN1B BASED(ADDR(P2PL11AL)),                               00038184
                                                                      00038284
 /*******************************************************************/ 00038384
 /***              WORK AREA 2 FOR FUNCTION 1B                   ***/ 00038484
 /***                                                            ***/ 00038584
 /*******************************************************************/ 00038684
    2 PIWA2_1B_1_ACCESS_KEY              CHAR(21),                    00038784
    2 PIWA2_1B_1_CONT_PARITY             CHAR(1),  /*(DUP ADDR IND)*/ 00038884
    2 PIWA2_1B_1_LOW_HOUSENUM            CHAR(11), /* SORT FORMAT */  00038984
    2 PIWA2_1B_1_HI_HOUSENUM             CHAR(11), /* SORT FORMAT */  00039084
    2 PIWA2_1B_1_PREF_LGC                CHAR(2),                     00039184
    2 PIWA2_1B_1_NUM_X_ST_LOW_END        CHAR(1),                     00039284
    2 PIWA2_1B_1_LOW_B5SC(5)             CHAR(6),                     00039384
    2 PIWA2_1B_1_NUM_X_ST_HI_END         CHAR(1),                     00039484
    2 PIWA2_1B_1_HI_B5SC(5)              CHAR(6),                     00039584
    2 PIWA2_1B_1_LIONKEY,                                             00039684
      3 PIWA2_1B_1_LION_BORO             CHAR(1),                     00039784
      3 PIWA2_1B_1_LION_FACECODE         CHAR(4),                     00039884
      3 PIWA2_1B_1_LION_SEQ              CHAR(5),                     00039984
    2 PIWA2_1B_1_SPECIAL_ADDR_FLAG       CHAR(1),                     00040084
    2 PIWA2_1B_1_SIDE_OF_STR             CHAR(1),                     00040184
    2 PIWA2_1B_1_SEG_LEN                 CHAR(5),                     00040284
    2 PIWA2_1B_1_XCOORD                  CHAR(7),                     00040384
    2 PIWA2_1B_1_YCOORD                  CHAR(7),                     00040484
    2 FILLER_1B_1_100                    CHAR(7), /* FOR ZCOORD */    00040584
    2 FILLER_1B_1_200                    CHAR(1), /* FOR GSS USE*/    00040684
```

```
2 PIWA2_1B_1_MARBLE_RIKERS_FLAG       CHAR(1),                    00040784
2 PIWA2_1B_1_DOT_SLA                  CHAR(1),                    00040884
2 PIWA2_1B_1_COM_DIST,                                            00040984
  3 PIWA2_1B_1_COM_DIST_BORO          CHAR(1),                    00041084
  3 PIWA2_1B_1_COM_DIST_NUM           CHAR(2),                    00041184
2 PIWA2_1B_1_ZIP                      CHAR(5),                    00041284
                                                                  00041384
2 PIWA2_1B_1_ELECT_DIST               CHAR(3), /****************/ 00041484
2 PIWA2_1B_1_ASSEM_DIST               CHAR(2), /* FUNCTION 1E   */ 00041584
2 PIWA2_1B_1_SPLIT_ED_FLAG            CHAR(1), /* FIELDS        */ 00041684
2 PIWA2_1B_1_CONG_DIST                CHAR(2), /*               */ 00041784
2 PIWA2_1B_1_SENATE_DIST              CHAR(2), /*               */ 00041884
2 PIWA2_1B_1_COURT_DIST               CHAR(2), /*               */ 00041984
2 PIWA2_1B_1_COUNCIL_DIST             CHAR(2), /****************/ 00042084
                                                                  00042184
2 PIWA2_1B_1_HEALTH_CENTER_DIST       CHAR(2),                    00042284
2 PIWA2_1B_1_HEALTH_AREA              CHAR(4),                    00042384
2 PIWA2_1B_1_SANI_DIST,                                           00042484
  3 PIWA2_1B_1_SANI_DIST_BORO         CHAR(1),                    00042584
  3 PIWA2_1B_1_SANI_DIST_NUM          CHAR(2),                    00042684
2 PIWA2_1B_1_SANI_SUBSEC              CHAR(2),                    00042784
2 PIWA2_1B_1_SANI_REG                 CHAR(5),                    00042884
2 PIWA2_1B_1_SANI_REC                 CHAR(3),                    00042984
2 PIWA2_1B_1_POLICE_DIST,                                         00043084
  3  PIWA2_1B_1_POL_PAT_BORO_CMD      CHAR(1),                    00043184
  3  PIWA2_1B_1_POL_PRECINCT          CHAR(3),                    00043284
2 PIWA2_1B_1_FIRE_DIV                 CHAR(2),                    00043384
2 PIWA2_1B_1_FIRE_BAT                 CHAR(2),                    00043484
2 PIWA2_1B_1_FIRE_CO,                                             00043584
  3 PIWA2_1B_1_FIRE_CO_TYPE           CHAR(1),                    00043684
  3 PIWA2_1B_1_FIRE_CO_NUM            CHAR(3),                    00043784
2 PIWA2_1B_1_FILL_DIST_SPLIT_FLAG     CHAR(1),                    00043884
2 PIWA2_1B_1_SCHL_DIST                CHAR(2),                    00043984
2 PIWA2_1B_1_DYN_BLK                  CHAR(3), /*ATOMIC POLYGON*/  00044084
2 PIWA2_1B_1_POLICE_PAT_BORO          CHAR(2),                    00044184
2 PIWA2_1B_1_FEATURE_TYPE             CHAR(1),                    00044284
2 PIWA2_1B_1_SEGMENT_TYPE             CHAR(1),                    00044384
2 PIWA2_1B_1_ALX                      CHAR(1),                    00044484
2 PIWA2_1B_1_COINCIDENT_SEG_CTR       CHAR(1),                    00044584
2 FILLER_1B_1_290                     CHAR(2),                    00044684
2 PIWA2_1B_1_CENS_TRCT_BORO           CHAR(1),                    00044784
2 PIWA2_1B_1_1990_CENS_TRCT           CHAR(6),                    00044884
2 PIWA2_1B_1_2010_CENSUS_TRACT        CHAR(6),                    00044984
2 PIWA2_1B_1_2010_CENSUS_BLOCK        CHAR(4),                    00045084
2 PIWA2_1B_1_2010_CENSUS_BLK_SF       CHAR(1), /*NOT IMPLELMENTED*/00045184
```

```
   2 PIWA2_1B_1_2000_CENS_TRACT          CHAR(6),                    00045284
   2 PIWA2_1B_1_2000_CENS_BLOCK          CHAR(4),                    00045384
   2 PIWA2_1B_1_2000_CENS_BLK_S          CHAR(1),                    00045484
   2 PIWA2_1B_1_NTA                      CHAR(4), /*NEIGHBORHOOD    */00045584
                                                  /*TABULATION AREA */00045684
   2 PIWA2_1B_1_SANIT_SNOW_PRIORITY      CHAR(1), /*SANITATION STRT*/ 00045784
                                                  /*SNOW PRIORITY */  00045884
   2 PIWA2_1B_1_SANIT_ORGANICS           CHAR(5), /*SANITATION */     00045984
                                                  /*ORGANIC PICK UP*/ 00046084
   2 PIWA2_1B_1_SANIT_BULK_PICK_UP       CHAR(5), /*SANIT BULK   */   00046184
/* 2 PIWA2_1B_1_SANIT_RESERVE *V16.4 **  CHAR(5),  *SANIT RESERVE*/   00046284
   2 PIWA2_1B_1_HURRICANE_ZONE           CHAR(2), /*OEM HURRICANE */  00046384
                                                  /*EVACUATION ZONE*/ 00046484
   2 FILLER_1B_1_400                     CHAR(11),                   00046584
   2 PIWA2_1B_1_UHNS                     CHAR(11),                   00046684
   2 PIWA2_1B_1_REAL_B7SC                CHAR(8),                    00046784
   2 PIWA2_1B_1_SEGMENT_ID               CHAR(7),                    00046884
   2 PIWA2_1B_1_CURVE_FLAG               CHAR(1),                    00046984
   2 PIWA2_1B_1_LGCS                     CHAR(8),                    00047084
   2 PIWA2_1B_1_BOE_PTR                  CHAR(1),                    00047184
   2 PIWA2_1B_1_AZIMUTH                  CHAR(3),                    00047284
   2 PIWA2_1B_1_ORIENT                   CHAR(1),                    00047384
   2 PIWA2_1B_1_X_LOW                    CHAR(7),                    00047484
   2 PIWA2_1B_1_Y_LOW                    CHAR(7),                    00047584
   2 PIWA2_1B_1_Z_LOW                    CHAR(7), /*NOT IMPLEMENTED*/ 00048027
   2 PIWA2_1B_1_X_HI                     CHAR(7),                    00049027
   2 PIWA2_1B_1_Y_HI                     CHAR(7),                    00049127
   2 PIWA2_1B_1_Z_HI                     CHAR(7), /*NOT IMPLEMENTED*/ 00049227
   /* SPATIAL COORDINATES OF CENTER OF CURVATURE                 */   00049327
   2 PIWA2_1B_1_X_CC                     CHAR(7),                    00049427
   2 PIWA2_1B_1_Y_CC                     CHAR(7),                    00049527
   2 PIWA2_1B_1_Z_CC                     CHAR(7), /*NOT IMPLEMENTED*/ 00049627
   2 PIWA2_1B_1_RADIUS                   CHAR(7),                    00049727
   2 PIWA2_1B_1_SECANT                   CHAR(1),                    00049827
   2 PIWA2_1B_1_ANGLE_FROM               CHAR(5),                    00049927
   2 PIWA2_1B_1_ANGLE_TO                 CHAR(5),                    00050027
   2 PIWA2_1B_1_NODE_FROM                CHAR(7),                    00051027
   2 PIWA2_1B_1_NODE_TO                  CHAR(7),                    00052027
   2 PIWA2_1B_1_VANITY_LION              CHAR(10),                   00053027
   2 PIWA2_1B_1_SOS                      CHAR(1),                    00054027
   2 PIWA2_1B_1_SPLIT_LOHSN              CHAR(11),                   00055027
   2 PIWA2_1B_1_TD                       CHAR(1),                    00056027
   2 PIWA2_1B_1_TR                       CHAR(10),                   00057027
   2 PIWA2_1B_1_CURVE_FRACTION           CHAR(3),                    00058027
   2 PIWA2_1B_1_ROADWAY_TYPE             CHAR(2),                    00058132
```

```
   2 PIWA2_1B_1_PHYSICAL_ID             CHAR(7),                    00058232
   2 PIWA2_1B_1_GENERIC_ID              CHAR(7),                    00058332
   2 PIWA2_1B_1_INTP_ID                 CHAR(7),  /*INTERNAL USE*/   00058436
   2 PIWA2_1B_1_INTF_ID                 CHAR(7),  /*INTERNAL USE*/   00058536
   2 PIWA2_1B_1_BIKE_LANE_2             CHAR(2),                    00058676
   2 PIWA2_1B_1_BIKE_TRAFFIC_DIR        CHAR(2),                    00058781
   2 PIWA2_1B_1_FILL450                 CHAR(3),                    00058879
/* 2 PIWA2_1B_1_FILL450      ** V17.1 ** CHAR(5),**/                00058979
/* 2 PIWA2_1B_1_FILL450      ** V16.4 ** CHAR(7),**/                00059079
/* 2 PIWA2_1B_1_BLOCKFACE_ID ** V16.1 ** CHAR(7) **/                00059179
   2 PIWA2_1B_1_STREET_STATUS           CHAR(1),                    00059279
   2 PIWA2_1B_1_STREET_WIDTH            CHAR(3),                    00059379
   2 PIWA2_1B_1_STREET_WIDTH_IRR        CHAR(1),                    00059479
   2 PIWA2_1B_1_BIKE_LANE               CHAR(1),                    00059579
   2 PIWA2_1B_1_FED_CLASS_CODE          CHAR(2),                    00059679
   2 PIWA2_1B_1_ROW_TYPE                CHAR(1),                    00059779
   2 PIWA2_1B_1_LGC_LIST_2              CHAR(10),                   00059879
   2 PIWA2_1B_1_LEGACY_SEG_ID           CHAR(7),                    00059979
   2 PIWA2_1B_1_LGC_LIST_FROM_1         CHAR(10),                   00060079
   2 PIWA2_1B_1_LGC_LIST_TO_1           CHAR(10),                   00060179
   2 PIWA2_1B_1_LGC_LIST_FROM_2         CHAR(10),                   00060279
   2 PIWA2_1B_1_LGC_LIST_TO_2           CHAR(10),                   00060379
   2 PIWA2_1B_1_NOCROSS_FLG             CHAR(1),                    00060479
   2 PIWA2_1B_1_IND_SEG_LEN             CHAR(5),                    00060579
   2 PIWA2_1B_1_NTA_NAME                CHAR(75),                   00060679
   2 PIWA2_1B_1_USPS_CITY_NAME          CHAR(25),                   00060779
   2 PIWA2_1B_1_LATITUDE                CHAR(9),                    00060879
   2 PIWA2_1B_1_LONGITUDE               CHAR(11),                   00060979
   2 PIWA2_1B_1_SEG_FROM_NODE           CHAR(7),                    00061079
   2 PIWA2_1B_1_SEG_TO_NODE             CHAR(7),                    00061179
   2 PIWA2_1B_1_SEG_FROM_XYZ            CHAR(21),                   00061279
   2 PIWA2_1B_1_SEG_TO_XYZ              CHAR(21),                   00061379
   2 PIWA2_1B_1_BLOCKFACE_ID            CHAR(10),                   00061479
   2 PIWA2_1B_1_NBR_TRAVEL_LANES        CHAR(2),                    00061579
   2 PIWA2_1B_1_NBR_PARK_LANES          CHAR(2),                    00061679
   2 PIWA2_1B_1_NBR_TOTAL_LANES         CHAR(2),                    00061779
   2 PIWA2_1B_1_STREET_WIDTH_MAX        CHAR(3),                    00061879
   2 PIWA2_1B_1_SPEED_LIMIT             CHAR(2),                    00061982
   2 PIWA2_1B_1_PUMA_CODE               CHAR(5),                    00062085
   2 PIWA2_1B_1_FILL500                 CHAR(245),                  00062284
/* 2 PIWA2_1B_1_FILL500 ** V18.1  **    CHAR(250),**/               00062384
/* 2 PIWA2_1B_1_FILL500 ** V17.4  **    CHAR(252),**/               00062484
/* 2 PIWA2_1B_1_FILL500 ** V16.4  **    CHAR(255) **/               00062584
/**2 PIWA2_1B_1_FILL500 ** V16.1  **    CHAR(271) **/               00062684
/**2 PIWA2_1B_1_FILL500 ** V15.3  **    CHAR(327) **/               00062784
```

```
/*****************************************************************/ 00062884
/***                                                           ***/ 00062984
/*** THE FOLLOWING FIELDS ARE AN ADDITION TO 1/1E                ***/ 00063084
/*****************************************************************/ 00063184
   2 PIWA2_1B_1_REASON_CODE              CHAR(1),                    00063284
   2 PIWA2_1B_1_REASON_CODE_QUAL         CHAR(1),                    00063384
   2 PIWA2_1B_1_WARN_CODE                CHAR(2),                    00063484
   2 PIWA2_1B_1_RETURN_CODE              CHAR(2),                    00063584
   2 PIWA2_1B_1_NUM_X_STS_LO_END         CHAR(1),                    00063684
   2 PIWA2_1B_1_LO_B7SC(5)               CHAR(8),                    00063784
   2 PIWA2_1B_1_NUM_X_STS_HI_END         CHAR(1),                    00064027
   2 PIWA2_1B_1_HI_B7SC(5)               CHAR(8),                    00065027
   2 PIWA2_1B_1_LO_ST_NAME(5)            CHAR(32),                   00066027
   2 PIWA2_1B_1_HI_ST_NAME(5)            CHAR(32),                   00067027
   2 PIWA2_1B_1_BOE_B7SC                 CHAR(8),                    00068027
   2 PIWA2_1B_1_BOE_ST_NAME              CHAR(32),                   00069027
   2 PIWA2_1B_1_FILL600                  CHAR(52),                   00069127
                                                                     00069227
/*****************************************************************/ 00069627
/***   THE FOLLOWING ARE FROM THE 1A WORK AREA 2                 ***/ 00069727
/***                                                           ***/ 00069827
/*****************************************************************/ 00069927
                                                                     00070027
  2 PIWA2_1B_1A_ACCESS_KEY               CHAR(21),                   00072027
  2 PIWA2_1B_1A_CONT_PARITY              CHAR(1), /*(DUP ADDR IND)*/ 00073027
  2 PIWA2_1B_1A_LOW_HOUSENUM             CHAR(11), /* SORT FORMAT */ 00074027
  2 PIWA2_1B_1A_BBL,                                                 00075027
    3 PIWA2_1B_1A_BBL_BORO               CHAR(1),                    00076027
    3 PIWA2_1B_1A_BLOCK                  CHAR(5),                    00077027
    3 PIWA2_1B_1A_LOT                    CHAR(4),                    00078027
  2 PIWA2_1B_1A_LOT_VER                  CHAR(1),                    00079027
  2 PIWA2_1B_1A_SCC                      CHAR(1),                    00079127
  2 FILLER_1B_1A_1                       CHAR(1),                    00079227
  2 PIWA2_1B_1A_GENERAL_LOT_INFO,                                    00079327
    3 PIWA2_1B_1A_RPAD_BLDG_CLASS        CHAR(2),                    00079427
    3 PIWA2_1B_1A_CORNER_CODE            CHAR(2),                    00079527
    3 PIWA2_1B_1A_NUM_OF_STRUCTURES      CHAR(4),                    00079627
    3 PIWA2_1B_1A_NUM_OF_BLOCKFACES      CHAR(2),                    00079727
    3 PIWA2_1B_1A_INTERIOR_FLAG          CHAR(1),                    00079827
    3 PIWA2_1B_1A_VACANT_FLAG            CHAR(1),                    00079927
    3 PIWA2_1B_1A_IRREG_LOT_FLAG         CHAR(1),                    00080027
  2 PIWA2_1B_1A_MARBLE_RIKERS_FLAG       CHAR(1),                    00081028
  2 PIWA2_1B_1A_OVERFLOW_FLAG            CHAR(1),                    00082072
  2 PIWA2_1B_1A_STROLL_KEY,                                          00083027
    3 PIWA2_1B_1A_STROLL_BORO            CHAR(1),                    00084027
```

```
  3 PIWA2_1B_1A_STROLL_5SC            CHAR(5),                    00085027
  3 PIWA2_1B_1A_STROLL_SIDE_OF_STR    CHAR(1),    /* L, R */      00086027
  3 PIWA2_1B_1A_STROLL_HI_HOUSENUM    CHAR(11), /* SORT FORMAT */ 00087027
  3 FILLER_1B_1A_2                    CHAR(1),                    00088027
2 FILLER_1B_1A_3                      CHAR(1),  /* FOR GSS USE*/  00089029
2 PIWA2_1B_1A_BIN                     CHAR(7),                    00089127
2 PIWA2_1B_1A_CONDO_FLAG              CHAR(1),                    00089227
2 FILLER_1B_1A_4                      CHAR(1),                    00089327
2 PIWA2_1B_1A_RPAD_CONDO_ID_NUM       CHAR(4),                    00089427
2 PIWA2_1B_1A_CONDO_UNIT_ID_NUM       CHAR(7),                    00089527
2 PIWA2_1B_1A_CONDO_BILL_BBL          CHAR(10),                   00089627
2 PIWA2_1B_1A_CONDO_BILL_BBL_VER      CHAR(1),                    00089727
2 PIWA2_1B_1A_CONDO_BILL_BBL_SCC      CHAR(1),                    00089827
2 PIWA2_1B_1A_CONDO_LOW_BBL           CHAR(10),                   00089927
2 PIWA2_1B_1A_CONDO_LOW_BBL_VER       CHAR(1),                    00090027
2 PIWA2_1B_1A_CONDO_HIGH_BBL          CHAR(10),                   00091027
2 PIWA2_1B_1A_CONDO_HIGH_BBL_VER      CHAR(1),                    00092027
2 FILLER_1B_1A_5                      CHAR(15),                   00093027
2 PIWA2_1B_1A_COOP_NUM                CHAR(4),                    00094027
2 PIWA2_1B_1A_SANBORN,                                            00095027
  3 PIWA2_1B_1A_SANBORN_BORO          CHAR(1),                    00096027
  3 PIWA2_1B_1A_SANBORN_VOL           CHAR(3),                    00097027
  3 PIWA2_1B_1A_SANBORN_PAGE          CHAR(4),                    00098027
2 PIWA2_1B_1A_COMMERC_DIST            CHAR(5),                    00099027
2 PIWA2_1B_1A_DOF_MAP_BORO            CHAR(1),                    00099127
2 PIWA2_1B_1A_DOF_MAP_SECVOL          CHAR(4),                    00099227
2 PIWA2_1B_1A_DOF_MAP_PAGE            CHAR(4),                    00099327
2 PIWA2_1B_1A_RESERVED                CHAR(3),                    00099464
2 PIWA2_1B_1A_LATITUDE                CHAR(9),                    00099564
2 PIWA2_1B_1A_LONGITUDE               CHAR(11),                   00099664
2 PIWA2_1B_1A_X_COORD                 CHAR(07),                   00099764
2 PIWA2_1B_1A_Y_COORD                 CHAR(07),                   00099864
2 PIWA2_1B_1A_BID                     CHAR(06),                   00099964
2 PIWA2_1B_1A_TPAD_BIN_ST             CHAR(01), /*CURRENT STATUS*/ 00100064
2 PIWA2_1B_1A_TPAD_NEW_BIN            CHAR(07), /*NEW BIN       */ 00100164
2 PIWA2_1B_1A_TPAD_NEW_BIN_ST         CHAR(01), /*NEW BIN STATUS*/ 00100264
2 PIWA2_1B_1A_TPAD_CONFLICT           CHAR(01), /*CONFLICT FLAG */ 00101027
2 PIWA2_1B_1A_DCP_ZONE_MAP            CHAR(03), /*DCP ZONING MAP*/ 00101183
2 FILLER_1B_1A_7                      CHAR(06),                   00102083
2 FILLER_1B_1A_8                      CHAR(8),  /*LGC M GSS USE*/ 00103070
2 PIWA2_1B_1A_REASON_CODE             CHAR(01),                   00104027
2 PIWA2_1B_1A_REASON_CODE_QUAL        CHAR(01),                   00105052
2 PIWA2_1B_1A_WARN_CODE               CHAR(02),                   00106027
2 PIWA2_1B_1A_RETURN_CODE             CHAR(02),                   00107027
2 FILLER_1B_1A_9                      CHAR(108),                  00108027
```

```
  2 PIWA2_1B_1A_NUM_OF_ADDR              CHAR(4),                    00109027
  2 PIWA2_1B_1A_ADDR_LIST(21),                                       00109127
    3 PIWA2_1B_1A_LIST_LOW_HOUSENUM      CHAR(16), /*DISPLAY FORMAT*/ 00109227
    3 PIWA2_1B_1A_LIST_HI_HOUSENUM       CHAR(16), /*DISPLAY FORMAT*/ 00109327
    3 PIWA2_1B_1A_LIST_BORO              CHAR(1),                    00109427
    3 PIWA2_1B_1A_LIST_5SC               CHAR(5),                    00109527
    3 PIWA2_1B_1A_LIST_LGC               CHAR(2),                    00109627
    3 PIWA2_1B_1A_LIST_BIN               CHAR(7),                    00109727
    3 PIWA2_1B_1A_LIST_SIDE_OF_STR       CHAR(1),  /* L, R */        00109827
    3 PIWA2_1B_1A_ADDR_TYPE              CHAR(1),  /*              */ 00109927
                                                   /*BLANK = NORMAL*/ 00110027
    3 PIWA2_1B_1A_TPAD_STATUS            CHAR(1),                    00111027
    3 PIWA2_1B_1A_ST_NAME                CHAR(32),                   00112027
    3 FILLER_1B_1A_10                    CHAR(34);                   00113027
                                                                     00120019
```

P2PL13S COPY FIle

```
/*****************************************************************/  00000100
/***  THIS IS THE PL/1 STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM  ***/  00000200
/***  INDEPENDENT WORK AREA 2 FOR FUNCTION: 3S.                  ***/  00000300
/***                                                             ***/  00000400
/**   COPY FILE - P2PL13S.                           09/17/97  ***/  00000500
/*****************************************************************/  00000600
DCL                                                                  00000700
 1 P2PL13S,                                                          00000800
   2 PIWA2_3S_ACCESS_KEY,                                            00000900
     3 FILLER_GSS                      CHAR(2),                     00001000
     3 PIWA2_3S_PORS_STNAME_IND        CHAR(1),/* P = PRIMARY */    00001100
                                               /* S = SECONDARY */  00001200
     3 PIWA2_3S_BORO                   CHAR(1),                     00001300
     3 PIWA2_3S_5SC                    CHAR(5),                     00001400
     3 PIWA2_3S_LGC                    CHAR(2),/* BLANK IF P IN */  00001500
     3 FILLER                          CHAR(10),/* POSITION 3 */   00001600
   2 PIWA2_3S_NUM_OF_INTERSECTS        CHAR(3),                     00001700
   2 PIWA2_3S_LIST_OF_INTERSECTS(350),                               00001800
     3 PIWA2_3S_MARBLE_RIKERS_FLAG     CHAR(1),                     00001900
     3 PIWA2_3S_DISTANCE               CHAR(5),                     00002000
     3 PIWA2_3S_GAP_FLAG               CHAR(1),                     00002100
     3 FILLER_100                      CHAR(7),                     00002200
     3 PIWA2_3S_NUM_OF_STR             CHAR(1),                     00002300
     3 PIWA2_3S_B7SC(5)                CHAR(8);                     00002400
```

P2PL1AP COPY File

```
/*****************************************************************/  00000100
/***  THIS IS THE PL/1 STRUCTURE FOR GEOSUPPORT SYSTEM PLATFORM  ***/  00000200
/***  INDEPENDENT      WORK AREA 2 FOR FUNCTIONS: AP , AND APX.  ***/  00000370
/***  MARCH 2015 BY YNL V15.2 FOR ADDRESS POINT AND AP EXTENDED. ***/  00000470
/***  COPY FILE - P2PL1AP.                                      ***/  00001170
/*****************************************************************/  00001226
                                                                       00001326
DCL 1 PIWA2_FNAPX,                                                     00026170
 /*****************************************************************/ 00026263
 /***              WORK AREA 2 FOR FUNCTION AP EXTENDED          ***/ 00026370
 /***                                                            ***/ 00026463
 /*****************************************************************/ 00026563
                                                                       00026663
                                                                       00026763
   2 PIWA2_APX_ACCESS_KEY              CHAR(21),                     00026870
   2 PIWA2_APX_CONT_PARITY             CHAR(1), /*(OR DUP ADDR IND)*/ 00026970
   2 PIWA2_APX_LOW_HOUSENUM            CHAR(11), /* SORT FORMAT */    00027070
   2 PIWA2_APX_BBL,                                                    00027170
     3 PIWA2_APX_BBL_BORO              CHAR(1),                      00027270
     3 PIWA2_APX_BLOCK                 CHAR(5),                      00027370
     3 PIWA2_APX_LOT                   CHAR(4),                      00027470
   2 FILLER_APX01                      CHAR(7),                      00027771
   2 PIWA2_APX_NUM_OF_STRUCTURES       CHAR(4),                      00028171
   2 FILLER_APX02                      CHAR(26),                     00028271
   2 FILLER_GSS1                       CHAR(1),  /* FOR GSS USE*/     00029571
   2 PIWA2_APX_BIN                     CHAR(7),                      00029670
   2 PIWA2_APX_CONDO_FLAG              CHAR(1),                      00029770
   2 FILLER_APX03                      CHAR(1),                      00029871
   2 PIWA2_APX_RPAD_CONDO_ID_NUM       CHAR(4),                      00029970
   2 FILLER_APX04                      CHAR(7),                      00030071
   2 PIWA2_APX_CONDO_BILL_BBL          CHAR(10),                     00030270
   2 FILLER_APX05                      CHAR(2),                      00030371
   2 PIWA2_APX_CONDO_LOW_BBL           CHAR(10),                     00030670
   2 FILLER_APX06                      CHAR(1),                      00030771
   2 PIWA2_APX_CONDO_HIGH_BBL          CHAR(10),                     00030970
   2 FILLER_APX07                      CHAR(16),                     00031071
   2 PIWA2_APX_COOP_NUM                CHAR(4),                      00031370
   2 FILLER_APX08                      CHAR(22),                     00031475
   2 PIWA2_APX_RESERVED                CHAR(03),                     00032370
   2 PIWA2_APX_LATITUDE                CHAR(09),                     00032470
   2 PIWA2_APX_LONGITUDE               CHAR(11),                     00032570
   2 PIWA2_APX_X_COORD                 CHAR(07),                     00032670
   2 PIWA2_APX_Y_COORD                 CHAR(07),                     00032770
   2 FILLER_APX09                      CHAR(16),                     00032873
   2 PIWA2_APX_AP_ID                   CHAR(09),                     00033473
```

```
  2 FILLER_GSS2                       CHAR(8),  /* LGC - GSS USE*/   00033571
  2 PIWA2_APX_REASON_CODE             CHAR(01),                     00033670
  2 PIWA2_APX_REASON_CODE_QUAL        CHAR(01),                     00033770
  2 PIWA2_APX_WARN_CODE               CHAR(02),                     00033870
  2 PIWA2_APX_RETURN_CODE             CHAR(02),                     00033970
  2 FILLER_APX10                      CHAR(108),                    00034072
  2 PIWA2_APX_NUM_OF_ADDR             CHAR(4),                      00034170
  2 PIWA2_APX_ADDR_LIST(21),                                        00034270
    3 PIWA2_APX_LIST_LOW_HOUSENUM     CHAR(16), /*DISPLAY FORMAT*/  00034370
    3 PIWA2_APX_LIST_HI_HOUSENUM      CHAR(16), /*DISPLAY FORMAT*/  00034470
    3 PIWA2_APX_LIST_BORO             CHAR(1),                      00034570
    3 PIWA2_APX_LIST_5SC              CHAR(5),                      00034670
    3 PIWA2_APX_LIST_LGC              CHAR(2),                      00034770
    3 PIWA2_APX_LIST_BIN              CHAR(7),                      00034870
    3 PIWA2_APX_LIST_SIDE_OF_STR      CHAR(1),  /* L, R */          00034970
    3 PIWA2_APX_ADDR_TYPE             CHAR(1),  /*              */  00035070
                                                /* BLANK = NORMAL*/  00035165
    3 FILLER_APX11                    CHAR(1),                      00035274
    3 PIWA2_APX_ST_NAME               CHAR(32),                     00035470
    3 FILLER_APX12                    CHAR(34);                     00035572
                                                                    00036065
                                                                    00037071
DCL 1 PIWA2_FNAP BASED(ADDR(PIWA2_FNAPX)),                          00037171
 /*******************************************************************/ 00039071
 /***              WORK AREA 2 FOR FUNCTION AP                   ***/ 00040071
 /***                                                            ***/ 00050071
 /*******************************************************************/ 00060071
                                                                    00070071
                                                                    00080071
  2 PIWA2_AP_ACCESS_KEY               CHAR(21),                     00090071
  2 PIWA2_AP_CONT_PARITY              CHAR(1), /*(OR DUP ADDR IND)*/ 00100071
  2 PIWA2_AP_LOW_HOUSENUM             CHAR(11), /* SORT FORMAT */   00110071
  2 PIWA2_AP_BBL,                                                   00120071
    3 PIWA2_AP_BBL_BORO               CHAR(1),                      00130071
    3 PIWA2_AP_BLOCK                  CHAR(5),                      00140071
    3 PIWA2_AP_LOT                    CHAR(4),                      00150071
  2 FILLER_AP01                       CHAR(7),                      00160071
  2 PIWA2_AP_NUM_OF_STRUCTURES        CHAR(4),                      00170071
  2 FILLER_AP02                       CHAR(26),                     00180071
  2 FILLER_GSS1                       CHAR(1),  /* FOR GSS USE*/    00190071
  2 PIWA2_AP_BIN                      CHAR(7),                      00200071
  2 PIWA2_AP_CONDO_FLAG               CHAR(1),                      00210071
  2 FILLER_AP03                       CHAR(1),                      00220071
  2 PIWA2_AP_RPAD_CONDO_ID_NUM        CHAR(4),                      00230071
  2 FILLER_AP04                       CHAR(7),                      00240071
```

```
  2 PIWA2_AP_CONDO_BILL_BBL          CHAR(10),                      00250071
  2 FILLER_AP05                      CHAR(2),                       00260071
  2 PIWA2_AP_CONDO_LOW_BBL           CHAR(10),                      00270071
  2 FILLER_AP06                      CHAR(1),                       00280071
  2 PIWA2_AP_CONDO_HIGH_BBL          CHAR(10),                      00290071
  2 FILLER_AP07                      CHAR(16),                      00300071
  2 PIWA2_AP_COOP_NUM                CHAR(4),                       00310071
  2 FILLER_AP08                      CHAR(18),                      00320072
  2 PIWA2_AP_DOF_MAP_PAGE            CHAR(4),                       00330071
  2 PIWA2_AP_RESERVED                CHAR(03),                      00340071
  2 PIWA2_AP_LATITUDE                CHAR(09),                      00350071
  2 PIWA2_AP_LONGITUDE               CHAR(11),                      00360071
  2 PIWA2_AP_X_COORD                 CHAR(07),                      00370071
  2 PIWA2_AP_Y_COORD                 CHAR(07),                      00380071
  2 FILLER_AP09                      CHAR(16),                      00390073
  2 PIWA2_AP_AP_ID                   CHAR(09),                      00400073
  2 FILLER_GSS2                      CHAR(8),  /* LGC - GSS USE*/   00410071
  2 PIWA2_AP_NUM_OF_ADDR             CHAR(4),                       00470071
  2 PIWA2_AP_ADDR_LIST(21),                                         00480071
    3 PIWA2_AP_LIST_LOW_HOUSENUM     CHAR(16), /*DISPLAY FORMAT*/   00490071
    3 PIWA2_AP_LIST_HI_HOUSENUM      CHAR(16), /*DISPLAY FORMAT*/   00500071
    3 PIWA2_AP_LIST_BORO             CHAR(1),                       00510071
    3 PIWA2_AP_LIST_5SC              CHAR(5),                       00520071
    3 PIWA2_AP_LIST_LGC              CHAR(2),                       00530071
    3 PIWA2_AP_LIST_BIN              CHAR(7),                       00540071
    3 PIWA2_AP_LIST_SIDE_OF_STR      CHAR(1),  /* L, R */           00550071
    3 PIWA2_AP_ADDR_TYPE             CHAR(1),  /*               */  00560071
                                               /* BLANK = NORMAL*/  00570071
    3 FILLER_AP10                    CHAR(4);                       00600071
                                                                    00610071
```

C COPY File (COW)

PAC COPY File

```
#ifndef GEOSUPPORT
#define GEOSUPPORT
#ifdef __cplusplus
extern "C" {
#endif
 /*********************************************************************/
 /*                                                                   */
 /*  Add new 5 bytes field 'PUMA code' in functions:                  */
 /*  1/1E (Etended),1B,3/3C (Extended).              TLV 12/2017 V18.1*/
```

```
/*  Add new 3 bytes field 'DCP Zoning Map' in       TLV 09/2017 V17.4*/
/*  functions: 1A,BL,BN; 1A,BL,BN(extended) and 1B.                  */
/*  Add new 2 bytes field 'Speed Limit' in          TLV 09/2017 V17.4*/
/*  functions: 1/1E(extended), 1B, 3X, 3CX.                          */
/*  Add new 2 bytes Bike Traffic Direction          TLV 12/2016 V17.1*/
/*  Replaced sanit_reserved with sanit_bulk_pick_up TLV  9/2016 V16.4*/
/*  Added 'unit' fields to WA1                      TLV  9/2016 V16.4*/
/*  Add new 2 bytes Bike Lane and Max Str Width     TLV  9/2016 V16.4*/
/*                                                                   */
/*********************************************************************/
/*                                                                   */
/*            GeoSupport System C-Language Header File               */
/*               for Platform-Independent Work Areas                 */
/*                                                                   */
/*                 Last Updated: February 2016                       */
/*                                                                   */
/*********************************************************************/

/*********************************************************************/
/*                                                                   */
/*      Group Items Used in Platform-Independent Work Area 1         */
/*                                                                   */
/*********************************************************************/
#define UNIT_SIZE     14               //unit type+identifier v16.4
#define UNITT_SIZE     4               //unit type            v16.4
#define UNITI_SIZE    10               //unit identfier       v16.4

typedef struct { char boro;              // Borough Code
                 char SC10[10];          // 10 Digit Street Code
                 char Street_name[32];   // Street Name
               } STREET;

typedef union { char bbl[10];            /* Borough-Block-Lot        */
                struct { char boro;      /* Borough                  */
                         char block[5];  /* Tax Block                */
                         char lot[4];    /* Tax Lot                  */
                       } cas;
              } BBL;

typedef struct {
  char unitt[UNITT_SIZE];                /* Output unit type  V16.4 */
  char uniti[UNITI_SIZE];                /* Output unit identifier  */
} UNIT, *PUNIT;                          /* Output unit       V16.4 */
```

```
typedef struct {
                 char func_code[2];      /* Function Code            */
                 char hse_nbr_disp[16];  /* House nbr in Disp form   */
                 char hse_nbr_hns[11];   /* House nbr in Sort form   */
                 char lohse_nbr_disp[16];/* Lo House nbr in Disp form*/
                 char lohse_nbr_hns[11]; /* Lo House nbr in Sort form*/
                 STREET sti[3];          /* Street Information       */
                 BBL bbli;               /* Borough-Block-Lot        */
                 char filler01;          /* Filler-Tax Lot Version # */
                 char bld_id[7];         /* Building Id Number (BIN) */
                 char comp_direction;    /* Compass Direction        */
                 char comp_direction2;   /* Compass Direction-Fn 3S  */
                 char node[7];           /* Node input for Fn2       */
                 char platform_ind;      /* Must be equal to 'C'     */
                 char zipin[5];          /* Input Zip Code           */
                 char unit[UNIT_SIZE];   /* Input unit          V16.4*/
                 char filler03[82];      /* Future Use               */

                        /* Flags that influence processing */

                 char long_WA_flag;      /* Long Work Area 2 Flag     */
                                         /* Next 2 fields not impl    */
                 char hse_nbr_justify;   /* Hse Nbr Justification Flg */
                 char hnl[2];            /* Hse Nbr Normalization len */
                 char hse_nbr_over_flag; /* Reserved for GSS Use      */
                 char snl[2];            /* Street Name Norm Length   */
                 char st_name_norm;      /* Street Name Normalization */
                                         /*   Format Flag             */
                 char expanded_format;   /* Expanded Format Flag      */
                 char roadbedrequest;    /* Roadbed Request Switch    */
                 char res_01;            /* Reserved for Internal Use */
                 char segaux_switch;     /* Request Auxiliary Segment */
                                         /* Information               */
                 char browse_flag;       /* Determines if browse      */
                                         /* displays all or some names*/
                 char real_street_only;  /* Display real streets only */
                 char tpad_switch;       /* TPAD read for PAD process */
                 char mode_switch;       /* Mode Flag                 */
                                         /* X = Extended WA2          */
                 char wto_switch;        /* WTOs Switch N = No WTOs   */
                                         /*   should be issued        */
                 char filler04[29];      /* Future Use                */
                } INWA1;

typedef struct {
```

```
                char boro_name[9];      /* Boro Name of First Street*/
                char hse_nbr_disp[16];  /* House nbr in Normalized  */
                                        /* Display form             */
                char hse_nbr_hns[11];   /* House number in Sort Form*/
                STREET sto[3];          /* Street Information       */
                BBL bblo;               /* Boro(len=1), Block(len=5)*/
                                        /* and Lot (len=4)-Normalizd*/
                char filler05;          /* Filler-Tax Lot Version # */
                char lo_hse_nbr_disp[16]; /* low Hse nbr - display  */
                char lo_hse_nbr_hns[11]; /* low Hse nbr - sort form */
                char bin[7];            /* Building Id Number       */
                char attrbytes[3];      /* NAP Identification Number*/
                char reason_code_2;     /* 2nd Reason Code          */
                char reason_code_qual_2;/* 2nd Reason Code Qualifier*/
            //  char filler08_2;        /* Future Use               */
                char warn_code_2[2];    /* 2nd Warning Return Code  */
                char ret_code_2[2];     /* 2nd GeoSupport Return Cod*/
                char msg_2[80];         /* 2nd GeoSupport Message   */
                char node[7];           /* Node output for Fn 2     */
                UNIT units;             /* Output unit Sort    V16.4*/
                char unitd[UNIT_SIZE];  /* Output unit Display V16.4*/
                char filler07[11];      /* Future Use               */
                char nap_id_nbr[6];     /* NAP Id Nbr - Not Impl.   */
                char int_use1;          /* Internal Use Only        */
                char reason_code;       /* Reason Code              */
                char reason_code_qual;  /* Reason Code Qualifier    */
            //  char filler08;          /* Future Use               */
                char warn_code[2];      /* Warning Ret. Code-NotImpl*/
                char ret_code[2];       /* GeoSupport Return Code   */
                char msg[80];           /* GeoSupport Message       */
                char nbr_names[2];      /* Nbr of Sreet Names       */
                char B_7SC[10][8];      /* 10 Boro+7-digit st codes */
                char st_names[10][32];  /* Up to 10 Street Names    */
              } OUTWA1;

/*********************************************************************/
/*                                                                   */
/*                 Platform-Independent Work Area 1                  */
/*                                                                   */
/*********************************************************************/

typedef struct { INWA1 input;
                 OUTWA1 output;
               } C_WA1;
```

```
/*****************************************************************/
/*                                                               */
/*     Group Items Used in Platform-Independent Work Area 2's    */
/*                                                               */
/*****************************************************************/

typedef struct {                        /* LION KEY                 */
                char lion_boro;         /* LION Borough Code        */
                                        /* Differs from GeoSupport  */
                                        /* Borough Codes            */
                char face[4];           /* Face Code                */
                char seq[5];            /* Sequence Number          */
              } LION;

typedef struct {
                char nbr_sts;           /* Number of streets */
                char B5SC[5][6];        /* Boro+5 Street Code*/
              } St_list;

typedef struct {                    /* used for longwa for TPAD */
  char bin[7];                              /* BIN               */
  char status;                              /* Status of BIN     */
} TPAD_LIST;

typedef struct {
  TPAD_LIST   tpadlist[2187];           /* or BINs + Status Byte  */
  char        fill[4];
} TPADLST;

typedef struct { char lo_hse_nbr[16];    /* Low House Nbr-Disply form*/
                char hi_hse_nbr[16];    /* Hi House Nbr-Display form*/
                char B5SC[6];           /* Boro & 5 digit Str Code  */
                char lgc[2];            /* DCP Preferred Street LGC */
                char bld_id[7];         /* BIN of address range     */
                char sos_ind;           /* Side of Street Indicator */
                char adr_type;          /* Address type - P=NAP,    */
                                        /*    B=NAB, Blank=Normal   */
                char TPAD_bin_status;   /* Status of Job            */
                char filler01[3];       /* Future Use               */
              } ADDR_RANGE;

typedef struct {
  char lo_hse_nbr[16];                  /* Low House Nbr-Disply form*/
  char hi_hse_nbr[16];                  /* Hi House Nbr-Display form*/
  char B5SC[6];                         /* Boro & 5 digit Str Code  */
```

```
  char lgc[2];                          /* DCP Preferred Street LGC */
  char bld_id[7];                       /* BIN of address range     */
  char sos_ind;                         /* Side of Street Indicator */
  char adr_type;                        /* Address type             */
                                        /* (Blank = Normal)         */
  char TPAD_bin_status;                 /* Status of BIN from TPAD  */
  char st_name[32];                     /* Street Name              */
  char filler01[34];                    /* Future Use               */
} ADDR_RANGE_1AX;

typedef struct { char lo_hse_nbr[16];    /* Low House Nbr-Disply form*/
                 char hi_hse_nbr[16];    /* Hi House Nbr-Display form*/
                 char B5SC[6];           /* Boro & 5 digit Str Code  */
                 char lgc[2];            /* DCP Preferred Street LGC */
                 char bld_id[7];         /* BIN of address range     */
                 char sos_ind;           /* Side of Street Indicator */
                 char adr_type;          /* Address type - V=VANITY  */
                                         /*   Blank=Normal           */
                 char filler02;          /* filler for func AP       */
                 char filler01[3];       /* Future Use               */
               } ADDR_RANGE_AP;

typedef struct { char lo_hse_nbr[16];    /* Low House Nbr-Disply form*/
                 char hi_hse_nbr[16];    /* Hi House Nbr-Display form*/
                 char B5SC[6];           /* Boro & 5 digit Str Code  */
                 char lgc[2];            /* DCP Preferred Street LGC */
                 char bld_id[7];         /* BIN of address range     */
                 char sos_ind;           /* Side of Street Indicator */
                 char adr_type;          /* Address type - V=VANITY  */
                                         /*    Blank=Normal          */
                 char filler02;          /* filler for func APX      */
                 char st_name[32];       /* Street Name              */
                 char filler01[34];      /* Future Use               */
               } ADDR_RANGE_APX;

typedef struct { char sanborn_boro;      /* Sanborn Borough Code     */
                 char sanborn_vol[3];    /* Sanborn Volume           */
                 char sanborn_page[4];   /* Sanborn Page             */
               } SANBORN;

typedef struct { char com_dist[3];       /* Community District       */
                 char lo_hse_nbr[16];    /* Low House Nbr-Disply form*/
                 char hi_hse_nbr[16];    /* Hi House Nbr-Display form*/
                 char filler01[32];      /* Future Use               */
                 char iaei;              /* Interim Ass'tance Elig   */
```

```
                                        /* Indicator                */
                char zip_code[5];       /* Zip code for Street seg. */
                char health_area[4];    /* Health Area        */
                char police_boro_com;   /* Police Patrl Boro Command*/
                char police_pre[3];     /* Police Precinct          */
                char fire_divisn[2];    /* Fire Division            */
                char fire_bat[2];       /* Fire Battalion           */
                char fire_co_type;      /* Fire Company Type        */
                char fire_co_nbr[3];    /* Fire Company Number      */
                char com_schl_dist[2];  /* Community School District*/
                char dynam_blk[3];      /* Atomic Polygon           */
                                        /* (was Dynamic Block)      */
                char ED[3];             /* ED                       */
                char AD[2];             /* AD                       */
                char police_pat_boro[2];/* Police Patrol Borough    */
          //    char instruc_div[2];    /* Instructional Division   */
                char filler02;          /* Future Use               */
                char boro;              /* Used for the NTA name    */
                char cen_tract_90[6];   /* 1990 Census Tract        */
                char cen_tract_10[6];   /* 2010 Census Tract        */
                char cen_blk_10[4];     /* 2010 Census Block        */
                char cen_blk_10_sufx;   /* 2010 Census Block Suffix */
                                        /* 2010 Suffix Not Implement*/
                char cen_tract_2000[6]; /* 2000 Census Tract        */
                char cen_blk_2000[4];   /* 2000 Census Block        */
                char cen_blk_2000_sufx; /* 2000 Census Block Suffix */
           //   char blockface_id[7];   /* "Blockface ID" became    */
                char filler03[7];       /* filler   V16.1           */
                char nta[4];            /* Neighborhood Tabulation  */
                                        /* Area                     */
                char filler04[8];       /* Future Use               */
              } SEGSIDE;

typedef struct { char mh_ri_flag;       /* Marble Hill/Rikers Island*/
                                        /* Alternative Boro flag    */
                char len[5];            /* Len in ft from prev node */
                char gap_flag;          /* Gap Flag                 */
                char node_nbr[7];       /* Node Number of Intersect */
                char nbr_streets;       /* Nbr streets intersecting */
                char B7SC[5][8];        /* Lowest B7SC at Intersect */
                                        /* is first and 2nd Lowest  */
                                        /* B7SC is next. Remaining  */
                                        /* B7SC's in no particular  */
                                        /* order.                   */
              } CROSS_STRS;
```

```
/*********************************************************************/
/*                                                                   */
/*        Platform-Independent Work Area 2 for Function 1            */
/*                                                                   */
/*********************************************************************/

typedef struct { char filler01[21];
                 char cont_parity_ind;   /* Continuous Parity Ind.   */
                                         /* or Duplicate Address Ind.*/
                 char lo_hse_nbr[11];    /* Lo House nbr in Sort form*/
                 char hi_hse_nbr[11];    /* Hi House Nbr in Sort form*/
                 char lgc[2];            /* DCP or BOE Preferred LGC */
                 St_list st[2];          /* 1=Low and 2=High         */
                                         /* Nbr of cross streets at  */
                                         /* low house nbr end of st  */
                                         /* B5SCs of lo end cross st */
                 LION key;               /* LION Key - 10 Characters */
                 char sagr_flag;         /* Special Address Generated*/
                                         /* Record flag              */
                 char sos_ind;           /* Side of Street Indicator */
                 char seg_len[5];        /* Segment Length in Feet   */
                 char coord[3][7];       /* 1 = X coordinate,        */
                                         /* 2 = Y coordinate,        */
                                         /* 3 = Z coordinate, Not Imp*/
                 char iaei;              /* Interim Ass'tance Elig   */
                                         /* Indicator                */
                 char mh_ri_flag;        /* Marble Hill/Rikers Island*/
                                         /* Alternative Borough flag */
                 char DOT_slca;          /* DOT St Lght Contractr Are*/
                 char com_dist[3];       /* Community District       */
                                         /* Position 0 contains the  */
                                         /* CD Boro Code & Pos 1 & 2,*/
                                         /* the district number      */
                 char zip_code[5];       /* Zip code for st seg      */

           /* Following seven fields used for Function 1E only*/

                 char ed[3];             /* Election District        */
                 char ad[2];             /* Assembly District        */
                 char sped_flag;         /* Split Elect District Flag*/
                 char congress_dist[2];  /* Congressional District   */
                 char state_sen_dist[2]; /* State Senatorial District*/
                 char civil_court[2];    /* Civil Court District     */
                 char city_council[2];   /* City Council District    */
```

```
        char health_cent[2];    /* Health Center Dictr*/
        char health_area[4];    /* Health Area        */
        char sanit_dist[3];     /* Sanitation District      */
        char sanit_sub_sect[2]; /* Sanit Collect Scheduling */
                                /* Section and Subsection   */
        char sanit_reg_pick_up[5]; /* Regular Pick up       */
        char sanit_recycle[3];  /* Recycle pick up          */
        char police_boro_com;   /* Police Patrol Boro Commnd*/
        char police_pre[3];     /* Police Precinct          */
        char fire_divisn[2];    /* Fire Division            */
        char fire_bat[2];       /* Fire Battalion           */
        char fire_co_type;      /* Fire Company Type        */
        char fire_co_nbr[3];    /* Fire Company Number      */
        char filler_scsd;       /* Was Split Com School     */
                                /* District Flag            */
        char com_schl_dist[2];  /* Community School District*/
        char dynam_blk[3];      /* Atomic Polygon           */
                                /* (was Dynamic Block)      */
        char police_pat_boro[2];/* Police Patrol Borough    */
//      char filler_indv[2];    /*                          */
//      char instruc_div[2];    /* Instructional Division   */
        char feature_type;      /* Feature Type Code        */
        char segmenttypecode;   /* Segment Type Code        */
        char alx;               /* Segment split by Alley(s)*/
                                /* A=Split by Alley(s)      */
                                /* X=Cross Streets Modified */
        char coincident_seg_cnt; /* Coincident Segment      */
                                /*    Counter               */
        char filler02[2];       /* Future Use               */
        char boro_of_cen_tract; /* boro of Census Tract used*/
        char cen_tract_90[6];   /* 1990 Census Tract        */
        char cen_tract_10[6];   /* 2010 Census Tract        */
        char cen_blk_10[4];     /* 2010 Census Block        */
        char cen_blk_10_sufx;   /* 2010 Census Block Suffix */
                                /* 2010 Suffix Not Implement*/
        char cen_tract_2000[6]; /* 2000 Census Tract        */
        char cen_blk_2000[4];   /* 2000 Census Block        */
        char cen_blk_2000_sufx; /* 2000 Census Block Suffix */
        char nta[4];            /* Neighborhood Tabulation  */
                                /* Area                     */
        char sanit_snow_priority;/* Sanitation Street Snow  */
                                /* Priority (P,S,T,V)       */
        char sanit_org_pick_up[5];/* Organics Pick up       */
        char sanit_bulk_pick_up[5]; /* Bulk Pick Up V16.4   */
      //char sanit_reserved[5]; /* Reserved for Possible    */
```

```
                char hurricane_zone[2]; /* Hurricane Evacuation Zone*/
                char filler04[11];      /* Future Use               */
                char true_hns[11];      /* Underlying HNS           */
                char true_b7sc[8];      /* True Boro 7 Street Code  */
                char seg_id[7];         /* Segment Identifier       */
                char curv_flag;         /* Curve Flag               */
              } C_WA2_F1;

 /*******************************************************************/
 /*                                                                 */
 /*      Platform-Independent Work Area 2 for Function 1V/1W        */
 /*                                                                 */
 /*******************************************************************/

typedef struct {
  C_WA2_F1 c_wa2_f1;
  char int_use[8];                      /* valid on street lgcs     */
  char boe_lgc;                         /* BOE LGC Pointer          */
  char seg_azm[3];                      /* Segment Azimuth          */
  char seg_orient;                      /* Segment Orientation      */
  char seg_coord[2][3][7];              /* Spatial Coordinates of   */
                                        /* Segment                  */
  char cc_coord[3][7];                  /* Spatial Coordinates of   */
                                        /* Center of Curvature      */
  char radius[7];                       /* Radius of Circle         */
  char cc_sos;                          /* Center of Curvature Side */
                                        /* of Street Flag           */
  char node_angles[2][5];               /* Angle to FROM & TO Nodes */
  char nodes[2][7];                     /* LION Node Numbers of     */
                                        /* FROM and TO nodes        */
  LION LION_key;                        /* LION Key for Vanity      */
                                        /* Addresses                */
  char LION_sos_ind;                    /* LION SoS Indicator       */
  char split_low_hn[11];                /* Split Low House Number   */
  char traffic_dir;                     /* Traffic Direction        */
  char turn_restricts[10];              /* Turn restrictions        */
  char curve_fraction[3];               /*                          */
  char roadway_type[2];                 /* Roadway Type             */
  char physical_id[7];                  /*                          */
  char generic_id[7];                   /*                          */
  char filler03[7];                     /* DCP internal use         */
  char filler04[7];                     /* DCP internal use         */
//char blockface_id[7];      /** V16.1 **  blockface id 10 bytes long*/
  char bike_lane_2[2];                  /*Bike Lane has 2 bytes     */
                                        /* numeric value moved in   */
```

```
                                        /* wa2 of F1EX              */
  char bike_traffic_dir[2];             //V17.1 Bike Traffic Direction
  char filler05[3];                     // V17.1
  char status;                          /*                          */
  char str_width[3];                    /*                          */
  char str_width_irregular;             /* Yes or No                */
  char bike_lane;                       /*                          */
  char fcc[2];                          /* Federal Classification Cd*/
  char row_type;                        /*                          */
  char lgcs_additional[5][2];           /* additional lgcs for on st*/
} C_WA2_F1V;

 /*******************************************************************/
 /*                                                                 */
 /*   Platform-Independent Work Area 2 for Function 1E Extended     */
 /*                                                                 */
 /*******************************************************************/
typedef struct {                        /* Fn 1E with extra bytes   */
  C_WA2_F1V cwa2f1v;
  char legacy_segid[7];                 /*                          */
  char from_preferred_lgcs[5][2];       /*                          */
  char to_preferred_lgcs[5][2];         /*                          */
  char from_additional_lgcs[5][2];      /*                          */
  char to_additional_lgcs[5][2];        /*                          */
  char no_x_st_calc_flg;                /* No Cross Street          */
                                        /* Calculation Flag         */
  char indiv_seg_len[5];                /* Individual Segment Length*/
                                        /* Used with Above Flag     */
  char nta_name[75];                    /* Neighborhood Tabulation  */
                                        /* Area Name                */
  char USPS_city_name[25];              /* USPS Preferred City Name */
  char latitude[9];                     /* Latitude calc from X-Y   */
  char longitude[11];                   /* Longitude calc from X-Y  */
  char seg_from_node[7];                /* Segment from node        */
  char seg_to_node[7];                  /* Segment to node          */
  char seg_from_xyz[3][7];              /* XYZ coord (segment from) */
  char seg_to_xyz[3][7];                /* XYZ coord (segment to)   */
  char blockface_id[10];                /* NEW location V16.1       */
                                        /* because of length changed*/
  char nbr_travel_lanes[2];             /* nbr of traveling lanes   */
  char nbr_park_lanes[2];               /* nbr of parking lanes     */
  char nbr_total_lanes[2];              /* total nbr of lanes       */
  char str_width_max[3];                /*street width maximum      */
  char speed_limit[2];                  /* Speed Limit              */
  char puma_code[5];                    /* PUMA Code          V18.1*/
```

```
  char filler6[245];                    /*                    V18.1*/
//char filler6[252];                    /* Future Use              */
  char reason_code;                     /* Reason Code             */
  char reason_code_qual;                /* Reason Code Qualifier   */
  char warn_code[2];                    /* Warning Return Code     */
  char ret_code[2];                     /* GeoSupport Return Code  */
  char nbr_names_lo;                    /* Nbr of St Names Low End */
  char B7SC_lo[5][8];                   /* 5(Boro+7-digit) st codes */
  char nbr_names_hi;                    /* Nbr of St Names High End */
  char B7SC_hi[5][8];                   /* 5 Boro+7-digit st codes */
  char st_names_lo[5][32];              /* Up to 5 St Names Low End */
  char st_names_hi[5][32];              /* Up to 5 St Names High End*/
  char BOE_B5SC[6];                     /* BOE Preffered B7SC      */
  char BOE_lgc[2];                      /* BOE Preffered B7SC      */
  char BOE_st_name[32];                 /* BOE Preffered Street Name*/
  char filler7[52];                     /* Future Use              */
} C_WA2_F1EX;                           /* Fn 1EX with filler      */

 /*********************************************************************/
 /*                                                                   */
 /*   Platform-Independent Work Area 2 for Function 1A Extended       */
 /*                                                                   */
 /*********************************************************************/
typedef struct {                        /* Fn 1A with extra bytes  */
  char filler01[21];
  char cont_parity_ind;                 /* Continuous Parity Ind   */
                                        /* or Duplicate Address Ind */
  char lo_hse_nbr[11];                  /* Low House Number-Sort Frm*/

  BBL  bbl;                             /* Borough-Block-Lot       */
  char filler02;                        /* Reserved for Tax Lot Ver#*/
  char RPAD_scc;                        /* RPAD Self_Check Code(SCC)*/
  char filler03;
  char RPAD_lucc[2];                    /* RPAD Land Use Class. Code*/
  char corner[2];                       /* Corner Code             */
  char nbr_blds[4];                     /* Nbr of buildings on lot */
  char nbr_str[2];                      /* Nbr Street Frontages    */
  char inter_flag;                      /* Interior Lot Flag       */
  char vacant_flag;                     /* Vacant Lot Flag         */
  char irreg_flag;                      /* Irregularly-Shaped Lot Fl*/
  char mh_ri_flag;                      /* Marble Hill/Rikers Island*/
  char adr_range_overflow;              /* Addr Rnge Lst Ovrflow Flg*/
  char stroll_key[18];                  /* Strolling key Not Implem */
  char filler04;
  char res_internal_use;                /* Reserved for Internal Use*/
```

```
char bld_id[7];                     /* Building Ident. Number   */
                                    /* (BIN) of Input Address of*/
                                    /* Existing Building, If any*/
char condo_flag;                    /* Condominium Flag         */
char filler05;                      /* Future Use               */
char condo_id[4];                   /* RPAD Condo Id Number     */
char condo_unit_id[7];              /* Condo Unit Id Nbr-Not Imp*/
BBL  condo_bill_bbl;                /* Condo Billing BBL        */
char filler06;                      /* Reserved for Tax Lot Ver */
char condo_scc;                     /* Self-Check Code          */
BBL  condo_lo_bbl;                  /* Low BBL of Condo         */
char filler07;                      /* Reserved for Tax Lot Ver */
BBL  condo_hi_bbl;                  /* High BBL of Condo        */
char filler08;                      /* Reserved for Tax Lot Ver */
char filler09[15];
char co_op_nbr[4];                  /* Co-op Number             */
SANBORN San;                        /* Sanborn Information      */
char business_area[5];              /* Business Area            */
char tax_map_nbr[5];                /* Tax Map Nbr-Sect and Vol */
char filler10[4];                   /* Tax Map Nbr Page Not Impl*/
char filler11[3];
char latitude[9];                   /* Latitude calc from X-Y   */
char longitude[11];                 /* Longitude calc from X-Y  */
char coord[2][7];                   /* 1 = X coordinate-Annotat */
                                    /* 2 = Y coordinate-Annotat */
char bid_id[6];                     /* Business Improvement     */
                                    /* District ID (BID)        */

char TPAD_bin_status;               /* Status of Demolition job */
                                    /* on Existing BIN of Input */
                                    /* Address                  */
char TPAD_new_bin[7];               /* BIN for New Building     */
char TPAD_new_bin_status;           /* Status of New Buildng BIN*/
char TPAD_conflict_flag;            /* From TPAD                */
char dcp_zone_map[3];               /* DCP Zoning Map           */
char filler12[6];

char int_use[8];                    /* Internal Use             */
char reason_code;                   /* Reason Code              */
char reason_code_qual;              /* Reason Code Qualifier    */
char warn_code[2];                  /* Warning Return Code      */
char ret_code[2];                   /* GeoSupport Return Code   */
char filler14[108];
char nbr_addr[4];                   /* Nbr of Addr Ranges or Nbr*/
                                    /* of BINs in List          */
```

```
  ADDR_RANGE_1AX addr_range_1ax[21];
} C_WA2_F1AX;                           /* Fn 1AX with filler       */
 /*******************************************************************/
 /*                                                                 */
 /*      Platform-Independent Work Area 2 for Function 1B           */
 /*                                                                 */
 /*******************************************************************/

typedef struct {                        /* Function 1B              */
  C_WA2_F1EX cwa2f1ex;                  /* 1EX Component            */
  C_WA2_F1AX cwa2f1ax;                  /* 1AX Component            */
} C_WA2_F1B;                            /* Fn 1B                    */

 /*******************************************************************/
 /*                                                                 */
 /*      Platform-Independent Work Area 2 for Function 1A           */
 /*                                                                 */
 /*******************************************************************/

typedef struct {
   char filler01[21];
   char cont_parity_ind;   /* Continuous Parity Ind    */
                           /* or Duplicate Address Ind */
   char lo_hse_nbr[11];    /* Low House Number-Sort Frm*/

   BBL bbl;                /* Borough-Block-Lot        */
   char filler02;          /* Reserved for Tax Lot Ver#*/
   char RPAD_scc;          /* RPAD Self_Check Code(SCC)*/
   char filler03;
   char RPAD_lucc[2];      /* RPAD Land Use Class. Code*/
   char corner[2];         /* Corner Code              */
   char nbr_blds[4];       /* Nbr of buildings on lot  */
   char nbr_str[2];        /* Nbr Street Frontages     */
   char inter_flag;        /* Interior Lot Flag        */
   char vacant_flag;       /* Vacant Lot Flag          */
   char irreg_flag;        /* Irregularly-Shaped Lot Fl*/
   char mh_ri_flag;        /* Marble Hill/Rikers Island*/
   char adr_range_overflow;/* Addr Rnge Lst Ovrflow Flg*/
   char stroll_key[18];    /* Strolling key            */
   char filler04;
   char res_internal_use;  /* Reserved for Internal Use*/
   char bld_id[7];         /* Building Ident. Number   */
                           /* (BIN) of Input Address of*/
                           /* Existing Building, If any*/
   char condo_flag;        /* Condominium Flag         */
```

```
   char filler05;          /* Future Use               */
   char condo_id[4];       /* RPAD Condo Id Number     */
   char condo_unit_id[7];  /* Condo Unit Id Nbr-Not Impl*/
   BBL  condo_bill_bbl;    /* Condo Billing BBL        */
   char filler06;          /* Reserved for Tax Lot Ver */
   char condo_scc;         /* Self-Check Code          */
   BBL  condo_lo_bbl;      /* Low BBL of Condo         */
   char filler07;          /* Reserved for Tax Lot Ver */
   BBL  condo_hi_bbl;      /* High BBL of Condo        */
   char filler08;          /* Reserved for Tax Lot Ver */
   char filler09[15];
   char co_op_nbr[4];      /* Co-op Number             */
   SANBORN San;            /* Sanborn Information      */
   char business_area[5];  /* Business Area            */
   char tax_map_nbr[5];    /* Tax Map Nbr-Sect and Vol */
   char filler10[4];       /* Tax Map Nbr Page Not Impl*/
   char filler11[3];
   char latitude[9];       /* Latitude calc from X-Y   */
   char longitude[11];     /* Longitude calc from X-Y  */
   char coord[2][7];       /* 1 = X coordinate-Annotat */
                           /* 2 = Y coordinate-Annotat  */
   char bid_id[6];         /* Business Improvement Dist */
                           /* District ID (BID)         */
   char TPAD_bin_status;   /* Existing BIN of Input Addr*/
   char TPAD_new_bin[7];    /* BIN for New Building job */
   char TPAD_new_bin_status;/* Status of New Buildng BIN*/
   char TPAD_conflict_flag; /* From TPAD                */
   char dcp_zone_map[3];    /* DCP Zoning Map           */
   char filler12[6];
   char int_use[8];        /* Internal Use             */
   char nbr_addr[4];       /* Nbr of Addr Ranges or Nbr*/
                           /* of BINs in List          */
   union {
           ADDR_RANGE addr_range[21]; /* List of Addr  */
           TPADLST   tpad_list;       /*or BINs + Status Byte */
           char bin_list[2500][7];    /* or BINs*/
         } bar;
} C_WA2_F1A;
 /*********************************************************************/
 /*                                                                   */
 /*      Platform-Independent Work Area 2 for Function AP             */
 /*                                                                   */
 /*********************************************************************/

typedef struct {
```

```
char filler01[21];
char cont_parity_ind;   /* Continuous Parity Ind    */
                        /* or Duplicate Address Ind */
char lo_hse_nbr[11];    /* Low House Number-Sort Frm*/

BBL bbl;                /* Borough-Block-Lot        */
char filler02;          /* Reserved for Tax Lot Ver#*/
char fil_RPAD_scc;      /* filler for func AP       */
char filler03;
char fil_RPAD_lucc[2];  /* fillers for func AP      */
char fil_corner[2];     /* fillers for func AP      */
char nbr_blds[4];       /* Nbr of buildings on lot  */
char fil_nbr_str[2];    /* fillers for func AP      */
char fil_inter_flag;    /* filler for func AP       */
char fil_vacant_flag;   /* filler for func AP       */
char fil_irreg_flag;    /* filler for func AP       */
char fil_mh_ri_flag;    /* filler for func AP       */
char fil_adr_range_overflow;/* filler for func AP   */
char fil_stroll_key[18];/* fillers for func AP      */
char filler04;
char res_internal_use;  /* Reserved for Internal Use*/
char bld_id[7];         /* Building Ident. Number   */
                        /* (BIN) of Input Address of*/
                        /* Existing Building,       */
char condo_flag;        /* Condominium Flag         */
char filler05;          /* Future Use               */
char condo_id[4];       /* RPAD Condo Id Number     */
char filler_unit_id[7]; /* Condo Unit Id Nbr-Not Impl*/
BBL  condo_bill_bbl;    /* Condo Billing BBL        */
char filler06;          /* Reserved for Tax Lot Ver */
char fil_condo_scc;     /* filler for func AP       */
BBL  condo_lo_bbl;      /* Low BBL of Condo         */
char filler07;          /* Reserved for Tax Lot Ver */
BBL  condo_hi_bbl;      /* High BBL of Condo        */
char filler08;          /* Reserved for Tax Lot Ver */
char filler09[15];
char co_op_nbr[4];      /* Co-op Number             */
char fil_sanborn[8];    /* fillers for func AP      */
char fil_business_area[5];  /* fillers for func AP  */
char fil_tax_map_nbr[5];    /* fillers for func AP  */
char filler10[4];
char filler11[3];
char latitude[9];       /* Latitude calc from X-Y   */
char longitude[11];     /* Longitude calc from X-Y  */
char coord[2][7];       /* 1 = X coordinate from AP */
```

```
                          /* 2 = Y coordinate from AP */
   char fil_bid_id[6];          /* fillers for func AP */
   char fil_TPAD_bin_status;    /* fillers for func AP */
   char fil_TPAD_new_bin[7];    /* fillers for func AP */
   char fil_TPAD_new_bin_status;/* filler for func AP  */
   char fil_TPAD_conflict_flag; /* filler for func AP  */
   char ap_id[9];               /* Address Point Id    */
   char int_use[8];             /* Internal Use        */
   char nbr_addr[4];            /* Nbr of Addr = 0001  */

   union {
           ADDR_RANGE_AP addr_range_ap[21]; /* List of Addr  */
           char fil_tpad_list[2191];
           char fil_bin_list[2500][7];
         } bar;
} C_WA2_FAP;

 /*********************************************************************/
 /*                                                                   */
 /*      Platform-Independent Work Area 2 for Function APX            */
 /*                                                                   */
 /*********************************************************************/

typedef struct {
   char filler01[21];      /* Fn AP with extra bytes   */
   char cont_parity_ind;   /* Continuous Parity Ind    */
                           /* or Duplicate Address Ind */
   char lo_hse_nbr[11];    /* Low House Number-Sort Frm*/

   BBL bbl;                /* Borough-Block-Lot        */
   char filler02;          /* Reserved for Tax Lot Ver#*/
   char fil_RPAD_scc;      /* filler for func AP       */
   char filler03;
   char fil_RPAD_lucc[2];  /* fillers for func AP      */
   char fil_corner[2];     /* fillers for func AP      */
   char nbr_blds[4];       /* Nbr of buildings on lot  */
   char fil_nbr_str[2];    /* fillers for func AP      */
   char fil_inter_flag;    /* filler for func AP       */
   char fil_vacant_flag;   /* filler for func AP       */
   char fil_irreg_flag;    /* filler for func AP       */
   char fil_mh_ri_flag;    /* filler for func AP       */
   char fil_adr_range_overflow;/* filler for func AP   */
   char fil_stroll_key[18];/* fillers for func AP      */
   char filler04;
   char res_internal_use;  /* Reserved for Internal Use*/
```

```
   char bld_id[7];         /* Building Ident. Number   */
                           /* (BIN) of Input Address of*/
                           /* Existing Building,       */
   char condo_flag;        /* Condominium Flag         */
   char filler05;          /* Future Use               */
   char condo_id[4];       /* RPAD Condo Id Number     */
   char filler_unit_id[7]; /* Condo Unit Id Nbr-Not Impl*/
   BBL  condo_bill_bbl;    /* Condo Billing BBL        */
   char filler06;          /* Reserved for Tax Lot Ver */
   char fil_condo_scc;     /* filler for func AP       */
   BBL  condo_lo_bbl;      /* Low BBL of Condo         */
   char filler07;          /* Reserved for Tax Lot Ver */
   BBL  condo_hi_bbl;      /* High BBL of Condo        */
   char filler08;          /* Reserved for Tax Lot Ver */
   char filler09[15];
   char co_op_nbr[4];      /* Co-op Number             */
   char fil_sanborn[8];    /* fillers for func AP      */
   char fil_business_area[5];  /* fillers for func AP  */
   char fil_tax_map_nbr[5];    /* fillers for func AP  */
   char filler10[4];
   char filler11[3];
   char latitude[9];       /* Latitude calc from X-Y   */
   char longitude[11];     /* Longitude calc from X-Y  */
   char coord[2][7];       /* 1 = X coordinate from AP */
                           /* 2 = Y coordinate from AP */
   char fil_bid_id[6];          /* fillers for func AP */
   char fil_TPAD_bin_status;    /* fillers for func AP */
   char fil_TPAD_new_bin[7];    /* fillers for func AP */
   char fil_TPAD_new_bin_status;/* filler for func AP  */
   char fil_TPAD_conflict_flag; /* filler for func AP  */
   char ap_id[9];               /* Address Point Id    */
   char int_use[8];             /* Internal Use        */
   char reason_code;            /* Reason Code              */
   char reason_code_qual;       /* Reason Code Qualifier    */
   char warn_code[2];           /* Warning Return Code      */
   char ret_code[2];            /* GeoSupport Return Code   */
   char filler14[108];
   char nbr_addr[4];            /* Nbr of Addr = 0001  */

   ADDR_RANGE_APX addr_range_apx[21];
} C_WA2_FAPX;

 /*********************************************************************/
 /*                                                                   */
 /*       Platform-Independent Work Area 2 for Function 2             */
```

```
/*                                                                  */
/*******************************************************************/

typedef struct { char filler01[21];
                 char rep_cnt;           /* Intersection Replication */
                                         /* Counter*/
                 char lgc[2][2];         /* Preferred LGCs           */
                 St_list inter;          /* Number of Intersecting St*/
                                         /* B5SCs of Intersection St */
                 char Dup_comp;          /* Duplicate compass Directn*/
                 char atomic_polygon[3]; /* Atomic Polygon added V131*/
                 char filler02[2];
                 char LION_node_nbr[7];  /* LION Node Number         */
                 char coord[3][7];       /* 1 = X coordinate,        */
                                         /* 2 = Y coordinate,        */
                                         /* 3 = Z coordinate, Not Imp*/
                 SANBORN San[2];         /* Sanborn Information      */
                 char mh_ri_flag;        /* Marble Hill/Rikers Island*/
                 char DOT_slca;          /* DOT St Lght Contractr Are*/
                 char com_dist[3];       /* Community District       */
                 char zip_code[5];       /* Zip code for st segment  */
                 char health_area[4];    /* Health Area        */
                 char police_boro_com;   /* Police Patrol Boro Commnd*/
                 char police_pre[3];     /* Police Precinct          */
                 char fire_sector[2];    /* Fire Sector              */
                 char fire_bat[2];       /* Fire Battalion           */
                 char fire_co_type;      /* Fire Company Type        */
                 char fire_co_nbr[3];    /* Fire Company Number      */
                 char com_schl_dist[2];  /* Community School District*/
                 char cen_tract_10[6];   /* 2010 Census Tract        */
                 char cen_tract_90[6];   /* 1990 Census Tract        */
                 char level_codes [10];  /* Level codes              */
                 char police_pat_boro[2];/* Police Patrol Borough    */
         //      char filler_indv[2];    /*                          */
         //      char instruc_div [2];   /* Instructional Division   */
                 char ad[2];             /* Assembly District        */
                 char congress_dist[2];  /* Congressional District   */
                 char state_sen_dist[2]; /* State Senatorial District*/
                 char civil_court[2];    /* Civil Court District     */
                 char city_council[2];   /* City Council District    */
                 char cd_eligible;       /* CD Eligibility           */
                 char dup_intersect_distance[5];  /*Distance in Feet */
                                         /*Betwn Duplicate Intersects*/
                                         /* not implemented */
                 char cen_tract_2000[6]; /* 2000 Census Tract        */
```

```
                char health_cen_dist[2];/* Health Cent Distr*/
                char sanit_dist[3];     /* Sanitation District      */
                char sanit_sub_sect[2]; /* Sanit Collect Scheduling */
                                        /* Section and Subsection   */
                char filler03[12];
              } C_WA2_F2;

 /*******************************************************************/
 /*                                                                 */
 /*   Platform-Independent Work Area 2 for Function 2W              */
 /*******************************************************************/
typedef struct {                        /* Fn 2 - 200 Bytes         */
  C_WA2_F2 cwa2f2;                      /* Start with Fn 2 WA2      */
  char filler04[22];                    /* Fields used for Grid gen */
  char lgcs_first_intersct[4][2];       /* Up to 4 LGC's for 1st    */
                                        /* intersecting street;     */
  char lgcs_second_intersct[4][2];      /* Up to 4 LGC's for 2nd    */
                                        /* intersecting street;     */
  char turn_restricts[10];              /* Up to 10 Turn restrictns */
  char pref_lgc_list[5][2];             /* Preferd LGCs for Str list*/
  char true_rep_cnt[2];                 /* True Int Replication Cntr*/
  char dup_node_list[20][7];       /* 140 *Node list for dup str code*/
  char b7sc_list[20][5][4][8];     /* 3200 *B7SC lists for Node list */
  char reason_code;                     /* Reason Code              */
  char reason_code_qual;                /* future use               */
  char warn_code[2];                    /* Warning Return Code      */
  char ret_code[2];                     /* GeoSupport Return Code   */
  char latitude[9];                     /* Latitude calc from X-Y   */
  char longitude[11];                   /* Longitude calc from X-Y  */
  char filler8[374];                    /* Future Use               */
} C_WA2_F2W, *PC_WA2_F2W;               /* Fn 2W with filler        */
 /*******************************************************************/
 /*                                                                 */
 /*        Platform-Independent Work Area 2 for Function 3          */
 /*                                                                 */
 /*******************************************************************/

typedef struct { char filler01[21];
                char dup_key_flag;      /* Duplicate Key Flag or    */
                                        /* Continuous Parity Flag   */
                char loc_stat_seg;      /* Locational Status of Seg */
                char cnty_bnd_ind;      /* County Boundary Indicat  */
                char lgc[3][2];         /* Preferred LGCs           */
                St_list st[2];          /* 1=Low and 2=High         */
                                        /* Nbr of cross sts at low  */
```

```
                                        /* house nbr end of street  */
                                        /* B5SCs of lo end X sts    */
                char x_street_reversal_flag; /* X St Reversal Flag  */
                LION key;               /* LION Key                 */
                char genr_flag;         /* Generated Record Flag    */
                char seg_len[5];        /* Segment Length in Feet   */
                char seg_azm[3];        /* Segment Azimuth          */
                char seg_orient;        /* Segment Orientation      */
                char mh_ri_flag;        /* Marble Hill/Rikers Island*/
                                        /* Alternative Boro flag    */
                char from_node[7];      /* From node                */
                char to_node[7];        /* To node                  */
                char sanit_snow_priority;/* Sanitation Street Snow  */
                                        /* Priority (P,S,T,V)       */
                char filler02[4];       /* Future use               */
                char seg_id[7];         /* Segment Identifier       */
                char DOT_slca;          /* DOT St Lght Contractr Are*/
                char curve_flag;        /* Curve Flag               */
                char dog_leg;           /* Dog leg flag             */
                char feature_type;      /* Feature Type Code        */
                char segmenttypecode;   /* Segment Type Code        */
                char coincident_seg_cnt; /* Coincident Segment      */
                                        /*    Counter               */
                char filler03[4];
                SEGSIDE side[2];        /* 1 = Left Side of street  */
                                        /* 2 = Right Side of street */
              } C_WA2_F3;

typedef struct { C_WA2_F3 cwa2f3;
                char filler1[6];        /* Future use              */
                char seg_cnt[4];        /* Number of Segments      */
                char segments[70][7];   /* Segment Ids             */
              } C_WA2_F3_AUXSEG;
 /*******************************************************************/
 /*                                                                 */
 /*      Platform-Independent Work Area 2 for Function 3 EXTENDED   */
 /*                                                                 */
 /*******************************************************************/

typedef struct {                        /*  Data from CSCL added    */
  C_WA2_F3 cwa2f3;
  char lgc_list[4][2];                  /* List of LGC's            */
  char from_lgcs[4][2];                 /* List of from LGC's       */
  char to_lgcs[4][2];                   /* List of to LGC's         */
  char left_hcd[2];                     /* Left Health Center   */
```

```
                                    /* District                 */
char right_hcd[2];                  /* Right Health Center  */
                                    /* District                 */
char filler_csd;                    /*                          */
char traffic_dir;                   /* Traffic Direction        */
char roadway_type[2];               /*                          */
char physical_id[7];                /*                          */
char generic_id[7];                 /*                          */
char filler03[7];                   /* DCP internal use         */
char filler04[7];                   /* DCP internal use         */
char street_status;                 /*                          */
char str_width[3];                  /* Street Width             */
char str_width_irr;                 /* Irregular Width Y or N   */
char bike_lane;                     /*                          */
char fcc[2];                        /* Federal Classification Cd*/
char row_type;                      /*                          */
char lgc5[2];                       /*                          */
char lgc6[2];                       /*                          */
char lgc7[2];                       /*                          */
char lgc8[2];                       /*                          */
char lgc9[2];                       /*                          */
char legacy_id[7];                  /*                          */
char nta_name_left[75];             /* Neighborhood Tabulation  */
                                    /* Area Name (Left)         */
char nta_name_right[75];            /* Neighborhood Tabulation  */
                                    /* Area Name (Right)        */
char from_coord[2][7];              /* 1 = X Coordinate         */
                                    /* 2 = Y Coordinate         */
char to_coord[2][7];                /* 1 = X Coordinate         */
                                    /* 2 = Y Coordinate         */
char from_latitude[9];              /*Latitude of from intersct.*/
char from_longitude[11];            /*Longitude of from intersct*/
char to_latitude[9];                /*Latitude of to intersect. */
char to_longitude[11];              /*Longitude of to intersect.*/
char left_blockface_id[10];         //NEW location of blockface id
char right_blockface_id[10];
char nbr_travel_lanes[2];           /* nbr of traveling lanes   */
char nbr_park_lanes[2];             /* nbr of parking lanes     */
char nbr_total_lanes[2];            /* total nbr of lanes       */
char bike_lane_2[2];                /*Bike Lane has 2 bytes     */
                                    /* numeric value            */
char str_width_max[3];              /*Street width maximum      */
char bike_traffic_dir[2];          //V17.1 Bike Traffic Direction
char speed_limit[2];                //V17.4 Speed Limit
char left_puma_code[5];             // PUMA Code (left) V18.1
```

```
  char right_puma_code[5];              // PUMA Code (right) V18.1
  char filler05[201];                   // V18.1
//char filler05[211];                   // V17.4
//char filler05[213];                   // V17.1
} C_WA2_F3X;

typedef struct {                        /* Fn 3 Extended with       */
  C_WA2_F3X cwa2f3x;                    /* Auxilary Segments        */
  char filler1[6];                       /* Future use              */
  char seg_cnt[4];                       /* Number of Segments      */
  char segments[70][7];                  /* Segment Ids             */
} C_WA2_F3X_AUXSEG;                     /* Fn 3X with AUXSEGID      */


 /*******************************************************************/
 /*                                                                 */
 /*        Platform-Independent Work Area 2 for Function 3C         */
 /*                                                                 */
 /*******************************************************************/

typedef struct { char filler01[21];
                 char dup_key_flag;     /* Duplicate Key Flag or    */
                                        /* Continuous Parity Flag   */
                 char loc_stat_seg;     /* Locational Status of Seg */
                 char cnty_bnd_ind;     /* County Boundary Indicat  */
                 char lgc[3][2];        /* Preferred LGCs           */
                 St_list st[2];         /* 1=Low and 2=High         */
                                        /* Nbr of cross sts at low  */
                                        /* house nbr end of street  */
                                        /* B5SCs of lo end Cross sts*/
                 char x_street_reversal_flag; /* X St Reversal Flag  */
                 LION key;              /* LION key                 */
                 char genr_flag;        /* Generated Record Flag    */
                 char seg_len[5];       /* Segment Length in Feet   */
                 char seg_azm[3];       /* Segment Azimuth          */
                 char seg_orient;       /* Segment Orientation      */
                 char mh_ri_flag;       /* Marble Hill/Rikers Island*/
                                        /* Alternative Boro flag    */
                 char from_node[7];     /* From node                */
                 char to_node[7];       /* To Node                  */
                 char sanit_snow_priority;/* Sanitation Street Snow  */
                                         /* Priority (P,S,T,V)      */
                 char filler02[4];      /* Future use               */
                 char seg_id  [7];      /* Segment Identifier       */
                 char DOT_slca;         /* DOT St Lght Contractr Are*/
```

```
                char sos_ind;           /* Side of Street Indicator */
                char curve_flag;        /* Curve Flag               */
                char feature_type;      /* Feature Type Code        */
                char segmenttypecode;   /* Segment Type Code        */
                char coincident_seg_cnt; /* Coincident Segment      */
                                         /*    Counter              */
                char filler03[4];
                SEGSIDE req;           /* Geographic Information for*/
            } C_WA2_F3C;

typedef struct { C_WA2_F3C cwa2f3c;
                char filler1[6];        /* Future use              */
                char seg_cnt[4];        /* Number of Segments      */
                char segments[70][7];   /* Segment ids             */
             } C_WA2_F3C_AUXSEG;

 /*********************************************************************/
 /*                                                                   */
 /*      Platform-Independent Work Area 2 for Function 3C EXTENDED    */
 /*                                                                   */
 /*********************************************************************/
typedef struct {                        /* Data from CSCL added     */
  C_WA2_F3C cwa2f3c;
  char lgc_list[4][2];                  /* List of LGC's            */
  char from_lgcs[4][2];                 /* List of from LGC's       */
  char to_lgcs[4][2];                   /* List of to LGC's         */
  char left_hcd[2];                     /* Left Health Center Distr */
  char right_hcd[2];                    /* Right Health Center Distr*/
  char fill_csd;                        /* Filler                   */
  char traffic_dir;                     /* Traffic Direction        */
  char roadway_type[2];                 /*                          */
  char physical_id[7];                  /*                          */
  char generic_id[7];                   /*                          */
  char filler03[7];                     /* DCP internal use         */
  char filler04[7];                     /* DCP internal use         */
  char street_status;                   /*                          */
  char str_width[3];                    /* Street Width             */
  char str_width_irr;                   /* Irregular Width Y or N   */
  char bike_lane;                       /*                          */
  char fcc[2];                          /* Federal Classification Cd*/
  char row_type;                        /*                          */
  char lgc5[2];                         /*                          */
  char lgc6[2];                         /*                          */
  char lgc7[2];                         /*                          */
  char lgc8[2];                         /*                          */
```

```
  char lgc9[2];                          /*                          */
  char legacy_id[7];                     /*                          */
  char nta_name[75];                     /* Neighborhood Tabulation  */
                                         /* Area Name                */
  char from_coord[2][7];                 /* 1 = X Coordinate         */
                                         /* 2 = Y Coordinate         */
  char to_coord[2][7];                   /* 1 = X Coordinate         */
                                         /* 2 = Y Coordinate         */
  char from_latitude[9];                /* Latitude of from intersct.*/
  char from_longitude[11];              /* Longitude of from intersct*/
  char to_latitude[9];                  /* Latitude of to intersct.  */
  char to_longitude[11];                /* Longitude of to intersct. */
  char blockface_id[10];                /* NEW location of this field*/
                                        /* because of length changed */
  char nbr_travel_lanes[2];              /* nbr of traveling lanes   */
  char nbr_park_lanes[2];                /* nbr of parking lanes     */
  char nbr_total_lanes[2];               /* total nbr of lanes       */
  char bike_lane_2[2];                   /*Bike Lane has 2 bytes     */
                                         /* numeric value            */
  char str_width_max[3];                 /*street width maximum      */
  char bike_traffic_dir[2];              //V17.1 Bike Traffic Direction
  char speed_limit[2];                   //V17.4 Speed Limit
  char puma_code[5];                     // PUMA Code V18.1
  char filler05[291];                    // V18.1
//char filler05[296];                    // V17.4
//char filler05[298];                    // V17.1
} C_WA2_F3CX;

typedef struct {                         /* Fn 3C Extended with      */
  C_WA2_F3CX cwa2f3cx;                   /* Auxilary Segments        */
  char filler1[6];                       /* Future use              */
  char seg_cnt[4];                       /* Number of Segments      */
  char segments[70][7];                  /* Segment Ids             */
} C_WA2_F3CX_AUXSEG;                     /* Fn 3CX with AUXSEGID     */

 /*********************************************************************/
 /*                                                                   */
 /*        Platform-Independent Work Area 2 for Function 3S           */
 /*                                                                   */
 /*********************************************************************/

typedef struct { char filler01[21];
                 char nbr_x_str[3];      /* Nbr of Cross sts in list */
                 CROSS_STRS cross_strs[350];/* Cross Street structure*/
               } C_WA2_F3S;
```

```
#ifdef __cplusplus
       }
#endif
#endif
```

NATURAL LDAs (COW)

GEOLP1 COPY File

```
*    USER PROGRAMS MUST RESET GEOLP1        BEFORE PRIMING WORKAREA 1
   1 GEOLP1                                        /* LRECL=1200
*    THE FIELD P1NAT IS USED AS A        PARAMETER TO CALL GEOSUPPORT        RT
   2 P1NAT                             A          2
R  2 P1NAT
*  * * * *   INPUT FIELDS    * * * *  *  * * * * * /* WORK AREA 1 FOR
*  *                                               /* ALL FUNCTIONS
   3 PIWA1-IN-FUNCTION-CODE            A          2
R  3 PIWA1-IN-FUNCTION-CODE
   4 PIWA1-IN-FUNCTION-1               A          1
   4 PIWA1-IN-FUNCTION-2               A          1
   2 PIWA1-IN-HOUSENUM-DISPLAY         A         16
   2 PIWA1-IN-HOUSENUM-SORT            A         11
   2 PIWA1-IN-LOW-HOUSENUM-DISPLAY     A         16
   2 PIWA1-IN-LOW-HOUSENUM-SORT        A         11
   2 PIWA1-IN-BORO-1                   A          1
   2 PIWA1-IN-10SC-1                   A         10
   2 PIWA1-IN-STREET-1                 A         32
   2 PIWA1-IN-BORO-2                   A          1
   2 PIWA1-IN-10SC-2                   A         10
   2 PIWA1-IN-STREET-2                 A         32
   2 PIWA1-IN-BORO-3                   A          1
   2 PIWA1-IN-10SC-3                   A         10
   2 PIWA1-IN-STREET-3                 A         32
   2 PIWA1-IN-BBL                      A         10 /* 3 LEVEL 3 ITEMS
R  2 PIWA1-IN-BBL
   3 PIWA1-IN-BBL-BORO                 A          1
   3 PIWA1-IN-BLOCK                    A          5
   3 PIWA1-IN-LOT                      A          4
   2 PIWA1-IN-LOT-VERSION              A          1 /* NA
   2 PIWA1-IN-BIN                      A          7
   2 PIWA1-IN-COMPASS                  A          1
   2 PIWA1-IN-COMPASS2                 A          1
   2 PIWA1-IN-NODE                     A          7
```

```
   2 PIWA1-IN-PLATFORM-INDICATOR      A          1
   2 PIWA1-IN-ZIPCODE                 A          5
   2 PIWA1-IN-UNIT                    A         14 /* V16.4 ADDITION
   2 FILLER-200                       A         82 /* V16.4 ALTERATION
*  2 FILLER-200                       A         96
   2 PIWA1-IN-LONG-WORKAREA2-FLAG     A          1 /* L=LONG WA - 1A/BL(1200)
   2 PIWA1-IN-HSE-NBR-JUSTIFY         A          1
   2 PIWA1-IN-HNL                     A          2 /* HN LENGTH
   2 PIWA1-IN-HSE-OVER-FLAG           A          1 /* HN OVERRIDE *,$,' '
   2 PIWA1-IN-SNL                     A          2
   2 PIWA1-IN-SN-NORM-FORMAT          A          1 /* C=COMPACT,S OR ' '=SORTT
   2 PIWA1-IN-EXPANDED-FORMAT         A          1
   2 PIWA1-IN-ROADBED-REQ-SWITCH      A          1
   2 PIWA1-IN-INTERNAL-USE-LEGACY     A          1 /* RESERVED FOR GSS USE
   2 PIWA1-IN-SEGAUX-SWITCH           A          1
   2 PIWA1-IN-BROWSE-FLAG             A          1
   2 PIWA1-IN-REAL-STREET-ONLY        A          1 /* FN 3S
   2 PIWA1-IN-TPAD-SWITCH             A          1 /* FN 1A
   2 PIWA1-IN-MODE-SWITCH             A          1
   2 PIWA1-IN-WTO-SWITCH              A          1
   2 FILLER-400                       A         29
*  * * * *   OUTPUT FIELDS   * * * *  *  * * * * *
   2 PIWA1-OUT-BORONAME               A          9
   2 PIWA1-OUT-HOUSENUM-DISPLAY       A         16
   2 PIWA1-OUT-HOUSENUM-SORT          A         11
   2 PIWA1-OUT-B10SC-1                A         11
   2 PIWA1-OUT-STREET-1               A         32
   2 PIWA1-OUT-B10SC-2                A         11
   2 PIWA1-OUT-STREET-2               A         32
   2 PIWA1-OUT-B10SC-3                A         11
   2 PIWA1-OUT-STREET-3               A         32
   2 PIWA1-OUT-BBL                    A         10 /* 3 LEVEL 3 ITEMS
R  2 PIWA1-OUT-BBL
   3 PIWA1-OUT-BBL-BORO               A          1
   3 PIWA1-OUT-BLOCK                  A          5
   3 PIWA1-OUT-LOT                    A          4
   2 PIWA1-OUT-LOT-VERSION            A          1 /* FOR FUTRUE LOT VERSION #
   2 PIWA1-OUT-LOW-HOUSENUM-DISPLAY   A         16
   2 PIWA1-OUT-LOW-HOUSENUM-SORT      A         11
   2 PIWA1-OUT-BIN                    A          7
   2 PIWA1-OUT-STREET-ATTR            A          1 (1:3) /* RES FOR GSS
   2 PIWA1-OUT-REASON-CODE-2          A          1 /* FN 1B
   2 PIWA1-OUT-REASON-CODE-QUAL-2     A          1 /*TPAD 2ND REASON CODE
*  *                                               /*QUALIFIER
   2 PIWA1-OUT-WARNING-CODE-2         A          2 /* FN 1B
```

```
   2 PIWA1-OUT-RETURN-CODE-2          A          2 /* FN 1B
   2 PIWA1-OUT-ERROR-MESSAGE-2        A         80 /* FN 1B
   2 PIWA1-OUT-NODE                   A          7
   2 PIWA1-OUT-UNIT-SORT              A         14 /* V16.4 ADDITION
R  2 PIWA1-OUT-UNIT-SORT
   3 PIWA1-OUT-UNIT-TYPE              A          4 /* V16.4 ADDITION
   3 PIWA1-OUT-UNIT-ID                A         10 /* V16.4 ADDITION
   2 PIWA1-OUT-UNIT-DISP              A         14 /* V16.4 ADDITION
   2 FILLER-550                       A         11 /* V16.4 ALTERATION
*  2 FILLER-550                       A         39
   2 FILLER-555                       A          6 /* NIN, NYI
   2 PIWA1-OUT-SND-ATTR               A          1 /* RES FOR GSS
   2 PIWA1-OUT-REASON-CODE            A          1
   2 PIWA1-OUT-REASON-CODE-QUAL       A          1 /*TAPAD REASON CODE
*  *                                               /*QUALIFIER
   2 PIWA1-OUT-WARNING-CODE           A          2
   2 PIWA1-OUT-RETURN-CODE            A          2
   2 PIWA1-OUT-ERROR-MESSAGE          A         80
   2 PIWA1-OUT-NUM-SIMILAR-STRS       A          2
   2 PIWA1-OUT-SIMILAR-B7SC           A          8 (1:10)
   2 PIWA1-OUT-SIMILAR-NAMES          A         32 (1:10)
```

GEOLP2 COPY File

```
0010      1 GEOLP2                                                          DSR
0744
0020   *    THE FIELD P2NAT IS USED AS A        PARAMETER TO CALL GEOSUPPORT FOR ALLLL     C
0030   *        FUNCTIONS THAT ARE REDEFINED           ON GEOLP2                          C
0040   *  * MAXIMUM LENGTH 2W - 4000 BYTES                                                 C
0050      2 P2NAT                            A         21                                  DK
0746
0060   R  2 P2NAT                                                                          DRR
0747
0070   *  *  BEGINNING OF FUNCTION 1 LAYOUT  *       **** *******                         C
0080      3 PIWA2-FN1-ACCESS-KEY             A         21                                  DFR
0748
0090      2 PIWA2-FN1-CONT-PARITY            A          1 /* (OR DUP ADDR IND)            DK
0749
0100      2 PIWA2-FN1-LOW-HOUSENUM           A         11 /* SORT FORMAT                  DK
0750
0110      2 PIWA2-FN1-HI-HOUSENUM            A         11 /* SORT FORMAT                  DK
0751
0120      2 PIWA2-FN1-PREFERRED-LGC          A          2                                  DK
0752
```

```
0130      2 PIWA2-FN1-NUM-X-ST-LOW-END       A          1                                DK
0753
0140      2 PIWA2-FN1-LOW-B5SC               A          6 (1:5) /* 30-BYTES               DK
I1   0754     M
0150      2 PIWA2-FN1-NUM-X-ST-HI-END        A          1                                DK
0755
0160      2 PIWA2-FN1-HI-B5SC                A          6 (1:5) /* 30-BYTES               DK
I1   0756     M
0170      2 PIWA2-FN1-LIONKEY                A         10                                DK
0757
0180   R  2 PIWA2-FN1-LIONKEY                                                            DRR
0758
0190      3 PIWA2-FN1-LION-BORO              A          1                                DFR
0759
0200      3 PIWA2-FN1-LION-FACECODE          A          4                                DFR
0760
0210      3 PIWA2-FN1-LION-SEQ               A          5                                DFR
0761
0220      2 PIWA2-FN1-SPECIAL-ADDR-FLAG      A          1                                DK
0762
0230      2 PIWA2-FN1-SIDE-OF-STR            A          1                                DK
0763
0240      2 PIWA2-FN1-SEG-LEN                A          5                                DK
0764
0250      2 PIWA2-FN1-X-COORD                A          7                                DK
0765
0260      2 PIWA2-FN1-Y-COORD                A          7                                DK
0766
0270      2 FILLER-100                       A          7 /* FOR ZCOORD                  DK
0767
0280      2 FILLER-200                       A          1 /* FOR GSS USE                 DK
0768
0290      2 PIWA2-FN1-MARBLE-RIKERS-FLAG     A          1                                DK
0769
0300      2 PIWA2-FN1-DOT-SLA                A          1                                DK
0770
0310      2 PIWA2-FN1-COM-DIST               A          3                                DK
0771
0320   R  2 PIWA2-FN1-COM-DIST                                                            DRR
0772
0330      3 PIWA2-FN1-COM-DIST-BORO          A          1                                DFR
0773
0340      3 PIWA2-FN1-COM-DIST-NUM           A          2                                DFR
0774
0350      2 PIWA2-FN1-ZIP                    A          5                                DK
```

```
0775
0360   *  *                                *       **** *****                          C
0370   *  *  THE FN1E FIELDS ARE VALID ONLY *       **** *****                          C
0380   *  *  FOR FUNCTION 1E, NOT FUNC 1.   *       **** *****                          C
0390      2 PIWA2-FN1E-ELECT-DIST           A          3                                DK
0776
0400      2 PIWA2-FN1E-ASSEM-DIST           A          2                                DK
0777
0410      2 PIWA2-FN1E-SPLIT-ED-FLAG        A          1                                DK
0778
0420      2 PIWA2-FN1E-CONG-DIST            A          2                                DK
0779
0430      2 PIWA2-FN1E-SENATE-DIST          A          2                                DK
0780
0440      2 PIWA2-FN1E-COURT-DIST           A          2                                DK
0781
0450      2 PIWA2-FN1E-COUNCIL-DIST         A          2                                DK
0782
0460   *  *                                *       **** *****                          C
0470      2 PIWA2-FN1-HEALTH-CENTER-DIST    A          2                                DK
0783
0480      2 PIWA2-FN1-HEALTH-AREA           A          4                                DK
0784
0490      2 PIWA2-FN1-SANI-DIST             A          3                                DK
0785
0500   R  2 PIWA2-FN1-SANI-DIST                                                         DRR
0786
0510      3 PIWA2-FN1-SANI-DIST-BORO        A          1                                DFR
0787
0520      3 PIWA2-FN1-SANI-DIST-NUM         A          2                                DFR
0788
0530      2 PIWA2-FN1-SANI-SUBSEC           A          2                                DK
0789
0540      2 PIWA2-FN1-SANI-REG              A          5                                DK
0790
0550      2 PIWA2-FN1-SANI-REC              A          3                                DK
0791
0560      2 PIWA2-FN1-POLICE-DIST           A          4                                DK
0792
0570   R  2 PIWA2-FN1-POLICE-DIST                                                       DRR
0793
0580      3 PIWA2-FN1-POL-PAT-BORO-CMD      A          1                                DFR
0794
0590      3 PIWA2-FN1-POL-PRECINCT          A          3                                DFR
0795
```

```
0600      2 PIWA2-FN1-FIRE-DIV              A          2                                DK
0796
0610      2 PIWA2-FN1-FIRE-BAT              A          2                                DK
0797
0620      2 PIWA2-FN1-FIRE-CO               A          4                                DK
0798
0630    R 2 PIWA2-FN1-FIRE-CO                                                           DRR
0799
0640      3 PIWA2-FN1-FIRE-CO-TYPE          A          1                                DFR
0800
0650      3 PIWA2-FN1-FIRE-CO-NUM           A          3                                DFR
0801
0660      2 PIWA2-FN1-SCHL-DIST-SPLIT-FLAG  A          1                                DK
0802
0670      2 PIWA2-FN1-SCHL-DIST             A          2                                DK
0803
0680      2 PIWA2-FN1-DYN-BLK               A          3                                DK
0804
0690      2 PIWA2-FN1-POLICE-PAT-BORO       A          2                                DK
0805
0700      2 PIWA2-FN1-FEATURE-TYPE          A          1                                DK
0806
0710      2 PIWA2-FN1-SEGMENT-TYPE          A          1                                DK
0807
0720      2 PIWA2-FN1-ALX                   A          1                                DK
0808
0730      2 PIWA2-FN1-COINCIDENT-SEG-CTR    A          1                                DK
0809
0740      2 FILLER-290                      A          3                                DK
0810
0750      2 PIWA2-FN1-1990-CENSUS-TRACT     A          6                                DK
0811
0760      2 PIWA2-FN1-2010-CENSUS-TRACT     A          6                                DK
0812
0770      2 PIWA2-FN1-2010-CENSUS-BLOCK     A          4                                DK
0813
0780      2 PIWA2-FN1-2010-CENSUS-BLOCK-SUF A          1 /* NA                         DK
0814
0790      2 PIWA2-FN1-2000-CENS-TRACT       A          6                                DK
0815
0800      2 PIWA2-FN1-2000-CENS-BLOCK       A          4                                DK
0816
0810      2 PIWA2-FN1-2000-CENS-BLOCK-SUF   A          1 /* NA                         DK
0817
0820      2 PIWA2-FN1-NTA                   A          4                                DK
```

```
0818
0830      2 PIWA2-FN1-SANIT-SNOW-PRIORITY    A          1                                DK
0819
0840      2 PIWA2-FN1-SANIT-ORGANICS         A          5                                DK
0820
0850      2 PIWA2-FN1-SANIT-BULK-PICK-UP     A          5 /* V16.4 ADDITION               DK
0821
0860    *  2 PIWA2-FN1-SANIT-RESERVED         A          5 /*FOR POSSIBLE FUTURE USE        CK
0821
0870      2 PIWA2-FN1-HURRICANE-ZONE         A          2 /*OEM HURRICANE EVAC ZONE        DK
0822
0880      2 FILLER-300                       A         11                                DK
0823
0890      2 PIWA2-FN1-UHNS                   A         11 /* UNDERLYING HNS               DK
0824
0900      2 PIWA2-FN1-REAL-B7SC              A          8                                DK
0825
0910      2 PIWA2-FN1-SEGMENT-ID             A          7                                DK
0826
0920      2 PIWA2-FN1-CURVE-FLAG             A          1                                DK
0827
0930      2 PIWA2-FN1-PSEUDO-FILLER          A       3700 /*MAX RECORD 2W IS 4000         DK
0828
0940    *  *  END OF FUNCTION 1 LAYOUT        *       **** *******                        C
0950    *  - ------------------------------- -       ---- ------------------------------- C
0960    *  *  BEGINNING OF FUNCTION 2                                                     C
0970    *  *           & FUNCTION 2C LAYOUT   * ********** *******                        C
0980    R  1 GEOLP2                                                                       DRR
0829
0990      2 PIWA2-FN2-ACCESS-KEY             A         21 /* FOR FUNCTIONS 2 & 2C         DFR
0830
1000      2 PIWA2-FN2-DUP-INTERSECT-FLAG     A          1                                DFR
0831
1010      2 PIWA2-FN2-PREFERRED-LGC1         A          2                                DFR
0832
1020      2 PIWA2-FN2-PREFERRED-LGC2         A          2                                DFR
0833
1030      2 PIWA2-FN2-NUM-OF-INTERSECTS      A          1                                DFR
0834
1040      2 PIWA2-FN2-INTERSECT-B5SC         A          6 (1:5) /* 30-BYTES
DFRI1   0835     M
1050      2 PIWA2-FN2-COMP-DIR               A          1                                DFR
0836
1060      2 PIWA2-FN2-ATOMIC-POLYGON         A          3                                DFR
0837
```

```
1070      2 FILLER-350                      A          2                                DFR
0838
1080      2 PIWA2-FN2-NODE-NUM              A          7                                DFR
0839
1090      2 PIWA2-FN2-X-COORD               A          7                                DFR
0840
1100      2 PIWA2-FN2-Y-COORD               A          7                                DFR
0841
1110      2 FILLER-400                      A          7 /* FOR ZCOORD                  DFR
0842
1120      2 PIWA2-FN2-SANBORN1              A          8                                DFR
0843
1130   R  2 PIWA2-FN2-SANBORN1                                                          DRR
0844
1140      3 PIWA2-FN2-SANBORN1-BORO         A          1                                DFR
0845
1150      3 PIWA2-FN2-SANBORN1-VOL          A          3                                DFR
0846
1160      3 PIWA2-FN2-SANBORN1-PAGE         A          4                                DFR
0847
1170      2 PIWA2-FN2-SANBORN2              A          8                                DFR
0848
1180   R  2 PIWA2-FN2-SANBORN2                                                          DRR
0849
1190      3 PIWA2-FN2-SANBORN2-BORO         A          1                                DFR
0850
1200      3 PIWA2-FN2-SANBORN2-VOL          A          3                                DFR
0851
1210      3 PIWA2-FN2-SANBORN2-PAGE         A          4                                DFR
0852
1220      2 PIWA2-FN2-MARBLE-RIKERS-FLAG    A          1                                DFR
0853
1230      2 PIWA2-FN2-DOT-SLA               A          1                                DFR
0854
1240      2 PIWA2-FN2-COM-DIST              A          3                                DFR
0855
1250   R  2 PIWA2-FN2-COM-DIST                                                          DRR
0856
1260      3 PIWA2-FN2-COM-DIST-BORO         A          1                                DFR
0857
1270      3 PIWA2-FN2-COM-DIST-NUM          A          2                                DFR
0858
1280      2 PIWA2-FN2-ZIP                   A          5                                DFR
0859
1290      2 PIWA2-FN2-HEALTH-AREA           A          4                                DFR
```

```
0860
1300      2 PIWA2-FN2-POLICE-DIST            A          4                                DFR
0861
1310   R  2 PIWA2-FN2-POLICE-DIST                                                         DRR
0862
1320      3 PIWA2-FN2-POL-PAT-BORO-CMD       A          1                                DFR
0863
1330      3 PIWA2-FN2-POL-PRECINCT           A          3                                DFR
0864
1340      2 PIWA2-FN2-FIRE-DIV               A          2                                DFR
0865
1350      2 PIWA2-FN2-FIRE-BAT               A          2                                DFR
0866
1360      2 PIWA2-FN2-FIRE-CO                A          4                                DFR
0867
1370   R  2 PIWA2-FN2-FIRE-CO                                                             DRR
0868
1380      3 PIWA2-FN2-FIRE-CO-TYPE           A          1                                DFR
0869
1390      3 PIWA2-FN2-FIRE-CO-NUM            A          3                                DFR
0870
1400      2 PIWA2-FN2-SCHL-DIST              A          2                                DFR
0871
1410      2 PIWA2-FN2-2010-CENSUS-TRACT      A          6                                DFR
0872
1420      2 PIWA2-FN2-1990-CENSUS-TRACT      A          6                                DFR
0873
1430      2 PIWA2-FN2-LEVEL-CODE-TBL         A         10                                DFR
0874
1440   R  2 PIWA2-FN2-LEVEL-CODE-TBL                                                      DRR
0875
1450      3 PIWA2-FN2-LEVEL-CODE             A          1 (5,2) /* 10-BYTES
DFRI2   0876     M
1460      2 PIWA2-FN2-POLICE-PAT-BORO        A          2                                DFR
0877
1470      2 PIWA2-FN2-ASSEM-DIST             A          2                                DFR
0878
1480      2 PIWA2-FN2-CONG-DIST              A          2                                DFR
0879
1490      2 PIWA2-FN2-SENATE-DIST            A          2                                DFR
0880
1500      2 PIWA2-FN2-COURT-DIST             A          2                                DFR
0881
1510      2 PIWA2-FN2-COUNCIL-DIST           A          2                                DFR
0882
```

```
1520      2 PIWA2-FN2-CD-ELIGIBLE            A          1                                DFR
0883
1530      2 PIWA2-FN2-DUP-INTERSECT-DIST     A          5                                DFR
0884
1540      2 PIWA2-FN2-2000-CENS-TRACT        A          6                                DFR
0885
1550      2 PIWA2-FN2-HEALTH-CENTER-DIST     A          2                                DFR
0886
1560      2 PIWA2-FN2-SANITATION-DIST        A          3                                DFR
0887
1570      2 PIWA2-FN2-SANITATION-SUBSEC      A          2                                DFR
0888
1580      2 FILLER-500                       A         12                                DFR
0889
1590    *  2 PIWA2-FN2-PSEUDO-FILLER          A       3800                                CFR
0789
1600    *  *  END OF FUNCTION 2              * ********** ********                       C
1610    *  *       & FUNCTION 2C LAYOUT       * ********** ********                       C
1620    *  * -------------------------------- - ---------- -----------------               C
1630    *  *  BEGINNING OF FUNCTION 2W        * ********** *******                        C
1640    R  1 GEOLP2                                                                       DRR
0890
1650      2 PIWA2-FN2W-ACCESS-KEY            A         21 /* FOR FUNCTION 2W               DFR
0891
1660      2 PIWA2-FN2W-DUP-INTERSECT-FLAG    A          1                                DFR
0892
1670      2 PIWA2-FN2W-PREFERRED-LGC1        A          2                                DFR
0893
1680      2 PIWA2-FN2W-PREFERRED-LGC2        A          2                                DFR
0894
1690      2 PIWA2-FN2W-NUM-OF-INTERSECTS     A          1                                DFR
0895
1700      2 PIWA2-FN2W-INTERSECT-B5SC        A          6 (1:5) /* 30-BYTES
DFRI1   0896     M
1710      2 PIWA2-FN2W-COMP-DIR              A          1                                DFR
0897
1720      2 PIWA2-FN2W-ATOMIC-POLYGON        A          3                                DFR
0898
1730      2 FILLER-350W                      A          2                                DFR
0899
1740      2 PIWA2-FN2W-NODE-NUM              A          7                                DFR
0900
1750      2 PIWA2-FN2W-X-COORD               A          7                                DFR
0901
1760      2 PIWA2-FN2W-Y-COORD               A          7                                DFR
```

```
0902
1770     2 FILLER-400W                     A          7 /* FOR ZCOORD                    DFR
0903
1780     2 PIWA2-FN2W-SANBORN1             A          8                                 DFR
0904
1790   R 2 PIWA2-FN2W-SANBORN1                                                           DRR
0905
1800     3 PIWA2-FN2W-SANBORN1-BORO        A          1                                 DFR
0906
1810     3 PIWA2-FN2W-SANBORN1-VOL         A          3                                 DFR
0907
1820     3 PIWA2-FN2W-SANBORN1-PAGE        A          4                                 DFR
0908
1830     2 PIWA2-FN2W-SANBORN2             A          8                                 DFR
0909
1840   R 2 PIWA2-FN2W-SANBORN2                                                           DRR
0910
1850     3 PIWA2-FN2W-SANBORN2-BORO        A          1                                 DFR
0911
1860     3 PIWA2-FN2W-SANBORN2-VOL         A          3                                 DFR
0912
1870     3 PIWA2-FN2W-SANBORN2-PAGE        A          4                                 DFR
0913
1880     2 PIWA2-FN2W-MARBLE-RIKERS-FLAG   A          1                                 DFR
0914
1890     2 PIWA2-FN2W-DOT-SLA              A          1                                 DFR
0915
1900     2 PIWA2-FN2W-COM-DIST             A          3                                 DFR
0916
1910   R 2 PIWA2-FN2W-COM-DIST                                                           DRR
0917
1920     3 PIWA2-FN2W-COM-DIST-BORO        A          1                                 DFR
0918
1930     3 PIWA2-FN2W-COM-DIST-NUM         A          2                                 DFR
0919
1940     2 PIWA2-FN2W-ZIP                  A          5                                 DFR
0920
1950     2 PIWA2-FN2W-HEALTH-AREA          A          4                                 DFR
0921
1960     2 PIWA2-FN2W-POLICE-DIST          A          4                                 DFR
0922
1970   R 2 PIWA2-FN2W-POLICE-DIST                                                        DRR
0923
1980     3 PIWA2-FN2W-POL-PAT-BORO-CMD     A          1                                 DFR
0924
```

```
1990      3 PIWA2-FN2W-POL-PRECINCT          A          3                                DFR
0925
2000      2 PIWA2-FN2W-FIRE-DIV              A          2                                DFR
0926
2010      2 PIWA2-FN2W-FIRE-BAT              A          2                                DFR
0927
2020      2 PIWA2-FN2W-FIRE-CO               A          4                                DFR
0928
2030   R  2 PIWA2-FN2W-FIRE-CO                                                           DRR
0929
2040      3 PIWA2-FN2W-FIRE-CO-TYPE          A          1                                DFR
0930
2050      3 PIWA2-FN2W-FIRE-CO-NUM           A          3                                DFR
0931
2060      2 PIWA2-FN2W-SCHL-DIST             A          2                                DFR
0932
2070      2 PIWA2-FN2W-2010-CENSUS-TRACT     A          6                                DFR
0933
2080      2 PIWA2-FN2W-1990-CENSUS-TRACT     A          6                                DFR
0934
2090      2 PIWA2-FN2W-LEVEL-CODE-TBL        A         10                                DFR
0935
2100   R  2 PIWA2-FN2W-LEVEL-CODE-TBL                                                    DRR
0936
2110      3 PIWA2-FN2W-LEVEL-CODE            A          1 (5,2) /* 10-BYTES
DFRI2   0937     M
2120      2 PIWA2-FN2W-POLICE-PAT-BORO       A          2                                DFR
0938
2130      2 PIWA2-FN2W-ASSEM-DIST            A          2                                DFR
0939
2140      2 PIWA2-FN2W-CONG-DIST             A          2                                DFR
0940
2150      2 PIWA2-FN2W-SENATE-DIST           A          2                                DFR
0941
2160      2 PIWA2-FN2W-COURT-DIST            A          2                                DFR
0942
2170      2 PIWA2-FN2W-COUNCIL-DIST          A          2                                DFR
0943
2180      2 PIWA2-FN2W-CD-ELIGIBLE           A          1                                DFR
0944
2190      2 PIWA2-FN2W-DUP-INTERSECT-DIST    A          5                                DFR
0945
2200      2 PIWA2-FN2W-2000-CENS-TRACT       A          6                                DFR
0946
2210      2 PIWA2-FN2W-HEALTH-CENTER-DIST    A          2                                DFR
```

```
0947
2220      2 PIWA2-FN2W-SANITATION-DIST       A          3                                DFR
0948
2230      2 PIWA2-FN2W-SANITATION-SUBSEC     A          2                                DFR
0949
2240      2 FILLER-500W                      A         12                                DFR
0950
2250      2 PIWA2-FN2W-FILLER-GRIDGEN        A         22 /*INTERNAL USE                  DFR
0951
2260      2 PIWA2-FN2W-LGCS-FIRST-INTERSCT   A          2 (1:4) /*UP TO 4 LGCS
DFRI1   0952     M
2270      2 PIWA2-FN2W-LGCS-SECOND-INTERSCT  A          2 (1:4) /*UP TO 4 LGCS
DFRI1   0953     M
2280      2 PIWA2-FN2W-TURN-RESTRICTIONS     A          1 (1:10)
DFRI1   0954     M
2290      2 PIWA2-FN2W-INTERSECT-B5SC-LGCS   A          2 (1:5) /*LGCS FOR LIST
DFRI1   0955     M
2300    *                                               /*OF INTERSECTING STS            C
2310      2 PIWA2-FN2W-REPLICATION-CNTR      A          2                                DFR
0956
2320      2 PIWA2-FN2W-NODE-LIST             A          7 (1:20) /*UP TO 20 NODES
DFRI1   0957     M
2330      2 PIWA2-FN2W-NODE-LIST-B7SCS-TBLS  A       3200                                DFR
0958
2340    R 2 PIWA2-FN2W-NODE-LIST-B7SCS-TBLS               /* REDEF. BEGIN : PIWA2-FN2W-NOD DRR
0959
2350      3 PIWA2-FN2W-NODE-LIST-B7SCS-TBL   A        160 (20)
DFRI1   0960     M
2360    R 2 PIWA2-FN2W-NODE-LIST-B7SCS-TBLS               /* REDEF. BEGIN : PIWA2-FN2W-NOD DRR
0961
2370      3 PIWA2-FN2W-NODE-LIST-B7SCS-STS   A         32 (20,5)
DFRI2   0962     M
2380    R 2 PIWA2-FN2W-NODE-LIST-B7SCS-TBLS               /* REDEF. BEGIN : PIWA2-FN2W-NOD DRR
0963
2390      3 PIWA2-FN2W-NODE-LIST-B7SCS       A          8 (20,5,4)
DFRI3   0964     M
2400      2 PIWA2-FN2W-REASON-CODE           A          1                                DFR
0965
2410      2 PIWA2-FN2W-REASON-CODE-QUAL      A          1                                DFR
0966
2420      2 PIWA2-FN2W-WARN-CODE             A          2                                DFR
0967
2430      2 PIWA2-FN2W-RETURN-CODE           A          2                                DFR
0968
2440      2 PIWA2-FN2W-LATITUDE              A          9                                DFR
```

```
2450      2 PIWA2-FN2W-LONGITUDE            A         11                                DFR
2460      2 PIWA2-FN2W-FILLER2W             A        374                                DFR
0969
2470   *  *  END OF FUNCTION 2W             * ********** ********                        C
2480   *  * ------------------------------- - ---------- -----------------               C
2490   *  *  BEGINNING OF FUNCTION 3 LAYOUT  * ********** *********                      CSR
0096
2500   R  1 GEOLP2                                                                       DRR
0970
2510      2 PIWA2-FN3-ACCESS-KEY            A         21                                DFR
0971
2520      2 PIWA2-FN3-DUP-KEY-FLAG          A          1 /* OR CONTI PARITY              DFR
0972
2530      2 PIWA2-FN3-LOCATION-STATUS       A          1                                DFR
0973
2540      2 PIWA2-FN3-COUNTY-BOUNDARY       A          1                                DFR
0974
2550      2 PIWA2-FN3-PREFERRED-LGC1        A          2                                DFR
0975
2560      2 PIWA2-FN3-PREFERRED-LGC2        A          2                                DFR
0976
2570      2 PIWA2-FN3-PREFERRED-LGC3        A          2                                DFR
0977
2580      2 PIWA2-FN3-NUM-X-ST-LOW-END      A          1                                DFR
0978
2590      2 PIWA2-FN3-LOW-B5SC              A          6 (1:5) /* 30-BYTES
DFRI1   0979     M
2600      2 PIWA2-FN3-NUM-X-ST-HI-END       A          1                                DFR
0980
2610      2 PIWA2-FN3-HI-B5SC               A          6 (1:5) /* 30-BYTES
DFRI1   0981     M
2620      2 PIWA2-FN3-REVERSAL-FLAG         A          1                                DFR
0982
2630      2 PIWA2-FN3-LION-KEY              A         10                                DFR
0983
2640   R  2 PIWA2-FN3-LION-KEY                                                           DRR
0984
2650      3 PIWA2-FN3-LION-BORO             A          1                                DFR
0985
2660      3 PIWA2-FN3-LION-FACECODE         A          4                                DFR
0986
2670      3 PIWA2-FN3-LION-SEQ              A          5                                DFR
0987
2680      2 PIWA2-FN3-GENREC-FLAG           A          1                                DFR
0988
```

```
2690      2 PIWA2-FN3-SEG-LENGTH            A          5                                DFR
0989
2700      2 PIWA2-FN3-SEG-SLOP              A          3                                DFR
0990
2710      2 PIWA2-FN3-SEG-ORIENT            A          1                                DFR
0991
2720      2 PIWA2-FN3-MARBLE-RIKERS-FLAG    A          1                                DFR
0992
2730      2 PIWA2-FN3-FROM-NODE             A          7                                DFR
0993
2740      2 PIWA2-FN3-TO-NODE               A          7                                DFR
0994
2750      2 PIWA2-FN3-SANIT-SNOW-PRIORITY   A          1 /*SANITATION STRT              DFR
0995
2760    * *                                              /*SNOW PRIORITY                 C
2770      2 FILLER-600                      A          4                                DFR
0996
2780      2 PIWA2-FN3-SEGMENT-ID            A          7                                DFR
0997
2790      2 PIWA2-FN3-DOT-SLA               A          1                                DFR
0998
2800      2 PIWA2-FN3-CURVE-FLAG            A          1                                DFR
0999
2810      2 PIWA2-FN3-DOG-LEG               A          1                                DFR
1000
2820      2 PIWA2-FN3-FEATURE-TYPE          A          1                                DFR
1001
2830      2 PIWA2-FN3-SEGMENT-TYPE          A          1                                DFR
1002
2840      2 PIWA2-FN3-COINCIDENT-SEG-CTR    A          1                                DFR
1003
2850      2 FILLER-700                      A          4                                DFR
1004
2860    * * *** LEFT SIDE OF THE STREET **** * ********** ******                        C
2870      2 PIWA2-FN3-LEFT-SIDE-OF-STR      A        150                                DFR
1005
2880    R 2 PIWA2-FN3-LEFT-SIDE-OF-STR                                                  DRR
1006
2890      3 PIWA2-FN3-L-COM-DIST            A          3                                DFR
1007
2900    R 3 PIWA2-FN3-L-COM-DIST                                                        DRR
1008
2910      4 PIWA2-FN3-L-COM-DIST-BORO       A          1                                DFR
1009
2920      4 PIWA2-FN3-L-COM-DIST-NUM        A          2                                DFR
```

```
1010
2930     3 PIWA2-FN3-L-LOW-HOUSENUM         A         16 /* DISPLAY FORMAT                DFR
1011
2940     3 PIWA2-FN3-L-HI-HOUSENUM          A         16 /* DISPLAY FORMAT                DFR
1012
2950     3 FILLER-800                       A         32 /* FOR FUTURE USE                DFR
1013
2960     3 PIWA2-FN3-L-CD-ELIGIBLE          A          1                                    DFR
1014
2970     3 PIWA2-FN3-L-ZIP                  A          5                                    DFR
1015
2980     3 PIWA2-FN3-L-HEALTH-AREA          A          4                                    DFR
1016
2990     3 PIWA2-FN3-L-POLICE-DIST          A          4                                    DFR
1017
3000   R 3 PIWA2-FN3-L-POLICE-DIST                                                          DRR
1018
3010     4 PIWA2-FN3-L-POL-PAT-BORO-CMD     A          1                                    DFR
1019
3020     4 PIWA2-FN3-L-POL-PRECINCT         A          3                                    DFR
1020
3030     3 PIWA2-FN3-L-FIRE-DIV             A          2                                    DFR
1021
3040     3 PIWA2-FN3-L-FIRE-BAT             A          2                                    DFR
1022
3050     3 PIWA2-FN3-L-FIRE-CO              A          4                                    DFR
1023
3060   R 3 PIWA2-FN3-L-FIRE-CO                                                              DRR
1024
3070     4 PIWA2-FN3-L-FIRE-CO-TYPE         A          1                                    DFR
1025
3080     4 PIWA2-FN3-L-FIRE-CO-NUM          A          3                                    DFR
1026
3090     3 PIWA2-FN3-L-SCHL-DIST            A          2                                    DFR
1027
3100     3 PIWA2-FN3-L-DYN-BLK              A          3                                    DFR
1028
3110     3 PIWA2-FN3-L-ED                   A          3                                    DFR
1029
3120     3 PIWA2-FN3-L-AD                   A          2                                    DFR
1030
3130     3 PIWA2-FN3-L-POLICE-PAT-BORO      A          2                                    DFR
3140     3 FILLER-880                       A          1                                    DFR
1031
3150     3 PIWA2-FN3-L-BORO                 A          1                                    DFR
```

```
1032
3160     3 PIWA2-FN3-L-1990-CENSUS-TRACT    A          6                                DFR
1033
3170     3 PIWA2-FN3-L-2010-CENSUS-TRACT    A          6                                DFR
1034
3180     3 PIWA2-FN3-L-2010-CENSUS-BLOCK    A          4                                DFR
1035
3190     3 PIWA2-FN3-L-2010-CENSUS-BLK-SUF  A          1 /* NA                          DFR
1036
3200     3 PIWA2-FN3-L-2000-CENS-TRACT      A          6                                DFR
1037
3210     3 PIWA2-FN3-L-2000-CENS-BLOCK      A          4                                DFR
1038
3220     3 PIWA2-FN3-L-2000-CENS-BLK-SUF    A          1 /* NA                          DFR
1039
3230     3 PIWA2-FN3-L-FILLER-890           A          7 /* V16.1 REPLACEMENT           DFR
1040
3240     3 PIWA2-FN3-L-NTA                  A          4 /*NEIGHBORHOOD                  DFR
1041
3250   *  *                                             /*TABULATION AREA               C
3260     3 FILLER-900                       A          8                                DFR
1042
3270   *  * *** RIGHT SIDE OF THE STREET *** * ********** ***********                   C
3280     2 PIWA2-FN3-RIGHT-SIDE-OF-STR      A        150                                DFR
1043
3290   R  2 PIWA2-FN3-RIGHT-SIDE-OF-STR                                                 DRR
1044
3300     3 PIWA2-FN3-R-COM-DIST             A          3                                DFR
1045
3310   R  3 PIWA2-FN3-R-COM-DIST                                                         DRR
1046
3320     4 PIWA2-FN3-R-COM-DIST-BORO        A          1                                DFR
1047
3330     4 PIWA2-FN3-R-COM-DIST-NUM         A          2                                DFR
1048
3340     3 PIWA2-FN3-R-LOW-HOUSENUM         A         16 /* DISPLAY FORMAT               DFR
1049
3350     3 PIWA2-FN3-R-HI-HOUSENUM          A         16 /* DISPLAY FORMAT               DFR
1050
3360     3 FILLER-1000                      A         32 /* FOR FUTURE USE               DFR
1051
3370     3 PIWA2-FN3-R-CD-ELIGIBLE          A          1                                DFR
1052
3380     3 PIWA2-FN3-R-ZIP                  A          5                                DFR
1053
```

```
3390      3 PIWA2-FN3-R-HEALTH-AREA          A          4                                DFR
1054
3400      3 PIWA2-FN3-R-POLICE-DIST          A          4                                DFR
1055
3410   R  3 PIWA2-FN3-R-POLICE-DIST                                                       DRR
1056
3420      4 PIWA2-FN3-R-POL-PAT-BORO-CMD     A          1                                DFR
1057
3430      4 PIWA2-FN3-R-POL-PRECINCT         A          3                                DFR
1058
3440      3 PIWA2-FN3-R-FIRE-DIV             A          2                                DFR
1059
3450      3 PIWA2-FN3-R-FIRE-BAT             A          2                                DFR
1060
3460      3 PIWA2-FN3-R-FIRE-CO              A          4                                DFR
1061
3470   R  3 PIWA2-FN3-R-FIRE-CO                                                           DRR
1062
3480      4 PIWA2-FN3-R-FIRE-CO-TYPE         A          1                                DFR
1063
3490      4 PIWA2-FN3-R-FIRE-CO-NUM          A          3                                DFR
1064
3500      3 PIWA2-FN3-R-SCHL-DIST            A          2                                DFR
1065
3510      3 PIWA2-FN3-R-DYN-BLK              A          3                                DFR
1066
3520      3 PIWA2-FN3-R-ED                   A          3                                DFR
1067
3530      3 PIWA2-FN3-R-AD                   A          2                                DFR
1068
3540      3 PIWA2-FN3-R-POLICE-PAT-BORO      A          2                                DFR
3550      3 FILLER-1080                      A          1                                DFR
1069
3560      3 PIWA2-FN3-R-BORO                 A          1                                DFR
1070
3570      3 PIWA2-FN3-R-1990-CENSUS-TRACT    A          6                                DFR
1071
3580      3 PIWA2-FN3-R-2010-CENSUS-TRACT    A          6                                DFR
1072
3590      3 PIWA2-FN3-R-2010-CENSUS-BLOCK    A          4                                DFR
1073
3600      3 PIWA2-FN3-R-2010-CENSUS-BLK-SUF  A          1 /* NA                         DFR
1074
3610      3 PIWA2-FN3-R-2000-CENS-TRACT      A          6                                DFR
1075
```

```
3620      3 PIWA2-FN3-R-2000-CENS-BLOCK      A          4                                DFR
1076
3630      3 PIWA2-FN3-R-2000-CENS-BLK-SUF    A          1 /* NA                          DFR
1077
3640      3 PIWA2-FN3-R-FILLER-1090          A          7 /* V16.1 REPLACEMENT            DFR
1078
3650      3 PIWA2-FN3-R-NTA                  A          4 /*NEIGHBORHOOD                  DFR
1079
3660   *  *                                               /*TABULATION AREA               C
3670      3 FILLER-1100                      A          8                                DFR
1080
3680   *  2 PIWA2-FN3-PSEUDO-FILLER          A       3550                                CFR
0901
3690   *  * ******************************** * ********** **********                     C
3700   * ** *** END OF FUNCTION 3 LAYOUT**** * ********** **********                     C
3710   R  1 GEOLP2                                                                       DRR
1081
3720      2 PIWA2-FN3-SEGAUX                 A        450 /* SAME AS FN3                  DFR
1082
3730      2 PIWA2-FN3-FILLER-SEGAUX          A          6 /* FOR FUTURE USE               DFR
1083
3740      2 PIWA2-FN3-SEGAUX-COUNTER         A          4                                DFR
1084
3750      2 PIWA2-FN3-SEGAUX-SEGMENTS        A          7 (1:70)
DFRI1   1085     M
3760   *  2 PIWA2-FN3-SEGAUX-PSEUDO-FILLER   A       3050                                CFR
0905
3770   *  * ******************************** * ********** FOR AUX SEGS                   C
3780   *  *  END OF FUNCTION 3 AUX LAYOUT    * ********** ********                       C
3790   *  * ------------------------------- - ---------- --------                       C
3800   *  *  START OF FUNCTION 3 EXTENDED      LAYOUT     ********                       CSR
0096
3810   R  1 GEOLP2                                                                       DRR
1086
3820      2 PIWA2-3X-ACCESS-KEY              A         21                                DFR
1087
3830      2 PIWA2-3X-DUP-KEY-FLAG            A          1 /* OR CONTI PARITY              DFR
1088
3840      2 PIWA2-3X-LOCATION-STATUS         A          1                                DFR
1089
3850      2 PIWA2-3X-COUNTY-BOUNDARY         A          1                                DFR
1090
3860      2 PIWA2-3X-PREFERRED-LGC1          A          2                                DFR
1091
3870      2 PIWA2-3X-PREFERRED-LGC2          A          2                                DFR
```

```
1092
3880      2 PIWA2-3X-PREFERRED-LGC3          A          2                                DFR
1093
3890      2 PIWA2-3X-NUM-X-ST-LOW-END        A          1                                DFR
1094
3900      2 PIWA2-3X-LOW-B5SC                A          6 (1:5) /* 30-BYTES
DFRI1   1095     M
3910      2 PIWA2-3X-NUM-X-ST-HI-END         A          1                                DFR
1096
3920      2 PIWA2-3X-HI-B5SC                 A          6 (1:5) /* 30-BYTES
DFRI1   1097     M
3930      2 PIWA2-3X-REVERSAL-FLAG           A          1                                DFR
1098
3940      2 PIWA2-3X-LION-KEY                A         10                                DFR
1099
3950   R  2 PIWA2-3X-LION-KEY                                                            DRR
1100
3960      3 PIWA2-3X-LION-BORO               A          1                                DFR
1101
3970      3 PIWA2-3X-LION-FACECODE           A          4                                DFR
1102
3980      3 PIWA2-3X-LION-SEQ                A          5                                DFR
1103
3990      2 PIWA2-3X-GENREC-FLAG             A          1                                DFR
1104
4000      2 PIWA2-3X-SEG-LENGTH              A          5                                DFR
1105
4010      2 PIWA2-3X-SEG-SLOP                A          3                                DFR
1106
4020      2 PIWA2-3X-SEG-ORIENT              A          1                                DFR
1107
4030      2 PIWA2-3X-MARBLE-RIKERS-FLAG      A          1                                DFR
1108
4040      2 PIWA2-3X-FROM-NODE               A          7                                DFR
1109
4050      2 PIWA2-3X-TO-NODE                 A          7                                DFR
1110
4060      2 PIWA2-3X-SANIT-SNOW-PRIORITY     A          1 /*SANITATION STRT              DFR
1111
4070   *  *                                               /*SNOW PRIORITY                C
4080      2 FILLER-3X-600                    A          4                                DFR
1112
4090      2 PIWA2-3X-SEGMENT-ID              A          7                                DFR
1113
4100      2 PIWA2-3X-DOT-SLA                 A          1                                DFR
```

```
1114
4110     2 PIWA2-3X-CURVE-FLAG              A          1                                DFR
1115
4120     2 PIWA2-3X-DOG-LEG                 A          1                                DFR
1116
4130     2 PIWA2-3X-FEATURE-TYPE            A          1                                DFR
1117
4140     2 PIWA2-3X-SEGMENT-TYPE            A          1                                DFR
1118
4150     2 PIWA2-3X-COINCIDENT-SEG-CTR      A          1                                DFR
1119
4160     2 FILLER-3X-700                    A          4                                DFR
1120
4170   *  * *** LEFT SIDE OF THE STREET **** * *** ****** ******                        C
4180     2 PIWA2-3X-LEFT-SIDE-OF-STR        A        150                                DFR
1121
4190   R  2 PIWA2-3X-LEFT-SIDE-OF-STR                                                   DRR
1122
4200     3 PIWA2-3X-L-COM-DIST              A          3                                DFR
1123
4210   R  3 PIWA2-3X-L-COM-DIST                                                         DRR
1124
4220     4 PIWA2-3X-L-COM-DIST-BORO         A          1                                DFR
1125
4230     4 PIWA2-3X-L-COM-DIST-NUM          A          2                                DFR
1126
4240     3 PIWA2-3X-L-LOW-HOUSENUM          A         16 /* DISPLAY FORMAT              DFR
1127
4250     3 PIWA2-3X-L-HI-HOUSENUM           A         16 /* DISPLAY FORMAT              DFR
1128
4260     3 FILLER-3X-800                    A         32 /* FOR FUTURE USE              DFR
1129
4270     3 PIWA2-3X-L-CD-ELIGIBLE           A          1                                DFR
1130
4280     3 PIWA2-3X-L-ZIP                   A          5                                DFR
1131
4290     3 PIWA2-3X-L-HEALTH-AREA           A          4                                DFR
1132
4300     3 PIWA2-3X-L-POLICE-DIST           A          4                                DFR
1133
4310   R  3 PIWA2-3X-L-POLICE-DIST                                                       DRR
1134
4320     4 PIWA2-3X-L-POL-PAT-BORO-CMD      A          1                                DFR
1135
4330     4 PIWA2-3X-L-POL-PRECINCT          A          3                                DFR
```

```
1136
4340     3 PIWA2-3X-L-FIRE-DIV              A          2                                DFR
1137
4350     3 PIWA2-3X-L-FIRE-BAT              A          2                                DFR
1138
4360     3 PIWA2-3X-L-FIRE-CO               A          4                                DFR
1139
4370   R 3 PIWA2-3X-L-FIRE-CO                                                            DRR
1140
4380     4 PIWA2-3X-L-FIRE-CO-TYPE          A          1                                DFR
1141
4390     4 PIWA2-3X-L-FIRE-CO-NUM           A          3                                DFR
1142
4400     3 PIWA2-3X-L-SCHL-DIST             A          2                                DFR
1143
4410     3 PIWA2-3X-L-DYN-BLK               A          3                                DFR
1144
4420     3 PIWA2-3X-L-ED                    A          3                                DFR
1145
4430     3 PIWA2-3X-L-AD                    A          2                                DFR
1146
4440     3 PIWA2-3X-L-POLICE-PAT-BORO       A          2                                DFR
4450     3 FILLER-3X-880                    A          1                                DFR
1147
4460     3 PIWA2-3X-L-BORO                  A          1                                DFR
1148
4470     3 PIWA2-3X-L-1990-CENSUS-TRACT     A          6                                DFR
1149
4480     3 PIWA2-3X-L-2010-CENSUS-TRACT     A          6                                DFR
1150
4490     3 PIWA2-3X-L-2010-CENSUS-BLOCK     A          4                                DFR
1151
4500     3 PIWA2-3X-L-2010-CENSUS-BLK-SUF   A          1 /* NA                         DFR
1152
4510     3 PIWA2-3X-L-2000-CENS-TRACT       A          6                                DFR
1153
4520     3 PIWA2-3X-L-2000-CENS-BLOCK       A          4                                DFR
1154
4530     3 PIWA2-3X-L-2010-CENS-BLK-SUF     A          1 /* NA                         DFR
1155
4540     3 PIWA2-3X-L-FILLER-890            A          7 /* V16.1 REPLACEMENT          DFR
1156
4550     3 PIWA2-3X-L-NTA                   A          4 /*NEIGHBORHOOD                 DFR
1157
4560   *  *                                             /*TABULATION AREA               C
```

```
4570      3 FILLER-3X-900                   A          8                                DFR
1158
4580   *  * *** RIGHT SIDE OF THE STREET *** * ********** ***********                   C
4590      2 PIWA2-3X-RIGHT-SIDE-OF-STR       A        150                                DFR
1159
4600   R  2 PIWA2-3X-RIGHT-SIDE-OF-STR                                                   DRR
1160
4610      3 PIWA2-3X-R-COM-DIST              A          3                                DFR
1161
4620   R  3 PIWA2-3X-R-COM-DIST                                                          DRR
1162
4630      4 PIWA2-3X-R-COM-DIST-BORO         A          1                                DFR
1163
4640      4 PIWA2-3X-R-COM-DIST-NUM          A          2                                DFR
1164
4650      3 PIWA2-3X-R-LOW-HOUSENUM          A         16 /* DISPLAY FORMAT              DFR
1165
4660      3 PIWA2-3X-R-HI-HOUSENUM           A         16 /* DISPLAY FORMAT              DFR
1166
4670      3 FILLER-3X-1000                   A         32 /* FOR FUTURE USE              DFR
1167
4680      3 PIWA2-3X-R-CD-ELIGIBLE           A          1                                DFR
1168
4690      3 PIWA2-3X-R-ZIP                   A          5                                DFR
1169
4700      3 PIWA2-3X-R-HEALTH-AREA           A          4                                DFR
1170
4710      3 PIWA2-3X-R-POLICE-DIST           A          4                                DFR
1171
4720   R  3 PIWA2-3X-R-POLICE-DIST                                                       DRR
1172
4730      4 PIWA2-3X-R-POL-PAT-BORO-CMD      A          1                                DFR
1173
4740      4 PIWA2-3X-R-POL-PRECINCT          A          3                                DFR
1174
4750      3 PIWA2-3X-R-FIRE-DIV              A          2                                DFR
1175
4760      3 PIWA2-3X-R-FIRE-BAT              A          2                                DFR
1176
4770      3 PIWA2-3X-R-FIRE-CO               A          4                                DFR
1177
4780   R  3 PIWA2-3X-R-FIRE-CO                                                           DRR
1178
4790      4 PIWA2-3X-R-FIRE-CO-TYPE          A          1                                DFR
1179
```

```
4800      4 PIWA2-3X-R-FIRE-CO-NUM          A          3                                DFR
1180
4810      3 PIWA2-3X-R-SCHL-DIST            A          2                                DFR
1181
4820      3 PIWA2-3X-R-DYN-BLK              A          3                                DFR
1182
4830      3 PIWA2-3X-R-ED                   A          3                                DFR
1183
4840      3 PIWA2-3X-R-AD                   A          2                                DFR
1184
4850      3 PIWA2-3X-R-POLICE-PAT-BORO      A          2                                DFR
4860      3 FILLER-3X-1080                  A          1                                DFR
1185
4870      3 PIWA2-3X-R-BORO                 A          1                                DFR
1186
4880      3 PIWA2-3X-R-1990-CENSUS-TRACT    A          6                                DFR
1187
4890      3 PIWA2-3X-R-2010-CENSUS-TRACT    A          6                                DFR
1188
4900      3 PIWA2-3X-R-2010-CENSUS-BLOCK    A          4                                DFR
1189
4910      3 PIWA2-3X-R-2010-CENSUS-BLK-SUF  A          1 /* NA                         DFR
1190
4920      3 PIWA2-3X-R-2000-CENS-TRACT      A          6                                DFR
1191
4930      3 PIWA2-3X-R-2000-CENS-BLOCK      A          4                                DFR
1192
4940      3 PIWA2-3X-R-2000-CENS-BLK-SUF    A          1 /* NA                         DFR
1193
4950      3 PIWA2-3X-R-FILLER-1090          A          7 /* V16.1 REPLACEMENT          DFR
1194
4960      3 PIWA2-3X-R-NTA                  A          4 /*NEIGHBORHOOD                 DFR
1195
4970    *   *                                           /*TABULATION AREA              C
4980      3 FILLER-3X-1100                  A          8                                DFR
1196
4990      2 PIWA2-3X-LGCS                   A          8                                DFR
1197
5000      2 PIWA2-3X-LGCS-FROM              A          8                                DFR
1198
5010      2 PIWA2-3X-LGCS-TO                A          8                                DFR
1199
5020      2 PIWA2-3X-L-HEALTH-CTR-DIST      A          2                                DFR
1200
5030      2 PIWA2-3X-R-HEALTH-CTR-DIST      A          2                                DFR
```

```
1201
5040      2 PIWA2-3X-FILL1                  A          1                                DFR
1202
5050      2 PIWA2-3X-TRAFFIC-DIR            A          1                                DFR
1203
5060      2 PIWA2-3X-ROADWAY-TYPE           A          2                                DFR
1204
5070      2 PIWA2-3X-PHYSICAL-ID            A          7                                DFR
1205
5080      2 PIWA2-3X-GENERIC-ID             A          7                                DFR
1206
5090      2 PIWA2-3X-INTP-ID                A          7 /* INTERNAL USE               DFR
1207
5100      2 PIWA2-3X-INTF-ID                A          7 /* INTERNAL USE               DFR
1208
5110      2 PIWA2-3X-STR-STATUS             A          1                                DFR
1209
5120      2 PIWA2-3X-STR-WIDTH              A          3                                DFR
1210
5130      2 PIWA2-3X-STR-WIDTH-IRREG        A          1                                DFR
1211
5140      2 PIWA2-3X-BIKE-LANE              A          1                                DFR
1212
5150      2 PIWA2-3X-FED-CLASS-CODE         A          2                                DFR
1213
5160      2 PIWA2-3X-ROW-TYPE               A          1                                DFR
1214
5170      2 PIWA2-3X-LGC-LIST               A         10                                DFR
1215
5180      2 PIWA2-3X-LEGACY-ID              A          7                                DFR
1216
5190      2 PIWA2-3X-L-NTA-NAME             A         75                                DFR
1217
5200      2 PIWA2-3X-R-NTA-NAME             A         75                                DFR
1218
5210      2 PIWA2-3X-FROM-XCOORD            A          7                                DFR
1219
5220      2 PIWA2-3X-FROM-YCOORD            A          7                                DFR
1220
5230      2 PIWA2-3X-TO-XCOORD              A          7                                DFR
1221
5240      2 PIWA2-3X-TO-YCOORD              A          7                                DFR
1222
5250      2 PIWA2-3X-FROM-LATITUDE          A          9                                DFR
5260      2 PIWA2-3X-FROM-LONGITUDE         A         11                                DFR
```

```
5270      2 PIWA2-3X-TO-LATITUDE            A          9                                DFR
5280      2 PIWA2-3X-TO-LONGITUDE           A         11                                DFR
5290      2 PIWA2-3X-L-BLOCKFACE-ID         A         10 /* V16.1 ADD                   DFR
5300      2 PIWA2-3X-R-BLOCKFACE-ID         A         10 /* V16.1 ADD                   DFR
5310      2 PIWA2-3X-NBR-TRAVEL-LANES       A          2 /* V16.1 ADD                   DFR
5320      2 PIWA2-3X-NBR-PARK-LANES         A          2 /* V16.1 ADD                   DFR
5330      2 PIWA2-3X-NBR-TOTAL-LANES        A          2 /* V16.1 ADD                   DFR
5340      2 PIWA2-3X-BIKE-LANE-2            A          2 /* V16.4 ADDITION              DFR
5350      2 PIWA2-3X-STR-WIDTH-MAX          A          3 /* V16.4 ADDITION              DFR
5360      2 PIWA2-3X-BIKE-TRAFFIC-DIR       A          2 /* V17.1 ADDITION              DFR
5370      2 PIWA2-3X-SPEED-LIMIT            A          2 /* V17.4 ADDITION              DFR
5380      2 PIWA2-3X-LEFT-PUMA-CODE         A          5 /* V18.1 ADDITION              DFR
5390      2 PIWA2-3X-RIGHT-PUMA-CODE        A          5 /* V18.1 ADDITION              DFR
5400      2 FILLER-3X-FILL2                 A        201 /* V17.1,V18.1 MOD             DFR
1223
5410    *  2 FILLER-3X-FILL2                 A        215 /* V16.4 ALTERATION            CFR
1223
5420    *  2 FILLER-3X-FILL2                 A        220 /* V16.1 MOD                   CFR
1223
5430    *  2 PIWA2-3X-PSEUDO-FILLER          A       3000                                CFR
1038
5440    *  * ******************************** * ********** **********                    C
5450    *  * END OF FCT 3 EXTENDED LAYOUT *** * ********** **********                    C
5460    R  1 GEOLP2                                                                      DRR
1224
5470      2 PIWA2-3X-SEGAUX                 A       1000 /* SAME AS FN 3X               DFR
1225
5480      2 PIWA2-3X-FILLER-SEGAUX          A          6 /* FOR FUTURE USE              DFR
1226
5490      2 PIWA2-3X-SEGAUX-COUNTER         A          4                                DFR
1227
5500      2 PIWA2-3X-SEGAUX-SEGMENTS        A          7 (1:70)
DFRI1   1228     M
5510    *  * ******************************** * ********** FOR AUX SEGS                  C
5520    *  * END OF FCT 3 EXTENDED AUX LAYOUT * ********** *************                 C
5530    *  * -------------------------------- - ---------- --------                      C
5540    *  *  BEGINNING OF FUNCTION 3C LAYOUT * ********** ********                      C
5550    R  1 GEOLP2                                                                      DRR
1229
5560      2 PIWA2-FN3C-ACCESS-KEY           A         21                                DFR
1230
5570      2 PIWA2-FN3C-DUP-KEY-FLAG         A          1 /* OR CONTI PARITY             DFR
1231
5580      2 PIWA2-FN3C-LOCATION-STATUS      A          1                                DFR
1232
```

```
5590      2 PIWA2-FN3C-COUNTY-BOUNDARY       A          1                                DFR
1233
5600      2 PIWA2-FN3C-PREFERRED-LGC1        A          2                                DFR
1234
5610      2 PIWA2-FN3C-PREFERRED-LGC2        A          2                                DFR
1235
5620      2 PIWA2-FN3C-PREFERRED-LGC3        A          2                                DFR
1236
5630      2 PIWA2-FN3C-NUM-X-ST-LOW-END      A          1                                DFR
1237
5640      2 PIWA2-FN3C-LOW-B5SC              A          6 (1:5) /* 30-BYTES
DFRI1   1238     M
5650      2 PIWA2-FN3C-NUM-X-ST-HI-END       A          1                                DFR
1239
5660      2 PIWA2-FN3C-HI-B5SC               A          6 (1:5) /* 30-BYTES
DFRI1   1240     M
5670      2 PIWA2-FN3C-REVERSAL-FLAG         A          1                                DFR
1241
5680      2 PIWA2-FN3C-LIONKEY               A         10                                DFR
1242
5690   R  2 PIWA2-FN3C-LIONKEY                                                           DRR
1243
5700      3 PIWA2-FN3C-LION-BORO             A          1                                DFR
1244
5710      3 PIWA2-FN3C-LION-FACECODE         A          4                                DFR
1245
5720      3 PIWA2-FN3C-LION-SEQ              A          5                                DFR
1246
5730      2 PIWA2-FN3C-GENREC-FLAG           A          1                                DFR
1247
5740      2 PIWA2-FN3C-SEG-LENGTH            A          5                                DFR
1248
5750      2 PIWA2-FN3C-SEG-AZIMUTH           A          3                                DFR
1249
5760      2 PIWA2-FN3C-SEG-ORIENT            A          1                                DFR
1250
5770      2 PIWA2-FN3C-MARBLE-RIKERS-FLAG    A          1                                DFR
1251
5780      2 PIWA2-FN3C-FROM-NODE             A          7                                DFR
1252
5790      2 PIWA2-FN3C-TO-NODE               A          7                                DFR
1253
5800      2 PIWA2-FN3C-SANIT-SNOW-PRIORITY   A          1 /*SANITATION STRT              DFR
1254
5810   *  *                                               /*SNOW PRIORITY                 C
```

```
5820      2 FILLER-1200                     A          4                                DFR
1255
5830      2 PIWA2-FN3C-SEGMENT-ID           A          7                                DFR
1256
5840      2 PIWA2-FN3C-DOT-SLA              A          1                                DFR
1257
5850      2 PIWA2-FN3C-SIDE-OF-STR          A          1                                DFR
1258
5860      2 PIWA2-FN3C-CURVE-FLAG           A          1                                DFR
1259
5870      2 PIWA2-FN3C-FEATURE-TYPE         A          1                                DFR
1260
5880      2 PIWA2-FN3C-SEGMENT-TYPE         A          1                                DFR
1261
5890      2 PIWA2-FN3C-COINCIDENT-SEG-CTR   A          1                                DFR
1262
5900      2 FILLER-1300                     A          4                                DFR
1263
5910    *   * *** FCT 3C BLOCKFACE INFORMATION * ********** *****************          CRR
0545
5920      2 PIWA2-FN3C-BLOCKFACE-INFO       A        150                                DFR
1264
5930    R 2 PIWA2-FN3C-BLOCKFACE-INFO                                                   DRR
1265
5940      3 PIWA2-FN3C-COM-DIST             A          3                                DFR
1266
5950    R 3 PIWA2-FN3C-COM-DIST                                                         DRR
1267
5960      4 PIWA2-FN3C-COMDIST-BORO         A          1                                DFR
1268
5970      4 PIWA2-FN3C-COMDIST-NUM          A          2                                DFR
1269
5980      3 PIWA2-FN3C-LOW-HOUSENUM         A         16 /* DISPLAY FORMAT              DFR
1270
5990      3 PIWA2-FN3C-HI-HOUSENUM          A         16 /* DISPLAY FORMAT              DFR
1271
6000      3 PIWA2-FN3C-LOW-HOUSENUM2        A         16 /* DISPLAY FORMAT              DFR
1272
6010      3 PIWA2-FN3C-HI-HOUSENUM2         A         16 /* DISPLAY FORMAT              DFR
1273
6020      3 PIWA2-FN3C-FILLER-1400          A          1 /* FOR GSS USE                 DFR
1274
6030      3 PIWA2-FN3C-ZIP                  A          5                                DFR
1275
6040      3 PIWA2-FN3C-HEALTH-AREA          A          4                                DFR
```

```
1276
6050      3 PIWA2-FN3C-POLICE-DIST           A          4                                DFR
1277
6060   R  3 PIWA2-FN3C-POLICE-DIST                                                        DRR
1278
6070      4 PIWA2-FN3C-POL-PAT-BORO-CMD      A          1                                DFR
1279
6080      4 PIWA2-FN3C-POL-PRECINCT          A          3                                DFR
1280
6090      3 PIWA2-FN3C-FIRE-DIV              A          2                                DFR
1281
6100      3 PIWA2-FN3C-FIRE-BAT              A          2                                DFR
1282
6110      3 PIWA2-FN3C-FIRE-CO               A          4                                DFR
1283
6120   R  3 PIWA2-FN3C-FIRE-CO                                                            DRR
1284
6130      4 PIWA2-FN3C-FIRE-CO-TYPE          A          1                                DFR
1285
6140      4 PIWA2-FN3C-FIRE-CO-NUM           A          3                                DFR
1286
6150      3 PIWA2-FN3C-SCHL-DIST             A          2                                DFR
1287
6160      3 PIWA2-FN3C-DYN-BLK               A          3                                DFR
1288
6170      3 PIWA2-FN3C-ED                    A          3                                DFR
1289
6180      3 PIWA2-FN3C-AD                    A          2                                DFR
1290
6190      3 PIWA2-FN3C-POLICE-PAT-BORO       A          2                                DFR
6200      3 FILLER-1480                      A          1                                DFR
1291
6210      3 PIWA2-FN3C-BORO                  A          1                                DFR
1292
6220      3 PIWA2-FN3C-1900-CENSUS-TRACT     A          6                                DFR
1293
6230      3 PIWA2-FN3C-2010-CENSUS-TRACT     A          6                                DFR
1294
6240      3 PIWA2-FN3C-2010-CENSUS-BLOCK     A          4                                DFR
1295
6250      3 PIWA2-FN3C-2010-CENSUS-BLOCK-SUF A          1 /* NA                         DFR
1296
6260      3 PIWA2-FN3C-2000-CENS-TRACT       A          6                                DFR
1297
6270      3 PIWA2-FN3C-2000-CENS-BLOCK       A          4                                DFR
```

```
1298
6280      3 PIWA2-FN3C-2000-CENS-BLK-SUF     A          1 /* NA                          DFR
1299
6290      3 PIWA2-FN3C-FILLER-1490           A          7 /* V16.1 REPLACEMENT           DFR
1300
6300      3 PIWA2-FN3C-NTA                   A          4 /*NEIGHBORHOOD                  DFR
1301
6310    *  *                                             /*TABULATION AREA               C
6320    *  3 FILLER-1500                      A          8                                CFR
1057
6330    *  * PIWA2-FN3C-PSEUDO-FILLER         A       3700 /*LEVEL 2 IN DEF                CFR
1093
6340    *  * ******************************** * ********** ******                        C
6350    *  *  END OF FCT 3C LAYOUT ********** * ********** ******                        C
6360    R  1 GEOLP2                                                                      DRR
1302
6370      2 PIWA2-FN3C-SEGAUX                A        300 /*SAME AS FN3C                  DFR
1303
6380      2 PIWA2-FN3C-SEGAUX-FILL           A          6                                DFR
1304
6390      2 PIWA2-FN3C-SEGAUX-CTR            A          4                                DFR
1305
6400      2 PIWA2-FN3C-SEGAUX-SEGS           A          7 (1:70)
DFRI1   1306     M
6410    *  2 PIWA2-FN3C-AUX-PSEUDO-FILLER     A       3200                                CFR
1121
6420    * ** ******************************** * ********** FN3C AUX SEGS                  C
6430    *  *  END OF FCT 3C AUX LAYOUT ****** * ********** *******                       C
6440    * ** ******************************** * ********** *************                 C
6450    * ** ******************************** * ********** *************                 C
6460    *  *  START OF FUNCTION 3CX LAYOUT    * ********** ********                      C
6470    R  1 GEOLP2                                                                      DRR
1307
6480      2 PIWA2-3CX-ACCESS-KEY             A         21                                DFR
1308
6490      2 PIWA2-3CX-DUP-KEY-FLAG           A          1 /* OR CONTI PARITY             DFR
1309
6500      2 PIWA2-3CX-LOCATION-STATUS        A          1                                DFR
1310
6510      2 PIWA2-3CX-COUNTY-BOUNDARY        A          1                                DFR
1311
6520      2 PIWA2-3CX-PREFERRED-LGC1         A          2                                DFR
1312
6530      2 PIWA2-3CX-PREFERRED-LGC2         A          2                                DFR
1313
```

```
6540      2 PIWA2-3CX-PREFERRED-LGC3         A          2                                DFR
1314
6550      2 PIWA2-3CX-NUM-X-ST-LOW-END       A          1                                DFR
1315
6560      2 PIWA2-3CX-LOW-B5SC               A          6 (1:5) /* 30-BYTES
DFRI1   1316     M
6570      2 PIWA2-3CX-NUM-X-ST-HI-END        A          1                                DFR
1317
6580      2 PIWA2-3CX-HI-B5SC                A          6 (1:5) /* 30-BYTES
DFRI1   1318     M
6590      2 PIWA2-3CX-REVERSAL-FLAG          A          1                                DFR
1319
6600      2 PIWA2-3CX-LIONKEY                A         10                                DFR
1320
6610   R  2 PIWA2-3CX-LIONKEY                                                            DRR
1321
6620      3 PIWA2-3CX-LION-BORO              A          1                                DFR
1322
6630      3 PIWA2-3CX-LION-FACECODE          A          4                                DFR
1323
6640      3 PIWA2-3CX-LION-SEQ               A          5                                DFR
1324
6650      2 PIWA2-3CX-GENREC-FLAG            A          1                                DFR
1325
6660      2 PIWA2-3CX-SEG-LENGTH             A          5                                DFR
1326
6670      2 PIWA2-3CX-SEG-SLOPE              A          3                                DFR
1327
6680      2 PIWA2-3CX-SEG-ORIENT             A          1                                DFR
1328
6690      2 PIWA2-3CX-MARBLE-RIKERS-FLAG     A          1                                DFR
1329
6700      2 PIWA2-3CX-FROM-NODE              A          7                                DFR
1330
6710      2 PIWA2-3CX-TO-NODE                A          7                                DFR
1331
6720      2 PIWA2-3CX-SANIT-SNOW-PRIORITY    A          1 /*SANITATION STRT              DFR
1332
6730   *  *                                               /*SNOW PRIORITY                C
6740      2 FILLER-3CX-1200                  A          4                                DFR
1333
6750      2 PIWA2-3CX-SEGMENT-ID             A          7                                DFR
1334
6760      2 PIWA2-3CX-DOT-SLA                A          1                                DFR
1335
```

```
6770      2 PIWA2-3CX-SIDE-OF-STR            A          1                                DFR
1336
6780      2 PIWA2-3CX-CURVE-FLAG             A          1                                DFR
1337
6790      2 PIWA2-3CX-FEATURE-TYPE           A          1                                DFR
1338
6800      2 PIWA2-3CX-SEGMENT-TYPE           A          1                                DFR
1339
6810      2 PIWA2-3CX-COINCIDENT-SEG-CTR     A          1                                DFR
1340
6820      2 FILLER-3CX-1300                  A          4                                DFR
1341
6830   *  * ***FCT 3C BLOCKFACE INFORMATION  * ********** *****************              CRR
0545
6840      2 PIWA2-3CX-BLOCKFACE-INFO         A        150                                DFR
1342
6850   R  2 PIWA2-3CX-BLOCKFACE-INFO                                                     DRR
1343
6860      3 PIWA2-3CX-COM-DIST               A          3                                DFR
1344
6870   R  3 PIWA2-3CX-COM-DIST                                                           DRR
1345
6880      4 PIWA2-3CX-COMDIST-BORO           A          1                                DFR
1346
6890      4 PIWA2-3CX-COMDIST-NUM            A          2                                DFR
1347
6900      3 PIWA2-3CX-LOW-HOUSENUM           A         16 /* DISPLAY FORMAT               DFR
1348
6910      3 PIWA2-3CX-HI-HOUSENUM            A         16 /* DISPLAY FORMAT               DFR
1349
6920      3 PIWA2-3CX-LOW-HOUSENUM2          A         16 /* DISPLAY FORMAT               DFR
1350
6930      3 PIWA2-3CX-HI-HOUSENUM2           A         16 /* DISPLAY FORMAT               DFR
1351
6940      3 FIWA2-3CX-CD-ELIGIBLE            A          1                                DFR
1352
6950      3 PIWA2-3CX-ZIP                    A          5                                DFR
1353
6960      3 PIWA2-3CX-HEALTH-AREA            A          4                                DFR
1354
6970      3 PIWA2-3CX-POLICE-DIST            A          4                                DFR
1355
6980   R  3 PIWA2-3CX-POLICE-DIST                                                        DRR
1356
6990      4 PIWA2-3CX-POL-PAT-BORO-CMD       A          1                                DFR
```

```
1357
7000      4 PIWA2-3CX-POL-PRECINCT           A          3                                DFR
1358
7010      3 PIWA2-3CX-FIRE-DIV               A          2                                DFR
1359
7020      3 PIWA2-3CX-FIRE-BAT               A          2                                DFR
1360
7030      3 PIWA2-3CX-FIRE-CO                A          4                                DFR
1361
7040   R  3 PIWA2-3CX-FIRE-CO                                                            DRR
1362
7050      4 PIWA2-3CX-FIRE-CO-TYPE           A          1                                DFR
1363
7060      4 PIWA2-3CX-FIRE-CO-NUM            A          3                                DFR
1364
7070      3 PIWA2-3CX-SCHL-DIST              A          2                                DFR
1365
7080      3 PIWA2-3CX-DYN-BLK                A          3                                DFR
1366
7090      3 PIWA2-3CX-ED                     A          3                                DFR
1367
7100      3 PIWA2-3CX-AD                     A          2                                DFR
1368
7110      3 PIWA2-3CX-POLICE-PAT-BORO        A          2                                DFR
7120      3 FILLER-3CX-1480                  A          1                                DFR
1369
7130      3 PIWA2-3CX-BORO                   A          1                                DFR
1370
7140      3 PIWA2-3CX-1990-CENSUS-TRACT      A          6                                DFR
1371
7150      3 PIWA2-3CX-2010-CENSUS-TRACT      A          6                                DFR
1372
7160      3 PIWA2-3CX-2010-CENSUS-BLOCK      A          4                                DFR
1373
7170      3 PIWA2-3CX-2010-CENSUS-BLOCK-SUF  A          1 /* NA                         DFR
1374
7180      3 PIWA2-3CX-2000-CENS-TRACT        A          6                                DFR
1375
7190      3 PIWA2-3CX-2000-CENS-BLOCK        A          4                                DFR
1376
7200      3 PIWA2-3CX-2000-CENS-BLK-SUF      A          1 /* NA                         DFR
1377
7210      3 PIWA2-3CX-FILLER-1490            A          7 /* V16.1 REPLACEMENT          DFR
1378
7220      3 PIWA2-3CX-NTA                    A          4 /*NEIGHBORHOOD                 DFR
```

```
1379
7230   *  *                                          /*TABULATION AREA                C
7240      3 FILLER-1500                     A          8                               DFR
1380
7250      2 PIWA2-3CX-LGCS                  A          8                               DFR
1381
7260      2 PIWA2-3CX-LGCS-FROM             A          8                               DFR
1382
7270      2 PIWA2-3CX-LGCS-TO               A          8                               DFR
1383
7280      2 PIWA2-3CX-L-HEALTH-CTR-DIST     A          2                               DFR
1384
7290      2 PIWA2-3CX-R-HEALTH-CTR-DIST     A          2                               DFR
1385
7300      2 PIWA2-3CX-FILL1                 A          1                               DFR
1386
7310      2 PIWA2-3CX-TRAFFIC-DIR           A          1                               DFR
1387
7320      2 PIWA2-3CX-ROADWAY-TYPE          A          2                               DFR
1388
7330      2 PIWA2-3CX-PHYSICAL-ID           A          7                               DFR
1389
7340      2 PIWA2-3CX-GENERIC-ID            A          7                               DFR
1390
7350      2 PIWA2-3CX-INTP-ID               A          7 /* INTERNAL USE              DFR
1391
7360      2 PIWA2-3CX-INTF-ID               A          7 /* INTERNAL USE              DFR
1392
7370      2 PIWA2-3CX-STREET-STATUS         A          1                               DFR
1393
7380      2 PIWA2-3CX-STREET-WIDTH          A          3                               DFR
1394
7390      2 PIWA2-3CX-STREET-WIDTH-IRREG    A          1                               DFR
1395
7400      2 PIWA2-3CX-BIKE-LANE             A          1                               DFR
1396
7410      2 PIWA2-3CX-FED-CLASS-CODE        A          2                               DFR
1397
7420      2 PIWA2-3CX-ROW-TYPE              A          1                               DFR
1398
7430      2 PIWA2-3CX-LGC-LIST              A         10                               DFR
1399
7440      2 PIWA2-3CX-LEGACY-ID             A          7                               DFR
1400
7450      2 PIWA2-3CX-NTA-NAME              A         75                               DFR
```

```
1401
7460      2 PIWA2-3CX-FROM-XCOORD            A          7                                DFR
1402
7470      2 PIWA2-3CX-FROM-YCOORD            A          7                                DFR
1403
7480      2 PIWA2-3CX-TO-XCOORD              A          7                                DFR
1404
7490      2 PIWA2-3CX-TO-YCOORD              A          7                                DFR
1405
7500      2 PIWA2-3CX-FROM-LATITUDE          A          9                                DFR
7510      2 PIWA2-3CX-FROM-LONGITUDE         A         11                                DFR
7520      2 PIWA2-3CX-TO-LATITUDE            A          9                                DFR
7530      2 PIWA2-3CX-TO-LONGITUDE           A         11                                DFR
7540      2 PIWA2-3CX-BLOCKFACE-ID           A         10 /* V16.1 ADD                  DFR
7550      2 PIWA2-3CX-NBR-TRAVEL-LANES       A          2 /* V16.1 ADD                  DFR
7560      2 PIWA2-3CX-NBR-PARK-LANES         A          2 /* V16.1 ADD                  DFR
7570      2 PIWA2-3CX-NBR-TOTAL-LANES        A          2 /* V16.1 ADD                  DFR
7580      2 PIWA2-3CX-BIKE-LANE-2            A          2 /* V16.4 ADDITION             DFR
7590      2 PIWA2-3CX-STR-WIDTH-MAX          A          3 /* V16.4 ADDITION             DFR
7600      2 PIWA2-3CX-BIKE-TRAFFIC-DIR       A          2 /* V17.1 ADDITION             DFR
7610      2 PIWA2-3CX-SPEED-LIMIT            A          2 /* V17.4 ADDITION             DFR
7620      2 PIWA2-3CX-PUMA-CODE              A          5 /* V18.1 ADDITION             DFR
7630      2 FILLER-3CX-FILL1560              A        291 /* V17.1,V18.1 MOD            DFR
1406
7640    *  2 FILLER-3CX-FILL1560             A        300 /* V16.4 ALTERATION           CFR
1406
7650    *  2 FILLER-3CX-FILL1560             A        305 /* V16.1 MOD                  CFR
1406
7660    *  2 PIWA2-3CX-PSEUDO-FILER          A       3150                                CFR
1225
7670    *  * ******************************** * ********** ******                        C
7680    *  *  END OF FCT 3CX LAYOUT ********* * ********** ******                        C
7690    R  1 GEOLP2                                                                      DRR
1407
7700      2 PIWA2-3CX-SEGAUX                 A        850 /* SAME AS FN 3CX             DFR
1408
7710      2 PIWA2-3CX-SEGAUX-FILL            A          6                                DFR
1409
7720      2 PIWA2-3CX-SEGAUX-CTR             A          4                                DFR
1410
7730      2 PIWA2-3CX-SEGAUX-SEGS            A          7 (1:70)
DFRI1   1411     M
7740    *  2 PIWA2-3CX-AUX-PSEUDO-FILLER     A       2650                                CFR
1223
7750    * ** ******************************** * ********** FN3C AUX SEGS                 C
```

```
7760   *  *  END OF FCT 3CX AUX LAYOUT*****  * ********** *******                        C
7770   * ** ******************************** * ********** *************                  C
7780   * ** ******************************** * ********** *************                  C
7790   *  *  BEGINNING OF FUNCTION 5 LAYOUT  *       **** *******                        C
7800   R  1 GEOLP2                                                                       DRR
1412
7810      2 PIWA2-FN5-ADDR-MATCHING-KEY      A         33                                DFR
1413
7820      2 FILLER-1600                      A        267                                DFR
1414
7830   *  *  END OF FUNCTION 5 LAYOUT        *       **** *******                        C
7840   *  - ------------------------------- -       ---- --------------------------------- C
***** End of List *****
```

GEOLP21A COPY File

```
0010      1 GEOLP21A                                  /*FCT 1A,BL USE SAME WA2  AYOUT  DS
0082
0020   *  * THE FIELD P2NAT1A IS USED AS A      PARAMETER TO CALL GEOSUPPORT              C
0030      2 P2NAT1A                          A         21                                DK
0084
0040   R  2 P2NAT1A                                                                       DRR
0085
0050      3 PIWA2-1A-ACCESS-KEY              A         21                                DFR
0086
0060      2 PIWA2-1A-CONT-PARITY             A          1 /* OR DUP ADDR IND              DK
0087
0070      2 PIWA2-1A-LOW-HOUSENUM            A         11 /* SORT FORMAT                  DK
0088
0080      2 PIWA2-1A-BBL                     A         10                                DK
0089
0090   R  2 PIWA2-1A-BBL                                                                   DRR
0090
0100      3 PIWA2-1A-BBL-BORO                A          1                                DFR
0091
0110      3 PIWA2-1A-BLOCK                   A          5                                DFR
0092
0120      3 PIWA2-1A-LOT                     A          4                                DFR
0093
0130      2 PIWA2-1A-LOT-VERSION             A          1 /* NYI */                       DK
0094
0140      2 PIWA2-1A-SCC                     A          1                                DK
0095
0150      2 FILLER-100                       A          1                                DK
```

```
0096
0160      2 PIWA2-1A-GENERAL-LOT-INFO                                          DS
0097
0170      3 PIWA2-1A-RPAD-BLDG-CLASS         A          2                      DK
0098
0180      3 PIWA2-1A-CORNER-CODE             A          2                      DK
0099
0190      3 PIWA2-1A-NUM-OF-STRUCTURES       A          4                      DK
0100
0200      3 PIWA2-1A-NUM-OF-BLOCKFACES       A          2                      DK
0101
0210      3 PIWA2-1A-INTERIOR-FLAG           A          1                      DK
0102
0220      3 PIWA2-1A-VACANT-FLAG             A          1                      DK
0103
0230      3 PIWA2-1A-IRREG-LOT-FLAG          A          1                      DK
0104
0240      2 PIWA2-1A-MARBLE-RIKERS-FLAG      A          1                      DK
0105
0250      2 PIWA2-1A-ADDR-LIST-OVFLOW-FLAG   A          1                      DK
0106
0260      2 PIWA2-1A-STROLL-KEY              A         19                      DK
0107
0270    R 2 PIWA2-1A-STROLL-KEY                                                DRR
0108
0280      3 PIWA2-1A-STROLL-BORO             A          1                      DFR
0109
0290      3 PIWA2-1A-STROLL-5SC              A          5                      DFR
0110
0300      3 PIWA2-1A-STROLL-SIDE-OF-STR      A          1 /* L OR R            DFR
0111
0310      3 PIWA2-1A-STROLL-HI-HOUSENUM      A         11 /* SORT FORMAT       DFR
0112
0320      3 FILLER-200                       A          1                      DFR
0113
0330      2 FILLER-300                       A          1 /* FOR GSS USE       DK
0114
0340      2 PIWA2-1A-BIN                     A          7                      DK
0115
0350      2 PIWA2-1A-CONDO-FLAG              A          1                      DK
0116
0360      2 FILLER-400                       A          1                      DK
0117
0370      2 PIWA2-1A-RPAD-CONDO-ID-NUM       A          4                      DK
0118
```

```
0380      2 PIWA2-1A-CONDO-UNIT-ID-NUM       A          7                                DK
0119
0390      2 PIWA2-1A-CONDO-BILL-BBL          A         10                                DK
0120
0400      2 PIWA2-1A-CONDO-BILL-BBL-VER      A          1                                DK
0121
0410      2 PIWA2-1A-CONDO-BILL-BBL-SCC      A          1                                DK
0122
0420      2 PIWA2-1A-CONDO-LOW-BBL           A         10                                DK
0123
0430      2 PIWA2-1A-CONDO-LOW-BBL-VER       A          1                                DK
0124
0440      2 PIWA2-1A-CONDO-HIGH-BBL          A         10                                DK
0125
0450      2 PIWA2-1A-CONDO-HIGH-BBL-VER      A          1                                DK
0126
0460      2 FILLER-500                       A         15                                DK
0127
0470      2 PIWA1-1A-COOP-NUM                A          4                                DK
0128
0480      2 PIWA2-1A-SANBORN                 A          8                                DK
0129
0490    R 2 PIWA2-1A-SANBORN                                                             DRR
0130
0500      3 PIWA2-1A-SANBORN-BORO            A          1                                DFR
0131
0510      3 PIWA2-1A-SANBORN-VOL             A          3                                DFR
0132
0520      3 PIWA2-1A-SANBORN-PAGE            A          4                                DFR
0133
0530      2 PIWA2-1A-COMMERC-DIST            A          5                                DK
0134
0540      2 PIWA2-1A-DOF-MAP-BORO            A          1                                DK
0135
0550      2 PIWA2-1A-DOF-MAP-SECVOL          A          4                                DK
0136
0560      2 PIWA2-1A-DOF-MAP-PAGE            A          4                                DK
0137
0570      2 FILLER-1A-RESERVED-DCP           A          3                                DK
0138
0580      2 PIWA2-1A-LATITUDE                A          9                                DK
0139
0590      2 PIWA2-1A-LONGITUDE               A         11                                DK
0140
0600      2 PIWA2-1A-X-COORD                 A          7                                DK
```

```
0141
0610      2 PIWA2-1A-Y-COORD                A          7                                DK
0142
0620      2 PIWA2-1A-BID                    A          6                                DK
0143
0630      2 PIWA2-1A-TPAD-BIN-ST            A          1 /* CURRENT STATUS */           DK
0144
0640      2 PIWA2-1A-TPAD-NEW-BIN           A          7 /* NEW BIN */                  DK
0145
0650      2 PIWA2-1A-TPAD-NEW-BIN-ST        A          1 /* NEW BIN STATUS */           DK
0146
0660      2 PIWA2-1A-TPAD-CONFLICT          A          1 /* CONFLICT FLAG */            DK
0147
0670      2 PIWA2-1A-DCP-ZONE-MAP           A          3 /* V17.4 ADDITION              DK
0680      2 FILLER-650                      A          6                                DK
0148
0690      2 FILLER-700                      A          8 /* FOR GSS USE                 DK
0149
0700      2 PIWA2-1A-NUM-OF-ADDR            A          4                                DK
0150
0710      2 PIWA2-1A-LIST-OF-ADDR                        (1:21)                         DS
I1   0151     M
0720      3 PIWA2-1A-LIST-LOW-HOUSENUM      A         16 /* DISPLAY FORMAT              DK
0152
0730      3 PIWA2-1A-LIST-HI-HOUSENUM       A         16 /* DISPLAY FORMAT              DK
0153
0740      3 PIWA2-1A-LIST-BORO              A          1                                DK
0154
0750      3 PIWA2-1A-LIST-5SC               A          5                                DK
0155
0760      3 PIWA2-1A-LIST-LGC               A          2                                DK
0156
0770      3 PIWA2-1A-LIST-BIN               A          7                                DK
0157
0780      3 PIWA2-1A-LIST-SIDE-OF-STR       A          1 /* L OR R                      DK
0158
0790      3 PIWA2-1A-LIST-ADDR-TYPE         A          1 /* P=NAP, B=NAB,          MAL  DK
0159
0800   *  *                                             /* BLANK=NORMAL                C
0810      3 PIWA2-1A-LIST-TPAD-STATUS       A          1 /* 0 - 9                       DK
0160
0820      3 FILLER-800                      A          3                                DK
0161
***** End of List *****
```

GEOLP2AL COPY File

```
0010      1 GEOLP2AL                                    /* FCT 1A, BL LONG WA2    WA2    DS
0572
0020   *  * THE FIELD P2NAT1AL IS USED AS A     PARAMETER TO CALL GEOSUPPORT              C
0030      2 P2NAT1AL                         A         21                                 DK
0574
0040   R  2 P2NAT1AL                                                                      DRR
0575
0050      3 PIWA2-1AL-ACCESS-KEY             A         21                                 DFR
0576
0060   *  * BEGINNING OF FUNCTION 1AL LAYOUT * ********** *******************             C
0070      2 PIWA2-1AL-CONT-PARITY            A          1 /* OR DUP ADDR IND              DK
0577
0080      2 PIWA2-1AL-LOW-HOUSENUM           A         11 /* SORT FORMAT                  DK
0578
0090      2 PIWA2-1AL-BBL                    A         10                                 DK
0579
0100   R  2 PIWA2-1AL-BBL                                                                  DRR
0580
0110      3 PIWA2-1AL-BBL-BORO               A          1                                 DFR
0581
0120      3 PIWA2-1AL-BLOCK                  A          5                                 DFR
0582
0130      3 PIWA2-1AL-LOT                    A          4                                 DFR
0583
0140      2 FILLER-1AL-LOT-VERSION           A          1 /* NA                           DK
0584
0150      2 PIWA2-1AL-SCC                    A          1                                 DK
0585
0160      2 FILLER-100                       A          1                                 DK
0586
0170      2 PIWA2-1AL-GENERAL-LOT-INFO                                                    DS
0587
0180      3 PIWA2-1AL-RPAD-BLDG-CLASS        A          2                                 DK
0588
0190      3 PIWA2-1AL-CORNER-CODE            A          2                                 DK
0589
0200      3 PIWA2-1AL-NUM-OF-STRUCTURES      A          4                                 DK
0590
0210      3 PIWA2-1AL-NUM-OF-BLOCKFACES      A          2                                 DK
0591
0220      3 PIWA2-1AL-INTERIOR-FLAG          A          1                                 DK
0592
```

```
0230      3 PIWA2-1AL-VACANT-FLAG           A          1                                DK
0593
0240      3 PIWA2-1AL-IRREG-LOT-FLAG        A          1                                DK
0594
0250      2 PIWA2-1AL-MARBLE-RIKERS-FLAG    A          1                                DK
0595
0260      2 PIWA2-1AL-ADDR-LIST-OVFLOW-FLAG A          1                                DK
0596
0270      2 PIWA2-1AL-STROLL-KEY            A         19                                DK
0597
0280    R 2 PIWA2-1AL-STROLL-KEY                                                        DRR
0598
0290      3 PIWA2-1AL-STROLL-KEY-BORO       A          1                                DFR
0599
0300      3 PIWA2-1AL-STROLL-KEY-5SC        A          5                                DFR
0600
0310      3 PIWA2-1AL-STROLL-SIDE-OF-STR    A          1 /* L OR R                      DFR
0601
0320      3 PIWA2-1AL-STROLL-HI-HOUSENUM    A         11 /* SORT FORMAT                 DFR
0602
0330      3 FILLER-200                      A          1                                DFR
0603
0340      2 FILLER-300                      A          1 /* FOR GSS USE                 DK
0604
0350      2 PIWA2-1AL-BIN                   A          7                                DK
0605
0360      2 PIWA2-1AL-CONDO-FLAG            A          1                                DK
0606
0370      2 FILLER-400                      A          1                                DK
0607
0380      2 PIWA2-1AL-RPAD-CONDO-ID-NUM     A          4                                DK
0608
0390      2 PIWA2-1AL-CONDO-UNIT-ID-NUM     A          7                                DK
0609
0400      2 PIWA2-1AL-CONDO-BILL-BBL        A         10                                DK
0610
0410      2 PIWA2-1AL-CONDO-BILL-BBL-VER    A          1                                DK
0611
0420      2 PIWA2-1AL-CONDO-BILL-BBL-SCC    A          1                                DK
0612
0430      2 PIWA2-1AL-CONDO-LOW-BBL         A         10                                DK
0613
0440      2 PIWA2-1AL-CONDO-LOW-BBL-VER     A          1                                DK
0614
0450      2 PIWA2-1AL-CONDO-HIGH-BBL        A         10                                DK
```

```
0615
0460      2 PIWA2-1AL-CONDO-HIGH-BBL-VER     A          1                                DK
0616
0470      2 FILLER-500                       A         15                                DK
0617
0480      2 PIWA2-1AL-COOP-NUM               A          4                                DK
0618
0490      2 PIWA2-1AL-SANBORN                A          8                                DK
0619
0500    R 2 PIWA2-1AL-SANBORN                                                            DRR
0620
0510      3 PIWA2-1AL-SANBORN-BORO           A          1                                DFR
0621
0520      3 PIWA2-1AL-SANBORN-VOL            A          3                                DFR
0622
0530      3 PIWA2-1AL-SANBORN-PAGE           A          4                                DFR
0623
0540      2 PIWA2-1AL-COMMERC-DIST           A          5                                DK
0624
0550      2 PIWA2-1AL-DOF-MAP-BORO           A          1                                DK
0625
0560      2 PIWA2-1AL-DOF-MAP-SECVOL         A          4                                DK
0626
0570      2 PIWA2-1AL-DOF-MAP-PAGE           A          4                                DK
0627
0580      2 FILLER-600                       A          3                                DK
0628
0590      2 PIWA2-1AL-LATITUDE               A          9                                DK
0629
0600      2 PIWA2-1AL-LONGITUDE              A         11                                DK
0630
0610      2 PIWA2-1AL-X-COORD                A          7                                DK
0631
0620      2 PIWA2-1AL-Y-COORD                A          7                                DK
0632
0630      2 PIWA2-1AL-BID                    A          6                                DK
0633
0640      2 PIWA2-1AL-TPAD-BIN-ST            A          1 /*CURRENT STATUS               DK
0634
0650      2 PIWA2-1AL-TPAD-NEW-BIN           A          7 /*NEW BIN                      DK
0635
0660      2 PIWA2-1AL-TPAD-NEW-BIN-ST        A          1 /*NEW BIN STATUS               DK
0636
0670      2 PIWA2-1AL-TPAD-CONFLICT          A          1 /*CONFLICT FLAG                DK
0637
```

```
0680      2 PIWA2-1AL-DCP-ZONE-MAP           A          3 /* V17.4 ADDITION                DK
0690      2 FILLER-650                       A          6                                 DK
0638
0700      2 FILLER-700                       A          8 /* LGC GSS USE                   DK
0639
0710      2 PIWA2-1AL-NUM-OF-BINS            A          4                                 DK
0640
0720      2 PIWA2-1AL-TPAD-BINLIST           A      17500                                 DK
0641
0730    R 2 PIWA2-1AL-TPAD-BINLIST                        /* REDEF. BEGIN : PIWA2-1AL-TPAD DRR
0642
0740      3 PIWA2-1AL-TPAD-BINS                           (1:2187)
DSRI1   0643     M
0750      4 PIWA2-1AL-TPAD-BIN               A          7                                 DKR
0644
0760      4 PIWA2-1AL-TPAD-BINS-STAT         A          1                                 DKR
0645
0770      3 PIWA2-1AL-TPAD-FILL              A          4                                 DKR
0646
0780    R 2 PIWA2-1AL-TPAD-BINLIST                                                        DRR
0647
0790      3 PIWA2-1AL-BINS                   A          7 (1:2500)
DKRI1   0648     M
0800    * ** END OF FUNCTION 1AL LAYOUT ***** * ********** *********************          C
0810    * -- ------------------------------- - ---------- -------------------------       C
0820    * ** BEGINNING OF FCT 1/1E EXTENDED * * ********** *********************          C
0830    R 1 GEOLP2AL                                                                      DRR
0649
0840      2 PIWA2-1EX-ACCESS-KEY             A         21                                 DFR
0650
0850      2 PIWA2-1EX-CONT-PARITY            A          1 /* (OR DUP ADDR IND)            DFR
0651
0860      2 PIWA2-1EX-LOW-HOUSENUM           A         11 /* SORT FORMAT                  DFR
0652
0870      2 PIWA2-1EX-HI-HOUSENUM            A         11 /* SORT FORMAT                  DFR
0653
0880      2 PIWA2-1EX-PREFERRED-LGC          A          2                                 DFR
0654
0890      2 PIWA2-1EX-NUM-X-ST-LOW-END       A          1                                 DFR
0655
0900      2 PIWA2-1EX-LOW-B5SC               A          6 (1:5) /* 30-BYTES
DFRI1   0656     M
0910      2 PIWA2-1EX-NUM-X-ST-HI-END        A          1                                 DFR
0657
0920      2 PIWA2-1EX-HI-B5SC                A          6 (1:5) /* 30-BYTES
```

```
DFRI1   0658     M
0930      2 PIWA2-1EX-LIONKEY               A         10                              DFR
0659
0940   R  2 PIWA2-1EX-LIONKEY                                                         DRR
0660
0950      3 PIWA2-1EX-LION-BORO             A          1                              DFR
0661
0960      3 PIWA2-1EX-LION-FACECODE         A          4                              DFR
0662
0970      3 PIWA2-1EX-LION-SEQ              A          5                              DFR
0663
0980      2 PIWA2-1EX-SPECIAL-ADDR-FLAG     A          1                              DFR
0664
0990      2 PIWA2-1EX-SIDE-OF-STR           A          1                              DFR
0665
1000      2 PIWA2-1EX-SEG-LEN               A          5                              DFR
0666
1010      2 PIWA2-1EX-X-COORD               A          7                              DFR
0667
1020      2 PIWA2-1EX-Y-COORD               A          7                              DFR
0668
1030      2 FILLER-1EX-100                  A          7 /* FOR ZCOORD                DFR
0669
1040      2 FILLER-1EX-200                  A          1 /* FOR GSS USE               DFR
0670
1050      2 PIWA2-1EX-MARBLE-RIKERS-FLAG    A          1                              DFR
0671
1060      2 PIWA2-1EX-DOT-SLA               A          1                              DFR
0672
1070      2 PIWA2-1EX-COM-DIST              A          3                              DFR
0673
1080   R  2 PIWA2-1EX-COM-DIST                                                         DRR
0674
1090      3 PIWA2-1EX-COM-DIST-BORO         A          1                              DFR
0675
1100      3 PIWA2-1EX-COM-DIST-NUM          A          2                              DFR
0676
1110      2 PIWA2-1EX-ZIP                   A          5                              DFR
0677
1120   *  *                                 *       **** *****                        C
1130   *  *  THE FN1E FIELDS ARE VALID ONLY *       **** *****                        C
1140   *  *  FOR FUNCTION 1E, NOT FUNC 1.   *       **** *****                        C
1150      2 PIWA2-1EX-ELECT-DIST            A          3                              DFR
0678
1160      2 PIWA2-1EX-ASSEM-DIST            A          2                              DFR
```

```
0679
1170     2 PIWA2-1EX-SPLIT-ED-FLAG          A          1                              DFR
0680
1180     2 PIWA2-1EX-CONG-DIST              A          2                              DFR
0681
1190     2 PIWA2-1EX-SENATE-DIST            A          2                              DFR
0682
1200     2 PIWA2-1EX-COURT-DIST             A          2                              DFR
0683
1210     2 PIWA2-1EX-COUNCIL-DIST           A          2                              DFR
0684
1220   *  *                                 *       **** *****                        C
1230     2 PIWA2-1EX-HEALTH-CENTER-DIST     A          2                              DFR
0685
1240     2 PIWA2-1EX-HEALTH-AREA            A          4                              DFR
0686
1250     2 PIWA2-1EX-SANI-DIST              A          3                              DFR
0687
1260   R 2 PIWA2-1EX-SANI-DIST                                                        DRR
0688
1270     3 PIWA2-1EX-SANI-DIST-BORO         A          1                              DFR
0689
1280     3 PIWA2-1EX-SANI-DIST-NUM          A          2                              DFR
0690
1290     2 PIWA2-1EX-SANI-SUBSEC            A          2                              DFR
0691
1300     2 PIWA2-1EX-SANI-REG               A          5                              DFR
0692
1310     2 PIWA2-1EX-SANI-REC               A          3                              DFR
0693
1320     2 PIWA2-1EX-POLICE-DIST            A          4                              DFR
0694
1330   R 2 PIWA2-1EX-POLICE-DIST                                                      DRR
0695
1340     3 PIWA2-1EX-POL-PAT-BORO-CMD       A          1                              DFR
0696
1350     3 PIWA2-1EX-POL-PRECINCT           A          3                              DFR
0697
1360     2 PIWA2-1EX-FIRE-DIV               A          2                              DFR
0698
1370     2 PIWA2-1EX-FIRE-BAT               A          2                              DFR
0699
1380     2 PIWA2-1EX-FIRE-CO                A          4                              DFR
0700
1390   R 2 PIWA2-1EX-FIRE-CO                                                          DRR
```

```
0701
1400      3 PIWA2-1EX-FIRE-CO-TYPE           A          1                                DFR
0702
1410      3 PIWA2-1EX-FIRE-CO-NUM            A          3                                DFR
0703
1420      2 PIWA2-1EX-SCHL-DIST-SPLIT-FLAG   A          1                                DFR
0704
1430      2 PIWA2-1EX-SCHL-DIST              A          2                                DFR
0705
1440      2 PIWA2-1EX-DYN-BLK                A          3                                DFR
0706
1450      2 PIWA2-1EX-POLICE-PAT-BORO        A          2                                DFR
0707
1460      2 PIWA2-1EX-FEATURE-TYPE           A          1                                DFR
0708
1470      2 PIWA2-1EX-SEGMENT-TYPE           A          1                                DFR
0709
1480      2 PIWA2-1EX-ALX                    A          1                                DFR
0710
1490      2 PIWA2-1EX-COINCIDENT-SEG-CTR     A          1                                DFR
0711
1500      2 FILLER-290                       A          3                                DFR
0712
1510      2 PIWA2-1EX-1990-CENSUS-TRACT      A          6                                DFR
0713
1520      2 PIWA2-1EX-2010-CENSUS-TRACT      A          6                                DFR
0714
1530      2 PIWA2-1EX-2010-CENSUS-BLOCK      A          4                                DFR
0715
1540      2 PIWA2-1EX-2010-CENSUS-BLOCK-SUF  A          1                                DFR
0716
1550      2 PIWA2-1EX-2000-CENSUS-TRACT      A          6 /* NA                          DFR
0717
1560      2 PIWA2-1EX-2000-CENSUS-BLOCK      A          4 /* NA                          DFR
0718
1570      2 PIWA2-1EX-2000-CENSUS-BLOCK-SUF  A          1 /* NA                          DFR
0719
1580      2 PIWA2-1EX-NTA                    A          4 /*NEIGHBORHOOD                   DFR
0720
1590    *   *                                            /*TABULATION AREA*/               C
1600      2 PIWA2-1EX-SANIT-SNOW-PRIORITY    A          1 /*SANITATION STRT                DFR
0721
1610    *   *                                            /*SNOW PRIORITY                   C
1620      2 PIWA2-1EX-SANIT-ORGANICS         A          5                                DFR
0722
```

```
1630      2 PIWA2-1EX-SANIT-BULK-PICK-UP     A          5 /* V16.4 ADDITION                DFR
0723
1640    * 2 PIWA2-1EX-SANIT-RESERVED         A          5                                CFR
0723
1650      2 PIWA2-1EX-HURRICANE-ZONE         A          2 /*OEM HURRICANE EVAC ZONE        DFR
0724
1660      2 FILLER-1EX-300                   A         11                                DFR
0725
1670      2 PIWA2-1EX-UHNS                   A         11                                DFR
0726
1680      2 PIWA2-1EX-REAL-B7SC              A          8                                DFR
0727
1690      2 PIWA2-1EX-SEGMENT-ID             A          7                                DFR
0728
1700      2 PIWA2-1EX-CURVE-FLAG             A          1                                DFR
0729
1710      2 PIWA2-1EX-LGC                    A          8                                DFR
0730
1720      2 PIWA2-1EX-BOE-PTR                A          1                                DFR
0731
1730      2 PIWA2-1EX-AZIMUTH                A          3                                DFR
0732
1740      2 PIWA2-1EX-ORIENT                 A          1                                DFR
0733
1750      2 PIWA2-1EX-X-LOW                  A          7                                DFR
0734
1760      2 PIWA2-1EX-Y-LOW                  A          7                                DFR
0735
1770      2 PIWA2-1EX-Z-LOW                  A          7                                DFR
0736
1780      2 PIWA2-1EX-X-HI                   A          7                                DFR
0737
1790      2 PIWA2-1EX-Y-HI                   A          7                                DFR
0738
1800      2 PIWA2-1EX-Z-HI                   A          7                                DFR
0739
1810      2 PIWA2-1EX-X-CC                   A          7                                DFR
0740
1820      2 PIWA2-1EX-Y-CC                   A          7                                DFR
0741
1830      2 PIWA2-1EX-Z-CC                   A          7                                DFR
0742
1840      2 PIWA2-1EX-RADIUS                 A          7                                DFR
0743
1850      2 PIWA2-1EX-SECANT                 A          1                                DFR
```

```
0744
1860      2 PIWA2-1EX-ANGLE-FROM            A          5                                DFR
0745
1870      2 PIWA2-1EX-ANGLE-TO              A          5                                DFR
0746
1880      2 PIWA2-1EX-NODE-FROM             A          7                                DFR
0747
1890      2 PIWA2-1EX-NODE-TO               A          7                                DFR
0748
1900      2 PIWA2-1EX-VANITY-LION           A         10                                DFR
0749
1910      2 PIWA2-1EX-SOS                   A          1                                DFR
0750
1920      2 PIWA2-1EX-SPLIT-LOHSN           A         11                                DFR
0751
1930      2 PIWA2-1EX-TD                    A          1                                DFR
0752
1940      2 PIWA2-1EX-TR                    A         10                                DFR
0753
1950      2 PIWA2-1EX-CURVE-FRACTION        A          3                                DFR
0754
1960      2 PIWA2-1EX-ROADWAY-TYPE          A          2                                DFR
0755
1970      2 PIWA2-1EX-PHYSICAL-ID           A          7                                DFR
0756
1980      2 PIWA2-1EX-GENERIC-ID            A          7                                DFR
0757
1990      2 PIWA2-1EX-INTP-ID               A          7                                DFR
0758
2000      2 PIWA2-1EX-INTF-ID               A          7                                DFR
0759
2010      2 PIWA2-1EX-BIKE-LANE-2           A          2 /* V16.4 ADDITION              DFR
2020      2 PIWA2-1EX-BIKE-TRAFFIC-DIR      A          2 /* V17.1 ADDITION              DFR
2030      2 PIWA2-1EX-FILL450               A          3 /* V17.1 ALTERATION            DFR
0760
2040    * 2 PIWA2-1EX-FILL450               A          5 /* V16.4 ALTERATION            CFR
0760
2050    * 2 PIWA2-1EX-FILL450               A          7 /* V16.1 REPLACEMENT           CFR
0760
2060      2 PIWA2-1EX-STREET-STATUS         A          1                                DFR
0761
2070      2 PIWA2-1EX-STREET-WIDTH          A          3                                DFR
0762
2080      2 PIWA2-1EX-STREET-IRR            A          1                                DFR
0763
```

```
2090      2 PIWA2-1EX-BIKE-LANE              A          1                                DFR
0764
2100      2 PIWA2-1EX-FED-CLASS-CODE         A          2                                DFR
0765
2110      2 PIWA2-1EX-ROW-TYPE               A          1                                DFR
0766
2120      2 PIWA2-1EX-LGC-LIST-2             A         10                                DFR
0767
2130      2 PIWA2-1EX-LEGACY-SEG-ID          A          7                                DFR
0768
2140      2 PIWA2-1EX-LGC-LIST-FROM-1        A         10                                DFR
0769
2150      2 PIWA2-1EX-LGC-LIST-TO-1          A         10                                DFR
0770
2160      2 PIWA2-1EX-LGC-LIST-FROM-2        A         10                                DFR
0771
2170      2 PIWA2-1EX-LGC-LIST-TO-2          A         10                                DFR
0772
2180      2 PIWA2-1EX-NOCROSS-FLG            A          1                                DFR
0773
2190      2 PIWA2-1EX-IND-SEG-LEN            A          5                                DFR
0774
2200      2 PIWA2-1EX-NTA-NAME               A         75                                DFR
0775
2210      2 PIWA2-1EX-USPS-CITY-NAME         A         25 /*USPS PREFERRED CITY NAME     DFR
0776
2220      2 PIWA2-1EX-LATITUDE               A          9                                DFR
0777
2230      2 PIWA2-1EX-LONGITUDE              A         11                                DFR
0778
2240      2 PIWA2-1EX-SEG-FROM-NODE          A          7                                DFR
2250      2 PIWA2-1EX-SEG-TO-NODE            A          7                                DFR
2260      2 PIWA2-1EX-SEG-FROM-XYZ           A         21                                DFR
2270      2 PIWA2-1EX-SEG-TO-XYZ             A         21                                DFR
2280      2 PIWA2-1EX-BLOCKFACE-ID           A         10 /* V16.1 ADD                  DFR
2290      2 PIWA2-1EX-NBR-TRAVEL-LANES       A          2 /* V16.1 ADD                  DFR
2300      2 PIWA2-1EX-NBR-PARK-LANES         A          2 /* V16.1 ADD                  DFR
2310      2 PIWA2-1EX-NBR-TOTAL-LANES        A          2 /* V16.1 ADD                  DFR
2320      2 PIWA2-1EX-STR-WIDTH-MAX          A          3 /* V16.4 ADDITION             DFR
2330      2 PIWA2-1EX-SPEED-LIMIT            A          2 /* V17.4 ADDITION             DFR
2340      2 PIWA2-1EX-PUMA-CODE              A          5 /* V18.1 ADDITION             DFR
2350      2 FILLER-1EX-500                   A        245 /* V16.1,V16.4,V18.1 MODS     DFR
0779
2360    * 2 FILLER-1EX-500                   A        255 /* V16.1 MOD                  CFR
0779
```

```
2370   * ** ***  THE FOLLOWING FIELDS ARE IN     ADDITION TO 1E ****************          CK
0432
2380      2 PIWA2-1EX-REASON-CODE            A          1                                DFR
0780
2390      2 PIWA2-1EX-REASON-CODE-QUAL       A          1                                DFR
0781
2400      2 PIWA2-1EX-WARN-CODE              A          2                                DFR
0782
2410      2 PIWA2-1EX-RETURN-CODE            A          2                                DFR
0783
2420      2 PIWA2-1EX-NUM-X-STS-LO-END       A          1                                DFR
0784
2430      2 PIWA2-1EX-LO-B7SC                A          8 (1:5)
DFRI1   0785     M
2440      2 PIWA2-1EX-NUM-X-STS-HI-END       A          1                                DFR
0786
2450      2 PIWA2-1EX-HI-B7SC                A          8 (1:5)
DFRI1   0787     M
2460      2 PIWA2-1EX-LO-ST-NAME             A         32 (1:5)
DFRI1   0788     M
2470      2 PIWA2-1EX-HI-ST-NAME             A         32 (1:5)
DFRI1   0789     M
2480      2 PIWA2-1EX-BOE-B7SC               A          8                                DFR
0790
2490      2 PIWA2-1EX-BOE-ST-NAME            A         32                                DFR
0791
2500      2 FILLER-1EX-600                   A         52                                DFR
0792
2510   *  *  END OF FUNCTION 1/1E LAYOUT     *       **** *******                        C
2520   *  - ------------------------------- -       ---- ------------------------------- C
2530   *  *  BEGNING OF FCT 1A EXTENDED      * ********** *******                        C
2540   R  1 GEOLP2AL                                                                     DRR
0793
2550      2 PIWA2-1AX-ACCESS-KEY             A         21                                DFR
0794
2560      2 PIWA2-1AX-CONT-PARITY            A          1 /* OR DUP ADDR IND              DFR
0795
2570      2 PIWA2-1AX-LOW-HOUSENUM           A         11 /* SORT FORMAT                  DFR
0796
2580      2 PIWA2-1AX-BBL                    A         10                                DFR
0797
2590   R  2 PIWA2-1AX-BBL                                                                DRR
0798
2600      3 PIWA2-1AX-BBL-BORO               A          1                                DFR
0799
```

```
2610      3 PIWA2-1AX-BLOCK                 A          5                                DFR
0800
2620      3 PIWA2-1AX-LOT                   A          4                                DFR
0801
2630      2 PIWA2-1AX-LOT-VERSION           A          1 /* NYI */                     DFR
0802
2640      2 PIWA2-1AX-SCC                   A          1                                DFR
0803
2650      2 FILLER-1AX-100                  A          1                                DFR
0804
2660      2 PIWA2-1AX-GENERAL-LOT-INFO                                                  DSR
0805
2670      3 PIWA2-1AX-RPAD-BLDG-CLASS       A          2                                DKR
0806
2680      3 PIWA2-1AX-CORNER-CODE           A          2                                DKR
0807
2690      3 PIWA2-1AX-NUM-OF-STRUCTURES     A          4                                DKR
0808
2700      3 PIWA2-1AX-NUM-OF-BLOCKFACES     A          2                                DKR
0809
2710      3 PIWA2-1AX-INTERIOR-FLAG         A          1                                DKR
0810
2720      3 PIWA2-1AX-VACANT-FLAG           A          1                                DKR
0811
2730      3 PIWA2-1AX-IRREG-LOT-FLAG        A          1                                DKR
0812
2740      2 PIWA2-1AX-MARBLE-RIKERS-FLAG    A          1                                DKR
0813
2750      2 PIWA2-1AX-ADDR-LIST-OVFLOW-FLAG A          1                                DKR
0814
2760      2 PIWA2-1AX-STROLL-KEY            A         19                                DKR
0815
2770    R 2 PIWA2-1AX-STROLL-KEY                                                        DRR
0816
2780      3 PIWA2-1AX-STROLL-BORO           A          1                                DKR
0817
2790      3 PIWA2-1AX-STROLL-5SC            A          5                                DKR
0818
2800      3 PIWA2-1AX-STROLL-SIDE-OF-STR    A          1 /* L OR R                      DKR
0819
2810      3 PIWA2-1AX-STROLL-HI-HOUSENUM    A         11 /* SORT FORMAT                 DKR
0820
2820      3 FILLER-1AX-200                  A          1                                DKR
0821
2830      2 FILLER-1AX-300                  A          1 /* FOR GSS USE                 DKR
```

```
0822
2840      2 PIWA2-1AX-BIN                    A          7                                DKR
0823
2850      2 PIWA2-1AX-CONDO-FLAG             A          1                                DKR
0824
2860      2 FILLER-1AX-400                   A          1                                DKR
0825
2870      2 PIWA2-1AX-RPAD-CONDO-ID-NUM      A          4                                DKR
0826
2880      2 PIWA2-1AX-CONDO-UNIT-ID-NUM      A          7                                DKR
0827
2890      2 PIWA2-1AX-CONDO-BILL-BBL         A         10                                DKR
0828
2900      2 PIWA2-1AX-CONDO-BILL-BBL-VER     A          1                                DKR
0829
2910      2 PIWA2-1AX-CONDO-BILL-BBL-SCC     A          1                                DKR
0830
2920      2 PIWA2-1AX-CONDO-LOW-BBL          A         10                                DKR
0831
2930      2 PIWA2-1AX-CONDO-LOW-BBL-VER      A          1                                DKR
0832
2940      2 PIWA2-1AX-CONDO-HIGH-BBL         A         10                                DKR
0833
2950      2 PIWA2-1AX-CONDO-HIGH-BBL-VER     A          1                                DKR
0834
2960      2 FILLER-1AX-600                   A         15                                DKR
0835
2970      2 PIWA1-1AX-COOP-NUM               A          4                                DKR
0836
2980      2 PIWA2-1AX-SANBORN                A          8                                DKR
0837
2990    R 2 PIWA2-1AX-SANBORN                                                            DRR
0838
3000      3 PIWA2-1AX-SANBORN-BORO           A          1                                DKR
0839
3010      3 PIWA2-1AX-SANBORN-VOL            A          3                                DKR
0840
3020      3 PIWA2-1AX-SANBORN-PAGE           A          4                                DKR
0841
3030      2 PIWA2-1AX-COMMERC-DIST           A          5                                DKR
0842
3040      2 PIWA2-1AX-DOF-MAP-BORO           A          1                                DKR
0843
3050      2 PIWA2-1AX-DOF-MAP-SECVOL         A          4                                DKR
0844
```

```
3060      2 PIWA2-1AX-DOF-MAP-PAGE           A          4                                DKR
0845
3070      2 FILLER-1AX-RESERVED-DCP          A          3                                DKR
0846
3080      2 PIWA2-1AX-LATITUDE               A          9                                DKR
0847
3090      2 PIWA2-1AX-LONGITUDE              A         11                                DKR
0848
3100      2 PIWA2-1AX-X-COORD                A          7                                DKR
0849
3110      2 PIWA2-1AX-Y-COORD                A          7                                DKR
0850
3120      2 PIWA2-1AX-BID                    A          6                                DKR
0851
3130      2 PIWA2-1AX-TPAD-BIN-ST            A          1 /* CURRENT STATUS */           DKR
0852
3140      2 PIWA2-1AX-TPAD-NEW-BIN           A          7 /* NEW BIN */                  DKR
0853
3150      2 PIWA2-1AX-TPAD-NEW-BIN-ST        A          1 /* NEW BIN STATUS */           DKR
0854
3160      2 PIWA2-1AX-TPAD-CONFLICT          A          1 /* CONFLICT FLAG */            DKR
0855
3170      2 PIWA2-1AX-DCP-ZONE-MAP           A          3 /* V17.4 ADDITION              DKR
3180      2 FILLER-1AX-650                   A          6                                DKR
0856
3190      2 FILLER-1AX-700                   A          8 /* FOR GSS USE                 DKR
0857
3200      2 PIWA2-1AX-REASON-CODE            A          1                                DKR
0858
3210      2 PIWA2-1AX-REASON-CODE-QUAL       A          1                                DKR
0859
3220      2 PIWA2-1AX-WARN-CODE              A          2                                DKR
0860
3230      2 PIWA2-1AX-RETURN-CODE            A          2                                DKR
0861
3240      2 FILLER-1AX-750                   A        108                                DKR
0862
3250      2 PIWA2-1AX-NUM-OF-ADDR            A          4                                DKR
0863
3260      2 PIWA2-1AX-LIST-OF-ADDR                        (1:21)
DSRI1   0864     M
3270      3 PIWA2-1AX-LIST-LOW-HOUSENUM      A         16 /* DISPLAY FORMAT              DKR
0865
3280      3 PIWA2-1AX-LIST-HI-HOUSENUM       A         16 /* DISPLAY FORMAT              DKR
0866
```

```
3290      3 PIWA2-1AX-LIST-BORO              A          1                                DKR
0867
3300      3 PIWA2-1AX-LIST-5SC               A          5                                DKR
0868
3310      3 PIWA2-1AX-LIST-LGC               A          2                                DKR
0869
3320      3 PIWA2-1AX-LIST-BIN               A          7                                DKR
0870
3330      3 PIWA2-1AX-LIST-SIDE-OF-STR       A          1 /* L OR R                      DKR
0871
3340      3 PIWA2-1AX-ADDR-TYPE              A          1 /* P=NAP, B=NAB,          MAL    DKR
0872
3350    R 3 PIWA2-1AX-ADDR-TYPE                           /* REDEF. BEGIN : PIWA2-1AX-ADDR DRR
0873
3360      4 PIWA2-1AX-LIST-ADDR-TYPE         A          1 /* BLANK=NORMAL                 DKR
0874
3370    * *                                             /* BLANK=NORMAL                 C
3380      3 PIWA2-1AX-TPAD-STATUS            A          1 /* 0 - 9                        DKR
0875
3390    R 3 PIWA2-1AX-TPAD-STATUS                         /* REDEF. BEGIN : PIWA2-1AX-TPAD DRR
0876
3400      4 PIWA2-1AX-LIST-TPAD-STATUS       A          1                                DKR
0877
3410      3 PIWA2-1AX-ST-NAME                A         32 /* 0 - 9                        DKR
0878
3420    R 3 PIWA2-1AX-ST-NAME                             /* REDEF. BEGIN : PIWA2-1AX-ST-N DRR
0879
3430      4 PIWA2-1AX-LIST-ST-NAME           A         32                                DKR
0880
3440      3 FILLER-800                       A         34                                DKR
0881
3450    * ** END OF FUNCTION 1A EXTENDED **** * ********** **********************         C
3460    * -- ------------------------------- - ---------- --------------------------       C
3470    * ** BEGINNING OF FUNCTION 1B ******* * ********** **********************         C
3480    R 1 GEOLP2AL                                                                      DRR
0882
3490      2 PIWA2-1B-1-ACCESS-KEY            A         21                                DFR
0883
3500      2 PIWA2-1B-1-CONT-PARITY           A          1 /* (OR DUP ADDR IND)            DFR
0884
3510      2 PIWA2-1B-1-LOW-HOUSENUM          A         11 /* SORT FORMAT                  DFR
0885
3520      2 PIWA2-1B-1-HI-HOUSENUM           A         11 /* SORT FORMAT                  DFR
0886
3530      2 PIWA2-1B-1-PREFERRED-LGC         A          2                                DFR
```

```
0887
3540      2 PIWA2-1B-1-NUM-X-ST-LOW-END      A          1                                DFR
0888
3550      2 PIWA2-1B-1-LOW-B5SC              A          6 (1:5) /* 30-BYTES
DFRI1   0889     M
3560      2 PIWA2-1B-1-NUM-X-ST-HI-END       A          1                                DFR
0890
3570      2 PIWA2-1B-1-HI-B5SC               A          6 (1:5) /* 30-BYTES
DFRI1   0891     M
3580      2 PIWA2-1B-1-LIONKEY               A         10                                DFR
0892
3590   R  2 PIWA2-1B-1-LIONKEY                                                           DRR
0893
3600      3 PIWA2-1B-1-LION-BORO             A          1                                DFR
0894
3610      3 PIWA2-1B-1-LION-FACECODE         A          4                                DFR
0895
3620      3 PIWA2-1B-1-LION-SEQ              A          5                                DFR
0896
3630      2 PIWA2-1B-1-SPECIAL-ADDR-FLAG     A          1                                DFR
0897
3640      2 PIWA2-1B-1-SIDE-OF-STR           A          1                                DFR
0898
3650      2 PIWA2-1B-1-SEG-LEN               A          5                                DFR
0899
3660      2 PIWA2-1B-1-X-COORD               A          7                                DFR
0900
3670      2 PIWA2-1B-1-Y-COORD               A          7                                DFR
0901
3680      2 FILLER-1B-1-100                  A          7 /* FOR ZCOORD                   DFR
0902
3690      2 PIWA2-1B-1-CD-ELIGIBLE           A          1                                DFR
0903
3700      2 PIWA2-1B-1-MARBLE-RIKERS-FLAG    A          1                                DFR
0904
3710      2 PIWA2-1B-1-DOT-SLA               A          1                                DFR
0905
3720      2 PIWA2-1B-1-COM-DIST              A          3                                DFR
0906
3730   R  2 PIWA2-1B-1-COM-DIST                                                           DRR
0907
3740      3 PIWA2-1B-1-COM-DIST-BORO         A          1                                DFR
0908
3750      3 PIWA2-1B-1-COM-DIST-NUM          A          2                                DFR
0909
```

```
3760      2 PIWA2-1B-1-ZIP                  A          5                                DFR
0910
3770   *  *                                 *       **** *****                          C
3780   *  *  THE FN1E FIELDS ARE VALID ONLY *       **** *****                          C
3790   *  *  FOR FUNCTION 1E, NOT FUNC 1.   *       **** *****                          C
3800      2 PIWA2-1B-1-ELECT-DIST           A          3                                DFR
0911
3810      2 PIWA2-1B-1-ASSEM-DIST           A          2                                DFR
0912
3820      2 PIWA2-1B-1-SPLIT-ED-FLAG        A          1                                DFR
0913
3830      2 PIWA2-1B-1-CONG-DIST            A          2                                DFR
0914
3840      2 PIWA2-1B-1-SENATE-DIST          A          2                                DFR
0915
3850      2 PIWA2-1B-1-COURT-DIST           A          2                                DFR
0916
3860      2 PIWA2-1B-1-COUNCIL-DIST         A          2                                DFR
0917
3870   *  *                                 *       **** *****                          C
3880      2 PIWA2-1B-1-HEALTH-CENTER-DIST   A          2                                DFR
0918
3890      2 PIWA2-1B-1-HEALTH-AREA          A          4                                DFR
0919
3900      2 PIWA2-1B-1-SANI-DIST            A          3                                DFR
0920
3910   R  2 PIWA2-1B-1-SANI-DIST                                                        DRR
0921
3920      3 PIWA2-1B-1-SANI-DIST-BORO       A          1                                DFR
0922
3930      3 PIWA2-1B-1-SANI-DIST-NUM        A          2                                DFR
0923
3940      2 PIWA2-1B-1-SANI-SUBSEC          A          2                                DFR
0924
3950      2 PIWA2-1B-1-SANI-REG             A          5                                DFR
0925
3960      2 PIWA2-1B-1-SANI-REC             A          3                                DFR
0926
3970      2 PIWA2-1B-1-POLICE-DIST          A          4                                DFR
0927
3980   R  2 PIWA2-1B-1-POLICE-DIST                                                      DRR
0928
3990      3 PIWA2-1B-1-POL-PAT-BORO-CMD     A          1                                DFR
0929
4000      3 PIWA2-1B-1-POL-PRECINCT         A          3                                DFR
```

```
0930
4010      2 PIWA2-1B-1-FIRE-DIV              A          2                                DFR
0931
4020      2 PIWA2-1B-1-FIRE-BAT              A          2                                DFR
0932
4030      2 PIWA2-1B-1-FIRE-CO               A          4                                DFR
0933
4040    R 2 PIWA2-1B-1-FIRE-CO                                                            DRR
0934
4050      3 PIWA2-1B-1-FIRE-CO-TYPE          A          1                                DFR
0935
4060      3 PIWA2-1B-1-FIRE-CO-NUM           A          3                                DFR
0936
4070      2 FILLER-1B-1-250                  A          1 /* WAS SPLIT COM SCHL           DFR
0937
4080      2 PIWA2-1B-1-SCHL-DIST             A          2                                DFR
0938
4090      2 PIWA2-1B-1-DYN-BLK               A          3                                DFR
0939
4100      2 PIWA2-1B-1-POLICE-PAT-BORO       A          2                                DFR
0940
4110      2 PIWA2-1B-1-FEATURE-TYPE          A          1                                DFR
0941
4120      2 PIWA2-1B-1-SEGMENT-TYPE          A          1                                DFR
0942
4130      2 PIWA2-1B-1-ALX                   A          1                                DFR
0943
4140      2 PIWA2-1B-1-COINCIDENT-SEG-CTR    A          1                                DFR
0944
4150      2 FILLER-1B-1-290                  A          3                                DFR
0945
4160      2 PIWA2-1B-1-1990-CENSUS-TRACT     A          6                                DFR
0946
4170      2 PIWA2-1B-1-2010-CENSUS-TRACT     A          6                                DFR
0947
4180      2 PIWA2-1B-1-2010-CENSUS-BLOCK     A          4                                DFR
0948
4190      2 PIWA2-1B-1-2010-CENSUS-BLOCK-SUF A          1                                DFR
0949
4200      2 PIWA2-1B-1-2000-CENSUS-TRACT     A          6 /* NA                          DFR
0950
4210      2 PIWA2-1B-1-2000-CENSUS-BLOCK     A          4 /* NA                          DFR
0951
4220      2 PIWA2-1B-1-2000-CENSUS-BLOCK-SUF A          1 /* NA                          DFR
0952
```

```
4230      2 PIWA2-1B-1-NTA                  A          4 /*NEIGHBORHOOD                  DFR
0953
4240   *  *                                            /*TABULATION AREA                C
4250      2 PIWA2-1B-1-SANIT-SNOW-PRIORITY  A          1 /*SANITATION STRT               DFR
0954
4260   *  *                                            /*SNOW PRIORITY                  C
4270      2 PIWA2-1B-1-SANIT-ORGANICS       A          5                                 DFR
0955
4280      2 PIWA2-1B-1-SANIT-BULK-PICK-UP   A          5 /* V16.4 ADDITION              DFR
0956
4290   *  2 PIWA2-1B-1-SANIT-RESERVED       A          5                                 CFR
0956
4300      2 PIWA2-1B-1-HURRICANE-ZONE       A          2 /*OEM HURRICANE EVAC ZONE       DFR
0957
4310      2 FILLER-1B-1-300                 A         11                                 DFR
0958
4320      2 PIWA2-1B-1-UHNS                 A         11 /* UNDERLYING HNS               DFR
0959
4330      2 PIWA2-1B-1-REAL-B7SC            A          8                                 DFR
0960
4340      2 PIWA2-1B-1-SEGMENT-ID           A          7                                 DFR
0961
4350      2 PIWA2-1B-1-CURVE-FLAG           A          1                                 DFR
0962
4360      2 PIWA2-1B-1-LGCS                 A          8                                 DFR
0963
4370      2 PIWA2-1B-1-BOE-PTR              A          1                                 DFR
0964
4380      2 PIWA2-1B-1-AZIMUTH              A          3                                 DFR
0965
4390      2 PIWA2-1B-1-ORIENT               A          1                                 DFR
0966
4400      2 PIWA2-1B-1-X-LOW                A          7                                 DFR
0967
4410      2 PIWA2-1B-1-Y-LOW                A          7                                 DFR
0968
4420      2 PIWA2-1B-1-Z-LOW                A          7                                 DFR
0969
4430      2 PIWA2-1B-1-X-HI                 A          7                                 DFR
0970
4440      2 PIWA2-1B-1-Y-HI                 A          7                                 DFR
0971
4450      2 PIWA2-1B-1-Z-HI                 A          7                                 DFR
0972
4460      2 PIWA2-1B-1-X-CC                 A          7                                 DFR
```

```
0973
4470      2 PIWA2-1B-1-Y-CC                 A          7                                DFR
0974
4480      2 PIWA2-1B-1-Z-CC                 A          7                                DFR
0975
4490      2 PIWA2-1B-1-RADIUS               A          7                                DFR
0976
4500      2 PIWA2-1B-1-SECANT               A          1                                DFR
0977
4510      2 PIWA2-1B-1-ANGLE-FROM           A          5                                DFR
0978
4520      2 PIWA2-1B-1-ANGLE-TO             A          5                                DFR
0979
4530      2 PIWA2-1B-1-NODE-FROM            A          7                                DFR
0980
4540      2 PIWA2-1B-1-NODE-TO              A          7                                DFR
0981
4550      2 PIWA2-1B-1-VANITY-LION          A         10                                DFR
0982
4560      2 PIWA2-1B-1-SOS                  A          1                                DFR
0983
4570      2 PIWA2-1B-1-SPLIT-LOHSN          A         11                                DFR
0984
4580      2 PIWA2-1B-1-TD                   A          1                                DFR
0985
4590      2 PIWA2-1B-1-TR                   A         10                                DFR
0986
4600      2 PIWA2-1B-1-CURVE-FRACTION       A          3                                DFR
0987
4610      2 PIWA2-1B-1-ROADWAY-TYPE         A          2                                DFR
0988
4620      2 PIWA2-1B-1-PHYSICAL-ID          A          7                                DFR
0989
4630      2 PIWA2-1B-1-GENERIC-ID           A          7                                DFR
0990
4640      2 PIWA2-1B-1-INTP-ID              A          7                                DFR
0991
4650      2 PIWA2-1B-1-INTF-ID              A          7                                DFR
0992
4660      2 PIWA2-1B-1-BIKE-LANE-2          A          2                                DFR
4670      2 PIWA2-1B-1-BIKE-TRAFFIC-DIR     A          2 /* V17.1 ADDITION             DFR
4680      2 PIWA2-1B-1-FILL450              A          3 /* V17.1 ALTERATION           DFR
0993
4690    * 2 PIWA2-1B-1-FILL450              A          5 /* V16.4 ALTERATION           CFR
0993
```

```
4700   *  2 PIWA2-1B-1-FILL450              A          7 /* V16.1 REPLACEMENT            CFR
0993
4710      2 PIWA2-1B-1-STREET-STATUS        A          1                                DFR
0994
4720      2 PIWA2-1B-1-STREET-WIDTH         A          3                                DFR
0995
4730      2 PIWA2-1B-1-STREET-WIDTH-IRR     A          1                                DFR
0996
4740      2 PIWA2-1B-1-BIKE-LANE            A          1                                DFR
0997
4750      2 PIWA2-1B-1-FED-CLASS-CODE       A          2                                DFR
0998
4760      2 PIWA2-1B-1-ROW-TYPE             A          1                                DFR
0999
4770      2 PIWA2-1B-1-LGC-LIST-2           A         10                                DFR
1000
4780      2 PIWA2-1B-1-LEGACY-SEG-ID        A          7                                DFR
1001
4790      2 PIWA2-1B-1-LGC-LIST-FROM-1      A         10                                DFR
1002
4800      2 PIWA2-1B-1-LGC-LIST-TO-1        A         10                                DFR
1003
4810      2 PIWA2-1B-1-LGC-LIST-FROM-2      A         10                                DFR
1004
4820      2 PIWA2-1B-1-LGC-LIST-TO-2        A         10                                DFR
1005
4830      2 PIWA2-1B-1-NOCROSS-FLG          A          1                                DFR
1006
4840      2 PIWA2-1B-1-IND-SEG-LEN          A          5                                DFR
1007
4850      2 PIWA2-1B-1-NTA-NAME             A         75                                DFR
1008
4860      2 PIWA2-1B-1-USPS-CITY-NAME       A         25 /*USPS PREFERRED CITY NAME     DFR
1009
4870      2 PIWA2-1B-1-LATITUDE             A          9                                DFR
1010
4880      2 PIWA2-1B-1-LONGITUDE            A         11                                DFR
1011
4890      2 PIWA2-1B-1-SEG-FROM-NODE        A          7                                DFR
4900      2 PIWA2-1B-1-SEG-TO-NODE          A          7                                DFR
4910      2 PIWA2-1B-1-SEG-FROM-XYZ         A         21                                DFR
4920      2 PIWA2-1B-1-SEG-TO-XYZ           A         21                                DFR
4930      2 PIWA2-1B-1-BLOCKFACE-ID         A         10 /* V16.1 ADD                  DFR
4940      2 PIWA2-1B-1-NBR-TRAVEL-LANES     A          2 /* V16.1 ADD                  DFR
4950      2 PIWA2-1B-1-NBR-PARK-LANES       A          2 /* V16.1 ADD                  DFR
```

```
4960      2 PIWA2-1B-1-NBR-TOTAL-LANES       A          2 /* V16.1 ADD                    DFR
4970      2 PIWA2-1B-1-STR-WIDTH-MAX         A          3 /* V16.4 ADDITION               DFR
4980      2 PIWA2-1B-1-SPEED-LIMIT           A          2 /* V17.4 ADDITION               DFR
4990      2 PIWA2-1B-1-PUMA-CODE             A          5 /* V18.1 ADDITION               DFR
5000      2 FILLER-1B-1-500                  A        245 /* V16.4,V18.1 MOD              DFR
1012
5010    *  2 FILLER-1B-1-500                  A        255 /* V16.1 MOD                    CFR
1012
5020    * ** **** THE FOLLOWING FIELDS ARE IN   ADDITION   TO 1/1E***************          C
5030      2 PIWA2-1B-1-REASON-CODE           A          1                                DFR
1013
5040      2 PIWA2-1B-1-REASON-CODE-QUAL      A          1                                DFR
1014
5050      2 PIWA2-1B-1-WARN-CODE             A          2                                DFR
1015
5060      2 PIWA2-1B-1-RETURN-CODE           A          2                                DFR
1016
5070      2 PIWA2-1B-1-NUM-X-STS-LO-END      A          1                                DFR
1017
5080      2 PIWA2-1B-1-LO-B7SC               A          8 (1:5)
DFRI1   1018     M
5090      2 PIWA2-1B-1-NUM-X-STS-HI-END      A          1                                DFR
1019
5100      2 PIWA2-1B-1-HI-B7SC               A          8 (1:5)
DFRI1   1020     M
5110      2 PIWA2-1B-1-LO-ST-NAME            A         32 (1:5)
DFRI1   1021     M
5120      2 PIWA2-1B-1-HI-ST-NAME            A         32 (1:5)
DFRI1   1022     M
5130      2 PIWA2-1B-1-BOE-B7SC              A          8                                DFR
1023
5140      2 PIWA2-1B-1-BOE-ST-NAME           A         32                                DFR
1024
5150      2 FILLER-1B-1-600                  A         52                                DFR
1025
5160    *  * ******************************** * ********** *****************             C
5170    *  * THE FOLLOWING FIELDS ARE         * ********** ********                       C
5180    *  *     PROPERTY LEVEL FIELDS        * ********** ********                       C
5190      2 PIWA2-1B-1A-ACCESS-KEY           A         21 /*CHG FROM LEVEL 3 TO 2???      DFR
1026
5200      2 PIWA2-1B-1A-CONT-PARITY          A          1 /* OR DUP ADDR IND              DFR
1027
5210      2 PIWA2-1B-1A-LOW-HOUSENUM         A         11 /* SORT FORMAT                  DFR
1028
5220      2 PIWA2-1B-1A-BBL                  A         10                                DFR
```

```
1029
5230   R  2 PIWA2-1B-1A-BBL                                                  DRR
1030
5240      3 PIWA2-1B-1A-BBL-BORO            A          1                    DFR
1031
5250      3 PIWA2-1B-1A-BLOCK               A          5                    DFR
1032
5260      3 PIWA2-1B-1A-LOT                 A          4                    DFR
1033
5270      2 PIWA2-1B-1A-LOT-VERSION         A          1 /* NYI */          DFR
1034
5280      2 PIWA2-1B-1A-SCC                 A          1                    DFR
1035
5290      2 FILLER-1B-1A-100                A          1                    DFR
1036
5300      2 PIWA2-1B-1A-GENERAL-LOT-INFO                                    DSR
1037
5310      3 PIWA2-1B-1A-RPAD-BLDG-CLASS     A          2                    DKR
1038
5320      3 PIWA2-1B-1A-CORNER-CODE         A          2                    DKR
1039
5330      3 PIWA2-1B-1A-NUM-OF-STRUCTURES   A          4                    DKR
1040
5340      3 PIWA2-1B-1A-NUM-OF-BLOCKFACES   A          2                    DKR
1041
5350      3 PIWA2-1B-1A-INTERIOR-FLAG       A          1                    DKR
1042
5360      3 PIWA2-1B-1A-VACANT-FLAG         A          1                    DKR
1043
5370      3 PIWA2-1B-1A-IRREG-LOT-FLAG      A          1                    DKR
1044
5380      2 PIWA2-1B-1A-MARBLE-RIKERS-FLAG  A          1                    DKR
1045
5390      2 PIWA2-1B-1A-ADDR-LIST-OVFLOW-FLG A        1 /*FLAG,FLG?????????  DKR
1046
5400      2 PIWA2-1B-1A-STROLL-KEY          A         19                    DKR
1047
5410   R  2 PIWA2-1B-1A-STROLL-KEY                                          DRR
1048
5420      3 PIWA2-1B-1A-STROLL-BORO         A          1                    DKR
1049
5430      3 PIWA2-1B-1A-STROLL-5SC          A          5                    DKR
1050
5440      3 PIWA2-1B-1A-STROLL-SIDE-OF-STR  A          1 /* L OR R         DKR
1051
```

```
5450      3 PIWA2-1B-1A-STROLL-HI-HOUSENUM   A         11 /* SORT FORMAT                  DKR
1052
5460      3 FILLER-1B-1A-200                 A          1                                 DKR
1053
5470      2 FILLER-1B-1A-300                 A          1 /* FOR GSS USE                  DKR
1054
5480      2 PIWA2-1B-1A-BIN                  A          7                                 DKR
1055
5490      2 PIWA2-1B-1A-CONDO-FLAG           A          1                                 DKR
1056
5500      2 FILLER-1B-1A-400                 A          1                                 DKR
1057
5510      2 PIWA2-1B-1A-RPAD-CONDO-ID-NUM    A          4                                 DKR
1058
5520      2 PIWA2-1B-1A-CONDO-UNIT-ID-NUM    A          7                                 DKR
1059
5530      2 PIWA2-1B-1A-CONDO-BILL-BBL       A         10                                 DKR
1060
5540      2 PIWA2-1B-1A-CONDO-BILL-BBL-VER   A          1                                 DKR
1061
5550      2 PIWA2-1B-1A-CONDO-BILL-BBL-SCC   A          1                                 DKR
1062
5560      2 PIWA2-1B-1A-CONDO-LOW-BBL        A         10                                 DKR
1063
5570      2 PIWA2-1B-1A-CONDO-LOW-BBL-VER    A          1                                 DKR
1064
5580      2 PIWA2-1B-1A-CONDO-HIGH-BBL       A         10                                 DKR
1065
5590      2 PIWA2-1B-1A-CONDO-HIGH-BBL-VER   A          1                                 DKR
1066
5600      2 FILLER-1B-1A-500                 A         15                                 DKR
1067
5610      2 PIWA1-1B-1A-COOP-NUM             A          4                                 DKR
1068
5620      2 PIWA2-1B-1A-SANBORN              A          8                                 DKR
1069
5630    R 2 PIWA2-1B-1A-SANBORN                                                            DRR
1070
5640      3 PIWA2-1B-1A-SANBORN-BORO         A          1                                 DKR
1071
5650      3 PIWA2-1B-1A-SANBORN-VOL          A          3                                 DKR
1072
5660      3 PIWA2-1B-1A-SANBORN-PAGE         A          4                                 DKR
1073
5670      2 PIWA2-1B-1A-COMMERC-DIST         A          5                                 DKR
```

```
1074
5680      2 PIWA2-1B-1A-DOF-MAP-BORO         A          1                                DKR
1075
5690      2 PIWA2-1B-1A-DOF-MAP-SECVOL       A          4                                DKR
1076
5700      2 PIWA2-1B-1A-DOF-MAP-PAGE         A          4                                DKR
1077
5710      2 FILLER-1B-1A-RESERVED-DCP        A          3                                DKR
1078
5720      2 PIWA2-1B-1A-LATITUDE             A          9                                DKR
1079
5730      2 PIWA2-1B-1A-LONGITUDE            A         11                                DKR
1080
5740      2 PIWA2-1B-1A-X-COORD              A          7                                DKR
1081
5750      2 PIWA2-1B-1A-Y-COORD              A          7                                DKR
1082
5760      2 PIWA2-1B-1A-BID                  A          6                                DKR
1083
5770      2 PIWA2-1B-1A-TPAD-BIN-ST          A          1 /* CURRENT STATUS */          DKR
1084
5780      2 PIWA2-1B-1A-TPAD-NEW-BIN         A          7 /* NEW BIN */                 DKR
1085
5790      2 PIWA2-1B-1A-TPAD-NEW-BIN-ST      A          1 /* NEW BIN STATUS */          DKR
1086
5800      2 PIWA2-1B-1A-TPAD-CONFLICT        A          1 /* CONFLICT FLAG */           DKR
1087
5810      2 PIWA2-1B-1A-DCP-ZONE-MAP         A          3 /* V17.4 ADDITION            DKR
5820      2 FILLER-1B-1A-650                 A          6                                DKR
1088
5830      2 FILLER-1B-1A-700                 A          8 /* FOR GSS USE               DKR
1089
5840      2 PIWA2-1B-1A-REASON-CODE          A          1                                DKR
1090
5850      2 PIWA2-1B-1A-REASON-CODE-FILL     A          1                                DKR
1091
5860      2 PIWA2-1B-1A-WARN-CODE            A          2                                DKR
1092
5870      2 PIWA2-1B-1A-RETURN-CODE          A          2                                DKR
1093
5880      2 FILLER-1B-1A-750                 A        108                                DKR
1094
5890      2 PIWA2-1B-1A-NUM-OF-ADDR          A          4                                DKR
1095
5900      2 PIWA2-1B-1A-LIST-OF-ADDR                      (1:21)
```

```
DSRI1   1096     M
5910      3 PIWA2-1B-1A-LIST-LOW-HOUSENUM    A         16 /* DISPLAY FORMAT                DKR
1097
5920      3 PIWA2-1B-1A-LIST-HI-HOUSENUM     A         16 /* DISPLAY FORMAT                DKR
1098
5930      3 PIWA2-1B-1A-LIST-BORO            A          1                                    DKR
1099
5940      3 PIWA2-1B-1A-LIST-5SC             A          5                                    DKR
1100
5950      3 PIWA2-1B-1A-LIST-LGC             A          2                                    DKR
1101
5960      3 PIWA2-1B-1A-LIST-BIN             A          7                                    DKR
1102
5970      3 PIWA2-1B-1A-LIST-SIDE-OF-STR     A          1 /* L OR R                        DKR
1103
5980      3 PIWA2-1B-1A-ADDR-TYPE            A          1 /* P=NAP, B=NAB,          MAL    DKR
1104
5990   R  3 PIWA2-1B-1A-ADDR-TYPE                         /* REDEF. BEGIN : PIWA2-1B-1A-AD DRR
1105
6000      4 PIWA2-1B-1A-LIST-ADDR-TYPE       A          1 /* BLANK=NORMAL                  DKR
1106
6010      3 PIWA2-1B-1A-TPAD-STATUS          A          1 /* 0 - 9                         DKR
1107
6020   R  3 PIWA2-1B-1A-TPAD-STATUS                      /* REDEF. BEGIN : PIWA2-1B-1A-TP DRR
1108
6030      4 PIWA2-1B-1A-LIST-TPAD-STATUS     A          1                                    DKR
1109
6040      3 PIWA2-1B-1A-ST-NAME              A         32                                    DKR
1110
6050   R  3 PIWA2-1B-1A-ST-NAME                          /* REDEF. BEGIN : PIWA2-1B-1A-ST DRR
1111
6060      4 PIWA2-1B-1A-LIST-ST-NAME         A         32                                    DKR
1112
6070      3 FILLER-1B-1A-800                 A         34                                    DKR
1113
6080   * ** END OF FUNCTION 1B ************* * ********** *************************       C
***** End of List *****
```

GEOLP23S COPY File

```
1 GEOLP23S
*  * THE FIELD P2NAT3S IS USED AS A      PARAMETER TO CALL GEOSUPPORT
2 P2NAT3S                          A         21
R  2 P2NAT3S
3 PIWA2-3S-ACCESS-KEY              A         21
R  3 PIWA2-3S-ACCESS-KEY
4 FILLER-GSS                       A          2
4 PIWA2-3S-PORS-STNAME-IND         A          1
4 PIWA2-3S-BORO                    A          1 /* P=PRIMARY
*  *                                            /* B=SECONDARY
4 PIWA2-3S-5SC                     A          5
4 PIWA2-3S-LGC                     A          2 /* BLANK IF P IN
4 FILLER                           A         10 /* POSITION 3
2 PIWA2-3S-NUM-OF-INTERSECTS       A          3
2 PIWA2-3S-LIST-OF-INTERSECTS                   (1:350)
3 PIWA2-3S-MARBLE-RIKERS-FLAG      A          1
3 PIWA2-3S-DISTANCE                A          5
3 PIWA2-3S-GAP-FLAG                A          1
3 FILLER-100                       A          7
3 PIWA2-3S-NUM-OF-STR              A          1
3 PIWA2-3S-B7SC                    A          8 (1:5)
```

GEOL2AP COPY File

```
1 GEOL2AP
2 P2NATAP                          A         21
R  2 P2NATAP
3 PIWA2-AP-ACCESS-KEY              A         21
2 PIWA2-AP-CONT-PARITY             A          1
2 PIWA2-AP-LOW-HOUSENUM            A         11
2 PIWA2-AP-BBL                     A         10
R  2 PIWA2-AP-BBL
3 PIWA2-AP-BBL-BORO                A          1
3 PIWA2-AP-BBL-BLOCK               A          5
3 PIWA2-AP-BBL-LOT                 A          4
2 FILLER-AP01                      A          7
2 PIWA2-AP-NUM-OF-STRUCTURES       A          4
2 FILLER-AP02                      A         26
2 FILLER-AP-GSS1                   A          1
2 PIWA2-AP-BIN                     A          7
2 PIWA2-AP-CONDO-FLAG              A          1
2 FILLER-AP03                      A          1
2 PIWA2-AP-RPAD-CONDO-ID-NUM       A          4
2 FILLER-AP04                      A          7
```

```
2 PIWA2-AP-CONDO-BILL-BBL          A         10
2 FILLER-AP05                      A          2
2 PIWA2-AP-CONDO-LOW-BBL           A         10
2 FILLER-AP06                      A          1
2 PIWA2-AP-CONDO-HIGH-BBL          A         10
2 FILLER-AP07                      A         16
2 PIWA2-AP-COOP-NUM                A          4
2 FILLER-AP08                      A         22
2 PIWA2-AP-RESERVED                A          3
2 PIWA2-AP-LATITUDE                A          9
2 PIWA2-AP-LONGITUDE               A         11
2 PIWA2-AP-X-COORD                 A          7
2 PIWA2-AP-Y-COORD                 A          7
2 FILLER-AP09                      A         16
2 PIWA2-AP-AP-ID                   A          9
2 FILLER-AP-GSS2                   A          8
2 PIWA2-AP-NUM-OF-ADDR             A          4
2 PIWA2-AP-ADDR-LIST                            (1:21)
3 PIWA2-AP-LIST-LOW-HOUSENUM       A         16
3 PIWA2-AP-LIST-HI-HOUSENUM        A         16
3 PIWA2-AP-LIST-BORO               A          1
3 PIWA2-AP-LIST-5SC                A          5
3 PIWA2-AP-LIST-LGC                A          2
3 PIWA2-AP-LIST-BIN                A          7
3 PIWA2-AP-LIST-SIDE-OF-STR        A          1
3 PIWA2-AP-ADDR-TYPE               A          1
R  3 PIWA2-AP-ADDR-TYPE
4 PIWA2-AP-LIST-ADDR-TYPE          A          1
3 FILLER-AP10                      A          4
```

GEOL2APX COPY File

```
1 GEOL2APX
2 P2NATAPX                         A         21
R  2 P2NATAPX
3 PIWA2-APX-ACCESS-KEY             A         21
2 PIWA2-APX-CONT-PARITY            A          1
2 PIWA2-APX-LOW-HOUSENUM           A         11
2 PIWA2-APX-BBL                    A         10
R  2 PIWA2-APX-BBL
3 PIWA2-APX-BBL-BORO               A          1
3 PIWA2-APX-BBL-BLOCK              A          5
3 PIWA2-APX-BBL-LOT                A          4
2 FILLER-APX01                     A          7
```

```
2 PIWA2-APX-NUM-OF-STRUCTURES      A          4
2 FILLER-APX02                     A         26
2 FILLER-APX-GSS1                  A          1
2 PIWA2-APX-BIN                    A          7
2 PIWA2-APX-CONDO-FLAG             A          1
2 FILLER-APX03                     A          1
2 PIWA2-APX-RPAD-CONDO-ID-NUM      A          4
2 FILLER-APX04                     A          7
2 PIWA2-APX-CONDO-BILL-BBL         A         10
2 FILLER-APX05                     A          2
2 PIWA2-APX-CONDO-LOW-BBL          A         10
2 FILLER-APX06                     A          1
2 PIWA2-APX-CONDO-HIGH-BBL         A         10
2 FILLER-APX07                     A         16
2 PIWA2-APX-COOP-NUM               A          4
2 FILLER-APX08                     A         22
2 PIWA2-APX-RESERVED               A          3
2 PIWA2-APX-LATITUDE               A          9
2 PIWA2-APX-LONGITUDE              A         11
2 PIWA2-APX-X-COORD                A          7
2 PIWA2-APX-Y-COORD                A          7
2 FILLER-APX09                     A         16
2 PIWA2-APX-AP-ID                  A          9
2 FILLER-APX-GSS2                  A          8
2 PIWA2-APX-REASON-CODE            A          1
2 PIWA2-APX-REASON-CODE-QUAL       A          1
2 PIWA2-APX-WARN-CODE              A          2
2 PIWA2-APX-RETURN-CODE            A          2
2 FILLER-APX10                     A        108
2 PIWA2-APX-NUM-OF-ADDR            A          4
2 PIWA2-APX-ADDR-LIST                           (1:21)
3 PIWA2-APX-LIST-LOW-HOUSENUM      A         16
3 PIWA2-APX-LIST-HI-HOUSENUM       A         16
3 PIWA2-APX-LIST-BORO              A          1
3 PIWA2-APX-LIST-5SC               A          5
3 PIWA2-APX-LIST-LGC               A          2
3 PIWA2-APX-LIST-BIN               A          7
3 PIWA2-APX-LIST-SIDE-OF-STR       A          1
3 PIWA2-APX-ADDR-TYPE              A          1
R  3 PIWA2-APX-ADDR-TYPE
4 PIWA2-APX-LIST-ADDR-TYPE         A          1
3 FILLER-APX11                     A          1
3 PIWA2-APX-ST-NAME                A         32
R  3 PIWA2-APX-ST-NAME
4 PIWA2-APX-LIST-ST-NAME           A         32
```

```
3 FILLER-APX12                    A          34
```

APPENDIX 15: 2010 CENSUS GEOGRAPHY – FUNCTIONS 1, 1E, 2, 3, and 3C

This appendix is based on the Geosupport System Technical Bulletin 11-01 for Geosupport Version 11.0. If you need a copy of the Bulletin, please be in touch with the GSS Manager of Geographic Research. Contact information is available in Appendix 6: Geosupport Feedback Procedures.

As of Geosupport Software Version 11.0 / Release 11A, Geosupport returns the new 2010 Census geography (e.g. census tract and census block). As of Software Version 11.4 / Release 12B, health areas are based on 2010 Census geography. Note that other tract based district information (e.g. community development eligibility) will still be based on the 2000 Census geography until further notice.

User Programming Considerations for 2010 Census Geography

- New 2010 Census data replaces 2000 Census data
- Census 2000 data has been moved to a new location and renamed
- There is no need to do any modifications to get 2010 Census information from GBAT or programs that use offsets, since the 2010 Census information replaces the 2000 information.
- Modification is needed to get 2000 Census information from GBAT or programs that use offsets, since the 2000 information has been moved to a new location.
    - See the tables of Census Data Offsets below.
- At some point, users must modify and recompile programs that access Census information, accessing the new 2010 or 2000 Census field names
    - See the new field names in the appropriate copy files
- If users do not recompile and Census data is processed, they will get the 2010 data. Note: If you do not recompile and you are accessing Census information via the field names in the copy books, the next time you try to recompile you will get a compile error since the existing Census field names no longer exist. You will have to indicate at that point whether you want Census 2010 or Census 2000 by modifying the field names in the programs
- **MSW Users: For Function 1/1E**, the 2000 Census information has been moved to Long Work Area 2, as there was no room for it in the regular Work Area 2. Census 2010 information is in the regular Work Area 2.

Every 10 years, in conjunction with the decennial census of the population, the U.S. Census Bureau defines a new set of census geography (census tract and census block boundary lines and identifiers) throughout the nation. The Geosupport System has been providing 1990 census tract and 2000 census tract, census block and census block suffix fields. This data will continue to be included in the output information returned from Functions 1, 1B, 1E, 2, 3 and 3C.

DCP/GSS received the 2010 census geography from the Census Bureau and now includes this information since File Release 11A, Geosupport Software Version 11.0. The 1990 census information will continue to be returned in the same work area fields that have been used in previous releases.

However, as of Release 11A, Version 11.0, the 2010 Census information for both COW and MSW outputs is now returned in the same positions that previously held the 2000 Census information, and the 2000 Census information has been moved to positions previously defined as filler. Also, the field names (in the Copy Books) of the 2000 Census information fields have been changed

This was done so that users who want the most current Census information will not have to immediately recompile their programs and change their GBAT jobs to get the 2010 Census information. However, **whenever users recompile their programs, they will have to update the field names for the 2010 Census information, and, if they want the 2000 Census information, they will have to update the field names for that as well.** The name changes were done purposely in order to force users who recompile programs that use the copylibs and look at Census information to change their programs and make decisions whether they want to continue receiving Census 2000 data and/or update their programs to receive Census 2010 data

CENSUS DATA OFFSETS – Table 1 (COW) and Table 2 (MSW)

TABLE 1 - Offsets for the 2010 and 2000 Census data for COW Work Area 2

Functions (COW)	Data Item	WA2 Position Prior to Release 11A	WA2 Position as of 11A
COW Fns 1, 1E and 1B	2010 Census Tract	Not Provided	224-229
	2010 Census Block	Not Provided	230-233
	2010 Census Block	Not Provided	230-233
	2010 Census Filler	Not Provided	234
	2000 Census Tract	224-229	235-240
	2000 Census Block Suffix	234	245
COW Fn 2	2010 Census Tract	Not Provided	136-141
	2000 Census Tract	136-141	176-181
	2010 Left Census Tract	Not Provided	260-265
	2010 Left Census Block	Not Provided	266-269
	2010 Left Census Filler	Not Provided	270-270
	2010 Right Census Tract	Not Provided	410-415
	2010 Right Census Block	Not Provided	416-419
	2010 Right Census Filler	Not Provided	420

COW Fn 3	2000 Left Census Tract	260-265	271-276
	2000 Left Census Block	266-269	277-280
	2000 Left Census Block Suffix	270-270	281-281
	2000 Right Census Tract	410-415	421-426
	2000 Right Census Block	416-419	427-430
	2000 Right Census Block Suffix	420-420	431-431
COW Fn 3C	2010 Census Tract	Not Provided	260-265
	2010 Census Block	Not Provided	266-269
	2010 Census Filler	Not Provided	270-270
	2000 Census Tract	260-265	271-276
	2000 Census Block	266-269	277-280
	2000 Census Block Suffix	270	281

TABLE 2 - Offsets for the 2010 and 2000 Census data for MSW Work Area 2

Functions (MSW)	Data Item	WA2 Position Prior to Release 11A	WA2 Position as of Release 11A
MSW Fns 1 and 1E	2010 Census Tract	Not Provided	91-96
	2010 Census Block	Not Provided	97-100
	2010 Census Filler	Not Provided	101-101
	2000 Census Tract	91-96	222-227 Available only with Long Work Area 2
	2000 Census Block	97-100	228-231 Available only with Long Work Area 2
	2000 Census Block Suffix	101-101	232 -232 Available only with Long Work Area 2
MSW Fn 2	2010 Census Tract	Not Provided	87-92
	2000 Census Tract	87-92	168-173
	2010 Left Census Tract	Not Provided	243-248 Available only with Long Work Area 2
	2010 Left Census Block	Not Provided	249-252 Available only with Long Work Area 2

MSW Fn 3	2010 Left Census Filler	Not Provided	253 - 253 Available only with Long Work Area 2
	2010 Right Census Tract	Not Provided	254-259 Available only with Long Work Area 2
	2010 Right Census Block	Not Provided	260-263 Available only with Long Work Area 2
	2010 Right Census Filler	Not Provided	264-264 Available only with Long Work Area 2
	2000 Left Census Tract	243-248 Available only with Long Work Area 2	279-284 Available only with Long Work Area 2
	2000 Left Census Block	249-252 Available only with Long Work Area 2	285-288 Available only with Long Work Area 2
	2000 Left Census Block Suffix	253-253 Available only with Long Work Area 2	289-289 Available only with Long Work Area 2
	2000 Right Census Tract	254-259 Available only with Long Work Area 2	290-295 Available only with Long Work Area 2
	2000 Right Census Block	260-263 Available only with Long Work Area 2	296-299 Available only with Long Work Area 2
	2000 Right Census Block Suffix	264-264 Available only with Long Work Area 2	300-300 Available only with Long Work Area2

APPENDIX 16: NEIGHBORHOOD TABULATION AREAS (NTAS) AND PUMAS

Originally created as Neighborhood Projection Areas for use in population projections, these aggregations of census tracts have been updated using 2010 census tracts and renamed Neighborhood Tabulation Areas (NTAs). The origin of Neighborhood Projection Areas as subsets of 55 Public Use Microdata Areas (PUMAs) is explained below.

The Neighborhood Tabulation Areas (NTAs) have been adopted by the Population Division of DCP as a method of presenting the U.S. Census Bureau's American Community Survey (ACS) release of census tract data for 5-year estimates. To mitigate the small sample size and accompanying large margins of error, ACS data are aggregated to NTA geography and made available in the ACS section of the DCP Population website. Because NTAs are subsets of PUMAs, they are important to anyone requiring ACS data for subareas of Community Districts. Regarding the 2010 census, these geographic areas offer a good compromise between the very detailed data for census tracts (2,168) and the broad strokes provided by community districts (59).

Neighborhood Projection Areas were created to project populations at a small area level, from 2000 to 2030. First and foremost, these aggregations were driven by population size in 2000 – neighborhood projection areas had to have a minimum population of 15,000, because this reduces the error associated with the projected population. This criterion resulted in combinations of neighborhoods that probably would not occur if one were solely designating boundaries of historical neighborhoods. Moreover, the neighborhood names associated with the neighborhood projections areas are not intended to be definitive.

Neighborhood projection areas were created using whole census tracts that were exact subdivisions of New York City's 55 Public Use Microdata Areas (PUMAs). (PUMAs were developed for use with the Census Bureau's Public Use Microdata Samples (PUMS) and are approximations of Community Districts.) Neighborhood projection areas were not permitted to cross PUMA boundaries.

Users need to be cognizant of the reason why these neighborhood projection areas were created, and the demographic and geographic constraints inherent in how they were configured.

APPENDIX 17: TPAD - ADDITIONAL INFORMATION

Geosupport Warnings, TPAD Conflict Flag, Reason Code Qualifier and Error Message

The TPAD Option allows users to get up-to-date property-level information. The TPAD Option is available for Function 1A, BL, BN, and 1B calls (PAD calls). When users turn the TPAD Switch 'on' in their applications, Geosupport reads the Transitional PAD file (TPAD) for intra-cycle PAD data and if any is found, Geosupport returns the TPAD data to the calling application. See Chapter VI.11 for a more detailed description of the TPAD option and the information it returns.

This appendix describes the special return code and error message handling with respect to TPAD. **If your applications make function 1A, BL, BN or 1B calls with the TPAD Option 'on', then you must read this description.**

Geosupport is designed to return information about both a normal warning (e.g. Hyphen Deleted) and a TPAD Conflict situation (e.g. …No Existing PAD BBL) with only one Function 1A, BL, BN or 1B call (with TPAD Switch 'on') to Geosupport. The value in the Geosupport Reason Code will be the value that a user would expect when a Geosupport function call has completed with a warning. The TPAD Conflict Flag will be in Work Area 2 (WA2) for all PAD calls with the TPAD Option 'on'. The '*' Reason Code (which indicates a TPAD Warning) will appear in only one exceptional case. In the situation where there was no regular Warning Message for the regular PAD call and there was TPAD data found that *conflicts* with the PAD data, then the GRC will contain '01' (indicating a warning) and the Reason Code will contain '*' (indicating that there is only a TPAD Conflict Flag warning and no regular Geosupport warning).

In addition, if TPAD data is found and there is a conflict with the PAD data, the value in the WA2 Conflict Flag field will also be placed into a new field called the Geosupport Reason Code Qualifier field which immediately follows the Geosupport Reason Code field in Work Area 1 (WA1). When this new field is populated with the TPAD Conflict Flag, the TPAD Conflict Message will be put in the Geosupport Error Message field instead of the Geosupport Warning Message that would normally appear. Note, therefore, that if there was a Geosupport Warning involving the regular PAD portion of this call, the Reason Code field will indicate the nature of the warning as with all other Geosupport calls (but the Error Message field for this warning will be overridden by the TPAD Conflict message if a conflict exists).

Values of '0' or '1' in the TPAD Conflict Flag (in WA2) are considered 'normal results'.
'0' signifies TPAD data was found and does not conflict with PAD data;
'1' signifies that no TPAD data was found.
When there are 'normal results', the WA2 TPAD Conflict Flag will not be placed into the new Geosupport Reason Qualifier field in WA1.

The following table shows the possible results for Function 1A, BL, BN an 1B calls with the TPAD Switch 'on'.

	Regular Geosupport Warning for PAD Call			
	Yes		**No**	
	TPAD Data Found		**TPAD Data Found**	
Work Area 1 Fields	Yes	No	Yes	No
Geosupport Return Code (GRC)	01	01	01	00
Reason Code	Warning Reason Code	Warning Reason Code	*	blank
Reason Code Qualifier	TPAD Conflict Flag†	blank	TPAD Conflict Flag†	blank
Error Message	TPAD Conflict Flag†	blank	TPAD Conflict Flag†	blank
WA2 Conflict Flag	TPAD Conflict Flag	TPAD Conflict Flag	TPAD Conflict Flag	TPAD Conflict Flag

† **Note:** *The TPAD Conflict Flag appears in the Reason Code Qualifier only if its value is greater than '1'. Similarly, the TPAD Conflict Message will appear in the Error Message field, only if the TPAD Conflict field is greater than '1'.*
The TPAD Conflict Flag '1' (no TPAD data was found) and the TPAD Conflict Flag '0' (TPAD data found and it does not conflict with PAD data) will not appear in the Reason Code Qualifier field in WA1. The Error Message field will have a TPAD Conflict Message only when TPAD data was found and it conflicts with the PAD data in some way (and as a result, the Reason Code Qualifier will be non-blank). Note that if there is no Regular Geosupport Warning, and there is TPAD data which does not conflict with the PAD data (Conflict Flag '0'), the GRC will be '00' the Reason Code, Reason Code Qualifier, and Error Message will all be blank.

See examples on the following pages.

Examples: PAD Data Found with Regular Warnings

PAD Data (with regular Geosupport warning) and No TPAD Data Found	
Input: 12-34 Sample Street	
WA1 Fields	**Value**
GRC	01
Reason Code	3 [indicates input address number altered – hyphen deleted]
Reason Code Qualifier	blank
Error Message	ADDR NUMBER ALTERED: HYPHEN DELETED
WA2 Conflict Flag	1

PAD Data (with regular Geosupport warning) and TPAD Data (with no conflicts)	
Input: 12-34 Sample Street	
WA1 Fields	**Value**
GRC	01
Reason Code	3 [indicates input address number altered – hyphen deleted]
Reason Code Qualifier	blank
Error Message	ADDR NUMBER ALTERED: HYPHEN DELETED
WA2 Conflict Flag	0

PAD Data (with regular Geosupport warning) and TPAD Data (with conflicts)	
Input: 12-34 Sample Street	
WA1 Fields	**Value**
GRC	01
Reason Code	3 [indicates input address number altered – hyphen deleted]
Reason Code Qualifier	D [indicates address in TPAD but not PAD (PAD data from BL call)]
Error Message	ADDRESS FOUND IN TPAD, NOT FOUND IN PAD……
WA2 Conflict Flag	D

Examples: PAD Data Found with No Regular Geosupport Warning

PAD Data (with no regular Geosupport warning) and No TPAD Data Found	
Input: 1234 Sample Street	
WA1 Fields	**Value**
GRC	00
Reason Code	Blank
Reason Code Qualifier	Blank
Error Message	Blank
WA2 Conflict Flag	1

PAD Data (with no regular Geosupport warning) and TPAD Data (with no conflicts)	
Input: 1234 Sample Street	
WA1 Fields	**Value**
GRC	00
Reason Code	Blank
Reason Code Qualifier	Blank
Error Message	Blank

WA2 Conflict Flag	0

PAD Data (with no regular Geosupport warning) and TPAD Data (with conflicts)	
Input: 1234 Sample Street	
WA1 Fields	**Value**
GRC	01
Reason Code	* [indicates TPAD Conflict only; no regular warning]
Reason Code Qualifier	D [indicates address in TPAD but not PAD (PAD data from BL call)]
Error Message	ADDRESS FOUND IN TPAD, NOT FOUND IN PAD……..
WA2 Conflict Flag	D

The Reason Code Qualifier is used to define a specific TPAD warning. When there is a true conflict between TPAD data and PAD data, the Reason Code Qualifier contains the same information as the TPAD Conflict Flag.

The following table indicates where in Work Area 1 the one-byte Reason Code Qualifier field(s) may be found.

(1 byte) Position			
Field Name	**Function(s)**	**COW**	**MSW**
Reason Code Qualifier	1A, BL, BN	714	n/a
Reason Code Qualifier 2	1B	575	n/a

For Functions 1A, BL, and BN the Reason Code Qualifier is a one-byte field, in column 714 of COW Work Area 1.
For Function 1B, the Reason Code Qualifier 2 is a one-byte field, in column 575 of COW Work Area 1.

The following table contains the field name in the COPY libraries for the Reason Code Qualifiers.

Reason Code Qualifier(s) Field Names in COPY Libraries			
Language	**COPY Library (COW Only)**	**Function(s) (COW Only)**	**Field Name**
BAL	P1BAL	1A, BL, BN 1B	reason_code_qual reason_code_qual_2
COBOL	P1COB	1A, BL, BN 1B	GEO-WA1-OUT-REASON-CODE-QUAL GEO-WA1-OUT-REASON-CODE-QUAL2
Natural	GEOLP1	1A, BL, BN	PIWA1-OUT-REASON-CODE-QUAL

		1B	PIWA1-OUT-REASON-CODE-QUAL-2
PL/1	P1PL1	1A, BL, BN 1B	PIWA1_OUT_REASON_CODE_QUAL PIWA1_OUT_REASON_CODE_QUAL_2

APPENDIX 18: GEOEXCEL, A GEOCODING SOLUTION FOR EXCEL

Updated: 5/22/2016

Features

GeoExcel incorporates many of the familiar interface elements of GBAT while adding new features to improve productivity and the overall user experience. GeoExcel is designed to be a comprehensive tool for performing geocoding tasks and offers the flexibility to fit into different user scenarios.

Requirements

- Latest 64 bit Geosupport desktop edition
- Microsoft Excel 2013
- Windows 7 or above
- Internet connection (desired)

Installation

NOTE: GeoExcel is a Microsoft Office 2013 VSTO add-in. Installation requires Admin access to the computer on which it is installed.

1. Unzip file folder
2. Double click “setup.exe”
3. Follow the instructions to complete installation (administrator privileges required)

Getting Started

If installation was successful, you will see a new tab when you open Excel 2013 that says “Geosupport”.
Here is where you will find the ribbon controls for GeoExcel.

Figure 1:

<u>Setting up the input</u>

1. Select the Geosupport function that you want to execute.

2. Data can be provided to GeoExcel in two ways using the input data selection screen:

Figure 2:

If "Data exists in input sheet" option is selected, GeoExcel assumes that the data is preloaded in the Excel spreadsheet. GeoExcel then expects the user to provide the column names where the input data resides. GeoExcel collects this information using the following screen which comes up when the user presses "Ok".

Figure 3:

On this screen, enter the columns where the input data resides. For Example with the selection of Function 1A, we need to provide GeoExcel with Borough information. If this information is in Column A, simply type “A” in the text box next to the label “Select the column with Borough information”. Once all the column information is provided, press “Process Data”.

The other way to provide input data to GeoExcel is directly entering the data into the Excel spreadsheet using a pre-formatted template. If the user wishes to use this option, then select “Load the Geosupport default template for data entry” in Figure 1.

This option loads a template in Excel which enables data entry. It should be noted that the template formatting is limited to a single row and is provided only as a reference for the user. However, the user can enter as many rows as required.

Figure 4:

Once data entry has been completed in the template, simply press the Submit button. GeoExcel displays the Geocoded output in the “Func – XX Output” tab and the errors in “Func–XX Errors” tab.

GeoExcel does not modify the original data as entered by the user.

Usage Tips:

1. Use the Excel spreadsheet only for one Function at a time. If additional functions are needed, please close Excel and open a new instance of the application.

2. Only one instance of Excel should be running at any time.

3. The Borough Code can be spelled out or it can be coded as “1” for Manhattan, similar to GBAT tool.

4. If you see a “ROT Issue” message, click on a window (other than Excel) and come back to the Excel application and resubmit. This is a known issue with Microsoft Office where Windows doesn’t recognize the running instance of Excel.

5. GeoExcel is configured to utilize a local geocoding service in the event of a blackout or outage situation

6. Refer to the latest UPG file included with the installation package to understand full Geosupport functionality as well as the GRC codes/messages that are returned.

If you have any questions or suggestions for improving the tool, please let us know. Send an email to: GSS_Software@planning.nyc.gov

APPENDIX 19: WORK AREA LAYOUTS (COWs)

Character-Only Work Areas

(as of Geosupport System Software Version 9.7.0)

This appendix contains layouts of all of the work areas used with the Geosupport System's API. These layouts are current as of the Geosupport software version indicated above. The layouts are in the Character-Only Work Area format[4]

Some Geosupport functions can only be called using one work area, Work Area 1 (WA1). Other functions can be called using two work areas, WA1 and Work Area 2 (WA2). WA1 contains both input fields (fields used to pass data from the application to Geosupport) and output fields (fields used to pass data from Geosupport to the application). WA1 is organized so that all the input fields occur first, followed by all the output fields. WA2 contains output fields only.

All functions use the same WA1 layout, but the set of WA1 fields that are used depends on the function. In the layout of WA1 in this appendix, the column labeled 'Functions' indicates which functions use each field.

The functions that can be called using two work areas use various WA2 layouts of various lengths. In some cases, several functions share a single WA2 layout. For functions 1A and BL, the user has a choice of two WA2 layouts, a 'regular' WA2 and a 'long' WA2.

The following is a list of all of the Geosupport work areas, indicating the length of each in bytes. Functions that are listed together share a single Work Area 2 layout.

Work Area	Length
WA1, all functions	1200
WA2, Function 1	300
Regular WA2, Functions 1A, BL, BN	1,363
Long WA2, Functions 1A and BL	17,750
WA2, Function 1E	300
WA2, Function 2	200
WA2, Function 3	450
WA2, Function 3C	300
WA2, Function 3S	19,274

Appendix 3 consists of a data item dictionary describing the fields that occur in the work areas.

Work Area 1 (COW) - All Functions

Field	Size	Position	Functions[5]
INPUT FIELDS:			

Geosupport Function Code	2	1	2	All
House Number - Display Format (HND)	16	3	18	1, 1A, 1E
House Number - Sort Format (HNS)	11	19	29	1, 1A, 1E, D *
Low House Number - Display Format (HND)	16	30	45	Internal Use
Low House Number - Sort Format (HNS)	2	1	2	All
Geosupport Function Code	11	46	56	D*, Internal Use
Borough Code-1	1	57	57	All but BL & BN
10SC [6]-1	10	58	67	All but BL & BN
Street Name-1	32	68	99	All but BL,BN & D *
Borough Code[7]-2	1	100	100	All but 1* & B*
10SC-2	10	101	110	All but 1* & B*
Street Name-2	32	111	142	All but 1* & B*
Borough Code-3	1	143	143	D*, 3*
10SC-3	10	144	153	D*, 3*
Street Name-3	32	154	185	D*, 3*
BOROUGH BLOCK LOT (BBL)	11	186	196	BL
Borough Code	1	186	186	BL
Tax Block	5	187	191	BL
Tax Lot	4	192	195	BL
Filler for Tax Lot Version Number	1	196	196	*Not Implemented*
Building Identification Number (BIN)	7	197	203	BN
Compass Direction	1	204	204	2, 3C, 3S
Compass Direction for 2nd Intersection	1	205	205	3S
Filler	7	206	212	
Work Area Format Indicator[8]	1	213	213	All
Filler	101	214	314	
Long Work Area 2 Flag[9]	1	315	315	1A, BL
House Number Justification Flag[10]	1	316	316	*Not Implemented*
House Number Normalization Length[11]	2	317	318	*Not Implemented*
House Number Normalization Override Flag	1	319	319	Internal Use
Street Name Normalization Length Limit	2	320	321	All
Street Name Normalization Format Flag[12]	1	322	322	All
Cross Street Names Flag[13]	1	323	323	1, 1E, 2, 3, 3C
Filler	37	324	360	

OUTPUT Fields:

First Borough Name	9	361	369	All but D*
First Borough Name	9	361	369	All but D*
House Number - Sort Format	11	386	396	1, 1A, 1E
B10SC - First Borough and Street Code	11	397	407	1*, 2, 3*

First Street Name Normalized	32	408	439	All but B*
B10SC - Second Borough and Street Code	11	440	450	2,3*
Second Street Name Normalized	32	451	482	2,3* ,D*
B10SC - Third Borough and Street Code	11	483	583	3*
Third Street Name Normalized	32	494	525	3* ,D*
BOROUGH BLOCK LOT (BBL)	10	526	535	BL
Borough Code	1	526	526	BL
Tax Block	5	527	535	BL
Tax Lot	4	532	535	BL
Filler for Tax Lot Version Number	1	536	536	*Not Implemented*
Low House Number - Display Format	16	537	552	Internal Use
Low House Number - Sort Format	11	553	563	Internal Use
Building Identification Number	7	564	570	1, 1E, BN
Attribute Bytes - Internal Use Only	3	571	573	Internal Use
Filler	132	574	705	
NIN[14]	6	706	711	*Not Implemented*
Street Attribute Indicator	1	712	712	Internal Use
Reason Code	1	713	713	All
Reason Code Qualifier	1	714	714	*Not Implemented*
Filler	2	715	716	
Geosupport Return Code	2	717	718	All
Message	80	719	798	All
Number of Street Codes and Names in List (up to 10)	2	799	800	1* ,2,3*
10 B7SC's	80	801	880	1* ,2,3*
List of Street Names(10 Street Name Fields, 32 Bytes Each)	320	881	660	1* ,2,3*

1* = 1, 1A, 1E, 1N
3* = 3, 3C, 3S
B* = BL, BN
D* = D, DG, DN

Work Area 2 (COW) - Functions 1 and 1E

Blockface Defined by Address Range Along a Street

Field	Size	Position		Comments
Internal Use	21	1	21	
Continuous Parity Indicator/Duplicate Address Indicator	1	22	22	
Low House Number of Block face-Sort Format	11	23	33	
High House Number of Block face-Sort Format	11	34	44	

DCP Preferred LGC[15]	2	45	46	
Number of Cross Streets at Low Address End	1	47	47	
List of Cross Streets at Low Address End (Up to 5 B5SCs)	30	48	77	B5SC - Blank-Filled
Number of Cross Streets at High Address End	1	78	78	
List of Cross Streets at High Address End (Up to 5 B5SCs)	30	79	108	B5SC - Blank-Filled
LION KEY	10	109	118	
Borough Code	1	109	109	
Face Code	4	110	113	
Sequence Number	5	114	118	
Special Address Generated Record Flag	1	119	119	
Side of Street Indicator	1	120	120	
Segment Length in Feet	5	121	125	
Spatial Coordinates of Address:				
X Coordinate	7	126	132	
Y Coordinate	7	133	139	
Reserved for Possible Z Coordinate	7	140	146	
Interim Assistance Eligibility Indicator Also known as Community Development Eligibility Indicator	1	147	147	
Marble Hill/Rikers Island Alternative Borough Flag	1	148	148	
DOT Street Light Contractor Area	1	149	149	
Community District:	3	150	152	
Community District Borough Code	1	150	150	
Community District Number	2	151	152	
Zip Code	14	158	171	
Function 1E Items	14	158	171	**Use ONLY for Function 1E**
Election District	3	158	160	Invalid for Fn 1
Assembly District	2	161	162	Invalid for Fn 1
Split Election District Flag	1	163	163	Invalid for Fn 1
Congressional District	2	164	165	Invalid for Fn 1
State Senatorial District	2	166	167	Invalid for Fn 1
Civil Court District	2	168	169	Invalid for Fn 1
City Council District	2	170	171	Invalid for Fn 1
Health Center District	2	172	173	
Health Area	4	174	177	
Sanitation District	3	178	180	
Sanitation Collection Scheduling Section and Subsection	2	181	182	

Sanitation Regular Collection Schedule	5	183	187
Sanitation Recycling Collection Schedule	3	188	190
Police Patrol Borough Command	1	191	191
Police Precinct	3	192	194
Fire Division	2	195	196
Fire Battalion	2	197	198
Fire Company Type	1	199	199
Fire Company Number	3	200	202
Split Community School District Flag	1	203	203
Community School District	2	204	205
Dynamic Block	3	206	208
Instructional Region	2	209	210
Feature Type Code	1	211	211
Filler	6	212	217
1990 Census Tract	6	218	223
2000 Census Tract	6	224	229
2000 Census Block	4	230	233
Filler	51	234	284
Underlying B7SC	8	285	292
Segment Identifier	7	293	299
Curve Flag	1	300	300

Work Area 2 (COW) - Functions 1A, BL and BN

Property Defined by Address, BBL, or BIN

Field	Size	Position		Comment
Internal Use	21	1	21	
Continuous Parity Indicator /Duplicate Address Indicator	1	22	22	
Low House Number of Defining Address Range	11	23	33	Sort Format
Borough-Tax Block-Tax Lot (BBL):	10	34	44	Billing BBL if Condo
Borough Code	10	34	44	
Tax Block	5	35	39	
Tax Lot	4	40	43	
Filler for Tax Lot Version Number	1	44	44	*Not Implemented*
RPAD Self-Check Code (SCC) for BBL	1	45	45	
Filler	1	46	46	
RPAD Building Classification Code	2	47	48	

Corner Code	2	49	50	
Number of Existing Structures on Lot	4	51	54	
Number of Street Frontages of Lot	2	55	56	
Interior Lot Flag	1	57	57	
Vacant Lot Flag	1	58	58	
Irregularly-Shaped Lot Flag	1	59	59	
Marble Hill/Rikers Island Alternate Borough Flag	1	60	60	
List of Geographic Identifiers Overflow Flag	1	61	61	When = 'E', there are more than 21 addresses for Fns 1A and BL.
STROLLING KEY:	19	62	80	*Not Implemented*
Borough	1	62	62	
5-Digit Street Code of ‘ON’ Street	5	63	67	
Side of Street Indicator	1	68	68	
High House Number	11	69	79	Sort Format
Filler	1	80	80	
Reserved for Internal Use	1	81	81	
Building Identification Number (BIN) of Input Address or NAP	1	82	88	
Condominium Flag	1	89	89	If condo, Flag = C
Filler	1	90	90	
DOF Condominium Identification Number	4	91	94	
Condominium Unit ID Number	7	95	101	*Not Implemented*
Condominium Billing BBL	10	102	111	
Tax Lot Version Number for Billing BBL	1	112	112	*Not Implemented*
Self-Check Code (SCC) of Billing BBL	1	113	113	
Low BBL of this Building’s Condominium Units	10	114	123	
Tax Lot Version Number of Low BBL	1	124	124	*Not Implemented*
High BBL of this Building’s Condominium Units	10	125	134	*Not Implemented*
Tax Log Version Number of High BBL	1	135	135	
Filler	15	136	150	
Cooperative ID Number	4	151	154	
SBVP (Sanborn Map Identifier):	8	155	162	
Sanborn Borough Code	1	155	155	
Volume Number	2	156	157	
Volume Number Suffix	1	158	158	
Page Number	3	159	161	

Page Number Suffix	1	162	162	
DCP Commercial Study Area	5	163	167	
Tax Map Number Section & Volume	5	168	172	
Reserved for Tax Map Page Number	4	173	176	*Not Implemented*
Multiple BBL Flag	1	177	177	These fields will be used with Multiple Entity NAPs
Next BBL	11	178	188	
Previous BBL	11	189	199	
Spatial Coordinates of Internal Label Point:				
X Coordinate	7	200	206	
Y Coordinate	7	207	213	
Filler	25	214	238	
Internal Use	8	239	246	
Number of Entries in List of Geographic Identifiers	4	247	250	
List of Geographic Identifiers:	1,113	251	1,363	
Variable length list of 53-byte entries as follows:				
Low House Number	16			Display format(HND)
High House Number	16			Display format(HND)
Borough Code	1			
5-Digit Street Code	5			
DCP-Preferred Local Group Code (LGC)	2			
Building Identification Number	7			
Side of Street Indicator	1			
Geographic Identifier	1			
				L - Left, R - Right N - NAP G - Generic NAP X - Part of Generic NAP B - NAUB F - Frontage W - Blank Wall Q - PseudoAddress V - Vanity Address R - Real Street O - Out-of-Sequence Address Blank - Normal Filler

Long Work Area 2 (COW) - Functions 1A and BL

Property Defined by Address or BBL

Field	Size	Position		Comment
Same as Regular Work Area 2 - Functions 1A/BL	246	1	246	
Number of Buildings on Tax Lot	4	247	250	
List of Buildings on Tax Lot	17,500	251	17,750	
Variable length list of up to 2,500 entries, each entry is a 7-byte BIN	7			

Work Area 2 (COW) - Function 2

Intersection Defined by Two Intersecting Streets

Field	Size	Position		Comment
Internal Use	21	1	21	
Intersection Replication Counter	1	22	22	
DCP-Preferred LGC for Street 1	2	23	24	
DCP-Preferred LGC for Street 2	2	25	26	
Number of Intersecting Streets	1	27	27	
List of Intersecting Streets (Up to five B5SCs, 6 bytes each)	30	28	57	
Compass Direction for Intersection Key or Counter for Multiple Intersections	1	58	58	
FillerL	5	59	63	
LION Node Number	7	64	70	
Spatial Coordinates:	21			
X Coordinate	7	71	77	
Y Coordinate	7	78	84	
Filler	7	85	91	
SBVP1 (Sanborn Map Identifier):	8			
Borough Code	1	92	92	
Volume Number	2	93	94	
Volume Number Suffix	1	95	95	
Page Number	3	96	98	
Page Number Suffix	1	99	99	
SBVP2 (Sanborn Map Identifier):	8			
Borough Code	1	100	100	
Volume Number	2	101	102	
Volume Number Suffix	1	103	103	
Page Number	3	104	106	

Page Number Suffix	1	107	107	
Marble Hill/Rikers Island Alternative Borough Flag	1	108	108	
DOT Street Light Contractor Area	1	109	109	
Community District:	3			
Community District Borough Code	1	110	110	
Community District Number	2	111	112	
Zip Code	5	113	117	
Health Area	4	118	121	
Police Patrol Borough Command	1	122	122	
Fire Division	2	126	127	
Fire Battalion	2	128	129	
Fire Company Type	1	130	130	
Fire Company Number	3	131	133	
Community School District	2	134	135	
2000 Census Tract	6	136	141	
1990 Census Tract	6	142	147	
List of Pairs of Level Codes	10	148	157	*Not Implemented*
Instructional Region	2	158	159	
Filler	41	160	200	

Work Area 2 (COW) - Function 3

Street Segment Defined by 'ON' Street and Two Cross Streets

Field	Size	Position		Comment
Internal Use	21	1	21	
Duplicate Key Flag or Continuous Parity	1	22	22	
Locational Status of Segment	1	23	23	
County Boundary Indicator	1	24	24	
DCP-Preferred LGC for Street 1	2	25	26	
DCP-Preferred LGC for Street 2	2	27	28	
DCP-Preferred LGC for Street 3	29	30		
Number of Cross Streets at Low Address End	1	31	31	
List of Cross Streets at Low Address End (Up to five B5SCs, 6 bytes each)	30	32	61	Blank Filled
Number of Cross Streets at High Address End	1	62	62	
List of Cross Streets at High Address End (Up to five B5SCs, 6 bytes each)	30	63	92	Blank Filled
Cross Street Reversal Flag	1	93	93	
LION KEY	10	94	103	

LION Borough Code	1	94	94	
LION Face Code	4	95	98	
LION Sequence Number	5	99	103	
Generated Record Flag	1	104	104	
Length of Segment in Feet	5	105	109	
Segment Azimuth	3	110	112	
Segment Orientation	1	113	113	
Marble Hill/Rikers Island Alternative Borough Flag	1	114	114	
Filler	19	115	133	
Segment Identifier	7	134	140	
DOT Street Light Contractor Area	1	141	141	
Curve Flag	1	142	142	
Dog Leg Flag	1	143	143	
Feature Type Code	1	144	144	
Filler	6	145	150	
LEFT SIDE:				
Community District:	3			
Community District Borough Code	1	151	151	
Community District Number	2	152	153	
Low House Number	16	154	169	Display Format
High House Number	16	170	185	Display Format
Reserved for Geosupport Use	32	186	217	
Interim Assistance Eligibility Indicator	1	218	218	
Zip Code	5	219	223	
Health Area	4	224	227	
Police Patrol Borough Command	1	228	228	
Police Precinct	3	229	231	
Fire Division	2	232	233	
Fire Battalion	2	234	235	
Fire Company Type	1	236	236	
Fire Company Number	3	237	239	
Community School District	2	240	241	
Dynamic Block	3	242	244	
Instructional Region	2	245	246	
Filler	7	247	253	
1990 Census Tract	6	252	259	
2000 Census Tract	6	260	265	
2000 Census Block	4	266	269	
Filler	4	374	377	
RIGHT SIDE:				

Community District:	3			
Community District Borough Code	1	301	301	
Community District Number	2	302	303	
Low House Number	16	304	319	Display Format
High House Number	16	320	335	Display Format
Reserved for Geosupport Use	32	336	367	
Interim Assistance Eligibility Indicator	1	368	368	
Zip Code	5	369	373	
Health Area	4	374	377	
Police Patrol Borough Command	1	378	378	
Police Precinct	1	379	380	
Fire Division	2	382	383	
Fire Battalion	2	384	385	
Fire Company Type	1	386	386	
Fire Company Number	3	387	389	
Community School District	2	390	391	
Dynamic Block	3	392	394	
Instructional Region	2	395	396	
Filler	7	397	403	
1990 Census Tract	6	404	409	
2000 Census Tract	6	410	415	
2000 Census Block	4	416	419	
Filler	31	420	450	

Work Area 2 (COW) - Function 3C

Blockface Defined by 'ON' Street, Two Cross Streets and Compass Direction

Field	Size	Position		Comment
Internal Use	21	1	21	
Duplicate Key Flag or Continuous Parity	1	22	22	
Locational Status of Segment	1	23	23	
County Boundary Indicator	1	24	24	
DCP-Preferred LGC for Street 1	2	25	26	
DCP-Preferred LGC for Street 2	2	27	28	
DCP-Preferred LGC for Street 3	2	29	30	
Number of Cross Streets at Low Address End	1	31	31	
List of Cross Streets at Low Address End (Up to five B5SCs, 6 bytes each)	30	32	60	

Number of Cross Streets at High Address End	1	62	62	
List of Cross Streets at High Address End (Up to five B5SCs, 6 bytes each)	30	63	92	
Cross Street Reversal Flag	1	93	93	
LION KEY	10	94	103	
LION Borough Code	1	94	94	
LION Face Code	4	95	98	
LION Sequence Number	5	99	103	
Generated Record Flag	1	104	104	
Length of Segment in Feet	5	105	109	
Segment Azimuth	3	110	112	
Segment Orientation	1	113	113	
Marble Hill/Rikers Island Alternative Borough Flag	1	114	114	
Filler	19	155	133	
Segment Identifier	7	134	140	
DOT Street Light Contractor Area	1	141	141	
Side of Street Indicator	1	142	142	
Curve Flag	1	143	143	
Feature Type Code	1	144	144	
Filler	6	145	150	
Community District:	3			
Community District Borough Code	1	151	151	
Community District Number	2	152	153	
Low House Number of Block Face	16	154	169	Display Format
High House Number of Block Face	16	170	185	Display Format
Alternate Low House Number	16	186	201	Supplied for Continuous
Alternate High House Number	16	202	217	Parity - Display Format
Interim Assistance Eligibility Indicator	1	218	218	
Zip Code	5	219	223	
Health Area	4	224	227	
Police Patrol Borough Command	1	228	228	
Police Precinct	3	229	231	
Fire Division	2	232	233	
Fire Battalion	2	234	235	
Fire Company Type	1	236	236	
Fire Company Number	3	237	239	
Community School District	2	240	241	
Dynamic Block	3	242	244	
Instructional Region	2	245	246	

Filler	7	247 253
1990 Census Tract	6	254 259
2000 Census Tract	6	260 265
2000 Census Block	4	266 269
Filler	31	270 300

Work Area 2 (COW) - Function 3S

Street Stretch Defined by 'ON' Street and Optionally Two Cross Streets

Field	Size	Position	Comment
Internal Use	2	1 2	
Primary/Secondary Street Name Indicator	1	3 3	P=Primary S = Secondary[16]
Borough Code	1	4 4	
5-Digit Street Code of 'on' Street	5	5 9	
LGC	2	10 11	Blank if P in position 3
Filler	10	12 21	Always Blank
NUMBER OF INTERSECTIONS	3	22 24	
LIST OF UP TO 350 Intersections Each List Entry is 55 bytes in length, structured as follows:	19,250	25 19,274	
Marble Hill/Rikers Island Flag	1		
Distance from previous intersection in list	5		
Gap Flag	1		
Node Number	7		
Number of streets at this intersection	1		
B7SC of a street at this intersection (up to 5)	40		DCP Preferred LGC

```
/*******************************************/
typedef struct {
  char boro; /* Borough Code char SC10[10]; /*
}
/*******************************************/
```

---

[4] Geosupport Desktop Edition supports the Character-Only Work Area format. The mainframe version of Geosupport supports both the Character-Only format (COW) and the Mainframe Specific format (MFS).

[5] An asterisk in the second position of a function code is used as a shorthand notation to represent all function codes having the indicated value in the first position, as follows:

[6] The user may supply either a 5-Digit, 7-Digit or 10-Digit Street code in this field. The contents are to be left-justified and blank-filled.

[7] The second and third borough codes are only required if they differ from the first.

[8] When the Work Area Format Indicator (a.k.a. the Platform Indicator) is set to C, Character-Only formats of the work areas (i.e., the formats documented herein) are used. A blank in this indicator means that the mainframe compatible work areas, known as MFS, are used.

[9] The Long Work Area 2 Flag is set to L to request the Long Work Area 2. At present it may only be set to L for Functions 1A and BL and means that a list of BINS will be returned in Work Area 2 to the user in place of the list of addresses.

[10] If the house number is to be right justified, the House Number Justification Flag is set to R and if the house number is to be left justified, the House Number Justification Flag is set to L or left blank.

[11] The House Number Normalization Length field is used to achieve compatibility between the MainFrame Specific (MFS) work areas and the COWs. In the COWs, the House Number is permitted to be 16 characters, but, in the MFS, it is limited to 12 characters. It is not anticipated that users will make use of this field.

[12] If the Street Name Normalization Format Flag is set to S or blank, then the street name is returned in sort format. If it is set to C, then the street name is returned in compact format.

[13] The Cross Street Names Flag (a.k.a Expanded Format Flag), if set to E, will return the street names in the List of Street Names in the output section of Work Area 1. BBL and BIN are also returned where possible.

[14] NAP Identification Number

[15] For Function 1E, the Board of Elections preferred LGC is provided.

[16] The functionality which creates the street stretches based upon the different LGCs has not been implemented.

APPENDIX 20: GEOSUPPORT HEADER AND TYPEDEF FILES

This appendix contains listings of a Geosupport Header file for C/C++ and a Geosupport Typedef file for Visual Basic. It is strongly recommended that you use the supplied files, because in the future they will be modified to reflect any changes to the various work areas.

The distributed filenames are:

C/C++ Header file	pac.h
Visual Basic Typedef file	vbwadef.bas

You may use different names in your environment.

C/C++ HEADER File

```
#ifndef GEOSUPPORT
char test;
# define GEOSUPPORT
ifdef __ cplusplus
extern "C" {
#endif
/*********************************************************************/
/*                                                                   * /
/*      GeoSupport System C-Language Header F                        * /
/*       for Platform-Independent Work Area                          * /
/*                                                                   * /
/*         Last Updated: 15 December 2003                            * /
/*                                                                   * /
/*********************************************************************/


/*********************************************************************/
/*                                                                   * /
/* Group Items Used in Platform-Independent Work Area 1              * /
/*                                                                   * /
/*********************************************************************/

typedef struct {  char boro;               /* Borough Code         * /
                  char SC10[10];           /* 10 Digit Street Code * /
                  char Street_name[32];    /* Street Name          * /
                }  STREET;
```

```
typedef union { char bbl[10];              /* Borough-Block-Lot    * /
                struct { char boro;       /* Borough              * /
                         char block[5];   /* Tax Block            * /
                         char lot[4];     /* Tax Lot              * /
                       } cas;
              }BBL;

typedef struct {
                char func_code[2];       /* Function Code          * /
                char hse_nbr_disp[16];   /* House nbr in Disp form  * /
                char hse_nbr_hns[11];    /* House nbr in Sort form  * /
                char lohse_nbr_disp[16]; /* Lo House nbr in Disp form*/
                char ohse_nbr_hns[11];   /* Lo House nbr in Sort form*/
                STREET sti[3];           /* Street Information      * /
                BBL bbli;                /* Borough-Block-Lot       * /
                char filler01;           /* Filler-Tax Lot Version #* /
                char bld_id[7];          /* Building Id Number (BIN) * /
                char comp_direction;     /* Compass Direction        * /
                char comp_direction2;    /* Compass Direction-Fn 3S  * /
                char filler02[7];        /* Future Use               * /
                char platform_ind;       /* Must be equal to 'C'     * /
                char filler03[101];      /* Future Use               * /
                  /* Flags that influence processing  * /
                char long_WA_flag;       /* Long Work Area 2 Flag    * /
                char hse_nbr_justify;    /* Hse Nbr Justification Flg* /
                char hnl[2];             /* Hse Nbr Normalization len* /
                char hse_nbr_over_flag;  /* Reserved for GSS Use     * /
                char snl[2];             /* Street Name Norm Length  * /
                char st_name_norm;       /* Street Name Normalization* /
                                         /* Format Flag              * /
                char expanded_format;    /* Expanded Format Flag     * /
                char filler04[37];       /* Future Use               * /
              } INWA1;

typedef struct{
                char boro_name[9];       /* Boro Name of First Street* /
                char hse_nbr_disp[16];   /* House nbr in Normalized  * /
                                         /* Display form             * /
                char hse_nbr_hns[11];    /* House number in Sort Form* /
                STREET sto[3];           /* Street Information       * /
                BBL bblo;                /* Boro(len=1), Block(len=5 * /
                                         /* and Lot (len=4)-Normalizd* /
                char filler05;           /* Filler-Tax Lot Version # * /
                char lo_hse_nbr_disp[16];/* low Hse nbr - display    * /
                char lo_hse_nbr_hns[11]; /* low Hse nbr - sort form  * /
```

```
              char bin[7];             /* Building Id Number       * /
              char attrbytes[3];       /* NAP Identification Number* /
              char filler07[132];      /* Future Use               * /
              char nap_id_nbr[6];      /* NAP Id Nbr - Not Impl.   * /
              char int_use1;           /* Internal Use Only        * /
              char reason_code;        /* Reason Code              * /
              char filler08;           /* Future Use               * /
              char warn_code[2];       /* Warning Ret. Code-NotImpl* /
              char ret_code[2];        /* GeoSupport Return Code   * /
              char msg[80];            /* GeoSupport Message       * /
              char nbr_names[2];       /* Nbr of Sreet Names       * /
              char B_7SC[10][8];       /* 10 Boro+7-digit st codes * /
              char st_names[10][32];   /* Up to 10 Street Names    * /
            }OUTWA1;

/*********************************************************************/
/*                  Platform-Independent Work Area 1                 * /
/*                                                                   * /
/*                                                                   * /
/*********************************************************************/

typedef struct { INWA1 input;
                 INWA1 output;
               }C_WA1;

/*********************************************************************/
/*       Group Items Used in Platform-Independent Work Area 2's      * /
/*                                                                   * /
/*                                                                   * /
/*********************************************************************/

typedef struct {                        /* LION KEY                 * /
                char lion_boro;         /* LION Borough Code        * /
                                        /* Differs from GeoSupport * /
                                        /* Borough Code             * /
                char face[4];           /* Face Code                * /
                char seq[5];            /* Sequence Number          * /
              }LION;

typedef struct {
                char nbr_sts;            /* Number of Streets       * /
                char B5SC[5][6];         /* Boro+5 Street Code      * /
              }St_list;

typedef struct {
```

```
                char lo_hse_nbr[16];      /* Low House Nbr-Disply form* /
                char hi_hse_nbr[16];      /* Hi House Nbr-Display form* /
                char B5SC[6];             /* Boro & 5 digit Str Code  * /
                char lgc[2];              /* DCP Preferred Street LGC * /
                char bld_id[7];           /* BIN of address range     * /
                char sos_ind;             /* Side of Street Indicator * /
                char adr_type;            /* Address type - P=NAP,    * /
                                          /* B=NAB, Blank=Normal      * /
                char filler01[4];         /* Future Use               * /
              }ADDR_RANGE;

typedef struct{
              char sanborn_boro;          /* Sanborn Borough Code      * /
              char sanborn_vol[3];        /* Sanborn Volume            * /
              char sanborn_page[4];       /* Sanborn Page              * /
              }SANBORN;

typedef struct {
                char com_dist[3];         /* Community District        * /
                char lo_hse_nbr[16];      /* Low House Nbr-Disply form * /
                char hi_hse_nbr[16];      /* Hi House Nbr-Display form * /
                char filler01[32];        /* Future Use                * /
                char iaei;                /* Interim Ass'tance Elig    * /
                                          /* Indicator                 * /
                char zip_code[5];         /* Zip code for Street seg   * /
                char health_area[4];      /* Health Area               * /
                char police_boro_com;     /* Police Patrl Boro Command * /
                char police_pre[3];       /* Police Precinct           * /
                char fire_divisn[2]       /* Fire Division             * /
                char fire_bat[2];         /* Fire Battalion            * /
                char fire_co_type;        /* Fire Company Number       * /
                char com_schl_dist[2];    /* Community School District * /
                char dynam_blk[3];        /* Dynamic Block             * /
                char instruc_div[2];      /* Instructional Division    * /
                char filler02[7];         /* Future Use                * /
                char cen_tract_90[6];     /* 1990 Census Tract         * /
                char cen_tract_00[6];     /* 2000 Census Tract         * /
                char cen_blk_00[4];       /* 2000 Census Block         * /
                char filler03[1 ];        /* Possible Census Blk Suff  * /
                char filler04[30];        /* Future Use                * /
                }SEGSIDE;

typedef struct {
              char mh_ri_flag;            /* Marble Hill/Rikers Island * /
                                          /* Alternative Boro flag     * /
```

```
                char len[5];                /* Len in ft from prev node  * /
                char gap_flag;              /* Gap Flag                  * /
                char node_nbr[7];           /* Node Number of Intersect  * /
                char nbr_streets;           /* Nbr streets intersecting  * /
                                            /* Lowest B7SC at Intersect  * /
                                            /* is first and 2nd Lowest   * /
                                            /* B7SC is next. Remaining   * /
                                            /* B7SC's in no particular   * /
                                            /* order                     * /
              }CROSS_STRS;

/*************************************************************************/
/*        Platform-Independent Work Area 2 for Function 1                * /
/*                                                                       * /
/*                                                                       * /
/*************************************************************************/

typedef struct {
                char filler01[21];
                cont_parity_ind;            /* Continuous Parity Ind.    * /
                                            /* or Duplicate Address Ind. * /
                char lo_hse_nbr[11];        /* Lo House nbr in Sort form * /
                char hi_hse_nbr[11];        /* Hi House Nbr in Sort form * /
                char lgc[2];                /* DCP or BOE Preferred LGC  * /
                St_list st[2];              /* 1=Low and 2=High          * /
                                            /* Nbr of cross streets at   * /
                                            /* low house nbr end of st   * /
                                            /* B5SCs of lo end cross st  * /
                LION key;                   /* LION Key - 10 Characters  * /
                char sagr_flag;             /* Special Address Generated * /
                                            /* Record flag               * /
                char sos_ind;               /* Side of Street Indicator  * /
                char seg_len[5];            /* Segment Length in Feet    * /
                char coord[3][7];           /* 1 = X coordinate,         * /
                                            /* 2 = Y coordinate,         * /
                                            /* 3 = Z coordinate, Not Imp * /
                char iaei;                  /* Interim Ass'tance Elig    * /
                                            /* Indicator                 * /
                char mh_ri_flag;            /* Marble Hill/Rikers Island * /
                                            /* Alternative Borough flag  * /
                char DOT_slcaz              /* DOT St Lght Contractr Are * /
                char com_dist[3];           /* Community District        * /
                                            /* Position 0 contains the   * /
                                            /* CD Boro Code & Pos 1 & 2, * /
                                            /* the district number       * /
```

```
            char zip_code[5];           /* Zip code for st seg       * /

            /*      Following seven fields             * /
            /*      used for Function 1E only          * /

            char ed[3];                 /* Election District         * /
            char ad[2];                 /* Assembly District         * /
            char sped_flag;             /* Split Elect District Flag * /
            char congress_dist[2];      /* Congressional District    * /
            char state_sen_dist[2];     /* State Senatorial District * /
            char civil_court[2];        /* Civil Court District      * /
            char city_council[2];       /* City Council District     * /
            char health_cent[2];        /* Health Center District    * /
            char health_area[4];        /* Health Area               * /
            char sanit_dist[3];         /* Sanitation District       * /
            char sanit_sub_sect[2];     /* Sanit Collect Scheduling  * /
                                        /* Section and Subsection    * /
            char sanit_reg_pick_up[5];  /* Regular Pick up           * /
            char sanit_recycle[3];      /* sanit_recycle[3];         * /
            char police_boro_com;       /* Police Patrol Boro Commnd * /
            char police_pre[3];         /* Police Precinct           * /
            char fire_divisn[2];        /* Fire Division             * /
            char fire_bat[2];           /* Fire Battalion            * /
            char fire_co_type;          /* Fire Company Type         * /
            char fire_co_nbr[3];        /* Fire Company Number       * /
            char scsd_flag;             /* Split Com School District * /
                                        /* flag                      * /
            char com_schl_dist[2];      /* Community School District * /
            char dynam_blk[3];          /* Dynamic Block             * /
            char instruc_div[2];        /* Instructional Division    * /
            char feature_type;          /* Feature Type Code         * /
            char filler02[6];           /* Future Use                * /
            char cen_tract_90[6];       /* 1990 Census Tract         * /
            char cen_tract_00[6];       /* 2000 Census Tract         * /
            char cen_blk_00[4];         /* 2000 Census Block         * /
            char filler03[01];          /* Possible Census Blk Suff  * /
            char filler04[50];          /* Future Use                * /
            char true_b7sc[8];          /* True Boro 7 Street Code   * /
            char seg_id[7];             /* Segment Identifier        * /
            char curv_flag;             /* Curve Flag                * /
          } C_WA2_F1;

/*********************************************************************/
/*       Platform-Independent Work Area 2 for Function 1A            * /
/*                                                                   * /
```

```
/*                                                                    * /
/*********************************************************************/

typedef struct {
                char filler01[21];
                char cont_parity_ind;   /* Continuous Parity Ind     * /
                                        /* or Duplicate Address Ind  * /
                char lo_hse_nbr[11];    /* Low House Number-Sort Frm * /
                BBL bbl;                /* Borough-Block-Lot         * /
                char filler02;          /* Reserved for Tax Lot Ver# * /
                char RPAD_scc;          /* RPAD Self_Check Code(SCC) * /
                char filler03;
                char RPAD_lucc[2];      /* RPAD Land Use Class. Code * /
                char corner[2];         /* Corner Code               * /
                char nbr_blds[4];       /* Nbr of buildings on lot   * /
                char nbr_str[2];        /* Nbr Street Frontages      * /
                char inter_flag;        /* Interior Lot Flag         * /
                char vacant_flag;       /* Vacant Lot Flag           * /
                char irreg_flag;        /* Irregularly-Shaped Lot Fl * /
                char mh_ri_flag;        /* Marble Hill/Rikers Island * /
                char adr_range_overflow;/* Addr Rnge Lst Ovrflow Flg * /
                char stroll_key[18];    /* Strolling key             * /
                char filler04;
                char res_internal_use;  /* Reserved for Internal Use * /
                char bld_id[7];         /* Building Ident. Number    * /
                                        /* (BIN) of Input Address of * /
                                        /* Existing Building, If any * /
                char condo_flag;        /* Condominium Flag          * /
                char filler05;          /* Future Use                * /
                char condo_id[4];       /* RPAD Condo Id Number      * /
                char condo_unit_id[7];  /* Condo Unit Id Nbr-Not Impl* /
                BBL condo_bill_bbl;     /* Condo Billing BBL         * /
                char filler06;          /* Reserved for Tax Lot Ver  * /
                char condo_scc;         /* Self-Check Code           * /
                BBL  condo_lo_bbl;      /* Low BBL of Condo          * /
                char filler07;          /* Reserved for Tax Lot Ver  * /
                BBL  condo_hi_bbl;      /* High BBL of Condo         * /
                char filler08;          /* Reserved for Tax Lot Ver  * /
                char filler09[15];
                char co_op_nbr[4];      /* Co-op Number              * /
                SANBORN San;            /* Sanborn Information       * /
                char business_area[5];  /* Business Area             * /
                char tax_map_nbr[5];    /* Tax Map Nbr-Sect and Vol  * /
                char filler10[4 ];      /* Tax Map Nbr Page Not Impl * /
                char filler11[23];
```

```
                char coord[2][7];       /* 1 = X coordinate-Annotat  * /
                                        /* 2 = Y coordinate-Annotat  * /
                char filler12[25];
                char int_use[8];        /* Internal Use              * /
                char nbr_addr[4];       /* Nbr of Addr Ranges or Nbr * /
                                        /* of BINs in List           * /

                union {
                      ADDR_RANGE addr_range[21];    /* List of Addr  * /
                      char bin_list[2500][7];       /* Ranges or BINs* /
                    }bar;
                  } C_WA2_F1A;


/*********************************************************************/
/*                                                                   * /
/*         Platform-Independent Work Area 2 for Function 2           * /
/*********************************************************************/

typedef struct {
                char filler01[21];
                char rep_cnt;           /* Intersection Replication  * /
                char lgc[2][2];         /* Preferred LGCs            * /
                St_list inter;          /* Number of Intersecting St * /
                                        /* B5SCs of Intersection St  * /
                char Dup_comp;          /* Duplicate compass Directn * /
                char filler02[5 ];
                char LION_node_nbr[7 ]; /* LION Node Number          * /
                char coord[3][7];       /* 1 = X coordinate,         * /
                                        /* 2 = Y coordinate,         * /
                                        /* 3 = Z coordinate, Not Imp * /
                SANBORN San[2];         /* Sanborn Information       * /
                char mh_ri_flag;        /* Marble Hill/Rikers Island * /
                char DOT_slca;          /* DOT St Lght Contractr  Are* /
                char com_dist[3];       /* Community District        * /
                char zip_code[5];       /* Zip code for st segment   * /
                char health_area[4];    /* Health Area               * /
                char police_boro_com;   /* Police Patrol Boro Commnd * /
                char police_pre[3];     /* Police Precinct           * /
                char fire_sector[2];    /* Fire Sector               * /
                char fire_bat[2];       /* Fire Battalion            * /
                char fire_co_type;      /* Fire Company Type         * /
                char fire_co_nbr[3];    /* Fire Company Number       * /
                char com_schl_dist[2];  /* Community School District * /
                char cen_tract_00[6];   /* 2000 Census Tract         * /
```

```
                char cen_tract_90[6];   /* 1990 Census Tract         * /
                char level_codes [10];  /* Level codes               * /
                char instruc_div [2];   /* Instructional Division    * /
                char filler03[41];
               } C_WA2_F2;

  /*********************************************************************/
  /*                                                                   * /
  /*        Platform-Independent Work Area 2 for Function 3            * /
  /*                                                                   * /
  /*********************************************************************/

  typedef struct {
                 char filler01[21];
                 char dup_key_flag     /* Duplicate Key Flag or     * /
                                       /* Continuous Parity Flag    * /
                 char loc_stat_seg;    /* Locational Status of Seg  * /
                 char cnty_bnd_ind;    /* County Boundary Indicat   * /
                 char lgc[3][2];       /* Preferred LGCs            * /
                 St_list st[2];        /* 1=Low and 2=High          * /
                                       /* Nbr of cross sts at low   * /
                                       /* house nbr end of street   * /
                                       /* B5SCs of lo end X sts     * /
                 char x_street_reversal_flag;/* X St Reversal Flag  * /
                 LION key;             /* LION Key                  * /
                 char genr_flag;       /* Generated Record Flag     * /
                 char seg_len[5];      /* Segment Length in Feet    * /
                 char seg_azm[3];      /* Segment Azimuth           * /
                 char seg_orient;      /* Segment Orientation       * /
                 char mh_ri_flag;      /* Marble Hill/Rikers Island * /
                                       /* Alternative Boro flag     * /
                 char filler02[19];    /* Future use                * /
                 char seg_id[7];       /* Segment Identifier        * /
                 char DOT_slca;        /* DOT St Lght Contractr Are * /
                 char curve_flag;      /* Curve Flag                * /
                 char dog_leg;         /* Dog leg flag              * /
                 char feature_type;    /* Feature Type Code         * /
                 char filler03[6];
                 SEGSIDE side[2];      /* 1 = Left Side of street   * /
                                       /* 2 = Right Side of street  * /
                } C_WA2_F3;

/*********************************************************************/
/*        Platform-Independent Work Area 2 for Function 3C           * /
/*                                                                   * /
```

```
/*                                                                    * /
/**********************************************************************/

typedef struct {
                char filler01[21];
                char dup_key_flag;      /* Duplicate Key Flag or     * /
                                        /* Continuous Parity Flag    * /
                char loc_stat_seg;      /* Locational Status of Seg  * /
                char cnty_bnd_ind;      /* County Boundary Indicat   * /
                char lgc[3][2];         /* Preferred LGCs            * /
                St_list st[2];          /* 1=Low and 2=High          * /
                                        /* Nbr of cross sts at low   * /
                                        /* house nbr end of street   * /
                                        /* B5SCs of lo end Cross sts * /
                char x_street_reversal_flag /* X St Reversal Flag    * /
                LION key;               /* LION key                  * /
                char genr_flag;         /* Generated Record Flag     * /
                char seg_len[5];        /* Segment Length in Feet    * /
                char seg_azm[3];        /* Segment Azimuth           * /
                char seg_orient;        /* Segment Orientation       * /
                char mh_ri_flag;        /* Marble Hill/Rikers Island * /
                                        /* Alternative Boro flag     * /
                char filler02[19];      /* Future use                * /
                char seg_id  [7];       /* Segment Identifier        * /
                char DOT_slca;          /* DOT St Lght Contractr Are * /
                char sos_ind;           /* Side of Street Indicator  * /
                char curve_flag;        /* Curve Flag                * /
                char feature_type;      /* Feature Type Code         * /
                char filler03[6];
                SEGSIDE req;            /* Geographic Information for* /
                                        /* Requested Side of segment * /
                } C_WA2_F3C;

/**********************************************************************/
/*        Platform-Independent Work Area 2 for Function 3S           * /
/*                                                                    * /
/*                                                                    * /
/**********************************************************************/

typedef struct {
                char filler01[21];
                char nbr_x_str[3];      /* Nbr of Cross sts in list  * /
                CROSS_STRS cross_strs[350]; /* Cross Street structure* /
                } C_WA2_F3S;
```

```
    #ifdef __ cplusplus
    #endif
    #endif
```

VISUAL BASIC TYPEDEF File

```
Option Explicit

'*****************************************************************

'*** geosupport for windows work area type defs for visual basic

'*****************************************************************
'*** Types must be declared as Private within Form Modules
'*****************************************************************
'*****************************************************************
'*** typedefs used in workareas
'*****************************************************************

STREET_type
  boro As String * 1
  sc10 As String * 10
  street_name As String * 32
End Type

Type BBL_type
 boro As String * 1
 block As String * 5
 lot As String * 4
End Type

Type ADDR_RANGE_type
 lo_housenum As String * 16
 hi_housenum As String * 16
 B5SC As String * 6
 lgc As String * 2
 bin As String * 7
 sos_ind As String * 1
 addr_type As String * 1
 filler01 As String * 4
End Type

'*****************************************************************
'*** typedef for input area of workarea 1
```

```
'*****************************************************************
Type INPUT_DEF
  func_code As String * 2
  housenum As String * 16
  housenum_sort As String * 11
  lo_housenum As String * 16
  lo_housenum_sort As String * 11
  sti(1 To 3) As STREET_type
  bbli As BBL_type
  filler01 As String * 1
  bin As String * 7
  compass As String * 1
  compass2 As String * 1
  filler02 As String * 7
  platform_ind As String * 1
  filler03 As String * 101
  long_WA2_flag As String * 1
 filler04 As String * 4
 snl As String * 2
 st_name_norm As String * 1
 expanded_format As String * 1
 filler05 As String * 37
End Type

'*****************************************************************
'*** typedef for output area of workarea 1
'*****************************************************************
Type OUTPUT_DEF
  boro_name As String * 9
  housenum As String * 16
  housenum_sort As String * 11
  sto(1 To 3) As STREET_type
  bblo As BBL_type
  filler05 As String * 1
  lo_housenum As String * 16
  lo_housenum_sort As String * 11
  bin As String * 7
  street_attr(1 To 3) As String * 1
  filler06 As String * 139
  reason_code As String * 1
  filler07 As String * 1
  warning_code As String * 2
  return_code As String * 2
  error_msg As String * 80
  similar_stnames_cnt As String * 2
```

```
  similar_B7SC(1 To 10) As String * 8
  similar_stnames(1 To 10) As String * 32
End Type

'*****************************************************************
'*** typedef for workarea 1
'*****************************************************************
Type C_WA1
  input1 As INPUT_DEF
  output1 As OUTPUT_DEF
End Type

'*****************************************************************
'*** typedefs used in workarea 2
'*****************************************************************
Type ST_LIST_type
  street_cnt As String * 1
  B5SC(1 To 5) As String * 6
End Type

Type LION_type
  boro As String * 1
  face As String * 4
  seq As String * 5
End Type

Type SANBORN_type
  boro As String * 1
  vol As String * 3
  page As String * 4
End Type

Type DOF_MAP_type
  boro As String * 1
  secvol As String * 4
  page As String * 4
End Type

Type SEGSIDE_type
  com_dist As String * 3
  lo_housenum As String * 16
  hi_housenum As String * 16
  filler01 As String * 32
  iaei As String * 1
  zip_code As String * 5
```

```
  health_area As String * 4
  police_boro_com As String * 1
  police_pct As String * 3
  fire_div As String * 2
  fire_bat As String * 2
  fire_co_type As String * 1
  fire_co_num As String * 3
  school_dist As String * 2
  dynamic_block As String * 3
  instruct_div As String * 2
  filler02 As String * 7
  cen_tract_1990 As String * 6
  cen_tract_2000 As String * 6
  cen_block_2000 As String * 4
  filler_03 As String * 31
End Type

Type CROSS_STRS_type
  mh_ri_flag As String * 1
  street_len As String * 5
  gap_flag As String * 1
  node_nbr As String * 7
  street_cnt As String * 1
  B7SC(1 To 5) As String * 8
End Type


'*****************************************************************
'*** typedef for workarea 2 for function 1/1E
'*****************************************************************

Type C_WA2_F1E
  fillera As String * 21
  cont_parity_dup_addr_ind As String * 1
  lo_housenum_sort As String * 11
  hi_housenum_sort As String * 11
  DCP_pref_lgc As String * 2
  lo_x_sts As ST_LIST_type
  hi_x_sts As ST_LIST_type
  lion_key As LION_type
  spec_addr_flag As String * 1
  sos_ind As String * 1
  segment_len As String * 5
  spatial_xyz_coord(1 To 3) As String * 7
  res_GSS As String * 1
```

```
  mh_ri_flag As String * 1
  DOT_st_light_cont_area As String * 1
  com_dist As String * 3
  zip_code As String * 5
  ED As String * 3
  AD As String * 2
  split_ED As String * 1
  CD As String * 2
  SD As String * 2
  MC As String * 2
  CO As String * 2
  health_center_dist As String * 2
  health_area As String * 4
  san_dist As String * 3
  san_sched As String * 2
  san_reg As String * 5
  san_recycle As String * 3
  police_boro_com As String * 1
  police_pct As String * 3
  fire_div As String * 2
  fire_bat As String * 2
  fire_co_type As String * 1
  fire_co_num As String * 3
  split_school_dist_flag As String * 1
  school_dist As String * 2
  dynamic_block As String * 3
  instruct_div As String * 2
  feature_type As String * 1
  filler_80ct As String * 6
  census_tract_1990 As String * 6
  census_tract_2000 As String * 6
  census_block_2000 As String * 4
  filler_left As String * 51
  real_b7sc As String * 8
  segment_id As String * 7
  curve_flag As String * 1
End Type


'*****************************************************************
'*** typedef for workarea 2 for function 1A
'*****************************************************************

Type C_WA2_F1A
  filler01 As String * 21
```

```
  cont_parity_ind As String * 1
  lo_housenum_sort As String * 11
  bbl As BBL_type
  filler02 As String * 1
  RPAD_scc As String * 1
  filler03 As String * 1
  RPAD_bldg_class As String * 2
  corner As String * 2
  num_of_bldgs As String * 4
  num_of_structures As String * 2
  interior_flag As String * 1
  vacant_flag As String * 1
  irreg_flag As String * 1
  mh_ri_flag As String * 1
  addr_range_overflow As String * 1
  stroll_key As String * 19
  res_internal_use As String * 1
  bin As String * 7
  condo_flag As String * 1
  filler05 As String * 1
  condo_id As String * 4
  filler05b As String * 7
  condo_bill_bbl As BBL_type
  filler06 As String * 1
  condo_bill_scc As String * 1
  condo_lo_bbl As BBL_type
  filler07 As String * 1
  condo_hi_bbl As BBL_type
  filler08 As String * 1
  filler09 As String * 15
  coop_num As String * 4
  Sanborn As SANBORN_type
  business_area As String * 5
  DOF_map AS DOF_MAP_type
  reserved_dcp As String * 23
  x_coord As String * 7
  y_coord As String * 7
  filler10 As String * 25
  int_use As String * 8
  numaddr As String * 4
  addr_range As ADDR_RANGE_type
End Type

'*****************************************************************
'*** typedef for workarea 2 for function 1A long
```

```
'*****************************************************************
Type C_WA2_F1AL
  filler01 As String * 21
  cont_parity_ind As String * 1
  bbl As BBL_type
  filler02 As String * 1
  RPAD_scc As String * 1
  filler03 As String * 1
  RPAD_bldg_class As String * 2
  corner As String * 2
  num_of_bldgs As String * 4
  num_of_structures As String * 2
  interior_flag As String * 1
  vacant_flag As String * 1
  irreg_flag As String * 1
  mh_ri_flag As String * 1
  addr_range_overflow As String * 1
  stroll_key As String * 19
  res_internal_use As String * 1
  bin As String * 7
  condo_flag As String * 1
  filler05 As String * 1
  condo_id As String * 4
  filler05b As String * 7
  condo_bill_bbl As BBL_type
  filler06 As String * 1
  condo_bill_scc As String * 1
  condo_lo_bbl As BBL_type
  filler07 As String * 1
  condo_hi_bbl As BBL_type
  filler08 As String * 1
  filler09 As String * 15
  coop_num As String * 4
  Sanborn As SANBORN_type
  business_area As String * 5
  DOF_map AS DOF_MAP_type
  filler10 As String * 62
  int_use As String * 8
  num_of_bins As String * 4
  bin_list(1 To 2500) As String * 7
End Type


'*****************************************************************
'*** typedef for workarea 2 for function 2
```

```
'*****************************************************************

Type C_WA2_F2
  filler01 As String * 21
  dup_intersect_cnt As String * 1
  DCP_pref_lgc(1 To 2) As String * 2
  intersect_str As ST_LIST_type
  compass As String * 1
  filler02 As String * 5
  lion_node_num As String * 7
  spatial_xyz_coord(1 To 3) As String * 7
  Sanborn(1 To 2) As SANBORN_type
  mh_ri_flag As String * 1
  DOT_slca As String * 1
  com_dist As String * 3
  zip_code As String * 5
  health_area As String * 4
  police_boro_com As String * 1
  police_pct As String * 3
  fire_div As String * 2
  fire_bat As String * 2
  fire_co_type As String * 1
  fire_co_num As String * 3
  school_dist As String * 2
  census_tract_2000 As String * 6
  census_tract_1990 As String * 6
  level_codes (1 to 5, 1 to 2) As String * 1
  instruct_div As String * 2
  filler03 As String * 41
End Type


'*****************************************************************
'*** typedef for workarea 2 for function 3
'*****************************************************************
Type C_WA2_F3
  filler01 As String * 21
  dup_key_flag As String * 1
  loc_status As String * 1
  county_boundary_ind As String * 1
  DCP_pref_lgc(1 To 3) As String * 2
  lo_x_st As ST_LIST_type
  hi_x_st As ST_LIST_type
  x_street_reversal_flag As String * 1
  lion_key As LION_type
```

```
  generated_rec_flag As String * 1
  segment_len As String * 5
  segment_azm As String * 3
  segment_orient As String * 1
  mh_ri_flag As String * 1
  filler02 As String * 19
  segment_id As String * 7
  DOT_slca As String * 1
  curve_flag As String * 1
  dog_leg As String * 1
  feature_type As String * 1
  filler03 As String * 6
  side_info(1 To 2) As SEGSIDE_type
End Type


'*****************************************************************
'*** typedef for workarea 2 for function 3C
'*****************************************************************
Type C_WA2_F3C
  filler01 As String * 21
  dup_key_flag As String * 1
  loc_status As String * 1
  county_boundary_ind As String * 1
  DCP_pref_lgc(1 To 3) As String * 2
  lo_x_st As ST_LIST_type
  hi_x_st As ST_LIST_type
  x_street_reversal_flag As String * 1
  lion_key As LION_type
  generated_rec_flag As String * 1
  segment_len As String * 5
  segment_azm As String * 3
  segment_orient As String * 1
  mh_ri_flag As String * 1
  filler02 As String * 19
  segment_id As String * 7
  DOT_slca As String * 1
  sos_ind As String * 1
  curve_flag As String * 1
  feature_type As String * 1
  filler03 As String * 6
  side_info As SEGSIDE_type
End Type
```

```
'*****************************************************************
'*** typedef for workarea 2 for function 3S
'*****************************************************************

Type C_WA2_F3S
  filler01 As String * 21
  intersect_num As String * 3
  x_sts(1 To 350) As CROSS_STRS_type
End Type
```

APPENDIX 21: Geosupport Desktop Edition: Quick Start Instructions

Minimum system requirements: PC running Windows 95 or higher 800 megabytes of available harddisk space CD-Rom drive

Step 1. Start Install Program

- Download the Geosupport Desktop Edition Application and Extract the application from the compressed(zippped) folder.
- Run the setup file from the downloaded application, double click setup> Run
- If Install Program does not start up, click Start > Run > downloads\gde_17b\setup > OK.

Step 2. Respond to Install Options

- The only question you need to answer is where you want the Geosupport Desktop Edition directory to reside. The default is *'harddrive:\Program Files\'*. You may change this if you want. Also your computer's default program directory might not be 'Program Files'. This will result in the Geosupport Desktop Editon directory residing in a directory other than *'harddrive:\Program Files\'*.
- After the Install Program has completed, re-start your computer. You are now ready to use Geosupport Desktop Edition.

Step 3. Verify that Installation was Successful

- Using Windows Explorer, navigate to the directory where Geosupport Desktop Editon programs were installed (*('harddrive:\Program Files\Geosupport Desktop Edition\Bin'* is the default).
- Double click on 'Goat.exe'.
- Select '1' from the toolbar. Enter '22' in the House Number box. Enter 'Reade Street' in the Street Name box. Click on the Manhattan radio button for the Borough. Press the OK button. If Geosupport Desktop Edition was successfully installed, then you should see data displayed in the window.

Congratulations on Successfully Installing Geosupport Desktop Edition

User documentation can be found in C:\Program Files\Geosupport Desktop Editon\Doc

- If you are interested in more information on how to use Goat, go to Chapter III: GOAT in the Geosupport Desktop Edition User Programming Guide.
- If you are interested in geocoding an existing PC database, go to Chapter IV: GBAT in the Geosupport Desktop Edition User Programming Guide.
- If you are interested in writing your own programs see Chapter II: Geosupport Desktop Edition API in the Geosupport Desktop Edition User Programming Guide.

View C:\Program Files\Geosupport Desktop Edition\readme.txt for additional items.

Geosupport System General Overview

FOREWORD

The Geosupport System is a data processing system originally designed to run on IBM mainframes to support many of the geographic processing needs common to New York City agencies. Geosupport was developed and is maintained and enhanced by the staff of the Geographic Systems (GSS) of the Department of City Planning's Information Technology Division. Geosupport is highly customized for New York City's geography and is widely recognized to be far superior to any other existing system for processing New York City geographic locations. Currently, Geosupport is used as a component of computer applications in more than thirty New York City agencies. The Geosupport Desktop Edition™ can be readily incorporated into users' Windows® based applications that require the processing of geographic data.

This General Overview serves as an introduction to the Geosupport System. It is intended for a general audience, and describes the goals, objectives and capabilities of the system. Other GSS documents contain information for technical managers, software designers, programmers and analysts, particularly the Geosupport System User Programming Guide (UPG) and the Geosupport Desktop Edition™ UPG Supplement.

Geosupport is continually enhanced to provide users with new features. When a new system release is implemented, technical bulletins are distributed to users explaining changes and new features.

To receive further information about Geosupport Desktop Edition, please email: GSS_Feedback@planning.nyc.gov

I Goals And Objectives of The Geosupport System

The computer applications that automate many municipal operations, such as collecting taxes, installing and repairing public infrastructure, processing citizen complaints, issuing permits, and providing social services, have similar geographic processing needs and require similar geographic information in order to be performed effectively and efficiently. Many non-governmental organizations also use geographic information for analysis and planning. Some of these common geographic processing functions are as follows:

- Identify and validate (confirm the existence of) various types of geographic locations, such as street names, addresses, inters and property identifiers (tax block and tax lot numbers).

- Recognize variations when there is more than one way to describe the same location, such as street name spelling variants, alternative street names, three-way inters, multiple addresses for a property.

- Obtain geographic information associated with the input location. Such information includes geographic areas, such as zip codes, community districts, census tracts, school districts, police precincts, city council districts, or application-specific districts, such as contractor areas or inspection zones. Other geographic information that applications may need include alternative addresses for a property, the cross streets adjacent to an address, the approximate distance between inters, and many others.

- Retrieve data from a user file by geographic location. Such retrieval should be consistent, that is, when a location can be specified in more than one way, retrieval should succeed no matter how the location is specified.

The Geosupport System is designed to support user computer applications by providing the above types of geographic processing functionality.

Usage of the Geosupport System has three main benefits:

1. Geosupport centralizes geographic processing among user operations, thus eliminating duplication of effort. Without a centralized system, users would have to develop and maintain their own geographic data files and geographic processing software. Centralization enables many users to benefit from the resources developed by the Department of City Planning's highly-trained staff of programmers with expertise in the specialized field of geographic processing software, and researchers with expertise in map and aerial photography interpretation.
2. Geosupport fosters geographic data compatibility among users' computer applications, resulting in improved efficiency and effectiveness. For example, Geosupport can enhance revenue collection by enabling a city agency that has issued fines to obtain the property identifiers (tax block and tax lot numbers) when an address of the property is known. The user can then retrieve the property owner's mailing address from a file maintained by the Department of Finance. Similarly, activities such as inspections, information gathering and enforcement can be coordinated or consolidated more easily when files are geographically compatible.
3. Geosupport improves the operational efficiency of user applications. This is done by the following means:

    a. Geosupport provides immediate (online) verification of location data (addresses, inters, etc) which lessens or eliminates tedious research to verify the data. This feature is useful for trapping errors when data entry staff record information provided by the general public or field staff.
    b. Geosupport allows users to specify an input location in different ways. As a result,

users do not have to be trained to record locations in a rigid format. For example, Geosupport recognizes that "6th Ave", "Sixth Avenue" and "Avenue of the Americas" all refer to the same street in Manhattan. A different type of example is the three-way inter of Chambers Street, Hudson Street and West Broadway in Manhattan: Geosupport recognizes any pair of these streets as a valid input specification for this inter.

c. Geosupport enables applications to retrieve data from user files consistently by location. 'Consistency' in this context means that, for locations that can be specified in more than one way, retrieval succeeds even if the location is specified differently at inquiry time from the way that it was originally entered. Applications can use this feature to identify and consolidate all of the transactions for a given location. One of the most important ways in which Geosupport enables consistent geographic retrieval of user data is through its system of numeric street codes representing the city's street names. Two different names or spellings of the same street are assigned the same five-digit street code. When designing an application, the user can exploit this design feature to achieve data retrieval from the user's application files that is independent of street name spelling variations. It is important to note that, if street codes are stored in a user file, the user must update those street codes to synchronize with street code changes reflected in each new Geosupport release (see IV-B).
d. Geosupport enables users to group information by proximity. For example, Geosupport can be used to geocode a list of potential customers to manageable geographic locations such as zip codes, enabling companies to efficiently allocate field sales staff. This reduces travel time, making service delivery more efficient.
e. Geosupport allows users to determine in which New York City administrative or political district a given location is contained. This is useful when a user must determine which contractor, inspector, service center, etc., is responsible for servicing or processing a given location.
f. Geosupport aids in performance analysis reviews performed by internal management. Statistics of activities and performance rates by district can be produced from individual cases. This can be done by using Geosupport to code each location to a community district or other area. This statistical information can be used, for example, to monitor and evaluate the performance work crews, to reallocate resources, or to plan for new field offices.
g. Geosupport enables graphic visualization of geographically-related user data by facilitating computer mapping. While Geosupport does not itself produce maps, its geocoding functionality and, in particular, its provision of spatial (xy) coordinates can be used in conjunction with separate computer mapping software and City Planning's LION street center line file or Tax Block or Lot files to enable data to be displayed cartographically.

II System requirements, Availability And Enhancements

The Geosupport System is easy to use, and is easily incorporated into a user's own computer application. The way that this is accomplished is outlined in Chapter III and discussed in detail in the technical documentation. Users usually develop their own computer application using their own resources. User-written programs communicate directly with Geosupport via its Application Programming Interface (API), which is a simple, standardized and well-documented programming procedure. Geosupport performs the geographic processing only; all other processing is done by the user application, which has its own input and output files, screen formats and/or printed reports. A major advantage of this approach is that users have total control of their own applications, and develop them in their conventional data processing environment, using their normal programming language. This contrasts with many geographic processing packages which require users to develop their applications within the specialized environment of that package, often using a specialized, proprietary programming language.

As an alternative to developing an application that accesses Geosupport via its API, users can run one of the Geosupport utility programs, GOAT or GBAT, which require no user programming. The API and the utility programs are further discussed in Chapter III.

Geosupport Desktop Edition™ is available to the general public through a licensing agreement. Geosupport can be installed on any Windows® based personal computer [1].Geosupport Desktop Edition™ users can write their applications, both online and batch, in any programming language that permits a standard Dynamic Link Library (DLL) call. Currently, Microsoft® Visual C+, Borland® C and Visual Basic for Applications (VBA) have been successfully tested.

III Accessing Geosupport: The Application Programming Interface And Utility Programs

The Geosupport System is available in both batch and online environments. Within each of these environments, Geosupport may be accessed either through user-written programs or via Geosupport utility programs. The two methods of access are described below.

1.User-written programs communicate with Geosupport via its Application Programming Interface (API). Using the API, the user program supplies geographic locations to Geosupport for processing. Geosupport determines if a user location is valid, and if so, returns geographic information about the location to the user program. (For a partial list of data items provided, see Appendix I When the user data are unrecognizable or invalid, Geosupport returns codes and messages to the user program that specify the nature of the problem. By virtue of the API mechanism, the user's programming efforts can be concentrated on the specific needs of the application, such as screen design and database updating, and the geographic processing can be left to Geosupport.

The Geosupport API is easy for programmers to use. Geosupport technical documents describe how to program user applications to interact with Geosupport via the API.

2.Geosupport contains two general purpose utility programs that perform many common geographic processing functions. While not specifically tailored to the needs of any one user, these utility programs allow many users to use Geosupport while minimizing or eliminating their own

programming efforts. The utility programs are called GOAT and GBAT and are described below. The API, GOAT and GBAT provide basically the same set of information. A partial list of the information that they provide is in Appendix I.

a. GOAT:
Geosupport's online utility program is called the Geosupport Online Address Translator (GOAT). GOAT enables users to enter a geographic location on a computer screen, and if the location is valid, to immediately receive a display of a set of geographic information about that location. If the user's location is rejected as invalid, an error message is displayed to indicate the specific reason for the rejection.

b. GBAT:
GBAT (Geosupport Batch Address Translator) is the Geosupport batch utility program. GBAT allows users to process large files containing geographic locations. It validates these locations and writes out an output file containing a set of geographic information for each valid input location.

The Geosupport utility programs cannot, by themselves, satisfy every need of every application. For example, GOAT does not allow users to design their own screens or update their own files. Those types of functions can only be done by user-written programs accessing Geosupport via the API. Nevertheless, the Geosupport utility programs are powerful tools, particularly when used in conjunction with user-written programs.

IV Geosupport Update Cycles And User Feedback

1.** Updates Cycles **

The Geosupport System is updated continually. Updated information becomes accessible to users when new releases of Geosupport are released for user access several times a year. New Geosupport releases reflect changes in the city's geography (new street names, new inters, new addresses, changes to various district boundaries, tax lot mergers and subdivisions, etc.), as well as correction of Geosupport data errors. Software enhancements and corrections are also implemented from time to time. Geosupport technical bulletins explaining new software features are distributed as needed.

2.** Resynchronizing User Files to Reflect New Geosupport Releases **

Applications are often designed so that items obtained from Geosupport are stored in user files. Some online applications use such items as 'keys' to retrieve data from the user's own files by geographic location. (For example, as mentioned in Chapter I, five-digit street codes are often stored and used as retrieval keys in order to make geographic retrieval independent of street name spellings.) In designing applications that store Geosupport-provided data items in user files, the user must consider the issue of updating or "resynchronizing" those stored items to reflect data changes reflected in new Geosupport releases, particularly when the application is using those items as retrieval keys. In cases where such resynchronization is necessary, it is the user's responsibility to set up a resynchronization procedure and to run it in conjunction with the deployment of each new Geosupport release.

3.** User Feedback **

The users of Geosupport are a crucial resource for providing feedback to GSS on changes required to the Geosupport geographic data and software. Although we cannot respond to individual user feedback, all reported problems are logged and appropriate action is taken. If in the course of reviewing user feedback it is determined that clarification is needed, users may be contacted directly. Feedback procedures are described below.

** Geographic Feedback **

Geosupport may reject a user-supplied geographic location as invalid. For example, Geosupport appropriately rejects the inter of Second Avenue and Third Avenue in Manhattan as a non-existent inter. Moreover, Geosupport geographic files may contain an error or may not be up to date, causing Geosupport to reject a valid location.

For rejected items that the user considers valid, a reject feedback procedure exists. The user can submit such data for review to GSS's Data Management Unit by filling out and submitting a Geosupport System User Feedback Form (see Appendix VI). Printouts, sketch maps or other material documenting the rejects should be attached to the form when available.

Based on its research of user feedback, the GSS staff updates or corrects Geosupport files as appropriate. The corrections are reflected in the Geosupport System in a future Geosupport release. Before submitting rejected data to GSS, users should screen their data for misspellings, data entry errors or other obvious mistakes.

The GSS Data Management Unit utilizes a variety of resources, including maps, aerial photographs, public utility address listings, site plans and administrative records to conduct its geographic research. GSS uses Geographic Information System (GIS) technology, which allows the GSS Data Management staff to display, update and generate key Geosupport geographic data using interactive computer mapping. (Note, however, that as accessed by users, Geosupport is a conventional computer application that does not provide the user with maps or other graphic output. Users who have their own computer mapping or GIS software can prepare their data for input to that software by using Geosupport's geocoding capabilities.)

In addition to receiving user feedback, GSS receives information about changes in city geography from a variety of sources. The Department of City Planning has City Charter-mandated responsibility for mapping new streets and street closures. New names for existing streets are obtained from the City Council; new addresses from the Borough Presidents' offices; tax block and tax lot changes from the Department of Finance; changes in election district boundaries from the Board of Elections; changes in Police Precinct boundaries from the Police Department, etc.

APPENDIX 22: GeoX Programming Guide

This document assumes that the developer is using the 64-bit verion of GeoX which is based on EntireX 8.2.2.

GeoX Overview

GeoX classes allow developers to write applications that can make Geosupport calls via an EntireX Broker running on the DoITT mainframe or to a locally running Geosupport Desktop Edition (GDE).
Most Geosupport calls consist of what we call “two work area calls”. A work area is a data structure. These two work areas are Work Area 1 which is used for all calls and a Work Area 2 (which varies depending on the Geosupport function call and options you are using).
Work Area 1 (Wa1) consists of input fields for the various function parameters and output fields which return standardized versions of the input parameters as well as return codes and return messages.
Work Area 2 corresponds to the type of Geosupport function you are calling and the options you are using. For example, if to make a Function 1E (geographic information for an input address) with the "extended mode switch" set to "X", then along with Wa1 you would pass in Wa2f1ex.

Setup

Install the 64-bit Geosupport Desktop Edition on your PC.
Navigate to **C:\Program Files\Geosupport Desktop Edition\GeoX\Dotnet\misc**
Run entirexminiruntime_64.exe (This will install the needed EntireX components)

The supporting files that are needed are:

Supporting Files	
DCP Components	GeoX.dll *(This is the primary component.)*
	GeoXClientStub.dll
	GeoConns.xml *(This is a list of Brokers that GeoX will call)*
EntireX Components	SoftwareAG.EntireX.NETWrapper.Runtime.dll
	broker.dll
	erx.dll
EntireX Configuration Files	SoftwareAG.EntireX.NETWrapper.Runtime.xml *(This tells the Runtime.dll the location for erx.dll.)*

Using GeoX in a .NET Program

Create your application project.

Add a reference to GeoX.dll to your project. This should bring in the following:

- GeoX.dll
- GeoXClientStub.dll
- SoftwareAG.EntireX.NETWrapper.Runtime.dll
- SoftwareAG.EntireX.NETWrapper.Runtime.xml

To use the GeoX.Net classes without using fully qualified names include the following:

```
Imports DCP.Geosupport.DotNet.GeoX          'for Visual Basic .Net
using DCP.Geosupport.DotNet.GeoX            //for C#
```

You are now ready to use the GeoX .Net classes in your application.

Important Note on Installing EntireX

When you are ready to distribute your application, you must make sure that GeoX.dll and its supporting components are copied along with your application. Additionally, the underlying components for EntireX (broker.dll and erx.dll) must be in the application PATH. You have two options for the underlying EntireX components:

1. This is the preferred method. Run entirexminiruntime_64.exe on each computer that you are going to deploy the application to. If this is going to be run from a server, then the server is the only computer you need to run this on; you do not need to run this on clients' computers that access the server. If you are to run as a stand-alone application on individual computers, then you must run this on each computer your application is installed on.

2. This method is primarily used when the application is accessed from a file server and there are too many users to easily run entirexminiruntime_64.exe on each computer. Manually copy the EntireX Components (broker.dll and erx.dll) to your application directory. Then modify SoftwareAG.EntireX.NETWrapper.Runtime.xml to indicate the location of these components. To do this:

a. Edit SoftwareAG.EntireX.NETWrapper.Runtime.xml
b. Search for "Runtime.ERX.Location"
c. Replace the existing location, likely "C:\Program Files\Common Files…"
With ".\" [Do Not Include the Quotes]

Sample Code for Function 1E

```
*****************************************************************************************
*
VB.Net Code Snippet for Extended Work Area 2 Function 1E Call
*****************************************************************************************
*
Imports DCP.Geosupport.DotNet.GeoX
```

```
Module Module1

'--create a list of connections to use
Dim myGeoConns as New GeoConnsCollection("GeoConns.xml")
'-----------------------------------------------------------------------------
'ASP.Net applications will instead need to add a line similar to this:
'     Dim myGeoConns as GeoConnCollection
'     myGeoConns = New GeoConnCollection(Server.MapPath("GeoConns.xml"))
'-----------------------------------------------------------------------------

'--create your geo object (makes calls to Geosupport
'--create your Wa1 object (input to Geosupport)
'--create your Wa2 object (output from Geosupport)
Dim myGeo As New geo(myGeoConns)
Dim myWa1 As New Wa1
Dim myWa2f1ex As New Wa2F1ex

Sub Main()

   '--initialize your input
   myWa1.Clear

   '--choose the Geosupport function to call (1 returns geographic info for an address)
   myWa1.in_func_code = "1E"

   '--tell Geosupport to use platform independent work areas
   myWa1.in_platform_ind = "C"

   '--set optional processing flags (if any)
   myWa1.in_mode_switch = "X"

   '--set the input data
   myWa1.in_B10sc1.boro = "1"
   myWa1.in_hnd = "22"
   myWa1.in_stname = "Reade Street"

   '--make a call to Geosupport passing in the correct Work Area 2 object
   myGeo.GeoCall(myWa1, myWa2f1ex)

   '--check the return codes from your Geosupport call
   If myWa1.out_grc = "00"
      Console.WriteLine("Successful Geosupport Call")
      Console.WriteLine(myWa2f1ex.Print)
   Else If myWa1.out_grc = "01"
```

```
      Console.WriteLine("Successful Geosupport Call with Warning")
      Console.WriteLine(myWa2f1ex.Print)
   Else If mywa1.out_grc = "XX"
      Console.WriteLine("Unable to find Broker or GDE")
      Console.WriteLine(myWa1.Print)
   Else
      Console.WriteLine("Unsuccessful Geosupport Call")
      Console.WriteLine(myWa1.Print)
   End If

End Sub

End Module
```

Sample Code for Function BL

```
*****************************************************************************************
*
    VB.Net Code Snippet for Extended Work Area 2 Function BL Call

*****************************************************************************************
*
    Imports DCP.Geosupport.DotNet.GeoX

    Module Module1

    '--create a list of connections to use
    Dim myGeoConns as New GeoConnsCollection("GeoConns.xml")
    '-----------------------------------------------------------------------
    'ASP.Net applications will instead need to add a line similar to this:
    '     Dim myGeoConns as GeoConnCollection
    '     myGeoConns = New GeoConnCollection(Server.MapPath("GeoConns.xml"))
    '-----------------------------------------------------------------------

    '--create your geo object (makes calls to Geosupport
    '--create your Wa1 object (input to Geosupport)
    '--create your Wa2 object (output from Geosupport)
    Dim myGeo As New geo(myGeoConns)
    Dim myWa1 As New Wa1
    Dim myWa2f1ax As New Wa2F1ax

    Sub Main()
```

```
    '--initialize your input
    myWa1.Clear

    '--choose the Geosupport function to call (BL returns tax lot info for an BBL)
    myWa1.in_func_code = "BL"

    '--tell Geosupport to use platform independent work areas
    myWa1.in_platform_ind = "C"

    '--set optional processing flags (if any)
    myWa1.in_mode_switch = "X"

    '--set the input data
    myWa1.in_bbl.boro = "1"
    myWa1.in_bbl.block = "00154"
    myWa1.in_bbl.lot = "0023"

    '--make a call to Geosupport passing in the correct Work Area 2 object
    myGeo.GeoCall(myWa1, myWa2f1ax)

    '--check the return codes from your Geosupport call
    If myWa1.out_grc = "00"
       Console.WriteLine("Successful Geosupport Call")
       Console.WriteLine(myWa2f1ax.Print)
    Else If myWa1.out_grc = "01"
       Console.WriteLine("Successful Geosupport Call with Warning")
       Console.WriteLine(myWa2f1ax.Print)
    Else If mywa1.out_grc = "XX"
       Console.WriteLine("Unable to find Broker or GDE")
       Console.WriteLine(myWa1.Print)
    Else
       Console.WriteLine("Unsuccessful Geosupport Call")
       Console.WriteLine(myWa1.Print)
    End If

End Sub

End Module
```

Selecting the Broker to Use

These classes allow developers to make calls to Geosupport running on the DoITT mainframe or a locally running Geosupport Desktop Edition. This is done by creating a GeoConnsCollection object that points to a list of Brokers. One of the benefits of using this collection is that if there is a

problem with one of the Brokers, the classes will go to the next Broker in the list.

The best way create the GeoConnsCollection object is to point it to a GeoConns.xml file that is external to the application. Below is a sample GeoConns.xml:

```
<?xml version="1.0"?>
<ArrayOfGeoConn xmlns:xsd="http://www.w3.org/2001/XMLSchema"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance">
  <GeoConn>
    <Broker>mvsp.nycnet:4036</Broker>
    <Server>P030A/GEOXSERVER/GEOSUPPORTSERVICE</Server>
  </GeoConn>
  <GeoConn>
    <Broker>mvsp.nycnet:4074</Broker>
    <Server>P030A/GEOXSERVER/GEOSUPPORTSERVICE</Server>
  </GeoConn>
  <GeoConn>
    <Broker>mvsp.nycnet:4055</Broker>
    <Server>T030A/GEOXSERVER/GEOSUPPORTSERVICE</Server>
  </GeoConn>
  <GeoConn>
    <Broker>GDE</Broker>
    <Server></Server>
  </GeoConn>
</ArrayOfGeoConn>
```

The first two GeoConn entries

```
  <GeoConn>
    <Broker>mvsp.nycnet:4036</Broker>
    <Server>P030A/GEOXSERVER/GEOSUPPORTSERVICE</Server>
  </GeoConn>
```

and

```
  <GeoConn>
    <Broker>mvsp.nycnet:4074</Broker>
    <Server>P030A/GEOXSERVER/GEOSUPPORTSERVICE</Server>
  </GeoConn>
```

point to the two production brokers (production Geosupport) on the DoITT mainframe.

The third entry

```
<GeoConn>
  <Broker>mvsp.nycnet:4055</Broker>
  <Server>T030A/GEOXSERVER/GEOSUPPORTSERVICE</Server>
</GeoConn>
```

points to the test broker (which points to the test version of Geosupport).

The final entry

```
<GeoConn>
  <Broker>GDE</Broker>
  <Server></Server>
</GeoConn>
```

means that a locally running Geosupport Desktop Edition (GDE) will be called instead of a broker. GDE must be installed or you will get an execption.

Which Functions to Use

Overview of What the Functions Do

Function	Input	Data Returned
1	address	Geographic and City Service Information
1E	address	Geographic, City Service Information, and Political Districts
1A	address	Tax Property Level Information, Alternate Addresses for Property
1B	address	Combines 1E (Extended) with 1A (Extended) information
AP	address	Address Point ID and Address Point XY coordinates
1N	street name	Normalized Street Name and Street Code
2	intersection, node id	Geographic Information
3, 3C	street segment	Geographic Information
3S	street segment	List of Intersecting Streets and their Node IDs
BL	BBL	Same as 1A
BIN	BIN	Same as 1A
D, DG, DN	street code	Normalized Street Name for input street code

Which Options to Use

Formatting Properties	
in_hn_justification	When set to “L” House Numbers in Display Format are left-justified
	When set to “R” House Numbers in Display Format are right-justified
	The input street names will be normalized to the indicated length

in_snl	Valid values are minimum of 4 and a maximum of 32
	Some streets may not be able to be normalized to the requested length
in_stname_normalization	When set to blank street names are normalized in sort format
	When set to “C” street names are normalized in compact format
	When set to “S” street names are normalized in sort format
Additional Information Properties (these usually require a different Work Area 2)	
in_auxseg_switch	When set to “Y” the list of Segment IDs for a street segment are
	Appended to the Work Area 2; for Functions 3 and 3C only
in_long_wa2_flag	When set to “Y” the long workarea for the function is returned
	For Functions 1A and BL a list of BINs for the tax lot are returned instead of a list of alternative addresses; Wa2F1al must be used for these calls.
	For Functions 1 and 1E additional information is returned; Wa2F1w and Wa2F1v must be used for these calls.
in_mode_switch	When set to “X” the extended work area 2 is used for the call
	For Functions 1, 1E, 1A, BL, BN, 3, and 3C only; where possible, we recommend that you use this option
in_tpad_switch	When set to “Y” TPAD data is added to the work area 2; for Functions 1A, BL, and BN only
in_xstreet_names_flag	When set to “E” for Functions 1, 1E, 3, and 3C the first 5 elements in Wa1.out_stname_list contain the Street Names for the intersecting streets at the low address end of the segment and the last 5 elements in Wa1.out_stname_list contain the Street Names for the intersecting streets at the high address end of the segment
	For Functions 1 and 1E only an additional Geosupport call to Function 1A is made. If successful the BBL and BIN obtained are returned in Wa1.out_bbl and Wa1.out_bin respectively.
	For Function 2 the first 5 elements in Wa1.out_stname_list contain the Street Names for the intersecting streets at the intersection.
	When set to space for Functions 1, 1E, 2, 3, and 3c if the Street Names of the list of intersecting streets are needed, then the user must take the street codes from Wa2 and make repeated Function D or DG calls.
Other	
in_browse_flag	Sets how Geosupport should normalize your input street names when “blank” the output street name is the normalized version of the input street name
	When “P” the output street name is the Primary Street Name for the input street
	When “F” the output street name is the Principal Street Name for the input street

	When “R” the output street name is the DCP Preferred Street Name for the input street
in_real_streets_only	When set to “R” Function 3S will return only intersections consisting of “real streets” and not changes in district boundaries or other items
in_roadbed_request_switch	When set to “R” Function 1 and 1E will return geographic data for the RoadBed street segments instead of for the Generic street segments which is the default

Selecting the Proper Work Area 2

Function	Work Area 1 Options				Work Area 2 to use
	in_auxseg_switch	in_long_wa2_flag	in_mode_switch*	in_tpad_switch	
1E	n/a	n/a	blank	n/a	WA2F1E
	n/a	n/a	X	n/a	WA2F1EX
2	n/a	n/a	n/a	n/a	WA2F2
2W	n/a	n/a	n/a	n/a	WA2F2W
3	blank	n/a	blank	n/a	WA2F3
	blank	n/a	X	n/a	WA2F3X
	Y	n/a	X	n/a	WA2F3XAS
3C	blank	n/a	blank	n/a	WA2F3C
	Y	n/a	blank	n/a	WA2F3CAS
	blank	n/a	X	n/a	WA2F3CX
	Y	n/a	X	n/a	WA2F3CXAS
3S	n/a	n/a	n/a	n/a	WA2F3S
1B	n/a	n/a	n/a	blank	WA2F1B
	n/a	n/a	n/a	Y	WA2F1B
1A	n/a	blank	blank	blank	WA2F1A
	n/a	L	blank	blank	WA2F1AL
	n/a	blank	X	blank	WA2F1AX
	n/a	L	X	blank	n/a

	n/a	blank	X	Y	WA2F1AX
	n/a	L	X	Y	n/a
	n/a	blank	blank	Y	WA2F1A
	n/a	L	blank	Y	WA2F1AL_TPAD
BL	n/a	blank	blank	blank	WA2F1A
	n/a	L	blank	blank	WA2F1AL
	n/a	blank	X	blank	WA2F1AX
	n/a	L	X	blank	n/a
	n/a	blank	X	Y	WA2F1AX
	n/a	L	X	Y	n/a
	n/a	blank	blank	Y	WA2F1A
	n/a	L	blank	Y	WA2F1AL_TPAD
BN	n/a	n/a	blank	blank	WA2F1A
	n/a	n/a	X	blank	WA2F1AX
	n/a	n/a	blank	Y	WA2F1A
	n/a	n/a	X	Y	WA2F1AX
AP	n/a	n/a	blank	n/a	WA2FAP
	n/a	n/a	X	n/a	WA2FAPX

We highly recommend that you use the in_mode_switch = "X" option

List of Classes and Overview

The Work Area and their Supporting classes all have the following methods:

- default constructor
- constructor that takes a string as a parameter
- Clear method that reinitializes the data in the class
- ToString method that converts the data structure to a string
- FromString method that converts a string into the data structure
- Display method that creates a string consisting of the data items separated by a dash

- Display(Char) method that creates a string consisting of the data items separate by “Char”
- Print method that creates a string with the data field names and the data values of the class
- Get/Set Properties for the data fields (with the exception of Work Area 1 input fields, these are usually limited to Get only) for the most part the names are self-explanatory

Classes

Main GeoX Classes	**Description**
Geo	Main GeoX object
GeoConn	Contains information needed to connect to an EntireX Broker or a locally running Geosupport Desktop Edition (GDE)
GeoConnCollection	Contains a list of GeoConn objects
GeoConnsException	Information relating to an exception involving a GeoConn object
Work Area Classes	**Description**
Wa1	Input Data, Normalized Input Data, Return Codes
Wa2F1	Geographic Information about a Street Segment
Wa2F1w	Wa2F1 with additional data
Wa2F1e	Wa2F1 with election district information
Wa2F1v	Wa2f1e with additional information (same as Wa2f1w with election district information)
Wa2F1ex	Wa2F1e with additional information and street names for all street codes
Wa2F1a	Tax Lot Information about an input Address, BBL, or BIN along with a list of alternate addresses associated with the tax lot
Wa2F1al	Same as Wa2F1a except with a list of BINs associated with the Tax Lot instead of a list of alternate addresses.
Wa2F1al_TPAD	Same as Wa2F1al with the addition of the TPAD status for each of the BINs in the BIN List
Wa2F1ax	Wa2F1a with additional information and street names for the alternate addresses for the Tax Lot
Wa2F1b	Combination of Wa2F1ex and Wa2F1ax for input address
Wa2F2	Geographic Information about an Intersection
Wa2F2w	Same as Wa2F3x with a list of additional Segment IDs for those street segments that have multiple Segment IDs associated with them
Wa2F3	Geographic information about an input street segment (consisting of an on-street and two succeeding cross streets for the on-street

Wa2F3as	Same as Wa2F3 with a list of additional Segment IDs for those street segments that have multiple Segment IDs associated with them
Wa2F3x	Same as Wa2F3 with additional information and street names for all street codes
Wa2F3xas	Same as Wa2F3x with a list of additional Segment IDs for those street segments that have multiple Segment IDs associated with them
Wa2F3c	Same information as Wa2F3 but for one side of the segment only
Wa2F3cas	Same as Wa2F3c with a list of additional Segment IDs for those street segments that have multiple Segment IDs associated with them
Wa2F3cx	Same as Wa2F3c with additional information and street names for all street codes
Wa2F3cxas	Same as Wa2F3x with a list of additional Segment IDs for those street segments that have multiple Segment IDs associated with them
Wa2F3s	List of Intersection for an input Street Stretch
Wa2F5	Returns a properly formatted Geosupport address key for an input address
Wa2Fhr	Returns the version of Geosupport and the Release Number for the data files
Wa2Fap	Address Point ID and XY Coordinates for input Address
Wa2Fapx	Same as Wa2Fap with addition of street name in address list
Wa1Aimz	Returns a list of Map IDs associated with the Input

Supporting Classes for Work Areas

- AddrRange
- AddrRangeX
- AddrRange_ap
- AddrRange_apx
- B10sc
- B5sc
- B7sc
- BBL
- BIN
- BusArea
- ComDist
- CrossStreetInfo
- DofMap
- FileInfo
- LionKey
- Sanborn
- SegSide

- TPADLongWa2Info
- VsamKey1

Glossary of Term And Acronyms

Citations in brackets are references to sections of the UPG where the given term is defined or is principally discussed. Phrases in **bold typeface** have entries in this glossary.

A

ADDRESSABLE PLACE NAME [Chapter III.6]: A **place name** that can be combined with a house number to form an address. (Contrast with **non-addressable place names**.) Geosupport's **address-processing functions** accept addressable place names as input data for the specification of an address. Some Manhattan examples are PENN PLAZA, WASHINGTON SQUARE VILLAGE and NEW YORK PLAZA.

ADDRESS / INTERSECTION TO MAP ZONES (AIMZ) [Chapter I.1]: A Geosupport CICS utility transaction that allows the user to enter an address, **place name**, intersection, tax lot identifier, or **Building Identification Number** and receive back a screen display of a set of map identifiers corresponding to the input location. The use of AIMZ requires no programming skills and AIMZ is not documented in detail in this **UPG**.

ADDRESS-PROCESSING FUNCTION [Chapter V]: Any of the Geosupport **functions** that accept the input of addresses. Currently, these are Functions 1, 1A, 1B, 1E and AP. Except for Function AP, address-processing functions also accept **non-addressable place names** as input data (typically with no input house numbers specified). The address-processing functions are a subset of the **location-processing functions**.

ALIAS [Chapter IV.2]: Two street names (or names of non-street geographic features) are aliases of each other if they are alternative names for the same street (or non-street feature) or any portion(s) thereof, or are spelling variants of the same street (or non-street feature) name. **Partial street names** are considered spelling variants, and therefore aliases, of the corresponding full street names. The alias relationship is embodied in the assignment of Geosupport **street codes**: two street names are aliases of each other if and only if they have the same borough-and-five-digit **street code**. Some examples of aliases in Manhattan: 6 AVENUE, SIXTH AVENUE, and AVENUE OF THE AMERICAS are all aliases of each other. SEVENTH AVENUE, 7 AVENUE, FASHION AVENUE and ADAM C POWELL JR BOULEVARD are all aliases of each other, even though some of these names are valid for differing portions of the street.

ALIASES (in GBAT) [Chapter XI.6]: User-defined street name aliases may be used in GBAT applications to supplement the set of street names that Geosupport recognizes. GBAT aliases are typically used to handle a consistent misspelling of a street name. The GBAT aliases are different from the **Alia**ses described in Chapter IV.2.

AIMZ - see **Address / Intersection to Map Zones**

AP - AP is the name of Function AP and the acronym of Address Point (AP). It is also the acronym for Addressable Place Name (AP) and Atomic Polygon (AP). The acronym's meaning should be clear by its usage. It is spelled out as needed.

API - see **Geosupport Application Programming Interface**

B

BACKGROUND COMPONENT [Chapter I.5]: The component of the Geosupport System in which GSS updates and validates geographic base files from which new releases of the **foreground component** files are periodically generated. The background component software and files are not directly accessed by users.

BBL ('Borough/Block/Lot') [Chapter VI.2]: A unique identifier for a parcel of real property, or tax lot, in New York City. The BBL is a 10-byte item formed by concatenating the one-byte borough code, five-byte tax block number and four-bye tax lot number. The New York City Department of Finance assigns tax block and tax lot numbers.

BEND [Chapter III.6]: A **pseudo-street name** that Geosupport accepts as street name input to specify a bending point of a street. Geosupport treats a point along a street as a bending point if the angle of the street at that point is not within the range 160-200 degrees, that is, if it is not within 20 degrees of a straight line.

BILLING BBL [Chapter VI.4]: A special **BBL** assigned by the Department of Finance to each condominium, to enable identification of the condominium in its entirety as distinct from the condominium's individual units.

BIN - see **Building Identification Number**

BLOCK FACE (a.k.a. BLOCKFACE) [Chapter VII.3] A continuous frontage of a physical city block along one street, encompassing any bending points of the street within that frontage.

BUILDING IDENTIFICATION NUMBER (BIN) [Chapter VI.3]: A unique, immutable identifier for each building in New York City. BINs are not to be confused with addresses. BINs are assigned by the Geographic Systems Section (GSS) at the Department of City Planning.

C

CHARACTER-ONLY WORK AREA (COW) [Appendix 12, Appendix 13 and Appendix 14]: The Geosupport work areas that have long been in use are called the Mainframe-Specific Work Areas (MSWs). Most of the MSWs contain one or more packed decimal fields, a data encoding schema unique to IBM mainframes. An alternative set of Geosupport work areas was introduced in 2002. It is called the Character-Only Work Areas (COWs) which, as the name implies, contain character fields only. The COW is an essential part of a long-term effort to port the Geosupport

System to other platforms. From now on, all new applications should be designed to use the COWs only. We also recommend that all existing applications be converted to use the COWs. See also Glossary entry for **Work Areas**.

CCO - See **Corporation Council Opinion**

CITY LIMIT [Chapter III.6]: A **pseudo-street name** that Geosupport accepts as street name input to refer to locations on the Bronx-Westchester County border, the Queens-Nassau County border, the New York-New Jersey border, and the Staten Island-New Jersey border.

CITYWIDE STREET CENTERLINE GEODATABASE - see **CSCL**

COMPACT FORMAT [Chapter III.3]: A Geosupport format for **normalize**d geographic feature names. The compact format is suitable for display but not for sorting. Contrast with the **sort format**, which is suitable for sorting but not for display.

COMPLEX [Chapter III.6]: A group of related buildings and/or other geographic features. The name of a complex is a **NAP** (Non-Addressable Place Name). Examples of complexes include housing projects, university and hospital campuses, cultural complexes (such as Lincoln Center) and airports. Compare to **simplex** and **constituent entity of a complex**.

CONSTITUENT ENTITY OF A COMPLEX [Chapter III.6]: An individual building or other geographically identifiable feature that is part of a **complex**. Examples are the buildings in Lincoln Center and in Stuyvesant Town.

COPY LIBRARY, COPY FILES [Chapter VIII.4]: Many programming languages have a facility for accessing external files of source code called COPY files during application program compilation. COPY files reside in a partitioned data set (PDS) called a COPY library. The Geosupport System has COPY libraries containing source code layouts of the **work areas** in Assembler, PL/1, COBOL, C and NATURAL. The use of the Geosupport COPY libraries by application developers is optional but is strongly recommended.

CORPORATION COUNCIL OPINION (CCO) [Appendix A3]: A Corporation Council Opinion (CCO) is a geographic feature type. A CCO is an opinion by the City's Law Department that a street area, not owned by the City, (e.g. a portion of a private street) has been dedicated for public use, consistent with the requirements of General City Law, Section 36(2). That allows the City to use public funds for various improvements and services, including paving of the roadway and installing sewers. The request usually relates to planned work by the City's Department of Transportation, Department of Design and Construction, and Department of Environmental Protection.

COW - See **Character-Only Work Area**

CSC - See **Computer Service Center**

CSCL ('NYC Citywide Street Centerline File'): An object-oriented database describing the features (streets, and non-street features) in NYC.

D

DAPS - see **Duplicate Address Pseudo-Street Name**

DEAD END [Chapter III.6]: A pseudo-street name that Geosupport accepts as street name input to refer to a termination point of a street at which there are no cross streets.

DEPARTMENT OF INFORMATION TECHNOLOGY AND TELECOMMUNICATIONS (DoITT): An agency of the City of New York responsible for city government-wide information technology infrastructure support. DoITT operates the **Computer Service Center.**

DISPLAY FUNCTION [Chapters IV.6 and V.2]: Any of the Geosupport **functions** that provide data items that can be used to display geographic locations on application screens, reports, mailing labels etc. Specifically, the display **functions** provide street names corresponding to input **street codes**, and provide house numbers in HND format corresponding to input house numbers in **HNI** (MSW) or **HNS** (COW) format. Note that the display **function**s do not actually display anything themselves; they merely provide data items that are suitable for an application to display. Currently, the display functions are Functions D, DG and DN.

DoITT - see **Department of Information Technology and Telecommunications**

DRIVER, GEOSUPPORT [Chapter II.1]: A Geosupport load module that serves as an interface enabling application programs to access Geosupport via **API** calls. There are two different drivers, one for batch applications and one for CICS applications. Application developers must link-edit the appropriate driver into the application program.

DSNY - The City of New York Department of Sanitation

DUPLICATE ADDRESS PSEUDO-STREET NAME (DAPS) [Chapter V.6]: A **pseudo-street name** accepted as street name input by Geosupport in duplicate address situations. DAPSs enable applications to specify which instance of a duplicated address the application wishes to process. As an example, Hillside Avenue exists in both the Bellerose section and the Douglaston section of Queens. To allow the user to refer to Hillside Avenue in a duplicate address situation two pseudo-street names are accepted by Geosupport, namely HILLSIDE AVENUE BELLEROSE and HILLSIDE AVENUE DOUGLASTON. As an alternative to a DAPS, for Functions 1, 1A, 1B, and 1E, the user may enter the conventional street name and the ZIP code which identifies the section of the borough, e.g. .ZIP Code 11426 for Bellerose and 11363 for Douglaston.

F

FOREGROUND COMPONENT [Chapter I.5]: The component of the Geosupport System that is directly accessed by a user application via the **API**. The foreground component includes both software and files.

FREE-FORM ADDRESS [Chapter V.3]: An address expressed with the house number and street name stored together in a single field. (Compare with **parsed-form address**.) Geosupport can process free-form addresses in which the house number and street name are passed together in the **WA1** input street name field (and no value is passed in the separate **WA1** input house number field).

FRONT-TRUNCATED STREET NAME [Chapter III.5(E)]: In the borough of Bronx or Manhattan only, a front-truncated street name is one that can be transformed to a valid street name by adding the word EAST or WEST to the front of the street name, for example 14 STREET is a front-truncated street name for EAST 14 STREET and WEST 14 STREET. Additional criteria are described in Section III.5(E).

FUNCTION [Chapters I.2, I.4]: The Geosupport System is organized into more than a dozen distinct functions that can be accessed by the user. Each function is identified by a one- or two-character function code.

G

GBAT - See **Geosupport Batch Address Translator**

GEOCODE [Chapter I.2]: The process of associating higher-level geographic information, such as the police precinct, ZIP code or census tract, with a specific geographic location, such as an address or street intersection. Geocoding is one of the Geosupport System's most important services.

GEOGRAPHIC ONLINE ADDRESS TRANSLATOR (GOAT) [Chapter I.1]: The Geosupport System's principal CICS utility transaction. GOAT is an inquiry transaction that allows the user to request any Geosupport **function**, enter input data and receive back a formatted screen display of the corresponding output information provided by that **function**. The use of GOAT requires no programming skills and it is not documented in detail in this **UPG**. (The GOAT utility was previously known as the Geosupport Online Address Translator (GOAT)).

GEOGRAPHIC RETRIEVAL CONSISTENCY [Chapter I.3]: Retrieval of information by geographic location in a manner that is independent of how the location is specified. The ability of an application to retrieve data consistently by geographic location from the application's own files is a critical design issue for many applications. One important means of implementing geographic retrieval consistency in an application is to use B5SCs (see the entry for **alias**) instead of street names in the retrieval key.

GEOSUPPORT APPLICATION PROGRAMMING INTERFACE (API) [Chapter II.1]: The Geosupport facility that enables user-written application programs to interact with Geosupport via standardized program calls. The API involves the use of a Geosupport **driver** module and Geosupport **work areas**.

GEOSUPPORT BATCH ADDRESS TRANSLATOR (GBAT) [Chapter XI.1]: The Geosupport System's batch utility program.

GEOSUPPORT ONLINE ADDRESS TRANSLATOR (GOAT)- see Geographic Online Address Translator(GOAT).

GEOSUPPORT RETURN CODE (GRC) [Chapter II.2]: A two-byte code that is returned in **WA1** upon completion of every **API** call to Geosupport, indicating to the calling application the outcome of the call. (Not to be confused with operating system return codes or condition codes.) A GRC value of '00' signifies an unconditionally successful call. A GRC value of '01' signifies a **warning**. A GRC value of other than '00' or '01' signifies a **reject**. See also the Glossary entries for **Reason Code** and **Message**. See Appendix 4 for a comprehensive list of **GRCs, Reason Codes** and **Messages**.

GEOSUPPORT SYSTEM ADMINISTRATOR [Chapter I.1]: A designated staff member (generally a systems programmer) of a computer center where Geosupport is installed on a mainframe, responsible for installing new Geosupport file releases and software versions, and for trouble-shooting system-related Geosupport problems. Note: the Geosupport System Administrator is not necessarily responsible for providing application-related support to users.

GOAT - see Geographic Online Address Translator

GRC - See **Geosupport Return Code**

GSS [Chapter I.1]: The Geographic Systems Section of the City of New York Department of City Planning's Information Technology Division. **GSS** is the developer and custodian of the Geosupport System.

H

HND - See **House Number in Display Format**

HNI - See **House Number in Internal Format**

HNS - See **House Number in Sort Format**

HOUSE NUMBER IN DISPLAY FORMAT (HND) [Chapter V.2]: One of Geosupport's three output normalized house number formats. The HND is a format suitable for applications to use for display on screens, reports and mailing labels.

HOUSE NUMBER IN INTERNAL FORMAT (HNI) [Chapter V.2]: One of Geosupport's three output normalized house number formats. The HNI is not suitable for display, because it is partly in packed decimal form, and it contains a code representing the house number suffix (if any) rather than the suffix itself. The HNI is used internally in the Geosupport System, and it is not of direct significance to most applications. HNI is valid in MSW only.

HOUSE NUMBER IN SORT FORMAT (HNS) [Chapter V.2]: One of Geosupport's three output normalized house number formats. The HNS is not suitable for display, because it has an internal format and contains a code representing the house number suffix (if any) rather than the

suffix itself. The HNS is used internally in the Geosupport System, and it is not of direct significance to most applications. HNS is valid in COW only.

HPD - Department of Housing Preservation and Development

I

ID-PROCESSING FUNCTION [Chapter I.4]: Any **location-processing function** that processes identification codes. Currently, the ID-processing functions are Function BL, which processes tax lots specified by an input **BBL**; Function BN, which processes buildings specified by an input **BIN**; and COW Function 2 which can process an intersection specified by a **Node ID**.

INPUT FIELD (IN A WORK AREA) [Chapter II.3]: A field into which the user application inserts a value to be passed to Geosupport. See also **output field, WA1** and **WA2**. WA1 has both input and output fields. **WA2** has output fields only.

L

LDF - see **LION Differences File**

LGC - See **Local Group Code**

LION DIFFERENCES FILE (LDF): The LION Differences File (LDF) is a sequential file containing records documenting certain types of changes that have occurred between a particular release of LION and the immediately previous LION release. A new LDF 'edition' is 'published' in conjunction with each new production release of LION. The changes documented in the LDF relate to node changes and segment changes.

LION FILE [Chapter VII.1]: A predecessor to CSCL, LION is a **background component** file that is a digital map of New York City. LION contains a single-line representation of the city's streets and city limits. Geosupport's **street configuration** processing is based on that representation.

LOCAL GROUP CODE (LGC) [Chapter IV.5]: The LGC consists of the sixth and seventh digits of the ten-digit street code. The LGC corresponds to a set of **locally valid street names** for the given street.

LOCALLY VALID STREET NAME [Chapter IV.5]: A name of a street that is valid for a particular portion (possibly all) of the street. The set of street names that are valid for the same portion of a street constitute a 'local group' and share the same **LGC** value.

LOCATION-PROCESSING FUNCTION: Any of the Geosupport **function**s that accept the input of a geographic location. These can be sub-classified into the **address-processing functions** (Functions 1, 1A and 1E); the **street-configuration-processing functions** (Functions 2, 3, 3C and 3S); and the **ID-processing functions** (Functions 2, BL and BN).

M

MAINFRAME-SPECIFIC WORK AREA (MSW (a.k.a. MFS)) - See **Character-Only Work Area**

MESSAGE [Chapter II.2]: A **WA1** output item returned for all **warnings** and **rejects**, consisting of an appropriate explanatory text message. See Appendix 4 for a comprehensive list of **GRC**s, **Reason Codes** and **Messages**.

MFS - See **MSW**

MSW - See **Mainframe-Specific Work Area**

N

NAP - See **Non-addressable Place Name**

NAUB - See **Non-addressable Un-named Building**

NODE [Chapter VII.2]: Either a conventional intersection of a street with another street, or a **pseudo-intersection** of a street with a **pseudo-street or where there is a change in a significant geocode such as zip code or a Police Beat..**

NODE ID [Chapter VII.2]: A unique identifier associated with each node in the Geosupport sytem. The Node ID is sometimes referred to as the Node Number.

NON-ADDRESSABLE PLACE NAME (NAP) [Chapter III.6]: A place name that is typically not combined with a house number to form an address. Examples: CITY HALL, EMPIRE STATE BUILDING, PLAZA HOTEL, LINCOLN CENTER, LA GUARDIA AIRPORT. A NAP can either be the name of a **simplex**, a **complex**, or a **constituent entity of a complex**. Geosupport's **address-processing functions** accept many NAPs as input data

NON-ADDRESSABLE UN-NAMED BUILDING (NAUB) [Chapter VI.3]: A building that has neither addresses nor **NAP**s, and can only be identified by its **BIN**. Typical example is a storage shed on the grounds of an industrial property.

NORMALIZE [Chapter III.2 for street names, Chapter V.2 for house numbers]: To produce a version of a data item in a standardized format. Geosupport normalizes every input geographic feature name into one of two formats selected by the user application, called the **compact format** and the **sort format**. Geosupport also normalizes every input house number. Geosupport returns output normalized names and house numbers to the calling application in **WA1**.

O

OUT-OF-SEQUENCE ADDRESS [Chapter V.10]: An address such that the house number is out of sequence relative to nearby house numbers along the given street. For an input out-of-sequence address, the output information that Functions 1 and 1E return is based on the street segment where the out-of-sequence address is actually located, including the cross streets and geographic district identifiers. The Spatial Coordinates returned are those of a point calculated under the assumption that the building entrance is located at the midpoint of the blockface. A warning is issued for any address on a blockface containing an out-of-sequence address.

OUTPUT FIELD (IN A WORK AREA) [Chapter II.3]: A field into which Geosupport inserts a value to be returned to the calling user application. See also **input field, WA1** and **WA2**. **WA1** has both input and output fields. **WA2** has output fields only.

P

PARSED-FORM ADDRESS [Chapter V.3]: An address that is expressed with the house number and street (name or code) stored in separate fields. (Compare to **free-form address**.)

PARTIAL STREET NAME [Chapter III.4]: A street name formed from a full normalized street name by deleting one or more entire words from the end of the full street name. For example, in Manhattan, READE is a partial street name for READE STREET. Geosupport accepts a partial street name as an input street name when the partial street name unambiguously represents a unique full street name in the specified input borough. Additional criteria are described in Chapter III.4.

PLACE NAME [Chapter III.6]: A name of a geographic feature other than a street name or a **pseudo-street name**. Examples of place names are the names of building complexes (such as university campuses, housing projects, hospital campuses etc.), individual named buildings (such as CITY HALL, EMPIRE STATE BUILDING, museums, hotels, theaters, stadiums etc.), parks, islands, airports etc. Geosupport recognizes some New York City place names, and more are being added over time. There are several types of place names; see Glossary entries for **Addressable Place Name, Non-Addressable Place Name, Simplex, Complex and Constituent Entity of a Complex**.

PREFERRED STREET NAME [Chapter IV.5]: If more than one local group of street names is valid at a particular location along a street, **GSS** designates one of them as the 'preferred' local group for that location. The preferred street name is the **principal street name** of the preferred local group.

PRIMARY STREET NAME [Chapter IV.3]: For every street in NYC, that is, for every valid B5SC value, **GSS** designates one spelling of one name of the street as the primary street name. Function D can be used to obtain the primary street name for a given B5SC value.

PRIMING WA1 [Chapter II.3]: The part of the API procedure in which the calling application program inserts values into **WA1 input fields** in preparation for issuing a call to the **driver**. Priming WA1 is how an application requests the **function** to be performed, passes the input geographic data (such as an address) to be processed, and specifies processing options.

PRINCIPAL STREET NAME OF LOCAL GROUP [Chapter IV.5]: The street name that **GSS** has designated as the 'best' representative from among all the names in a local group. Function DG can be used to obtain the principal street name for a given B7SC value. **PSEUDO-ADDRESS [Chapter VI.5]:** An address unofficially assigned by **GSS** to a street frontage of a tax lot that has no 'real' building addresses, such as a driveway. Function 1A accepts pseudo-addresses as input.

PSEUDO-INTERSECTION [Chapter VII.2]: A point along a street specified in terms of a **pseudo-street name,** i.e., a bend, a dead end or a city limit point.

PSEUDO-STREET NAME [Chapter III.6]: An 'unofficial' street name that Geosupport accepts as street name input for certain geographic situations. **DAPS**s are pseudo-street names that the **address-processing functions** accept as input only for the city's very few cases of duplicate addresses (see Chapter V.6). DEAD END, CITY LIMIT, BEND and their **aliases** are pseudo-street names accepted as input by the **functions** that process **street configurations** (see Chapter VII).

R

REASON CODE [Chapter II.2]: A one-byte output **WA1** item that qualifies the reason for a **warning** or **rejection** with greater specificity than does the **GRC** alone. Non-blank reason codes are returned for all **warnings** and for selected **rejects**. See Appendix 4 for a comprehensive list of **GRC**s, **Reason Codes** and **Messages**.

REJECT, REJECTION [Chapter II.2]: An unsuccessful outcome of an **API** call to Geosupport, indicated by a **GRC** value other than '00' or '01', accompanied by an appropriate **Message**, and for selected rejects, by a **Reason Code**.

RELEASE (OF GEOSUPPORT FOREGROUND FILES) [Chapter I.5]: Geosupport's **foreground component** files are read-only files, and are periodically replaced by updated files. Every foreground file is identified as belonging to a specific Geosupport release.

RESYNCHRONIZATION OF STREET CODES [Chapter IV.4]: The updating of Geosupport **street codes** stored in a user application file to reflect street code assignment changes made in a Geosupport **release**.

ROADBED [Chapter V.5]: A roadbed is a street segment that is bounded on both sides by a physical separator such as a sidewalk, median barrier or median strip. Street segments that have painted medians separating travel direction do not form multiple roadbeds. Well-known examples of streets with multiple roadbeds include Park Avenue in Manhattan, Queens Blvd in Queens and Ocean Parkway in Brooklyn.

S

SIMILAR NAME [Chapter III.5]: When an input street name is rejected, Geosupport returns a list of up to ten 'similar names' in **WA1**, as an aid to the application in handling the **reject**. A 'similar name' is a valid full street name from the specified input borough that Geosupport, in

accordance with certain criteria, deems to be similar to the rejected input street name.

SIMPLEX [Chapter III.6]: A 'stand-alone' named geographic feature, that is, a feature that has a **NAP** and that is not a **complex** or a **constituent entity of a complex.** Examples: Empire State Building, Plaza Hotel, Gramercy Park.

SNC - See **Street Name Code**

SNL - See **Street Name Normalization Length Limit**

SORT FORMAT [Chapter III.3]: A Geosupport format for **normalize**d geographic feature names. The sort format is suitable for sorting but not for display. Contrast with the **compact format**, which is suitable for display but not for sorting.

STREET CODE [Chapter IV]: In the Geosupport System, a set of numeric street codes is assigned to represent the city's street names and other geographic feature names. A borough code combined with a ten-digit street code, or B10SC, corresponds to a specific spelling of a specific street name in the given borough. Portions of the B10SC also have special significance. In particular, the first six bytes of the B10SC, the borough-and-five-digit street code (B5SC), encodes the **alias** relationship between street names.

STREET CONFIGURATION [Chapter VII.1]: A geographic location specified in terms of a combination of two or three streets. Street configurations include intersections, street segments, **blockfaces** and street stretches.

STREET-CONFIGURATION-PROCESSING FUNCTION [Chapter VII]: Any of the Geosupport **location-processing functions** that process **street configurations**. Currently, these are Function 2, which processes street intersections; Function 3, which processes street segments; Function 3C, which processes **blockfaces**; and Function 3S, which processes street stretches.

STREET NAME CODE (SNC): The final three digits of the B10SC (Borough and Ten-digit **Street Code**) are called the Street Name Code (SNC). Thus, the B10SC consists of the concatenation of the borough code, 5SC, **LGC** and SNC. The SNC serves simply to serialize the street names within a local group, so that the full B10SC is unique to a specific spelling of a specific street name.

STREET NAME NORMALIZATION LENGTH LIMIT (SNL) [Chapter III.2]: A user-specifiable parameter that sets the maximum length in bytes within which Geosupport **normalizes** input street names. The default value is 32.

U

UPG - See **User Programming Guide**

USER PROGRAMMING GUIDE (UPG) [Chapter I.6]: This document.

VANITY ADDRESS [Chapters V.9]: An address such that the street name refers to a different street than the one on which the referenced building entrance is actually located. For an input vanity address, the output information that Functions 1 and 1E return is based on the street segment where the vanity address is actually located, including the cross streets, geographic district identifiers and spatial coordinates. The source for the Spatial Coordinates (a.k.a. X-Y coordinates) returned for Vanity Addresses (and NAPs) is the **Citywide Street Centerline file (CSCL)**. The CSCL information guarantees that the X-Y coordinates fall within the actual location (e.g. building footprint) of the Vanity Address. A warning is issued accordingly. The output information that Function 1A returns is based on the building associated with the vanity address. No warning is issued for Function 1A.

V

VERSION (OF GEOSUPPORT FOREGROUND SOFTWARE) [Chapter I.5]: Self-explanatory. Contrast use of the term 'version' for Geosupport software and **'release'** for Geosupport data files.

VESTIGIAL FEATURE [Chapter I.5]: An element of the Geosupport System, such as a **function**, a **work area**, a data item or a JCL statement, that is obsolete and has been superseded by an enhancement. Vestigial features may continue to be operational but should not be used in new applications, and should be eliminated from existing ones.

W

WARNING [Chapter II.2]: A conditionally successful completion of an **API** call to Geosupport. A warning is signified by a GRC value of '01' and an accompanying **Reason Code** and **Message**. In most cases, it is appropriate for applications to treat warnings in the same way as successful completions. It is sound practice, however, to examine the Reason Codes and Messages.

WA1, WA2 - See **Work Areas**

WORK AREAS [Chapter II.1]: Standard-layout blocks of data in memory that are shared between Geosupport and an application. The Geosupport work areas are an essential component of the Geosupport **API**, and constitute the sole means by which information passes between the application and Geosupport. Different Geosupport **functions** use different work area layouts. **API** calls can involve the passing of either one work area, called **Work Area 1 (WA1)**, or two work areas, **WA1 and Work Area 2 (WA2)**.

CITY OF NEW YORK
Bill de Blasio, Mayor

DEPARTMENT OF CITY PLANNING
Marisa Lago, Director
Anita Laremont, Executive Director
Jon Kaufman, Chief Operating Officer

INFORMATION TECHNOLOGY DIVISION
Hassan Adekoya, Chief Information Officer
Michele McInnes, AICP, PMP, Senior Advisor, IT Strategic Planning and Administration

ENTERPRISE DATA MANAGEMENT
Lynn Seirup, Director

Thomas Costa, AICP, Manager, Geographic Research
Rodrigo Zapata, Deputy Manager, Geographic Research

CITYWIDE GEOGRAPHIC APPLICATION SERVICES

Nilesh Palve, Director
Programming Staff
Jie Ding
Gloria Katz
Yoel Lebel
Steve Oliver
Jasmine Tse
Tatyana Vechnyak

The Geosupport logo is a trademark of the Department of City Planning / City of New York.
Geosupport Desktop Edition is a trademark of the Department of City Planning / City of New York

Windows is a registered trademark of Microsoft Corporation in the United States and/or other countries.

Other product and company names mentioned herein may be the trademarks or registered trademarks of their respective owners.