# Day 2: Communications

## Hands on building a Goby application from scratch

#### Minimal example that builds

In the <code>goby3-course</code> repository, I have created two application patterns (or "templates" but I avoid that term in this context because of the potential confusion with C++ templates) that you can copy to create new Goby applications quickly:

```
goby3-course/src/bin/patterns/multi_thread
goby3-course/src/bin/patterns/single_thread
```

Use of these pattern files is completely optional, and as you gain further understanding you will likely wish to generate your applications from scratch.

We will now walk through building up the single\_thread pattern. At a minimum, when using the Protobuf Configurator (as we will in this course), a Goby application will have three files:

```
app.cpp  # actual code
config.proto  # configuration proto message
CMakeLists.txt  # build instructions
```

app.cpp can be split across several files (\*.h and \*.cpp as needed) for logical and structural clarity as needed as the program grows (and does not need to be called app.cpp at all).

First, we will build up the app.cpp file. Let's do this in src/bin/myapp.

All ZeroMQ Goby applications inherit from either goby::zeromq::SingleThreadApplication or goby::zeromq::MultiThreadApplication, depending on whether you want to be able to have an InterThreadTransporter for thread-to-thread comms.

So, let's declare a subclass:

```
// app.cpp
#include <goby/zeromq/application/single_thread.h>

class MyApp : public goby::zeromq::SingleThreadApplication<...>
{
};
```

As we see already, we need a template parameter <code>config</code> for our application. All Goby applications must have a configuration object, which is filled from the command line parameters and/or a configuration file. This configuration object is populated by a Configurator class, which contains instructions on how to parse the command line syntax into this object.

For this course we will use the default Configurator, <code>goby::middleware::ProtobufConfigurator</code>. This class uses a Google Protocol Buffers ("Protobuf") message to define the valid configuration, then parses the command line and/or configuration file using the TextFormat specification for Protobuf.

Thus, all we need to do to configure our application is define a Protobuf message that specifies the valid configuration parameters for our application. This is done in config.proto, which we will now create:

```
// config.proto
syntax="proto2";
package config; // becomes "namespace config {}"

message MyApp
{
}
```

This message must contain at least an app block. It also must contain an interprocess block if we want to be able to communicate with gobyd:

```
// config.proto
import "goby/middleware/protobuf/app_config.proto";
import "goby/zeromq/protobuf/interprocess_config.proto";

message MyApp
{
    optional goby.middleware.protobuf.AppConfig app = 1;
    optional goby.zeromq.protobuf.InterProcessPortalConfig interprocess = 2;
}
```

All other parameters are up to the application you're creating. We can accept an integer called value\_a, for example:

```
// config.proto
message MyApp
{
    // ...
    optional int32 value_a = 3;
}
```

If you're not familiar with Protobuf, it's worth reading through the getting started guide: <a href="https://developers.google.com/protocol-buffers/docs/cpptutorial">https://developers.google.com/protocol-buffers/docs/cpptutorial</a>. Note that we are using "proto2" throughout this course.

Now that we have a configuration message, we can use the C++ version of it in our app.cpp:

```
// app.cpp
#include "config.pb.h"

class MyApp : public goby::zeromq::SingleThreadApplication<config::MyApp>
{};
```

Now, we need to declare a main function, because every C++ application must have one. When using the Goby application classes, this is a simple matter of calling goby::run:

```
// app.cpp
int main(int argc, char* argv[])
```

```
{
    return goby::run<MyApp>(goby::middleware::ProtobufConfigurator(argc,
argv));
}
```

Note that we pass the command line arguments to ProtobufConfigurator, which then generates the appropriate configuration for our class. Inside our MyApp class, we can access this configuration by calling the class method cfg().

Now we need to build our code. This is done by adding a CMakeLists.txt file, which is read by CMake to generate files for either Make or Ninja to use to actually build the code.

We will copy this one, as this course isn't about learning CMake:

```
# CMakeLists.txt
# change for your new application - this is name the binary will be caleed
set (APP goby3 course my app)
# turn the config.proto into C++ code: config.pb.cc and config.pb.h
protobuf generate cpp(PROTO SRCS PROTO HDRS ${CMAKE CURRENT BINARY DIR}
config.proto)
# create an executable (binary)
add executable(${APP})
 app.cpp
  ${PROTO SRCS} ${PROTO HDRS})
# link it to the appropriate goby libraries and course messages library
target link libraries(${APP})
 goby
 goby zeromq
 goby3 course messages)
# generate the interfaces file using goby clang tool for later visualization
if(export goby interfaces)
  generate interfaces(${APP})
endif()
```

Finally, we need to inform the parent directory's CMakeLists.txt that we have added a new directory
to the build tree:

```
# src/bin/CMakeLists.txt
add_subdirectory(myapp)
```

Now we are ready to build:

```
cd goby3-course
./build.sh
```

If successful, you will have a new binary in goby3-course/build/bin:

```
> ls ~/goby3-course/build/bin/goby3_course_my_app
/home/toby/goby3-course/build/bin/goby3_course_my_app
```

### Synchronous loop() method

Some applications will find it convenient to have an event that is triggered on a regular interval of time. For this purpose, the Goby Application classes have a virtual loop() method. If you choose to override this method, you can pass the desired frequency that this method is called into the base class constructor.

The example, if we want <u>loop()</u> called at 10 Hz, we would write:

Note that the <u>loop()</u> method is run in the same thread as the subscription callbacks (which we will get to shortly), so if these block, the <u>loop()</u> method will be delayed.

We can test this by starting a gobyd (since our app won't construct if it cannot connect to one) and running with -v so that we see VERBOSE glog output:

```
gobyd
// new terminal
goby3_course_my_app -v
```

#### yields:

```
goby3_course_my_app [2021-Feb-19 20:35:58.500129]: This is called 10 times per second goby3_course_my_app [2021-Feb-19 20:35:58.600132]: This is called 10 times per second goby3_course_my_app [2021-Feb-19 20:35:58.700122]: This is called 10 times per second
```

### Configuration values

The contents of your configuration message are available via a call to cfg():

Now if we rebuild and run our application, passing --value a on the command line:

```
goby3_course_my_app --value_a 3 -v
```

#### results in

```
goby3_course_my_app [2021-Feb-19 20:35:58.460566]: My configuration value a is:
```

If you ever need to remember the syntax for flags on the command line, you can run:

```
goby3_course_my_app --help
```

Configuration values can be passed in a file that is given as the first argument (e.g. <a href="mailto:goby3\_course\_my\_app my\_app.pb.cfg">goby3\_course\_my\_app my\_app.pb.cfg</a>), where the syntax of <a href="mailto:my\_app.pb.cfg">my\_app.pb.cfg</a> is the Protobuf TextFormat language. This is used by most real applications as it becomes unwieldy to pass large amounts of configuration via command line flags. All valid configuration values that could be put in this file are provided when you run:

```
goby3_course_my_app --example_config
```

(Remember that the values in both cases are what we provided in <a href="config:proto">config:proto</a>). If you provide both a configuration file and command line flags, they are merged, with the command line flags taking precedence.

We have now built up the code that is essentially the same as what is provided in the single\_thread
pattern directory:

```
goby3-course/src/bin/patterns/single_thread
```

From the rest of this course, we will copy that as a starting point for our Goby applications.

Now we are ready to start exploring the most significant benefits of using a Goby application: publishing and subscribing to data.

## Understanding Nested Publish/Subscribe

Recall from Day 1 the three-layer nested hierarchy:

- **interthread**: Thread to thread using shared pointers
- **interprocess**: Process to process using a interprocess transport (we will use ZeroMQ for this course)
- intervehicle: Vehicle to vehicle (or other platform) using acoustic comms, satellite, wifi, etc.

#### **Interprocess**

We will start in the middle of this hierarchy (at **interprocess**) as this is the most familiar to users of ROS, MOOS, LCM, etc.

At it simplest, interprocess communications using a publish/subscribe model requires:

- A single publisher
- A single subscriber




This is the topology we will explore for the next part of today's lecture.

In the Goby3 reference implementation of interprocess, based on ZeroMQ, the interprocess communication is mediated by a ZeroMQ XPUB/XSUB "proxy" (or broker), which is contained within gobyd:




For many of the graphs, we will omit gobyd but it is always part of the actual communications path.

For more realistic systems, we will have multiple subscribers, and multiple publishers:



Less frequently, we may even have two publishers of the same data type:



All of these topologies are supported in Goby.

Hands-on with one publisher / one subscriber in Goby3