# Feature extractors

### Contents

- Available backbones and layers
- Backbone and layer selection

This guide demonstrates how different backbones can be used as feature extractors for anomaly detection models. Most of these models use Timm Feature Extractor except **CSFLOW** which uses TorchFx Feature Extractor. Here we show how to use API and CLI to use different backbones as feature extractors.



### Available backbones and layers

#### Timm TorchFX

When using TorchFX for feature extraction, you can use either model name, custom model, or instance of model. In this guide, we will cover pretrained models from Torchvision passed by name. For use of the custom model or instance of a model refer to

TorchFxFeatureExtractor class examples.

Available torchvision models are listed on <u>Torchvision models page</u>.

We can get layer names for selected r ' ' he following code:

Back to top

```
# Import model and function to list names
from torchvision.models import resnet18
```

1 di 3

```
from torchvision.models.feature_extraction import get_graph_node_names
# Make an instance of model with default (latest) weights
model = resnet18(weights="DEFAULT")
# Get and print node (layer) names
train_nodes, eval_nodes = get_graph_node_names(model)
print(eval_nodes)
>>>['x', 'conv1', 'bn1', 'relu', 'maxpool', ..., 'layer4.1.relu_1', 'avgpool', 'fla
```

As a result, we get a list of all model nodes, which is guite long.

Now for example, if we want only output from the last node in the block named | layer4|, we specify layer4.1.relu\_1. If we want to avoid writing layer4.1.relu\_1 to get the last output of [layer4] block, we can shorten it to [layer4].

We can then use selected model name and layer names with either API or using config file.



#### See also

Additional info about TorchFX feature extraction can be found on PyTorch FX page and feature\_extraction documentation page.



### Warning

Some models might not support every backbone.

## Backbone and layer selection

#### API **CLI**

When using API, we need to specify backbone and layers when instantiating the model with a non-default backbone.

```
1 # Import the required modules
                                   Back to top
2 from anomalib.data import MV1.
3 from anomalib.models import Padim
4 from anomalib.engine import Engine
5
```

2 di 3 29/03/2024, 06:07

```
6 # Initialize the datamodule, model, and engine
7 datamodule = MVTec(num_workers=0)
8 # Specify backbone and layers
9 model = Padim(backbone="resnet18", layers=["layer1", "layer2"])
10 engine = Engine(image_metrics=["AUROC"], pixel_metrics=["AUROC"])
11
12 # Train the model
13 engine.fit(datamodule=datamodule, model=model)
```

Previous
Model Tutorials

Next >

Back to top

3 di 3