```
bitcoin core configuration file)
/home/user/.bitcoin/bitcoin.testnet.conf

rpcuser = bitcoin-rpc
rpcpassword = PaSS
server = 1
daemon = 1
txindex = 1
addrindex = 1
rpctimeout = 300
testnet = 1
```

```
counterparty-client configuration file
/home/user/.config/counterparty/client.testnet.conf

[Default]
wallet-user = bitcoin-rpc
wallet-password = PaSS
wallet-connect = localhost
wallet-name = bitcoincore
counterparty-rpc-user = counterparty-rpc
```

EXAMPLES: SERVICE STATUS COMMANDS

bitcoind (testnet)

testnet = 1

bitcoin-cli -conf=\$HOME/.bitcoin/bitcoin.testnet.conf getinfo

counterparty client (testnet)

counterparty-rpc-password = WoRD

counterparty-client --config-file \$HOME/.config/counterparty/client.testnet.conf wallet

counterparty server (testnet) [enter this command as single line]

curl http://localhost:14000/api/ --user counterparty-rpc:WoRD -H 'Content-Type: application/json; charset=UTF-8' -H 'Accept:application/json, text/javascript' --data-binary '{"jsonrpc":"2.0","id":0,"method":"get_asset_info","params": {"assets": ["XCP"]}}'

counterparty-server configuration file /home/user/.config/counterparty/server.testnet.conf

```
[Default]
backend-name = addrindex
backend-user = bitcoin-rpc
backend-password = PaSS
rpc-host = localhost
rpc-user = counterparty-rpc
rpc-password = WoRD
testnet = 1
```

LOCATIONS OF IMPORTANT FILES

PATHS

Symlink path to your bitcoind, bitcoin-cli binary (from BTCdrak) to shared locations:

sudo ln -sf ~/bitcoin-0.10.0/bin/bitcoind /usr/bin/bitcoind
sudo ln -sf ~/bitcoin-0.10.0/bin/bitcoin-cli /usr/bin/bitcoin-cli

START

To start services with root-owned configuration files and data:

bitcoind -conf=\$HOME/.bitcoin/bitcoin.testnet.conf
counterparty-server --config-file \$HOME/.config/counterparty/server.testnet.conf start

DATA

bitcoind (testnet) data:

\$HOME/.bitcoin/testnet3

counterparty-server (testnet) data:

\$HOME/.local/share/counterparty/counterparty.testnet.*

LOGS

bitcoind (testnet) log:

\$HOME/.bitcoin/testnet3/debug.log

counterparty-server (testnet) logs:

\$HOME/.cache/counterparty/log/server.testnet.log

\$HOME/.cache/counterparty/log/server.testnet.api.log

NOTE

This release assumes Bitcoin Core 0.12 with addrindex (by btcdrak) or newer is used

counterparty-lib cheat sheet (v9.55) (testnet only)

```
bitcoin core configuration file))
%APPDATA%\Bitcoin\bitcoin.testnet.conf
rpcuser = bitcoin-rpc
rpcpassword = PaSS
server = 1
daemon = 1
txindex = 1
addrindex = 1
rpctimeout = 300
testnet = 1
```

counterparty-client configuration file %APPDATA%\Counterparty\client.testnet.conf

```
[Default]
wallet-user = bitcoin-rpc
wallet-password = Pass
wallet-connect = localhost
wallet-name = bitcoincore
counterparty-rpc-user = counterparty-rpc
counterparty-rpc-password = WoRD
testnet = 1
```

EXAMPLES: SERVICE STATUS COMMANDS

bitcoind (testnet)

bitcoin-cli -conf=%APPDATA%\Bitcoin\bitcoin.testnet.conf getinfo

counterparty client (testnet)

set of files (bitcoin.conf, server.conf, client.conf) without "testnet=1" in them)

counterparty-client --config-file %APPDATA%\Counterparty\counterparty\server.testnet.conf wallet

counterparty server (testnet) [enter this command as single line, preferably from Cygwin or other UNIXy shell]

```
counterparty-server configuration file
Windows 7
                    %APPDATA%\Counterparty\server.testnet.conf
                    [Default]
                    backend-name = addrindex
                    backend-user = bitcoin-rpc
                    backend-password = PaSS
                    rpc-host = localhost
                    rpc-user = counterparty-rpc
                    rpc-password = WoRD
                    testnet = 1
```

LOCATIONS OF IMPORTANT FILES

PATHS

To be able to easier run from the CLI, add these to the system PATH variable:

C:\Program Files (x86)\Bitcoin\daemon (bitcoind.exe)

C:\Program Files (x86)\Bitcoin (bitcoin-qt.exe)

C:\Python34\Scripts (counterparty-server.exe, counterparty-client.exe)

START

To start services:

1. Start > Program Files > Bitcoin Core > Bitcoin Core or "bitcoind" in the console

2. counterparty-server --config-file

%APPDATA%\Counterparty\counterparty\server.testnet.conf start

DATA

bitcoind (testnet) data:

%APPDATA%\Bitcoin\testnet3

counterparty-server (testnet) data:

C:\Users\<USERNAME>\AppData\Local\Counterparty\counterparty

LOGS

curl http://localhost:14000/api/ --user counterparty-rpc:WoRD -H 'Content-Type: application/json; charset=UTF-8' -H 'Accept:application/json,

bitcoind (testnet) log:

%APPDATA%\Bitcoin\testnet3\debug.log

counterparty-server (testnet) logs:

C:\Users\<USERNAME>\AppData\Local\Counterparty\counterparty\server.testnet.log C:\Users\<USERNAME>\AppData\Local\Counterparty\counterparty\server.testnet.api.log NOTE:

This release assumes Bitcoin Core 0.12 with addrindex (by btcdrak) or newer is used