

CompTIA A+ Core 1 Playbook

IT Labs

Prepared by Garrick White

8.1.6 Create Virtual Hard Disks

You have installed Hyper-V on ITAdmin. You want to create two new virtual machines (VMs) on which you will later install Windows 11. These new VMs will be used for testing.

In this lab, your task is to:

- Create a new virtual machine named VM1 using the following parameters:
 - Virtual machine name: **VM1**
 - Virtual machine location: **D:\HYPERV**
 - Generation: **Generation 1**
 - Startup memory: **1024 MB** (do not use dynamic memory)
 - Networking connection: **External**
 - Virtual hard disk name: **VM1.vhdx**
 - Virtual hard disk location: **D:\HYPERV\Virtual Hard Disks**
 - Virtual hard disk size: **50 GB**
 - The operating system will be installed later.
- Create a new virtual machine named VM2 using the following parameters:
 - Virtual machine name: **VM2**
 - Virtual machine location: **D:\HYPERV**
 - Generation: **Generation 1**
 - Startup memory: **2048 MB** (use dynamic memory)
 - Networking connection: **Internal**
 - Virtual hard disk name: **VM2.vhdx**
 - Virtual hard disk location: **D:\HYPERV\Virtual Hard Disks**
 - Virtual hard disk size: **250 GB**
 - The operating system will be installed later.

- Configure the minimum and maximum RAM values for VM2.
 - Minimum RAM: **512 MB**
 - Maximum RAM: **4096 MB**

To create a new virtual machine, start Hyper-V Manager, right-click ITADMIN, then select **New > Virtual Machine**.

To configure RAM, right-click a virtual machine, then select **Settings**.

Explanation

Complete this lab as follows:

1. Start Hyper-V Manager.
 1. From the taskbar, select **Start**.
 2. In the search field, type **Hyper-V**.
 3. Under *Best match*, select **Hyper-V Manager**.
2. From ITAdmin, create a new virtual machine named VM1.
 1. Right-click **ITADMIN** and then select **New > Virtual Machine**.
 2. In the *Before You Begin* window, select **Next**.
 3. In the Name field, enter **VM1** and then select **Next**.
 4. Make sure **Generation 1** is selected, and then select **Next**.
 5. For the Startup memory field, use **1024 MB** as the amount of memory to use with the virtual machine; then select **Next**.
 6. For Connection, use the drop-down menu to select **External** and then select **Next**.
 7. Make sure **Create a virtual hard disk** is selected.

Virtual disks created along with virtual machines are dynamically expanding disks. If you need to create any other kind of disk, you can either create the disk before the virtual machine or convert the disk type after the virtual machine has been created.
 8. In the Name field, make sure **VM1.vhdx** is entered.
 9. In the Location field, make sure **D:\HYPERV\Virtual Hard Disks** is entered.
 10. For the Size field, use **50 GB** and then select **Next**.
 11. Make sure **Install an operating system later** is selected and then select **Next**.
 12. Select **Finish** to create the virtual machine.
3. From ITAdmin, create a new virtual machine named VM2.

1. From Hyper-V manager, right-click **ITADMIN** and then select **New > Virtual Machine**.
 2. In the *Before You Begin* window, select **Next**.
 3. In the Name field, enter **VM2**.
 4. Select **Next**.
 5. Make sure **Generation 1** is selected and then select **Next**.
 6. In the Startup memory field, enter **2048** MB of memory to use with the virtual machine.
 7. Mark **Use Dynamic Memory for this virtual machine** and then select **Next**.
 8. For Connection, use the drop-down menu to select **Internal** and then select **Next**.
 9. Make sure **Create a virtual hard disk** is selected.
 10. In the Name field, make sure **VM2.vhdx** is entered.
 11. In the Location field, make sure **D:\HYPERV\Virtual Hard Disks** is entered.
 12. For the Size field, use **250** GB and then select **Next**.
 13. Make sure that **Install an operating system later** is selected and then select **Next**.
 14. Select **Finish** to create the virtual machine.
4. Configure the minimum and maximum RAM values for VM2.
 1. Under Virtual Machines, right-click **VM2** and select **Settings**.
 2. From the left pane, select **Memory**.
 3. For the Minimum RAM field, use **512** MB.
 4. For the Maximum RAM field, use **4096** MB and then select **OK**.