通过HAProxy 跨region 访问Redis server



一、创建Redis Server

Instance properties	
Tier	Standard
Location	us-central1-a
Capacity	1 GB
Estimated network throughput (Mb/s)	375 / 1500
Version	5.0
Estimated cost ?	\$46.72/month

Connection properties

IP address	
172. 25. 160. 4	<u>_</u>
Port	
6379	0

二、配置HAProxy 完成跨region 流量转发

1、安装HAProxy, centos 7

```
$ sed -i "s/enforcing/disabled/g" /etc/selinux/config &&
setenforce 0 && systemctl status firewalld #关闭防火墙
$ yum install -y haproxy # 安装HAProxy
```

2、HAProxy 配置文件

vim /etc/haproxy/haproxy.cfg

```
#----
# common defaults that all the 'listen' and 'backend' sections
will
# use if not designated in their block
#----
```

```
defaults
                                 # 修改为4层 TCP proxy
  mode
                     tcp
  log
                     global
  option
                     tcplog
  option
                     dontlognull
                     redispatch
  option
                     5
  retries
  timeout queue
                     3m
  timeout connect
                     30s
  timeout client
                    1m
  timeout server
                    1m
  timeout check
                    10s
                    3000 # 后面可以根据需求修改
  maxconn
#-----
# main frontend which proxys to the backends
frontend main *:6379
                redis # 配置后端
  default_backend
#-----
# static backend for serving up images, stylesheets and such
backend redis
  server redis1 172.25.160.4:6379 check
```

三、验证跨region 访问redis

```
## 通过内网地址访问redis server
$ telnet 10.128.0.10 6379
Trying 10.128.0.10...
Connected to 10.128.0.10.
Escape character is '^]'.
```