LLARS - Getting Started & Script Setup Guide

Current User Guide

Current for LLARS v2

Scope - This guide documents the public LLARS project as it operates in v2. Follow the shared framework and the current GUI/API behavior described here.

Contents

1. Before You Start
2. Choosing and Launching a Script
3. How LLARS Configuration Is Split
4. Information and Setup Tools
5. Configuration Status and Reset Config
6. Setting Up Coordinates
7. Setting Up Hotkeys
8. Setting Up Colors
9. Optional Settings and Dependencies
10. Run Modes
11. Starting a Run
12. RuneScape Focus and Input Safety
13. Pausing, Resuming, and Stopping
14. Random Sleep
15. Developer Mode and Support
16. Input Settings and AHI
17. Backup, Restore, and Updates
18. If You Change Your Game Layout
19. Common Problems and Best Practices
20. The Simple Version

1. Before You Start

- Keep the complete LLARS folder extracted. Do not run individual scripts from inside a ZIP/RAR/7Z archive.
- Install AutoHotkey v1.1.37.02. AutoHotkey v2 is not a drop-in replacement.
- Open RuneScape 3 and arrange the game window/interface the way you plan to use it.
- Keep script-local Config.ini files beside their scripts. Some scripts intentionally do not have a local Config.ini.
- Read the script Information text and any Config.ini comments before first use.

Input backend - LLARS recommends AutoHotInterception (AHI). If AHI/Interception is not ready, LLARS can use Standard AutoHotkey fallback. Input Settings shows which route is actually active.

2. Choosing and Launching a Script

Run Script Selector.ahk for the project menu, or open a script directly from its Scripts folder. The selector is the easiest way to browse the collection.

- Search filters the visible script list as you type. Press Ctrl+F to focus Search.
- The view selector provides All Scripts, Favorites, and Recent.
- Add Favorite / Remove Favorite changes the selected script in your persistent favorites list.
- Recent keeps the five most recently launched scripts in newest-first order.
- Clear Filters returns to All Scripts and clears the current search text.
- Favorites and Recent are preferences stored in the root LLARS Config.ini. Empty lists are valid.

3. How LLARS Configuration Is Split

LLARS uses a shared root configuration plus optional script-local configuration.

File	Purpose
LLARS Config.ini	Shared hotkeys, GUI position/opacity, Random Sleep, Developer Mode, input backend, and Script Selector preferences.
Scripts/.../Config.ini	Activity-specific coordinates, colors, hotkeys, timers, options, and other typed settings when that script needs them.

The root configuration uses config_schema=1. LLARS accepts compatible existing configuration and rejects a future schema it does not understand rather than guessing.

4. Information and Setup Tools

Open Information from a script GUI for script guidance and project tools. Current v2 actions include Backup Config, Restore Config, Input Settings, and links/help appropriate to the script.

- Backup Config copies the root LLARS Config.ini plus script-local Config.ini files into the project backup set.
- Restore Config restores the saved configuration set using the same project tools.
- Input Settings shows configured backend, active route, AHI driver/device readiness, last mouse/keyboard transport, startup timing, and fallback state.

5. Configuration Status and Reset Config

Configuration Status summarizes whether typed settings required by the current script are ready. Optional or disabled dependencies are not treated as missing. Scripts with no local configuration can report Not Required.

Reset Config clears supported user-entered values so they can be captured again. Use it when a coordinate, color, or hotkey was recorded incorrectly or after a layout change.

6. Setting Up Coordinates

1. Open the script setup tool for coordinates.
2. Follow the script-specific prompt and move the mouse to the requested location or range.
3. Capture the value exactly as requested. Some actions use a rectangular range (xmin/xmax/ymin/ymax); color watches may use a single x/y point.
4. Re-check coordinates after moving or resizing RuneScape UI elements.

Coordinate safety - Normal game-facing clicks should come from configured LLARS coordinates or shared detection helpers. LLARS validates the selected RuneScape client and focus before framework-managed physical input.

7. Setting Up Hotkeys

Configure hotkeys in Setup > Hotkeys. Defaults: F9 Start; F10 Information (always); F11 Setup (idle) or Pause/Resume (running); F12 Exit; Ctrl+Shift+D Developer Mode. Existing custom bindings remain supported.

8. Setting Up Colors

Color-based scripts store configured target colors in their script Config.ini. Follow the script prompt and sample the requested RuneScape pixel or target state. Developer Mode can show Current Pixel, Pixel Target, and detection state for troubleshooting.

9. Optional Settings and Dependencies

A setting with option=false is normally disabled. Typed dependent settings are only required when their owning option is enabled. Configuration Status reflects that dependency instead of flagging disabled features as errors.

10. Run Modes

Mode	Behavior
RunCount	Repeats a creator callback a selected number of times and estimates time from declared sleep/timing behavior.
Timer	Runs for a selected duration and may use managed or script timers.
MultiTimer	Runs multiple independently randomized callbacks during one timed session.
UntilDone / specialized	Script-defined completion condition while LLARS keeps shared run state and safety controls.

11. Starting a Run

5. Finish required setup until Configuration Status is ready.
6. Bring the intended RuneScape client into a usable state.
7. Use the script Start action or configured Start hotkey.
8. For a RunCount script, enter the requested run count; for timed scripts, choose the duration.
9. LLARS captures the RuneScape window for the run and manages shared run state.

12. RuneScape Focus and Input Safety

LLARS binds a run to the selected RuneScape window. Framework-managed clicks, keys, and pixel reads verify the target window and recover focus when needed. If the window cannot be validated, LLARS blocks the action rather than sending input to an arbitrary application.

Pausing or switching away from RuneScape suspends appropriate game-facing work. Configured waits restore RuneScape when they finish unless the run is paused.

13. Pausing, Resuming, and Stopping

- Use the script pause control/hotkey to pause and resume supported runs.
- Exit stops the script process and framework-managed timers.
- Closing a script or ending a run releases shared run state and managed input/timer resources.

14. Random Sleep

Random Sleep is a shared optional long-break feature in LLARS Config.ini. When enabled, chance controls how often a break is selected and min/max define the break range in milliseconds. RunCount estimation accounts for its expected contribution.

15. Developer Mode and Support

Developer Mode is an optional diagnostic view. Scripts must work with it closed. Full Mode includes live framework state; Lightweight Mode focuses on recent actions.

- Active Hotkeys and run state.
- Live Inspector for mouse/pixel/configured targets.

- Configuration Diagnostics.
- Detection state, including creator-supplied confidence/threshold/detail when available.
- Recent Framework Actions and recovery/error events.
- Copy Support, which regenerates and copies a sanitized support report.

The support report is stored at Logs\LLARS-Support.txt when generated or when LLARS records relevant failures/fallbacks. Do not edit the report before sharing unless you intentionally want to remove details.

16. Input Settings and AHI

Information > Input Settings is the authoritative input-health view.

- AHI is the recommended configured backend.
- Test AHI is non-invasive: it checks runtime/driver/device readiness without moving the mouse, clicking, or typing.
- Enable/Repair AHI can install or repair the bundled Interception/AHI components and may require Administrator approval plus a Windows restart.
- Use Standard selects the AutoHotkey fallback.
- Uninstall removes the LLARS-managed Interception driver path; LLARS does not ask you to manually delete driver files.
- The active mouse and keyboard routes may fall back independently if a route is unavailable.

17. Backup, Restore, and Updates

The Backup folder contains Config Backup.bat, Config Restore.bat, and the written backup/restore guide. The same backup mechanism is invoked before an accepted LLARS update download begins.

LLARS checks for a newer release before the main selector/script GUI. If you accept an update, keep the current folder until the replacement ZIP is saved and validated. Canceling or a failed download returns to the current installation.

18. If You Change Your Game Layout

Coordinates and pixel colors describe your current interface. Moving RuneScape, changing scaling, changing interface layout, or changing relevant visual settings can invalidate them. Re-capture affected coordinates/colors and use Developer Mode to verify the current state.

19. Common Problems and Best Practices

Symptom	What to check
Config Error	Read the section/key named in the dialog. Required values cannot be blank; optional selector Favorites/Recent may be empty.
Game Not Found / focus issue	Open RuneScape 3, confirm the correct client is visible, and retry.
AHI unavailable	Open Input Settings, run Test AHI, repair/restart if instructed, or use Standard fallback.
Click/pixel misses after UI changes	Re-capture coordinates/colors and compare Developer Mode Current Pixel / Pixel Target.
Need support	Use Developer Mode > Copy Support and include the script name plus what you were doing.

- Keep a configuration backup before large changes.
- Use the project GUI instead of editing AHK source for normal setup.
- Do not move a single script away from Core, Assets, Vendor, and the rest of the project.
- Read script-specific Information and Config.ini comments; different activities can have different requirements.

20. The Simple Version

10. Extract the complete LLARS folder.
11. Install AutoHotkey v1.1.37.02.
12. Run Script Selector.ahk and choose a script.
13. Use Information/setup tools until Configuration Status is ready.
14. Start the script with RuneScape open.
15. If input fails, use Input Settings > Test AHI; if setup/detection fails, use Developer Mode and Copy Support.