LLARS - Getting Started & Script Setup Guide

Current User Guide

Welcome to LLARS.

LLARS stands for Local Library of Automated Routines & Scripts.

LLARS is designed so most users can set up and run scripts through the GUI without editing the .ahk file. This guide focuses on choosing a script, configuring the values it needs, understanding the available run modes, and knowing what LLARS will do while a run is active.

Table of Contents

1. Before You Start
2. Choosing and Launching a Script
3. How LLARS Configuration Is Split
4. The Main Setup Tools
5. Configuration Status and Reset Config
6. Setting Up Coordinates
7. Setting Up Hotkeys
8. Setting Up Colors
9. Optional Settings and Dependencies
10. Run Modes
11. Starting a Run
12. What Happens to RuneScape Focus
13. Pausing, Resuming, and Stopping
14. Random Sleep
15. Developer Mode
16. If You Change Your Game Layout
17. Common Problems
18. Best Practices
19. About LLARS
20. The Simple Version

1. Before You Start

- Keep the complete LLARS folder extracted.
- Install AutoHotkey v1.1.37.02. LLARS recommends AHI; first launch offers bundled setup (UAC + one restart).
- Open RuneScape and arrange the game window/interface the way you plan to use it.
- Keep scripts in the LLARS folder structure and keep any provided Config.ini beside its script.
- Read the script Information and, when present, its Config.ini comments during first setup.

Most users should not manually edit framework code or move individual scripts out of the project.

2. Choosing and Launching a Script

Use Script Selector.ahk when you want the project menu for choosing a script. A script can also be run directly from its folder when needed.

Each script is built for one activity and may ask for different setup. Do not assume settings from one script apply to another.

- Choose the script/activity.
- Read its Information text and any provided Config.ini comments.
- Open the LLARS setup tools and configure only the settings that script requires.
- Start with a short test run before using a long duration or large run count.

3. How LLARS Configuration Is Split

LLARS Config.ini

The root LLARS Config.ini stores framework-wide settings such as LLARS control hotkeys, transparency, Random Sleep, and other shared options.

Script Config.ini

Most configurable scripts have a local Config.ini in the same folder; some scripts do not require one.
When present, it describes coordinates, hotkeys, colors, waits, options, and other script-specific settings.

> **Note:** Use the GUI for normal colors/coordinates/hotkeys setup. Config.ini is still worth reading because comments often explain exactly what to select or how an activity must be arranged.

4. The Main Setup Tools

Information

Shows script-specific information. Information > Input Settings shows the configured backend, Active input, and AHI driver state; use it to Enable/Repair or Uninstall AHI.

Colors / Coordinates / Hotkeys

This is the main script-specific setup area. LLARS shows only typed settings that exist in the current script.

Configuration Status

Shows whether typed settings are Ready, Missing, or Not Required.

Reset Config

Clears selected typed colors/coordinates/hotkeys without changing unrelated script settings.

5. Configuration Status and Reset Config

Status	Meaning
Ready	The required typed value is configured.
Missing	The script still needs this setting before it can run correctly.
Not Required	The setting is currently disabled or depends on a disabled feature.

Reset Selected clears the chosen typed value. Clear All clears typed hotkey/coordinate/color values in the current script after confirmation. Sleep ranges, timer values, option flags, unrelated settings, and the shared LLARS Config.ini are not part of script Reset Config.

6. Setting Up Coordinates

Coordinate settings tell a script where something is inside the RuneScape client.

Coordinate area

Many actions use a rectangular area rather than one exact pixel. Right-click the requested top-left point, then right-click the bottom-right point. LLARS can choose a randomized point inside that range when the script clicks.

Exact pixel

Color-detection scripts can use one exact Pixel Coordinate. Right-click once on the exact point requested by the script instructions.

- Set up RuneScape first, then capture coordinates.
- Do not move/rescale important interface elements afterward unless you plan to capture them again.
- Read the comment above each Config.ini coordinate section; different sections may want different kinds of selections.

7. Setting Up Hotkeys

Configured hotkeys are user-selectable RuneScape bindings. Make sure the chosen key actually performs the intended action in RuneScape before saving it in LLARS.

1. Open Colors/Coordinates/Hotkeys.
2. Choose Hotkeys.
3. Select the script setting.
4. Enter the desired key or combination.
5. Save and test it in RuneScape.

> **Note:** Some scripts also use purposeful fixed keys such as Space or Enter. Those do not appear as configurable script hotkeys because the script is designed to use that key directly.

8. Setting Up Colors

Color settings let a script recognize a particular game state at a configured pixel.

1. Open the relevant RuneScape state so the desired color is visible.

2. Open Colors/Coordinates/Hotkeys and choose Colors.
3. Select the target color setting.
4. If the color maps to a coordinate, LLARS samples that saved pixel; otherwise follow the capture prompt.
5. Save the value.

Multi-color scripts can have several Target Color sections for one Pixel Coordinate. Each color represents a valid state the script knows how to recognize.

9. Optional Settings and Dependencies

Some script features can be disabled. When an optional parent feature is off, its dependent coordinate/hotkey/color settings normally show Not Required instead of Missing.

Only enable and configure optional behavior you actually intend to use. This keeps Configuration Status focused on the setup that matters for the run.

10. Run Modes

RunCount

Asks for 1 to 1000 complete repetitions. One run is one complete sequence defined by the script.

Timer

Asks for an overall duration in minutes; decimals are accepted (0.5 = 30 seconds, 1 = 1 minute).

Until Complete

Starts without a run-count or duration prompt and runs until the script's own completion condition is met.

11. Starting a Run

When Start is pressed, LLARS validates required configuration, captures the RuneScape client, and prompts only when the selected run mode needs a RunCount or duration. Until Complete starts without either prompt.

RunCount estimate

Before loop 1 starts, LLARS calculates a starting loop/run estimate from the script's standardized timing configuration. The estimate is shown before automation begins and becomes more accurate as following loops complete. During the script's true final sleep, the current-loop countdown becomes exact.

Timer countdown

Timed scripts show the user-selected remaining time. Developer Mode Progress, when open, mirrors the same live countdown.

12. What Happens to RuneScape Focus

LLARS locks the run to the exact RuneScape window selected at start. Game-facing actions such as clicks, mouse movement, keyboard input, managed timer actions, and framework pixel reads verify that RuneScape is foreground before they operate.

During waits

LLARS sleeps do not hold RuneScape in the foreground. You can Alt-Tab to another application during a long wait.

When the next action is due

When a configured LLARS sleep or Random Sleep finishes, or when another managed action becomes due, LLARS brings the selected RuneScape client back to the foreground and continues only after verifying the correct window.

> **Important:** If you do not want LLARS to take RuneScape focus when the next action becomes due, Pause the run first. Pause/Exit are the controls that stop active automation focus reclaim.

13. Pausing, Resuming, and Stopping

Pause

Pause stops the active automation state and prevents action-time focus reclaim while paused.

Resume

Resume returns the script to its running state. The next game-facing action will make sure the selected RuneScape client is foreground.

Exit

Exit ends LLARS and stops managed script timers. Use Exit if you are finished rather than leaving a paused automation running indefinitely.

14. Random Sleep

Random Sleep is a shared optional LLARS setting. When enabled, scripts that call it may occasionally wait for a random amount of time based on the configured chance and duration range.

During Random Sleep, the main GUI shows the temporary countdown and RuneScape is not held in the foreground. When the wait finishes, LLARS restores the selected RuneScape client before continuing.

15. Developer Mode

Developer Mode is primarily for script creators and troubleshooting, but advanced users can open it to see what LLARS is doing.

Full mode

- State / Run Type / Progress, then Elapsed / Final Sleep.
- Live Inspector with mouse position, Mouse RGB, and configured pixel current-vs-target colors.
- Active Hotkeys.
- Configuration Diagnostics.
- Recent Framework Actions.

Lightweight mode

Lightweight Mode uses the same window width but shows only Recent Framework Actions. The Developer Mode hotkey toggles whichever view is selected.

Coordinate overlay

While either Developer Mode view is open, LLARS shows the coordinate range for the current NaturalClick action and leaves it visible briefly after a successful click.

Developer Mode is optional. Scripts must work normally with the window closed.

16. If You Change Your Game Layout

Coordinates and pixel colors depend on the RuneScape layout you configured. If you move, resize, scale, or rearrange important game/interface elements, captured values may no longer describe the intended location/state.

- Re-capture affected coordinates.
- Re-capture colors if visual state/pixel placement changed.
- Re-test configured hotkeys if the skillbar/action binding changed.
- Use Configuration Status after resetting/reconfiguring typed values.

17. Common Problems

Configuration Error / Missing

Open Configuration Status and complete the typed settings marked Missing. Read the Config.ini comments for exactly what each section expects.

RuneScape Not Found

Make sure RuneScape is running and recognizable before starting the script.

Script clicks the wrong place

Re-check the coordinate instructions and capture the area again using the current game layout.

Pixel script does not trigger

Use Developer Mode Live Inspector to compare Current Pixel to Pixel Target for each configured color.

Developer Mode hotkey seems to open the wrong view

The hotkey remembers Full vs Lightweight. Use the Full Mode button inside Lightweight to switch the preference back to Full.

18. Best Practices

- Read the script Information and any Config.ini comments before first use.
- Configure only the options you need.
- Test with a short run first.
- Use Pause before doing something that should not be interrupted by LLARS reclaiming RuneScape.
- Do not manually edit coordinates/hotkeys/colors when the GUI can configure them.
- Re-run setup after major RuneScape layout changes.
- Use Developer Mode as a troubleshooting view, not as a requirement for normal operation.

19. About LLARS

LLARS stands for Local Library of Automated Routines & Scripts. The project, framework, scripts, templates, and documentation are created and maintained by Gubna. LLARS is free and open source.

GitHub: https://github.com/Gubna-Tech/RuneScape

20. The Simple Version

- Open RuneScape and set up the interface for the script.
- Choose the script and read its Information and any Config.ini comments.
- Use Colors/Coordinates/Hotkeys plus Configuration Status to finish setup.
- For RunCount/Timer scripts, start with a short test; Until Complete uses its own completion condition.
- You can Alt-Tab during waits; configured waits restore RuneScape when they finish unless paused.
  paused.
- Pause when you do not want automation to reclaim RuneScape.
- Use Developer Mode only when you want extra diagnostics.
- Reconfigure coordinates/colors after changing the game layout.