Ingres® 2006 Release 3

Character-based Querying and Reporting Tools User Guide



July 2007

This documentation and related computer software program (hereinafter referred to as the "Documentation") is for the end user's informational purposes only and is subject to change or withdrawal by Ingres Corporation ("Ingres") at any time.

This Documentation may not be copied, transferred, reproduced, disclosed or duplicated, in whole or in part, without the prior written consent of Ingres. This Documentation is proprietary information of Ingres and protected by the copyright laws of the United States and international treaties.

Notwithstanding the foregoing, licensed users may print a reasonable number of copies of this Documentation for their own internal use, provided that all Ingres copyright notices and legends are affixed to each reproduced copy. Only authorized employees, consultants, or agents of the user who are bound by the confidentiality provisions of the license for the software are permitted to have access to such copies.

This right to print copies is limited to the period during which the license for the product remains in full force and effect. The user consents to Ingres obtaining injunctive relief precluding any unauthorized use of the Documentation. Should the license terminate for any reason, it shall be the user's responsibility to return to Ingres the reproduced copies or to certify to Ingres that same have been destroyed.

To the extent permitted by applicable law, INGRES PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NONINFRINGEMENT. IN NO EVENT WILL INGRES BE LIABLE TO THE END USER OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF INGRES IS EXPRESSLY ADVISED OF SUCH LOSS OR DAMAGE.

The use of any product referenced in this Documentation and this Documentation is governed by the end user's applicable license agreement.

The manufacturer of this Documentation is Ingres Corporation.

For government users, the Documentation is delivered with "Restricted Rights" as set forth in 48 C.F.R. Section 12.212, 48 C.F.R. Sections 52.227-19(c)(1) and (2) or DFARS Section 252.227-7013 or applicable successor provisions.

Copyright © 2007 Ingres Corporation.

All Rights Reserved.

Ingres, OpenROAD, and EDBC are registered trademarks of Ingres Corporation. All other trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

Contents

Chapter 1: Introduction	
What You Need to Know	1-2
Special Considerations	
Conventions	1-3
Query Languages	
Operating System Differences	
Entering Data from the Keyboard	
Terminology	1-4
Syntax	1-4
Chapter 2: Fundamentals of Using Que Tools	erying and Reporting
Before Starting Ingres	2-1
Enabling Access to the Database	2-1
Setting System Variables	2-2
About Your Database	2-3
System Catalogs and the Catalogdb Utility	2-3
Creating and Maintaining Databases	2-4
Starting an Ingres Tool	
Using Ingres Menu	
Specifying Startup Commands	2-8
Database on Remote Network Node	2-10
Non-Ingres Database	2-10
Distributed Database	2-11
Accessing Database Tables	2-11
Using Synonyms	2-12
Using Schemas for Owner Qualification	2-12
Frames and Forms	2-13
Forms	2-14
Fields on Forms	2-14
Menus	2-17
Menu Environment	2-17
Choosing a Menu Option	2-18
Leaving Submenus and Quitting Ingres	2-19

Keys and Mouse Support2-20

Keys for Menu Operations	2-20
Keys for Standard Functions	2-20
Cursor Movement and Editing Keys	2-21
Mouse Support	2-21
On-Screen Help	2-22
Printing and Redrawing the Screen	2-22
Printing the Screen	2-23
Refreshing the Screen	2-23
Error Messages	2-23
Viewing Error Messages	2-24
Naming and Name Use Conventions	2-24
Schema and User Names	2-24
Conventions for Regular Identifiers	2-25
Delimited Identifiers	2-26
Chapter 2: Using the Tables Utility	
Chapter 3: Using the Tables Utility	
Before Using the Tables Utility	
Tables	3-2
Synonyms	3-2
Views	3-2
Indexes	3-3
Starting the Tables Utility	
Creating Tables	
Table Names	
Column Names	3-7
Data Types	3-7
Key Numbers	3-8
Nulls	3-8
Defaults	
Setting Unique Keys	
Moving Column Specifications	
Cloning Table Specifications with GetTableDef	
Destroying Tables, Synonyms, Views, and Indexes	3-13
Getting Information about Tables and Views	
Adding or Deleting Columns in an Existing Table	3-16
Chapter 4: Using QBF	
Before Starting QBF	<i>1</i> 2
Query Definition Phase	
246 y 26111111011 1 11436	

Query Execution Phase	
Starting QBF	4-3
Starting QBF from the Operating System	4-3
Starting QBF from the Ingres Menu	4-3
Choosing a Query Target	
Using Catalog Frames for Query Target Selection	4-5
Data Display Forms for Query Targets	
Executing a Query	4-8
Displaying and Saving Query Results	4-10
Chapter 5: Working with QBF Operation	ons
QBF Append Operation	5-1
Starting the Append Operation	
Using the Append Frame	
Exiting the Operation	5-4
QBF Retrieve Operation	5-5
Starting the Retrieve Operation	5-5
Using the Retrieve Frame	5-6
Qualifying Retrievals	5-7
Sorting Query Results	5-17
Viewing Retrieved Records	5-20
Transaction Deadlock in Retrieve Mode	5-24
Exiting the Retrieve	5-24
QBF Update Operation	5-24
Starting the Update Operation	
Modifying Data	
Deleting Data	
Saving Updates	
Exiting the Update Operation	5-30
Chapter 6: Using JoinDefs in QBF	
What Is a JointDef?	
JoinDef Rules	
Join Columns with Coercible Data Types	6-4
Multiple Join Columns	
Join Types	
Master/Master JoinDefs	
Master/Detail JoinDefs	6-8
Automatic Joins	

Fields on a JoinDef Form	6-9
Creating a JoinDef	6-10
Optional JoinDef Specifications	6-12
JoinDefs Catalog Frame	6-13
JoinDef Definition Frame	6-14
JoinDef Name	6-15
Role	6-15
Table Name	6-16
Owner	6-16
Abbreviation	6-16
Choosing Table-Field Format	6-16
Specifying Join Columns	6-17
Viewing or Changing Joined Columns	6-19
Getting Information on Table Column Data Types	6-20
Finishing with the JoinDef Join Specification Frame	6-20
Single-Table JoinDefs	6-20
Update and Delete Rules	6-22
Default Update and Delete Rules	6-23
Determining Update Rules	6-23
Determining Delete Rules	6-24
Exiting the JoinDef Update and Delete Rules Frame	6-24
Changing the Display of JoinDefs	6-24
Deleting Fields from JoinDef Displays	6-26
Exiting the JoinDef Change Display Frame	6-26
Testing JoinDefs	6-26
Saving JoinDefs	6-27
Editing JoinDefs	6-28
Deleting JoinDefs	6-28
Chapter 7: Using RBF	
RBF Frames and Operations	7-2
Starting RBF	
Starting RBF from the Operating System	7-3
Starting RBF from the Ingres Menu	7-3
Obtaining Information About a Report Specification	7-5
Using RBF Pop-Up Frames	7-6
Preview Reports	7-6
Report Specifications	7-7
Sources of Report Data	7-7
Sort Columns and Breaks	7-8
Date, Time, and Page Number	7-9

Report Styles	
Tabular	7-10
Wrap	7-12
Block	7-12
Indented	7-13
Master/Detail	7-13
Labels	7-14
Report Structure	7-15
Chapter 8: Working with RBF Report Specificat	tions
Creating a Default Report Specification	8-1
Using the ChooseColumns Operation	8-4
Choosing a Report Style	
RBF Report Layout Frame	8-6
Getting to the Report Layout Frame	8-7
Layout Frame and Report Components	8-7
Creating New Report Components	8-11
Creating Break Headers, Footers, and Other Report Sections	8-12
Creating Trim	8-14
Creating a Column	8-14
Aggregates	8-16
Creating Additional Heading Lines	8-19
Creating Blank Lines	
Deleting Report Components	8-20
Deleting Break Headers, Footers, and Other Report Sections	
Deleting Other Report Components	
Editing Report Components	8-22
Editing Trim and Headings	
Editing Columns	
Editing Column Display Formats	
Representation of Display Formats	
Changing Display Formats	
Editing Column Sort and Selection Options	
Defining Sort Order	
Specifying Runtime Data Selection	
Editing Column Break Options	
Options for Showing a Change of Value	
Using the Break Options Operation	
Moving Report Components	
Moving Trim, Columns, Aggregates, and Headings	
Moving the Report Margins	8-35

	8-36
Page Length	8-37
Underlining	8-38
Page Header on First Page	8-38
Display of Null Values	8-38
Form Feeds	8-39
Date, Time, and Page Components	8-39
Obtaining the Name of a Column	8-41
Undoing Edits	8-41
Saving a Report Specification	8-42
Save Report Frame	8-42
Using the Save Operation	8-45
Save Report Pop-up	8-45
Archiving a Report Definition	8-46
Using the Archive Operation	8-46
Comment Blocks in Archived Reports	8-47
Copying Report Specifications	8-48
Deleting a Report Specification	8-49
Chapter 9: Producing a RBF Report	
Report Destinations	
Background Mode	
Report Log	
Specifying Report Variables	
Producing a Preview Report	
Producing a Report from a Report Specification	
Sending a Report to and from a Screen	9-5
Sending Reports from a Screen to a File	9-7
Sending Reports from a Screen to a Printer	9-7 9-8
Sending a Report Directly to a File	
Sending Reports from a Screen to a Printer	
Sending a Report Directly to a File	
Sending Reports from a Screen to a Printer	9-7 9-8 9-9
Sending Reports from a Screen to a Printer Sending a Report Directly to a File Sending a Report Directly to a Printer Chapter 10: Using Report-Writer	9-79-89-99-10
Sending Reports from a Screen to a Printer Sending a Report Directly to a File Sending a Report Directly to a Printer Chapter 10: Using Report-Writer What Is Report-Writer?	9-79-89-99-1010-1
Sending Reports from a Screen to a Printer Sending a Report Directly to a File Sending a Report Directly to a Printer Chapter 10: Using Report-Writer What Is Report-Writer? Report-Writer and RBF	9-79-89-99-1010-110-2
Sending Reports from a Screen to a Printer Sending a Report Directly to a File Sending a Report Directly to a Printer Chapter 10: Using Report-Writer What Is Report-Writer? Report-Writer and RBF Before Starting Report-Writer	

Headers and Footers	
Detail Section	
Producing a Report	
Creating a Specification	
Saving the Report Specification	
Executing the Report Specification	
Specifying Report Specifications	
Types of Report Specification Statements	
Format of Report Specification Statements	
Summary of Report-Writer Specifications	
Setting Up and Formatting a Report	
Creating Reports with Variables	
Creating Reports Using Several Tables	
Specifying Sorts and Breaks	
Pagination in Reports	
Setting Report Margins	
Positioning, Formatting, and Printing Data	
Using Conditional and Assignment Statements	
Calculating and Printing Summary Data	
Automatic Determination of Default Settings	
Character 11. Decreed Weller France of the control of	a man and a
Chapter 11: Report-Writer Expressions and I	
ANSI/ISO Entry SQL-92 Compliant Databases	11-2
ANSI/ISO Entry SQL-92 Compliant Databases	11-2 11-2
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers	11-2 11-2 11-3
ANSI/ISO Entry SQL-92 Compliant Databases	11-2 11-2 11-3
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words Types of Data in Expressions	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words Types of Data in Expressions String Constants	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words Types of Data in Expressions String Constants Hexadecimal Strings	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words Types of Data in Expressions String Constants Hexadecimal Strings Numeric Constants	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words Types of Data in Expressions String Constants Hexadecimal Strings Numeric Constants Date Constants	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words Types of Data in Expressions String Constants Hexadecimal Strings Numeric Constants Date Constants Columns	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words Types of Data in Expressions String Constants Hexadecimal Strings Numeric Constants Date Constants Columns Variables	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words Types of Data in Expressions String Constants Hexadecimal Strings Numeric Constants Date Constants Columns Variables Special Report Variables	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants Reserved Words Types of Data in Expressions String Constants Hexadecimal Strings Numeric Constants Date Constants Columns Variables Special Report Variables Aggregates	
ANSI/ISO Entry SQL-92 Compliant Databases Delimited Identifiers Using Delimited Identifiers Specifying Delimited Identifiers Precedence over String Constants. Reserved Words Types of Data in Expressions String Constants Hexadecimal Strings Numeric Constants Date Constants Columns Variables Special Report Variables Aggregates Operations	

	Pattern Matching with Wild Cards	11-22
	Logical Operators	11-24
	Built-in Functions	11-24
	Boolean Functions	11-26
For	rmat Specifications	11-26
	Default Formats	11-28
	Blanking Format B	11-31
	Character String Format C	11-31
	Date Format D	11-34
	Numeric Format E	11-38
	Numeric Format F	11-39
	Numeric Format G	11-40
	Numeric Format I	11-41
	Numeric Format N	11-42
	Numeric Templates	11-43
	Control Character Format Q0	11-46
	Character String Format T	11-47
Ex	pressions and Formats Syntax Summary	11-48
	Special Report Variables	11-49
	Arithmetic Operators	11-49
	SQL Conversion Functions	11-49
	QUEL Conversion Functions	11-50
	Numeric Functions	11-50
	SQL and QUEL String Functions	11-50
	Date Functions	11-51
	Boolean Function	11-51
	Aggregates	11-51
	Formats	11-51
C	hapter 12: Report-Writer Statements	
		10 1
FOI	rmat of Report Specification Statements	
	Statement and Parameter Delimiters	
T		
	pes of Report Specification Statements	
Re	port Setup Statements	
	Break	
	.Cleanup	
	Comments	
	.Data	
	.Declare	
	.Delimid	12-15

.Delimid with QUEL Query	12-16
.Include	12-17
.Longremark/.Endremark	12-18
.Name	12-19
.Output	12-20
.Query	12-21
.Query for QUEL Users	12-26
.Setup	12-30
.Shortremark	12-33
.Sort	12-34
Page Layout and Control Statements	12-36
.Formfeeds/.Noformfeeds	12-37
.Leftmargin	12-38
.Need	12-39
.Newpage	12-40
.Nofirstff	12-42
.Pagelength	12-42
.Pagewidth	12-44
.Rightmargin	12-45
Report Structure Statements	12-46
.Detail	12-46
.Footer	12-47
.Header	12-48
Column and Block Statements	12-50
.Block/.Endblock	12-51
.Bottom	12-53
.Format	12-53
.Position	12-55
.Tforma	12-57
.Top	12-59
.Width	12-60
.Within/.Endwithin	12-62
Text Positioning Statements	12-65
.Center	12-66
.Left	12-68
.Lineend	12-70
.Linestart	12-71
.Newline	12-71
.Right	12-73
.Tab	12-75
Print Statements	12-77
.Nullstring	12-78
Print and Println	

.Ulcharacter	
.Underline and .Nounderline	
Conditional and Assignment Statements	
.lf	
.Let	
Statements Syntax Summary	
Chapter 13: Using VIFRED	
VIFRED Frames and Operations	
Starting VIFRED	
Starting VIFRED from the Operating System	
Starting VIFRED from the Ingres Menu	
Starting VIFRED in Expert Mode	
VIFRED Forms Catalog Frame	
Creating New and Duplicate Forms	
Duplicating Forms	
Creating Blank Forms	
Creating Default Forms	
Creating Forms that Use Multiple Tables	
Form Layout Frame	
Alignment Guides	
Layout Frame Menu Options	
Specifying a Form's Display Attributes	
Choosing a Form's Display Style	
Fullscreen	
Pop-up	
Changing a Form's Style	
Specifying Borders for Pop-up Forms	
Setting Form Size and Position	
Setting Size and Position Attributes	
Moving the Margins of a Form	
Visually Adjusting a Form	
Saving Forms	
Save Submenu	
Save Changes Pop-up	
Destroying Forms	
Editing Existing Forms	
Renaming Forms	
Compiling Forms	
Printing Forms	
QBFNames Operation	

QBFNames Catalog Frame	13-29
Assigning Additional QBFNames to Forms	13-30
Running QBF from VIFRED	13-31
Exiting VIFRED	13-31
Chapter 14: VIFRED Form Components	
Parts of a Form	14-1
Fields	14-1
Using Operations on the Form Layout Frame	14-3
Create Operation	14-4
Creating and Editing Trim	
Creating New Blank Lines on the Form	
Creating and Editing Boxes and Lines	
Creating and Editing Simple Fields	
Creating and Editing Table Fields	
Creating Duplicate Fields	
Deleting Form Components	
Changing the Tabbing Order of Fields on a Form	
Moving Components on a Form	
Moving a Single Component	
Moving a Group of Components at Once	14-32
Chapter 15: VIFRED Field Specifications	
Specifying Field Attributes	15 1
Default Attributes	
Setting Attributes for a Field or Column	
Attributes in the Set List	
An Alternative to the BoxField Attribute	
Setting the Invisible Attribute	
Turning Input Masking On or Off	
Required and Other Attributes	
Changing the Internal Name of a Field	
Changing a Field's Data Type	
Setting Nullable Data Types	
Changing the Color	
Scrollable Fields	
Setting Default Values for a Field	15-10
Specifying a Validation Check	15-11
Comparison Operator Validation Checks	15-12

3	
Derived Fields	
Using Forms with Derived Fields	
Specifying a Derived Field	
Guidelines for Specifying Derivation Formulas	
Improving Performance of Derived Fields	
Chapter 14: Interactive Query Language	Torminal Manitar
Chapter 16: Interactive Query Language	
Capabilities of the Interactive Terminal Monitor	
Starting the Interactive Terminal Monitor	
Entering Query Language Statements	
Menu Operations	
Reading from and Writing to a File	
Executing Query Language Statements	
Printing or Filing Output	
Error Messages	
	the Forms-based
Chapter 17: Using System Commands for Tools Syntax Conventions	
	17-1
Tools Syntax Conventions	
Tools Syntax Conventions	
Tools Syntax Conventions	
Tools Syntax Conventions	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform	17-1 17-2 17-2 17-4 17-4 17-5 17-6
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform Syntax Description Example Example Copyform Syntax Description Examples	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform Syntax Description Description Description	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform Syntax Description Examples Copyrep Syntax	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform Syntax Description Examples Copyrep Syntax Description Examples	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform Syntax Description Examples Copyrep Syntax Description Examples Copyrep Syntax Description Example Example	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform Syntax Description Examples Copyrep Syntax Description Examples Copyrep Syntax Description Example Delobj	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform Syntax Description Examples Copyrep Syntax Description Examples Copyrep Syntax Description Example Syntax Description Example Syntax Description Example Syntax Description Example	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform Syntax Description Examples Copyrep Syntax Description Examples Copyrep Syntax Description Example Delobj Syntax Description Example Delobj Syntax Description	
Tools Syntax Conventions Report-Writer Command Syntax Standard Flags and Parameters Compform Syntax Description Example Copyform Syntax Description Examples Copyrep Syntax Description Examples Copyrep Syntax Description Example Syntax Description Example Syntax Description Example Syntax Description Example	17-1 17-2 17-2 17-4 17-4 17-5 17-6 17-6 17-7 17-7 17-10 17-10 17-12 17-12 17-12 17-13

Syntax	17-15
Description	17-15
Examples	17-15
Iquel	17-16
Syntax	17-16
Description	17-16
Isql	17-16
Syntax	17-16
Description	17-17
Examples	17-19
Printform	17-19
Syntax	17-19
Description	17-20
Example	17-20
Qbf	17-20
Syntax	17-20
Description	17-21
Examples	17-22
Query	17-23
Syntax	17-23
Description	17-23
Examples	17-23
Rbf	17-24
Syntax	17-24
Examples	
Report	17-27
Syntax	
Description	
Examples	
Passing Parameters on the Command Line	
Sending Reports to and from a Screen	
Sreport	17-48
Vifred	17-50
Charatar 10: Warling with Bata Tonge and Bata Bi	and an a
Chapter 18: Working with Data Types and Data Dis	spiay
Formats	
Data Types	18-1
Character	
Date	
Floating Point	
Decimal	
200	

Integer	
Money	
Nulls	
Data Display and Input Formats	18-9
Data Types and Display Formats	18-9
Display Format Syntax	
Default Data Display Formats	
Displaying Character Data	
Displaying Numeric and Money Data	
Displaying Date Data	
Using Format Templates	
Numeric Templates	
Input Masking with Numeric Templates	
Special Numeric Template Characters	
Numeric Template Examples	
Date and Time Templates	
Absolute Date and Time Templates	
Time Interval Templates	
String Input Templates	
Creating a String Template	
Forcing Mandatory Entry	
Examples of User-Defined Character Sets	
Examples of String Templates	
Appendix A: Defining Your Terminal	
The Termcap File	Α-1
How to Define Your Terminal	
Defining Your Terminal: Windows	
Defining Your Terminal: UNIX	
Defining Your Terminal: VMS	
Terminal Names	
Tommul Names	
Appendix B: Defining Function and Con	trol Keys
Key Mapping Overview (PC Environment)	B-1
Termcap File	B-2
FRS Mapping File	B-4
Mapping File Example	B-5
Standard FRS Mapping Files	B-6
Application Mapping Files	B-10

Key Mapping Overview (UNIX and VMS Environments)	B-11
Role of the Termcap File	B-12
Mapping Files	B-13
Mapping File Example	B-14
Levels of Mapping	B-16
Obtaining Information on Mappings	B-23
FRS Mapping Objects	B-24
FRS Commands	B-24
Menu Items	B-27
FRS Keys	B-29
Mapping File Syntax	B-31
Mapping Statements	B-32
Disabling Statements	B-35
Comments	B-36
Mapping File Errors	B-36
Troubleshooting (PC Environment)	B-36
Restrictions and Limitations	
Troubleshooting Checklist	B-37
Troubleshooting (UNIX and VMS Environments)	
Restrictions and Limitations	
Troubleshooting Checklist	B-40
Appendix C: Writing Termcap Descriptions	0.1
Modifying the Termcap File	
Modifying the Termcap File Setting the II_TERMCAP_FILE Variable Format of a Termcap Description Writing New Termcap Descriptions Eleven Basic Commands Cursor Motion Command	
Modifying the Termcap File	
Modifying the Termcap File Setting the II_TERMCAP_FILE Variable Format of a Termcap Description Writing New Termcap Descriptions Eleven Basic Commands Cursor Motion Command Commands for Advanced Features (PC Environment) Commands Used to Program Video Attributes	
Modifying the Termcap File Setting the II_TERMCAP_FILE Variable Format of a Termcap Description Writing New Termcap Descriptions Eleven Basic Commands Cursor Motion Command Commands for Advanced Features (PC Environment) Commands Used to Program Video Attributes Commands Used for Color	
Modifying the Termcap File Setting the II_TERMCAP_FILE Variable Format of a Termcap Description Writing New Termcap Descriptions Eleven Basic Commands Cursor Motion Command Commands for Advanced Features (PC Environment) Commands Used to Program Video Attributes Commands Used for Color Specifying Fonts	
Modifying the Termcap File Setting the II_TERMCAP_FILE Variable Format of a Termcap Description Writing New Termcap Descriptions Eleven Basic Commands Cursor Motion Command Commands for Advanced Features (PC Environment) Commands Used to Program Video Attributes Commands Used for Color Specifying Fonts Commands for Advanced Features (UNIX and VMS Environment)	
Modifying the Termcap File Setting the II_TERMCAP_FILE Variable Format of a Termcap Description Writing New Termcap Descriptions Eleven Basic Commands Cursor Motion Command Commands for Advanced Features (PC Environment) Commands Used to Program Video Attributes Commands Used for Color Specifying Fonts Commands Of Advanced Features (UNIX and VMS Environment) Commands Used to Program Video Attributes	
Modifying the Termcap File Setting the II_TERMCAP_FILE Variable Format of a Termcap Description Writing New Termcap Descriptions Eleven Basic Commands Cursor Motion Command Commands for Advanced Features (PC Environment) Commands Used to Program Video Attributes Commands Used for Color Specifying Fonts Commands for Advanced Features (UNIX and VMS Environment) Commands Used to Program Video Attributes Commands Needed for Boxing Characters	
Modifying the Termcap File . Setting the II_TERMCAP_FILE Variable . Format of a Termcap Description . Writing New Termcap Descriptions . Eleven Basic Commands . Cursor Motion Command . Commands for Advanced Features (PC Environment) . Commands Used to Program Video Attributes . Commands Used for Color . Specifying Fonts . Commands for Advanced Features (UNIX and VMS Environment) . Commands Used to Program Video Attributes . Commands Used to Program Video Attributes . Commands Needed for Boxing Characters . Commands Needed for Function Keys .	
Modifying the Termcap File . Setting the II_TERMCAP_FILE Variable . Format of a Termcap Description . Writing New Termcap Descriptions . Eleven Basic Commands . Cursor Motion Command . Commands for Advanced Features (PC Environment) . Commands Used to Program Video Attributes . Commands Used for Color . Specifying Fonts . Commands for Advanced Features (UNIX and VMS Environment) . Commands Used to Program Video Attributes . Commands Needed for Boxing Characters . Commands Needed for Function Keys . Commands Needed for Arrow Keys .	
Modifying the Termcap File . Setting the II_TERMCAP_FILE Variable . Format of a Termcap Description . Writing New Termcap Descriptions . Eleven Basic Commands . Cursor Motion Command . Commands for Advanced Features (PC Environment) . Commands Used to Program Video Attributes . Commands Used for Color . Specifying Fonts . Commands for Advanced Features (UNIX and VMS Environment) . Commands Used to Program Video Attributes . Commands Needed for Boxing Characters . Commands Needed for Function Keys . Commands Needed for Arrow Keys . Commands Used for Color .	
Modifying the Termcap File . Setting the II_TERMCAP_FILE Variable . Format of a Termcap Description . Writing New Termcap Descriptions . Eleven Basic Commands . Cursor Motion Command . Commands for Advanced Features (PC Environment) . Commands Used to Program Video Attributes . Commands Used for Color . Specifying Fonts . Commands for Advanced Features (UNIX and VMS Environment) . Commands Used to Program Video Attributes . Commands Needed for Boxing Characters . Commands Needed for Function Keys . Commands Needed for Arrow Keys .	

Commands to Optimize Cursor Movement	
Commands for Special Situations	
Commands from the UNIX Termcap File	
Examples of Termcap Descriptions	
DEC VT100 (All-Inclusive)	
DEC VT100 (Simple)	C-25
Envision 230	C-25
Concept 100	C-26
Datamedia 3045	C-26
Appendix D: Data Types	
Data Types in SQL, OpenSQL, and QUEL	D-1
A	
Appendix E: Calling Ingres Tools from Er	mbeaded SQL and
OpenSQL	
Call Statement	E-1
Tools and Parameters	E-2
Abf Command	E-2
Ingmenu Command	E-2
Isql Command	E-2
Qbf Command	E-3
Rbf Command	E-3
Report Command	E-4
Sql Command	E-6
Sreport Command	E-6
System Command	E-6
Vifred Command	E-6
Appendix F: Report-Writer Report Examp	oles
Population Example	
Pop2 Example	
Account Example	
Dictionary Example	
Dict2 Example	
Label Example	
Creating Reports Using Several Tables	
Joining Tables for a Report	F-31

Avoiding Awkward Page Breaks	F-35
Appendix G: Troubleshooting Report-V	Vriter
Parameter Substitution	
Queries	
Comments	
Default Print Positions	
Formfeeds	
Performance Problems	
Query Problems	
Conversion Functions	
Memory Usage	

Index

Chapter 1: Introduction

The Character-based Querying and Reporting Tools User Guide describes how to use the following forms-based tools:

- **Tables Utility**
- Query-By-Forms (QBF)
- Report-By-Forms (RBF)
- Visual Forms Editor (VIFRED)
- A terminal monitor (interactive query language facility)
- Report-Writer

The remaining forms-based tools, Application-By-Forms (ABF) and Vision, are discussed in a separate guide, Forms-based Application Development Tools User Guide.

A forms-based tool is a user interface to the Ingres® database management system that uses forms and menus to provide database access and manipulation capabilities.

The following list briefly describes the forms-based tools discussed in this guide:

Forms-Based Tool	Description
Tables Utility	Forms-based utility that allows you to create, modify, or perform other operations on tables in the database.
QBF	Forms-based query tool that allows you to look at, modify, or delete selective data in the database.
RBF	Forms-based reporting tool that allows you to set up report specifications and run reports on the data in the database.
VIFRED	Forms-creation tool that allows you to create and modify forms for use with QBF and customized applications.
A terminal monitor (interactive query language facility)	Query tool that allows you to interact with the database by entering query language instructions on a blank form in the window.

Forms-Based Tool	Description
Report-Writer	Report language tool that allows you to create and run reports without writing an application. You can also use it to enhance reports you created with RBF.

What You Need to Know

This guide is designed for anyone who wants to use a forms-based tool to:

- Create tables, views, and JoinDefs to organize data in the database.
- Look at, update, or create reports on the data in the database.
- Create individual components of a database application, such as a query form or report specification.

To use this guide effectively, you must:

- Have a basic understanding of how Ingres or another database management system works, including the interaction between user interfaces and the database servers.
- Be familiar with the structure of Ingres databases and database tables, as well as the concept of local, remote, and distributed databases.
- Understand the differences between and purpose of Ingres tables, views, and JoinDefs.
- Know how to use the database query language (SQL or QUEL) used at your site to query Ingres databases.

If you are a beginner in database management or if you are unfamiliar with the preceding topics, read the *Database Administrator Guide*.

Special Considerations

Before using this guide or any of the Ingres forms-based tools, you must be aware of the following:

- Enterprise Access Products Compatibility
 - If you are working through an Enterprise Access product, see your Enterprise Access product documentation for information about command syntax that can differ from that described in this guide. Refer also to the *OpenSQL Reference Guide* for query language details.
- Query Languages

Some of the text and examples in this guide pertain only to the SQL query language. For more information on using the forms-based tools with QUEL, see the appendix "Data Types" or the QUEL User Notes section in some chapters.

Conventions

This guide uses the following conventions for consistency and clarity.

Query Languages

The industry standard query language, SQL, is used as the standard query language throughout the body of this guide.

Ingres is compliant with ANSI/ISO Entry SQL-92. In addition, numerous vendor extensions are included. For details about the settings required to operate in compliance with ANSI/ISO Entry SQL-92, see the SQL Reference Guide.

For a description of the QUEL statements available, see the QUEL Reference Guide.

Operating System Differences

This guide provides information that is specific to your operating system, as in these examples:



Information is specific to the UNIX operating system.



Information is specific to the VMS operating system.

The symbol **■** indicates the end of the system-specific text.

If an entire section is system-specific, it is indicated in the section title.

Entering Data from the Keyboard

This guide uses **boldface** text to represent text that you type exactly as shown; for example:

Type **ipm** at the operating system prompt.

The guide uses a distinct typeface to indicate text that appears on your screen, such as the following prompt:

Enter database name:

Terminology

The documentation observes the following distinction in terminology:

- A command is an operation that you execute at the operating system level.
- A *statement* is an operation that you embed within a program or execute interactively from a terminal monitor.

A statement can be written in Ingres 4GL, a host programming language (such as C), a database query language (SQL or QUEL), or in the Report-Writer language (for report specifications).

Syntax

This guide uses the following conventions to describe statement and command syntax specifications:

Convention	Usage
Boldface	Indicates keywords, symbols, or punctuation that you must enter as shown
Italics	Represent a variable name for which you must supply an actual value
[] (brackets)	Indicate an optional item
{ } (braces)	Indicate an optional item that you can repeat as many times as appropriate
(vertical bar)	Used between items in a list to indicate that you must choose one of the items

The following example illustrates the syntax conventions:

create table tablename (columnname format {, columnname format}) [with_clause]

Chapter 2: Fundamentals of Using Querying and Reporting Tools

This chapter provides important information about:

- Setup requirements for using Ingres forms-based tools
- Using Ingres databases with the forms-based tools
- Starting an Ingres forms-based tool
- Specifying the database to access
- Accessing database tables
- Getting around in the Menu system
- Using frames, forms, and fields
- Using menus, keyboard keys, and on-screen help
- Printing and redrawing the screen
- Object naming and name use conventions

Explanations include both keyboard and mouse procedures where appropriate.

Before Starting Ingres

You or the system administrator must install Ingres on your computer before you can use the program.

Enabling Access to the Database

Ingres provides access to data stored locally on your computer, or if you are connected by a network, to data stored remotely on other nodes as well.

Your database always resides on a remote host computer. Access the database through a server installed on the remote host.

To access a database, you must have been given access to it by the database administrator. Additionally, your system must meet the following requirements to enable access to local and remote databases:

For access to a local database, a server must be running on your local node.

- For access to a database on a remote node in your network, Ingres Net must be installed on both the local node and the remote node, and a server must be running on the remote node.
- For access to a non-Ingres database, the Enterprise Access product for that database must be installed. See the installation guide specific to that Enterprise Access product.
- For access to a distributed database, if your system supports it, Ingres Star must be installed.

Check with your system administrator for the status of access to local and remote databases on your system from your terminal. Check with the database administrator for a particular database to determine whether you have permission to access it.

Setting System Variables

The system administrator or the person installing your system sets environment variables or logicals that affect the operation of the program and the way data is handled. For example, one environment variable/logical sets the time zone; another establishes the type of currency symbol to use. These system variables are discussed in the *System Administrator Guide* for the system on which your database resides.

Defining the Terminal

VMS

UNIX

You or the system administrator must define the type of terminal you are using. Normally, the system administrator sets up all such session options and defines your terminal to Ingres. However, if the terminal you are using has not been defined to Ingres, you must do so before you can access your database.

The environment variable/logical, TERM_INGRES, allows you to define to the type of terminal you are using. Depending on your operating system, use one of the following commands:

UNIX

For the C shell:

setenv TERM_INGRES termname

For the Bourne shell:

TERM_INGRES=termname export TERM_INGRES ■

VMS

define TERM_INGRES termname

The termname is the name of the terminal description for your terminal in the termcap file, such as VT100i. For details, see the chapter "Defining Your Terminal."

Mapping Function Keys

Menu operations, cursor movement, and all other operations can be mapped to a particular function or control keys on your keyboard. Once you have specified a mapping, you can invoke the operation by pressing the specified key. For a discussion of key mapping, see the appendix "Defining Function and Control Keys."

About Your Database

Ingres is a relational database management system, which stores data in integrated collections called tables. An Ingres database can consist of any number of tables containing data of a variety of types. In addition to tables, the database contains other objects, such as forms, JoinDefs, reports, and applications you create to manipulate your data, as well as system catalogs that keep track of the objects associated with the database.

For a complete introduction to Ingres database concepts, see the *Database* Administrator Guide.

System Catalogs and the Catalogdb Utility

A system catalog is set up for each database created. The system catalog is a table that holds information about the database as you work with it. These system catalogs make up the data dictionary. System catalogs store specifications for the tables, indexes, forms, reports, and queries associated with a specific database.

You can review the information stored in the system catalogs by using the following statements, operations, or commands:

- Help statement
- Select statement. For more information, see your guery language reference guide.
- Examine operation. For more information, see Getting Information about Tables and Views in the chapter "Using the Tables Utility."
- Catalogdb command

You access the catalogdb utility from the operating system.

You can obtain information about individual databases, lists of the databases you own, and the databases you are authorized to access, and the locations of specific files, such as the checkpoints and journals associated with a database. The catalogdb command is not applicable to Enterprise Access products. For a full explanation of catalogdb, see the Command Reference Guide.

Creating and Maintaining Databases

When you create a database, you become the database administrator (DBA) for that database. The DBA creates an Ingres database with the system-level command createdb. Unless the DBA specifies that a database must be private, all databases created by the DBA are public and accessible to other users. The DBA is responsible for maintaining the database, and only the DBA who created the database can remove (destroy) it. Destroying a database removes all tables and objects associated with that database.

In this environment, the DBA is the person who creates and maintains the database on the remote host computer. The remote host computer is connected to a PC through a network that provides access to the database.

For more information about creating, maintaining, and destroying databases, see the Database Administrator Guide.

Location and Type of Database

The specific locations of your databases vary according to your operating system and to the way Ingres was installed.

To access a database, you must know whether it is:

- An Ingres or non-Ingres database. If it is a non-Ingres database, you must know the server type required to access it.
- Located on a local or remote computer. If located on a remote computer, you must know the name of the remote node.

If you want to know the exact locations of databases, consult the system administrator or other individual in charge of installing Ingres or maintaining the database. For more information on accessing a database, see Specifying Startup Commands.

Copying and Destroying Tables in a Database

If the DBA has granted you the proper permissions, you can copy or destroy tables in a database, whether you are the DBA for that database. To copy a table, use the system-level command, copydb. For more information, see the Database Administrator Guide.

To destroy a table, you can use database query language statements. For more information, see your query language reference guide.

Backing Up and Restoring

Hardware failure or human error can accidentally damage databases or individual tables. An integral logging facility keeps track of all database transactions automatically. One installation-wide logging file keeps track of all Ingres transactions of all users.

All database backup and restore procedures are carried out by the system administrator on the host computer where the database resides. For more information, see the System Administrator Guide. If you are using an Enterprise Access product, see your database documentation for more information.

Starting an Ingres Tool

You can start any Ingres forms-based tool, such as Ingres QBF or the Visual-Forms-Editor, by:

- Starting Ingres Menu and then choosing an operation to start a particular Ingres tool
- Entering a startup command at the system prompt (or in a Run dialog in Windows)

Using Ingres Menu

Ingres Menu is a visually oriented, forms-driven, menu interface that provides access to all Ingres forms-based tools and data. These tools allow you to:

- Manipulate database tables.
- Design, edit, and customize window-based forms.
- Join tables to create a single object to be queried called a JoinDef.
- Format and print reports.
- Create and print graphs.
- Develop and use applications that manage the data.
- Display, add, delete, or modify data in the database.

Accessing an individual tool through the Ingres Menu gives you the ability to switch quickly from one forms-based tool to another, without having to go back to the window manager or operating system command line to do so.

Bypassing Ingres Menu

You can bypass the Ingres Menu by entering a command to start a specific tool from the operating system command line. In this case, the Ingres Menu is not displayed and you are able to access only the particular tool you specified. For details, see Specifying Startup Commands.

If you choose Ingres from an applications menu or load it from a script file, whether you see the Ingres Menu frame depends on how the menu or script has been configured.

Accessing Ingres Menu

To access the Ingres Menu from your operating system command line, issue the following command:

ingmenu dbname|v node::dbname [/server type]

For detailed information about these parameters, see <u>Specifying Startup</u> <u>Commands</u>. For a complete list of the flags and other parameters associated with the ingmenu command, see the chapter "Using System Commands for the Forms-based Tools."


The Ingres Menu is illustrated in the following figure.



The Ingres Menu frame is divided into the following two parts:

- List of the forms-based tools you can access, as described in the table following this discussion
- Menu of operations that enable you to make your selection, get help, end the session, and so forth

The map in the following figure shows each forms-based tool that is accessible from the Ingres Menu main frame. The menu choices you see depend on your authorizations and on your environment.



To view additional menu maps corresponding to each of the main Ingres Menu choices discussed in this guide, see the chapter that introduces the associated tool. The Graphics and Applications menu choices see your graphics software, ABF, and Vision, all of which are discussed in separate guides.

The following table explains each of the main Ingres Menu choices:

Operation	Description
Tables	Provides access to the Tables Utility for adding or manipulating tables in your database.
Forms	Provides access to tools for creating, editing, and using custom or default forms.
JoinDefs	Enables you to run a query on several tables at once using a JoinDef.
r	Enables you to run a report, or create and edit a report specification designed with RBF.
Graphs	Enables you to display or print existing graphs or create new ones. For more information, see the documentation for your graphics software.
Applications	Enables you to access the tools for generating applications: Vision and Applications-By-Forms. For additional information about the application generation tools, consult the <i>Forms-based Application Development Tools User Guide</i> .
Queries	Provides access to the interactive query languages through the Interactive Terminal Monitor and to QBF, a forms-based query system.

To choose one of the Ingres tools listed on the Ingres Menu frame, click on the item with your mouse, or use the cursor control keys to highlight the item you want and choose the Select operation.

Specifying Startup Commands

You can start the Ingres Menu or an Ingres forms-based tool with a startup command entered on the operating system command line. You must specify the database in which you want to work by including its name after the command to start the Ingres Menu or the Ingres tool and before any other non-flag parameters, as follows:

command dbname

For example, to start the Ingres Menu with access to the personnel database, enter the following command:

ingmenu personnel

Depending on the type and location of the database you want to access, you must sometimes specify the server type or location of the database in addition to its name.

The following table defines the situations in which you are required to do so:

Database Type and Location	Command Syntax	Example
Local Ingres database	command dbname	ingmenu admin
Remote Ingres database	command v_node∷dbname	ingmenu ny∷admin
Local non-Ingres database	command dbname/server_type	qbf sales/db2
Remote non-Ingres database	command v_node::dbname/server type	qbf ohio::sales/db2
Local Ingres distributed database	command dbname/ d command dbname/ star	rbf corpdata/star
Remote Ingres distributed database	command v_node∷dbname/ d command v_node∷dbname/ star	rbf ny∷corpdata/d

The following table defines the access parameters you use in the commands to start the Ingres Menu or an Ingres forms-based tool:

Operation	Function
command	Any command used to invoke the Ingres Menu or an Ingres tool.
v_node	Virtual node name of the remote node on which the database is located. The <i>v_node</i> name implies the actual network node address and the network protocol. They are identified when the node name is defined with the netu utility. Two colons (::) must follow <i>v_node</i> .
dbname	Name of the database containing the relevant data. It can be the name of a distributed database.
server_type	Name of the type of server being accessed at the local or remote site, (the default is Ingres, which is the server_type designated for the DBMS Server). Other server types are Star or one of the Enterprise Access products to a non-Ingres database. For specific names, see the database documentation.

The following sections provide a more detailed explanation and examples of the basic command line syntax for each database type. For the complete list of optional flags and parameters for each startup command, see the chapter "Using System Commands for the Forms-based Tools."

Database on Remote Network Node

If the database you want to access is on a remote network node, then you must include the virtual node name (v_node) of the remote node, followed by two colons (::), as follows:

```
command v node::dbname
```

The virtual node name is the name of the computer as registered with Net. For more information about Net, see the networking guide for your system or consult your network administrator.

For example, to start Ingres Menu for the personnel database on the berkeley node, enter:

```
ingmenu berkeley::personnel
```

Non-Ingres Database

If you want to access a non-Ingres database through an Enterprise Access product, you must include the server type for the database, preceded by a slash (/).

If the non-Ingres or distributed database is located on a remote node, you must also include the virtual node name.

```
command dbname| v_node::dbname| server_type
```

For example, to use QBF with an IMS database called sales located on a local node, enter:

```
qbf sales/ims
```

If the sales database resides on the remote node, hq, enter:

```
qbf hq::sales/ims
```

For more information about using tools through an Enterprise Access product and for associated server types, see the documentation for the specific Enterprise Access product.

Distributed Database

For those systems that support Star Server, using a distributed database requires that you specify the server type. The server type for a distributed database is /d or /star.

To start the Ingres Menu with a distributed database called corpdata, enter either of the following commands:

ingmenu corpdata/d ingmenu corpdata/star

If the database is on the remote oakland node, enter:

ingmenu oakland::corpdata/d ingmenu oakland::corpdata/star

For more information about distributed databases, see the *Database* Administrator Guide.

Accessing Database Tables

You can access a table, view, or synonym in the forms-based tools only if one of the following is true:

- You are the object's owner
- You have been granted the proper permission to access the object

Access to a view automatically provides access to the columns in the underlying table that are defined in the view. The DBA or owner of a table can grant different types of access to a table, called *privileges*. These privileges are:

- Select
- Insert
- Delete
- Update
- Reference

For specific instructions on obtaining or granting access to database tables, see the Database Administrator Guide for the system on which your database resides.

Select a table, view, or synonym by:

Typing its name on the command line when entering an appropriate command

- Typing its name in a table name field on the current frame
- Highlighting it in a displayed list of choices and choosing the appropriate operation

Each table, view, or synonym, also has a schema name that associates the object with the user who owns it and distinguishes it from identically named objects in different schemata. Lists of choices in the forms-based tools contain all tables and views, including their schema names, to which you have access, whether owned by you, the DBA, or another user. These lists also contain all synonyms that you own or that are owned by the DBA, to which you have access. For more information on synonyms, see <u>Using Synonyms</u>. For more information on schemas, see <u>Using Schemas for Owner Qualification</u>.

Using Synonyms

A *synonym* is a definable label for a table name. You can use an existing synonym, whether yours or someone else's, to refer to a table when the actual table name is subject to frequent or occasional change. Synonyms also provide a shorter way to reference a long table name. Your entry is interpreted as the table name currently defined by the synonym you entered.

Access to the underlying table implies access to its synonyms. In lists of available choices, the Ingres forms-based tools display only the synonyms that you own and those owned by the DBA to which you have access. Synonyms owned by other users are not displayed.

To view a list of any other synonyms, you can enter the following SQL statement from the Interactive Terminal Monitor:

help synonym *

If you want to use a synonym that belongs to another user, include its schema name in the table name entry field. For more information on owner qualification, see <u>Using Schemas for Owner Qualification</u>.

Although you can use existing synonyms in your database, you cannot define them with an Ingres forms-based tool.

Using Schemas for Owner Qualification

A *schema* is a collection of database objects, such as tables. Each table, view, and synonym belongs to a schema that is determined when the object is created. The schema name corresponds to the user who owns the object. The schema name helps distinguish between objects with identical names and different owners.

Schema names appear in the Owner column of table selection lists. You can also specify a schema name for a table, view, or synonym on the command line or in a table name entry field to qualify the object name with its owner. You use the following syntax to specify ownership:

schema.objectname

For example, to access the table named empinfo having a schema name of dave, you would enter the table name as:

dave.empinfo

The period (.) must immediately follow the schema name and precede the object name, with no intervening spaces. Both the schema name and the object name can be delimited identifiers.

If you do not use a schema name when referencing a table, view, or synonym, Ingres looks first for an object with a schema corresponding to the current user; then it looks for an object owned by the DBA to which you have access. Lastly, if the object name begins with ii, Ingres looks for a system catalog with that name. For more information on schemas, see the *Database Administrator Guide*.

Frames and Forms

A frame is a form with associated program code that defines the available menu items. A frame contains the following parts:

- Window for displaying a form for data entry or data display
- Menu area for appropriate menu options
- Area for displaying program and error messages

Depending on the Ingres tool you are using and the menu operation you have chosen, a form appears in the frame's window with menu choices in the menu area that are appropriate for that particular task.

The menu displays the operations available on the form in the current frame. For more information on menus, see <u>Menus</u>.

EMP Table

Name: Applegate, Donald
Hourly Rate: \$51.00

TASKS TABLE:

Project Task Hours
Advertise Test 8
Graphic Design 16
TextProc Design 10
TextProc Implement 10

NextMaster(F9) Query(SH-F2) Help(F1) End(F10)

The following figure illustrates a typical frame.

Forms

A *form* is the electronic equivalent of a paper form. The Ingres forms-based tools display ready-made *forms* in a frame. These forms can contain data fields in which you view or enter data.

Forms consist of trim and fields.

- *Trim* is independent of the data input and output functions of the form. It can be text that provides helpful information or box graphics that provide a decorative border.
- A *field* on a form displays data and/or accepts data entry. A field generally corresponds with a value from a table.

Fields on Forms


Two types of fields appear on forms:

- Simple fields
- Table fields

A simple field displays data or accept data input one item at a time. The following figure displays a form with six simple fields.

```
| PROJECTS Table | Project: Advertise | Description: Advertising Analysis | Dept: Sales | Due Date: $9500.00 | Due Date: $02-mar-1999 | Due Date:
```

A *table field*, as shown in the following figure, displays several rows and columns of data at a time.



You can include simple fields and a table field on the same form. A table field can have more rows than can be displayed at one time. Use the arrow keys or the Scrollup and Scrolldown keys to display more rows.

If the form itself is larger than the window, tabbing to a field or column automatically brings that portion of the form into view. You can also use the Scrollleft and Scrollright keys to move around a large form, or the Scrollup and Scrolldown keys to display a simple field that is beyond the top or bottom of your window.

Each field on a form consists of a data window, attributes, internal name, and an optional title:


■ The data window is the area in which data is displayed or entered.

- Attributes affect the way data is displayed in a field and the way a user can work with a form. Some attributes control the *look* of the data. For example, you can use video highlight on the data in the data window. Other attributes control such things as the error message a user sees if the wrong value is entered into a field.
- The *internal name* identifies the field and can be linked to the column in the database table from which the field receives its data, or to which it writes data. An application accesses the field by using the internal name. The internal name is not visible on the form. For more information on internal names, see the chapter "VIFRED Form Components."
- The *title* describes the data that appears in a field. The title is optional and need not correspond to the name of a column in a database table.

The following figure illustrates the title and data window of a simple field.



The following figure identifies the same components on a table field.



For more information on forms, see the chapters "Using VIFRED," "VIFRED Form Components" and "VIFRED Field Specifications."

Menus

Menu operations are displayed at the bottom of each frame. To access the menu using your keyboard, press the Menu key (the key that is mapped to the menu operation in your key mapping file). The cursor moves to the first menu operation.

The key on your keyboard that acts as the Menu key depends on your keyboard type and the individual key mappings you have chosen. On a VT100i keyboard, it is usually mapped to the PF1 key by default. In some cases, it can be mapped to the Escape or F1 key. On a PC keyboard, it is usually mapped to the Escape or F2 key by default. For more information on standard key assignments, see Keys and Mouse Support. For more information on key mapping, see the appendix "Defining Function and Control Keys."

Your menu's appearance and the method used to display additional menu options depend on your particular environment and whether you are using a mouse or your keyboard. The following sections contain information about menus and choosing menu options.

Menu Environment

The menu appears at the bottom of the window and looks similar to this one: Create(1) Destroy(2) Examine(3) Query(4) Report(5) >

Some menus are longer than the width of the frame. The presence of additional menu items is indicated by either a greater than sign (>) at the right end of the menu, a less than sign (<) at the left end, or both. If you are using a mouse, click anywhere on the menu or click on the > or < signs to view additional menu options.

If you are using your keyboard, press the Menu key to access the menu; then press the Menu key repeatedly to cycle through the menu options.

To return to the forms window, click on the window or press the Return key.

Using Menus with a Mouse

If your system displays classic menus and you are using a mouse, click the right mouse button (or right-click) from anywhere in the frame to access the menu; then right-click the right repeatedly to cycle through the menu options.

If you are using your keyboard, press the Menu key to access the menu; then press the Menu key repeatedly to cycle through the menu options.

To return to the forms window, click on the window or press the Enter key.

Choosing a Menu Option

Choose a menu option using one of these methods:

- Click on the operation with the mouse, if installed.
- Press a function key associated with the operation.
- Access the menu with the Menu key and type the capitalized or first few letters of the operation.

Using the Mouse

If you are using a mouse, you can choose a menu operation by moving the mouse pointer to the operation and clicking on it with the appropriate mouse button.

Using a Function Key

Generally, a menu operation has a function key (or key combination) mapped to it. In most environments, the associated key appears in parentheses following the operation on the menu line.

Windows

In a Windows environment, the function key associated with the currently highlighted menu item appears on the bottom line of your window. You can also display a definition list of Ingres function keys by pressing F1 or clicking on the Help operation with the mouse and then choosing the Keys operation.

М

You can choose the menu operation by pressing its associated function key, regardless of the cursor location. This invokes the operation immediately. You do not have to press Return. For example, if Quit(PF4) appears on the menu line (or if PF4 is associated with Quit in a Help window), you press the PF4 key to invoke the Quit operation. If ^F is shown as the associated key, hold down the Control key and press the F key.

Typing or Highlighting the Operation Name

If your keyboard mapping does not correspond to the key designations on the menu, or if for some other reason the function keys do not work, you can use the following alternative keyboard procedure to choose an operation from the menu:

- 1. Move the cursor to the menu by pressing the Menu key.
- 2. Do one of the following:

Windows

Type as many letters as necessary to make the operation name unique. For example, if both the End and Edit operations appear on a menu, you must type ed to use the Edit operation or en to use the End operation.

In a Windows environment, press the arrow keys or Space Bar to move the Input focus bar to your selection, or type the capitalized letter of the desired operation. For example, type C for the Create operation.

3. Press Return.

Operation	Function
Blank	Clears the window of all entries
Cancel	Returns to a previous window without saving changes entered in current window
End	Ends operations in current window and returns to previous window
Go	Follows the specified request
Help	Displays Help windows relevant to the current action
Insert	Puts a blank line at the cursor location
ListChoices	Lists the available choices for the selected field
Undo	Undoes or cancels the previous operation
Quit	Exits module, either to the Ingres Menu or to the operating system

Leaving Submenus and Quitting Ingres

When you choose an operation from a menu, you are often presented with a submenu of operations on a pop-up form. An operation chosen from that submenu can in turn present another pop-up form with a further set of operations.

When you leave a submenu with the End operation, you always return to the next higher-level menu.

When you leave a submenu with the Quit operation, you return to the Ingres Menu or to the operating system or Windows program(depending on how you entered the application or Ingres forms-based tool). When you quit from the main menu, you quit Ingres and return to the operating system or Windows program.

Keys and Mouse Support

Through the use of key mapping, you can attain a high degree of flexibility in your keyboard interaction with Ingres. The way the different keys on your keyboard function depends on your keyboard and the specific changes you have made to your key-mapping file. Application developers can also re-map function keys for use in their applications. For more information on key mapping, see the appendix "Defining Function and Control Keys."

You can view the current mappings for your keyboard by choosing the Keys operation on the Help menu.

Keys for Menu Operations

Menu choices on frames are generally associated with keyboard keys or key combinations, such as Control-E or F1 that you can press to activate the menu choice. These key assignments assume you are using a keyboard that corresponds to your key-mapping file. The key assignment generally appears in parentheses after each menu option on the menu line. If not displayed on the menu line, you can use the Help operation to display current key assignments.

Keys for Standard Functions

By default, certain functions, such as access the menu, get help, move cursor to next field, or move cursor to previous field, have been assigned to specific keys that operate consistently on any frame. Your key mapping files determines the exact key you press. The following table lists some of the default function keys that are common to all of the Ingres forms-based tools:

Function or Menu Operation	MS Windows Keyboard	VT100i Keyboard
Go to Menu	Esc or F2	PF1
Get help	F1	PF2 (or sometimes Escape or F1)
Move cursor to next field and clear it of data	Enter	Return
Move cursor to next field and retain its data	Tab	Tab
Move cursor to previous field for editing	Shift+Tab	Control-P

Function or Menu Operation	MS Windows Keyboard	VT100i Keyboard
End operation	F2 or F10	PF3
Quit operation	F6	PF4

The Tab, Return, and Enter keys move the cursor to the next field, but in different ways:

- Tab moves the cursor to the next field or next column in a table field, without clearing the contents of the field. If the cursor is in the last field, Tab moves the cursor to the first field of the same form.
- Return (or Enter) moves the cursor to the next field and clears data to the end of that field at the same time, unless it is a read-only form or table field. In a table field, this key moves the cursor to the next column. If the cursor is in the last column, it moves the cursor to the first column of the next row.

If you do not want the Return (or Enter) key to clear the data to the end of the field, you can map this key so that it works like the Tab key.

This guide refers to the Enter key as the Return key.

Cursor Movement and Editing Keys

Keys that facilitate moving the cursor within forms are both system and keyboard-dependent. The keys that normally control cursor movement on your keyboard can usually be used to control scrolling and other movements of the cursor in a form.

You can edit text or work in either overstrike or insert mode. In overstrike mode, which is the default, each character you type replaces the existing character beneath it. In insert mode, characters are moved to the right as you enter new characters. The key that controls your editing mode is called the Mode key, and acts as a toggle that enables you to switch modes.

Mouse Support

In addition to using the keyboard keys to move around forms and menus, you can also use a mouse.

On-Screen Help

Context-sensitive help is provided online. This means that the assistance is based on the current task you are attempting to accomplish and the current field you are attempting to complete. Sometimes help is provided on several screens.

You can obtain help by choosing the Help operation from the menu, or you can press the Help key to get help at any time. The Help key is designated in parentheses following the Help operation—if your system displays key assignments on the menu line. The key to which this function is mapped can vary. On a VT100i keyboard, it is usually mapped to the PF2 key by default. On a PC keyboard, it is usually mapped to the F1 key by default. You can also determine your Help key by choosing the Help operation from your menu using another method, and then choosing the Keys operation on the Help submenu.

Help windows for Ingres contain the menu choices shown in the following table:

Operation	Function
Keys	Describes the function, control, and arrow keys and their current definition.
SubTopics	Displays a pop-up with a list of subtopics. For an explanation of a particular subtopic, select it from the pop-up. This option appears only when subtopics are available.
Help	Displays the type of Help available.
End	Exits from any Help window to the previous window.

To make a selection on a Help window, press the key designated in parentheses after the operation, or type the first few unique characters of the operation and press Return. To move through the Help windows, use the cursor movement keys specific to your keyboard. If available for your terminal type, you can also use the key mapped to the string-search (FRS Find) operation to search for a specified text string within a Help window. Use the Help Keys operation to determine which key is mapped to the string-search operation.

Printing and Redrawing the Screen

You can print or redraw the currently displayed screen.

Printing the Screen

Depending on how you have defined your terminal or your keyboard keys, you can print the contents of the currently displayed screen by pressing the designated printscreen key.

You can also set the II_PRINTSCREEN_FILE environment variable/logical to a file name that automatically writes the results of the printscreen function, or to printer to send the screen contents to the line printer. For more information on setting environment variables or logicals, see the *System Administrator Guide*.

To print the current screen

1. Press the key assigned to that function.

On a VT100, press Control-G; on a VT220, press F8; on a PC, press Prtsc. The key assignment can vary from keyboard to keyboard.

If you have set II_PRINTSCREEN_FILE to a specific file or to printer, the screen contents are sent to the file or printer. Otherwise, a prompt appears:

Enter file name:

- 2. Do one of the following:
 - Type the name of a file and press Return to transfer an image of the current form, including all displayed data values, to the specified file. The entire form is included, even though it can be longer and wider than your window.
 - Type printer as the file name and press Return to send the image to the line printer.

Refreshing the Screen

You can also refresh, or *redraw*, the current screen, including any data you have entered into its field. This is useful if you receive messages on the screen or if disruptions in communication with the computer occur. The redrawing function is assigned by default to Control+W, regardless of your terminal or keyboard.

Error Messages

Context-sensitive error messages are provided in pop-up windows that appear at the bottom of your screen. The error message you receive indicates the error type, the error code, and in some cases offers an explanation.

Viewing Error Messages

For messages with explanations, the first line is displayed, along with a prompt offering you a choice of either End or More if the message contains more than one line. To exit the message without reading the explanation, press the End key or click on the word End with your mouse. To read the explanation, press the More key or click on the word More. After reading the explanation, press Return or Enter to return to your work in progress, or click anywhere inside the message box to dismiss the message.

For messages without an explanation, a single-line message is displayed with a prompt that tells you to press Return or Enter after reading the message. This removes the message and returns you to your work in progress. Alternatively, if you are using a mouse, click anywhere inside the message box to remove it and return to your work.

Naming and Name Use Conventions

You can define a wide range of objects, from databases to reports and join definitions. You must follow certain conventions when naming or referencing objects. *Identifiers* are names for objects, such as table names, JoinDef names, column names, QBFNames, and so forth.

There are two types of identifiers:

- Regular identifiers
- Delimited identifiers

Regular identifiers are user and object names that follow standard naming conventions for that database. Delimited identifiers are delimited by double quotes (") and can contain additional characters and words that are disallowed in regular identifiers.

You can use only regular identifiers to name Ingres tools objects, such as JoinDefs, reports, forms, and QBFNames, which you create with QBF, RBF, and VIFRED. You can use either type of identifier to name Ingres database objects, which you create in the Tables Utility or with query language statements.

Schema and User Names

Schema names for objects can be specified as either regular or delimited identifiers, depending on the schema name's compliance with conventions. If a schema name contains characters unacceptable in a regular identifier, such as in Da Vinci or O'Neil, then it must be specified as a delimited identifier in double quotes.

Default schema names are created based on the user ID associated with the database connection. The user ID can be stored in uppercase, lowercase, or mixed case, depending on choices made by the DBA when the database was created. If a user ID is stored in mixed case, any schema name based on that user ID can also be stored in mixed case and must be specified as a delimited identifier, in double quotes, when qualifying an object with an owner name.

Also, you must specify any mixed-case user ID as a delimited identifier when impersonating that user with the -u flag on the command line.

For more information on schema names or on specifying case conventions for user identifiers in a particular database, see the Database Administrator Guide.

Conventions for Regular Identifiers

The following table lists the conventions you must follow when using a regular identifier to specify the name for any object:

Quality	For General Use	For ANSI/ISO Entry SQL-92 Compliant Databases
Size	No more than 32 characters	No more than 18 characters
First character	Must be alphabetic (a-z) or the underscore (_)	Must be alphabetic (a-z)
Other allowable characters	0-9, #,@, and \$ allowed <i>afte</i> r the first character	Only alphabetic, numeric, or underscore characters allowed
Case sensitivity	Case insensitive	Case insensitive

Examples of valid regular identifiers for object names are:

- new_york
- march98
- Quinn (equivalent to quinn or QUINN)
- _geneva\$ (not allowed in databases that comply with ANSI/ISO Entry SQL92 standards)

In addition to the restrictions described above, you must not use reserved words as regular identifiers. For a full list of standard or embedded SQL, OpenSQL, and QUEL reserved words, see your query language reference guide or the Forms-based Application Development Tools User Guide.

Delimited Identifiers

Delimited identifiers are database object names that are identical to reserved words or that contain spaces or non-alphanumeric characters that are disallowed in a regular identifier. If the database was created as case sensitive, you can also use delimited identifiers to distinguish among identical names with different case (for example, SALES as distinct from Sales). For more information on allowable characters in delimited identifiers, see the SQL Reference Guide.

You can use delimited identifiers for names of all database objects, such as:

- Table names
- View names
- Correlation names
- Column names in tables
- Schema and user names

You are not allowed to use delimited identifiers for Ingres tools objects such as JoinDefs, reports, forms, and QBFNames.

Wild Card Characters

In some situations, you can use the SQL wild cards, underscore (_), asterisk (*), or brackets ([]), within delimited identifiers in the forms-based tools. To enter a wild card character as an explicit character, you must dereference it by preceding it with a backslash (\). For more information, see the chapter(s) on the specific forms-based tool or the command descriptions.

Case Sensitivity

When specifying delimited identifiers, follow the rules for case as defined for your database. In standard Ingres databases, delimited identifiers can be either case sensitive or case insensitive, as determined by the DBA when creating the database. By default, standard Ingres databases are case insensitive.

In databases compliant with ANSI/ISO Entry SQL-92 standards, delimited identifiers are case sensitive. The following is an example of a case-sensitive delimited identifier:

"Sales for March"

For more information on setting case for identifiers in Ingres databases, see the *Database Administrator Guide*.

Using Delimited Identifiers in Forms

You must always enclose delimited identifiers within double quotes ("), as shown in the following examples:

As a table, view, or synonym:

```
"dave's table"
```

As a column name:

```
"Stocks & Bonds"
```

■ In Help statement queries in the query language Interactive Terminal Monitor; for example:

```
help table "my table"
```

■ In VIFRED field validations; for example:

```
field name in "table one"."column two"
```

As a correlation name and column name in correlation_name.column_name constructs:

When using owner qualification, for either or both the schema name and/or object name, as follows:

```
"schema 1".table2
dave."Dave's table"
"schema 1"."view table1 & table2"
field_name in "schema 1"."table one"."column two"
```

 On the command line, as a username for the -u flag, groupid parameter for the -G flag, or database object in a command parameter.

```
-u"user 2"
-G"tech sup"
```

Your operating system can require additional delimiting and dereferencing quotes for these parameters and for delimited identifiers on the command line. For details, see the *System Administrator Guide*.

Delimited identifiers are displayed in catalogs and other lists of available choices without their surrounding double quotes, except when displayed for update. You can choose a delimited identifier from one of these lists as you do any other identifier—by moving the cursor to the item and choosing the appropriate operation.

Delimiting quotes and, if present, de-referenced embedded double quotes are shown in pop-up forms and entry fields containing delimited identifiers displayed for update. If you edit a delimited identifier or enter one into a field by manually typing it, you must also include the delimiting double quotes (") and dereference any embedded double quotes by preceding them with another double quote(""):

```
"""expert"" witness"
```

Do not dereference single quotes or apostrophes within delimited identifiers: "dave's table"


For information about specifying delimiting and dereferencing quotes in delimited identifiers on the command line, see the *System Administrator Guide*.

Chapter 3: Using the Tables Utility

The Tables Utility lets you create or destroy tables in a database and inspect their structure. It also provides access to Ingres forms-based tools that allow you to run queries and reports on data contained in the tables. You can perform the same operations offered in the Tables Utility by using database query language commands, which are discussed in your query language reference guide.

This chapter describes how to create, destroy, and examine tables using the Tables Utility, and explains how to enter the column specifications for a new table.

The tables operation is illustrated in the following figure:



Before Using the Tables Utility

Before using the Tables Utility to access any of the following, you must understand how each of them is used and what operations you can perform on them in the Tables Utility:

- Tables
- Synonyms

- Views
- Indexes

Tables

Tables are used to store all the data in your database. Each row in a table holds an individual record that contains one or more related data items. Each column contains one particular type of data. You can use the Tables Utility to create and delete tables, to look at the structure of a table, and to retrieve or modify the data contained in a table.

Except for rows containing large objects (long varchar, byte, byte varying, and long byte data types), all rows in a given table are the same width, measured in bytes, with no row exceeding the lesser of the maximum configured row size and 32,000. The number of rows is limited only by disk space.

Each column is assigned a data type to indicate the type of data to be stored and the length of the data (or width of the column). For example, a column with a data type of varchar (25) can hold 25 text (ASCII) characters. For more information, see Data Types. A maximum of 1024 columns is allowed in a table. Each column has a name that uniquely identifies the column within the table.

You can access any table for which you have been granted the proper permissions. For more information on permissions, see the *Database Administrator Guide*.

Synonyms

A synonym is a redefinable label for a table, which you can use as an alternative to the actual table name. You can access a table with an existing synonym, but you cannot create synonyms in the Tables Utility. The list of tables from which you can choose contains only synonyms you or the DBA own, freely intermixed with table names. For more information on synonyms, see Accessing Database Tables in the chapter "Fundamentals of Using Querying and Reporting Tools."

Views

A view is actually a special definition, or virtual table, constructed from one or more tables. A view is a way of looking at or updating data stored in tables and does not contain any data or exist in physical storage.

Views enable you to:

■ Limit a user's access to specific rows and columns of a table

- Manipulate data from multiple tables as if all the data were contained in a single table
- Gain access to aggregates (sets of data) as if they were individual columns of data

Views simplify retrieval and modify the user's view of data to only certain rows and columns in a table. For example, the table on which you base a view can contain the columns name, title, and hourly_rate. However, the view based on that table might only show columns for name and title and could be restricted to certain rows. Views also allow you to run queries and reports on specific subsets of data and to specify certain rows that fit particular criteria.

You can use the Tables Utility to look at the structure of a view, and to retrieve, modify, or perform computations on the data in the underlying tables. For example, while in the Tables Utility, you could access a particular view based on the emp and tasks tables to compute the average hourly rate of programmers (emp table) working on a particular project (tasks table).

Views are created with a query language such as SQL. You cannot create or destroy views from within the Ingres Menu or the Tables Utility. For detailed information on views, see the description of the create view command in your query language reference guide.

You can access any view for which you have been granted the proper permissions. For more information on permissions, see the *Database* Administrator Guide.

Indexes

An index is a table that indicates where data is stored in another table. It contains the locations of specified columns in the base table that are queried frequently. The index can speed up the retrieval of information.


You can examine an index's structure but cannot perform any other operations on it in the Tables Utility. You create an index on one or more columns of a table, using a query language such as SQL. Whenever a user enters a query based on the indexed column in the base table, the index helps locate the information quickly. Use of indexes is recommended to improve performance of the queries in your applications.

Indexes are created with the create index query language statement. You cannot create, destroy, or directly query or run reports on indexes from within the Ingres Menu or the Tables Utility. For more information on indexes, see the create index statement in your query language reference guide.

Starting the Tables Utility

To start the Tables Utility from the Ingres Menu:

1. Choose the Tables operation from the Ingres Menu. The Tables Catalog frame displays.



The Tables Catalog frame lists the tables, views, and indexes in the database to which you have access, as well as who owns each one. It also lists the synonyms that you or the DBA own.

2. To locate a table, synonym, view, or index name, scroll through the list or type the first letter of the item you are searching for. If you type the first letter, the cursor jumps to the next item in the list that begins with that letter.


The Tables Catalog frame includes the following menu options:

Operation	Function
Create	Create a new table. Displays the Table Create frame. Cannot be used to create synonyms, views, or indexes.
Destroy	Destroys the selected table, synonym, view, or index after asking for verification. Destroying a synonym does not destroy the underlying table.
Examine	Displays information about the names and data types of the columns in the selected table, view, synonym, or index. Invokes the Table Information frame.
Query	Allows you to retrieve data from the selected table (or underlying table for a synonym, view, or index). Also allows update and append operations on tables.

Operation	Function
Report	Runs a preview report on the selected table, view, synonym, or index. Displays a submenu with the following report styles: Tabular, Wrap, or Block. For descriptions of preview reports and report styles, see the chapter "Using RBF." After you select the report style, it sends the report to a file or screen. For additional instructions, see Sending a Report Directly to a File or Sending a Report to and from a Screen in the chapter "Producing a RBF Report."
Help, End, Quit	Standard operations.

Creating Tables

When you choose the Create operation from the Tables Catalog frame, the Create a Table frame displays.



The following table describes the operations available on the menu on this frame:

Operation	Function
Insert	Insert a new column specification row directly above the row on which the cursor now rests. You can then fill in the column name and data format for the new row.
Delete	Delete the column specification row on which the cursor now rests.
Blank	Clear the entire Table Create form of all entries and start over.

Operation	Function
Move	Move the column specification row on which the cursor now rests to a new location. For more information, see Moving Column Specifications .
GetTableDef	Copy column specifications from a different table. For more information, see <u>Cloning Table Specifications with GetTableDef</u> .
EditDefaults	Displays a pop-up frame in which you can enter a user-defined default value for the current column. It changes the value of the Defaults column to value.
ListChoices	Lists the available choices for the selected field.
Cancel	Returns to the Tables Catalog frame without saving the changes you entered on this frame.
Help, End	Standard operations

To create a new table in the Tables Utility, follow these steps. See the following sections for an explanation of each field.

- 1. Enter the name of the table in the first field. Press Return. The cursor moves to the first row in the Column Specifications list.
- 2. Each row in the Column Specifications form represents one data column in the table you are creating. Enter a Column Name, Data Type, Key # (if any), Nulls (if any), and Defaults (if any), for each of the data columns that you want to have in this table. You can use the GetTableDef operation, as explained later in Cloning Table Specifications with GetTableDef, to copy in column specifications from other tables.
- 3. When you finish listing your table's data columns in the Column Specification form, select End to save the table and return to the Create a Table frame.

You can also use a query language create table statement to create a table, or an SQL create schema statement to create a collection of tables. For details, see your query language reference guide.

Table Names

Table names must conform to the standard object naming conventions discussed in Naming and Name Use Conventions. Table names must be unique by user. That is, one user cannot have two tables with the same name, unless the identical names are delimited identifiers in different case. For more information on delimited identifiers, see Naming and Name Use Conventions in the chapter "Fundamentals of Using Querying and Reporting Tools." Different users can each have tables with the same names; however, we recommend that you do not use the name of a table created by the database administrator.

Column Names

Column names must conform to the standard object naming conventions discussed in the chapter "Fundamentals of Using Querying and Reporting Tools." Different tables can have the same column names; however, column names within a single table must be unique, unless the names are delimited identifiers in different case. For more information on delimited identifiers, see Naming and Name Use Conventions in the chapter "Fundamentals of Using Querying and Reporting Tools."

Data Types

Specify data types by entering a type identifier and, in some cases, a number representing the maximum width of the data column. For example, the data type c15 specifies a character data type and a maximum width of 15 characters. Be aware of the maximum possible length of the data type so that you do not exceed it when you are specifying data types.

The following general data types are supported:

- Character
- Numeric
- Money
- Date

For a full description of all data types and their functionality, see the chapter "Working with Data Types and Data Display Formats" and your query language reference guide.

Key Numbers

A key number is optional. When you specify a key number for a data column, data entered into the table is automatically sorted by ascending data value in the key column. For example, if a column named Lastname had the key number of 1, all data in the table is stored according to the alphabetic order of the names in the Lastname column.

You can specify more than one column as a key. This is known as a *multicolumn* key. The data column is sorted with the lowest key number first, then the column with the next highest number, and so on, until all the key columns are sorted.

For example, in a table containing information about employees, if the Department data column is key 1, and the Lastname column is key 2, all the data rows for each department are stored together, and within each department group the rows are alphabetized by last name.

When you are finished creating the table, you can optionally specify that all key columns in the table be used as unique constraints. These constraints prevent the user from entering multiple rows of data that have identical values in the key columns. For details, see <u>Setting Unique Keys</u>.

You can also use ISQL in the Interactive Terminal Monitor or SQL outside of the Tables Utility to specify unique constraints for the table, using the SQL modify statement. For details, see the *SQL Reference Guide*.

Nulls

This field allows you to specify whether the data column accepts null values. A *null value* is a special value that represents unknown or unavailable data. On standard installations, a null value appears to be an empty field, but there is a difference between a null value and a blank or a zero. A *nullable* column is one that accepts a null value. The Nulls field works in conjunction with the Defaults field.

To specify that the data column can *accept null values*, enter y in this field. If a user does not enter data into a nullable column, a value is entered for that column as specified by the Defaults field. For more information, see <u>Defaults</u>.

To specify that the column *cannot accept null values*, enter n. When a user does not enter data into a non-nullable data column, either the value of zero (0) is automatically entered into the column if it is a numeric column, or the column is left blank if it is a character column, or the user is required to enter a value. Use the Defaults column in the Column Specification form to specify this choice.

Defaults

The Defaults field allows you to control what happens when a user does not enter a value in the specified data column. It works in conjunction with the Nulls field specification.

Standard Defaults

You can enter certain standard default instructions directly into the Defaults field, as described in the following table:

Note: To enter a specific, user-defined default for the data column, see User-Defined Defaults.

Nulls Field	Defaults Field	Results if User Does Not Enter Data
Yes	yes	Enters a null value in the data column.
Yes	no	Requires a user to enter data in this column. User can explicitly specify a null value. Any QBFor VIFRED form created from this table can have the Mandatory attribute set for this data column.
No	yes	Enters a default value as follows:
		Numeric column = 0
		Variable-length character column = string of zero length
		Fixed-length character column = blanks
		Date column = empty date
		User cannot enter an explicit null value.
No	no	Requires a user to enter data in this column. User cannot enter a null value. Any QBFor VIFRED form that is created from this table can have the Mandatory attribute set for this data column.
Yes	null	Enters a null value in the data column.
No	null	Not allowed.
Yes	user	Enters the <i>username</i> of the runtime user in the data column if no value is explicitly specified. User can explicitly specify a null value.
No	user	Enters the <i>username</i> of the runtime user in the data column. User cannot enter an explicit null value.
Yes	value	Enters a user-defined default value created with the EditDefaults operation.
No	value	Enters a user-defined default value created with the EditDefaults operation.

User-Defined Defaults

You can specify a user-defined default entry for a data column, using the EditDefaults menu option on the Create a Table frame. A value is then entered in the specified data column if an end user does not enter a value for that column. You can specify a user-defined default value for a column even if none of the other columns for the row have been filled in on the Create a Table frame.

To specify a user-defined default value:

- 1. In the Create a Table frame, place the cursor in the Defaults field for the row in the column specifications table field for which you want to define a default value.
- 2. Type the word, value.
- 3. Tab out of the field or choose the End operation. The EditDefaults pop-up window displays.



The pop-up contains a scrollable default value window that is initially 23 characters wide and scrollable to 1500 characters. The DBMS limit for default values is 1000 characters; however, the extra space in the default window allows for dereferencing characters.

4. Type the default value for the data column. The value can be any valid entry that is compatible with the data type of the column, including today or now for a date column.

You can remove or change the user-defined default value at any time. To remove a user-defined default entirely, change the Defaults field entry to yes, no, user, or null, as appropriate. To change the user-defined default, place the cursor in the Defaults field and choose the EditDefaults menu operation; then enter the new default value in the pop-up frame.

The previous user-defined default value is saved temporarily. To restore it, type value in the Defaults field.

Setting Unique Keys

You can prevent a user from entering duplicate rows in a table by specifying that all key columns for a table shall be unique keys. The unique key columns function as a combined unique constraint during data entry, which can improve performance and data integrity. If you use unique keys in your table, you require that each key value in the table be unique. The key value is the concatenation, or combined listing, of all the values in the key columns in a row. If you specify unique keys, the table can only hold one record for each combined key value.

For example, if you have specified that Firstname and Lastname are the key columns in your table, and you specify that your table must use unique keys, then the combined Firstname and Lastname columns are the unique key value for the table. This prevents any entry that has a combined first and last name from being identical to an existing entry in the table.

To make all key columns in your table a combined unique constraint:

1. After creating a table in an Ingres database and entering key columns for the table, select End. The Tables Utility displays a pop-up menu:

The following describes the options at the bottom of the pop-up menu frame:

Option	Description
Select	Selects the highlighted option in the pop-up menu.
Cancel	Returns you to the Create a Table frame without specifying unique keys.
Help	Displays information about unique keys.

2. Move the cursor to the Unique option on the Unique Keys pop-up frame and click the appropriate mouse button or choose Select at the bottom of the frame to make the columns you specified in the Key column your combined unique constraint.

Moving Column Specifications

The order in which you enter the data columns in the Column Specification form determines the way table data is presented in default reports. In default reports, the report data is sorted on the values in the first column. You can use the Move operation to change the order of data columns when creating a table.

The top data column specification in the table field is the first data column in the table and can be the leftmost data column in any default report created from the table. To move a data column specification from one row of the Column Specification form to another:

- Place the cursor on the data column specification row that you want to move.
- 2. Select the Move operation. The Move submenu appears.
- 3. Position the cursor on the row to which you want to move the data column specification row.
- 4. Select the Place operation from the submenu to move the column specification to the new location. The column specification row to be moved is inserted at the new cursor location and the current row is pushed down by the newly moved row.

Cloning Table Specifications with GetTableDef

The GetTableDef operation allows you to copy column specifications from an existing table into your new table. This is useful because tables in the same database often have identical data columns that are frequently used for joins and views. By copying the column specifications from one table to another, you ensure that these repeating columns all have the same data type, column width, and null and default values.

When you select the GetTableDef operation, you are prompted for the name of the table containing the column specifications you want to copy. Enter that table's name to copy all of that table's column specifications into the Column Specification form. You can copy columns from more than one table into the new table column specifications.

After copying the column specifications into the new table, you can use the Delete and Move operations to eliminate column specifications you do not need and to modify the column order.

Destroying Tables, Synonyms, Views, and Indexes

To destroy (delete) a table, synonym, view, or index, you must own them or have proper access permissions. Note that destroying a synonym does not destroy the underlying database table.

To destroy a table, synonym, view, or index and all its contents from a database:

- 1. Place the cursor on the name of the table, synonym, view, or index you want to destroy. (You cannot destroy any object that does not appear in the displayed list.)
- 2. Select the Destroy operation. A pop-up form asks you for confirmation.
- 3. Place the cursor on yes to confirm that you want to destroy the chosen object or no to leave the object as is.
- 4. Click the appropriate mouse button or choose the Select operation.


You can also destroy a table, synonym, view, or index using a query language. For details, see your query language reference guide.

Keep in mind that you cannot later *undo* the destruction of a table, synonym, view, or index, or recover the contents of a destroyed table. To recover a table later, copy it to a file with the copydb command before deleting it from the database. Otherwise, you can recover the object only by restoring the entire database from a backup tape, if you have one. For instructions on using the copydb command, see the Database Administrator Guide.

Getting Information about Tables and Views

Use the Examine operation on the Tables Catalog frame to display information about a table, synonymview, or index.

To use the Examine operation, place the cursor over the name of the table or view you wish to learn about and choose the Examine operation. The Examine operation displays the Examine a Table frame.



If you are examining a synonym or view, the Rows, Storage Structure, Pages/Overflow, and Journaling fields do not appear on the frame.

If you are examining a synonym, the base table's name and schema name also display. If you do not have access to the base table, *only* the base table's name and schema name display.

All the fields on the Table Information frame are display-only; you cannot edit or change any information.

The following table describes the menu operations on the Examine a Table frame:

Function	Description
NewTable	Allows you to name a new table that you want to examine without returning to the Tables Catalog frame.
ViewDefaults	Allows you to look at the actual user-defined default value for a data column, if the Defaults field entry for the data column is value. If the Defaults field contains any other entry, an error message is displayed.
Help, End	Standard operations.

The following table describes the fields on the Examine a Table frame:

Field	Function
Owner	Name of the schema in which the table or view resides.
Row Width	Total width, in bytes, of any data row in the table.
Rows	Approximate number of data rows (records) currently stored in the table. For a new table that has not yet had data entered into it, this number is zero (0). You can multiply the row width by the number of data rows to calculate how much disk storage space the table now occupies.
Columns	Number of columns in the table.
Table Type	Table type (table, view, or secondary index).
Storage Structure	Type of storage structure that the table uses; for example, heap or compressed B-tree.
Pages/Overflow	Number of pages and overflow pages the table now occupies.
Base Table	Name of the underlying table (for a synonym only).
Base Table Owner	Name of the schema in which the base table resides (for a synonym only).
Journaling	Indicates whether journaling is enabled for this table. Journaling is a process of logging all changes to the table over time.
Column Name	The name of the column in the table.
Data Type	The type of data (and in some cases maximum number of characters) stored in the column.
Key #	The key sort priority number of the column, if any.
Nulls	Indicates whether null values are accepted in the column.
Defaults	Indicates whether default values can be automatically entered in the column if no data is entered by the user.

Adding or Deleting Columns in an Existing Table

To add or delete columns in an existing table, you must use query language statements outside of the Tables Utility. This allows you to recreate the table with all or some of the columns from the original table, as well as add any new columns. For specific instructions on how to do this, see the *Database Administrator Guide* for the system on which your database resides.

Note: When you recreate a table, you also must recreate any synonyms, views, or indexes based on the original table. In addition, you must edit any forms or reports based on the original table, if the form or report references any changed or deleted columns or if it is to access any new column in the table.

Chapter 4: Using QBF


QBF is an interactive, visually oriented, forms-based tool for adding, deleting, changing, and viewing data on selected query targets in a database.

A query target can be a table, JoinDef, or QBFName. For ease of use, you can use default forms to access tables or JoinDefs in QBF. You can also define a customized form to suit your particular needs for accessing a table or JoinDef with which the customized form is associated. A table or JoinDef that has been associated with a customized form is called a QBFName. Use the VIFRED to create the customized form for a QBFName, as described in the chapter "Using VIFRED."

This chapter explains the difference between the definition and execution phases of QBF, and provides instructions for starting QBF, choosing a query target, and executing a query.

The Append, Retrieve, and Update operations are described in the chapter "Working with QBF Operations." The chapter "Using JoinDefs in QBF" discusses how to create, edit, and delete JoinDefs.

You can access all other QBF frames from the QBF Startup frame. For a map of the options available to you when you choose the JoinDefs operation, see the chapter "Using JoinDefs in QBF."



Before Starting QBF

Before starting QBF, you must understand the difference between the two phases involved in performing a query. They are:

- Query definition phase
- Query execution phase

When starting QBF from the operating system, you can use different commands to enter QBF at the correct phase.

When starting QBF from the Ingres Menu, you can move through each phase in a predetermined order.

Query Definition Phase

In the *query definition* phase, you choose or create a query target. A *query target* contains the data you want to review, add to, or change. You can use a query target for queries as often as you like. There are three recognized types of query targets:

Query Target	Description
Tables	Two-dimensional arrays of data
JoinDefs	Two or more tables joined through common values in one or more columns
QBFNames	The association of a table or JoinDef with a form created in the VIFRED

If your query target is a table or JoinDef that does not yet exist, you can create it from the appropriate Catalog frame in the query definition phase. To create a QBFName, however, you must use the VIFRED, which is accessed through the Forms menu choice on the main Ingres Menu frame.

You can choose a defined synonym or an existing view as a query target in place of a table name. However, you cannot create a synonym or view from the Tables Catalog frame or any other QBF frame. You can create views only with a query language. For more information on synonyms and views, see the chapter "Using the Tables Utility."

Query Execution Phase

After choosing or creating the query target, you enter the guery execution phase. In this phase, you can manipulate data in these basic ways:

- Append (add) data rows to a table
- Retrieve (view) data from tables
- Update (modify or delete) data in tables

For a discussion of these functions, see the chapter "Working with QBF Operations."

Starting QBF

You can start QBF from the operating system or from the Ingres Menu.

Starting QBF from the Operating System

The command and command line syntax you use to start QBF at the operating system prompt determines the starting QBF phase:

- Using the QBF command without a query target starts QBF in the query definition phase. From the query definition phase, you can then move to the query execution phase.
- Using the QBF command with a specified query target starts QBF in the query execution phase.
- Using the query command, which requires specification of a query target, starts QBF in the query execution phase.

For more information on the QBF and query commands and their parameters, see the chapter "Using System Command for the Forms-based Tools."

Starting QBF from the Ingres Menu

To start QBF from the Ingres Menu:

- 1. Choose the Queries operation from the Menu to display the Queries frame.
- 2. Choose the QBF operation from the Queries frame. The QBF Start-Up frame displays.

```
🖁 Ingres - QBF
     - Start-Up Frame
 Query-By-Forms (QBF) is an interactive interface for adding, deleting, changing and viewing data in your database.
You may get a catalog of QBFNames, JoinDefs, or Tables in your database to serve as a basis for editing and viewing. In summary, they are:
                          a name that combines a joindef or table name with a
form name. QBFNames are created in UIFRED.
a stored specification of joins between tables, and
rules governing how to update data in QBF.
a table or view in your database.
    Table
 From each of the catalogs, you can browse names, and choose one to serve as a basis for editing or viewing.
Additional utility commands on this menu are:
                          displays help on QBF and your terminal key functions. leaves QBF.
 QBFNames(SH-F1) JoinDefs(SH-F2) Tables(SH-F3) Help(F1) >:
```

3. From the QBF Start-Up frame, choose QBFNames, JoinDefs, or Tables.

An appropriate Catalog frame displays, as discussed in Choosing a Query Target.

Choosing a Query Target

Catalogs automatically keep track of query targets. A Catalog frame displays a list of query targets, a menu of available operations, and some explanatory information.

Query targets can be:

- Tables
- QBFNames associated with tables or JoinDefs
- Synonyms referring to tables
- Views or JoinDefs based upon tables

You must either own the query target object or have been granted the appropriate permissions to access or perform an operation on the object. For more information on granting or obtaining permissions, see the Database Administrator Guide.

To locate the query target you want, scroll through the list in the Catalog frame. A quicker alternative is to type the first letter of the item you are searching for. The cursor moves to the next item in the list that begins with that letter.

For each type of query target, a different type of form is used for displaying your query results. For more information on data display forms, see Data Display Forms for Query Targets.

Using Catalog Frames for Query Target Selection


Each type of guery target—QBFName, JoinDef, and table—has its own Catalog frame. Each Catalog frame offers various operations, such as create, destroy, edit, or examine, that are specific to that type of query target. The Tables Catalog frame operations are discussed in detail in the chapter "Using the Tables Utility." Operations on the JoinDefs and QBFNames Catalog frames are discussed in the chapters "Using JoinDefs in QBF" and "Using VIFRED."

All catalog frames offer the following standard operations for use with QBF:

Operation	Description
Go	Runs a query on the target you choose
Help, Quit	Standard operations

QBFNames Catalog Frame


The QBFNames Catalog frame, shown in the following figure, contains a list of the QBFNames that you can access. A QBFName represents a data display form designed or customized with the VIFRED and then linked to a JoinDef or table. For a discussion of QBFNames, see the chapter "Using VIFRED."



Choosing a QBFName query target from the QBFNames Catalog frame informs QBF to use the customized data display form and the associated JoinDef or table in the query operation.


JoinDefs Catalog Frame

The JoinDefs Catalog frame, shown in the following figure, contains a list of the JoinDefs that you can access.



Tables Catalog Frame

The Tables Catalog frame, shown in the following figure, lists the names and owners of all tables and views to which you have access in the current database.



Choose any table or view in the Tables Catalog frame as a query target for query execution. However, when executing a query on a view, you can only perform a Retrieve operation. You cannot perform the Update or Append operations on a view. For more information on views, see the chapter "Using the Tables Utility."

Data Display Forms for Query Targets

If you choose an existing QBFName as your query target, an associated custom form for the query is used. If you choose a query target that is a table or JoinDef, an appropriate default form for the query is used. For a table, you can choose between two additional options, SimpleFields or TableField format, to specify which default form to use.

Custom Forms

You can use the VIFRED to develop a custom form and associate it with a query target. VIFRED allows you to specify the dimensions and general appearance of the form or form components and to specify different display and behavior attributes for the fields on the form. For information about creating custom forms, see the chapters "Using VIFRED," "VIFRED Form Components," and "VIFRED Field Specifications."

To specify a query target for use with a custom form, you use the QBFName that associates the form with the table or JoinDef.

Default Forms

When displaying a default form for a query, QBF uses the column names and data types of the table or tables in the guery target. Unless there is a conflict, QBF uses the table column names as the internal name for each field on the form. When conflicts occur, QBF creates unique internal field names by slightly changing one of the column names.

When creating a form, QBF allocates each field enough space on the form for data entry and field titles. If you have specified that a table field must appear on the form, QBF first places all the simple fields on the form and then places the table field at the end of the form.

QBF supports several types of fields, corresponding to the basic data types:

- Integer (whole numbers only)
- Floating-point (numbers including decimal places and scientific notation)
- Character (alphanumeric characters)
- Date
- Money

For more detailed information about data types and formats, see the chapter "Working with RBF Report Specifications."

Executing a Query

You can start query execution from within the Ingres Menu, following the query definition phase, or from the operating system, without traversing the Ingres Menu and QBF definition phase screens. For instructions on starting query execution from the operating system, see the chapter "Using System Commands for the Forms-based Tools."

To begin the query execution phase from the Ingres Menu, follow these steps:


- 1. Start QBF in the query definition phase and choose a query target, as described in the sections, Starting QBF and Choosing a Query Target:
 - a. Choose Queries.
 - b. Choose QBF.
 - From the Start-Up frame, choose either Tables, JoinDefs, or QBFNames.

A Catalog frame displays with the available query targets of the type you specified.

2. Place the cursor on the row in the Catalog frame that contains the query target you want and choose the Go operation.

If your query target is a table, a submenu appears. Choose the SimpleFields or TableField operation to specify the format for the default form.

The data is retrieved from the system catalogs and displays an appropriate QBF Execution Phase frame.



3. Choose an appropriate operation, as described in the following table:

Operation	Description
Append	Adds information to the database.
Retrieve	Retrieves information from the database.
Update	Changes or deletes information in the database.
Help, End, Quit	Standard operations.

When you choose Append, Update, or Retrieve, QBF displays the appropriate frame for the operation and query target you have chosen.

If you access the QBF Execution Phase frame directly from the operating system by specifying a query target in the qbf command, two additional operations on the QBF Execution Phase menu appear:


Operation	Description
NewQueryTarget	Chooses a new query target to run.
Start	Goes to the Start-Up frame.

The NewQueryTarget operation lets you specify a new query target without exiting QBF. You are prompted for the name of a new guery target. It searches for a query target with that name first among QBFNames, then, among JoinDefs, and last, among tables. The Start operation returns you to the Start-Up frame.


Displaying and Saving Query Results

The Retrieve operation allows you to view, but not change, data. Both the Append and Update operations allow you to make changes to the data, which you can save.

A default form for all three operations used with tables and JoinDefs is generated. For example, if your query target is a JoinDef, the default form might look like the following figure.



The data retrieved by this query is shown in the following figure.



When you modify data with the Update operation, the changes you make are stored in a temporary location. It does not write them into the actual table until you select the Save operation. If you leave QBF execution without specifically saving your changes, you can lose your modifications and the data in the database tables remains unaltered.

If a join column in a JoinDef has been protected from updates with the Rules operation, you cannot update the join column but you can update the rest of the row. If the table has been protected from updates with the Rules operation, you are not allowed to save changes to the protected table. QBF issues an error message when you try to execute the Save operation. For information on the Rules operation, see the chapter "Using JoinDefs in QBF."

Chapter 5: Working with QBF Operations

This chapter explains how to use the QBF operations, Append, Retrieve, and *Update*. Append adds new records to a table, Retrieve retrieves information and displays it in a window, and Update modifies, updates, or deletes existing data.

QBF Append Operation

This section explains how to use the Append operation in QBF to add new records (rows) to a table. To append data, you fill in a QBF form and choose the appropriate menu operation.

In QBF, you can append data only to tables for which you have been granted the Append privilege to add rows.

Starting the Append Operation

You can start the Append operation from the operating system or from the Ingres Menu."

The following steps describe how to start the Append operation from the Ingres Menu. The chapter "Using QBF" discusses steps 1 through 5 in more detail.

- 1. Choose Queries.
- 2. Choose QBF to reach the QBF Start-Up frame.
- 3. Choose Tables, QBFNames, or JoinDefs for the appropriate Catalog frame.
 - When working with a table query target, you must also choose SimpleFields or TableField format.
- 4. Place the cursor on the name of your query target in the Catalog frame and choose the Go operation. The Execution Phase frame displays.
- 5. On the Execution Phase frame, choose Append.
 - A default query form displays.

Using the Append Frame

Two approaches to adding new rows of data to a table with QBF are available:

- Use a table field to append many rows of data at once.
- Use simple fields to append one row at a time.

Each field on the Append frame corresponds to a single column in the query target table(s). On a default form, if the query target is a JoinDef, the join field(s) appears in reverse video, if your terminal has that capability.

Whether you use simple fields or a table field depends on the query target:

- If the guery target is a table, the menu choices SimpleFields and TableField appear, following the table you chose in the Tables Catalog frame.
- If the query target is a Master/Detail JoinDef, the default format is a table field for the detail table and simple fields for the master. You can change this default on the JoinDef Definition frame.
- If the query target is a QBFName, the form shown on the frame can have table fields or simple fields or both. The appearance and behavior of a QBFName form can be altered using the VIFRED as described in the chapters "Using VIFRED," "VIFRED Form Components," and "VIFRED Field Specifications."

Procedure for Adding New Rows of Data

To add new rows of data to the database:

- 1. Start the Append operation from the operating system or from the Ingres Menu, as described in the section, Starting the Append Operation.
- 2. Enter your data in the fields of the form. If you are using a table field, you can tab through the fields in each row. Press Return at the end of the row.
 - If the query target is a QBFName, the sequence in which the cursor moves from one field to the next is determined by the order specified in the custom form created in VIFRED.
- 3. When you have typed in all the rows of data that you want to add, choose the Append operation from the Append frame menu to save your additions.

Your data is added to the database tables and displays a message telling you how many rows of data it has appended.

If you do not choose the Append operation in the Append frame, your additions are not saved.

The methods you use to append data differ slightly depending on whether you are using a simple-fields or table-field format.

Simple-Fields Format

If you are appending data using simple-fields format, you can append only one row at a time. When you are finished entering data, choose Append to write your new data into the database. Append is the only operation available.

Table-Fields Format

If you are appending data using table-field format, you can enter more than one row of data in the table field before choosing Append. When finished entering data, choose Append to write your new data into the database.

The following menu operations are available on the Append frame if you choose the table-field format:

Operation	Description
Append	Appends the data to the table.
Insert	Inserts a new blank row in the table field.
ListChoices	Displays the available choices for the selected field on a QBFName.
Help, End	Standard operations.

The Insert operation on the Append frame allows you to open a new line in the table and insert a new row of data in a specific location. Using Insert does not affect the retrieval or reporting of data in the table(s). The Insert operation is provided as a convenience so that you can visually order your new rows as you enter them on the frame.

To use the Insert operation, follow these steps:

- 1. Put the cursor where you want the new row to appear.
- 2. Choose Insert.

QBF places the cursor at the beginning of a new blank row inserted above the previously selected row.

Data Entry Errors

When you choose Append, each field is checked for errors. If an error is detected, an error message appears and the cursor returns to either the field containing the error or to the first field on the form.

Choose Append again to add your corrections to the database.

If your query target is a QBFName, your customized form can contain mandatory fields, validation checks, or special attributes. These requirements must all be met before QBF allows the Append operation to add data from the form to the database.

Duplicating Previous Entries

When entering data in simple-field format, press Control-A to duplicate the previously entered value for that field. For example, pressing Control-A in the Zipcode field enters whatever zip code was entered on the previous form. Control-A does not work in table-field columns.

Transaction Deadlock in Append Mode

Because transactions are supported, a transaction deadlock can occur in Append mode. This can only happen after you select the Append command to add the data you have entered in the form to the database. If an attempt to add a row to one of your query targets aborts because of a transaction deadlock, QBF informs you that a deadlock has occurred and that your transaction has been aborted. QBF then automatically retries the entire append.

Confirmation Messages

If an append is successful, QBF displays a confirmation message, for example: Appended 1 master and 2 detail row(s)...

QBF displays an error message if you attempt to append information to a table that has update rules preventing this, or if you violate an integrity constraint, which defines a valid range for data.

Exiting the Operation

After appending your data with the Append operation, choose End to exit to the QBF Execution Phase frame. End returns you to the previous frame. If you try to exit without committing the data with the Append operation, QBF prompts:

Do you wish to leave APPEND without appending data on the frame?

If you type \mathbf{y} (yes), QBF displays a message indicating how many rows of data have been appended in this session and returns you to the QBF Execution Phase frame without appending the current data. If you answer n (no), QBF returns you to the form where you can choose Append.

Each time you exit after appending data, QBF displays a message containing the number of rows successfully appended during the session.

QBF Retrieve Operation

This section explains how to use the Retrieve operation to retrieve information from the database and display it in your window. In Retrieve mode, you can browse through the retrieved data, but you cannot make any changes to it.

When you use Retrieve, QBF displays a blank form representing the JoinDef or tables you want to review. To specify which data you wish to view, enter search qualifications in the fields on a form.

Starting the Retrieve Operation

You can start the Retrieve operation from the operating system or from the Ingres Menu.

The following steps describe how to start the Retrieve operation from the Ingres Menu. The chapter "Using QBF" discusses steps 1 through 4 in more detail.

- Choose Oueries.
- 2. Choose QBF to reach the QBF Start-Up frame.
- 3. Choose QBFNames, JoinDefs, or Tables for the appropriate Catalog frame. When working with a table guery target, you must also choose SimpleFields or TableField format.
- 4. Place the cursor over the name of your query target in the Catalog frame and choose the Go operation. QBF displays the Execution Phase frame.
- 5. On the QBF Execution Phase frame, click Retrieve.

QBF displays the Retrieve frame with the fields of your query target and a menu of operations. The appearance of the Retrieve frame varies depending on the type of query target. The following section discusses the Retrieve Frame.

Some data columns in a table can be hidden from your view by the JoinDef ChangeDisplay operation.

Using the Retrieve Frame

The following figure shows the Retrieve frame for a JoinDef query target. The Retrieve frame can contain simple fields and/or a table field.



Join columns are indicated by reverse video on a Retrieve frame if your terminal has that capability.

If the query target contains too many columns to fit in your window, tab through the columns to scroll to those that are outside the displayed window.

Operation	Description
Go	Executes the query.
Blank	Clears the current entries from the window.
Order	Displays current data sort order specification for review or editing.
LastQuery	Places the contents of the previously run query on the form for review or editing.
ListChoices	Lists the available choices for the selected field on a QBFName.
Help, End	Standard operations.

Follow these steps for using the Retrieve frame:

- 1. Enter search conditions in the columns of the Retrieve frame form to qualify your search. Qualifying a search limits the results to records (rows) containing the types of data you specified in the Retrieve frame. For example, to look at only those records pertaining to the advertising department, only records for the month of January, or only records of employees with salaries greater than \$30,000 per year. For more information, see Qualifying Retrievals.
- 2. Use the optional Order operation to specify the order in which you want to view the retrieved records. For example, to view records chronologically, or by department, or size of budget. For more information, see Sorting Query Results.
- 3. Choose the Go operation to start the search. For instructions on viewing the retrieved data, see Viewing Retrieved Records.
- 4. Begin a new query by choosing the Query operation.


Qualifying Retrievals

Qualification is the process of specifying which rows in the table(s) you want to retrieve. You indicate which rows to retrieve by entering your qualification criteria, or search conditions, in the fields on the Retrieve form. This restricts retrieval to those records (table rows) that match or meet the qualification criteria you entered.


For example, if the Retrieve form has a Lastname field, and you enter Lincoln in that field, the word Lincoln becomes a search condition. QBF retrieves only those records with a value of Lincoln in the Lastname field.

Leaving all the fields on the QBF Retrieve form blank is equivalent to specifying no restrictions on retrieval so that all records of data from the table(s) are displayed.

The following figure gives an example of search conditions that restrict retrieval of records from the Managers table to those data rows with the Project of Advertise.



The following figure shows the results of a query that restricted retrieval of records to data rows with the Projects Advertise and TextProc.



If the query target contains too many columns to fit in your window, tab through the columns to scroll to those that are outside the displayed window.

The search conditions you enter in a field can exceed the field's window width on the form. When you enter a long specification in a field, the window scrolls as you type.

You can duplicate a qualification value from a simple field on a form. For information about using auto-duplication on your terminal, see the appendix "Defining Function and Control Keys."

Trailing blanks are ignored in a qualification specification.

Use various operators and expressions to further qualify your retrieval search. These are discussed in the following sections.


Using Comparison Operators

A comparison operator is a symbol that informs QBF that you want to compare two values or search for a range of data.

Qualify your query with these comparison operators.

Operator	Description
=	equal to
!=	not equal to
<	less than
<=	less than or equal to
>	greater than
>=	greater than or equal to

For example, the following figure shows a query that searches the Projects table for records with a budget greater than or equal to \$12,000.



All comparison operators have equal precedence.

QBF assumes that fields containing values with no comparison operator have a defacto equals sign as the comparison operator. The equals sign works differently when querying non-nullable and nullable fields. For more information, see Queries in Blank and Nullable Fields.

Comparison operators are often combined with the AND operator within a field. For example, entering a search condition of >100 and <900 searches for all values between 100 and 900. You can also use the OR operator. For example, <100 or >900 searches for all values that are either less than 100 or greater than 900. Likewise, >=a <=d retrieves all character strings that begin with the letters a, b, c, or d.

When using a comparison operator on a character field, the search is case-sensitive because QBF treats lowercase and uppercase characters as different characters. All uppercase letters come before all lowercase letters. If you enter >a, you cannot find any character strings that begin with uppercase letters, while if you enter >A <a, you can find all strings that began with uppercase letters but no strings that began with lowercase letters.

Just as capital letters are ordered ahead of lowercase letters, QBF orders numbers in a character field ahead of both uppercase and lowercase letters.

You cannot combine a greater than (>) or less than (<) comparison operator with pattern matching. For example, >Sa% is not allowed. For more information on pattern-matching, see <u>Using Pattern-Matching Characters</u>.

Using Logical Operators

QBF allows you to use the *logical operators* AND (conjunction) and OR (disjunctive) to qualify retrievals. AND and OR are known as Boolean operators:

- When you use the AND operator, QBF retrieves only data records that meet both or all of the criteria you specify.
- When you use the OR operator, QBF retrieves data records that meet any one of the criteria you specify.

There are two ways to use the AND and OR operators:

- Within a column
- Between different columns

For more information on the use of Boolean operators, see the chapter "VIFRED Field Specifications."

Logical Operators Within a Column

You can use logical operators within a data column. For example, if you enter Lincoln or Douglas or Tubman in a Lastname field, the query returns records with a value of either Lincoln or Douglas or Tubman in the Lastname column.

You can explicitly enter the AND operator in a field, as you do the OR operator, or you can imply the AND operator by leaving a space between words. For example, entering Delta Gamma is the same as entering Delta and Gamma.

If you want to search for a string of words separated by literal spaces, you must enclose the string with double quotation marks (" "), because QBF otherwise interprets the spaces as implied AND operators.

For most practical purposes, the AND operator is only useful in numeric fields because the AND operator requires that the data in the field meet two separate and exclusive criteria. For example, a number can be both greater than 10 and less than 100.

Because the AND operator is exclusive, it usually returns nothing in a character column. For example, entering 1776 and Adams and Street in an Address field does not return the address 1776 Adams Street because QBF looks for a single field with a value of 1776 and nothing else, a value of Adams and nothing else, and a value of Street and nothing else. Because no field could meet such impossible conditions, no data records can be found.


You can use the AND operator in a character field if you use the greater than (>) and less than (<) comparison operators. For example, entering the search condition >a and <d retrieves all character strings that begin with either b or

Logical Operators Between Columns


When using logical operators between columns, you do not enter the words AND or OR in the form as you do when you use these operators in a single column. In QBF, the AND and OR operators are implied by the way the qualifying criteria is entered in the fields. Simple fields and table fields differ in how logical operators are implied:

- On a form with simple fields, the AND operator is always implied when information is entered in more than one field.
- On a form in table-field format, the AND operator is implied when information is entered in the columns across one row of a table field.

In the following figure, for example, QBF only retrieves data from the Project and Managers tables that have the Project ID Advertise AND a Budget of more than \$5,000.



■ The OR operator can be implied only in table-field format. Values in different rows of a table field are implicitly OR. In the following figure, for example, QBF can retrieve data that has the Project ID Advertise OR has a budget of more than \$5,000.



Grouping Values

When using logical operators, you can use parentheses to group values. For example, to retrieve all projects with budgets less than \$5,000 or between \$15,000 and \$20,000, enter the following expression in the Budget field:

<5000 or (>=15000 and <=20000)

For information on handling queries containing literal parentheses, see Character String Qualifications.

Using Pattern-Matching Characters

For further qualification of queries, you can perform pattern matching with wild card characters. Wild card characters are symbols that represent unspecified character values. In QBF, the asterisk (*) and the question mark (?) are the default wild card characters. Pattern-matching characters cannot be used in fields with numeric data types.

As explained in The % and _ Pattern Matching Characters, you can specify that your system use the % and _ character in place of ? and *.

? and * Pattern-Matching Characters

Use the question mark (?) to represent one unspecified character. For example, T?P can find the values TAP, TCP, TOP, and so on. You can use more than one question mark to indicate more than one character. For example, to search for all 5-digit identification codes beginning with 941 enter 941??.

Use the asterisk to represent any number of unspecified characters or no characters at all. For example, to search for all product codes containing the characters ALPHA enter *ALPHA*. This returns answers such as:

122-STAR-ALPHA STAR-ALPHA-X4 ALPHA-987-PROTO **ALPHA**

To search for all product codes that begin with the characters STAR you enter STAR*. This returns answers such as:

STAR-98-BETA STAR-ALPHA **STAR**

You can combine the question mark and the asterisk. For example, to locate any product that begins with four characters and a dash and ends with ALPHA, enter ????-*ALPHA. This returns answers such as:

STAR-986-ALPHA PROT-BETA/ALPHA TEST-ALPHA

Pattern-matching characters and logical operators interact with each other. For example, you can combine the OR operator and pattern matching characters in a column by entering STAR* or ALPHA-????. This returns answers such as:

ALPHA-98G5 ALPHA-TEST ALPHA-5005 STAR-87-BETA STAR-876-ALPHA-X STAR

For most practical purposes, the AND operator is only useful in numeric fields because it requires that the data in the field meet two separate criteria. Therefore, the AND operator is rarely used in conjunction with patternmatching characters.

Because QBF treats spaces in search qualifications as an implied AND operator, you must enclose pattern-matching qualifications containing a literal space in quotation marks. For example, in an address field the specification 1776 Adams* returns nothing and does not find 1776 Adams St because the space is treated as an AND operator. To include a space in a character field specification you must enclose the specification in quotation marks. For example, entering 1776 Adams* returns answers such as:

1776 Adams Ln. 1776 Adams St. 1776 Adams Street 1776 Adamstown Court

To use the asterisk or the question mark as actual characters rather than as wild card characters, precede them with the backslash character (\). For example, enter A*B to look for the actual sequence A*B. If you enter A*B by mistake, QBF searches for any combination of any number of characters that begin with the letter A and end with the letter B.

You cannot use a wild card pattern-matching symbol in conjunction with a greater than (>) or less than (<) comparison operator. For example, >Sm* is not allowed.

% and _ Pattern-Matching Characters

You can choose to use the underscore (_) and percent sign (%) pattern-matching characters in place of the ? and * characters. The underscore is equivalent to the question mark and the percent sign is equivalent to the asterisk. To specify these pattern-matching characters, use the II_PATTERN_MATCH environment variable/logical as explained in the *System Administrator Guide*.

Using Bracketed Expressions

By enclosing characters within brackets ([]), you can stipulate specific values in a pattern-matching search. For example, if you want to find employees whose last names begin with R or T, enter [RT]* in a Lastname field. This returns last names such as Randall, Rotelli, Tamatomi, and Tijerina. You can include any number of characters within brackets and they can be placed in any order.

All pattern-matching queries work in Query mode. However, if you invoke QBF with the -e flag (for expert mode) you cannot use bracketed pattern-matching operators for specifying selection criteria in an empty catalog in order to retrieve a set of tables or other objects for querying.


A bracketed pattern is often used when a table contains data in different cases. For example, if you entered S* as a query specification in the Dept field, a retrieve returns rows with Sales, but not rows with sales. However, the query specification [Ss]* returns all rows containing both Sales and sales. By separating characters with a hyphen and surrounding them with brackets, you can stipulate a range of characters for pattern matching. Thus, entering [A-M]* in the Name field retrieves the names of all employees whose last names begin with any letter in the first half of the alphabet, such as Alcott, Chung, Feldmann, King, and Moore. The wild card characters can be combined with bracketed expressions. Used either before or after the brackets, they further refine a search for patterns in data.

Complex Queries

The following figure is an example of a complex guery that utilizes comparison operators, logical operators, and wild card characters. The query searches for information from a JoinDef consisting of the Staff table and the Tasks table. Specifically, it searches for records of employees whose names begin with the letter B, whose hourly rate is less than \$50, and who have either worked in the Design phase or have worked more than 25 hours in the Implement phase.

QBF interprets the search conditions on this form as follows:

Display the data if name = B^* and hourly rate <50 and (task = Design or (task = Implement and hours >25))



Character String Qualifications

The following sections describe the use of case, parentheses, and multiple words in character strings.

Case Character string search conditions are case-sensitive. For example, if you

enter Franklin as a search condition, QBF displays only records with Franklin,

but not FRANKLIN or franklin.

Parentheses If a character string contains a literal parenthesis, you must enclose the

entire string in quotation marks. For example, to retrieve the record for

Martin (E) Smith, enter Martin (E) Smith.

Multiple Words in Character Fields

If a character field contains two or more words separated by spaces, such as a street address, you must either use a pattern-matching wild card character, as explained in Using Pattern-Matching Characters, or enclose a multi-word search condition in quotation marks.

For example, suppose you want to find records with a value of 1776 Adams Street in the Address column. You could do this by entering 1776 Adams Street as a search condition in the Address field.

However, if you enter 1776 Adams Street with no quotation marks as a search condition in the Address field, nothing is found because QBF interprets the spaces between the three words as implied AND operators.

As explained in the section on pattern-matching, you could also use a wild card character. For example, entering a search condition of 1776* finds all addresses on all streets beginning with 1776. Entering a search condition of 1776 Adams St* finds both 1776 Adams St. and 1776 Adams Street.

Date and Time Qualifications

Date fields can hold either a simple date, such as 22-mar-1998, or a date and time, such as 22-mar-1998 10:44:23. You cannot use wild card characters in date fields to qualify a retrieval. However, you can use comparison and logical operators to retrieve a range of dates and/or times.

For example, to retrieve all records with dates from January 1, 1998 through December 31, 1998, enter the following qualification in a date only field:

>=1-jan-1998 and <1-jan-1998

If the field contains only date values and no time values, you can retrieve all records for a single date, such as March 22, 1998, by entering a qualification such as:

22-mar-1998

If the field contains values in the date and time format and you want to retrieve only records with the specific date and time of March 22, 1998 10:44:23, enter the qualification:

22-mar-1998 10:44:23

If the field contains both the date and time and you want to retrieve all records for March 22, 1998, regardless of the time, enter the following date range qualification in the date and time field:

>=22-mar-1998 and <23-mar-1998

To qualify the retrieval for a specific hour of one day, enter a qualification such

>=22-mar-1998 10:00 and <22-mar-1998 11:00

Queries in Blank and Nullable Fields

Query specifications differ between nullable and non-nullable fields. For general information on nulls and nullable columns, see the chapters "Using the Tables Utility" and "Working with Data Types and Data Display Formats."

In a nullable column, blank fields are treated as nulls (no data). In a query operation, entering the equals sign (=) into a nullable numeric column without anything else tells QBF to look for and return only rows in which the specified field is null.

In a non-nullable column, blank fields are treated as if they contain a value of zero (0). Entering the equals sign (=) into a non-nullable column without entering anything else returns all rows containing a value of zero (0) in that field.

Sorting Query Results

Use the Order operation to specify the order in which your retrieved data displays.

Choosing Order on the Retrieve frame temporarily clears all qualification specifications from the Retrieve frame form so that you can enter order qualifications. Any previously entered sort-order specifications displays.

The frame menu now displays the following operations:

Operation	Description
Blank	Clears any specifications that have been entered.
Cancel	Restores the previous ordering specifications, if any, and returns to the previous Retrieve frame.
Help, End	Standard operations.

Sort Sequence and Sort Priority

You control the order in which data displays in your window by specifying the sort order. Sort order is governed by sort keys. Sort keys are data columns (fields) that have been given a sort priority number. For example, if a field called Name is the sort key, QBF presents all the data rows in alphabetic order by Name.

If you do not use the Order operation to specify a sort order, QBF displays the data according to how it is stored in the table. How data is stored in the table depends on the table's storage structure.

By default, QBF sorts columns in ascending order.

You can specify the sort order in master and detail tables, with or without table fields, for any query target.

For example, Lastname might be the first field listed on the form and Zip the fifth. But if you specify that you want zip-codes to be the primary sort key, and last names the second sort key, your data is displayed by zip-code in numeric order with the last names within each zip-code arranged alphabetically.

To set the ordering sequence for a field, follow these steps:

- 1. Click Order on the Retrieve frame.
- 2. Put the cursor in a column (field) you want to sort on.
- 3. Type a number from 1 to 1024. This is the sort priority number. QBF sorts the field with the lowest number first. The first sort is called the primary sort. If you want the field displayed in descending order, follow the sort priority number by d (or D). For ascending order, you can enter a (or A) or no letter, because ascending order is the default.
- 4. If you want a secondary sort, repeat steps 2 and 3 in the secondary sort field. Make sure that the number you enter in the secondary field is higher than the number entered in the primary field. If you want additional sorts, continue this process until all the fields you want to sort on have been assigned a sort priority.

- 5. When you are finished, click End to return to the original menu for the Retrieve frame and remove the sort order specifications.
- 6. Click Go to execute the query.
- 7. If you choose Order again, the previous sort priority numbers and sort sequence letters display in the fields. To change them, type new values. Use the Blank operation to erase all sort specifications and begin with a blank form.

You can assign a sort sequence to any and all fields and table fields on the form.


The Order operation treats sort sequence numbers as relative. If you assign sequence numbers 1, 3, and 80, Order interprets them as follows:

- 1 primary
- 3 secondary
- 80 tertiary

The following figure shows a JoinDef of the Projects and Tasks tables. The primary sort column is Dept. The secondary sort column is Budget. Because d is specified for Budget, the highest figure is displayed first. The third sort column (specified as 5) is Due Date, and the fourth (specified as 10) is Project.

When specifying sort order, the default is ascending order (A before B, 1 before 2). If you type d for descending order, the Order operation sorts text fields in reverse order (Z before Y, 9 before 8). If desired, you can use a colon (:) to separate the priority number from the sort direction.

For example, specifying either 2d or 2:d in the Budget field makes Budget the secondary sort key and instructs QBF to display the results in descending order according to Budget (highest budget first, lowest budget last).



Keep in mind that QBF sorts numbers in numeric fields differently than numbers in character fields. Numbers in numeric fields are sorted by value (1, 2, 3, 10, 11, 12, 101, 112, 121,...). When numbers are part of a character field (in an address, for example), they are sorted alphabetically (1, 10, 101, 11, 12, 121, 2, 3,...).

Nulls in a character field are sorted last.

Sort Precedence in JoinDef Execution

QBF sorts Master/Master JoinDefs in the same way as tables. The fields can be sorted in any order.

In Master/Detail JoinDefs, the sorting sequence in a master field must have a higher precedence (lower sort priority number) than a sorting sequence assigned to a detail field. This rule ensures that the detail field remains subordinate to the master field.

Viewing Retrieved Records

After entering the data qualification and sort order specifications (if any), choose the Go operation on the Retrieve frame to display the data you have specified.

The operations available on the Retrieve frame while viewing data vary depending on the type of query target and whether the query target has a table field or simple fields.

Viewing Retrieve Results for a Table

If the query target is a table in simple-fields format, you view retrieve results one row at a time:

Operation	Description
Next	Retrieves the next record.
Query	Clears the window of all retrieved information and allows you to make another query.
Help, End	Standard operations.

Use the Next operation to display the next record. To start a new query, click Query. Click End to exit to the QBF Execution Phase frame.

The following figure shows query results for a table displayed on a form in simple-fields format.

```
🔏 Ingres - QBF
                                                                                                  _ 🗆 ×
                                              EMP Table
Name: Alcott, Scott_
Hourly Rate: $ 50.00____
                                                           Title: Sr Programmer_
Manager: Wolfe, Neal____
 Next(F9) Query(SH-F2) Help(F1) End(F10)
```

If the query target is in table-field format, you can view multiple rows in the table field. The operations on the menu are Query, Help, and End.

After QBF displays all rows retrieved by your query, regardless of format, it displays the following message:

No more rows in query

Viewing Sort Results for a Master/Master JoinDef

QBF displays the sorted results of a query on a Master/Master JoinDef with records from each table in simple fields or in table fields.

If the rows are displayed in simple-fields format, click Next to display the next single record.

The following table shows operations for a Master/Master join with simple fields:

Operation	Description
Next	Retrieves the next record (row) of data.
Query	Clears the window of all retrieved information and allows you to make another query.
Help, End	Standard operations.

If the rows are displayed in a table field, scroll through the data, if necessary, to see all rows. QBF displays an Out of Data message if you attempt to scroll past the end of the table field. You can suppress this message by changing the setting of the II_SCROLL_MSG environment variable/logical. For details, see the *System Administrator Guide*.


The following table shows operations for a Master/Master join with table fields:

Operation	Description	
Query	Clears the window of all retrieved information and allows you to make another query.	
Help, End	Standard operations.	

Viewing Sort Results for a Master/Detail JoinDef

When you retrieve a master record in a Master/Detail JoinDef, QBF automatically retrieves all detail records associated with it. The master record is displayed in simple fields. The detail records display in either a table field or simple fields, depending on which format you chose when you created the JoinDef.

Regardless of the format, use the NextMaster operation to go from one master record to the next. Within each master you can view all associated detail records. If the display includes a table field for the detail records, QBF loads all detail records for a single master into the table field. If all the rows do not fit in your window, you can scroll through them. QBF displays an Out of Data message if you attempt to scroll past the end of the table field. You can suppress this message by changing the setting of the II_SCROLL_MSG environment variable/logical. For details, see the *System Administrator Guide*.



The following figure is an example of a retrieval for a Master/Detail JoinDef.

The preceding example includes a master row and its associated detail rows. The detail rows in the table field are sorted in ascending order, based on the Task column.

The following table shows the operations when records appear only in simple-field format:

Operation	Description
NextMaster	Retrieves the next master record.
Query	Clears the window of all retrieved information and allows you to make another query.
NxtDetail	Retrieves the next detail record.
Help, End	Standard operations.

Use the NextMaster operation to display a master record and the first detail record associated with it. Use NxtDetail to display the next detail record associated with the same master; the master data cannot change. If you choose NxtDetail when the last detail for that master has been displayed, QBF displays the following message:

No more details for this master . . .

It then retrieves the next master and its first detail record.

When QBF has displayed all rows delivered by your query, it displays the following message:

No more masters

No Rows Meeting Specifications

If QBF does not find any rows meeting the specifications in your query, it displays the message:

No rows found for this query

It then returns you to the Retrieve frame to enter a new query.

Transaction Deadlock in Retrieve Mode

If a transaction deadlock occurs while you are viewing data retrieved by a query, QBF aborts the query and returns you to the Query Specification frame to enter a new query. When this occurs, QBF displays the following message:

Deadlock detected, your transaction has been aborted.

Exiting the Retrieve

To set up another query specification, click End or Query. If you invoked the Retrieve operation from the command line with the qbf or query command, you can return to the operating system by choosing Quit.

QBF Update Operation

This section explains how to use the Update operation to modify, update, or delete existing data. Using Update, you fill in a form to retrieve rows of data, modify or delete the data in the form, and then save your results to the database.

Starting the Update Operation

You can start the Update operation from the operating system or from the Ingres Menu.

The following steps describe how to start the Update operation from the Ingres Menu. The chapter "Using QBF" discusses steps 1 through 4 in more detail.

- 1. Choose Queries.
- 2. Choose QBF to reach the QBF Start-Up frame.
- 3. Choose QBFNames, JoinDefs, or Tables for the appropriate Catalog frame.

Note: When working with a table query target, choose SimpleFields or TableField format.

- 4. Place the cursor on the name of your query target in the Catalog frame and choose the Go operation. QBF displays the QBF Execution Phase frame.
- 5. On the QBF Execution Phase frame, choose Update. QBF displays the Update frame, containing an appropriate query form for the query target you chose. At the top of the Update frame query form is the name of your query target.

The Update frame provides the following operations for use with the query form:

Operation	Description
Go	Executes the query.
Blank	Clears the current entries from the frame.
LastQuery	Displays your last query specification for editing.
Order	Sets the order of rows for sorting.
ListChoices	Lists the available choices for the selected field on a QBFName.
Help, End	Standard operations.

- 6. Specify the row(s) you wish to retrieve for updating by filling in the appropriate fields on the Update frame query form. This procedure works in the same way as filling out the form on the Retrieve frame, as described in the chapter "Working with QBF Operations."
- 7. Choose Go to display the data that matches your specified criteria. You can then modify or delete this data as explained in Modifying Data and Deleting Data.

If QBF does not find any rows meeting your specifications, it displays the following message and returns you to the Update frame query form to enter a new query.

No rows found for this query

Modifying Data

QBF displays the data from your query on a data display form in the Update frame. You can edit or delete this data, with the following exceptions:

- If the table or tables you are accessing have permissions assigned to them, you need permission to perform an update.
- If JoinDef update rules specify that the table or tables you are accessing cannot be updated, you cannot update columns in that JoinDef.

- If JoinDef update rules have been applied to a join column on the frame, the cursor cannot stop on that field.
- Delete rules have been established to prevent deletion of the rows in the underlying tables.

For more information on restrictions for updating JoinDefs, see <u>Update and Delete Rules</u> in the chapter "Using JoinDefs in QBF."

To edit the data, type your corrections over the displayed text. QBF does not commit your changes to the actual database as you enter them, but stores them in a temporary buffer. To save your changes and update the database, choose Save on the Update frame data display form menu.

Within QBF, you can change only one row of data at a time. However, you can use the SQL update statement in the Interactive Terminal Monitor to change all qualifying rows of data at one time.

Update Frame Data Display Form Operations

The operations for use with the Update frame's data display form vary, depending on the type of query target and whether the format is for a table field or simple fields. QBF automatically presents the operations that are appropriate for the query target and format you chose.

Operation	Description
NextMaster	Displays the next row of data from master and associated detail table fields.
NxtDetail	Displays the next row of detail. (This operation is valid only for JoinDefs in simple-field format.)
AddDetail	Adds a new detail record to the currently displayed master. (This operation is valid only for JoinDefs in simple-field format.)
Next	Displays the next frame of data.
Query	Returns to the Update frame query form and clears all fields so that you can enter a new query, including sort sequence and order values.
Delete	Deletes the entry in the database, as shown on a simple-fields data display form. Displays a new menu to specify the deletion on a table-field form or Master/Detail JoinDef.
Save	Saves the changes from this session in the database.
Help, End	Standard operations.

Adding New Detail Rows to a JoinDef

Use the AddDetail operation on the QBF Update frame data display menu to add detail table records when both the master and detail table of a join definition are displayed as simple fields.

After you have displayed a master table record and corresponding detail record, you can add a new detail record by using the following procedure:

- 1. Position the cursor on the first simple field for the detail table.
- 2. Type the data for the new record over the existing data in the currently displayed detail record.
- 3. Instead of *saving* the modified record, choose the AddDetail operation from the menu.
 - QBF writes the new detail record into a temporary buffer and redisplays the prior detail record (as it appeared before you overtyped it with the new data). If desired, you can continue to add additional records by repeating the preceding procedure. Be sure to choose AddDetail rather than Save to write the new record to the buffer; otherwise, you overwrite the existing record rather than add a new one.
- 4. When you are done entering new detail records, choose Save to commit the new records to the database.

Do not choose AddDetail until you have typed the new data into the existing record. If you choose this menu option before typing the new data, one of the following occurs:

- If duplicates are allowed, QBF enters the record that currently appears in the window as a duplicate record.
- If duplicates are not allowed, an error message displays.

Deleting Data

You use the Delete operation to erase an entire record (row) of data. The menu on the Update frame for the data display form includes this operation, regardless of the type of query target you specify.

As you delete rows, QBF writes the deletions to a temporary buffer. If you delete one row in a table field, the remaining rows scroll upward.

When you choose Delete on an Update frame with only simple fields displayed in the data display form, the menu is unchanged. In this display format, rows can only be deleted one at a time. QBF does not commit the deletions until you choose Save.

When you choose Delete for a data display form that displays a JoinDef or a form with a table field or both simple fields and a table field, the menu changes. It includes the operations appropriate to the various combinations of query target types and display formats listed in the following table.

To delete a detail row in a JoinDef or in a form that includes a table field, place the cursor on the row to be deleted and choose Delete. When the Delete menu appears, choose DetailRow.

Operation	Description
Master	Deletes the master record currently displayed and all its detail records.
AllDetailRows	Deletes all retrieved rows in the table field for the detail tables of the master currently displayed—QBF deletes all rows regardless of whether they are visible in the window.
DetailRow	Deletes the single detail row indicated by the cursor in table-field display.
Detail	Deletes the currently displayed detail row in simple-fields display.
ListChoices	Lists the available choices for the selected field on a QBFName.
AllRows	Deletes all retrieved rows in the table field, regardless of whether they are visible in the window.
Row	Deletes the row indicated by the cursor.
Help, End	Standard operations.

Saving Updates

QBF stores your modifications and deletions in a temporary buffer. To save the changes permanently, choose the Save operation on the data display form Update frame. As QBF writes your changes to the database, it displays this message:

Saving changes . . .

When the process is complete, QBF displays the following message and returns you to the Update frame query form so that you can specify a new query: Changes saved.

When you choose the Save operation, QBF attempts to update the database with the current contents of all fields on the form, not just the field or fields that you changed. It also checks the contents of all fields on the Update data display form for data type consistency, integrity violations, and permission violations, and reports any errors.

Update Operation and JoinDef Rules

When you update or delete rows using a JoinDef, be aware of the update and delete rules for that JoinDef. For more information, see Update and Delete Rules in the chapter "Using JoinDefs in QBF." If you attempt to save invalid changes, QBF does not commit your updates to those tables.

Errors Reported During the Save Process

If you attempt to update rows for which you do not have permission, QBF does not commit your changes.

If you violate an integrity constraint (which guards against data of the wrong data type being entered), QBF displays a message to that effect. If this happens, you can:

- Press End to return to the field with the error and correct it.
- Press More to get more information about the error.

Transaction Deadlock in Update Mode

Deadlocks can occur at two times during the QBF Update function. First, a deadlock can occur while you are editing rows of retrieved data. QBF displays the following error message:

Deadlock detected, your transaction has been aborted.

This means that you cannot update any more rows retrieved by your last query. However, any changes you have made before this point are still stored in the buffer. In this situation, QBF displays the following message:

Do you wish to save the changes made thus far?

Answering \mathbf{y} (yes) is equivalent to selecting the Save operation. As QBF writes your changes into the database, it displays the message:

Saving Changes

The second type of deadlock can occur during the Save operation while your changes are being written from the temporary storage buffer to the database. In this case, QBF displays the message:

Deadlock detected, your transaction has been aborted.

In this situation, all changes made since the last Save operation are lost and you must begin again with a clear form.

Exiting the Update Operation

If you want to commit your modifications or deletions to the database before exiting the Update frame, choose Save from the data display form's menu on the Update frame. This also returns you to the Update frame's query form.

To leave the Update operation, choose End from the query form's menu on the Update frame. End returns you to the Query Execution frame.

If you make changes to the data and try to exit the Update frame's data display form before executing a Save operation, QBF asks:

Do you wish to leave UPDATE without saving changes?

If you type y (yes), QBF allows you to leave without saving your work. If you type n (no), QBF redisplays the Update frame's data display form, enabling you to select the Save operation.

Chapter 6: Using JoinDefs in QBF

This chapter explains how to create, edit, and delete JoinDefs.

What Is a JointDef?

A JoinDef, or join definition, is a definition of a virtual table that conceptually joins together multiple tables in your database. A JoinDef does not exist as an actual table in the database, but temporarily links the information in different tables by their common columns. This enables you to work with the data in the tables simultaneously, as if it was contained in one table.

For example, in a relational database in which each table typically is devoted to information related to a single item of interest, you can have the following separate tables:

- Staff (employee's name, hourly rate, title, and manager)
- Tasks (employee's name, project identification, tasks, and the hours spent on each task)


If you wanted to find out what tasks have been assigned to employees who work for a certain manager, you would need to link the information in the Staff and Tasks tables by employee name.

When you use a JoinDef to guery multiple tables, you gain access to the data in all of the columns in all of the joined tables. When you use a JoinDef to append new data or update existing data, QBF writes identical information into the common columns of the different tables in the JoinDef. For example, if a common Lastname column links two tables, the same last name is simultaneously written into both Lastname columns. QBF writes changes or additions you made in non-common columns only to the table containing that column.

A JoinDef is similar to a view in that you can use either to display data contained in more than one table. However, whereas a JoinDef contains *all* of the columns from the joined tables, a view can contain only *selected* columns from the tables on which it is based. Also, you cannot use a view to append new data or modify existing data in the underlying tables, as you can with a JoinDef. You create JoinDefs with QBF, but you must use a query language to create a view. Once created, QBF lists a view as if it were a table, but always lists JoinDefs separately from tables. For additional information on views, see your query language reference guide.


You can use JoinDefs in QBF, RBF, and VIFRED. However, you cannot manipulate or access JoinDefs from within the Tables Utility, as you can a view.

The map in the following figure illustrates the route QBF takes when you choose JoinDefs from Ingres Menu or from the QBF menu:



JoinDef Rules

To be linked with a JoinDef, two or more tables must have at least one column with the same data type and one or more common values in those columns. For example, if a table named Projects and a table named Departments both have a column named Dept, which contains names of departments, the common values in the two Dept columns join the two tables in the JoinDef, as shown in the following figure:




While the two columns in this example have the same name, this is not required for a JoinDef.

If you think of tables as two-dimensional grids of columns and rows, then JoinDefs are the third dimension. JoinDefs can be described as corridors linking the columns of two tables.

JoinDefs must follow these rules:

- The two join columns need not have the same name.
- Join column pairs must either be of the same basic data type, such as an integer column joined to another integer column, or be of data types that are coercible to one another.
- Except in a Master/Detail join, the data values in all the join columns must be identical in the joined tables in order for a query to return that row.
- A JoinDef can join a total of 10 tables, either Master or Detail, that together total no more than 600 columns.
- You can specify up to 50 columns in each table as join columns.
- You can create a JoinDef for a single table, which has several advantages over using the table itself as a query target. See Single-Table JoinDefs.

The figure below shows some examples of JoinDefs. As long as you do not exceed the total limit of 10 tables, you can join one table to as many other tables as you desire. However, any given JoinDef can have only one Master-Detail join.



Queries only return those records that have identical data values in all the join columns. Thus, if the Projects and Tasks tables are joined by the Project column and they share only the single project name of Release6, a query returns only one row of data from each table. If they share the project names Release6 and Popup, then a query returns two rows from each table.

Join Columns with Coercible Data Types

Data columns are *coercible* when their data type can be changed from one to the other. An integer data type, for instance, can be changed (coerced) into a floating-point data type. In the same way, a money data type can be changed into a floating-point data type. But a character data type cannot be coerced into a numeric type.

When you join two columns that have coercible but not identical data types, QBF displays a warning message, and QBF adopts the data characteristics of the table column listed first in the JoinDef.

For example, if two character columns of different lengths are joined, the data display on the QBF form uses the length of whichever column was specified first in the JoinDef. The same principle holds true for column nullability and data type. If two columns, one nullable and the other not, are joined, Query-By-Form treats them both as nullable or not nullable according to which was listed first in the JoinDef. If a floating-point column is joined to an integer column, QBF uses the data type of the first one.

Multiple Join Columns

The maximum number of join columns in a JoinDef is 50. When you use multiple columns in a join other than a Master/Detail join, every set of join columns must have common values in order for the query to return a row. For example, if one set of join columns contains last names, and a second set of join columns contains first names, a query returns only the rows in which the first and last names are both identical. Thus, if two joined tables contained the first name Thomas and last name Jefferson in a particular row, a query returns data for that row from both tables. But if one table contained the first name Thomas and last name Jefferson, and the other contained the first name Thomas and last name Becket, a query cannot return any rows because only the Firstname join columns had a name in common.

Join Types


QBF allows two types of joins:

- Master/Master (one-to-one)—These JoinDefs correspond to an ordinary relational equi-join.
- Master/Detail (one-to-many)—This type of JoinDef corresponds to a relational outer join.

The terms *master* and *detail* are meaningful only as they relate to each other. The determining factor in whether a join is one-to-one or one-to-many is the nature of the data in the tables you are joining.

Each column of each table in a *Master/Master* join contains singular or exclusive properties. For example, the Staff table lists each employee only once and the Managers table lists each manager only once. If you join the Name column in the Staff table to the Manager column in the Manager table, QBF returns one row of data for every employee who is also a manager.


In a *Master/Detail* join, each detail table contains at least one column that is not restricted to one item. That is, the column contains non-singular or non-exclusive information. The join column—the common element—is the bridge between each column in the master table and the column(s) in the following detail table:



For example, in the Tasks table both the Project and Task columns contain non-singular information. Wallace Fielding, for instance, might have three rows showing that he works on the Portfolio project (Project column). Within the Portfolio project, he works on three different tasks: Design, Manage, Test (Task column). Each Portfolio task is on a separate row in the table.

If the EMP table (master) were joined to the Tasks table (detail) through the Name column in each, you could access information such as the tasks, projects, and hours (from the Tasks table) of employees who work for a certain manager (from the Staff table).

Thus, the many entries in the Task column of the Tasks table are accessible through the one entry in the Manager column of the Staff table. The following figure shows Jones, Betty, in the Manager field of a form for the EMP table.



The following figure displays a record retrieved for one of the employees she manages.




Master/Master JoinDefs

When used for a query, a Master/Master JoinDef selects records from two or more tables based on the common values in the join columns. While the respective join columns must share at least one common value, they need not share all values. However, only records containing common values are returned in a query.

For example, suppose two tables are joined by the Lastname column that both tables have. The Lastname column of the first table contains the names Adams, Baker, Choy, and Diaz, while the Lastname column of the second table contains the names Adams, Baruch, Choy, and Donelli. In this case, a query returns only the records in both tables that contain the names Adams and Choy.

When you create a Master/Master JoinDef, you enter the table name and whether it is a master or detail table on the JoinDef Definition frame. For more information, see Creating a JoinDef.

In the following figure is an example of a Master/Master JoinDef on the JoinDef Definition frame.



The following figure shows the data retrieved from the JoinDef displayed in the preceding figure.



Master/Detail JoinDefs

When QBF executes a query in which the query target is a *Master/Detail JoinDef*, the data appears to have come from two tables—one that is a set of all the master tables and one that is a set of all the detail tables. The master table information is displayed as simple fields, and the detail table information is displayed as either a table field or simple fields.

If there are no detail records for the master record, QBF still retrieves the master record. Thus, QBF retrieves and displays master records even if there are no corresponding identical values in the detail table join column.

A JoinDef can contain several Master/Master joins, but only one Master/Detail join. You can include multiple detail tables relative to the master table(s) in a Master/Detail JoinDef by joining them to the detail table in the Master/Detail join. For example, the second figure in this chapter shows a Master/Detail relationship combining only one pair of tables. This figure also shows several pairs joined together with Master/Master joins and several Detail tables joined to each other. For illustrations of a Master/Master JoinDef and resulting data, see the preceding two figures.

Automatic Joins

Columns involved in a join need not have the same name, just the same data type and common values. However, when tables specified in a join have columns with the same name and data type, those columns automatically become the join column. This is known as an automatic, default, or natural join. QBF displays a list of join columns on the JoinDef Specification frame, described later in this chapter. You can specify different columns as the join columns or remove columns from the join columns list. For more information, see Specifying Join Columns.

Keep in mind that when two tables have multiple join columns, all the data values in each join column must be identical for a query to return that row of data. For this reason, you must delete unneeded joins.

Fields on a JoinDef Form


You can use a JoinDef to append, retrieve, or update data. The JoinDef form contains fields representing columns in all of the joined tables. On a default form, QBF marks the common columns—the join fields—by displaying them in reverse video if your monitor has that capability.

Creating a JoinDef

Creating a JoinDef requires specifying the tables, the common join column(s), the update and delete rules, and the columns to be displayed.

The following steps describe the general process of creating, testing, and saving a JoinDef. (The steps and frames are all discussed in more detail later in this chapter.)

- Choose JoinDefs from either the Ingres Menu or from the QBF Startup frame.
- 2. Choose Create from the JoinDefs Catalog frame.
- 3. When the Creating a JoinDef pop-up form appears, place the cursor on one of the available options and choose the Select operation:
 - Blank (to create a JoinDef from a blank frame)
 - Duplicate (to base a JoinDef on an existing JoinDef definition)




If you are basing the new JoinDef on an existing one, the Creating a JoinDef by Duplication pop-up form appears. See the following figure. Proceed to Step 4.

If you are creating a JoinDef from a blank frame, the JoinDefs Catalog frame appears. Proceed to Step 5.

4. Enter the name of the existing JoinDef on the Creating a JoinDef by Duplication pop-up form and choose the Select operation.

If you do not know the name of the existing JoinDef, select the ListChoices operation to display a list of the available choices.



5. When the JoinDefs Catalog frame appears, choose the Create operation. See the following figure.

See JoinDefs Catalog Frame and JoinDef Definition Frame.

Type the JoinDef name in the space following JoinDef Name and press Return.

Perform the next three steps for each table you want to join. Use Tab and the arrow keys to move from column to column and row to row as needed.

- 7. Type the kind of table it is (Master or Detail) in the Role column. If none of the tables has a Master/Detail relationship to each other, enter them all as Master tables even if some or all of them are Detail tables on other JoinDefs. Enter as a Detail table any table that has a detail relationship (many records to one record) to any master table.
- 8. Type the table name in the Table Name column.

If you do not know the table name, use the ListChoices operation to display a list of the available tables.

- 9. Type an optional abbreviation for the table name in the Abbreviation column.
- 10. Type **n** (no) in the Table Field Format field if you want to view all your data in simple-fields format.

The default is to display the data in table-field form.

11. Choose Joins to display the JoinDef Join Specification frame. If QBF has automatically established join columns to join the tables, they are displayed. If necessary, enter or change the join specifications. For more information, see Specifying Join Columns.

12. Return to the JoinDef Definition frame and save your JoinDef by selecting the End operation. For more information, see Saving JoinDefs. Before or after you save your JoinDef, you can perform either or both of the optional enhancements listed below.

Optional JoinDef Specifications


You can further enhance your JoinDef specification by performing one or both of the two optional operations listed below. (If you perform either of these operations, be sure to save the changed JoinDef when you are finished.)

- To establish update and delete rules for the join columns, choose Rules to display the JoinDef Update & Delete Rules frame. For more information, see Update and Delete Rules.
- To hide one or more columns from view on the default query form created by the JoinDef, choose ChangeDisplay to display the JoinDef Change Display frame. For more information, see Changing the Display of JoinDefs.

To run a JoinDef, choose the Go operation. The QBF Execution Phase frame appears. Choose Append, Retrieve, or Update. A default form for your new JoinDef appears. Use the menu items as desired.

JoinDefs Catalog Frame

The JoinDefs Catalog frame, shown in the following figure, displays a list of existing JoinDefs and a menu of operations for working with JoinDefs.




The menu operations are described in the following table:

Operation	Description
Create	Guides/enables creation of a JoinDef.
Destroy	Removes a JoinDef from the database.
Edit	Enables editing or viewing of an existing JoinDef.
Rename	Changes the name of an existing JoinDef.
Go	Runs a query on an existing JoinDef.
MoreInfo	Displays additional information about the JoinDef.
Help, End, Quit	These are standard operations.

JoinDef Definition Frame

Use the JoinDef Definition frame to specify the tables to be included in a JoinDef and their roles (Master or Detail), and whether the JoinDef must include table fields.



The following table defines the menu items at the bottom of the frame:

Operation	Description
Go	Executes the JoinDef.
Blank	Erases the current entries in the window.
ChangeDisplay	Drops unnecessary columns from the JoinDef specification.
Joins	Displays the JoinDef Specification frame for viewing or changing the join columns.
Rules	Establishes rules for deleting or updating data in the tables included in the JoinDef.
Save	Saves the JoinDef.
ListChoices	Lists the available choices for the selected field.
Help, End, Quit	These are standard operations.

JoinDef Name

On the JoinDef Definition frame, name a new JoinDef by typing a unique name of no more than 32 letters or numbers. A database cannot have two JoinDefs with identical names. For naming conventions in databases compliant with ANSI/ISO Entry SQL-92 standards, see the chapter "Fundamentals of Using Querying and Reporting Tools."

If you create a JoinDef based on an existing JoinDef, enter a different name for the new JoinDef on this frame.

Role

In the Role column, type either Master or Detail for the role of each table. You can use m or d as abbreviations.

At least one table in every JoinDef must be entered as a Master table. Keep in mind that Master and Detail are relative terms. You can have as many Master tables in a JoinDef as you need (up to the maximum of 10). You must designate a table (or tables) as a detail table only if it has a many-to-one relation to one or more of the master tables. For example, the Staff table lists an employee only once, while the Tasks table can list that employee many times for many different tasks. Thus, the Tasks table has a many-to-one relationship to the Staff table and is designated as a detail table in a JoinDef that links Staff to Tasks.

A table that is a master in one JoinDef can be a detail table in some other JoinDef. You need to specify each table's role as it relates to the current JoinDef.

For example, the Staff table contains each employee's name, title, hourly rate, and manager. The Manager table contains the names of managers and their titles. If you joined these two tables on the Manager column in each table, the result is a Master/Detail join because one manager in the Manager table might be the manager for several different employees. Thus, this join could be used to list those employees supervised by each manager.

However, if you joined these two tables on the Manager column in the Manager table and the Name column in the Staff table, the result is a Master/Master join because those employees who were managers are listed only once in each table. You can use this join to display the title and hourly rate of those employees who were managers.

A complicated JoinDef containing many tables can have multiple master and multiple detail tables.

Table Name

In the Table Name column, enter the name of each table. You can enter a maximum of 10 names (that is, you can join a maximum of 10 tables in a JoinDef).

Owner

In the Ownercolumn, enter the name of the schema to which the table belongs; this also substantiates ownership. If you do not enter a name here, QBF assumes the owner is the same as the current user ID. For more information on schemas, see Using Schemas for Owner Qualification.

Abbreviation

An *abbreviation* is an alternate, usually shortened, name for a table. For example, the Projects table could be abbreviated to the letter p. Abbreviations are also sometimes known as *correlation names* or *range variables*. If you do not specify an abbreviation, QBF assigns the table name as the abbreviation.

Abbreviations are necessary when you want to join two identically named tables with different owners, or to join a table to itself. In these cases, use an abbreviation for one of the table names when you specify the join. For more information, see Single-Table JoinDefs.

Choosing Table-Field Format

The *Table Field Format?* or *Simple-Fields Format?* question controls how this JoinDef displays data:

- Master/Master—If the JoinDef contains all master tables, answer this question with y (yes) to specify table format for all data. Answer this question with n (no) to display all data one record at a time in simple-field format.
- Master/Detail—If the JoinDef contains both master tables and detail tables, answer this question with y (yes) to specify simple-field format for all data for all the master tables, and table format for all data for the detail tables. Answer this question with n (no) to display all data for all tables one record at a time in simple-field format.

Table-field format is particularly useful for Master/Detail joins, where many detail rows in the table field can correspond to a single row in the master table.

After you complete the JoinDef Definition frame, you can specify other components of the JoinDef-the join columns, the update and delete rules, and the display characteristics—as explained in the following sections.

Specifying Join Columns

When you create a JoinDef on the JoinDef Definition frame and select either Go or Save, QBF selects as the join columns the columns in the two tables that have the same name. QBF then compares the data types, leading to one of three possible situations:

- The data types are the same, in which case QBF completes the join.
- The data types are not the same, but are coercible.
 - This means that the data types can be changed from one to the other. For example, a money data type can be coerced into a numeric type. In this situation, QBF displays a warning message, but completes the join.
- The data types are different and not coercible.

For example, a character data type cannot be coerced into a numeric type. QBF prompts you to modify your joins using the JoinDef Specification frame in order to establish proper joins. For more information, see Finishing with the JoinDef Join Specification Frame.

To reach the JoinDef Specification frame, choose the Joins operation. The JoinDef Join Specification frame includes a list at the top of the frame that details existing joins, a table field for displaying information about table column names, and a menu of operations.



You can use the JoinDef Join Specification frame to change Join columns.

For example, in a JoinDef containing the tables Staff and Tasks, QBF selects the column called Name in each table as the join column. If there are no common columns with the same name, the JoinDef Join Specification frame is displayed empty, and you must enter the join columns you wish to use.

Operation	Description
Rules	Establishes rules for deleting or updating data in the tables included in the JoinDef.
GetTablDef	Gets information on columns in a table.
ListChoices	Lists the available choices for the selected field.
Cancel	Cancels any changes made to the join specification and returns to the JoinDef Definition frame.
Help, End	These are standard operations.

The rules and GetTableDef operations are described later in this chapter.

Viewing or Changing Joined Columns

In the following figure, the Name column in the Staff table is the join column with the Manager column of the Manager table. The MM between the twotable/column names indicates that this is a Master/Master join.



The following table describes the table field at the top of the JoinDef Join Specification frame shown in the following figure:

Field	Description
Column	Contains the column name of join column(s) in the table. Column name format: <i>abbreviation.columnname</i> , where <i>abbreviation</i> is the abbreviation of the table name and <i>columnname</i> is the column name. In the above figure, the column name m.manager means the name column from the Manager table. The column on the left is joined to the column on the right.
Join	Indicates whether the join is Master/Master (MM), Master/Detail (MD), or Detail/Detail (D/D).
Column	Contains the column name of join column(s) in the second table. Column name format is the same as for the first column. In the above figure, the column name s.name means the name column from the Staff table.

You can add, delete, or change join specifications by editing the table field at the top of the frame. If you alter the join specification, make sure that the two join columns in each table are of the same data type.

Getting Information on Table Column Data Types

To display a list of a table's columns and column formats, enter the name (or abbreviation) of the table and select the GetTableDef operation. That table's columns and their data types are then displayed, as shown in the following figure.



Finishing with the JoinDef Join Specification Frame

When you exit the JoinDef Join Specification frame by selecting Rules or End, QBF checks the validity of your entries and reports any errors it finds. If the join information is valid, you exit the frame. If it is not valid, QBF displays an error message that indicates the problem and returns you to the frame so that you can correct it:

- Select Rules to set rules for modifying the tables in your JoinDef. For more information, see <u>Update and Delete Rules</u>.
- Choose the End operation to return to the JoinDef Definition frame.
- Choose the Cancel operation to cancel any changes made to the JoinDef Join Specification frame and return to the JoinDef Definition frame.

Single-Table JoinDefs

Although you can use a table *as is* for a query target, if you define a table as a single-table JoinDef you can:

Specify that the table is displayed in table-field format rather than simple-field format.

- Set up a Master/Detail or Master/Master relationship between different fields (columns) in the same table.
- Delete columns containing sensitive or unnecessary information from the display by using the ChangeDisplay operation.
- Protect columns from updates but allow queries to display data by using the Rules operation.
- Disable deletion of rows by using the Rules operation.
- Save these formatting features in the database for later execution.

To build a single-table JoinDef, follow these steps:

- 1. Follow Steps 1 through 4 in Creating a JoinDef, earlier in this chapter, to get to the JoinDefs Catalog frame.
- Choose Create on the JoinDefs Catalog frame.
- 3. Enter a name for the JoinDef.
- 4. On the JoinDef Definition Frame, enter master in the Role column, type the name of the table you wish to use in the Table Name column. In the Owner column, type the name of the schema to which the table belongs, if appropriate. Then enter an optional abbreviation for the table in the Abbreviation column.
 - If you are joining a table to itself in order to create a Master/Detail or Master/Master relationship between two columns in the same table, perform Step 5. Otherwise, skip to Step 6.
- 5. To establish a Master/Detail or Master/Master relationship between two columns in the table, move the cursor down to the second line. Enter d (detail) or m (master) in the Role column of the second line, as appropriate. After entering the role, enter the table name and, if necessary, the table's schema name. Then enter a unique abbreviation for the table in the Abbreviation column.
- When you have finished specifying the tables, specify the field format. Table-field format is the default, which you can change to No if desired.
 - If you are simply creating a single-table JoinDef in order to establish display or update and delete rules, skip to Step 9.
- 7. Choose the Joins operation to display the JoinDef Join Specification frame.
- To create a Master/Detail join between two different data columns in the table, type blank spaces over the default join specifications established by QBF to delete them.
 - Specify the join by entering [schema.]tablename.columnname for the join's master data column in the left side of the form and alternateabbr.columnname for the detail data column in the right side.
 - Whenever you enter a column name in the right side of the form, you always use the alternate abbreviation for the table.

- 9. Choose the End operation to finish specifying the join columns.
- 10. Choose the Go operation. The Query Execution frame is displayed.

You can choose the Rules operation to use the JoinDef update and delete rules frame to modify update and deletion rules. You can use the JoinDef Change Display frame to hide specified columns from view when you use the JoinDef form. The following sections provide details.


Update and Delete Rules


A JoinDef allows you to modify data in single or multiple tables using a form. You can use the form to delete or update information in the tables. QBF provides update and delete rules that allow you to control the impact of changes made when executing queries on multiple tables. These rules allow you to specify the fields in which a user can perform updates and the tables from which a user can delete records.

To reach the JoinDef Update & Delete Rules frame, choose Rules on the JoinDef Definition frame or the Join Specification frame.

Operation	Description
Joins	Goes to the JoinDef Specification frame.
Cancel	Cancels any changes made in this frame and returns to the JoinDef Definition frame.
ListChoices	Lists the available choices for the selected field.
Help, End	These are standard operations.

Default Update and Delete Rules





The Update default is No and the Delete default is Yes for all columns in all tables in the JoinDef. This means that, by default, updates to the join column or columns are not allowed, but records can be deleted from any table in the JoinDef.

You can browse through defaults and modify them to suit your needs. Change the Yes and No values in the last column in each list to specify whether or not data in a particular table or column can be updated or deleted. To do so, move the cursor to the value and type \mathbf{n} (no) or \mathbf{y} (yes) over the current entry.

Determining Update Rules

Each row in the Update Information list on the JoinDef Update & Delete Rules frame lists a table in the join and a join column in that table. If a table has more than one join column, the table name appears in more than one row.

The list in the Update column shows whether updates are permitted for the join column. The default for all join columns is No. This means that any changes to values in the join column cannot be entered into the database. Yes in the Update column allows changes to go into the database. You can allow updates to a join column in one table and yet deny them in the corresponding join column of the second table.

These update rules only apply to join columns. The other columns in a table can be updated by the user. If you want to specify that a column that is not a join column cannot be updated, you must edit the form with VIFRED.

Changing update rules can control the movement of the cursor through the fields on a form for a JoinDef. If neither table allows updates to a join column, that field becomes a display-only field on the JoinDef form and you cannot move the cursor into it.

Determining Delete Rules

The list in the Delete Information section on the JoinDef Update & Delete Rules frame contains one row for each table in the JoinDef. This row specifies its type (master or detail), table name or abbreviation, and whether or not rows can be deleted from that table. Again, only the Delete list can be modified. Move the cursor to the entry and type the new value. Changing Yes to No specifies that rows cannot be deleted from that table. Menu choices during query execution change to fit the rules you have specified.

Exiting the JoinDef Update and Delete Rules Frame

To go to the JoinDef Join Specification frame, choose Joins. For more information, see <u>Specifying Join Columns</u>. Click End to finish and return to the previous frame. Click Cancel to cancel any changes and return to the JoinDef Definition frame.

Changing the Display of JoinDefs

You can decide not to display certain columns on a form when you execute a JoinDef. For example, you can hide blank columns or columns containing confidential information in one of two ways:

- To avoid displaying certain columns, build a QBFName from a custom form edited with the VIFRED. For more information about QBFNames, see the chapter "Using VIFRED."
- Use the ChangeDisplay operation as explained below to delete the display of a column from a OBF form.



When you choose ChangeDisplay on the JoinDef Definition frame, the JoinDef Change Display frame appears, as in the following figure.

Operation	Description
NextTable	Displays the next table in the JoinDef.
Delete	Deletes a column from the display of the JoinDef when a query is executed.
Undo	Backs out the effects of the last Delete or Undo action.
Help, End	These are standard operations.

On this form, you can scroll the Table name field to see the entire table name, schema.tablename, if necessary.

The Column Name column and the Field Name column both list the names of table's columns. In most cases, the names listed in each column are identical. However, when joined tables have non-join columns with the same name, QBF changes one of the internal field names for JoinDef identification purposes. In this case, the Column Name column lists the original column name as it still appears in the table, and the Field Name column gives the altered name as it appears on the JoinDef.

For example, suppose the Manager table is joined to the Staff table by joining the Manager.Manager column to the Staff.Name column. In this example, both tables have a column named Title that is not the join column. On the JoinDef Change Display frame for the Manager table, both Column Name and Field Name display title, but on the Change Display frame for the Staff table, Column Name shows title and Field Name shows title0.

Deleting Fields from JoinDef Displays

Use the Delete operation on the JoinDef Change Display frame to remove unwanted columns from the display. If the JoinDef contains more than one table, you must delete columns from each table separately.

Columns deleted on this frame are deleted from the JoinDef form only, and not from the database itself.

To delete a column from a table in the JoinDef, first display the table on the form. Select the NextTable operation to display the proper table, if necessary. Place the cursor on the row you want to delete and choose the Delete operation. JoinDef join columns are indicated by an asterisk (*) in the leftmost column. JoinDef join fields cannot be deleted.

If you change your mind about deleting a row, click Undo before pressing any other key.

Exiting the JoinDef Change Display Frame

Choose the End operation to return to the JoinDef Definition frame.

You can then click Save to save the changes. If you click Quit without saving, QBF reminds you of this and asks whether you want to quit anyway.

Testing JoinDefs


QBF provides a convenient way to test your JoinDef while you are still defining it. At the JoinDef Definition frame, choose the Go operation. QBF builds a form for the JoinDef and automatically goes into the query execution phase. In query execution, you can append, retrieve, or update data in the tables used in your JoinDef. These operations are described later in this chapter.

When you exit query execution after testing a JoinDef, QBF returns you to the JoinDef Definition frame so that you can view or modify your JoinDef entries. After making changes, you can easily switch to query execution phase by clicking Go again.

Saving JoinDefs

Saving a JoinDef places it in the JoinDef Catalog and ensures that you can run it again without having to rebuild it. Also, you can easily edit the appearance of a saved JoinDef with the VIFRED and save the edited version under a new name. For more information, see Editing JoinDefs.

To save a JoinDef, click Save on the JoinDef Definition frame.



If this is a new JoinDef, QBF displays the JoinDef Save frame. Enter the name of the JoinDef. Be sure you choose a unique name. If you enter a name already in use and try to save the JoinDef, QBF informs you that a JoinDef by that name exists and asks whether you want to save the new JoinDef by the same name. If you type **y** (yes), QBF overwrites the existing JoinDef.

The JoinDef Save frame allows you to enter a short remark or description of the JoinDef and also a longer remark or description. These remarks are useful for keeping track of your JoinDefs. The Short Remark that you enter here appears on the JoinDefs Catalog frame to the right of the JoinDef's name and owner. The Long Remark that you enter here appears whenever a user chooses MoreInfo about a JoinDef.

Editing JoinDefs

You can edit either the definition for a JoinDef on the JoinDef Definition frame, or you can edit the JoinDef form on which the JoinDef guery is run.

When you run a JoinDef, QBF provides a default form in the query execution phase. You can make some adjustments to this form with the ChangeDisplay operation, described above. Use the VIFRED QBF for more extensive customization, such as adding descriptive title, validation checks, or displaying fields in reverse video. This further customization turns your JoinDef into a QBFname.

To make a JoinDef form accessible to VIFRED, be sure to save the JoinDef to store it in the JoinDefs Catalog.

To modify a saved JoinDef from within QBF, put the cursor on the name of an existing JoinDef on the JoinDefs Catalog frame and choose the Edit operation. This displays the JoinDef Definition frame for that JoinDef.

To create a new JoinDef from an existing one without affecting the original version, simply type a new name over the current one in the JoinDef Name field on the JoinDef Definition frame and then save it. QBF stores your changes under the new name when you choose the Save operation.

Deleting JoinDefs

You can delete a JoinDef with the JoinDefs Catalog frame. Place the cursor on the name of the JoinDef you want to erase and choose the Destroy operation. QBF prompts you for confirmation:

Do you wish to destroy JoinDef 'name'?

Type \mathbf{y} (yes) to permanently delete the JoinDef. Type \mathbf{n} (no) if you decide not to delete the JoinDef.

You can also delete a JoinDef on the command line, using the delobj command. For details, see the chapter "Using System Commands for the Forms-based Tools."

Chapter 7: Using RBF

This chapter provides an overview of RBF, a forms-based interface for creating and producing reports from an Ingres database.

Using RBF, you can:

- Produce a report immediately with the Preview operation
- Create, edit, and save report specifications that you can use repeatedly to produce reports at any time


You can also create report specifications with Report-Writer, a command language release of RBF. With Report-Writer, you can produce more complex reports than you can with RBF, including conditional expressions, break control, and complex queries. For complete information on creating report specifications with Report-Writer, see the chapter "Using Report-Writer."


This chapter explains how to start RBF and how to use the Report Catalog frame to look up an existing report specification. It also discusses sources of report data, the basic report styles, and concepts associated with reports.

For information on creating, editing, saving, and producing a report, see the chapters "Working with RBF Report Specifications" and "Producing a RBF Report."

RBF Frames and Operations

The following figures contain maps of the various RBF frames and operations.





Starting RBF

You can start RBF from the operating system or from the Ingres Menu.

Starting RBF from the Operating System


Use the rbf command to start RBF from the operating system. You can optionally include parameters that:

- Display a named report specification for editing in the Report Layout Frame
- Display the Report Catalog Frame, where you can examine or select one of the listed report specifications
- Create a default report specification based on the layout style parameter you specify

For more information on the rbf command and its parameters, see the chapter "Using System Commands for the Forms-based Tools."

Starting RBF from the Ingres Menu

To start RBF from the Ingres Menu, choose the Reports operation from the menu. RBF displays the Report Catalog Frame, shown in the following figure, which provides access to all the basic RBF functions.



The table field portion of this frame lists all the report specifications for this database owned by you or the database administrator. Report specifications owned by other users are not listed in the Report Catalog frame.

With each report specification name, RBF lists its owner (you or the DBA) and a short description. To locate a report specification, scroll through the list or type the first letter of the report specification you are searching for. If you type the first letter, RBF places the cursor on the next report specification in the list that begins with that letter.

The following table describes the menu items on the Report Catalog frame:


Operation	Description
Create	Creates a new report specification for a specified table, view, RBF report, or JoinDef.
Destroy	Deletes a report specification that you own from the database.
Edit	Selects a report specification for further editing. Places you in the Report Layout frame. You can edit RBF reports only; you cannot edit reports saved with the sreport command. For additional information, see the chapter "Working with RBF Report Specifications."
Rename	Changes the name of a report specification that you own.
MoreInfo	Calls a second frame containing more information on the selected report specification.
Preview	Runs a report immediately for the specified table or view. Produces a one-time only report in the default format for the report style you selected. Contains all the data in the specified table or view. Does not save a report specification. For instructions on producing a preview report, see the chapter "Producing a RBF Report."
Utilities	Archives a report to a text file. For instructions, see the chapter "Working with RBF Report Specifications."
Go	Runs an existing report specification.
Help, End, Quit	These are standard operations.

Obtaining Information About a Report Specification

To display information about a report specification:

- 1. Place the cursor over the name of the report specification on the Report Catalog frame.
- 2. Choose the MoreInfo operation.

The MoreInfo about a Report frame displays.



The name of the table, view, or JoinDef on which the report is based appears in the Data Table field. If the report is based on a JoinDef, the initials JD appear in parentheses after the JoinDef name.

To edit the Short Remark (which is displayed along with the report specification name on the Report Catalog frame) and the Long Remark, move the cursor into the field and edit as you would in any form field. To save the changes you made, select the Save operation.

The following table shows the operations in the Report MoreInfo frame:

Operation	Description
Next	Displays information for the next report that is listed in the Report Catalog frame.
Previous	Displays information for the previous report that is listed in the Report Catalog frame.
Save	Saves changes to the Short Remark and Long Remark fields in the frame.
Go	Runs the selected report.
Help, End	These are standard operations.

Using RBF Pop-Up Frames

When you create or edit a report specification with RBF, use a series of popups. These pop-ups either provide selections for you to choose from or fields for you to complete.

Each time a pop-up appears, the menu line changes. It can contain some or all of the operations listed in the following table:

Operation	Description
ListChoices	Lists the available choices for the selected field.
Select	Chooses the highlighted item.
Help, Cancel	These are standard operations.

Preview Reports

A preview report provides a quick method of producing a simple report containing all the data in a given table, view, or JoinDef. Each preview report is a one-time event; you cannot save a preview report.

The advantages of a preview report are:

- Ease
- Simplicity
- Speed (Producing a preview report is faster than creating and running a report specification.)

The disadvantages of a preview report are that you cannot:

- Use aggregates
- Edit the report format
- Specify data sorting
- Produce Master/Detail, labels, or indented style reports
- Save the report specification

You can produce preview reports only in tabular, wrap, or block styles. Reportsorts the data by the first column only. If your table has duplicate data in the first column, RBF reports those rows together, but in an undetermined order relative to each other.

For instructions on producing preview reports, see the chapter "Producing a RBF Report."

Report Specifications

A report specification is a set of instructions telling RBF what data you want included in the report and how you want the data presented. With RBF, you can create report specifications:

- Based on tables, views, join definitions (JoinDefs), or other RBF reports
- In six different styles, which you can edit
- With report, page, and break headers and footers, which you can design to your specifications
- With aggregated data

Once you have named and created a report specification, you can use the same specification to produce a report as many times as you wish. The report will always reflect the most recent data in the database.

If you edit the table, view, or JoinDef on which your report is based, you must re-create your report specification. For restrictions that apply to the use of certain report data sources, see Sources of Report Data.

Note: Report specifications created for this release of Ingres cannot be edited or run in earlier releases due to changes in the underlying table name formats.

To produce a report from a report specification, you:

- 1. Create a default report specification and edit it, if you wish. For details, see the chapter "Working with RBF Report Specifications."
- 2. Save the report specification. For details, see the chapter "Working with RBF Report Specifications."
- 3. Run the report specification. For details, see the chapter "Producing a RBF Report."

Sources of Report Data

A RBF report can be based on:

- A table
- Selected columns in a table
- A view
- A joinDef
- An existing RBF report

When choosing the source for your report, be aware of the following restrictions:

- If you base the report on a table and later add a column to the table, the report will not reflect the addition.
- If you delete a column or change the data type of a column, you will not be able to edit or run the report using RBF.
- If ownership of the table changes to other than the DBA or the catalog owner, you will not be able to edit or run the report using RBF, unless the new owner grants you access.
- If you base the report on a view or JoinDef and later change the definition of the view or JoinDef, the report will not reflect those changes.
- You cannot base a report on an existing report that was saved with the sreport command, a system-level command used for saving reports in Report-Writer format. For more information about sreport, see the chapters "Working with RBF Report Specifications" or "Using Report-Writer."
- You must specify SQL as the query language if you create a report in that contains any of the following objects:
 - JoinDef
 - Table owned by a user other than yourself or the DBA
 - Table, column, or correlation name that is a delimited identifier
- You cannot run the report under earlier releases of Ingres.

Sort Columns and Breaks

To specify the order in which your report must print the data, you can designate certain data columns as primary or subordinate *sort* columns. For instance, if you specify the Company column as the primary sort column, and the Department column as the next subordinate sort column, the report will organize the data first by Company, and then by Department within each Company.

A *break* marks a change in the value of a report column that is designated as a sort column. For instance, in the previous example, a break occurs each time RBF encounters a new department name in the Department column. You can designate how the report must indicate a break. For example, you could instruct RBF to suppress duplicate department names in the Department column and to start a new page for each new department name. Breaks are helpful for presenting data in logical divisions that are easy to read.

To indicate a break you can:

Suppress duplicate values in a sort column and print a value only when it changes.

For instance, in the following example, the company name prints only once and is not repeated for each of its departments:

RB Associates Development

Personnel Sales Support

Weston, Inc. Accounting

Marketing

- Start a new page each time a value in a sort column changes.
- Create a break header to indicate the beginning of a group of related rows that have the same value in the sort column.
- Create a break footer to indicate the end of a group of related rows that have the same value in the sort column.
- Create an aggregate in a break footer to calculate a subtotal or to otherwise summarize information up to the break.

An example of a break is shown in the indented report style figure. The Dept (department) column is a sort column. Each time the department name changes, RBF prints a break header containing the department name.

Default RBF report styles have predefined sort columns (usually the first column only) and predefined break actions associated with each sort column. To customize the report, you must specify additional or different sort columns and break actions. For details on using breaks, see the chapter "Working with RBF Report Specifications."

Date, Time, and Page Number

The Report Options frame allows you to specify whether or not, and in what format, you want the date, time, and page numbers to appear in your report. By default, RBF automatically places the date and time in the report and page headers and the page number in the page footer. These fields do not display on the screen when you are creating a report specification. However, they do appear on the report when it is run. If you delete these report sections, this information will not appear on your report.

When you run a report including the date or time, RBF takes the date and time from your computer's operating system. If your system's date and time are incorrect, the report date and time will also be incorrect.

The report reflects the date and time when data is taken from the database, not when the report specification was created. When you send a report to a file for future printing, the date and time on the report reflect when you take the data from the database rather than when you send the report to the printer.

For more information, see <u>Date, Time, and Page Components</u> in the chapter "Working with RBF Report Specifications."

Report Styles

RBF offers the following six report styles:

- Tabular (or Column)
- Wrap
- Block
- Indented
- Master/Detail
- Labels

When you select a report style for your report, RBF provides you with the *default report specification* for the chosen style. You can then edit the default report specification to look exactly the way you want. The report style that you initially choose is not a persistent attribute of the report; rather, it is a starting point for further customization. There are some restrictions on editing labels reports, as discussed in Labels Style.

After you have created and saved a report specification, you cannot instruct RBF to convert it to a different style. For instance, you cannot take an existing tabular report and instruct RBF to convert it to block style. But, you can always change the appearance of the report by editing it, as noted above.

All styles are not always available. For example, the Master/Detail style is available only when you base your report on a Master/Detail JoinDef. RBF displays only those styles available for your report.

Tabular

Tabular reports, also called *column* reports, list the name of each column in the table with column headings and the data in columnar format.

This style produces a report as wide as necessary to fit all the columns in your table. When you print a tabular report that is too wide to fit across a printed page, the data that cannot fit is either wrapped around to the next line or truncated (eliminated) from the report. Whether an overly wide report is truncated or wrapped depends on your output device.

By default, tabular reports break on the first sort column and do not print duplicate break values, except over page breaks.

This figure shows an example of a tabular report, which breaks on Manager, the first sort column.



Wrap


Wrap style is similar to tabular style, except the column headings and data are wrapped around to the next line at screen or page width.

This figure shows a wrap report with the Budget and Due Date columns wrapped around to subsequent lines of the report.



Block

In a *block* report, each row of report data is formatted in a block. Each column heading appears immediately to the left of its data on the same detail line. The following figure shows a block report.



Indented

The indented style, also called the hierarchical control break style, allows you to produce a report with multiple levels of breaks. When specifying this report style, you must specify at least one sort (break) column. The following figure shows an indented report.



Master/Detail

A Master/Detail report presents master data in a break header and detail data in columns. The default break column is the first Master/Detail join column. If there are multiple join columns, RBF sorts the data on all the join columns. However, only the first join column contains default break actions. If you want specific break actions to occur on the other join columns, you have to add the break actions yourself. For more information on specifying break actions, see Editing Column Break Options in the chapter "Working with RBF Report Specifications."

A Master/Detail report must be based on a Master/Detail JoinDef. This figure shows a Master/Detail report.

```
Start of Output
17-sep-1998
Report Name: task_assignments
14:48:40
Report on JoinDef: task_assignments

Name: Alcott, Scott
Title: Sr Programmer
Hourly Rate:
Manager: Wolfe, Neal
Project Iask Hours
Advertise Implement 5
Advertise Test 8

Print(SH-F1) File(SH-F2) Help(F1) End(F10)
```

The query language for a Master/Detail report is SQL. For additional information about the query language used for retrieving your report data, see the chapter "Working with RBF Report Specifications."

Labels

The *label*s style produces a report similar to a mailing list. It presents blocks of data across the page.

RBF calculates the size of the label and the number of labels across the page. It bases its calculation on the size of the data fields and the location of the right margin.

Unlike the other report styles, you cannot change the basic style of a labels report. The data must appear in blocks across the page. Additionally, you cannot delete the report footer, specify break options, or specify headers in labels reports.

The following figure shows a labels report.




Report Structure

A RBF report can contain some or all of the sections listed in the following table:

Section	Description
Report header	Printed on the first page of the report.
Page header	Printed at the top of the second and subsequent pages of the report.
	To print the Page Header on the first page of the report as part of the report header, use the ReportOptions operation. For instructions, see the chapter "Working with RBF Report Specifications."
Break header	Printed before the report's detail lines. A report can have one break header for each column designated as a sort column. On the report specification, the break header contains the name of the associated sort column. For example, in the following figure, the column associated with the break header is the Dept column, so the break header is titled Dept-Break-Header.
	If a report has multiple break headers, they are printed in the order designated by the sort sequence of the sort columns. For example, the first break header contains the column with a sort sequence of 1, the second break header contains the column with a sort sequence of 2, and so forth.
	To define the sort sequence, use the ColumnOptions operation. For instructions, see the chapter "Working with RBF Report Specifications."
Detail lines	Printed for each row in the table, view, or JoinDef associated with this report.
Break footer	Printed after the report's detail lines. A report can have one break footer for each column designated as a sort column.
	On the report specification, the break footer contains the name of the associated sort column. For example, in the following figure, the column associated with the break footer is the Dept column, so the break footer is titled Dept-Break-Footer. As with break headers, if a report has multiple break footers, they are printed in the order designated by the sort sequence of the sort columns.
Page footer	Printed at the bottom of each report page.
Report footer	Printed at the end of the report.

The following figure shows a report specification with all of the report sections listed. The break, page, and report footers contain aggregates. The aggregates are discussed in the chapter "Working with RBF Report Specifications."



The report sections that appear in your report are determined initially by the default report layout for the report style you chose. The default layout for each report style is shown in the following table. For instructions, see the chapter "Working with RBF Report Specifications." The Layout operation, also described in that chapter, allows you to add and delete some report sections to customize the report.

Report Styles	Report Header	Page Header	Break Header	Detail	Break Footer	Page Footer	Report Footer
Tabular	yes	yes	yes	yes	no	yes	no
Wrap	yes	yes	no	yes	no	yes	no
Block	yes	yes	no	yes	no	yes	no
Indented	yes	yes	yes	yes	no	yes	no
Master/Detail	yes	yes	yes	yes	no	yes	no
Labels	yes	yes	no	yes	no	yes	yes

Chapter 8: Working with RBF Report **Specifications**

This chapter describes how to create a default report specification with RBF. It also explains how to edit a report specification in the Report Layout frame to produce a more sophisticated report, using operations to:


- Create, delete, edit, and move report components, such as columns and trim
- Change the report's layout by adding and deleting report sections, including report headers and footers, page headers and footers, and break headers and footers
- Specify column options, including sort order and runtime selection criteria
- Specify report options, including page length, form feeds, underlining, display of null values, and whether to duplicate the page header on the first page of the report

This chapter also discusses saving and archiving a report specification. A report specification must be saved before you can either archive it or use it to run a report.

Creating a Default Report Specification

To create a default report specification with RBF:

- 1. Start RBF.
- 2. When the Report Catalog frame appears, select the Create operation. RBF displays the Creating a Report pop-up, which lists the sources of data on which you can base your report.




The following table describes the selections on the Creating a Report popup:

Selection	Description
Duplicate	Bases your report on an existing report. A report cannot be based on one that was saved with the sreport command.
Table	Bases your report on a table or view, as it was defined when you created the report specification.
JoinDef	Bases your report on a JoinDef, as it was defined when you created the report specification.

For restrictions and limitations on the use of tables, views, JoinDefs, and other report specifications as sources of data for your reports, see <u>Sources of Report Data</u> in the chapter "Using RBF."

3. Place the cursor on Duplicate, Table, or JoinDef and choose Select.

RBF displays a pop-up similar to one in the following figure.




- Do one of the following:
 - If necessary, use the ListChoices operation to display a list of available choices and select an item from the list.
 - On the Create a Report Based on a Table pop-up, enter the name of a table and choose ChooseColumns to base your report only on certain columns of a database table. For details, see Using the ChooseColumns Operation. RBF returns to the report specification process when done.
 - On the Create a Report Based on a JoinDef pop-up, choose the Create operation to create or edit a JoinDef on which you are basing the report. Then enter the name of an existing or new JoinDef and choose the Edit operation to access QBF. RBF returns you to the report specification process.
 - On the appropriate pop-up, enter the name of a report, table, view, or JoinDef on which you want to base the report and click OK.
- 5. If your report is based on a table, view, or JoinDef, you must choose a report style. For more information, see Choosing a Report Style.

If your report is based on an existing report, or after you have chosen a report style, RBF displays the default report specification in the Report Layout frame in the figure below. At this point, you can either:

- Customize the report specification, as described in the remainder of this chapter
- Save the report specification, as is, by choosing the Save operation. For instructions, see Saving a Report Specification.

The following figure shows a default report specification for a tabular report.



Using the ChooseColumns Operation

The ChooseColumns operation on the Create a Report Based on a Table popup allows you to specify only certain columns on which you wish to base the report, as noted in Step 4 of the previous procedure for creating a default report specification.

To specify particular columns in a table on which you want to base the report:

- 1. Choose the Create operation on the Report Catalog frame; then select the Table option from the Creating a Report pop-up. RBF displays the Table Name pop-up.
- 2. Enter the name of a table on the Table Name pop-up and choose the ChooseColumns operation. RBF displays a pop-up containing a list of all columns in the table.
 - Up to 10 columns appear in the pop-up. You can scroll to view any additional columns.
- 3. Use the cursor to select a column and choose an appropriate operation on the menu to edit the list of columns on which to base the report. The following table describes each available operation:


Operation	Description
ОК	Accepts the report column list as is, and returns the user to the Table Name pop-up.
Add	Redisplays a list of previously deleted columns. To add the column back into the report column list (above the current column), select it with the cursor and choose the Select operation.
Delete	Deletes the current column from the report column list.
Move	Displays a submenu of move operations for the current column (Above, Below, Help, and End). Choosing End cancels the Move operation.
RemoveAll	Deletes all columns from the report column list at once. You can then use the Add operation to put a few of the deleted columns back into the list.
Cancel, Help	These are standard operations.

- 4. When done editing the list of columns, choose the OK operation. RBF returns you to the Table Name pop-up.
- 5. On the Table Name pop-up, choose OK again to continue with the creation of your report specification. RBF displays the Choose a Report Style popup.

Choosing a Report Style

If your report is to be based on a table, view, or JoinDef, you must choose a report style when the Choose a Report Style pop-up in the following figure appears during report specification creation.

The Choose a Report Style pop-up contains a list of the report styles available for your report. The Master/Detail style is available only if you based your report on a JoinDef.



To choose a report style:

1. Place the cursor on the desired report style and choose Select.

If you selected the indented style, go to Step 2.


If you selected the tabular, wrap, block, Master/Detail, or labels style, the Report Layout frame appears with the default report specification. Go to step 3.

2. The Break Columns pop-up appears in the figure below. This pop-up lists all of the columns in the table or JoinDef on which your report is based.

To select break columns, enter a number between 1 and 1024 in the Sort Sequence field. Each Column Name must have a unique sort sequence number. Enter a zero (0) if you do not want to assign a sort sequence to the column.

Break columns appear in the order specified by the sort sequence; that is, the column with a sort sequence of 1 is the first break column, the column with a sort sequence of 2 is the second break column, and so forth.


You must specify at least one break for an indented report. For a discussion of breaks, see the chapter "Using RBF."



- 3. When you have chosen the report style and break columns, if appropriate, RBF displays the default report specification in the Report Layout frame in the following figure. At this point, you can either:
 - Customize the report specification, as described in the remainder of this chapter
 - Save the report specification, as is, by choosing the Save operation.
 For instructions, see <u>Saving a Report Specification</u>.

RBF Report Layout Frame

The Report Layout frame is the primary frame for editing RBF report specifications. You can use this frame to add, edit, or delete report components. From this frame, you also can call up other frames to add and delete report sections, and to specify report sorting order, runtime selection criteria, and report output options.



The preceding figure shows a Report Layout frame for a tabular report with a break header for the Name column. A layout frame for a report in another style looks different. The operations of the Report Layout frame function the same way regardless of the report's style.

Getting to the Report Layout Frame

Use one of the following ways to load a default report specification into the Report Layout frame:

- Create a default report specification with the Create operation on the Report Catalog frame. RBF automatically places the new report specification in the Report Layout frame for further editing.
- Place the cursor over an existing RBF report specification name in the Report Catalog frame and choose the Edit option. RBF places the selected report specification in the Report Layout frame.
- Use the rbf command and specify a table, view, or report name as a parameter.

Layout Frame and Report Components

The Report Layout frame in the preceding figure the layout of the report sections and other report components, as described in the following sections.

Report Sections

A Report Layout frame is divided into some or all of the following report sections, depending on the report style you choose:

- Report header
- Page header
- Break headers
- **Detail lines**
- Break footers
- Page footer
- Report footer

Each report section is marked off by lines of dashes labeled with the name of the section.

You use the Layout operation to create or delete report sections. You use the Create and Line operations to add blank lines and other components to a report section, and the Delete operation to delete them from a report section. These operations are summarized in Report Layout Frame Menu.


Report Margins and Alignment Guides

The report's bottom margin is identified by the line marked End-of-Report. The report's right margin is identified by a vertical line that is marked End. Initially, the right margin line is located beyond the right edge of your screen, although in the preceding figure it has been moved so that you can see it.

Use the Move operation, as described later in this chapter, to move these margins and thus expand or contract the size of your report. Both report margins, as well as the report section dividers, optionally display ruler marks every fifth column or row, and a decimal digit every tenth column or row. Use these rulers as alignment guides to help you determine the coordinates for report components.

The Report Layout frame also provides optional horizontal and vertical straight edge alignment guides for aligning report components. If straight edges are turned on, the vertical and horizontal straight edges appear initially in the last column of the report specification and the last row of the Detail section, respectively. Move straight edges with the Move operation, as you would a piece of trim or other report component.

The following figure shows straight edges aligned on the Hours column and rulers turned on. For best results, use a monitor with a line graphics character set.



You cannot delete the section markers from the Report Layout frame. However, you can turn rulers and straight edges on or off independently of each other by choosing the Rulers operation on the Report Layout frame. On the pop-up menu, set each alignment guide to y (yes) or n (no). Regardless of whether the alignment guides are set on or off, the section markers, margin lines, and straight edges do not print on your report.

Trim

Trim is a report component that consists of all lines, words, and characters, other than data or aggregates that print on your report. You can place trim in any section of the report.

Headings are considered trim. A heading provides a description of the contents of a column or aggregate. A heading can only be associated with a column or aggregate. You can edit, add, delete, and move headings to any section of the report. Headings are not available in Labels reports.

Columns and Aggregate Functions

Columns and aggregate functions are report components that deal with the data in your report. Columns contain the actual data obtained from the table, view, or JoinDef on which the report is based. You use an aggregate function, such as sum or count, to calculate the value of a specified column up to the occurrence of a break.

Columns and aggregate functions are represented on the Report Layout frame by fields containing:

- Letters and symbols, which denote the data display format For information about these formats, see Editing Column Display Formats.
- Solid lines, which show the width of the column or aggregate

Fields that represent data columns appear in the Detail section of the Report Layout frame. The Report Layout frame does not initially display the names of the columns associated with the fields in the Detail section. You can use the Name operation to obtain the column name for a field. For details, see Obtaining the Name of a Column.

At the bottom of the frame is the Report Layout menu. It allows you to perform the following operations:

Operation	Description	
Create	Displays a submenu with operations that allow you to create most new report components, including trim, columns, aggregates, headings, and blank lines. For instructions, see Creating New Report Components . To create break headers, footers, and other report sections, use the Layout operation instead of Create.	
Delete	Deletes the report component at the cursor position. For instructions, see <u>Deleting Report Components</u> . To delete break headers, footers, and other report sections, use the Layout operation instead of Delete.	
Edit	If the cursor is on trim, edit the trim.	
	If the cursor is on a column or aggregate, displays a submenu with operations that allow you to change the column's data display format or other column options, including the sort order and runtime selection criteria. If the column being edited is a sort column, this submenu also includes the BreakOptions operation, which allows you to specify how RBF handles breaks in column values.	
	For instructions, see Editing Report Components.	
Move	Moves the current component through operations presented on submenus. For instructions, see Moving Report Components .	
Layout	Creates and deletes break headers, footers, and other report sections. For instructions, see Components and Deleting Report Components .	
ColumnOptions	Establishes sort order, sort direction, and runtime selection criteria. For instructions, see <u>Editing Column Sort and Selection Options</u> .	
ReportOptions	Establishes a variety of report options, including page length, inclusion of form feeds, display of null values, and underlining capabilities. For more information, see Specifying Report Options .	
Rulers	Allows you to use horizontal and vertical straight edge alignment guides for aligning report components. For instructions, see Layout Frame and Report Components .	
Name	Allows you to obtain the name of a column for a field in the Detail section of the Report Layout frame. For more information, see Obtaining the Name of a Column.	
Undo	Reverses the effects of the last editing operation. For instructions, see <u>Undoing Edits</u> .	

Operation	Description
Save	Saves the edited report specification into the database with the report name of your choosing. For instructions, see Saving a Report Specification .
Help, End	These are standard operations.

Creating New Report Components

Use the Layout operation to create these report sections:

- Report header
- Page header
- Break headers
- Detail section
- Break footers
- Page footer
- Report footer

For instructions on using the Layout operation, see Deleting Break Headers, Footers, and Other Report Sections.

Use the Create operation to create:

- Trim
- Columns
- Aggregates
- Column headings
- Blank lines

To use the Create operation:

the following table:

- 1. Position the cursor where you want to create the new component.
- 2. Choose the Create operation from the Report Layout frame menu. RBF displays the Create submenu, which offers the options described in

Operation	Description	
Trim	Enters the text of a new trim element at the cursor position. For instructions, see Creating Trim .	
Column	Creates a new column and column heading at the cursor position. In Labels reports, creates a column without a column heading. For more information, see Creating a Column .	
Aggregate	Create an aggregate, such as sum or average, on a column. Aggregates can be cumulative or unique and must be in break, page, or report footer sections. For instructions, see Aggregates .	
Heading	Creates a new or additional heading line (not available for Labels reports). The new heading line must be associated with an existing heading, column, or aggregate. For details, see Creating Additional Heading Lines .	
Line	Inserts a blank line above the line on which the cursor rests. For instructions, see <u>Creating Blank Lines</u> .	
Help, End	These are standard operations.	

The following sections present specific information about creating different types of components.

Creating Break Headers, Footers, and Other Report Sections

The default report specification for each style of report contains its own default report sections. You can use the Layout operation to create additional break headers, footers, and other report sections in your report specification.

Note these restrictions:

- A report can contain only one of each of the following sections:
 - Report header
 - Report footer
 - Page header
 - Page footer
- A report can contain one break header and one break footer for each sort column in the report

If the section you want to add is a header or footer for a column, you must have first designated the column as a *sort* column. For instructions on designating a sort column, see <u>Editing Column Sort and Selection Options</u>.

To add a report section:

1. Select the Layout operation from the Report Layout frame menu. The Edit Report Layout pop-up appears.



2. Select the Create operation from the menu. The Creating a Report Layout Section pop-up appears, similar to the one in the following figure. This pop-up contains a list of the report sections you can create.




This list always includes the option to create a break header or footer, because you can create many of these. However, it only contains other report sections if they do not already exist.

3. Place the cursor on the name of the report section that you want to create and choose the Select operation.

If you are creating a report or page header or footer, proceed to Step 5.

If you are creating a break header or footer, the Sort Columns pop-up appears in the following figure. It contains a list of the sort columns available for the break header or footer.



- 4. Move the cursor to the desired sort column and choose the Select operation.
- 5. Select the End operation to return to the Report Layout frame.

The new report section appears on the Report Layout frame. If you created a break header or footer, the name of the sort column appears with the report section name.

Creating Trim

To create trim:

- 1. Position the cursor where you want to add the trim.
- 2. Select the Create operation from the Report Layout menu.
- 3. Select the Trim operation from the Create submenu.
- 4. Enter the text of the new trim.

If you want to create lines and borders for your report, use keyboard characters such as the hyphen (-) or underscore (_).

5. Press the Menu key.

If necessary, correct the trim position with the Move operation.

Creating a Column


Use the Column operation to create a new column and column heading in your report. Note these restrictions:

- The column must exist in the table, view, or JoinDef from which the report is generated.
- The column must not already appear on the Report Layout frame.

In labels reports, the Column operation creates a column without a column heading.

To create the new column:

- 1. Move the cursor into an open spot in any section of the report.
- 2. Select the Create operation from the Report Layout Menu.
- 3. Select the Column operation from the Create submenu.



RBF displays the Create a Column pop-up (shown below), which contains a list of the columns that are available for mapping.



4. Position the cursor on the desired column and choose the Select operation.

RBF inserts the column and column heading at the cursor location and pushes existing columns to the right, if necessary.

The new column is in block style with the heading to the left of the column. To change this, use the Move operation.

For Labels reports, RBF creates the column only. It does not create a column heading. To add a column heading, use the Trim operation.

Aggregates

You use an aggregate function, such as sum or count, to calculate the value of a specified column up to the occurrence of a break. In RBF, an aggregate must appear in a footer for a report, page, or break. RBF calculates the aggregate value each time a break occurs in the specified footer.

The cut-off point for data to be included in the calculation of an aggregate depends on whether the aggregate is simple or cumulative. For more information, see <u>Simple and Cumulative Aggregates</u>.

The following table lists all of the available aggregate functions:

Aggregate Function:	Returns:
Any	1 if any data exists, 0 if none exists
Average	Mean average of all values in the column
Count	Count of all the values in the column
Minimum	Smallest value in the column
Maximum	Largest value in the column
Sum Arithmetic sum of all the values in the	

Note these restrictions:

- If the aggregate column is numeric, all of these functions are available.
- If the aggregate column is a character or date data type, the any, count, minimum, and maximum aggregate functions are available. Additionally, you can take a sum of a date data type column, but only if date intervals (such as 1 day, 2 hours) are stored in the column. Taking a sum on absolute dates (such as December 13, 1988) results in an error.

Simple and Cumulative Aggregates

Aggregates can be simple or cumulative.

A *simple aggregate* is determined by the type of footer in which you specify it. For example:

- If you specify the sum aggregate for the budget column in a report footer, then the aggregate contains the sum of the values in the budget column for all rows in the report.
- If you specify the sum aggregate for the budget column in the page footer, the aggregate contains the sum of the values in the budget column for the rows printed on each page of the report.

If you specify the sum aggregate for the budget column in the break footer for the Department column, the aggregate contains the sum of the values in the budget column for all rows in each department.

A cumulative aggregate is a running total. It contains the aggregate of all the rows processed since the start of the report and does not depend on the location of the aggregate.

Unique Aggregates

You can create unique aggregates for sort (break) columns only. Unique aggregates are calculated by using only the unique values of the sort columns. You cannot specify a unique aggregate for a non-sort column.

If you change a column that has a unique aggregate associated with it from a sort to non-sort column, RBF gives you the following options:

- Deleting the unique aggregate
- Changing the unique aggregate to non-unique

The unique aggregates are described in the following table:

Unique Aggregate	Returns:
Average (Unique)	Mean average of all the unique values in a sort column.
Count (Unique)	Count of all the unique values in a sort column.
Sum (Unique)	Sum of all the unique values in a sort column.

Guidelines for Creating an Aggregate

When creating aggregates, you:

- Must create an aggregate in a footer (break, page, or report)
- Can create an aggregate on any column (the column does not have to be a sort column)
- Can create more than one aggregate in a footer and more than one type of aggregate for a particular column

For example, in a table containing the columns Project, Employee, and Salary, you can create a break footer for the Project column (Project_Break_Footer). Then, you can create Average and Sum aggregates (non-cumulative) for the Salary column in the Project_break_footer. This instructs RBF to:

Break each time it finds a new value in the Project column


Calculate the total salary and average salary cost of each project

Creating an Aggregate

To create an aggregate:

- 1. Place the cursor in the position in the footer section where you want to create the aggregate. If you must create a footer section, see <u>Creating Break Headers</u>, <u>Footers</u>, <u>and Other Report Sections</u>.
- 2. Select the Create operation from the Report Layout frame menu.
- 3. Select the Aggregate operation from the Create submenu.

The Create an Aggregate pop-up appears. This pop-up contains a list of the columns in your report.



- 4. Position the cursor on the column for which you want the aggregate.
- 5. Choose the Select operation.

The Selecting Aggregates pop-up appears.



This pop-up contains a list of the aggregate functions that are available for the column to be aggregated.

- 6. Place the cursor on the desired aggregate function.
- 7. Choose the Select operation. The Cumulative Aggregation pop-up appears.



For a description of simple and cumulative aggregates, see Simple and Cumulative Aggregates.

- 8. Select Yes to make the aggregate cumulative or No to make the aggregate simple (non-cumulative).
- 9. Choose the Select operation to finish creating the aggregate and return to the Report Layout frame.

Editing an Aggregate

After creating an aggregate, you can edit it in the same way you edit columns. You can:

- Change its display format
- Edit it or the associated headings
- Move it to another footer section
- Delete the aggregate

Creating Additional Heading Lines

By using the Create and Heading operations, you can add a new heading or additional heading line to a column or aggregate, except in Labels reports.

In Labels reports, use the Create and Trim operations to add column headings. However, be aware that you cannot move columns with headings added in this manner as a unit; you must move them separately. For instructions on moving trim, columns, aggregates, and headings, see Moving Report Components.

To create a new heading line:

- Place the cursor on the existing heading or, if there is no existing heading, on the column or aggregate.
- 2. Select the Create operation from the Report Layout frame menu.
- 3. Select the Heading operation from the Create submenu. See the first figure in the <u>Creating a Column</u> topic.
 - If there is an existing heading, RBF moves the cursor to the first blank line below the existing heading line, creating a new line, if necessary. If there is no existing heading, RBF moves the cursor to the Page Header section immediately above the column.
- 4. At the prompt, enter the new or additional heading and press the Menu key. RBF inserts the heading.

Creating Blank Lines

When creating blank lines, keep in mind that the Line operation inserts the new blank line at the current cursor position, pushing the current line and everything below it down one line.

To add a blank line:

- 1. Place the cursor at the position where you want to insert the new line.
- 2. Select the Create operation from the Report Layout menu.
- 3. Select the Line operation from the Create submenu. See the first figure in the <u>Creating a Column</u> topic. RBF inserts the blank line.

Deleting Report Components

You use the Layout operation on the Report Layout frame to delete report sections and the Delete operation to delete other report components, as described in the following subsections.

Deleting Break Headers, Footers, and Other Report Sections

The default report specification for each style of report contains its own default report sections. You can use the Layout operation to delete some of the break headers, footers, and other report sections in your report specification.

Note these restrictions on deleting report sections:

- You can never delete detail sections.
- You cannot delete sections that are needed for the options set with the BreakOptions operation. For example, if you choose to print on page breaks, you cannot delete the page header. For more information, see Editing Column Break Options.
- You cannot delete a section if doing so would cause the report to have no data (columns or aggregates).
- Because the report and page header contain the report date and time, and the page footer contains page numbers, your report cannot contain this information if you delete these sections.

To delete a report section:

1. Select the Layout operation from the Report Layout frame menu. RBF displays the Edit Report Layout pop-up, which contains a list of the report sections you can delete.



- 2. Position the cursor on the report section you want to delete and select the Delete operation from the menu.
- 3. Select the End operation to return to the Report Layout frame menu.

When you return to the Report Layout frame, the deleted section and its contents disappear from the frame.

Deleting Other Report Components

Use the Delete operation on the Report Layout frame to remove any columns, aggregates column headings, or trim from your report specification.

If you delete a column or aggregate, RBF automatically removes the associated heading, but this is not true in reverse. If you delete a heading, RBF does *not* automatically delete the associated column or aggregate.

If you delete all the trim on a line, a blank line is left. You can remove blank lines by placing the cursor on the line and choosing Delete.

To delete a column, aggregate, heading, or trim:

- 1. Place the cursor on the component.
- 2. Select the Delete operation from the Report Layout frame menu.

Editing Report Components

Use the Edit operation to:

- Edit trim and headings
- Change a column or aggregate's display format
- Change column options, such as sort order or runtime selection criteria
- Establish how your report handles breaks in sort columns

Editing Trim and Headings

The default editing mode is overstrike, which means that the characters you type replace the existing character at the cursor position. To change to *Insert* mode (in which the characters you type push existing characters to the right), press the Mode key for your keyboard.

When you are editing a report component, the current editing mode is displayed in the lower right corner of the frame.

When editing a report specification, you can only work on one line of trim at a time. Each line of trim is considered a separate component. You cannot extend or push a line of trim past the report's right margin, but you can use the Move operation to extend the report's right margin.

To edit trim and headings:

- 1. Place the cursor on the trim or heading component that you want to edit.
- 2. Select the Edit operation from the Report Layout frame menu.

- 3. Edit the component.
- 4. Press the Menu key.

Editing Columns

To edit a column:

- 1. Place the cursor on the column's display format (the cursor must be on the actual column, not on the column heading).
- 2. Choose the Edit operation from the Report Layout frame menu.
- 3. When the Edit submenu appears, select one of the operations described in the following table:


Operation	Description
DisplayFormat	To edit the data display format.
ColumnOptions	To specify sort order, sort direction, or runtime selection criteria. This is the same as the ColumnOptions operation on the Report Layout frame main menu.
BreakOptions	To suppress the printing of duplicate values in sort (break) columns or to print a new page each time the value in a sort column changes. This operation appears only if the selected column is a sort column.

Editing Column Display Formats

The data display formats for each of the columns in your report specification determine the way data appears in the report. You can display the data in a particular column in various ways. For example, for a column containing dates, you can choose from date formats such as January 15th, 1944 or 1/15/44.

RBF assigns a default display format for each data type. You can use the Edit operation, as described in Changing Display Formats, to change these default display formats. However, RBF does not allow you to use a display format that is incompatible with the data type. For example, you cannot use the character display format with a numeric data type.

Representation of Display Formats



i

The letter **i** indicates the integer display format and the underscore line shows the remaining number of characters in the column. Fixed punctuation is also shown in a display format representation. For example, a display format for a column containing financial data might look like this:



The total width of the representation (symbols plus underscore) equals the total width of the column.

RBF permits the same display formats as Report-Writer except for the B, q0, and c0 formats. The c0.w format, however, is valid in RBF.

Changing Display Formats

To change a display format:

- 1. Place the cursor on the column or aggregate you want to change.
- 2. Select the Edit operation from the Report Layout frame menu.
- 3. Select the DisplayFormat operation from the Edit submenu.

The data display component changes from graphic representation of the format definition to the symbol definition. For example, f_____ becomes f6. The cursor appears on the first character of the display format definition.

- 4. Enter the new display format definition, following the syntax shown in the Display Format Syntax and Descriptions table in the chapter "Working with Data Types and Data Display Formats."
- 5. Press the Menu key.

The new format appears as a graphic representation.


Editing Column Sort and Selection Options

- Create sort (break) columns for your report
- Modify a column's sort order

Specify runtime selection criteria for a column

For an explanation of sorts and breaks, see Sort Columns and Breaks.

To get to the Column Options frame, you choose the ColumnOptions operation on either the Report Layout frame or the Edit Submenu of the Report Layout frame.



Defining Sort Order

Sort order determines the order in which data is presented in a report. There are two components to sort order:

- Sort sequence
- Sort direction

Sort sequence is the order in which the columns are sorted. You designate one column as the primary sort column. For instance, in a report of employees, you could designate the Lastname column as the primary sort column so that the report can be sorted according to last name.

You can designate additional columns as subordinate sort columns. Subordinate sort columns sort data within each sort value of the primary sort column. For example, if the primary sort column is Zipcode and the secondary sort column is Lastname, all of the data rows containing zip code 00001 are presented first. Within the 00001 group, the data rows are sorted by the alphabetic order of the names in the Lastname column.

If you do not specify a sort order, data appears in the report in whatever order it was stored in the table, view, or JoinDef on which the report is based.

Sort Direction

Sort direction is another component of sort order. The sort direction is ascending or descending. In ascending order, the lowest values are presented first (1,2,3, a,b,c). In descending order, the highest values are given first (9,8,7, z,y,x).

Sort Order and Data Type

Sort order is performed according to the data type of the column:

- Date columns are sorted in ascending or descending chronology.
- Numeric columns are sorted by ascending or descending numeric value.
- Character columns are sorted in ascending or descending alphabetical order.

This means that numbers entered in a character column (in an address, for instance) are sorted differently than numbers entered into a numeric column. Numbers in a character column are sorted alphabetically, as shown in the following sample table:

Numbers sorted in numeric column	Numbers sorted in character column
1	1
2	101
3	11
11	12
12	2
22	22
101	3

Default Sort Order

When you create a default report specification or preview report, RBF sets an initial default sort order based on the values in the first column of the table, view, or JoinDef on which the report is based. Two exceptions to this are Indented reports and Master/Detail joins, which can have multiple sort columns.

The following rules apply:

- If the data type of the sort column is character, RBF sorts report rows in ascending alphabetic order on the first column.
- If the data type of the sort column is numeric, RBF sorts report rows in ascending numeric order.
- If the data type of the sort column is date, then RBF sorts report rows according to ascending chronological order.
- Except for Indented reports, if the first column contains duplicate values, RBF sorts the rows in an indeterminable manner.

For Tabular reports with duplicate values in the first column, RBF prints the duplicate value only once and does not print a value in the first column until the value changes.

Sort Columns and Breaks

Before you create a break header or footer, you must designate the column you want to break on as a sort column. If you change the sort order of the columns, the order of the report's break headers and footers also changes.

Changing a Column from Sort to Non-Sort

RBF does not allow you to change a sort column into a non-sort column if the column has an associated break header or footer. In this case, you must delete the associated break header or footer first with the Layout operation. See Deleting Report Components.

Additionally, if you try to change a sort column into a non-sort column, you must decide what to do with any unique aggregates. You can:

- Delete all unique aggregates associated with the column
- Change the unique aggregates to non-unique aggregates

Changing the Sort Order

To change the sort order of your report:

- 1. Select the ColumnOptions operation from the Report Layout frame menu.
 - The Column Options frame (in the seventh figure) appears, with a default sort order based on the first column of the table, view, or JoinDef on which your report is based. For more details, see **Default Sort Order**.
- 2. Tab to the Sort Sequence field and enter the order in which you want the column sorted.

You can have from 1 to 1024 sort columns, with 1 as the primary sort column, 2 as the secondary, and so forth.

If you do not want to designate a column as a sort column, set the sort order to zero (0).

- 3. For each sort column designated, establish the sort direction:
 - f. Tab to the Sort Direction field.
 - g. If necessary, type a (for ascending) or d (for descending) over the values currently in the field and press Return. (RBF fills out the field with the complete word for you.)
- 4. Select the End operation to return to the Report Layout frame.

Specifying Runtime Data Selection

Users often must limit the data that goes into a report. For example, a table can contain sales figures for the past three years, but you only want a report on sales data for the previous quarter. You can use the Column Options frame to specify that RBF ask the user to enter criteria for the data to be selected from that column when the report is run. This is called runtime data selection.

Runtime data selection is specified on a column-by-column basis. If the report has a Date column, and you specify a runtime data selection range for that column, each time a user runs the report RBF can ask the user to enter a minimum (earliest) date and the maximum (latest) date. The resulting report can only contain data from rows in which the date falls within the specified range.

You can specify runtime data selection on more than one column. For example, you can specify a runtime data selection for both the Date and Customer columns. In this case, the user could specify a range of dates for a particular customer at report runtime.

You can specify runtime data selection for both sort and nonsort columns.

Enter options in the Selection Criteria column on the Column Options frame to specify whether RBF must use runtime selection criteria. The Column Options frame provides three runtime data selection criteria options, as shown in the following table. You must specify one of these options for each column in the report.

Option	Effect at Runtime	
none (or n)	No runtime selection criteria for this column. This is the default. All data is presented in the report.	
value (or v)	You are asked to enter a specific value at runtime.	

Option	Effect at Runtime	
range (or r)	You are asked to enter a maximum and minimum range of values at runtime.	

In a default report specification, all columns are set to the none option (no runtime data selection).

Each time a user runs a report for which the value or range runtime data selection option has been specified, RBF asks the user to enter the selection criteria before running the report:

- Value If the selection criteria is a value, the user enters the value.
- Range If the selection criteria is a range, RBF prompts the user to enter first the minimum value of the range and then the maximum value of the range.

Hexadecimal Constants

To specify a nonprintable character, you can use a hexadecimal string constant with the following format:

 $X|x'nn\{nn\}'$

The introductory X identifies the string as a hexadecimal string constant. You must specify the nonprintable character as two hexadecimal digits (nn) in the range 0-9, a-f, or A-F, and the string must contain an even number of characters. There must be no intervening white space between the **X** and the single-quoted string of hexadecimal digits. The **X** and the hexadecimal digits are case insensitive. RBF translates the hexadecimal constant into its corresponding character value.

Null Values for Numeric Variables

If the user does not enter a value at runtime for a numeric variable with runtime qualification, RBF issues an error message. To avoid this circumstance, application developers have the following options:

Quote the variable in the query by archiving the RBF report specification and editing it in Report-Writer.

If the user does not enter a variable, RBF interprets the quoted empty variable as a value of zero. This procedure is not recommended for fields in which this behavior is semantically incorrect—for example, in nullable fields. Once you have saved a report specification with the archive command, you can no longer edit it in RBF.

Supply the variable value in a call report statement, or require the user to supply it on the command line, so the value is ensured to exist; then call Report-Writer to run the report.

For details on accomplishing this, see <u>Passing Parameters on the Command Line</u> and the section on report frames in the *4GL Reference Guide*.

Editing Column Break Options

The BreakOptions operation allows you to control how your report shows a change of value in a sort column in the following ways:

- Optionally suppress duplicate values in sort (break) columns in the Detail section of a report.
- Optionally print a new page when a sort column value changes.

You can also create break headers and footers to call attention to a change of value in a sort column. To create break headers and footers, or to use aggregate functions to summarize data in break footers, see Creating Break Headers, Footers, and Other Report Sections topic.

The BreakOptions operation is not available for Labels reports.

Options for Showing a Change of Value


By default for most report styles, RBF prints a value in every column for every row it retrieves. If several rows contain the same value for a column, RBF prints each duplicate value. You can suppress duplicate values in sort columns to make the report more readable.

Use the BreakOptions operation to specify one or a combination of the following options for printing sort column values:

- Always print the value, including duplicates, as shown in the following figure.
- Print the value only once when the initial break occurs and suppress duplicates, as shown in the nineteenth figure.
- Print the value when a new page is printed.
- Create a new page when the sort column value changes.

Regardless of the other options you have chosen, you can instruct RBF to print a new page when the value in a sort column changes. For example, for the report shown in either of the following figures, you can instruct RBF to print a new page when the value in the Dept column changes from Admin to Account.

By default, Tabular reports always suppress duplicate values, as shown in the following figures. RBF prints the value in the Dept sort column only when it changes from Account to Admin, and from Admin to Commun.





Using the Break Options Operation

To use the BreakOptions operation:

- 1. Place the cursor on a sort column and select Edit from the Report Layout menu.
 - The BreakOptions operation appears on the Edit submenu only if the column you select is a sort column.
- 2. Select BreakOptions from the Edit submenu.
 - If the selected sort column is in the Detail section of the report, the Break Column Output Options pop-up appears.

If the selected sort column is in another section of the report, the Break Column Output Options appears.



3. Specify the report's break column options, as described in the following table:

Option	Description	
Always	To print a sort column value always, type yes (or y) in this field.	
	If you enter yes in this field, RBF automatically changes the values in the On breaks and On page breaks fields to NO.	
On breaks	To print a sort column value when it changes only, type yes (or y) in this field.	
	If you choose to print on breaks and the report does not have a break header for the sort column, RBF creates one.	

Option	Description
On page breaks	To print a sort column value when a new page is printed, type yes (or y) in this field.
	If you choose to print on page breaks and the report does not have a page header, RBF creates one.
Do you want a new page on each break in	To start a new page each time the sort column value changes, type yes in this field.
the value of this column?	If you enter yes and the report does not have a break footer, RBF creates one.

4. Click OK to return to the Report Layout frame.

Moving Report Components

Use the Move operation to move:

- Trim, columns, aggregates, and headings
- Straight edge alignment guides
- Report's right and bottom margins

Note these restrictions:

- You can only move aggregates to report, page, or break footer sections.
- The Column operation, which enables you to move columns and their associated headings together, is not available for Labels reports (you must move columns and column headings separately).

You move the straight edge alignment guides exactly as you do a piece of trim, except that none of the other report components move. The alignment guides can appear superimposed upon other report components.

Moving Trim, Columns, Aggregates, and Headings

To move trim, columns, aggregates, and headings:

- 1. Use the arrow keys or your mouse to position the cursor on and select the component you wish to move. You can place the cursor anywhere on the component.
- 2. Choose the Move operation from the Report Layout frame menu.

The component is highlighted in inverse or blinking video if your terminal is capable of doing so.

3. Position the cursor at the new location, if appropriate. Then choose one of the operations on the Move submenu.

The following table describes the Move submenu operations:

Operation	Description
Place	Moves the selected component to a position indicated by the cursor. Before choosing this operation, position the cursor at the desired location. For more information, see Place and Shift Operations .
Left	Moves the selected component to the current left margin of the report layout, on the indicated line.
Center	Moves the selected component to the center of the indicated line, as defined by the report's current margins.
Right	Moves the selected component to the current right margin of the report layout, on the indicated line.
Shift	Moves the selected component to a position indicated by the cursor, shifting other components to the right. Before choosing this operation, position the cursor at the desired location. For more information, see Place and Shift Operations .
Column	This operation appears after you place the cursor on a column, aggregate, or heading. It instructs RBF to move the column or aggregate and the associated heading as a unit.
	After choosing the Column operation, choose one of the other move operations to move both the column or aggregate and the associated heading. If you do not choose the Column operation, you must move columns or aggregates and the associated headings separately.
	This operation is not available for Labels reports. In Labels reports, you are required to move columns and column headings separately.
Help, End	These are standard operations.

Place and Shift Operations

The Place and Shift operations allow you to move a component to a specified location, even if it is on another line. Before choosing either of these operations, you must place the cursor where you want to move the component. The location of the cursor marks where the first (leftmost) character of the component is placed.

If the new location for the component does not affect any other component, there is no difference between the Place and Shift operations. However, if the new location causes the relocated component to overlap another component, Place and Shift handle the situation differently.

Operation	Description
Place	Pushes the other component to the right. If there is not enough space for the pushed component to fit without overlapping additional components, the pushed component is dropped down one line. Thus, the Place operation affects only two components: the moved component and the component pushed out of the way.
Shift	Pushes the other component to the right. If there is not enough space for the pushed component to fit without overlapping additional components, the additional components are also pushed to the right to make room. If all the components cannot fit on a line, some components are forced down to the next line. A Shift operation can affect all components to the right of the moved components' new location.
Centering	The Center operation positions a report component in the center of the total report line width (not the width of your screen). If the report is wider than your screen, the centered component appears off-center on your screen, but is correctly centered on the printed report.

You can set report line width when you create the report specification. You can also use the Move operation to move the right margin, as explained in the following discussion.

Moving the Report Margins

You can use the Move operation to expand or contract the width or length of the report by moving the right or bottom margin of the report.

To move a report margin:

- 1. Place the cursor on the margin line.
- 2. Select the Move operation from the Report Layout frame menu. The following submenu appears:

Operation	Description
Place	Places the selected boundary at the cursor position. If this causes overlap with other form components, the boundary is placed as close to the last component as possible.
Expand	Expands the form by a quarter of a display screen either to the right (if you are moving the right border) or down (if you are moving the bottom of the form).
Help, End	These are standard operations.

3. To narrow the width or length of the report, position the cursor at the location where you want the new margin to be and choose the Place operation.

The margin moves left or up to the cursor location.

To expand the width or length of the report, choose the Expand operation. The Expand operation moves the right margin to the right by one quarter of your screen width. Expand moves the bottom margin down by one quarter of your screen's height. Each time you choose Expand, the margin expands by one quarter of your screen width or height.


RBF defines the width of a report in number of characters across the page, not in inches, centimeters, or picas. The actual width in inches of a report printed on paper can vary from printer to printer, depending on the size of the characters that the printer uses.

Specifying Report Options

The Report Options frame allows you to specify output options that apply to the report as a whole. With the Report Options frame you can specify:

- Page length in number of lines
- Character to be used for underlining
- When and where to use underlining
- Whether to insert form feeds
- How to display null values
- Whether to print the page header on the first page of the report

To call up the Report Options frame, select the ReportOptions operation from the Report Layout frame menu.



Because the Report Options frame concerns the report as a whole, cursor position on the Report Layout frame does not matter.

Page Length

RBF automatically formats reports in numbered pages. A report page length is determined by its number of lines. RBF uses two different default page lengths—one for reports displayed on a screen and one for reports sent to a file or printer:

- Default screen page length equals 20 lines
- Default file or printer page length equals 61 lines

Report page lengths include all report lines, including title, trim, headings, detail lines, headers, and footers.

You can specify a different page length for a report by moving the cursor to the Page Length field and entering a new number of lines. The number of lines you enter here is applied to reports displayed on your screen as well as reports sent to a file. If you leave this field blank, the defaults are 20 lines when the report is written to a screen and 61 when the report is sent to a file or printer. To suppress all pagination (that is, to eliminate all breaks), enter a zero (0) in this field.

Most printers print six lines to the vertical inch. Some printers print eight lines per inch and some can be set to a variable number of lines per inch.

Underlining

The Report Options frame allows you to determine how you want to use underlining in reports written to a file or printer. Underlining is suppressed when the report appears on your screen.

The default underlining character for reports sent to files or printers is the underscore (_). To specify a different character, such as a hyphen (-), enter it in the Underlining Character field.

Use the table field at the bottom of the Report Options frame to determine how you want to apply underlining to different types of text elements in the report. To specify how many lines of a particular report section must be underlined, move the cursor to the appropriate field and enter one of the codes listed in the following table:

Option	Action
all (or a)	Underline all lines of text in the layout area
last (or I)	Underline only the last line of text in the report section
none (or n)	Underline nothing

The default is to underline the last line in the:

- Report header (for all reports)
- Page header (for Tabular and Wrap reports only)

There is no default underlining for newly created sections.

When you are satisfied with your specifications on this frame, select the End operation to return to the Report Catalog frame.

Page Header on First Page

If your report has a page header, it appears on the second and subsequent pages of the report. To print the page header on the first page of the report, type **yes** (or y) in the Print Page Header field.

Display of Null Values

The Display Null Values field allows you to specify how your report presents null values. Depending on the data definition of the underlying table, a null value can be left blank or printed as some special value.

The default is to simply leave null values as blanks on the report. However, you can use this field to specify some other value. For example, you can specify that null values appear on the report as NA, Not Available, or To Be Determined.

Form Feeds

Form feeds are commands sent to the printer telling the printer to advance to the next piece of paper when a report page is finished. In a report file, a form feed is usually indicated by Control-L.

By including form feeds in your report specification, you ensure that each new page of the report begins on a new piece of paper, even if the number of lines specified for the report page is not the same as the number of lines the printer can put on a page. The default is to include form feeds in the report specification. You can change this by entering \mathbf{n} (no) in the Insert Formfeeds field.

If you include form feeds, you can also specify whether to print the first form feed. This initial form feed occurs at the start of the report before the first page has been printed. The default is yes. Enter **n** (no) in the Print First Formfeed field to suppress the initial form feed.

Date, Time, and Page Components

You can choose whether to print the date, time, and page number on the pages of your report. By default, these components print in the following positions on each and every page of the report:

- Date in upper left corner
- Time in upper right corner
- Page number centered at the bottom of page

You cannot change the print position of the page number, but you can reverse the date and time or print both in the upper left or upper right corners by using certain date and time formats, as described later in this section.

You can print or suppress each component independently of the others. The default for each component is yes. Enter n (no) in the Include in Report field for any component to omit it from your report.

For each component included in the report, you can specify a print format as indicated in the following table:

Report Component	Format
Date	Date and/or time format, or a character format (cannot be a multi-line character format).
Time	Date and/or time format, or a character format (cannot be a multi-line character format).
Page	Numeric format or template. You can include characters such as hyphens or parentheses if you dereference each one by preceding it with a backslash (\).

The Date and Time components both contain the same data value, which actually includes both a date and a time value. Therefore, when specifying a date template for the Date or Time components, you can use either or both the date and time designations. The portion of the date and time string used in your template determines whether the date, time, or both appear in that component's location on the page. For instance, specifying d'16:05:06' for the Date component and d'03-feb-1901' for the Time component prints the time in the upper left corner (where the Date component would ordinarily print) and the date in the upper right corner (where the Time component would ordinarily print).

Specifying c25 for a Date or Time component displays the component as *dd-mmm-yyyy hh:mm:ss*, which is equivalent to the date template, d'03-feb-1901 16:05:06'. You cannot specify a multi-line character format such as c30.5, cj30.15, or cf30.6 for the Date and Time components.

Component	Format	Sample Result
Date	d'03-Feb-1901'	12-Sep-1993
	d'03-Feb-1901 16:05:06'	12-Sep-1993 17:07:55
	d'04:05:06 PM'	05:07:55 PM
	d'2/3/1'	9/12/93
	d'02/03/01'	09/12/93
	d'February'	September
	d'010203'	930912
Time	d'04:05:06 PM'	05:07:55 PM
	d'16:05:06'	17:07:55
	d'03-Feb-1901 16:05:06'	14-Sep-1993 17:07:55
	d'03-Feb-1901'	14-Sep-1993
Page	'\P\a\g\e zzz'	Page 123

Component	Format	Sample Result
	'nnnnn'	00123

Obtaining the Name of a Column

The Report Layout frame does not automatically display the names of the columns for the data fields in your report specification. It shows the data fields only as lines and letters or symbols that indicate the maximum length and data type of the data to be included in your report. The column headings shown in the trim line can differ from the actual database table column names.

Use the Name operation Report Layout frame to display column represented by a field in the Detail section of your report specification, as follows:

- 1. Place the cursor on a field in the Detail section of your report specification.
- Choose the Name operation.

RBF displays the name of the database column at the bottom of the screen. The following figure shows the actual column name, title, for the second column in the Detail section, whose trim heading is Position.



Undoing Edits

You can reverse the effects of a Create, Delete, Edit, or Move operation by choosing the Undo operation. Undo cancels the immediately preceding operation, including another Undo operation. The report specification reverts to its original state before the operation.

Undo only reverses the last operation. Undo has no effect on the ReportOptions, ColumnOptions, BreakOptions, Save, or Layout operations.

Saving a Report Specification

You use the Save operation to save your report specification in RBF after creating it or to save any changes you made while editing it.

The Save operation appears on the Report Layout frame, as well as on other RBF frames and pop-up menus. When you choose the Save operation from any frame, RBF displays either the Save Report frame or the Save submenu.

The Save Report frame, as shown in the following figure, allows you to edit the report name or other general information about the report, such as a brief description in the Long or Short Remarks field. This is the same information that appears whenever you select the MoreInfo operation on the Report Catalog frame. If you are creating a new report specification, RBF always displays the Save Report frame.

If you are editing an existing report, RBF displays the Save submenu with the following operations:

Operation	Description
EditInfo	Displays the Save Report frame so you can edit the name or other information displayed on the Report MoreInfo frame.
Save	Saves the report specification under its existing name.
Cancel	Returns you to the previous frame.

Note: Report specifications created for this release of Ingres cannot be edited or run in earlier releases of Ingres, due to changes in the underlying table name formats.

Save Report Frame

The following figure shows an example of a Save Report frame.



The following table lists the fields contained in the Save Report frame:

Field	Description	
Name	Name of the report. A newly created report specification initially has the same name as the table, view, or JoinDef on which it is based. Whenever you change the name in this field, you create a new report under the new name that includes all your changes. The old report, under its old name, is left unchanged. If you save a report without changing its name, your changes are incorporated and the old version is eliminated.	
Created	Display-only field giving the date and time the report was created. If you are saving a report for the first time, this field is blank.	
Owner	Display-only field identifying the owner of the report specification. If you copy a report owned by the DBA, your name is entered as the owner of the newly saved report.	
Modified	Display-only field showing the last date and time the report specification was saved. If you are saving a new report specification for the first time, this field is blank.	
Short Remark	Short description of the report specification. The description you enter here is displayed on the Report Catalog frame.	
Long Remark	Long description of the report specification. The long description you enter here is displayed in the More Information about a Report frame when you choose MoreInfo from the Report Catalog frame.	

Field	Description
Data Table	Name of the table, view, or JoinDef on which the report specification is based. Do not change the Data Table name to the name of a table, view, or JoinDef that does not contain the same columns as the one on which the report was originally based. If you do this, the report cannot run and you cannot be able to use RBF to edit the report specification or correct the Data Table name.
Query Language	Query language you want to use in retrieving the data for the report (if your installation supports more than one database language). If RBF has predetermined the appropriate query language, you cannot be able to edit this field.
	The database language specified here is the one that is used when the report specification is written into the database. Additionally, if you write the report specification into a text file with the Archive operation, any .query statement generated by that operation is written in the database language specified here.
	Specify SQL as the query language if your report is based on any of the following:
	- JoinDef
	- Table owned by a user other than yourself or the DBA
	- Table, column, or correlation name that is a delimited identifier
	For additional information, see <u>Archiving a Report Definition</u> .

The following table lists the menu operations you can choose on the Save Report frame:

Operation	Function	
Save	Saves the report specification in the database with the specified report name; then returns to the Report Layout frame. You can select Save as often as you want during th process of editing a report specification.	
Cancel	Resets all field values in this frame to the original values and returns to the Report Layout frame without saving the current edits.	
Help	Standard operation.	

Using the Save Operation

To save a report specification using the Save operation on the Save Report frame:

- 1. Choose the Save operation from any RBF frame. If the Save submenu appears, choose the EditInfo operation.
 - RBF displays the Save Report frame, as shown in the preceding figure.
- 2. Make any changes to the report information displayed in the Save Report frame.
- 3. Select the Save operation.

A message near the bottom of the frame indicates that RBF is copying the edited report specification into the database, with the specified report and table names.


If you decide you are not ready to save the specification, select the Cancel operation instead.

When you select either Save or Cancel, RBF returns you to the Report Layout frame.

4. Continue editing the report specification, or select End to exit the frame and return to the Reports Catalog frame, or Quit to terminate your RBF session.

Save Report Pop-up

If you select the End or Quit operations on an RBF frame without first saving the report specification, RBF displays the Save Changes to Report pop-up, shown in the following figure. Select Yes to save the report specification or No to end without saving the specification.



Archiving a Report Definition


Use the Archive operation to make a text file copy of a RBF report specification that you can edit with a word processor or text editor. This allows you to use Report-Writer to add sophisticated data selection and formatting commands that are beyond the capabilities of RBF. You use the sreport command to save the edited report specification text file. Once saved, the report specification can be run at any time with the report command or the RBF Go operation to produce the report.

After saving a report specification with sreport, you cannot edit it from RBF. A report specification saved with sreport appears as a report title in the RBF Report Catalog frame, and you can run the report by placing the cursor on it and selecting the Go operation. However, if you choose the MoreInfo operation for a report saved with sreport, you can see that the RBF Editable Field? has been set to NO.

Using the Archive Operation

To archive a saved report specification:

- 1. On the Report Catalog frame, place the cursor over the name of the report specification that you want to archive.
- 2. Choose the Utilities operation.
- 3. From the Utilities submenu, choose Archive. The Archiving a Report popup appears.



4. In the File Name field, enter a file name for the report specification text file.

The Archive operation automatically adds .rw to the end of the file name you specify (unless you add your own extension). For example, if you entered the file name staffprojects, the archived file has the name, staffprojects.rw.

Comment Blocks in Archived Reports

RBF generates certain comment blocks in the report specification file. They are the width comment block, JoinDef comment block, and union select comment block. Comment blocks are visible when a report is archived or copied with the copyrep command.

Do not modify comment blocks in RBF reports. Changing a comment block can make the report unusable by RBF, sreport, and Report-Writer. If the report specification file has been archived, you can replace certain comment blocks with Report-Writer statements, if appropriate, as noted in the following subsections.

Width Comment Block

Following is an example of a width comment block:

```
/* WIDTH 148
DO NOT MODIFY. DOING SO MAY CAUSE REPORT TO BE
   UNUSABLE.
```

This comment block, which saves the report width, is generated for all RBF reports. If the report is archived and you want to override its width by using the .pagewidth Report-Writer statement, delete all three comment lines. For additional information, see the chapter "Report-Writer Statements."

JoinDef Comment Block

The following is an example of a JoinDef comment block:

```
DO NOT MODIFY. DOING SO MAY CAUSE REPORT TO BE
   UNUSABLE.
  md
```

RBF generates the JoinDef comment block for JoinDef reports only. You cannot modify or delete this comment block.

Union Select Comment Block

The following is an example of a union select comment block:

```
/*
DO NOT MODIFY. DOING SO MAY CAUSE REPORT TO BE
     UNUSABLE.
*
The union clause is commented out because a selection
     criteria on a detail table is specified.
*/
/*
union select poheader.orderno, poheader.orddate,
    poheader.vendorno, poheader.invoiceno,
    poheader.status,'' as partno,' ' as qty,
     ' ' as unit_pr,' ' as unit_pr, ' ' as det_tot
     from poheader poheader where not exists(select *
     from podettot podettot.orderno '$det_tot'))
*/
```

RBF generates the union select comment block for Master/Detail JoinDef reports that have a selection criteria on a column in a detail table. You must not modify or delete this comment block.

Copying Report Specifications

You can copy a report specification by using one of the following techniques:

- Create a report based on an existing report.
- Change the report specification name when saving it.

To create a report based on an existing report, choose the Duplicate option on the Creating a Report pop-up menu on the Report Catalog frame. For more information, see <u>Creating a Default Report Specification</u>.

To save an existing report specification to a new file with a new report specification name, edit the name on the Save Report frame. If you have already saved the report specification under its current name, changing the name before re-saving causes RBF to save a duplicate copy under the new name. For more information, see <u>Saving a Report Specification</u>.

You can also use the copyrep and sreport commands on the operating system command line to copy a report specification out of one database and into another. However, the sreport command saves the copied report specification for use with Report-Writer only, and the report cannot be edited with RBF.

Deleting a Report Specification

You use the delobj command on the operating system command line to delete a report specification. With this command, you can delete a:

- Named report
- List of reports that you specify on the command line
- Several reports whose names are listed in a file
- All reports that match a wild card specification

You can also use the delobj command to delete other database objects.

Chapter 9: Producing a RBF Report

You can produce reports:

- With the RBF Preview operation
- By running a report specification from RBF
- By issuing the report command from the operating system

This chapter provides instructions for using the Preview operation and for running a report specification from RBF. Additionally, it:

- Describes report destinations
- Provides instructions for running a report in the background, which allows you to continue to work in RBF while your report runs
- Tells you how to view reports on a screen and send reports to a file or printer

For instructions on using the report command to run a report specification, see the chapter "Using System Commands in the Forms-based Tools."

Report Destinations

You can send a report to the following destinations:

- Default
- File
- Printer

The default destination can be a file or your screen. If the report specification contains an .output statement, choosing the default destination causes RBF to send the report to the file specified in the statement. Otherwise, RBF sends the report to the screen. Only report definitions created or modified with Report-Writer statements and saved with sreport can contain .output statements.

After sending a report to a screen, you can:

- Send the report to a file
- Send the report to a printer
- Use the Forms Runtime System (FRS) printscreen command key to send the currently displayed form to a file or printer

For additional information, see Sending a Report to and from a Screen.

If you choose the File destination, RBF sends the report to a file whose name you provide. If the report specification contains an <code>.output</code> statement, as previously described, the file name you provide overrides the file name in the statement.

If you choose the Printer destination, RBF sends the report directly to a printer (either the default printer or a printer whose name you provide). If the report specification contains an **.**output statement, as previously described, RBF also sends the report to the file named in the statement.

Background Mode

VMS

If you send your report to a file or printer, you can either wait or not wait for it to finish running (the default is to wait). If you do not wait, you can continue using RBF while your report is running. The choice not to wait is sometimes referred to as running a report in the background or running in batch.

RBF submits the report to the batch queue, SYS\$BATCH. Be sure that your login.com file sets up your environment to run Ingres, because it is executed at the start of the batch job to run the report.

Report Log

RBF logs all report statistics and errors, if any, in a report log. Because all report errors go to this log file, we recommend that you do not run reports still under development in the background. By default, RBF creates the report log in the following directory:

Windows

Your working directory. ■

UNIX


Your working directory. ■

VMS

Your home directory. ■

Specifying Report Variables

When running a report in the background, RBF prompts you to enter values for the report's declared variables or runtime selection criteria, if any, before sending the report to a file or printer. If the report was saved with the sreport command, the variables must have been declared with prompt. Specify values for these variables on the Declared Variables frame (in the following figure), which contains a prompt for each variable. The prompt can be up to 98 characters long, but only 31 characters are displayed. To see the entire prompt, use the FullPrompt operation.



To specify the values:


- 1. Enter the value in the field beside the prompt.
- 2. Select the OK operation.

Producing a Preview Report


Use the Preview operation to produce a report on any table, view, or JoinDef. The Preview operation produces a report directly from the selected table or view; it does not produce a report specification.

To run a preview report:

- 1. Choose the Preview operation from the Report Catalog frame.
- 2. When the Run a Report Based on a Table pop-up appears (in the following figure), enter the name of the table, view, or JoinDef for which you want a report and select the OK operation.



3. The Choose a Report Style pop-up appears.



Place the cursor on the desired report style and choose the Select operation. You can choose:

- Tabular
- Wrap
- Block


The Master/Detail, Label, and Indented report styles are not available for Preview reports.

- 4. When the Select a Destination pop-up appears, place the cursor on the desired destination and choose the Select operation. You can choose:
 - Default—The report appears on your screen. See <u>Sending a Report to</u> and from a <u>Screen</u>.
 - File—If you choose File, see <u>Sending a Report Directly to a File</u> for additional instructions.
 - Printer—If you choose Printer, see <u>Sending a Report Directly to a Printer</u> for additional instructions.

Producing a Report from a Report Specification

To use a report specification to produce a report from RBF:


1. Go to the Report Catalog frame and position the cursor on the name of the report specification that you want to run. RBF displays the Select a Destination pop-up.



- 2. Place the cursor on the desired destination and choose the Select operation. You can choose:
 - **Default**—If you choose Default, the report either appears on your screen or is sent to a file, as described previously in Report Destinations.
 - File—If you choose File, see Sending a Report Directly to a File for additional instructions.
 - **Printer**—If you choose Printer, see <u>Sending a Report Directly to a</u> Printer for additional instructions.

Sending a Report to and from a Screen

When you send a report to your screen, RBF displays the first page of the report (in the following figure). If the report contains more than a single page, you can scroll through the report by using the ScrollUp, ScrollDown, ScrollLeft, and ScrollRight keys.



The report screen contains the following menu operations:

Field	Descriptions
Print	Sends the report to a printer.
File	Sends the report to a file.
Help, End	Standard operations.

After sending a report to a screen, you can:

- Use the Print operation to send the report to a printer. For instructions, see <u>Sending Reports from a Screen to a Printer</u>)
- Use the File operation to send the report to a file. For instructions, see Sending Reports from a Screen to a File.
- Use the FRS printscreen command to send the currently displayed form to a file or printer. For instructions, see Printing and Redrawing the Screen.


When sending a report from the screen to a file or printer, you can send the entire report or only the executed portion. The executed portion is the portion that you have viewed on your screen.

If you send a report from a screen to a file or printer, RBF formats the report to 20 lines per page. To format the report to 61 lines per page, send the report *directly* to a printer or file, as explained in Sending a Report Directly to a File and Sending a Report Directly to a Printer.

Sending Reports from a Screen to a File

To send a report from your screen to a file:

1. Select the File operation from the report menu. The Sending a Report to a File pop-up appears.



2. In the File Name field, enter the name of the file to which you want to send the report.

You can enter a file name or full file name specification. If you enter a file name only, RBF sends the report to your working directory.

3. To file the entire report, choose the OK operation. (If you have not run the report to completion, RBF executes the entire report before sending it to the file.)

To file the executed portion of the report only, choose the FilePartial operation.

Sending Reports from a Screen to a Printer

To send a report from a screen to a printer:

1. Select the Print operation from the report menu.

The Sending a Report to a Printer pop-up appears.



2. To send the report to a printer other than the default, type the printer name in the Printer field.


To send the report to the default printer, tab past this field. The default is to send the report to the default printer, which is determined by the system administrator.

- 3. In the Copies field, type the number of copies to print. The default is 1 and the maximum is 999.
- 4. In the File Name field, type the name of a temporary file to send the report to. You can enter a file name or full file name specification. If you enter a file name only, RBF sends the report to your working directory.
 - RBF first sends the report to this file and then sends it to a printer. After RBF sends the report to the printer, it deletes this file.
- 5. To print the entire report, choose the OK operation. (If you have not run the report to completion, RBF executes the entire report before sending it to the printer.)

To print only the executed portion of the report, choose the PrintPartial operation.

Sending a Report Directly to a File

If you send the report directly to a file, RBF displays the Sending a Report to a File pop-up.




To send a report to a file, complete the fields on this pop-up:

- 1. In the File Name field, type the name of the file to send the report to. You can enter a file name or full file name specification. If you enter a file name only, RBF sends the file to your working directory.
- 2. To run the report in the background while you continue working in RBF, type no (or n) in the Wait for Report to Complete field. The default is yes; that is, wait for the report.

If you enter NO, the Report Log field appears. Type the name of a file to receive report statistics and errors. (After the report runs, check this file for report errors.) If the report has variables, the Declared Variables frame appears. For instructions, see Background Mode.

Sending a Report Directly to a Printer

If you send the report directly to a printer, RBF displays the Sending a Report to a Printer pop-up.



To send the report to a printer, complete the fields on this pop-up:

- 1. To send the report to a printer other than the default printer, type the printer name in the Printer field. The default is to send the report to the default printer, which the system administrator determines.
- 2. Type the number of copies you want to print in the Copies field. The default is 1 and the maximum is 999.
- 3. To run the report in the background while you continue working in RBF, type no (or n) in the Wait for Report to Complete field. The default is yes; that is, *wait* for the report.

If you enter no, the Report Log field appears. Type the name of a file to receive report statistics and errors. (After the report runs, check this file for report errors.) If the report has variables, the Declared Variables frame appears. For instructions, see <u>Background Mode</u>.

Chapter 10: Using Report-Writer

This chapter introduces Report-Writer, and describes how it can be used with RBF. In addition, it provides an overview of the information you must gather before creating and producing a report. This chapter also discusses report specifications, initial setup statements, creating reports using variables and multiple tables, and setting up and printing reports.

What Is Report-Writer?

Report-Writer provides a high-level report language that allows you to guickly create sophisticated reports without having to write an application program. With Report-Writer, you can create regular production reports, as well as special reports for your application, when needed.

Report-Writer contains features and capabilities to create reports that meet your own special needs. Some broad categories of features include:

- Powerful tools to help you extract the data you want to print For a simple report, you can easily specify which table to access and how to sort the information. For a complex report, you can use a database query to retrieve selected rows of data to be used in the report.
- Support for nulls

Your Report-Writer specifications can include use of logical operators, null variables, dynamic definition of null strings, and complex null expressions for specifying how null data is to be reported.

- Complete control over the appearance of the report
 - You have complete control over the appearance of titles, headings, and placement of the data on the page. A powerful set of formatting commands allows you to specify exactly how you want the numbers and text information to print. Text formatting features include many features similar to word-processing capabilities, such as centering, justification, and automatic pagination.
- Powerful arithmetic capabilities

There are many functions to help you compute totals and averages over ranges of data in your report; many arithmetic functions make almost any kind of computation possible.

Expressions and variables for report flexibility

You can customize reports using expressions and variables as arguments to Report-Writer statements. Users can assign values to variables interactively by responding to a prompt that you specify.

Direct running of reports

You can use the report command with appropriate flags to run reports from a report specification that you saved to a text file or to the database. Running a report directly from a text file is more efficient for interactive testing.

Parameters to dynamically change the report each time it is printed You can specify ranges of data, table names to operate on, or any other information at the time the report is run. This allows you to use the same report formatting commands for many different reports.

Report-Writer and RBF

Report-Writer alone provides a sophisticated language for creating and customizing reports with detailed formats and multiple data sources. Report-Writer, used in conjunction with RBF, provides a way for you to create a report specification in RBF, use its archive operation to save the file as a text file, and then edit the file to add additional Report-Writer features.

RBF is an interactive, visually oriented, forms-based approach to creating simple reports. It offers its own default report styles in addition to the ones available in Report-Writer. In RBF, you can edit the column headings, formats, aggregates, and other parts of a default report in an on-screen display that shows the overall layout of your report.

Although RBF is not as flexible as the full Report-Writer formatting language described in this guide, it is adequate to create your report.

Before Starting Report-Writer

Before creating a report with Report-Writer, you must decide what data and what kinds of summary information (such as subtotals) you want in your report and how it is laid out on the printed page (or screen). These factors are important in determining how the data must be extracted from the database, how the data must be ordered, and where you must place *breaks* (logical divisions between groups of data) in your report. The following sections discuss data extraction, sorted data, and break actions. For information on specific statements, see Types of Report Specification Statements in this chapter or the chapter "Report-Writer Statements."

Obtaining Data for Reports

Depending on the intended use of the report, obtain the data for your report in one of three ways:

- Specify a report directly from an existing table (or view) with the .data statement.
- Specify a query to retrieve a specific subset of the data in the tables each time the report is run.
- Create one or more temporary tables based on one or more existing tables.

If you obtain data for your report with the .data statement, Report-Writer reads all rows and columns in the table each time you run the report.

You can limit the data for the report by specifying conditions in a where clause in the query. You can also specify a query that contains variables (generally in the guery's where clause) to be specified each time the report is run.

Another way you can obtain data for the report is to create a temporary table by specifying a series of query language statements in a .setup section. Create this section with the optional .setup statement in conjunction with the required .data or .query statement in your report. The .setup section can also be customized at runtime, using variables.

Sorted Data

Most reports display sorted data. It is often desirable to sort the data for the report for the sake of readability and usability. For instance, if you want a list of employees in order by job title within each department, you must sort the data in the table. Reports with subtotaling require sorted data. Sorting data is discussed in more detail in Specifying Sorts and Breaks this chapter.

Breaks

Breaks are divisions between parts of a report (such as page breaks) or between groups of data in your report (for instance, between data for Employee 1 and Employee 2). You specify breaks between groups of data by designating certain columns in a report as break columns. A break occurs when Report-Writer encounters a change of value in a break column while reading the data.

You can instruct Report-Writer to perform some action after a break has occurred by placing formatting instructions, called *break actions*, in a *header* or *footer* section associated with the break column. For example, you can instruct Report-Writer to print heading information for the next group of data rows, print summary information for the data rows associated with the last break column value, or skip to a new page and print a page header.

Automatic Report Breaks

When running a report, several types of breaks occur automatically:

- Start-of-report (report header)—When the report begins, a start-of-report (or report header) break occurs. This break can be thought of as a change of value from no data to some data. Use this break to specify titles and other heading information that appears once at the top of the report.
- End-of-report (report footer)—When the report finishes, an end-of-report (or report footer) break occurs. This break can be thought of as the change from some data to no data. Use this break to specify information that is only printed once, at the end of the report, such as grand totals, footnotes, and so forth.
- **Detail**—When each data row is read by the report, a *detail* break occurs. For the detail break, detailed printing of data items is most commonly specified.

Page Breaks

You can also specify break actions to occur at the top and bottom of pages. Page breaks occur when the report comes within a specified number of lines at the end of the page. You can define the page size to fit your needs, or specify a page footer to be printed at the page break, followed by a page header at the top of the next page. You might want to print page numbers, the current date or time, values of data items currently being processed by the report, or any number of other items.

Headers and Footers

Headers and *footers* are sections of your report code where you put instructions to tell Report-Writer what actions it must perform at the break for that part of the report.

You can specify headers and footers for the report itself, for page breaks, and for those columns you have designated as break columns. The page header appears at the top of each page, except the first. The only header you can specify at the top of the first page is the report header.

If you specify break columns, the header section is executed each time the column value changes, and the footer section is executed before the new value of the column is retrieved.

Report-Writer performs the specified footer actions after it has processed all rows in a group of data (indicated by the break designation). For instance, you can specify a footer action to occur after Report-Writer has read all rows for the entire report, all rows which can fit on a page, or all rows having the same value in the specified break column.

The footer section often contains instructions for calculating and printing subtotals or other summary information at the designated break. The special functions used to calculate this information are called set functions or aggregates, which you specify in print statements. A header action, if specified, can occur at the start of the report, at the start of a new page, or before the next group of data is processed.

You can specify both footer and header actions to occur in response to a change of value in a break column. Report-Writer performs the footer actions on the previous group of data rows and the header actions for the group yet to come. At the end of the report, however, Report-Writer performs only footer actions, because there is no more data. Similarly, at the start of the report, a break in each of the break columns occurs and Report-Writer can perform header actions for each of the major to minor break columns. However, because there is no previous group of data, footer actions are not relevant.

Detail Section

Detail instructions are Report-Writer statements that format, position, and print a row of data retrieved from the data table. The detail instructions are grouped together in a detail section.

Producing a Report

The following steps are required to produce a report with Report-Writer. These steps are described in detail in the sections below.

- 1. Create the report specification by entering your Report-Writer statements in a text file.
- 2. Save the resulting text file, or store the report specification in the database using the sreport command.
- 3. Execute the report using the report command.

Creating a Specification

The report specification is a text file consisting of Report-Writer statements that define the content and format of your report. You can create a report specification in one of the following ways:

- Create Report-Writer source code from scratch in a text file using any text editor and the language described in this guide.
- Use RBF to create a default report based on available default styles and the table or view of your choice; then edit the report in Report-Writer, if necessary.

Use the RBF Archive operation to save a RBF default report specification as a text file that you can edit in Report-Writer. The Archive operation allows you to choose a name for the text file. You can then edit the file to customize the report to your needs by adding or deleting Report-Writer statements.

Note: Once a RBF report specification has been archived for use with Report-Writer and stored in the database with the sreport command, the report specification can no longer be edited in RBF.

Saving the Report Specification

The sreport report specifier command is used to compile and store the report specification in the database. The sreport command reads the text file containing your report specification statements, which are described in this document, and performs the following tasks:

- Performs rudimentary syntax checking
- Loads the report specifications into your Ingres database from your base text file, including any additional Report-Writer code in files specified in .include statements

Note: If your database and database server reside on another system called the remote host, whenever you specify a database, indicate the v_n node (virtual node) name of the remote host.

Enters the report name in the Reports Catalog

If a report of the same name does not already exist in the Reports Catalog, sreport adds the specification into the database. If a report with the specified name already exists, sreport replaces the old report specification with the new one. The sreport command only adds or replaces a report if it detects no errors.

After you have stored a report specification with sreport, it appears in the RBF Report Catalog frame under the report name in your specification. You can run the report from RBF to produce it, but it cannot be edited from RBF.

Note: The sreport command compiles and stores a report for later use—it does not actually run it. You execute a report with the report command. If you want, you can execute a report directly from a text file without compiling and saving it to the database. For details, see the following section.

Executing the Report Specification

After you have successfully stored the report, you can run Report-Writer using the report command to create the desired output. Or, if you choose to run the report without compiling and storing the specification, you can use the report command with the -i parameter to read the report specification directly from a text file.

Executing a report directly from a text file is useful if you are testing the report for content and appearance and do not want to save the specification until it meets your standards. However, once you are satisfied with the report, you must store the specification in the database, using the sreport command.

After a satisfactory specification has been stored in the database, execute the report command each time you want to produce a new report. You need not execute sreport before issuing the report command, unless you modify the report specification.

Executing the report command performs the following tasks:

- Loads the report specification by reading in the report specification created by RBF or stored by an sreport command and performing additional error checking
- Runs the database query to extract the data (if specified)
- Writes the formatted report either to a file, to your screen, or sends the output to a printer

The report command offers the option of producing a default report from a specified table or view name. You can specify one of three available styles as the format for the default report. The three available styles are:

- Wrap
- Tabular (also known as column)
- Block

The wrap style lists the data in columns across the page, with column headings at the tops of the pages. For tables with too many columns to fit across the page, Report-Writer calculates a convenient place to wrap the remaining column headings or entries to the next line, directly beneath the first line of headings or entries. In this style of report, the column entries for a single record (row) can be displayed on consecutive rows of the report, with data in columns from the far right of a table wrapped beneath data in the initial columns.

The tabular style, like the wrap style, also lists the data in columns across the page, with column headings at the top of the page. However, depending on your output device, Report-Writer either truncates lines wider than the page or wraps them around to the next line.

The block style lists data without column headings, preceding each data value with the name of the column from which it comes and organizing the columns into blocks of data for each record.

If you do not specify a report style with the table or view name, Report-Writer chooses as the default style either the tabular (column) or block style, whichever is best suited for the report. Additional styles are also available through RBF.

Specifying Report Specifications

To specify a report, you must create a text file containing report formatting and structure statements. These statements define the data to be reported, the order of the data, the page layout, explanatory text to be inserted in the report, and the position and format of titles and data items.

Before developing your report specifications, you must know how you want the finished report to look. Consider some of the following issues:

- What data is needed from your database to create the report?
 If you must run a database query to get the data, design the query and run it from a terminal monitor to make sure it retrieves the desired data.
- How do you want the data sorted?
 If you want headings or footings for subgroups of your data, the data must be sorted on the columns that define the subgroups. You must choose the sort.
- What do you want the various headers and footers to look like?
 Decide whether you want titles, subtotals, or other aggregates, extra blank lines, or other types of headers or footers in your report. Sketch the report layout on a piece of paper to see how it looks.

- What information must be printed for each specific data row of the report, and in what format must the information appear?
 - For numbers, you must think about the number of significant digits to print, and the number of decimal places.
- What kind of page headers and footers do you want?

Types of Report Specification Statements

The following sections give a quick summary of the report statements, grouped by function for easier reference.

Report Setup Statements

Statements for setting up the overall report environment:

- The .name statement names the report.
- The .delimitedidentifier statement enables recognition of delimited identifiers for table, view, user, and column names in report specifications.
- The .setup/.cleanup statements perform data preparation and cleanup tasks (specified through query language statements). The .setup tasks occur before processing the guery, whereas .cleanup tasks occur after processing the query, but just before exiting the report.
- The .shortremark statement allows you to provide a brief description about the report. This information is included in the Reports Catalog and the Save window in RBF.
- The .longremark and .endremarkstatements allow you to enter a large amount of descriptive text to describe the report specification. This text is displayed in the RBF Save window and on the Reports Catalog frame in RBF when you choose the MoreInfo operation.
- Comments can be placed in the text file of report specifications if preceded with /* and followed with */. Comments are ignored in report processing.
- The .output statement sets up an external file to receive the report output.
- The .data or .query statements define the data to be used by the report output.
- The .sort statement defines the sort order of the data for the report.
- The .break statement specifies the break columns for the report and the order in which to process occurrences of breaks.
- The .declare statement declares variables to be a given data type and allows definition of a prompt string or value string if required for that variable.

- The .include statement specifies the inclusion of Report-Writer code residing in different files, and is executed when you run the sreport command to store the report specification.
- The .cleanup statement performs initialization tasks, (specified through query language statements) just before exiting the report.

Page Layout and Control Statements

You can specify the layout of report pages with the following statements:

- The .pagelength statement defines the page length, in lines.
- The .pagewidth statement defines the page width, in characters.
- The .formfeeds statement instructs Report-Writer to insert formfeed characters to force a page break at the start of the report and at the end of each page.
- The .noformfeeds statement suppresses the addition of formfeed characters to the end of pages in the report.
- The .leftmargin statement sets up a left margin as the default start of all new lines and for use with the .left and the .center statements.
 - If the left margin is not explicitly specified, Report-Writer determines this default automatically from an analysis of the other report formatting statements. For more information, see <u>Automatic Determination of Default Settings</u> in this chapter.
- The .rightmargin statement sets the right margin of the report for use with the .right and the .center statements.
- If the right margin is not explicitly specified, Report-Writer determines this default automatically from an analysis of the other report formatting statements. For more information, see <u>Automatic Determination of Default Settings</u>.
- The .need statement tests for a given number of lines on a page to see if a page break is appropriate.
- The .newpage statement skips to a new page, and optionally sets a page number.

Report Structure Statements

Statements used in setting up the structure of the report:

- The .header statement designates a group of formatting statements for the heading of the report, the page, or one of the break or sort columns.
- The .footer statement designates a group of formatting statements for the report footer, the page, or one of the break or sort columns.

The .detail statement designates a group of formatting statements for each data row in the report.

Column and Block Statements

You can use column and block statements to set up an explicit print position, column width, and format for the values contained in the named database column or for a report block (as defined by a .block statement). For instance, you can use the .position and .width statements to assign the starting print position and column width for a column or block, which are used in conjunction with text positioning statements such as .tab and .right justification. See Text Positioning Statements. If you do not explicitly specify column print positions, column widths, and column formats with these statements, then Report-Writer assigns defaults automatically from an analysis of the other report formatting statements. See Automatic Determination of Default Settings.

Use the following column and block statements:

- The .format statement explicitly specifies a print format (such as character string or standard decimal notation) for a column.
- The .tformat statement temporarily changes the print format for a column, only for the next value to be printed.
 - This statement is used for such functions as printing a value of a column on the first line of a page or of a group only, or including a currency symbol only on the first printing of a column value.
- The position statement sets up an explicit starting print position for a column, which can be used with the .tab, .right, .left, or .center statements.
- The .width statement sets up an explicit width for a column, to be used with the .right or .center statements.
- The .block and .endblock statements allow you to treat sections of the report as blocks.
 - This enables you to refer to positions on previous as well as on subsequent lines in the report. These statements can be used in conjunction with the .top and .bottom statements to align blocks of data horizontally adjacent to each other rather than in vertical sequence.
- The .top statement, used while in block mode, moves the current position to the top line of the current block.
- The .bottom statement, used while in block mode, moves the current position to the bottom line of the current block.
- The .within and .endwithin statements allow you to temporarily set the report margins to the confines of a specific column, using its position and width.

Text Positioning Statements

You can use text positioning statements to specify a print position—absolute or relative to other positions—for any text to be printed. Most of these statements also accept the name of a column for which a print position or column width has been set with the .position or .width statements as value. See Column and Block Statements.

Use the following text positioning statements:

- The .tab statement tabs to an exact or relative position before continuing printing.
 - It can be used with the name of a column to tab to the specified or default print position for that column.
- The .newline statement prints out the current line and skips to the start of a new line.
- The .center statement centers text around the center of the page or around a specified alternate position.
 - It can be used with the name of a column to center the text within the specified or default margins for that column.
- The .right statement right justifies text to the right margin or to a specified position.
 - It can be used with the name of a column to right justify text within the specified default margins for that column.
- The .left statement left justifies text to the left margin or to a specified position.
 - It can be used with the name of a column to left justify text within the specified or default margins for that column.
- The .lineend statement tabs to the end of the text on the current line before continuing to print.
- The .linestart statement tabs to the left margin before continuing to print.

Print Statements

Use these statements to print text or data values in a report:

- The .print statement prints text or values at a default position, or at a position which was previously specified with the column and block and/or text positioning statements.
- The .nullstring statement specifies a string of characters you want to print in the report whenever a null value is encountered in the data.
- The .underline and .nounderline statements control underlining for sections of text.

The .ulcharacter statement sets up a different underline character than the default, for use with Report-Writer underlining statements.

Use an expression in the .print statement syntax to specify the text or value you want to print. Expressions can include any (or any combination) of the following:

- Column names from the data retrieval statement
- Variables
- Constants
- **Functions**
- Aggregates
- Special report variables, such as the current_time, current_date, or page_number

You can optionally indicate the print format within the syntax of the .print statement, or you can specify it in a separate .format or .tformat statement for column values. See Column and Block Statements.

Conditional and Assignment Statements

Use these statements to specify alternative blocks of statements or to assign values to variables:

- The .if, .then, and .else statements specify alternative blocks of statements to be executed under specified conditions.
- The .let statement assigns a value to a variable, which can be used in subsequent computations.

Format of Report Specification Statements

Specify report formatting statements with a keyword proceeded by white space and a period (.), and optionally followed by parameters. The general format of a report formatting (specification) statement is:

statement {parameters}

This table describes the parameters in a report formatting statement:

Parameter	Description	
statement	One of the text formatting statements, such as .data or .tab. You can specify statements in uppercase, lowercase,	
	or mixed case letters.	

Parameter	Description
parameters	Optional parameters to the statement. Parameters take many different forms, depending on the specific statements. In many cases, parameters to the statement can also be variables and expressions. To obtain the value of a variable, precede the variable with a dollar sign (\$).

Here are some examples of report formatting statements; they include a .tab, .newline, .header, .println, and a .sort statement:

The sample reports in the appendix, "Report-Writer Report Examples" demonstrate the correct specification of statements.

Statement and Parameter Delimiters

You must precede and follow a report formatting statement with white space, either by explicitly entering spaces or tabs before and after a statement, or by using line breaks to separate the statements. White space following a statement must occur between the statement and any numeric parameter following the statement, as in:

```
.pagewidth 80
```

Lack or incorrect placement of white space statement delimiters can result in incorrect statement interpretation and could cause an error.

Statements can span any number of lines. Except where otherwise noted, commas separate multiple values for a parameter within statements, such as in the .sort or .print statements.

If a parameter is a user name, column name, or table name (including view names and synonyms), you can delimit it with double quotes (") to include spaces or other characters that are usually disallowed in these names. For more information, see <u>Delimited Identifiers</u> in the chapter "Report-Writer Expressions and Formats."

Using Schemas for Owner Qualification

A schema is a collection of database objects, such as tables. Each table, view, or synonym belongs to a schema that is determined when the object is created. The schema name corresponds to the user who owns the object. The schema name helps distinguish between objects with identical names and different owners.

In report specifications containing a SQL .query or .data statement, you can qualify a table name, view name, or synonym by specifying the schema to which it belongs (which also implies its owner), using the following construct:

schema.objectname

This allows you to access a table, view, or synonym owned by a user other than yourself or the DBA, if you have the correct permissions to access it.

A period (.) must immediately follow the schema name, although white space following the period is allowed. For example, Report-Writer allows the following construction:

schema. objectname

Both the schema name and the object name (table name, view name, or synonym) can be variables or delimited identifiers. A schema.objectname construct in which both the schema and table name are variables would take the form:

\$schema.\$objectname

A schema.objectname construct in which both the schema and object name are delimited identifiers would take the form:

"schema name"."object name"

A separate set of double quotes must surround each delimited identifier. For more information on delimited identifiers and variable substitution, see the chapter "Report-Writer Expressions and Formats."

You can use the schema.objectname qualification within the following statements:

- .cleanup
- .data
- .declare (in the with value string)
- .query (SQL only)
- .setup

If you do not qualify the table, view, or synonym with a schema, Report-Writer searches for the specified object in the following order:

- 1. Objects owned by the current user.
- 2. Objects owned by the DBA to which you have been granted access.
- 3. Objects in the system

Summary of Report-Writer Specifications

In summary, the general specification of a report can be defined as a collection of distinct groups of related statements. Some of these statements relate to the overall composition of the report and some relate to major action groups within a report:

- The Report Header—At the start of the report, you can specify some textual information to print and set up many of the report layout specifications, such as page size and margins. The report header precedes the page header on the first page of the report.
- Page Headers and Footers—At the top of each page, except the first page, you can specify that Report-Writer print a page header, and at the bottom, a page footer. These usually include titles, page numbers, the date and time the report was printed, and so on.
- A Break Header—When Report-Writer detects a change of value in any of the designated break columns, a break occurs. Before Report-Writer processes a new group of data rows, it performs the break header actions. Break headers often highlight information such as the value of the break column, as well as textual information.
- **Detail Section**—Report-Writer processes this group of statements as it reads each new row of data. These statements generally include the instructions necessary to format and print specific data items. The detail break is the only break that does not include a header and a footer.
- A Break Footer—Report-Writer processes the break footer at the end of a group of data rows (as determined by the next break). A break footer often prints the current value of the break column just before the break, or prints a subtotal associated with the data rows just processed.
- The Report Footer—At the end of the report, you can specify some textual information to be printed.

Sample Report

The following example demonstrates a simple report using Report-Writer. This report specification was created with a text editor, stored within the database with the sreport command, and run with the report command.

The report shows a titled listing of data from an existing table, edat in a database. The jobcat column is displayed only once for each job category value.

```
/* Sample report */
  . NAME
               iobcat
  .OUTPUT
               jobcat.out
  . DATA
               edat
  . SORT
               jobcat, name
  .HEADER REPORT
      .NEWLINE 2
      .CENTER
      .PRINT 'Sample Report'
      .NEWLINE 2
  .HEADER jobcat
    .TFORMAT jobcat(' zzzz ')
    .PRINT jobcat(b8), name(c15), dept,
      code, age, sales(f12.3)
    .NEWLINE
```

The report output looks like this:

```
Sample Report
10
    Adams, Joe
                  toy
                         0 22
                                10500.000
                         0 34
     Green, James
                  toy
                                43645.000
                         0
                            48
                                8690.000
     Smith, Tony
                  acct
                  music 0
                            56
                                234987.000
20
    Davis, Miles
     Tanhous, Karl
                  music 0
                            20
                                18765.000
     Jones, Mary
                  acct
                         1
                            34
                                34599.000
     Maney,Sikkim
                 none
                         1
                            51
                                15333.000
     Mellon, Tim
                  toy
                         0 24
                               45098.000
                         0
                            44
                                67876.000
     Mellon, Tim
                  any
     Norris, Bill
                  acct
                         0
                            22
                                23988.000
```

This list briefly explains each statement's function:

- The .name statement gives a name to the report, which is placed in the Reports Catalog by the sreport facility and is used by the report command to locate the report specifications.
- The .data statement identifies an existing table or view in the database that contains the data to report.
- The .sort statement indicates the order the data is to be displayed on the report.
- The .header report statement begins the section of Report-Writer statements to be performed at the start of the report.
- The .newline, .center, and .print statements are used in positioning and printing a title.
- The header jobcat statement begins the section of Report-Writer statements to be performed any time the value in the jobcat column changes. The .tformat statement is used to temporarily change the normal print format of the jobcat column on the next printing of jobcat, which occurs in the .detail section.

Normally jobcat is not printed. Its format is (b8), which means "print 8 blank spaces." The .tformat statement makes a change to the format to enable a one-time printing of this value, so the actual value of the jobcat column is output. The .detail statement begins the specification of Report-Writer statements to be performed on each row in the data table.

The .print statement within the detail section prints out the values of the columns in the formats given after the column names, or the default format for that type of data item, if no format is specified. The chapter "Report-Writer Expressions and Formats" describes the format specifications that appear in the parentheses following the column names in detail.

This table shows the table definition data on which the report was run:

Column Name	Туре	Length	Nulls	Defaults
jobcat	integer	4	yes	no
name	char	15	yes	no
dept	char	6	yes	no
code	integer	1	yes	no
age	integer	2	yes	no
sales	money		yes	no

This table shows the data for the sample report:

jobcat	name	dept	code	age	sales
10	Adams, Joe	toy	0	22	\$10500.00
10	Green, James	toy	0	34	\$43645.00
10	Smith, Tony	acct	0	48	\$8690.00
20	Davis, Miles	music	0	56	\$234987.00
20	Tanhaus, Karl	music	0	20	\$18765.00
30	Jones, Mary	acct	1	34	\$34599.00
30	Maney, Sikkim	none	1	51	\$15333.00
30	Mellon, Tim	toy	0	44	\$67876.00
30	Mellon, Tim	any	0	24	\$45098.00
30	Norris, Bill	acct	0	26	\$23988.00
30 30 30	Maney, Sikkim Mellon, Tim Mellon, Tim	none toy any	1 0 0	51 44 24	\$15333 \$67876 \$45098

Setting Up and Formatting a Report

At the beginning of your report specification file, you must include some statements to perform the following setup tasks:

- Name the report.
- Set up a report results file.
- Specify SQL statements to perform setup and cleanup tasks that occur before the main query is processed.
- Specify the table, view, or query from which data is to be obtained.
- Specify the optional inclusion of Report-Writer formatting statements residing in different files.
- Define the order in which the data is to be sorted.
- Define the break columns for the report.
- Declare any variables used in the report specification.
- Enter optional remarks and comments.

Use the .name statement to name the report, the .output statement to set up the report results file, and the .declare statement to declare variables for creating custom runtime query or formatting criteria.

Additionally, you can use the optional .setup statement to perform set up tasks (such as setting the lock mode, or creating a temporary table), and the .cleanup statement to perform clean up tasks (such as dropping a temporary table).

To obtain the data for your report, use either the .data or the .query statement. These statements are mutually exclusive. Use the .data statement to name a table or view in the database from which data can be obtained. Use the .guery statement to retrieve a subset of the available data, based on the results of the query. By including parameters in the query, you can allow users to choose the criteria for the report at runtime. For more information on queries and data retrieval, see Creating Reports with Variables and Creating Reports Using Several Tables.

To sort the data for your report, you must include a .sort statement in your report specification. The .sort statement lists the columns, in order of precedence, on which the data can be sorted. You also must specify the break columns, using the .break statement, if you want breaks to occur between data items in columns other than those specified in the .sort statement. For more information on sorts and breaks, see Specifying Sorts and Breaks.

To ensure standardization between reports and to take advantage of repeated report formatting statements, you can create commonly used Report-Writer formatting statements in text files for inclusion in report specifications. The include statement allows you to specify the text file containing the formatting statements. This statement can appear anywhere in your specification, if it is logically correct and is executed when you run the sreport command to store the report specification.

In addition to the report setup statements described above, you can include in your report specification some descriptive text about your report. The .shortremark and .longremark statements can be used to include text that appears on the RBF Save frame and in the MoreInfo display on the RBF Reports Catalog frame. Additionally, you can include comments anywhere in the report specification by enclosing them with the comment delimiters /* and */. The chapter "Report-Writer Statements" discusses the use and syntax of remark statements and comments in detail.

Creating Reports with Variables

For more dynamic report specifications, you can design a report using variables. You can use variables in queries or report formatting specifications. The values of the variables are specified at runtime by:

- Assigning initialization values using the .declare statement
- Responding to prompts for values
- Assigning values using the .let statement
- Passing values as parameters on the command line

You are *strongly* encouraged to define all variables with the .declare statement. Although Report-Writer recognizes any name preceded by a dollar sign (\$) as a variable, undeclared variables assume default types and characteristics that are often incompatible with their intended use. By defining variables with .declare, you can use the variables in all of the ways described previously. If a variable has *not* been defined through the .declare statement, you can assign it a value only by using a command line parameter or by entering a value in response to a runtime prompt. A value cannot be specified for an undeclared variable with a .let statement. In addition, unless the variable has been declared, attempting to pass a parameter with a null value to Report-Writer can produce incorrect results.

During execution of the report, the value assigned to a variable from data retrieval can vary, depending on the placement of the assignment statement in various .header, .footer, or .detail sections.

Note: A report cannot be run in the background if it contains undeclared variables.

Many Report-Writer statements accept variables, alone or in expressions, to allow users flexibility in determining report specifications.

For information on these specific statements: Report Setup Statements, Page Layout and Control Statements, Report Structure Statements, Column and Block Statements, Text Positioning Statements, Print Statements, and Conditional and Assignment Statements, see the chapter "Report-Writer Statements."

Procedures for using variables are common throughout Report-Writer statements. Exceptions are the .declare and .let statements, which are used to define the variables.

Using variables in the .query statement allows the end user to retrieve data that meets particular needs. For instance, the user can obtain a report on a single employee or on all employees in a specified department by entering the employee name or the department name at runtime.

To create a report with user-specified variable values, precede the variable with a dollar sign (\$) when specifying it in the query. At report runtime, the user can either put the value for the variable on the command line when invoking the report, or respond to a program prompt.

For example, suppose you have a banking database in which you keep a table of customer accounts. In this table you have fields for customer names (custname), customer account numbers (custno), checking account balances (checking), and savings account balances (savings). You want to create two reports. They must be identically formatted, but must present different information; one report must provide checking account balances, and the other must provide savings account balances. To accomplish this task you can write a query like this:

```
.declare account type = c10 with prompt
'Please enter "savings" or "checking":
.query
   select custno, custname,$account_type as val
        from account
```

The value of the variable account_type is the column name checking or savings rather than a string value.

As Report-Writer generates your report, it prompts you to enter an account type (savings or checking). Your response tells Report-Writer which kind of information it must retrieve with the query. If you respond to the prompt with checking, the completed query looks like this:

```
select custno, custname, checking as val
from account
```

For variables declared with the .declare statement, you can create a customized prompt string by using the with prompt clause, or you can specify an initial value for the variable by using the with value clause. For those variables that are undeclared, Report-Writer uses a default prompt string when prompting the user for the variable value.

You can also use variables in titles and other places within the report. For details on using variables in reports, see the .query, .declare, and .let statements in the chapter "Report-Writer Statements."

Creating Reports Using Several Tables

At times, you must use Report-Writer to produce a report from related information scattered across several tables that share one or more column definitions. You can do this several ways. You can specify the tables in a query in the .query section of your specification. Alternatively, you can build a report on an existing view or you can create a temporary table or view based on multiple tables using query language statements in the .setup section. You can then drop the table or view, or update a status, in the .cleanup section of the same report.

For a discussion and example of joining tables for a report, see <u>Joining Tables</u> for a Report in the appendix "Report-Writer Report Examples."

Specifying Sorts and Breaks

To produce a report that is orderly and easy to read, you must sort the retrieved data based on one or more of the columns. The data *must* be sorted if you want to include subtotals or other summary information in your report. In addition, you must specify the break columns in which a change of value signals Report-Writer to look for subtotaling or other special statements. For example, the Population Example in the appendix, "Report-Writer Report Examples" is a 1970 U.S. population report by region and state. To generate the regional population subtotals, the states must first be grouped by the value of the region column in the database, and breaks must occur at each change of value in the region column.

The easiest way to group rows is to sort them on the column that is used as the grouping column (in this example, region). Often, a report is sorted on more than one column. In such cases, the rows are first grouped on the basis of the first sort column (called the *major* sort column) and, within those groups, on the basis of the next sort column (called a *minor* sort column), and so forth. The sort order is specified by naming the columns in the .sort statement in a section containing report set-up statements. If you have a .query statement with an order by clause, you cannot use the .sort statement.

By default, Report-Writer assumes the break columns are the same as the sort columns. In the above example, for instance, no other breaks need be specified. However, you can override the default breaks by specifying break columns with the .break statement. Use the .break statement to specify your break columns if you have a .query statement with an order by clause.

The currently active list of break columns (specified by either the .sort or .break statement) is known as the break list. The first column in the break list indicates a major break column, while those that follow are considered minor break columns. A break on one break column automatically produces a break on all subsequent break columns in the currently active break list.

In the Account Example of the appendix "Report-Writer Report Examples," break columns are not explicitly specified, so breaks can occur on the sort columns. Report-Writer sorts the data based on acctnum (the major sort column) and, within acctnum, based on date. When a change occurs in the value of date, the date break occurs and Report-Writer looks for some of your formatting instructions to process. When a change in value occurs in the acctnum column, breaks in both acctnum and date occur.

You need not specify actions for every break in your report. You can specify sort columns (which produce breaks) simply for the appearance of the report. In the Population Example, in the appendix, "Report-Writer Report Examples," breaks in region invoke a number of summary and heading actions, whereas breaks in state do not.

Under certain conditions, such as with numeric columns of rounded values, breaks occur by default when the formatted value changes, not when the actual value changes. For example, assume a column is rounded to the first decimal place. There can be no break between the actual values of 35.87 and 35.92, because each rounds to 35.9.

You have control over how numeric values are rounded through the format specification. For more information, see the Format Specifications section in the chapter "Report-Writer Expressions and Formats." To force breaks to occur on the actual values rather than on the formatted values, specify the -t flag on the report command line. For more information on the -t flag, see the Report command in the chapter "Using System Commands for Forms-Based Tools."

Pagination in Reports

Pagination in the report is controlled by a number of statements. The .pagelength statement specifies the vertical size of pages, in lines, while the .pagewidth specifies the horizontal size of pages, in characters. Statements are used in the page header and footer sections to define actions to be taken at the beginning and end of each page. Use the .newpage and .need statements to force page breaks, and the .formfeeds statement to instruct Report-Writer to send a formfeed character to the printer after printing all lines that fit on the defined page. Line numbering begins at 1 (top line).

Before Report-Writer begins to print a report, it calculates the number of lines in the page header and footer you have specified. After printing each line, it compares the specified or default page length with the number of lines already printed. If there are only enough blank lines left to write the page footer, Report-Writer prints the page footer, issues a formfeed character (if specified) for a page break, updates the page number, and prints the page header for the next page.

If the .formfeeds statement is in effect, Report-Writer inserts the formfeed character at the start of the report and at the end of each page. In some cases, the .formfeeds statement is not needed. For instance, the .print statement automatically inserts formfeeds appropriate for 11-inch paper if you use the default page length (61 lines).

The following command, issued at the operating system prompt, sends the output of "myreport" to the specified file and to the default printer, assuming the default value of 61 lines per page. It does not require the .formfeeds statement.

```
report mydb myreport -frepfile.lis -o
```

For a format that uses 66 lines per page, you can add the flag -v66 at the end of the report command line, or you can use the .pagelength statement in the report specification.

For a printer that is 80 characters wide, you can add the flag -180 or use the .pagewidth statement.

For special forms and other printers, use the .formfeeds statement to instruct Report-Writer to insert its own formfeeds, or the .noformfeeds statement to prevent Report-Writer from inserting them.

You can use the .newpage statement to force an immediate page break at any point in the report. This statement causes Report-Writer to skip enough lines to get to the first line of the page footer (if specified), and to print the page footer before going to the top of the next page.

The .need statement forces a page break to occur if the remaining available lines on the page are less than the number of lines specified in the .need statement. It is used to keep lines of text together on the same page. For instance, this statement can be used prior to a break header to insure that enough lines remain on the current page to print the entire break header.

For details on using variables in reports, see <a>Page Layout and Control Statements in the chapter "Report-Writer Statements."

Setting Report Margins

Report-Writer can determine report margins by analyzing your report code. (Automatic Determination of Default Settings is discussed in more detail later in this chapter.) In most cases, the default settings generated by Report-Writer are guite adequate. However, in some cases you must define these settings explicitly, using the .leftmargin and .rightmargin page layout statements to indicate the starting and ending character positions. Horizontal character positions start at 0 (left margin).

In some reports, the right and left margins are changed dynamically to achieve different effects. See Dictionary Example in the appendix "Report-Writer Report Examples." In cases such as these, you must keep the margins for the page header and footer independent of the margins for the rest of the report, because the report margins have been set to values inappropriate for the footer and header when a page break is encountered.

Because the margins for the page header and footer can be independent of the margins for the rest of the report, the page header margins are stored separately. These can be determined automatically in the same way that default margins for the report are determined, or you can specify the margin setting statements, .leftmargin and .rightmargin, in the formatting statements for the page header.

For detailed information on margin setting statements, see Page Layout and Control Statements in the chapter "Report-Writer Statements."

Positioning, Formatting, and Printing Data

Report-Writer relies on three different groups of statements to print data in the correct place and format. These are:

- Column and block default setting statements
- Text positioning statements
- Print statements

You use these statements to:

- Set default print positions and widths for columns
- Position text explicitly, or left justify, right justify, or center column values within the margins defined by the column defaults
- Define the print format (for instance, character string or decimal) for the value to be printed
- Print an explicit value or print the next value in a column at the previously defined position, in the designated format

The following discussions describe the process of positioning, formatting, and printing data in more detail.

Note: Column defaults can be explicitly defined with the column and block or other statements noted previously. If defaults are left undefined, Report-Writer automatically determines the defaults from an analysis of your report code. See Automatic Determination of Default Settings. Explicitly set defaults override any automatically determined ones.

Setting Default Print Positions for Columns

Before you can print a value, indicate *where* it must be printed. As noted previously, Report-Writer automatically determines default column print positions from an analysis of the other report formatting statements. However, if you want to set up your own defaults, you can do so with the following column and block statements:

- position
- .width

Using the .position statement, you can effectively set up margins for each column. This statement allows you to set the starting print position for a column and optionally, the width of the printed column in number of characters. You can also set the width of a column with the .width statement. All horizontal print positions start at 0 (left margin).

To print columns horizontally adjacent to each other, you must reference the column names within the same .print statement, separated by commas. If possible, Report-Writer can print the columns next to each other, at the positions specified in the .position statement(s) or at default print positions.

In some cases, however, the following block statements can be used to exercise more control over the printing of horizontally adjacent text:

- .block and .endblock
- .top

- .bottom
- .within and .endwithin

The .block and .endblock statements allow you to define a block of formatting and print statements to be treated as a unit. Then, you can use the .top or bottom statements to reset the current line to the top or bottom of the defined block before processing the next statement. The .within and .endwithin statements temporarily set the report margins to the margins for a referenced column. This allows you to print text (such as the caption, Total) within the column margins without having to calculate the exact print position.

Column and Block Statements in the chapter "Report-Writer Statements" discusses the column and block statements in detail.

Positioning Text

In addition to the column and block default-setting statements, you generally use another group of statements, called text positioning statements, to tell Report-Writer how to position the text or data in relation to the default position. The text positioning statements are:

- .tab
- .newline
- .left
- .center
- .right
- .lineend
- .linestart

You can use the .tab statement with a column name to tab to the assigned print position for that column before issuing a .print statement. In addition to tabbing, text positioning statements allow you to center or justify text within the default column margins, or to position text at the beginning or end of a line or on another line.

You can also use the text positioning statements with explicit values (instead of column names) or variables for the tab setting, left and right justify positions, and so on. Explicitly set positions override column defaults. Text Positioning Statements in the chapter "Report-Writer Statements" discusses text positioning statements in detail.

Specifying the Print Format

The appearance of the text or data in your report is controlled by the format specification. For instance, the c format indicates a character string format and the e format causes a value to be printed in scientific notation. You can also specify the format with a template such as \$zz,zzz.nn, containing characters with special meanings, which define the way a value is to be printed.

The print format can be specified in the .print statement, or can be used in a .format statement to set a default print format for a column, as in the code fragment:

```
.format emp (c12), sal ('$zz,zzz,zzn.nn')
.print emp,sal
```

The results might look like this:

```
Jones $ 109,224.00
Smith $ 32,575.00
```

You can temporarily override a default column format with the .tformat statement to print the *next value only* in a different format. After the value is printed, the format returns to the original default type. This is useful for printing a dollar sign only once at the start of a page, for instance.

You can also override a default format by specifying the format as a parameter in the .print statement, as in this example:

```
.print salary ('zz,zzz,zzn.nn')
```

This code fragment causes Report-Writer to print salary values in the specified format, without the dollar sign, until it encounters another format or print statement for this column. For more information on print formats, see Format Specifications in the chapter "Report-Writer Expressions and Formats."

To indicate underlining of text or values, use the .underline and .nounderline statements. Any .print statements located between the .underline and .nounderline statements can produce underlined text. By default, the underline character is the underscore (_) for reports written to a file (reports written to the screen do not display underlining). You can change the default to any other character, using the .ulcharacter statement. All underline characters are printed on the line below the text, except for the underscore (_) character, which appears on the same line as the text. For more information on underlining, see Print Statements in the chapter "Report-Writer Statements."

Specifying What to Print

The actual text or value to be printed is specified as an expression in the .print statement syntax. The expression can be a column name, a constant, a function, an aggregate, a runtime report variable such as the current date and time, or a variable whose value is specified in a .declare or .let statement or on the command line, with or without a prompt.

By default, Report-Writer prints an empty string when it encounters a null value. You can change this default to any string of characters, using the .nullstring statement. For instance, you can tell Report-Writer to print the string "none" wherever it finds a null value in the data.

For more information on the .print and .nullstring statements, see Print Statements in the chapter "Report-Writer Statements."

Using Conditional and Assignment Statements

Use the conditional .if, .then, and .else statements to tell Report-Writer to execute alternative blocks of statements, under specified conditions. For example, you can test for the current line number or character position using one of the special report variables (discussed in the chapter "Report-Writer Expressions and Formats"), and then issue a .newpage or .newline statement. Or, you can execute alternative .print statements to suppress or print confidential data, based on a user's ID number stored in a declared variable.

The condition in an .if statement is a boolean expression that evaluates to true or false. Each of the following is a condition:

- a clause
- a boolean function
- not condition
- condition or condition
- condition and condition
- (condition)

Some examples of conditions in .if statements are:

```
age <= 50
not (age <= 50)
    (age <= 50) and (salary >= 40000) and
    (job = 'programming')
 age > avage
```

You can use the .let statement to assign a value to a declared variable. For instance, you could calculate the number of years which have elapsed since an employee was hired, and assign the result to a variable for a report on employee longevity. The .let statement is often used in conjunction with the .if, .then, and .else statements.

Note that the .declare statement, used to define variables, can also be used to assign an initial (first-time) value to the variable during the loading of the report specification. See the <u>.Declare</u> statement in the chapter "Report-Writer Statements."

For more information, see <u>Conditional and Assignment Statements</u> in the chapter "Report-Writer Statements."

Calculating and Printing Summary Data

You can use aggregate functions such as sum or count, as well as arithmetic and other built-in functions, to calculate subtotals and other summary values to be printed in a report. Many Report-Writer statements accept expressions. For example, you can specify an aggregate, arithmetic operation, or function in the .print statement for immediate printing of the calculated value. Alternatively, you can use an expression containing the operation in a .let statement to assign the calculated value to a variable prior to printing, in case you want to use the result in additional calculations.

Automatic Determination of Default Settings

If you have not explicitly specified them, Report-Writer calculates default settings for the right and left margins of the report, for the starting position and width of each column (for use with statements such as .tab and .right), and/or for the formats to use when printing columns. Report-Writer determines the default settings on the basis of an analysis of the other report formatting statements, which are performed after the report set up and page layout statements (such as .leftmargin), but before the first printing of the report.

Analysis of Report Formatting Statements

To determine default values, Report-Writer analyzes the formatting statements in reverse hierarchical order, from the *innermost* (detail level) statements to the *outermost* (report level) statements, as shown below:

- 1. .detail section statements
- 2. .footer statements for innermost sort column
- 3. .header section for innermost sort column

- 4. .footer and .header sections for the next to the last sort column, and so on
- 5. .footer and .header text for the page
- 6. .footer and .header text for the report

By analyzing the report code in this way, Report-Writer attempts to determine the innermost references to columns in the report, and to determine the leftmost and rightmost print positions indicated by the specified report formatting statements.

Determining Default Page Width

For default reports—that is, a report based on a table, as in the command, report mydb tblname—the page width default is 80 characters if the report is displayed on the screen, or 132 characters if the report is written to a file or sent to the printer. You can override the default with the .pagewidth statement. See the .Pagewidth statement in the chapter "Report-Writer Statements."

Determining Default Margins

If you explicitly specify the margins for the report with the .leftmargin and .rightmargin statements, these values are used. Otherwise, Report-Writer determines the minimum and maximum print positions for a line in the report while scanning the report formatting statements. If only one of the margins is explicitly stated, Report-Writer determines the other one during the scan. Report-Writer uses margins derived in this manner to determine line positions for the .center, .right, or .left statements, when these statements are used without specified parameters.

Determining Default Column Positions

If you do not specify a .position statement for a column, Report-Writer determines the column's default position for use with the .tab, .right, .left, or .center statements from the analysis of report formatting statements. Report-Writer determines default column positions by the first print position it encounters that has been specified for the printing of a value in that column or for an aggregate of that column.

Reports are usually set up in such a way that the innermost printing of column values occurs in the .detail statements of the report. Items such as column headers and aggregates, which print in the header or footer text for a break, can then use the .tab or another positioning statement in relation to the default position for the innermost position of a column. If you want to change the position of a column and its associated heading and/or aggregates, you must change the innermost print position for the column. Because all references to headers and aggregates are given in relative terms, Report-Writer changes their positions automatically.

As an example, see <u>Account Example</u> in the appendix "Report-Writer Report Examples." The default position for the amt column is determined by the cumulative aggregate for amt.

Determining Default Column Formats

If you do not specify a .format statement for a column, Report-Writer determines the column's default format in a manner similar to that used for determining the default column position. Report-Writer uses the innermost reference to a format for a column, or to an aggregate for a column, as the default format for a column. If you do not specify any formats for a column, Report-Writer determines defaults from the data type of the column, as described in <u>Default Formats</u> in the chapter "Report-Writer Expressions and Formats."

The default format for a column is best used in situations where you specify the format in the reference to a column in the .detail formatting statements. Aggregates of that column are specified in the footers for some of the breaks. Report-Writer then correctly uses the format you specified in the .detail section for the aggregates.

However, the .format statement is often quite useful for specifying a series of columns that are given the same format. For a good illustration of the use of the .format statement for this purpose, see Population Example in the appendix "Report-Writer Report Examples."

Determining Default Column Widths

If you do not specify a .width statement or width parameter to the .position statement for a given column, Report-Writer determines the default column width by the default format for that column, as specified by the .format statement or as determined from the analysis of report formatting statements. The default width of a column is the width required by the column format to print a value. Report-Writer uses the column width to determine the print positions for the .right or .center statements.

Chapter 11: Report-Writer Expressions and Formats

In Report-Writer, expressions are used to obtain data values in your report. Expressions are composed of constants, variables, columns, aggregates, and functions that are combined with operators to produce a single value. Each of these types of expressions is described in this chapter.

Many Report-Writer statements accept expressions that provide users control and flexibility in determining report values. In general, Report-Writer statements can be divided into the following two categories:

- Statements that accept only variables and are evaluated once during the loading of the report specification before retrieving the report data.
- Statements that accept any expression appropriate in the context of the statement and are evaluated each time the statement is executed.

For ways to use expressions in a given statement, see each individual statements in the chapter "Report-Writer Statements."

The .print and .query statements are two statements in which you often use variables and expressions. One way you use variables in the .guery statement is in the where clause to retrieve a subset of the data. In the .print statement, you can use expressions to print multi-column functions, such as adding columns together, or to determine the printing format.

You can compare expressions to other expressions in conditions for the .if statement, or use them in the .let statement to specify a value to be assigned to a variable. For details on conditional and assignment statements, see the chapter "Report-Writer Statements."

The following example uses several expressions. The example uses a database, which has a table of shipments featuring part number, number of defective parts in a shipment, and the total number of parts in a particular shipment. Suppose you want a report of the shipments grouped by part number, with the calculated percentage of defective parts for all the shipments of that part. The following report fragment would accomplish this:

```
.sort partno
.footer partno
    .print partno, ' IS '
    .print (sum (defective)/sum (total)) * 100,
      % DEFECTIVE
    .newline
```

In the previous example, the following are expressions:

```
partno
' IS '
(sum(defective)/sum(total)) * 100
'% DEFECTIVE'
```

Because no print formats have been explicitly specified in the preceding report code, Report-Writer automatically uses predetermined ones.

ANSI/ISO Entry SQL-92 Compliant Databases

For reports based on tables or views in ANSI/ISO Entry SQL-92 compliant databases, observe the following conventions regarding object names when referencing them within Report-Writer statements and commands:

- Names consist of 18 or fewer characters.
- Regular identifiers begin with an alphabetic character (a z) and contain only alphabetic, numeric, or underscore (_) characters.
- Regular identifiers are case insensitive.
- Delimited identifiers are case sensitive.

These conventions differ somewhat from standard Ingres conventions for regular and delimited identifiers, which can be up to 32 characters long. Also, in standard Ingres databases, regular identifiers can include the non-alphanumeric characters #, @, and \$, and delimited identifiers can be case insensitive, depending on how the database was created.

Delimited Identifiers

Using delimited identifiers allows you to reference database objects such as tables and columns that are identical to reserved words or that contain spaces or other characters disallowed in regular identifiers. If the database was created as case sensitive, you can also use delimited identifiers to distinguish between identical names with different cases (for example, "SALES" as opposed to "Sales").

Using Delimited Identifiers

Report-Writer statements accept delimited identifiers as table names, view names, synonyms, column names, correlation names, and schemas under the following conditions:

- Recognition of delimited identifiers has been turned on with the .delimid statement.
- Statement syntax permits a table, view, column, or schema.
- SQL is used in .query statements.

Report-Writer also accepts delimited identifiers as user identifiers in system level commands.

In order for Report-Writer to recognize delimited identifiers within a report specification, the .delimid statement must be included in the report specification file. For details, see the chapter "Report-Writer Statements." Otherwise, any use of delimited identifiers within the report specification results in errors when compiling the report.

If you attempt to run a report with delimited identifiers against a database created with an earlier release, Report-Writer interprets the delimited identifiers as string constants, which can result in unpredictable behavior.

Ingres supports delimited identifiers in .query statements if the query language is SQL. Delimited identifiers cannot be used in QUEL queries.

QUEL User Notes

Delimited identifiers are not available for use in QUEL queries. If you have specified the .delimid statement in a report specification that uses a QUEL query, Report-Writer suppresses recognition of delimited identifiers during the query. Although it is possible to use delimited identifiers in other parts of your report specification, we do not recommend that you do so if you are using a QUEL guery, as this can cause errors in some circumstances. For example, if you create temporary tables in the .setup section that have delimited identifiers as table names or columns, those tables or columns cannot be accessed in a QUEL query.

Specifying Delimited Identifiers

You can specify delimited identifiers for database objects in the following circumstances:

- Within the report specification code
- On the command line within a command to run a report

 On the command line in response to a prompt for runtime substitution of a variable

To specify a delimited identifier in the report specification code, as a parameter on the command line, or in response to an Ingres prompt on the command line, enclose the delimited identifier within double quotes (") and escape any embedded double quotes by doubling them. For convenience, we refer to this as *editable format*. You can specify delimited identifiers as follows:

Editable Format	Stored Format
"Dave's table"	Dave's table
"Dave's ""Expert"" Witness table"	Dave's "Expert" Witness table

You can use delimited identifiers in the following circumstances:

■ As a table, view, or synonym:

```
.data "Dave's table"
```

As a column name:

```
.print "Stocks & Bonds"
```

 As a correlation name and column name in correlation name.column name constructs:

```
.query
    select "t-1"."col 1" as col1, "t-2"."col 2"
    as col2
    from table_one "t-1", table_two "t-2"
```

• When using schemas for owner qualification, for either or both the schema name and/or object name, as follows:

```
"schema 1".table2
dave."Dave's table"
"schema 1"."view table1 & table2"
```

• On the command line, as a *username* for the -u flag, *groupid* parameter for the -G flag, or database object in a command parameter

If your operating system requires additional delimiting and dereferencing quotes for delimited identifiers on the command line, see the *System Administrator Guide*.

When using schemas for owner qualification or when specifying a user ID on the command line, the schema or user ID must be enclosed in double quotes if it does not conform to the conventions for regular identifiers. If a schema or user ID contains characters unacceptable in a regular identifier, such as in Da Vinci or O'Neil, then all objects created by that user can have a schema name that must be specified as a delimited identifier in double quotes.

In addition, the DBA can specify at database creation time whether Ingres stores user IDs in uppercase, lowercase, or mixed case when impersonating that user with the -u flag on the command line.

Also, any schema name that Ingres creates by default based on that user ID is stored in mixed case and must be specified as a delimited identifier, in double quotes, when qualifying an object with an owner name.

For more information on schema names or specifying case conventions for user identifiers in a particular database, see the Database Administrator Guide for the system on which your database resides. For information about specifying embedded quotes and other special characters in delimited identifiers, see the SQL Reference Guide.

Case Sensitivity

When specifying delimited identifiers, follow the rules for case as defined for your database. In standard Ingres databases, delimited identifiers can be either case sensitive or case insensitive, as determined by the DBA when creating the database. By default, standard Ingres databases are case insensitive.

In databases compliant with ANSI/ISO Entry SQL-92 standards, delimited identifiers are case sensitive.

Multiple Delimited Identifiers

Separate multiple delimited identifiers on the same line with at least one space, because Ingres perceives two adjacent double quotes ("") as an escaped double quote ("). For example, suppose you specify:

```
.print "abc""def"
```

it is interpreted as:

```
.print abc"def
```

Separating delimited identifiers with white space prevents confusion. For example, include a space between the delimited identifiers "abc" and "def":

```
.print "abc" "def"
```

It is correctly interpreted as:

```
.print abc def
```

Precedence over String Constants

When enabled, delimited identifiers take precedence over double-quoted string constants. For example, the following statement causes Ingres to attempt to print the value of a column named "a b c" rather than the string "a b c".

```
.print "a b c"
```

If it does not find a column matching that description, Ingres issues an error.

To avoid any potential confusion between delimited identifiers and string constants or format templates, we strongly recommend that you use single quotes (') to delimit quoted strings and format templates within Report-Writer. The only exception to this rule is in .query statements if the query language is QUEL, in which case double quotes for string constants and format templates are required. This does not pose a problem because delimited identifiers are not allowed within QUEL queries.

Reserved Words

The identifiers in the following table are reserved for use as keywords by Report-Writer. If delimited identifiers have been turned on, you can use reserved words as delimited identifiers for table, view, column, schema, or user names by enclosing them within double quotes ("). Using reserved words in QUEL is not allowed. Follow all rules for using delimited identifiers, as described in the section, Delimited Identifiers. Using reserved words in any other way is likely to produce incorrect results when Report-Writer prints the report.

abs	current_time	locate	page_width
and	date	log	position_
ascii	decimal	lowercase	numberreport
atan	detail	max	right
average	dow	maximum	right_margin
averageu	exp	maximumu	run
avg	float	maxu	shift
avgu	float4	min	sin
break	float8	minimum	smallint
cnt	int4	minimumu	sqrt
cntu	integer	minu	squeeze
concat	integer1	mod	sum
COS	integer4	not	sumu
count	interval	null	table
countu	left	or	trim
cum	left_margin	page	uppercase
cumulative	length	page_length	w_column
current_date	line_number	page_number	w_name
current_day			

If you use one of the reserved words in the preceding table as a column name without delimiting it, Report-Writer issues a warning message. It also supersedes the definition of the built-in function with the column name you specify. All further references to the reserved word relate to the column, not to the Report-Writer function, which could produce unexpected results.

All SQL keywords are also reserved words in Report-Writer. For a complete list of these keywords, see the SQL Reference Guide.

Types of Data in Expressions

Expressions can contain any of the following data elements, which are described in the following sections:

- String Constants
- **Numeric Constants**
- **Date Constants**
- Columns
- Variables
- Special Report Variables
- Aggregates
- Operators
- **Boolean Functions**
- Format Specifications

String Constants

Many reports have lines of text that appear in the body of the report. You can specify these string constants by enclosing them in single quotation marks ('). The correct syntax for specifying any character string in most Report-Writer statements is:

'string'

However, within a .query statement, use the quotes appropriate to your query language. As a convention, this document uses single quotes ('), as required in SQL queries, to delimit string constants.

Using double quotes for string constants outside of SQL queries does not necessarily generate an error in Report-Writer. However, if you activate delimited identifiers with the .delimid statement, using double quotes for string constants produces unexpected or incorrect results, because Ingres interprets the double quotes as signifying a delimited identifier.

If you want to include a single quotation mark within the text of a single-quoted string constant, enter it as two adjacent single quotes, together on a single line, so that Report-Writer does not assume it has found the end of a string. Ingres automatically interprets a backslash (\) within a single-quoted string as a literal backslash, unless it precedes a wild card character. For more information about wild card characters, see Operations.

For information on dereferencing double quotes within double-quoted strings, see the QUEL User Notes section below.

Examples of valid strings delimited by single quotes are:

```
'This is a string'
'This string has extra blanks '
'This string has one \ backslash in it'
'This string has a ''single-quoted'' string in it'
'This string has a "double-quoted" string in it'
```

QUEL User Notes

Within a .query statement, the following must be enclosed in double quotes ("):

- String constants
- Dates, specified as string constants
- Numeric templates

You need to dereference a literal double quotation mark (") or backslash (\) within a string constant by preceding it with a backslash (\).

Examples of valid strings delimited by double quotes are:

```
"This is a string"
"This has extra blanks"
"This has a \"quoted\" string in it"
"This has one \\ backslash in it"
```

The syntax for a valid absolute date and time format for use in a QUEL query is:

```
"mm/dd/yy hh:mm:ss"
```

An example of a valid numeric template for use in a QUEL query is:

```
"$zz,zzz,zzn.nn"
```

Hexadecimal Strings

To specify a nonprintable character, you can use a hexadecimal string constant with the following format:

```
X|x'nn\{nn\}'
```

The introductory X identifies the string as a hexadecimal string constant. You need to specify the nonprintable character as two hexadecimal digits (nn) in the range 0-9, a-f, or A-F, and the string must contain an even number of characters. There must be no intervening white space between the X and the single-quoted string of hexadecimal digits. The X and the hexadecimal digits are case insensitive. Report-Writer interprets hexadecimal constants as data type varchar.

You can use hexadecimal string constants anywhere you use a string constant. Ingres translates the hexadecimal constant into its corresponding character value. The following example uses hexadecimal string constants in a .query statement:

```
.auerv
     select binary_key, X'414243' as abc
     from my table
     where binary_key = X'5A7B0034'
```

You can also use hexadecimal string constants as expressions in .print statements. Hexadecimal strings are intended for use primarily with the q0 format, which sends the string directly to the output device as is, without interpretation. Hexadecimal strings in .print statements without the q0 format are interpreted by the formatting routines and can produce undesirable results or cause Report-Writer to fail. For more information on the q0 format, see Control Character Format Q0.

QUEL User Notes

Hexadecimal string constants are not supported within QUEL .query statements.

Numeric Constants

Numeric constants consist of an integer, a decimal point, and a fraction or exponential (scientific) notation. You can specify numeric constants with the following format, where *d* is a digit:

```
[+|-] {d} [.{d} [e|E[+|-]d[d]]]
```

Some examples of valid numeric constants are:

```
23
8.97327
4.7 e-2
```

Numeric constants can range from -10**38 to +10**38 (** denoting "to the power of") with precision to 17 decimal places.

Report-Writer interprets a numeric constant as follows:

- Integer, if it has no decimal point or exponent. A numeric constant of type integer is treated as type decimal if the value exceeds i4 (4,294,967,295)
- Decimal, if it has a decimal point but no exponent. Under the following circumstances, a numeric constant of type decimal is treated as type float:
 - If the total number of digits exceeds 31
 - If you have set the II_NUMERIC_LITERAL environment variable/logical to float
- Float, if it has an exponent, or if the release is Ingres 6.4 or earlier and it has a decimal point.

Date Constants

Dates are referenced as single-quoted character string constants. However, as with string constants within a .query statement, the quotation marks appropriate to your query language must be used.

Report-Writer accepts the following variations as date expression. You can specify a date template for the date expression in the .print, .format, or .tformat statement. For details, see Format Specifications.

Absolute dates - Examples of expressions of the date November 15, 1998 are:

```
'11/15/98'
'15-nov-98'
'15-nov-1998'
'11-15-98'
'98.11.15'
'111598'
'11/15'
'11-15'
```

The string 'today' is a legal absolute date, which returns today's date as its value. The string 'now' is a legal absolute date and time, which returns today's date and the current time as its value.

■ Absolute times - Examples of expressions of the time 10:30:00 are:

```
'10:30:00'
'10:30:00 pst
'10:30'
```

Note: Report-Writer supplies the appropriate time zone designation. Time formats are assumed to be on a 24-hour clock. However, time entered with a designation of "am" or "pm" is automatically converted to 24-hour internal representation. Any such designation must follow the absolute time and precede the time zone, if included. If you do not specify a date with an absolute time, today's date (that is, the current day) is supplied.

Absolute date and time - Examples of expressions of the date and time, November 15, 1998, 10:30:00 are:

```
'11/15/98 10:30:00'
'15-nov-98 10:30:00'
'11/15/98 10:30:00 pst'
'15-nov-98 10:30:00 pst'
'11/15/98 10:30'
'15-nov-98 10:30'
'11/15/98 10:30 pst'
'15-nov-98 10:30 pst'
```

Date intervals - Examples of date interval expressions are:

```
'5 years'
'8 months'
'14 days'
'5 yrs 8 mos 14 days'
'5 years 8 months'
'5 years 14 days'
'8 months 14 days'
```

Time intervals - Examples of time interval expressions are:

```
'23 hours'
'38 minutes'
'53 seconds'
'23 hrs 38 mins 53 secs'
'23 hrs 53 seconds'
'28 hrs 38 mins'
'38 mins 53 secs'
'23:38 hours'
'23:38:53 hours'
```

Columns

To reference a column value in a data row currently being processed, you can:

- Specify the database column name directly
- Reference the column by a name you give it in the as clause of a select statement within the .query statement

You can use the select as construct in a .query statement to select a column by its correlation name, which is not recognized by Report-Writer, and then give it another name, which you can use in Report-Writer statements. You can also use this construct to select a column whose name is a delimited identifier, and give it another name that is easier to reference in other Report-Writer statements.

To reference a column from a database table by a name other than its actual database column name, use the following construct in a .query statement:

select columnname as resultcolumn from tablename

Thereafter, refer to the column by its result name, as in the following print statement:

.print resultcolumn

After assigning a result name in the query, any references to *columnname* causes an error.

Use a delimited identifier to reference a column that contains spaces or other non-alphanumeric characters, or that is identical to a reserved word. For more information on delimited identifiers, see <u>Delimited Identifiers</u>.

Columns are comprised of one of the following types of expressions:

- Numeric
- Character
- Abstract

This table shows the SQL data types that belong to each of these categories. See the QUEL User Notes for QUEL data types.

Numeric	Character	Abstract	
decimal	char	date	
float	С	money	
float4	text		
float8	varchar		
integer1			
integer2 (smallint)			
integer4			

Report-Writer perceives and treats a user-defined (UDT) data type as a character string. It does not recognize columns of data types long varchar, byte, byte varying, and long byte. If you specify a column of this data type in the query, Report-Writer silently ignores and does not print values for that column.

Note: If Report-Writer encounters subsequent references to a column of the long varchar, byte, byte varying, and long byte data types—for example, in sort operations—it issues an error message and terminates the report.

QUEL User Notes

The QUEL data types that belong to these categories are listed in the following table:

Numeric	Character	Abstract	
f4	char	date	
f8	С	money	
i1	text		
i2	varchar		
i4			

Variables

Variables are user-defined symbol names that represent a data value that can change with each run of the report. Many Report-Writer statements accept variables as parameters. For example, in a .query statement you can use variables as substitutes for any part of a query. See .Query in the chapter "Report-Writer Statements."

In Report-Writer, assign variable values in the following ways:

- At report runtime, as a parameter on the command line or in response to a default or custom prompt
- In a .declare statement, as an initial value for a variable (useful for variables evaluated during the loading of a report specification)
- In a .let statement, where you can assign a value to a variable for use within the body of the report. See .Let in the chapter "Report-Writer Statements."

You define variables through the .declare statement, which allows you to name a variable. The .declare statement also allows you to:

- Create your own custom prompt
- Specify the data type and nullability of the variable

You are strongly encouraged to define all variables with the .declare statement. By declaring variables, there are no limits to the ways you can use them in your report. Although Report-Writer recognizes any name preceded by a dollar sign (\$) as a variable, undeclared variables assume default types and characteristics that are often incompatible with their intended use.

If you use a variable in your report without declaring it, you can assign it a value only by using a command line parameter or by entering a value in response to a runtime prompt.

You *cannot* specify a value for an undeclared variable with a .let statement. In addition, unless the variable has been declared, attempting to pass a parameter with a null value to Report-Writer can produce incorrect results. For more information, see the <u>.Declare</u> statement in the chapter "Report-Writer Statements."

Note: If you run reports from the RBF catalog, they cannot be run in the background if they contain undeclared variables.

When you specify variables for runtime substitution of values in expressions, precede the variable name with a dollar sign (\$). The dollar sign cannot be embedded within the variable (for example, var\$name). In addition, variable names must follow these rules:

- Can be up to 32 characters long. Valid characters are letters, digits, and underscore (_). For ANSI/ISO Entry SQL-92 compliant database restrictions, see ANSI/ISO Entry SQL-92 Compliant Databases.
- Must begin with a letter
- Cannot match any of the reserved words listed in the Reserved Words section
- Any commas (,), parentheses (), or colons (:) required in the statement syntax must be explicitly stated and cannot be part of the variable.

Some examples of variables are:

\$myvar
\$your_name
\$salary
\$start_date

A variable used in a query can be referenced in other parts of the report specification as well, but it must always be preceded by a dollar sign (\$). The variable must logically correspond to its intended value. For example, if the variable is used as a number, its value must be a legal Ingres number. If the variable is used as a date, its value must be a legal Ingres date. Otherwise, Ingres interprets the variable as a character string.

Special Report Variables

You can use the following predefined report variables to generate and print such items as page numbers and the date and time a report is run, or to control the report layout.

Name	Description	
page_number	Current page number in the report—pages number from 1	
line_number	Current line number on the page—starts at 1	
position_number	Current column position on the page—starts at 0	
page_length	Current length of the page	
page_width	Current width of the report	
left_margin	Current left margin column position.	
right_margin	Current right margin column position	
current_date	Date when report is run. This does <i>not</i> include the time component. For full date and time, use <i>current_time</i> .	
current_day	Day of the week when report is run. This is a three- character string (for example, Mon or Fri).	
current_time	Complete date and time of day when report is run	
w_name	Name of the column currently being used in a within block. This is a string.	
w_column	Value of the <i>w_name</i> column in the data row currently being processed.	

Aggregates

You use an aggregate function, or set function, such as sum or count, to perform a calculation on data read in from one column, up to the occurrence of a break in another column. For instance, in the section, Population Example in the appendix, "Report-Writer Report Examples," the regional population subtotals represent use of the sum aggregate on each of the columns tot, tot_18 to 65, tot_under18, and tot_over65 up to a break in region. Additionally, the population totals at the end of the report represent use of the sum aggregate for the same columns up to a break in "report."

You specify which data must be used in the calculation by naming the column containing that data as a parameter of the aggregate function. In the POPULATION example, the columns containing the relevant data are tot, tot_18 to 65, tot_under18, and tot_over65. You indicate the cut-off point for the data to be included in each calculation by placing the aggregate function within the footer section for a particular column or section of the report. The aggregate value is calculated each time a break occurs in the specified footer. Aggregates can be *non-unique* or *unique*, *simple*, or *cumulative*. A *non-unique* aggregate performs a calculation based on *every* value read in from the aggregate column up to a break in the specified footer. A *unique* aggregate performs a calculation on each *break value* in the aggregate column, up to a break in the specified footer. (Depending on how the data is sorted and where the aggregate is specified, the *break values* can or cannot be the actual *unique* values in a column.)

A *simple* aggregate produces a single value, calculated on all the values in the aggregate column up to a break in the specified footer. A *cumulative* aggregate calculates a running total for each value in the aggregate column up to the break containing the aggregate instruction. Simple and cumulative aggregates can be either non-unique or unique. Aggregate types are discussed in more detail later in this section.

The following aggregates are allowed:

Aggregate	Description
avg	Finds the average value of a numeric column up to a break in the specified footer. You can take the average value of a date data type column that has date intervals. Taking an average of absolute dates generates a DBMS error.
avgu	Finds the average value of the unique or break values for a numeric column up to a break in the specified footer. You can specify avgu only for a break column. For additional details, see Unique Aggregates . You can take the average value of a date data type column that has date intervals. Taking an average of absolute dates generates a DBMS error.
count	Counts the number of rows up to a break in the specified footer.
countu	Counts the number of unique or break values up to a break in the specified footer. You can specify countu only for break columns. For additional details, see Unique Aggregates .
min	Finds the minimum value of a numeric or date column up to a break in the specified footer.
max	Finds the maximum value of a numeric or date column up to a break in the specified footer.
sum	Calculates the sum of a numeric column up to a break in the specified footer. In columns of data type date, you can use the sum aggregate only if the column contains time intervals. Taking a sum on absolute dates generates a DBMS error.

Aggregate	Description
sumu	Calculates the sum of the unique or break values in a numeric column up to a break in the specified footer. You can specify sumu only for break columns. For additional details, see <u>Unique Aggregates</u> . In columns of data type date, you can use the sumu aggregate only if the column contains time intervals. Taking a sum on absolute dates generates a DBMS error.

Syntax of Aggregates

The basic syntax of an aggregate specification is:

[cumulative|cum [(breakname)]] aggname (columnname [, preset])

The following table describes the parameters for specifying aggregates:

Parameter	Description
breakname	Name of a break in the report (either a sort column name, or report or page). It is optionally used as a parameter to the cumulative function to indicate when to reset the cumulative. The value of a cumulative represents the aggregate since the last break in breakname. The default value for <i>breakname</i> is report (that is, the value represents the cumulative value of an aggregate since the start of the report).
aggname	Name of the aggregation to be executed. Valid <i>aggnames</i> and synonyms are average (avg), decimal, count (cnt), minimum (min), maximum (max), and sum.
columnname	Column name in the data being reported. Values of this column are aggregated. Therefore, the column must be of the correct type (that is, numeric or date columns only for all aggregates except count). Note that a <i>columnname</i> must be specified for the count aggregate even though all columns result in the same value.

Parameter	Description
preset	Either a constant value or the name of a column that is used for pre-setting the aggregate before calculations begin. This is used primarily with the cumulative function to set an aggregate to a non-zero value before starting.
	For example, if to print an account balance next to each transaction in an account, use the cumulative sum aggregate with a <i>preset</i> to the starting balance of the account. For an example, see Account Example in the appendix "Report-Writer Report Examples." If <i>preset</i> is a constant, the aggregate is set to that value. It can be a numeric or date constant.
	If <i>preset</i> is a valid numeric or date column name, the aggregate is set to the value in that column at the start of the break over which the aggregate is defined. In addition, <i>preset</i> is not allowed with the average aggregate.

Simple Non-Unique Aggregates

The scope of a simple non-unique aggregate is determined by the context in which it is specified. For example, if you specify sum (salary) in the footer for the report, it refers to the sum of salary for all rows read in the report. If you specify sum (salary) in the page footer, it refers to the sum of salary for all rows that were processed during the printing of each page. If specified in the footer for a break in department, sum (salary) refers to the sum of salary for all rows in each department.

You can specify simple aggregates only in the .footer section for breaks, because these calculations are intended to provide summary information.

Unique Aggregates

You specify a *unique* aggregate by following the aggregate name with the letter "u," as in sumu, countu or avgu, respectively. The difference between a unique and a non-unique aggregate is that a unique aggregate performs an operation only when the value in the aggregate column *changes*, while a non-unique aggregate performs the operation for *every* value in the aggregate column. Therefore, a unique aggregate performs its calculation only on the break values in the specified column, up to the break containing the aggregate instruction.

For example, if you specify the aggregate, count(region), in the report footer for the sample report in the Population Example section of the appendix, "Report-Writer Report Examples," the result would be 51 (remember District of Columbia), because there are 51 rows in the report. However, if you specify "countu(region)" instead, the result would be 9, because nine breaks occur on region.

The number of breaks is not necessarily the same as the actual unique values in the column. This result depends on the break in which the aggregate instruction is placed, and on whether the data in the aggregate column has been sorted or not. For instance, countu would produce a result of 3 on the following unsorted data in Column 1, even though the data contains only two unique values, because three breaks would occur:

Column 1

AAA

BBB

AAA

Cumulative Aggregates

Preceding an aggregate name with the keyword cumulative or cum indicates that the cumulative value of an aggregate is to be calculated and printed. As such, you can specify cumulatives in any context (for instance, in detail sections), because you use them to provide running totals. You can apply a cumulative to any of the other aggregates. Cumulatives are particularly useful for applications that need to use running totals, such as account balance applications.

If you do not specify a breakname after the cumulative keyword, or if you specify a breakname of report, Report-Writer assumes that the cumulative aggregate refers to all data rows processed since the start of the report. If a breakname of page is specified, the cumulative aggregate refers to all data rows processed since the last page break. If a breakname is specified which is one of the break columns, the cumulative aggregate refers to all data rows processed since the last break in that column.

You can specify the *preset* parameter to set the cumulative function to a constant value or to the value of a column when it is initialized (that is, at the start of the break in *breakname*). For example, in the <u>Account Example</u> section of the appendix, "Report-Writer Report Examples," the aggregate, cum(acctnum) sum(amt,balance), in the detail block indicates a common use of the *preset* parameter. When a break occurs in acctnum, Report-Writer sets the cumulative function to the value of balance. As each new transaction is processed, Report-Writer adds the value of amt to the cumulative aggregate. Because deposits are positive and withdrawals are negative, the cumulative aggregate reflects the running balance.

Rounded or Actual Values

By specifying the +t flag on the report command line, aggregates utilize the rounded values for any floating point column whose format has been specified in a .format statement with a template or as numeric F (for additional information about these formats, see Format Specifications). That is, the value of the aggregate for such a column is derived from the rounded values for the individual column rows. To force the aggregate to utilize the actual, rather than the rounded, values, specify the -t flag on the report command line. For more information, see the Report command description.

Examples of Aggregates

Here are some examples of aggregates:

min(salary)

Specified in footer for dept, this element gives the minimum value of salary for all data rows in a dept.

average(age)

Specified in the footer for class, this element gives the average age for all data rows in a class.

count (name, 200)

Specified in the footer for the report, this element gives the count of the number of data rows in the report + 200.

sum(transact,oldbal)

Specified in the footer for acct, this element gives the sum of transact, initialized by the value of oldbal at the start of each acct.

cumulative avg(height)

Specified in the detail text, this element gives the cumulative average of height since the start of the report.

cum(acctnum) sum(amt,balance)

Specified in the detail text, this element gives the cumulative sum of amt since the last change in acctnum and initialized by the value of balance at the last change of value in acctnum.

Operations

The following operators can be used in expressions.

Arithmetic Operators

Numeric expressions can be combined arithmetically to produce other (compound) expressions. The following arithmetic operators are supported (in descending order of precedence):

Operator	Description
+, -	plus, minus (unary)
**	exponentiation
*,/	multiplication, division
+, -	addition, subtraction (binary)

Unary operators group from right to left, while binary operators group from left to right. You can force the order of precedence of operations using parentheses. For example, the following is an expression with no ambiguity as to precedence of operations.

```
(salary + 1000) * 12
```

Some arithmetic operations on date expressions are available:

Date Addition:

interval + interval -> interval interval + absolute --> absolute

Date Subtraction:

interval - interval -> interval absolute - absolute --> interval absolute - interval -> absolute

Report-Writer does not support multiplication or division of date values. For example, suppose birthdate is an absolute date column in the data table. The following constructs give tomorrow's date and the age of the person with that birthdate, respectively:

```
current_date + date('1 days')
```

current date - birthdate

Comparison Operators

A comparison operator is a binary operator that takes two expressions as operands. Both expressions must be of the same type—numeric, string, or date. The following operators are recognized:

Operator	Description
=	equal to
!= or <>	not equal to
>	greater than
>=	greater than or equal to
<	less than
<=	less than or equal to

All comparisons are of equal precedence. When comparisons involving character strings are made, all blanks are ignored.

Conditional Expressions

A conditional expression has the form:

expr comp op expr

The *expr* is an expression, and *comp_op* is a comparison operator.

An expression can be enclosed in parentheses without affecting its interpretation, as in the following examples:

```
(age < 50)
((salary * 12) >= 20000)
```

A conditional expression evaluates to true or false. It can contain partial match specification characters.

Pattern Matching with Wild Cards

You can indicate partial matches of character string data in a conditional clause in an .if statement and in the where clause of a query by using special wild card characters with the comparison operators. The character string data must be delimited by single quotes (except when used in a QUEL query).

Wild Cards in an .If Clause

When used in a string within an .if condition, the special meaning of wild card characters can be disabled by preceding them with a backslash (\) character. Report-Writer then interprets the wild card character literally. Thus, * refers to the asterisk character. When used outside of an .if condition, wild card characters have no special meaning and are *always* interpreted literally.

You can use the following wild card characters within a conditional clause in an .if statement for the purpose of comparing character string data:

Character	Description
*	Matches any string of zero or more characters
?	Matches any single character
[]	Matches any of the characters in the brackets

Any of these special characters can be used alone or in combination to specify partial match criteria:

Example	Description
ename = '*'	Matches all values in the "ename" column
ename = 'E*'	Matches any value beginning with "E"
ename = '*ein'	Matches any value ending with "ein"
ename = '*[aeiou]*'	Matches any value with at least one vowel
ename = 'Br???'	Matches any five-character value beginning with "Br"
ename = '[A-J]*'	Matches any value beginning with A, B, C,, J
ename = '[N-Z]???'	Matches any four-character value beginning with N, O, P,, Z

You cannot use blanks in bracketed expressions such as "[A-J]*" or "[N-Z]???".

Wild Cards in Queries

When a string appears within the where clause of a .query statement, the wild card conventions must follow those of the database query language you are using to retrieve the data.

Logical Operators

Report-Writer recognizes the following Boolean logical operato	Report-Writer	recognizes	the	following	Boolean	logical	operator
--	---------------	------------	-----	-----------	---------	---------	----------

Operator	Description
not	logical not - negation
and	logical and - conjunction
or	logical or - disjunction
is null	test to see if value is null
is not null	test to see if value is null

These operators take Boolean expressions as operands and evaluate to true or false. The not operator has the highest precedence of the operators; and/or have equal precedence. You can use parentheses for arbitrary grouping. Logical operators group from left to right.

Built-in Functions

You denote a function by a function name, followed by an operand (or two operands) in parentheses. When valid expressions are substituted for the operands, the result itself is an expression that evaluates to a number, string, or date.

The resulting expression assumes the default print format appropriate for that type of expression (number, string, or date), as described in Format Specifications. For example, if you specify the following:

```
.print uppercase(column1)
```

The expression, uppercase(column1), evaluates to a string. When printing the string, Report-Writer uses the default format for strings (c0), *not* the format for the specified column. If you want to print the resulting expression in a format other than the default for number, string, or date, specify the format explicitly in a .print or .format statement; for example:

```
.print uppercase(column1) (cf30.6)
```

A faster and more efficient way to unconditionally print the column value in uppercase for all retrieved rows would be:

```
select uppercase(column1) as column_a
.format column_a (cf30.6)
.print column_a
```

You can nest functions to any level.

All of the Ingres conversion, numeric, string, and date functions are syntactically allowed in the .cleanup, .query, and .setup statements. For all other Report-Writer statements the following table lists the supported functions. To determine if a function is appropriate for use in a particular context within Report-Writer, see its description in the SQL Reference Guide, or if you are using an Enterprise Access product, the OpenSQL Reference Guide.

The following table lists the built-in functions:

Conversion	Numeric	String	Date
c(expr)	abs(n)	charextract (c1,n)	date_gmt (<i>date</i>)
char(expr)	atan(n)	concat(<i>c1</i> ,c2)	date_part (<i>unit,date</i>)_
date(<i>expr</i>)	cos(n)	left(c1,len)	date_trunc (<i>unit,date</i>)_
dow(<i>expr</i>)	exp(n)	length(c1)	interval (unit,date_interval)_
float4(expr)	log(n)	locate(c1,c2)	_date(s)
float8(expr)	mod(n,b)	lowercase(c1)	_time(s)
hex(<i>expr</i>)	sin(n)	pad(<i>c1</i>)	
int1(expr)	sqrt(n)	right(<i>c1,len</i>)	
int2(expr)		shift(c1,nshift)	
int4(expr)		size(c1)	
money(expr)		squeeze(c1)	
object_key (<i>expr</i>)		trim(c1)	
table_key (expr)		uppercase(c1)	
text(expr)			
varchar(<i>expr</i>)			
vchar(expr)			

Boolean Functions

A Boolean function is like a built-in function except that it returns a value of true or false instead of number, string, or date. The result of a Boolean function cannot be printed; it can only be used as a condition. A Boolean function is composed of a function name followed by an operand in parentheses.

The break function is the only Boolean function found in Report-Writer. For more information, see <u>Breaks</u> in the chapter "Using Report-Writer." Its syntax is:

```
break (columnname)
```

The *columnname* parameter must either be a break column (that is, it must be in the sort list) or the value report.

If you specify a break column, Report-Writer returns a value of *true* if the current value for that column has changed from the previous value *or* if the current value in any column of higher precedence than *column* has changed. If neither the current value for *column* nor the current value of any column of higher precedence in the sort list has changed, it returns a value of *false*. If report is specified, it returns *true* if the end of the report is reached; otherwise, it returns *false*.

The following example illustrates the use of Boolean functions:

This generates a new page when the employee number breaks, but only if no break occurs on the department.

Format Specifications

You can give special format specifications to expressions in the report in the .print statement or in a .format or .tformat statement. The format determines whether the data is printed as a character string, decimal value, date, or in some other format. Be sure to use the right type of format depending on the type of expression. As discussed in Automatic Determination of Default Settings in the chapter "Using Report-Writer," if no format is specified, Report-Writer determines a default format from an analysis of your other statements.

The following formats are allowed:

- B format specifies that the value be blanked out. This is a special format used for blanking out a field, for use with temporary formats in conjunction with the .tformat statement.
- C format specifies character strings.
- Date templates are formats that allow you very detailed control over the appearance of dates and times in your reports.
- E format specifies numeric expressions printed in scientific notation.
- F format specifies numeric expressions.
- In the F format, you can control the placement of the decimal point or suppress it entirely.
- G format specifies numeric expressions. This format chooses either F or E format, depending on what fits in the field width. This format also guarantees that decimal points align, whether printed in F or E format.
- I format specifies numeric expressions printed in integer format.
- N format specifies numeric expressions like G format, but decimal points do not necessarily align.
- Numeric templates are complex formats for numeric data that allow you to control placement of dollar signs, commas, or other punctuation within the number.
- Q0 format specifies character strings like the C format, except that control characters can be part of the character string without affecting the layout of the report.
- T format specifies character strings like the C format, except that it displays certain unprintable characters in a visible format.

Each of these formats is discussed in more detail in its own section later in this chapter.

You can precede any of the preceding format specifications with a sign character to indicate that the value printed is to be either right justified, left justified, or centered. The following list describes each of the valid sign characters:

- A minus sign (-) indicates that the data is to be left-justified in the specified field width.
- An asterisk (*) indicates that the data is to be centered in the width of the field.
- A plus sign (+) indicates that the data is to be right-justified in the specified field width.

The behavior of the sign characters is different for each data type. The discussions for each data format type later in this section contain examples of the effect of each sign character. If no sign is given, justification defaults to left justification for character fields and right justification for numeric fields.

Default Formats

If you do not specify a format after an expression, Report-Writer uses a default format.

Default Format for Strings

Report-Writer prints any string expression without a specified format in its entirety. That is, the default format for strings is c0.

Default Format for Columns

If you do not specify a column format with the .format statement, Report-Writer uses the default format for the column. The default format is based on the data type of the column. For more information, see Determining Default Column Formats in the chapter "Using Report-Writer."

The following table lists default formats for SQL data types:

SQL Data Type	For Reports Other Than Block Style	For Block Style Reports
c1 - c35	c1 - c35	c1 - c35
c36 - c <i>n</i>	cj0.35	cj0.35
where <i>n</i> is the lesser of the maximum configured row size and 32,000		
char(1) - char(35)	c1 - c35	c1 - c35
char(36) - char(n)	cj0.35	cj0.35
where n is the lesser of the maximum configured row size and 32,000		
text(1) - text(35)	c1 - c35	c1 - c35
text(36) - text(n)	cj0.35	cj0.35
where n is the lesser of the maximum configured row size and 32,000		
varchar(1) - varchar(35)	c1 - c35	c1 - c35

SQL Data Type	For Reports Other Than Block Style	For Block Style Reports
varchar(36) - varchar(n)	cj0.35	cj0.35
where n is the lesser of the maximum configured row size and 32,000		
integer1	f6	f10
smallint (integer2)	f6	f10
integer (integer4)	f13	f10
decimal (31.31 - 31.0)	Based on size. For example, decimal (5.1) defaults to f7.1, allowing additional digits for the decimal point and an optional + -sign.	
float(n	n10.3	f10.3
float4	n10.3	f10.3
float8	n10.3	f10.3
date	c25	c25
money	'\$.nn'	- '\$.nn'

Note: All character data types are fully supported in non-Ingres databases accessed by way of an Enterprise Access product, in which case the column size limit can be greater than the lesser of the maximum configured row size and 32,000.

Default Format for Special Report Variables

The following non-string report variables have the corresponding default formats:

Report Variable	Default Format
page_number	f6
line_number	f6
position_number	f6
left_margin	f6
right_margin	f6

Report Variable	Default Format
page_length	f6
page_width	f6
current_date	d' 3-feb-1901'
current_time	d' 3-feb-1901 16:05:06'
w_column	The default format for the column currently being used in a .within block. See the default column formats in the previous table.

Default Format for Aggregates

The default format for all the aggregates except count(u) is the format of the column being aggregated. For count(u), Report-Writer uses the default format Nw, where w is the width of the column being counted.

Default Format for Numbers

Any other numeric expressions such as numeric constants, numeric functions, numeric parameters, and arithmetic operations have a default format based on its data type.

Default Format for Dates

Any other date expressions, such as the date function, date parameters and date arithmetic operations, have a default format of c0, which appears in the report as if specified as "d' 3-feb-1901'" for an absolute date, "d' 3-feb-1901 16:05:06'" for an absolute date and time, or as the needed portion of the template "d' 1 yrs 2 mos 3 days 4 hrs 5 mins 6 secs" for a time interval.

QUEL User Notes

The default column formats used for reports based on QUEL data are identical to those listed in the Default Formats for Columns table, but with the following data types designated differently in QUEL:

In place of: Use QUEL Data Type:	
integer1	i1
smallint	i2

In place of:	Use QUEL Data Type:
integer	i4
float4	f4
float	f8

Blanking Format B

The B format can be used with any type of data to print blanks in place of the value of the specified variable.

The syntax of the B format is:

 $\mathbf{b}w$

The w parameter specifies the desired field width.

You can specify either an uppercase B or lowercase b (they are identical). Report-Writer ignores the value of the expression, and prints w spaces in the output instead.

You can use this format in conjunction with the .tformat statement, which temporarily changes a column format, to suppress printing of unchanged values in break columns. For more information, see the description of the .Tforma statement in the chapter "Report-Writer Statements."

Character String Format C

Use the C format to print string expressions.

The syntax of the C format specification is:

[-|*|+] c[f|j]n[.w]

The following table describes the C format parameters:

Parameter	Description
f	Instructs Report-Writer to fold (wrap) text by breaking between words when printing strings that span multiple lines. Tab and carriage return characters produce tab and carriage return actions within the string. Must be specified in conjunction with either <i>w</i> and/or <i>n</i> .

Parameter	Description
j	Instructs Report-Writer to fold (wrap) text by breaking between words, and to right justify text by padding the line with blanks between words, when printing strings that span multiple lines. Tab and carriage return characters produce tab and carriage return actions within the string. Must be specified in conjunction with either w and/or n.
n	Specifies the maximum number of characters to print. If there are more than <i>n</i> characters in the string, it truncates the excess. If there are fewer, it pads the rest of the string with blanks until <i>n</i> characters have been printed. Use a value of 0 for <i>n</i> if the entire string is to be printed, regardless of its length.
W	Specifies the number of characters to print on each line. If n is greater than w , then more than one line is written, in newspaper-style column format. By default, w is set to n .

When specifying the previous options, you can use either uppercase or lowercase letters interchangeably. The optional field width n can be specified to give an exact width. If n is specified and the character string is less than n characters wide, blanks are added to the output to assure n characters. If the string is longer than n characters, only the leftmost n characters are printed and the rest are ignored.

If you specify a value for w as well as n, you can print text in column format (that is, newspaper style). The f and j modifiers can be used to assure breaking of words at blanks, or right justification of text. If neither is specified, simple wrap-around of text occurs, regardless of where the line break might occur.

Report-Writer has a default maximum of 310 lines for printing a character string. If you exceed this maximum, some of the text can not appear in your report. You can override the default by specifying the -wmxwrap parameter on the command line.

If you use the C format statement, the following unprintable characters are printed as spaces:

- Horizontal tab
- Vertical tab
- Line feed
- Form feed
- Carriage return

Note that tabs and carriage returns cause tabs and carriage return actions if you are using multi-line formats, such as cf or cj.

To print a visual representation of unprintable characters, use the T format statement. For more information, see Character String Format T.

These examples illustrate the use of the C format.

Example 1:

Suppose your report contains a character column called name that you want to print, and a value for name is Jones, J. Then, suppose you issue the following six .print statements:

```
.print 'First :', name (c15),':First' .nl
.print 'Second:', name (c4), ':Second' .nl
.print 'Third :', name (c0), ':Third' .nl
.print 'Fourth:', name (-c15), ':Fourth' .nl
.print 'Fifth :', name (+c15), ':Fifth' .nl
.print 'Sixth :', name (*c15), ':Sixth' .nl
```

The print statements produce, respectively, the following six lines of output:

```
First :Jones, J.
                      :First
Second: Jone: Second
Third :Jones, J.:Third
                      :Fourth
Fourth: Jones, J.
Fifth :
            Jones, J.:Fifth
Sixth: Jones, J.
                     :Sixth
```

Example 2:

If your data includes the character string, "Now is the time for all good men to come to the aid of their party.", the following table shows the effect of three different format specifications used to print the output on multiple lines in three different ways:

c0.15	cf100.15	cj0.15
Now is the time	Now is the time	Now is the time
for all good m	for all good	for all good
en to come to t	men to come to	men to come to
he aid of their	the aid of	the aid of
party.	their party.	their party.

Because the second format specification, cf100.15, specifies an actual number of character positions to print, Report-Writer prints out two blank lines after the text, to pad out the 75 characters already printed to the full 100-character column width specified.

After Report-Writer prints a string in column format, it sets the position for the next text output to the top line of the column, at the end of that line (in the example, this would be after "time").

Date Format D

You can output date expressions using a D format specification. The date format specification is a D or d, followed by a quoted string *template* indicating exactly how a specific date would be printed. Ingres requires that you delimit the template with single (') or double (") quotation marks; single quotes are recommended for consistency with requirements for quoting string constants.

The date is left justified by default, but by specifying the optional plus sign (+), you can right justify the date. The template must be surrounded with single quotes.

The syntax of a date template is:

[-|*|+] **D**|**d** 'template'

The date format parameter is as follows:

Parameter	Description	
template	A string of characters representing a sample absolute date and time	

Specifying Absolute Date and Time Templates

Specify the absolute date and time format by a string containing one of many possible representations of a sample date and time, such as "SUN Feb 3 04:05:06 p.m." or "FEB 03 16:05." The selection and arrangement of the sample date and time elements within the template indicate the way you want all dates and times to be displayed or printed. The following date and time must be used as the basis for your template:

Sunday, 1901 February 3 at 4:05:06 p.m.

Note: This specific date and time was chosen as the sample for the template because Sunday is the first day of the week, and arguments 1, 2, 3, 4, 5, and 6 are the year, month, day, hour, minute, and second, respectively. This makes it easy to interpret the elements of the template correctly. For instance, in the template '2/3/01,' the 2 indicates the month (February), the 3 indicates the day (3), and 01 indicates the year (1901).

Your template can contain only the weekday of Sunday and the month name of February (or their accepted abbreviations), the day of the month as 3, the year 1901, the time 04:05:06 p.m. in various formats, and the time designation p or p.m. (including the periods for p.m.). Report-Writer prints any other word exactly as entered.

You can specify 24-hour (military) time by using 16 instead of 4 for the hour in your template. Do not use p or p.m. with 24-hour time.

You can use all or only some of the arguments in your template, and you can arrange the arguments in any order. You can use any combination of lowercase and uppercase letters, and you can abbreviate the day of the week as Sun or Su and the month as Feb or Fe. The resulting output assumes the same format as your template.

You can create ordinal numbers from numbers by suffixing them with the appropriate "st", "nd", "rd", or "th," as in:

d'3rd day of the 2nd month of 1901'

To print the day of the year, you specify the day and year, but leave out the month:

d'3/1901'

The following examples demonstrate the use of absolute date and time templates:

Format	Value	Output
d' 2/ 3/01'	25-oct-1998	10/25/98
d' 2/ 3/01'	5-jun-1909	6/ 5/09
d'03-02-01'	5-oct-1998 07:24:12	05-10-98
d'2/3/1'	25-oct-1998	10/25/98
d'2/3/1'	5-jun-1909	6/5/9
d'010203'	5-oct-1998	981005
d'1\ 2\ 3'	5-oct-1998	98 10 5
d'FEBRUARY, 1901'	1-sep-2134 09:13:02	SEPTEMBER 2134
d'FEBRUARY, 1901'	7-may-1962 13:08:42	MAY, 1962
d'Sunday'	5-oct-1998	Wednesday
d'SUN Feb 3 16:05 1901'	13-oct-1998 07:24:03	THU Oct 13 07:24 1998
d'FEB 03 4:05:06 p.m.'	12-dec-1998 22:13:03	DEC 12 10:13:03 p.m.
d'04:05:06 PM'	5-oct-1998 14:08:45	02:08:45 PM
d'04:05:06 PM'	5-oct-1998 07:29:12	07:29:12 AM
d'16:05 pst'	5-oct-1998 14:08:45	14:08 pst
d'3/01'	5-oct-1998	278/98
d'February 3rd'	29-jul-1954	July 29th

Format	Value	Output
d'3rd day of 1901'	11-may-1999	131st day of 1999

If you use the special report variables, <code>current_date</code>, <code>current_day</code>, or <code>current_time</code>, to print an absolute date, day, or date and time, be sure to use only that portion of the date template that matches the returned variable value. Specifying more of the template than you need causes Report-Writer to print zeros (0) or empty strings for the unneeded portions of the template. For example, suppose you specify the following:

```
.print current_date(d' FEB 03 1901 16:05:06')
```

Report-Writer returns the current date, but with a time of 00:00:00, because the *current_date* report variable returns only the date and not the time.

Numbers requiring more than one digit replace preceding blanks or zeroes in the template, as needed. If there are no more available preceding blanks or zeroes, the number expands to the right. Ingres retains in the output any single blank following a letter, word, or number in the template; it does not replace such a blank with a succeeding number.

You can align columns of numbers by preceding them with an appropriate number of blanks or zeroes (as shown by the first three examples in the preceding examples of output).

Because full month and weekday names (as well as numbers without preceding blanks or zeros) are of differing lengths, date columns using either of these components in the format rarely line up.

Following February or Sunday with a vertical bar (|) specifies that for shorter month names or weekdays, an appropriate number of blanks are substituted for the vertical bar to line up the components. Similarly, if you place a vertical bar after a single digit number in your template, Report-Writer prints a blank before each single-digit number it encounters (unless the digit is already preceded by a blank or zero).

For example, the template Sunday, | February | 3, | 1901 produces dates like:

```
Friday, January 15, 1998
Wednesday, May 4, 1998
Saturday, November 20, 1998
```

Report-Writer prints any character preceded by a backslash exactly as it appears.

Specifying Date and Time Interval Templates

Date and time interval templates show the amount of elapsed time between two dates or times, rather than an absolute date or time. Specify a time interval with a quoted string containing one of many possible representations of a sample time interval, such as 1 year or 1 yr 3 day. The selection and arrangement of the time interval elements within the template indicate the way you want time intervals to be displayed or printed. Use the following time interval as the basis for your template:

1 year 2 months 3 days 4 hours 5 minutes 6 seconds

You can use all or only some of these units in your template, and the units can be arranged in any order. Use the plural or singular form of any unit, as well as the singular or plural form of the abbreviations, yr and mo, hr, min, and sec.

To specify a time interval, use the format d'template', where template contains one or more time interval keywords (for example, minutes) preceded by the appropriate digit from the representative time interval string, as in: d'5 minutes'

This format displays results followed by the keyword; for example: 9 minutes

The following examples demonstrate the use of the time interval templates:

Format	Value	Output
D'1 year'	3 yrs 5 mos 16 days	3 years
d'2 MONTHS, 3 DAYS'	3 yrs 5 mos 1 days	41 MONTHS, 1 DAY
d'1 yr 3 day'	1 yrs 5 mos 16 days	1 yr 168 days
D'4 hours 6 seconds'	23 hrs 8 mins 53 secs	23 hours 533 seconds
d'04:05 \hours'	23 hrs 0 mins 53 secs	23:01 hours
d'3 days 4 hours'	23 hrs 8 mins 53 secs	0 days 23 hours
d' 1 yr 2 mos 3 days'	200 yrs 11 mos 28 days	200 yr 11 mos 28 days
d' 1 yr 2 mos 3 days'	5 yrs 1 mos 3 days	5 yr 1 mos 3 days

For the purpose of date interval calculation, Report-Writer assumes there are 30.4376875 days in a month and 365.2425 days in a year. The smallest unit is rounded up.

Numbers requiring more than one digit replace preceding blanks or zeroes in the template, as needed. If there are no more available preceding blanks or zeroes, the number expands to the right. Report-Writer retains in the output any single blank following a letter, word, or number in the template; it does not replace such a blank with a succeeding number. You can align columns of numbers by preceding them with an appropriate number of blanks or zeroes (as shown by the last two examples in the preceding examples of output).

For English-language releases, if the number preceding a completely spelled template word is 1, Report-Writer prints the template word in its singular form (for example, 1 year); otherwise, it prints the word in its plural form (for example, 2 years). Report-Writer makes this adjustment only if you spell out the template word completely. For example, specifying 2 month would produce appropriate singular and plural results, such as 1 month, 5 months, and 9 months. Specifying 2 mo would produce only singular results such as 1 mo, 5 mo, or 9 mo.

Report-Writer prints any character preceded by a backslash (\) exactly as it appears.

Numeric Format E

The E format prints numeric expressions in scientific notation. Numbers output in E format take the form of

[-]m.nnnnnE|e[+|-]ppp (or [-]m.nnnnnE|e[+|-]pp for VMS), where m is the mantissa, n is the number of decimal digits, and p is an exponential digit. For example, 10.456e+03 means 10.456 times 10 raised to the 3rd power. Numbers output in E format are right justified in the field, unless preceded by a .left statement or the minus sign (-) in the format designation.

The syntax of an E format specification is:

[-|*|+] ew[.d]

The E format parameters are as follows:

Parameter	Description	
w	The maximum field width.	
d	The precision or the number of digits to print after the decimal point.	

You can specify either an uppercase or lowercase e, which also determines the case of the "e" in the output. Specify the field width w, which refers to the maximum number of spaces in the field. Be sure to include spaces in the field width to account for the exponential part of the printout—that is, include five spaces for E+ppp (or four spaces for E+pp for VMS). If the value can be printed in fewer than w spaces, Report-Writer right justifies it in the field. If this width is too small to fit the value to be printed, Report-Writer fills the entire field with asterisks (*) instead.

If you specify d, Report-Writer prints a decimal point, followed by d digits to the right of the decimal point.

If you do not specify d, or if you specify a value of "0" for d (for example, E20.0), Report-Writer does not print the decimal point and rounds off any fractional digits (it does print the exponential part).

This table illustrates the E format specification. The carets (^) in the Output column are used here only to show where blanks occur in the output; they do not print in your report.

Format	Value	Output
e10.3	22.3	22.300e+00
E10.2	123	-12.30E-02
e10	123.789	^ ^1238e-01
E4.2	22.34	***
+E10.2	22.34	^22.34E+00
-e10.2	22.34	22.34e+00^

Numeric Format F

The F format causes Report-Writer to print numeric expressions in standard decimal notation, with or without a decimal point. Numbers in F format are right justified in the field, unless preceded by a .left statement or by the minus sign (-) in the format designation.

The syntax of an F format specification is:

[-|*|+] **f**w[.d]

The F format parameters are as follows:

Parameter	Description	
w	The maximum field width.	
d	The precision or the number of digits to print after the decimal point.	

The minus sign (-) and plus sign (+) characters, when used as prefixes for the format specification, specify how the entire text must appear in the field—as either right or left justified. They do not refer to the placement of the sign of the number, as is the case in some programming languages.

You can specify this format with either uppercase or lowercase letters. Specify the field width w, which refers to the maximum number of printing positions in the field. If the value can be printed in fewer than w spaces, Report-Writer right justifies it in the field. If the value cannot be printed in w or more spaces, Report-Writer fills the entire field with asterisks (*).

If you specify d, Report-Writer prints a decimal point followed by d digits to the right of the decimal point. The number of digits to the left of the decimal point is a maximum of (w - (d + 1)), because you need to account for the fractional part in the field-width specification.

If you do not specify d, or if you specify a value of "0" for d (for example, F20.0), Report-Writer does not print a decimal point and rounds off any fractional digit.

The following table illustrates the F format specification. The carets (^) in the Output column are used here only to show where blanks occur in the output; they do not print in your report.

Format	Value	Output
f10.2	22.3	22.30^^^^
F10.2	123	-0.12^^^^
f10	123.789	124^^^^^
f4.2	22.34	***
+f10.2	22.6	^^^^22.60
-f10.2	22.6	22.60^^^^

Numeric Format G

The G format uses an F format specification if there is enough room in the field, or E format if there is not enough room.

The syntax of the G format specification is:

[-|*|+] gw[.d]

The G format parameters are as follows:

Parameter	Description	
W	The maximum field width.	
d	The precision or number of digits to print after the decimal point.	

You can specify either an uppercase G or lowercase g, which determines the case of the "e" if the value is printed in scientific notation. For a full description of the meanings of w and d_i see Numeric Format E and Numeric Format F.

Report-Writer aligns data on the decimal point and then justifies the entire column right or left, according to the sign specified. By default, the column of numbers is right justified. To align F format numbers with E format numbers, Report-Writer right justifies F format numbers to a location several spaces in from the right edge of the field to account for the space taken up by the E format's exponential power designator—that is, five spaces for E+|-ppp (or four spaces for E+|-pp for VMS).

The following table of examples illustrates the G format. The carets (^) in the Output column are used here only to show where blanks occur in the output; they do not print in your report.

Format	Value	Output
g10.2	123.456	123.46^^^
G10.2	123456	^12.35E+04
g8.2	-134.65	13e+03
g8	-123	-123^^^
+g10.2	123.45	^^^123.45
-g10.2	123.45	123.45^^^

Numeric Format I

The I format prints numeric expressions in integer format. The syntax of the I format specification is:

[-|*|+] iw

The I format parameter is as follows:

Parameter	Description
W	The maximum field width.

Specifying i9 prints a number up to nine characters long in integer format, including an optional sign, and left justifies it in the column by default. Specifying a plus sign (+i9) right justifies the number in the column.

Format	Value	Output
i10	22,000	22000^^^^
I10	-120,300,000	-120300000
i4	123.789	124^
i4	22,800	***
+i8	22.4	^^^^22
-i8	22.6	23^^^^

Numeric Format N

The N format specification is identical to the G format specification except that the field is right justified, whether printed with E or F format. Of course, if you specify the optional minus sign (-) before the format designation, the value is left justified.

The syntax of the N format specification is:

[-|*|+] **n**w[.d]

The N format parameters are as follows:

Parameter	Description	
w	The maximum field width.	
d	The precision or number of spaces to print after the decimal.	

You can specify either an uppercase N or lowercase n, which determines the case of the "e" if printed in scientific notation. For a full description of the meanings of w and d, see Numeric Format E and Numeric Format F.

Numbers printed with N format are right justified in the output field. Unlike G format, the decimal points are not always aligned.

The following table of examples illustrates the N format. The carets (^) in the Output column are used here only to show where blanks occur in the output; they do not print in your report.

Format	Value	Output
n10.2	123.456	^^^123.46
N10.2	123456	^12.35E+04

Format	Value	Output
n8.2	-134.65	13e+03
n8	-123	^^^-123
+n10.2	123.79	^^^123.79
-n10.2	123.79	123.79^^^

Numeric Templates

If you need more complex numeric formats than the standard formats offer, you can specify a numeric format in a template form. Essentially, a template is an example of what the formatted output appearance. However, instead of specifying an actual sequence of digits, you use specially designated characters to indicate what must be printed at that position in the template. For instance, a Z indicates that the next digit in the number (or a space, if no digits remain) must be printed. A comma (,) in the template causes a comma to be printed in that position. So the template Z,ZZZ would cause the number 1000 to be printed as 1,000. In addition to the specially defined characters listed below, you can include any other character directly in the numeric template by preceding it with a backslash.

The general syntax of a numeric template is:

[-|*|+] '{c}'

The parameter for a numeric template is as follows:

Parameter	Description	
C	One of several special characters that can be repeated any number of times.	

The numeric template, like any number, is right justified by default. You can left justify the template by specifying the optional minus sign (-) as the first character in the template. Surround the template with single (') or double (") quotes; single quotes are recommended for consistency with requirements for quoting string constants.

Ingres evaluates the data from right to left, as it compares the number to the template. The following table describes the special characters you can use in a numeric template:

Character	Description
n or N	Prints a digit if the number contains a digit in that position. Otherwise, prints a zero. If a field is specified without n in the numeric positions and Report-Writer encounters a value of zero (0), Report-Writer enters blanks in the field.
z or Z	Prints a digit if the number contains a digit in that position. Otherwise, prints a space. This is used for standard blank-padded numeric fields.
\$	(Dollar sign) Prints a digit if the number contains a digit in that position. If no digits remain, prints a floating dollar sign immediately to the left of the last evaluated digit. Report-Writer displays a dollar sign only once in the output field. If a dollar sign has already been printed, Report-Writer prints a space in this position. This can be used to print a dollar sign directly to the left of the number, or to place a dollar sign in a fixed position in the field when used with other template characters.
-	(Minus sign—Preceding or Trailing)
	For preceding: Prints a digit if the number contains a digit in that position. If no digits remain and if the number is negative, prints a floating minus sign immediately to the left of the last evaluated digit. Report-Writer prints a minus sign only once in the output field. If a minus sign has already been printed, or if the number is positive and no digits remain, Report-Writer prints a space in this position.
	For trailing: Prints a minus sign in the position if the number is negative, or if the number is positive, prints a space.
+	(Plus sign—Preceding or Trailing)
	For preceding: Prints a digit if the number contains a digit in that position. If no digits remain, prints a floating sign (+ or -). Report-Writer prints a plus or minus sign only once in the output field. If one has already been printed, Report-Writer prints a space in this position.
	For trailing: Prints a plus sign in the position if the number is positive or a minus sign if the number is negative.
,	(Comma) Prints a comma if the number contains any digits to the left of this position. If no digits remain, prints a space.
	(Decimal point) Prints a decimal point in this position. The template can contain only one decimal point.

Character	Description
*	(Asterisk) Prints a digit if the number contains a digit in this position. If no digits remain, prints an asterisk. This is useful to fill a number on the left with asterisks (for example, for checks).
space	Prints a blank space in this position. This is identical to specifying a backslash followed by a space, and is provided for convenience only. Do not use spaces as thousands separators in place of commas and a decimal point if your template contains floating characters (+ - \$ [] () < > { }). Floating characters work correctly only when used with commas and the decimal point as separators.
\c	(Backslash) Prints in the specified position any character <i>c</i> preceded by a backslash. This allows you to insert hyphens, slashes, or other characters into the number. (The backslash is not printed.)
CR	(Two characters) Inserts the characters "CR" (for credit) if the number is negative, or two blanks if positive. The letters "CR" appear exactly as specified, in uppercase and/or lowercase letters.
DB	(Two characters) Inserts the characters "DB" (for debit) if the number is negative, or two blanks if positive. The letters "DB" appear exactly as specified, in uppercase and/or lowercase letters.
() or [] or < >	(Parentheses, brackets or angle brackets) If the number is negative, prints it within the specified symbols.

If Report-Writer encounters a value of zero, it prints blanks (spaces) in the output field, unless the template contains n in the numeric positions. Report-Writer prints a floating symbol (\$, - , or +) only once in the output field, regardless of the number of times it appears in the template.

The following examples demonstrate the use of numeric templates. The carets (^) in the Output column are used here only to show where blanks occur in the output; they do not print in your report.

Format	Value	Output
'zzzzz'	123	^^123
'zZzZz.Zz'	0	^ ^ ^ ^ ^ ^ ^ ^ ^ ^
'zzzzz.nn'	0	^^^^
'+++,+++,+++'	23456	^^^+23,456

Format	Value	Output
',NN'	23456.789	^^^^23,456.79
',ZZ '	-3142.666	^^^^-3,142.67^
'ZZZ,ZZZ,ZZZ.ZZ-'	-3142.666	^^^^^3,142.67-
'\$\$\$,\$\$\$,\$\$s.nncr'	235122.21	^^^\$235,122.21^^
'\$\$\$,\$\$\$,\$\$s.nnDb'	-235122.21	^^^\$235,122.21Db
'\$zz,zzz,zzn.nn'	1234.56	\$^^^^1,234.56
'\$**,***,***.nn'	12345	\$****12,345.00
'+\$\$,\$\$\$,\$\$\$. '	54321	^^^+\$54,321.00
' nnn\-nn\-nnnn '	023243567	^023-24-3567^
-'ZZZZZ'	123	123^^
'(zzzzz)'	-123	(^^123)
'[[[[z]'	-123	^^[123]

Control Character Format Q0

The q0 (q zero) format allows you to print a character string without the string taking up any actual space in the report. Report-Writer treats the string as if it had a length of zero. This format is designed to allow the printing of control character sequences within a report, although it can be used for other purposes. A typical use for the q0 format in a report might be to send an initialization sequence to an output device to change fonts or write bar codes.

The syntax of the q0 format is:

q0

The parameter for the q0 format is as follows:

Parameter	Description
0	This required parameter permits any string length to be printed in this format. The parameter assumes a control sequence or a non-printable string is being specified.

Any printable character or hexadecimal string can be printed with this format. You must specify non-printable characters, such as TAB, SPACE, LF, FF, CR, and ASCII NUL (X'00'), as hexadecimal strings in the format, X|x'nn{nn}'. The q0 format sends the string directly to the output device as is, without interpretation. Hexadecimal strings in .print statements without the q0 format are interpreted by the formatting routines and can produce undesirable results or cause Report-Writer to fail. For more information, see <u>Hexadecimal Strings</u>.

Important! Sending a report with a *q0* character string to a device other than the one intended can halt your output device. For example, if your report uses *q0* to highlight specific characters on your screen, your printer halts because it does not understand the initialization string.

Also, if you are sending a report with a q0 format to the screen, place positioning commands (such as .tab or .right) on a separate line from the q0 format and its string. For example:

```
.tab 14
.println $start_hilite (q0), 'This is
   hi- lighted', $end hilite (q0)
.println $start hilite (q0)
```

Placing positioning commands between the Q0 format and its string can produce incorrect positioning of the string output.

The following example initializes the printer to use a special font. The initialization sequence has been previously assigned to the variable *start_font*. After Report-Writer prints the string, the variable *end_font* resets the printer back to the original font.

```
.print $start_font (q0)
.print 'This will be printed in a different font.'
.print $end_font (q0)
```

Character String Format T

The T format is nearly identical to the C format, except that the T format translates characters outside the normal character set into visible representations. For more information, see the description of the Character String Format C.

This format is useful when you want to produce output that looks exactly like that of a terminal monitor, which expands unprintable characters into visible representations.

The syntax of a T format specification is:

```
[-|*|+] tn[.w]
```

The value for n is the width of the field that the expanded output occupies on the page. It does not refer to the number of characters of data that are translated.

Assume the data you wish to print is the character string "John?Smith,\Esq.", where the question mark (?) actually stands for a non-printing *formfeed* character. You might enter a print statement such as:

```
.print 'Output:', user_data(t0), ':Output'
.newline
```

The preceding statement would produce the following output:

```
Output: John\fSmith, \\Esq.:Output
```

The following list describes the character representation of each unprintable character translated by the T format:

- Newline becomes \n.
- Horizontal Tab becomes \t.
- Backspace becomes \b.
- Carriage Return becomes \r.
- Form Feed becomes \f.
- Backslash becomes \\.
- Null becomes \0.
- Any other unprintable character is printed as the character string \nnn, where nnn is the three-digit octal number equivalent to the character.

Expressions and Formats Syntax Summary

The following lists useful expressions and formats syntax.

Special Report Variables

current_date current_day current_time left_margin line_number page_length page_number page_width position_number right_margin w_name w_column

Arithmetic Operators

```
+, -
       plus, minus (unary)
```

** exponentiation

*,/ multiplication, division

addition, subtraction (binary) +, -

SQL Conversion Functions

```
c(expr)
char(expr)
date(expr)
dow(expr)
float4(expr)
float8(expr)
hex(expr)
int1(expr)
int2(expr)
int4(expr)
money(expr)
text(expr)
vchar(expr)
varchar(expr)
table_key(expr)
object_key(expr)
```

QUEL Conversion Functions

c(expr) char(expr) date(expr) dow(expr) float4(expr) float8(expr) **hex**(*expr*) int1(expr) int2(expr) int4(expr) money(*expr*) text(expr) vchar(expr) varchar(expr)

Numeric Functions

abs(n) atan(n) $\cos(n)$ exp(n)log(n)**mod**(*n*,*b*) sin(n)sqrt(n)

SQL and **QUEL** String Functions

charextract(c1,n) concat(c1,c2)**left**(c1,len) length(c1)locate(c1)lowercase(c1) pad(c1)right(c1, len) shift(c1,nshift) **size**(*c1*) squeeze(c1) trim(c1)uppercase(c1)

Date Functions

```
date_trunc(unit,date_)
date_part(unit,date_)
date_gmt(date)
_date(s)
interval(unit,date_interval)
_time(s)
```

Boolean Function

break (columnname)

Aggregates

```
cumulative [(breakname)] sum[u] (columnname [preset])
cumulative [(breakname)] count[u] (columnname [preset])
cumulative [(breakname)] minimum (columnname [preset])
cumulative [(breakname)] maximum (columnname [preset])
cumulative [(breakname)] average[u] (columnname) [(format)]
```

Formats

[+ * -] b w	where w is width
[+ * -]c[f j] n[.w]	where n is total string length, and w is the column width
[+ * -]ew[.d]	where w is width, d is precision
[+ * -]] f w[.d]	where w is width, d is precision
[+ * -] g w[.d]	where w is width, d is precision
[+ * -] n w[.d]	where w is width, d is precision
[+ * -] t n[.w]	where n is total string length, and w is the columnwidth
[+ * -] '{c}'	valid characters are: n or N z or Z $\ + \ '$, . * CR [] () DB \c or space
[+ * -] D d] 'templat	where <i>template</i> is a string of characters specifying the absolute date and time or specifying a time interval
q0	where 0 is a required parameter that permits any string length to be printed

Chapter 12: Report-Writer Statements

To specify a report, a text file containing report formatting and structure statements must be created. These statements define the data to be reported, the order of the data, the page layout, explanatory text to be inserted in the report, and the position and format of titles and data items.

Before developing your report specifications, you should know how you want the finished report to look. Consider some of the following issues:

- What data is needed from your database to create the report? If you need to run a database query to get the data, design the guery and run it from a terminal monitor to make sure it retrieves the desired data.
- How do you want the data sorted?
 - If you want headings or footings for subgroups of your data, the data must be sorted on the columns that define the subgroups. You must decide which sort order is to be used.
- What do you want the various headers and footers to look like?
 - Decide whether you want titles, subtotals or other aggregates, extra blank lines, or other types of headers or footers in your report. Sketch the report layout on a piece of paper to see how it looks.
- What information should be printed for each specific data row of the report, and in what format should the information appear?
 - For numbers, you should think about the number of significant digits to print, and the number of decimal places.
- What kind of page headers and footers do you want?

Format of Report Specification Statements

Specify report formatting statements with a keyword preceded by white space and a period (.), and optionally followed by parameters.

The general format of a report formatting (specification) statement is:

statement {parameters}

This table describes the parameters in a report formatting statement:

Parameter	Description
statement	One of the text formatting statements, such as .data or .tab. Specify statements in uppercase, lowercase, or mixed case letters.
parameters	Optional parameters to the statement. Parameters take many different forms, depending on the specific statements. In many cases, parameters to the statement can also be variables and expressions. To obtain the value of a variable, precede the variable with a dollar sign (\$).

Here are some examples of report formatting statements; they include a .tab, .newline, .header, .println, and a .sort statement:

The sample reports in the appendix, "Report-Writer Report Examples," demonstrate the correct specification of statements.

Statement and Parameter Delimiters

A report formatting statement must be preceded and followed with white space, either by explicitly entering spaces or tabs before and after a statement, or by using line breaks to separate the statements. White space following a statement must occur between the statement and any numeric parameter following the statement, as in:

```
.pagewidth 80
```

Lack or incorrect placement of white space statement delimiters can result in incorrect statement interpretation and could cause an error.

Statements can span any number of lines. Except where otherwise noted, commas separate multiple values for a parameter within statements, such as in the .sort or .print statements.

If a parameter is a user name, column name, or table name (including view names and synonyms), you can delimit it with double quotes (") to include spaces or other characters that are usually disallowed in these names. For more information, see <u>Delimited Identifiers</u>.

Using Schemas for Owner Qualification

A schema is a collection of database objects, such as tables. Each table, view, or synonym belongs to a schema that is determined when the object is created. The schema name corresponds to the user who owns the object. The schema name helps distinguish between objects with identical names and different owners.

In report specifications containing an SQL .query or .data statement, you can qualify a table name, view name, or synonym by specifying the schema to which it belongs (which also implies its owner), using the following construct:

schema.objectname

This allows you to access a table, view, or synonym owned by a user other than yourself or the DBA, if you have the correct permissions to access it.

A period (.) must immediately follow the schema name, although white space following the period is allowed. For example, Report-Writer allows the following construction:

schema. objectname

Both the schema name and the object name (table name, view name, or synonym) can be variables or delimited identifiers. A schema.objectname construct in which both the schema and table name are variables would take the form:

\$schema**.\$**objectname

A schema.objectname construct in which both the schema and object name are delimited identifiers would take the form:

"schema name"."object name"

A separate set of double quotes must surround each delimited identifier.

You can use the *schema.objectname* qualification within the following statements:

- .cleanup
- .data
- .declare (in the with value string)
- .query (SQL only)
- .setup

If you do not qualify the table, view, or synonym with a schema, Report-Writer searches for the specified object in the following order:

- a. Objects owned by the current user.
- b. Objects owned by the DBA to which you have been granted access.
- c. Objects in the System Catalogs

QUEL User Notes

If you are a QUEL user, you cannot use schemas or owner qualification for a table name, view name, or synonym in a report specification that contains a QUEL query. If you use the *schema.objectname* construct in reports with QUEL queries, Ingres tries to interpret the construct as a Report-Writer statement, which generates a runtime error.

Types of Report Specification Statements

There are seven types of report specification statements:

- Report Setup Statements
- Page Layout and Control Statements
- Report Structure Statements
- Column and Block Statements
- Text Positioning Statements
- Print Statements
- Conditions and Assignment Statements

The following sections provide detailed information about each type of report specification statement. The statement types are grouped by function for easier reference.

Note: For more information, see the <u>Statements Syntax Summary</u> in this chapter.

Report Setup Statements

Statements for setting up the overall report environment:

- The .break statement specifies the break columns for the report and the order in which to process occurrences of breaks.
- The .cleanup statement performs initialization tasks, (specified through query language statements) just before exiting the report.
- Comments can be placed in the text file of report specifications if preceded with /* and followed with */. Comments are ignored in report processing.
- The .data or .query statements define the data to be used by the report output.
- The .declare statement declares variables to be a given data type and allows definition of a prompt string or value string if required for that variable.
- The .delimid identifier statement allows recognition of delimited identifiers for table, view, user, and column names in report specifications.
- The .include statement specifies the inclusion of Report-Writer code residing in different files, and is executed when you run the sreport command to store the report specification.
- The .longremark and .endremarkstatements allow you to enter a large amount of descriptive text to describe the report specification. This text displays in the RBF Save window and on the Reports Catalog frame in RBF when you choose the MoreInfo operation.
- The .name statement names the report.
- The .output statement sets up an external file to receive the report output.
- The .setup/.cleanup statements perform data preparation and cleanup tasks (specified through query language statements).
 - The .setup tasks occur before processing the query, whereas .cleanup tasks occur after processing the query, but just before exiting the report.
- The .shortremark statement allows you to provide a brief description about the report. This information is included in the Reports Catalog and the Save window in RBF.
- The .sort statement defines the sort order of the data for the report.

.Break

Specifies the break columns for the report and the order in which they should break.

Syntax

.break | .brk columnname{, columnname}

In the preceding syntax, *columnname* can be expressed optionally as a delimited identifier or a variable. The comma (,) must be stated explicitly and cannot be part of a *columnname* variable.

Description

You can use the optional .break statement to specify the break columns if no .sort statement has been specified, or to override the default break columns created by the .sort statement. The order in which Report-Writer processes the break statements is the order in which they appear in the specified break list. A break on one column in the list produces a break on all subsequent columns in the list.

If a variable is specified as the column, Report-Writer evaluates the *columnname* during the loading of the report specification, before retrieving the data.

If a .sort statement is not specified, all columns that have .header or .footer statements must be included in the break list.

If you specify an order by clause in a .query statement, a .break statement that lists the columns in the order by clause must also be specified. The .query statement does *not* create default column breaks as does the .sort statement.

Note: When using a variable for *columnname*, the variable must be specified identically in corresponding .sort, .header, and .footer statements.

The parameters for the .break statement are as follows:

Parameter	Description
columnname	Name of a column in the table used as the basis for your report, or the label for a column in the result column list of the specified query. You can specify <i>columnname</i> as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
\$columnvariable	Variable whose value is a column name. The variable must be preceded with a dollar sign (\$).

Example 1

The following example breaks on the columns, state and city of employment (a delimited identifier). The order to sort the rows retrieved from the database appears in the .query statement. The .break statement is required to identify the sort columns to Report-Writer.

```
.query
     select *
       from emp
       order by state, "city of employment"
.break state, "city of employment"
```

Example 2

The following example overrides the original sort order specified in the .sort statement by using the .break statement. This might be done so that a change in the second sort column does not trigger a break on the third column. Note the consistent usage of variable names.

```
.sort
          $first col :a,
          $second col :a,
          $third_col :a
.break
          $first col, $third col
```

.Cleanup

Embeds SQL statements that do not involve data retrieval into Report-Writer sections. Report-Writer executes the statements after the main report query is processed.

Syntax

.cleanup SQL_statement; {SQL_statement;}

For a complete explanation of all available statements, see the SQL Reference Guide.

Description

Use the optional .cleanup statement to embed groups of SQL statements that perform cleanup tasks such as dropping temporary tables created in the .setup section. Report-Writer executes the .cleanup section after it substitutes Report-Writer variables into the SQL statements. For information on embedding groups of SQL statements before the report is processed, see the .Setup statement.

Use as many lines as you need to specify the .cleanup. You can also include embedded declared variables within an SQL statement in the .cleanup section. The end of .cleanup is detected by the start of a new Report-Writer statement or an end-of-file indicator.

The parameter for the .cleanup statement is as follows:

Parameter	Description
SQL_statement	One or more action SQL statements that do not involve data retrieval, separated by semicolons (;). (Note that the select statement cannot be used.)

The following rules apply to the .cleanup section:

- The .cleanup section only supports SQL statements. The language of your .query section determines the query language of the report. If you have a QUEL .query section, the query language is QUEL; otherwise it is SQL. You can have a QUEL guery and SQL .setup and .cleanup sections.
- If the report query language is SQL, the default value of autocommit is off. If it is QUEL, the default is on. To override the default commit behavior, set autocommit off or on as the first statement in your .setup section.
- Only statements that are compatible with execute immediate are permitted in a .cleanup section. For a list of compatible statements, see the SQL Reference Guide. Neither the select statement nor any statement requiring embedded semicolons (;) or colons (:), such as create procedure, are allowed. Semicolons within quoted strings are allowed. Therefore, you can specify a table for selection by using the expression:

create table tablename as select...

- Report-Writer evaluates variables in the .cleanup section only once, before running the report. Therefore, you can set the value of the variable only at report runtime, as follows:
 - On the command line in a *variablename=valuestring* clause
 - On the command line in response to a prompt
 - In the with value or with prompt clause of a .declare statement associated with the variable

While actually executing the .cleanup section, Report-Writer does not recognize any changes that have been made to .cleanup section variables while the report was being run.

- In the .cleanup section, Report-Writer evaluates variables before sending them to the Database Management System (DBMS) and evaluates SQL statements at report runtime. It generates error messages at runtime from the DBMS. If it does not detect any errors in the report or in the .cleanup and .setup sections, and if autocommit is off, Report-Writer executes an explicit commit at the close of report processing.
- Use the -d flag with the report command to run the report as if there were no errors. This flag causes DBMS errors in the .setup and .cleanup section to be ignored. The failure of the .setup statement, however, can affect data availability in the .query. For example, if you run the report on a temporary table created improperly in the .setup section, the report fails.

- When you specify the -d flag, error messages continues to display on the screen. Although it is not recommended, you can also run the report with the -s flag if you do not want error messages to display.
- If you do not use the -d flag, errors and transaction handling follow these rules:
 - If Report-Writer detects an error in the .cleanup section, the .setup section (if it exists) and the report have already run. The transaction is rolled back if autocommit is off.
 - If Report-Writer detects an error in the .setup section, neither the report nor the .cleanup section runs. The transaction is rolled back if autocommit is off.
 - If Report-Writer detects an error in the query, or if there is a fatal error in the report, neither the .cleanup section nor the report runs. The transaction is rolled back if autocommit is off.

For .cleanup examples, see <u>.Setup</u> in this chapter.

Comments

Include comments for your own documentation within a report specification saved as a text file.

Syntax

/* {any_text} */

Description

To create internal documentation for a report specification saved as a text file, you can include comments within the report specification by bracketing them between the /* and */ characters. Report-Writer ignores all text between these characters during report processing. If you save your report specification with the sreport command, Report-Writer ignores the comments and does not save them when storing your report specification in the database.

Comments can be nested; that is, you can have a set of comments within another set of comments. You can place comments anywhere within your file.

Comments can be defined as follows:

Parameter	Description
any_text	Any text, except the characters */ which close the comment.

Example 1 /* this is an example

of a comment...

Example 2 /* You can also have

/* nested comments */

in Report-Writer specifications */

.Data

Specifies the table or view in the database containing data for the report.

Svntax

.data | .dat | .table | .view [schema.]tablename|viewname|synonym

In the preceding syntax, *schema, tablename, viewname*, and *synonym* can be expressed as variables or delimited identifiers.

Description

The .data statement identifies a table or view in the database that is used in its entirety in the report. The four statement names shown in the syntax are synonymous and can be used interchangeably. Each time you run a report with the report command, all of the rows and columns in the table or view are available for use in the report specification. One exception to this is that Report-Writer silently ignores and does not print values for columns with unsupported data types such as long varchar, byte, byte varying, and long byte.

Note: If Report-Writer encounters subsequent references to a column of an unsupported data type, such as within sort operations, it issues an error message and terminates the report.

You can use a delimited identifier for *tablename* if you have previously specified the .delimid statement. For more information on delimited identifiers, see <u>Delimited Identifiers</u> and <u>.Delimid</u> in this chapter.

If you specify a variable as the table, Report-Writer evaluates *tablename* during the loading of the report specification, before retrieving the data.

An SQL language report specification includes duplicate rows in the data for reports that use the .data, .table, or .view statements. To specify distinct rows, you can specify the -6 flag on the report command line.

Either the .data or the .query statement is a required statement for each report. The .data and .query statements are mutually exclusive; both cannot appear in the same report specification.

	The parameters	for the	.data	statement	are	listed	below:
--	----------------	---------	-------	-----------	-----	--------	--------

Parameter	Description
schema	Collection of database objects to which the specified object belongs. The schema also implies the user that owns the object.
tablename viewname	Name of a table or view in the database. You can also use a synonym for <i>tablename</i> . Report-Writer reads all rows and columns in the specified table or view each time the report is run. Rules for the use of <i>tablename</i> and <i>viewname</i> are the same as in all other Ingres tools.
\$ tablevariable	Variable whose value is the name of a table, view, or synonym for a table in the database. The variable must be preceded with a dollar sign (\$).

Example 1 Use table "repdat" for the report.

.data repdat

Example 2 Use view "myview" for the report.

.table myview

Example 3 Use the value of variable *rep_table* as the table for the report.

.data \$rep_table

Example 4 For the report, use the table whose name is the delimited identifier "my

table" and whose schema is "robert."

.data robert."my table"

.Declare

Declares variables that can be assigned values and used in expressions.

Syntax .declare variablename = datatype

[with null | not null] [with prompt 'promptstring'] [with value 'valuestring'] {, variablename = datatype...}

Description

The .declare statement declares variables that can be assigned values interactively or in Report-Writer code. You can assign a value to the variable in any of the following ways:

• On the command line during runtime

- On the command line in response to a runtime prompt, which you define in the with prompt clause of a .declare statement
- In .let assignment statements placed in any .header, .footer, or .detail sections.
- In the with value clause of a .declare statement

Declared variables can also be used in a query block to specify runtime substitution of text in the query. For details, see the .Query statement in this chapter.

More than one .declare statement can be specified in a report.

The parameters for the .declare statement are listed below:

Parameter	Description
variablename	A valid variable name. In standard Ingres databases, the variable name can be up to 32 characters long and must begin with an alphabetic, or underscore (_) character. Following characters must be alphanumeric or underscore. For naming conventions in databases compliant with ANSI/ISO Entry SQL-92 standards, see ANSI/ISO Entry SQL-92 Compliant Databases.
datatype	A legal data type.
promptstring	A string constant up to 100 characters in length including quotes. The constant must be enclosed in single quotes to preserve spaces. For more information, see String Constants ."
valuestring	An initial string value for the variable up to 100 characters in length including quotes. The value must be expressed as a constant in character, numeric, or date format and must be enclosed in quotes to preserve spaces. It can contain delimited identifiers (enclosed in double quotes) or schema.objectname constructs.

Note: To reference the value of a declared variable within a report specification, the variable must be preceded with a dollar sign (\$); otherwise, the *name* of the variable is referenced. Do not use the dollar sign (\$) when referencing the name of the variable in the .declare statement or on the left side of an assignment in the .let statement. For example:

```
.declare var = c3 . . .
.let var = 'abc'
.print $var
```

The .declare statement declares each variable to be the given data type. You can specify whether a data type is nullable or not nullable by including the with null or not null option.

- If the variable is declared as nullable with the with null option, it is automatically initialized to the null value.
- If the variable is declared with the not null option, it is initialized to the default value for the data type.

If you specify neither option, the variable data type defaults to null or not null, depending on the query language (SQL or QUEL) used in the .query statement. If you specify a .data statement instead of the .guery statement, the installation default language determines default nullability.

The with prompt option instructs Report-Writer to prompt for the initial value of the variable at runtime, using the specified prompt string. The with value option instructs Report-Writer to use an initial value that you specify for the variable in the .declare statement. Using both the with prompt and with value options allows you to specify a default value if the user fails to enter a value at the prompt. This value remains unchanged by any .let statement until after the query. For more information, see the .Query and .let statements.

You can use the *schema.objectname* construct in the with value clause, as appropriate. You can also use a delimited identifier as the schema name, table name, or name of a column in the with value clause, if you have previously specified the .delimid statement.

For example, the following code fragment declares the variable, default_table, with an initial default value of a table belonging to the schema "dave" and whose name is the delimited identifier, "my table." The value string parameter for the with value clause is enclosed in single quotes.

```
.declare default table=varchar(65) with value
    'dave."my table"
.query
   select * from $default_table
```

For more information on delimited identifiers, see Delimited Identifiers in the chapter "Report-Writer Expression and Formats" and .Delimid in this chapter.

If you do not specify an initial value or prompt, and you reference the variable outside of a query block, the initial value is null (or the default value for that data type, if not null was used). When you reference a declared variable within a guery block, its initial value must be entered either in the .declare statement, on the command line, or in response to a prompt string specified in the .declare statement.

Note: Some statements (such as .query) accept variables that can be executed before the .header report statement. However, variable values cannot be assigned with the .let statement before the .header report statement. In these cases, the person running the report must specify the value of a variable as a parameter on the command line or in response to a prompt.

The with value option, used in conjunction with the .include statement, allows greater reporting flexibility. For example, you can create various include files to define date formats for various languages. Instead of entering the initial value of the date format interactively, the date formats are initialized in the .declare statement during the loading of the report specification. For more information, see Example 2 in the following section, Examples.

If both the with prompt and with value options are included in a declaration, the *promptstring* overrides the *valuestring*. No warning is issued about the override. The user is prompted with the specified *promptstring* for an initial value at runtime.

Examples

Example 1

Declare variables using with prompt, with null, and not null.

Example 2

Declare variables using with value in .include files "BR_fmts.rw" and "AM_fmts.rw," and then include the appropriate definition for that version of your report.

```
.declare date_fmt = c30 with value 'd\'03/20/01\'' or .declare date fmt = c30 with value 'd\'02/03/01\'' ^{\prime\prime}
```

The main body of the report can be written independently of the exact value of the date format; for example:

```
.print current_date ($date_fmt)
```

Example 3

Declare a variable with a value that is an schema-qualified table name.

```
.declare var1 = varchar(65) with value 'mike.table abcd'
```

Either or both the schema and table name can be delimited identifiers, if you have specified the .delimid statement. The variables have been declared with the maximum size to accommodate a compound identifier in which each part is a delimited identifier.

```
.delimid
.declare var2 = varchar(133)
        with value 'jane."table efg"'
.declare var3 = varchar(133)
        with value '"c bradley".table_hijk'
.declare var4 = varchar(133)
        with value '"r panzer". "table xyz"'
```

.Delimid

Allows recognition of delimited identifiers for table, view, column, schema, and user names.

Svntax

.delimid

Description

Specify the .delimid statement in the Report-Writer source file to enable Report-Writer to recognize delimited identifiers in your report specification code. For a detailed discussion of delimited identifiers, see the chapter "Report-Writer Expressions and Formats."

You only need to specify this statement once in the source file. However, Report-Writer accepts multiple occurrences in a report specification to support use of the statement in individual and independent .include files for which delimited identifiers must be enabled.

Note: If you use the .delimid statement in an .include file, be sure the included file actually contains code that requires this statement. Otherwise, Report-Writer can produce unexpected results.

Observe the following rules regarding placement of this statement in your report specification:

- The .delimid statement must precede any statement that allows delimited identifiers. Therefore, only the following statements can precede the .delimid statement:
 - .name
 - .shortremark
 - .longremarkendremark
 - .[no]formfeeds
 - .nullstring
 - .output
 - .ulcharacter

The .include statement cannot precede the .delimid statement because the included file can contain statements that allow delimited identifiers.

■ If your report specification contains a .query statement specifying QUEL as the query language, .<u>Delimid with QUEL Query</u> for additional information.

Example

The following example shows use of the .delimid statement in a report specification that creates a temporary table with columns "aaaa" and "delim col," then selects and prints values from column "aaaa" that match the value entered in response to a prompt for the variable "my_smallint."

```
.name sql_setup
.delimid
.declare my_smallint = smallint with prompt 'Enter
    selection key numeric value: '
.setup
    create table my_temp_table (aaaa smallint,
        "delim col" varchar(4));
    insert into my_temp_table values (123,'abcd');
.query
    select aaaa from my_temp_table where aaaa =
        '$my_smallint'
.detail
    .println 'Key Value: ',aaaa
.cleanup
    drop table my temp table;
```

.Delimid with QUEL Query

Delimited identifiers cannot be used in a QUEL query. However, you can use delimited identifiers and the .delimid statement in non-query portions of a report specification that contains a QUEL query, as shown in the following example.

QUEL Example

This example creates a temporary table with columns "aaaa" and "delim col," then retrieves and prints values from column "aaaa" that match the value entered in response to a prompt for the variable "my_smallint."

```
.name sql_setup
.delimid
.declare my_smallint = smallint with prompt 'Enter
        selection key numeric value:
.setup
        create table my_temp_table (aaaa smallint,
             "delim col" varchar(4));
        insert into my temp table values (123, 'abcd');
.query
        range of mtt is my_temp_table
        retrieve (mtt.aaaa, quote = "\"")
where mtt.aaaa = "$my_smallint"
.detail
        .println 'Key Value: ',aaaa
.cleanup
        drop table my temp table;
        create table my_temp_table (aaaa smallint,
             "delim col" varchar(4));
        insert into my_temp_table values (123, 'abcd');
        drop table my_temp_table;
```

.Include

Imports Report-Writer code residing in more than one file when the report is saved.

Syntax

.include filename

Description

Use the optional .include statement to specify one or more files containing Report-Writer code to be imported into the command text file. By using this statement, you can avoid retyping commonly used constructs that you need in more than one of your reports. You can nest .include statements within an .include statement.

Because Report-Writer constructs do not have to appear in any particular order, the .include statement can appear anywhere within Report-Writer code. However, the .name statement must still be the first statement in your specification.

Report-Writer incorporates the contents of the file specified in an .include statement each time you execute the sreport command to save your report specification. This means that when you update included files, the report specifications that include those files must be saved again using sreport to incorporate the changes. As Report-Writer executes sreport, it displays a message notifying you of each file that is included in your specification. This message can help diagnose report errors if any should occur.

The parameter for the .include statement is as follows:

Parameter	Description
filename	The name of a text file containing a Report-Writer construct to be included in a report. If necessary, specify the full path name for the file. If you do not explicitly specify an extension for the file, the system assumes ".rw" as the default extension.

VMS

If you give the full path name for a file, enclose the name in single quotes. If it is the name of a file in the current directory, no quotes are needed.

The following rules apply to the .include section:

The .include statements cannot contain variables. This is because variables are only available at runtime and Report-Writer only executes .include statements when you save the report specification with the sreport command (rather than when the report is executed with the report command).

- An included file can contain more than one statement. However, a single Report-Writer statement must be contained completely within one file. You cannot use .include statements in the middle of another Report-Writer statement.
- Within an .include file, you can have nested .include statements.
- The maximum number of nested .include statements permitted is based on the number of open files allowed in your system.
- A corresponding .if -.then-.else[if] -.endif statement must all be contained in the same .include file, but statements following the condition can be other .include statements.

Example 1 Include a file in current directory.

.include otherrep.rw

Example 2 Include a file name with full path name.

Windows

include \direct\subdirect\otherrep.rw

UNIX

.include /direct/subdirect/otherrep.rw

VMS

.include '[direct.subdirect]otherrep.rw'

.Longremark/.Endremark

Begins and ends a multi-line block of text that describes the report.

Syntax .longremark | .lrem

remark text

.endremark | .endrem

Description The .longremark and .endremark statements are an optional pair that specify

> a lengthy description of the report. Indicate the start of the block of descriptive text with the .longremark statement and denote the end of the block with the .endremark statement. This long description appears in the

Save frame and MoreInfo display of the Catalog frame in RBF.

The long remark differs from a Report-Writer comment (/* comment text */). Report-Writer stores the descriptive text in the .longremark statement in the database when you save the report with the sreport command, so that it is thereafter available to other Ingres application development tools. By contrast, you can only save Report-Writer comments in the text file. The sreport command ignores comments of this type and does not save them in the database.

There can be only one .longremark statement in a report specification. Should you attempt to enter two .longremark statements in one report specification, the second is flagged with a syntax error. You can enter as much remark text as you like. However, only the first 600 characters of remark text is saved in the DBMS and appear in the RBF windows; the rest is ignored. Report-Writer ignores leading spaces that separate the .longremark statement from the first character of the remark text. Tab characters convert to blank characters.

The parameter for the .longremark statement is as follows:

Parameter	Description
remark-text	Any number of characters or lines of text.

Examples

.longremark

Example 1

This report correlates information from the sales order header, the sales order detail, and the inventory files, to produce the customer backlog by part number report.

.endremark

.1rem

Example 2

Stock Analysis Report 8 1/2" x 11" output 10 minutes runtime Input: Begin/End date .endrem

.Name

Names reports.

Syntax

.name | .nam reportname

Description

The .name statement is required and must be the first statement specified for a report. The program sreport stores the report in the database under the report name rather than the file name of the file containing the report specification statements.

Specifications for several reports can be stored in one text file by using several name statements. Each occurrence of a name statement signals the end of the previous report's specification statements and the beginning of a new report. You can then save the reports in the database by using sreport.

When executing a report directly by using the -i flag with the report command, you must have exactly one .name statement specifying one report only. The .name statement cannot appear in a file specified by an .include statement.

The parameter for the .name statement is as follows:

Parameter	Description
reportname	The name of a report to which the next set of formatting statements apply. The <i>reportname</i> is a standard object, with a maximum length of 32 characters for a standard Ingres database, or 18 characters for ANSI/ISO Entry SQL-92 compliant databases.

Examples

Example 1 Denote the start of the report, abc:

.name abc

Example 2 Denote the start of report, my_rep:

.name my_rep

.Output

Specifies the file name where the report is written.

Syntax .output | .out filename

In the preceding syntax, *filename* can be expressed as a variable.

DescriptionThe .output statement is an optional statement that specifies the name of a file where the report is written.

If you specify a variable for *filename* Report-Wr

If you specify a variable for *filename*, Report-Writer evaluates the variable during the loading of the report specification, before retrieving the data.

If you don't use the .output statement in your report specification, Report-Writer either directs the output to the screen, or to a file name specified on the command line for the report command with the -f flag. The -f flag takes precedence over the .output statement. If both the -f flag and the .output statement are present, the report results are sent to the file specified by the -f flag, rather than of the .output statement. If the .output statement is not specified, and no file is specified with the -f flag, the report appears on your screen.

The parameters for the .output statement are as follows:

Parameter	Description
filename	A file to which the formatted report is written each time the report is run. The <i>filename</i> parameter must follow all conventions for valid file names in the operating system.
\$filevariable	Variable whose value is the file name. The variable is preceded by a dollar sign (\$).

VMS

If you give the full path name for a file, enclose the name in single quotes. If it is the name of a file in the current directory, no quotes are needed.

Examples

Example 1 Write to file in current directory.

.output myreport.lis

Example 2 Write to file with full path name.

Windows

.out \direct\subdirect\myreport.lis ■

UNIX

.out /direct/subdirect/myreport.lis ■

VMS

.out '[direct.subdirect]myreport.lis'

.Query

Specifies an SQL or QUEL query to be used to generate data for a report. The statement syntax and description provided here apply to SQL only. If you are using the QUEL language, see .Query for QUEL Users for the correct syntax, parameters, and description of this statement.

Syntax

For a complete explanation of the syntax and parameters for the SQL select statement within the Report-Writer .query statement, see the *SQL Reference Guide*.

Description

The .query statement indicates the start of a valid SQL query that creates the data to be reported. This query follows the same rules as any other SQL select statement, although it can also contain variables. You can use as many lines as you need to specify the query. The end of the query is indicated by the start of a new report formatting statement.

Specify either the .query or the .data statement (but not both) for every report. Only one .query statement is permitted for a report, and only one data retrieval statement is permitted within the .query statement. Both a .query with an order by clause and a .sort statement cannot be in the same report specification.

You can use the optional select <code>column_list</code> as <code>resultcolumn_list</code> construct to reference a column in subsequent statements by a name other than its database table column name. For example, if you selected A_column as B_column, thereafter you need to refer to B_column in all statements referencing that column. This construct is useful for printing the value of a column that is specified as a runtime variable. When Report-Writer encounters a .print statement that directly references a runtime variable for a column name (for example, .print \$account_type), it prints the <code>name</code> of the column as entered at runtime, rather than its <code>data</code>. To print the data rather than the column name, you use the select <code>column_list</code> as <code>resultcolumn_list</code> construct in the query and reference the <code>resultcolumn_list</code> name in the .print statement. For example:

The Examples section contains a complete example of this usage.

Because the .query statement generates a standard query, the standard limits apply to any report's query. For Ingres databases, these limits are 1024 columns and 2008 bytes per row. These limits are extended for some Enterprise Access products. For details, see your Enterprise Access product guide.

If any column you specify with select * is of an unsupported data type, such as long varchar, byte, byte varying, and long byte, Report-Writer silently ignores and does not print any values for that column. If you explicitly specify a column with an unsupported data type in the column list of a select statement in a query, Report-Writer additionally issues a warning message. If it encounters any subsequent reference to a column with an unsupported data type, regardless of the method used to select the column, Report-Writer issues an error message and terminates the report.

You can specify the table, view, or synonym as schema.objectname. You can also use delimited identifiers for table, column, or schema names if you have previously specified the .delimid statement. This includes use of delimited identifiers as either or both the correlation name and the column name in a correlationname.identifier as resultcolumn construct. For more information on delimited identifiers, see Delimited Identifiers in the chapter "Report-Writer Expressions and Formats" and .Delimid in this chapter.

To avoid any potential confusion with delimited identifiers, which are double-quoted, enclose string constants with the standard SQL string delimiter, the single quote (').

Variables

For standard Ingres databases, variable names:

- Can be up to 32 characters long. Valid characters are letters, digits, and underscore (_).
- Must begin with a letter.
- Cannot match any of the words in the reserved words list. For more information, see Reserved Words in the chapter "Report-Writer Expressions and Formats."

For variable naming conventions in databases that comply with ANSI/ISO Entry SQL-92 standards, see ANSI/ISO Entry SQL-92 Compliant Databases.

You can use variables as runtime substitutes for any part of a query (that is, as a field name, table name, or even in where clauses). You indicate variables in a query by preceding the name with a dollar sign (\$). For example, you can specify a query as follows:

```
.query
   select empname, salary, manager
     from emp
     where salary>$minsal
```

Subsequently, you can invoke the report with a statement such as:

```
report mydb myrep (minsal = 20000)
```

If the parenthetical clause contains characters that are treated specially by your operating system (such as parentheses in Windows NT), enclose it in double quotes:

```
report mydb myrep "(minsal = 20000)"
```

Report-Writer converts the query to:

```
... where salary>20000
```

You can also assign an initial value for the variable using the with value option in the .declare statement. Report-Writer initializes the variable with your assigned value during the loading of the report specification.

If the value of a variable is not assigned on the command line or during the loading of the report specification, Report-Writer prompts you for the value, using the custom string specified in the with prompt option in the variable declaration. If you did not specify a custom string prompt, Report-Writer uses a default prompt.

You are *strongly* encouraged to define all variables with the .declare statement. Although Report-Writer recognizes any name preceded by a dollar sign (\$) as a variable, undeclared variables assume default types and characteristics that are often incompatible with their intended use.

By defining variables with .declare, there is no limit to the ways you can use the variable in your report. You can assign a value to an undeclared variable only by using a command line parameter or by entering a value in response to a runtime prompt. A value for an undeclared variable cannot be specified with a .let statement. In addition, unless the variable has been declared, attempting to pass a parameter with a null value to Report-Writer can produce incorrect results.

Specify as many variables as you want in a query by defining a unique name for each variable. If the same variable is to be substituted more than once within the query, specify the name, prefixed by a dollar sign (\$), at each place where substitution is to be done.

Variables can be specified anywhere in the query, or example, within the column list for a select statement or as a value to which the contents of a column is compared. For example, the following query phrases are legal:

```
... select $var, ... from emp ...
... where name = '$employee_name' ..
```

If the variable is a character string used for comparison purposes in a where clause, enclose the variable within quotes that are appropriate for your query language (single quotes for SQL), as shown in the preceding example. If you omit these quotes in the query, the user must be made aware of the need to include them in the string value for the variable at runtime.

If you actually want to include the dollar sign (\$) as a literal part of the query, precede it with a backslash (\). For example:

```
... where symbol = '\$' ...
```

You can also use variables specified in the .query statement in the body of the report. Report-Writer prints the value of the variable if the variable name is preceded by a dollar sign (\$). For more information, see the Population **Example** in the appendix "Report-Writer Report Examples."

Examples

Example 1

You set up the query as:

```
.query
    select *
          from emp
          where salary > $sal
          and dept = '$dept'
```

You invoke the command:

```
report mydb myrep (sal = 50000, dept = 'toy')
```

Enclose toy within single quotes to identify it to Report-Writer as a string. Report-Writer strips off these quotes before passing it to the query.

Note: If your operating system requires it, enclose the parenthetical clause within double quotes:

```
report mydb myrep "(sal = 50000, dept = 'toy')"
```

Report-Writer executes the following query:

```
select *
```

```
from emp
where salary > 50000
and dept = 'toy'
```

Example 2

Consider a table called account owned by davis with columns including customer number, customer name, checking, and savings. You have separate fields for checking and savings accounts on one row, because most customers have both a savings and a checking account with the bank.

If you want to write one report specification that prints either the savings or checking account balances with a single query, you could code a .query statement similar to the following, using the select *column_list* as *resultcolumn_list* construct:

The column names and table name in the preceding code must be double-quoted, according to standard rules for specifying delimited identifiers.

You can invoke the preceding query with the command:

```
report otherdb repname
```

At execution, Report-Writer issues the following prompt and, in this example, the user enters the column name, savings:

```
Please enter the type of account: savings
```

The following query would be executed, which selects values from the savings column and assigns them to the result column name, val:

```
select "customer number", "customer name", savings as val
    from davis."bank account"
```

To print the value of the column, savings, refer to the result column name, val:

```
.println val
```

.Query for QUEL Users

This statement specifies a QUEL query to be used to generate data for a report.

Syntax

```
.query|.quer
{range_statement(s)}
retrieve [unique] (target_list) [where qual]
  [sort by | order by...] sort-list
```

Description

The .query statement indicates the start of a valid QUEL query that creates the data to be reported. All range statements needed to designate the row markers for the query must be specified. This query follows the same rules as any other QUEL query, although it can also contain parameters. You can use as many lines as you need to specify the query—sreport detects the end of the query by the start of a new report formatter statement.

Either the .guery or the .data statement (but not both) must be specified for every report. Because the .query statement generates a standard Ingres query, the usual limits of 1024 columns and a maximum row width of 2008 bytes apply to any query issued through the Report-Writer.

If any column you specify with retrieve all is of an unsupported data type, such as long varchar, byte, byte varying, and long byte, Report-Writer silently ignores and does not print any values for that column. If you explicitly specify a column with an unsupported data type in the column_list of a retrieve statement in a guery, Report-Writer additionally issues a warning message. If it encounters any subsequent reference to a column with an unsupported data type, regardless of the method used to select the column, Report-Writer issues an error message and terminates the report.

You can use the optional retrieve (resultcolumn=table.columname) construct to reference a column in subsequent statements by a name other than its database table column name. For example, if you retrieved B_column=table1.A_column, in subsequent statements refer to the column as B_column.

Only one .query statement is permitted for a report, and only one data retrieval statement is permitted within the .query statement.

You cannot have both a .query with an order by or sort by clause and a .sort statement in the same report specification, because their functions are mutually exclusive.

Neither delimited identifiers nor the schema.objectname construct are allowed in QUEL queries.

String constants must be enclosed by the standard QUEL string delimiter, the double quote ("). The double quote string delimiter is required only within the .query statement; within other Report-Writer statements, the string delimiter is the single quote.

Variable names:

- Can be up to 32 characters long. Letters of the alphabet, digits, and the underscore (_) are valid characters.
- Must begin with a letter of the alphabet.
- Cannot match any of the reserved words listed in Reserved Words in the chapter "Report-Writer Expressions and Formats."

The parameters for the QUEL .query statement are listed below:

Parameter	Description
range_statement(s)	Valid QUEL range statements used to identify the tables used in the query.
target_list	A valid QUEL target list that creates data for the report. The retrieve into form of the retrieve statement is not used.
qual	A valid QUEL qualification to a query.
sort_list	A valid set of sort columns according to the rules for constructing QUEL retrieve statements. Note that you cannot use both a .sort statement and a sort by or order by clause in the same report specification.

Variables in the Query

You can use variables as runtime substitutes for any part of a query (that is, field names, table names, or even where clauses). You indicate variables in a query by preceding the name with a dollar sign (\$). For example, you can specify a query as follows:

```
.query
    range of e is emp
    retrieve (e.empname,e.salary,e.manager)
    where e.salary > $minsal
```

Subsequently, you can invoke the report with something like the following: report mydb myrep (minsal = 20000)

If the parenthetical clause contains characters that are treated specially by your operating system (such as parentheses in Windows NT and UNIX or slashes in VMS), enclose it in double quotes:

```
report mydb myrep "(minsal = 20000)"
```

Report-Writer converts the query to:

```
... where e.salary > 20000
```

You can also assign an initial value for the variable using the with value option in the .declare statement. Report-Writer initializes the variable with your assigned value during the loading of the report specification.

If the value of a variable is not assigned on the command line or during the loading of the report specification, Report-Writer prompts you for the value, using the custom string specified in the with prompt option in the variable declaration. If you did not specify a custom string prompt, Report-Writer uses a default prompt.

We strongly encourage you to define all variables with the .declare statement. Although Report-Writer recognizes any name preceded by a dollar sign (\$) as a variable, undeclared variables assume default types and characteristics that are often incompatible with their intended use. By defining variables with .declare, there is no limit to the ways you can use the variable in your report. You can assign a value to an undeclared variable only by using a command line parameter or by entering a value in response to a runtime prompt. You cannot specify a value for an undeclared variable with a .let statement. Also, unless the variable has been declared, attempting to pass a parameter with a null value to Report-Writer can produce incorrect results.

You can specify as many variables as needed in a query by defining a unique name for each variable. If the same variable is to be substituted more than once within the query, specify the name, prefixed by a dollar sign (\$), at each place where substitution is to be done.

You can specify variables anywhere in the query—for example, within the column list for a retrieve statement or as a value to which the contents of a column is compared. For example, the following query phrases are legal:

```
... where e.name = "$employee name" ...
... retrieve (e.$var, ...) ...
```

When the variable is a character string used for comparison purposes in a where clause, enclose the variable within quotes that are appropriate for your query language (double quotes for QUEL), as shown in the preceding example.

If you actually want to include the dollar sign (\$) as a literal part of the query, precede it with a backslash (\). For example:

```
... where e.symbol = "\$" ...
```

You can also use variables specified in the .query statement in the body of the report. Report-Writer prints the value of the variable if the variable name is preceded by a dollar sign (\$). For more information, see the Population **Example** in the appendix "Report-Writer Report Examples."

Examples

Example 1

You set up the query as:

```
.query
           range of e is emp
           retrieve (e.all)
                     where e.salary > $sal
and e.dept = "$dept"
```

You invoke the command:

```
report mydb myrep (sal = 50000, dept = 'toy')
```

Enclose toy within single quotes to identify it to Report-Writer as a string. Report-Writer strips off these quotes before passing it to the query.

Note: If your operating system requires it, enclose the parenthetical clause within double quotes:

```
report mydb myrep "(sal = 50000, dept = 'toy')"
```

Report-Writer executes the following query:

Example 2

Consider a table called, account, with columns including custno, custname, checking, and savings. You have separate fields for checking and savings accounts on one row, because most customers have both a savings and a checking account with the bank. To write one report specification that prints either the savings or checking account balances with a single query, you can code a .query statement similar to the following:

```
.declare account_type = c10 with prompt
    "Please enter the type of account:"
.quel
    range of a is account
    retrieve(a.custno, a.custname, val=a.$account_type)
```

You can invoke the query with the command:

report otherdb repname

At execution, Report-Writer issues the following prompt:

Please enter the type of account:

Suppose you respond with:

savings

The following query would be executed:

```
range of a is account
retrieve(a.custno, a.custname, val=a.savings)
```

To print the value of the savings column, use:

```
.println val
```

This query selects values from the database savings column, not the string constant, savings.

.Setup

Embeds SQL statements that do not involve data retrieval into Report-Writer sections. Report-Writer executes the statements *before* it processes the main report query.

Syntax

.setup SQL_statement; {SQL_statement;}

For a complete explanation of all available SQL statements, see the SQL Reference Guide.

Description

Use the optional .setup statement to embed groups of SQL statements to perform tasks such as creating and qualifying temporary tables for use in the report and setting up lock modes. Report-Writer executes the .setup statement after substituting variables into the SQL statements. You can use as many lines as you need to specify the .setup. You can also include embedded declared variables within an SQL statement. The end of .setup is indicated by the start of a new Report-Writer statement. For information on embedding groups of SQL statements after the report is processed, see the .Cleanup statement.

If you are running reports with an Ingres database and you are not updating the data in your report, we recommend that you set up your report to be read only. To do this, provide the following statement in the .setup section:

set lockmode session where readlock=nolock;

Note: Keep in mind that when you set the lockmode to be read only, other users can still update the table used to produce the report. In this case, your report can not always match actual database values. If it is critical to keep the table consistent throughout the printing of the report, lock the table. For details on using lockmodes, see the Database Administrator Guide.

The parameter for the .setup statement is listed below:

Parameter	Description
SQL_statement	One or more action SQL statements that do not involve data retrieval, separated by semicolons (;). (Note that the select statement cannot be used.)

The following rules apply to the .setup section:

- The .setup section only supports SQL statements. The language of your .query section determines the query language of the report. If you have a QUEL .guery section, the guery language is QUEL; otherwise it is SQL. It is acceptable to have a QUEL guery and SQL .setup and .cleanup sections.
- If the report query language is SQL, the default value of autocommit is off. If it is QUEL, the default is on. To override the default commit behavior, simply set autocommit off or on as the first statement in your .setup section.

- Only statements that are compatible with execute immediate are permitted in a .setup section. For a list of compatible statements, see the SQL Reference Guide. Neither the select statement nor any statement requiring embedded semicolons (;) or colons (:), such as create procedure, are allowed. Semicolons within quoted strings are allowed. Therefore, you can specify a table for selection by using the expression:
 - create table tablename as select...
- In the .setup section, Report-Writer evaluates variables only once, before running the report. Therefore, you can set the value of the variable only at report initiation time as follows:
 - On the command line in a variablename=valuestring clause
 - On the command line in response to a prompt
 - In the with value or with prompt clause of a .declare statement associated with the variable
- In the .setup section, Report-Writer evaluates variables before sending them to the Database Management System (DBMS) and evaluates SQL statements at report runtime. It generates error messages at runtime from the DBMS. If it has detected no errors in the report or in the .cleanup and .setup sections and autocommit is off, Report-Writer executes an explicit commit at the close of report processing.
- Use the -d flag with the report command to run the report as if there were no errors. This flag causes Report-Writer to ignore DBMS errors in the .setup and .cleanup sections. The failure of the.setup statement, however, can affect data availability in the .query. For example, if you run the report on a temporary table created improperly in the .setup section, the report fails.
- If you specify the -d flag, error messages continue to display on the screen. Although it is not recommended, you can run the report with the -s flag if you do not want error messages to display.
- If you do not use the -d flag, errors and transaction handling follow these rules:
 - If there is an error in the .setup section, neither the report nor the .cleanup section runs. The transaction is rolled back if autocommit is
 - If there is an error in the .cleanup section, the .setup section (if it existed) and the report have already run. The transaction is rolled back if autocommit is off.
 - If there is an error in the query or a fatal error in the report, neither the .cleanup section nor the report runs. The transaction is rolled back if autocommit is off.

```
.NAME books2
.OUTPUT books2.out
. LONGREMARK
     The BOOKS2 report demonstrates using setup
     and cleanup to produce temporary tables.
. ENDREMARK
. SETUP
     set lockmode session where readlock=nolock;
     create view tempbooks as
        select b.id, b.title, a.name, '' as subject,
           1 as code
             from book b, author a
             where b.id = a.id
        union
        select b.id, b.title, '' as name, s.subject,
             2 as code
            from book b, subject s
            where b.id = s.id;
     create table subj_count as
         select id, count(subject) as num_sub
             from tempbooks
            where code = 2
             group by id;
     create table auth_count as
          select id, count(name) as num_auths
             from tempbooks
            where code = 1
            group by id;
.CLEANUP
   drop tempbooks;
   drop subj count;
   drop auth count;
.QUERY
   select b.id, b.title, b.name, b.subject, b.code,
          a.num_auths, s.num_sub
          from tempbooks b, subj_count s, auth_count a
         where b.id = a.id and b.id = s.id
```

.Shortremark

Specifies a one-line remark describing the report.

Syntax

.shortremark | .srem remark_text

Description

The .shortremark statement is an optional statement that specifies a one-line description of the report. You can use this short description to help document your report specifications, but its primary purpose is to provide information that appears on the Catalog and Save frames of RBF.

There can only be one .shortremark statement in a program. The second .shortremark statement is flagged with a syntax error. Only the first 60 characters of the descriptive text are stored in the database. All characters past 60 are ignored.

The parameter for the .shortremark statement is listed below:

Parameter	Description
remark_text	A string of characters on the same line as the statement keyword.

.shortremark Monthly Accounts Receivables

Example 1

.srem customized emp & dept report tables

Example 2

.Sort

Specifies the ordering of rows to be reported.

Syntax

.sort | .srt {columnname[:sortorder] {, columnname[:sortorder]}}

In the preceding syntax, *columnname* and *sortorder* can be expressed as a variable. The colon (:) and the comma (,) must be explicitly stated and cannot be part of the *sortorder* variable.

Description

The optional .sort statement specifies the ordering that applies to the rows of data to be reported. Report-Writer initially sorts rows on the first column in the list. If several rows have the same value in the first sort column, Report-Writer then sorts them on the second column in the list, and so forth. If there is exactly one sort column, and there are duplicate values for the sort column, all rows with that value appears together, but in an undetermined order relative to each other.

By default, the .sort statement also specifies the columns used as break columns in the report. You can specify break headers and footers for each column, using the .header and .footer statements. A break on one column in the sort list produces a break on all subsequent columns in the sort list.

If you want, you can use the .sort statement to order rows for appearance in the report only, without specifying these columns as break columns. To override the default break specifications in the .sort statement, specify break columns in a .break statement.

An SQL language report specification includes duplicate rows in the data for reports that use the .sort statements. To specify distinct rows, you can specify the -6 flag on the report command line.

If you specify variables as the *columnname* and/or *sortorder* parameters, Report-Writer evaluates these variables during the loading of the report specification, before retrieving the data.

You can have either a .sort statement or an order by clause in a .query statement but not both in a report specification.

Note: When using a variable for *columnname*, specify the same variable identically in corresponding .break, .header, and .footer statements.

The parameters for the .sort statement are listed below:

Parameter	Description
columnname	The name of a column in the table to be reported, or the label for a column in the result column list of the specified query. You can express <i>columnname</i> as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
sortorder	Either ascending (also a or asc or ascend) or descending (also d or desc or descend), depending on how you want the rows to be ordered. If neither is specified, the default is ascending.
\$columnvariable	The variable whose value is the name of a column. Precede the variable with a dollar sign (\$).
\$sortorder	The variable whose value is a sort order that evaluates to an acceptable sort direction. For more information, see the description of <i>sortorder</i> in this table. Precede the variable with a dollar sign (\$).

Examples

Example 1

Sort two columns of a table (whose names are specified by delimited identifiers), with both columns in ascending order:

.sort "last name", "first name"

Example 2

Sort three columns of a table, with first and last columns in descending order, and the second column in ascending order.

.sort dept:descending, jobcode, name:d

Sort the column specified by the value of the variable *sort_col* in the order specified by the value of the variable *sort_order*. For example, the value of *sort_col* might be last_name and the value of *sort_order* might be for ascending.

```
.sort $sort_col:$sort_order
...
.header $sort_col
...
.out \direct\subdirect\myreport.lis
.include \direct\subdirect\otherrep.rw
```

Page Layout and Control Statements

You can specify the layout of report pages with the following statements:

- The .formfeeds statement instructs Report-Writer to insert formfeed characters to force a page break at the start of the report and at the end of each page.
- The .leftmargin statement sets up a left margin as the default start of all new lines and for use with the .left and the .center statements.
 - If the left margin is not explicitly specified, Report-Writer determines this default automatically from an analysis of the other report formatting statements. For details, see <u>Automatic Determination of Default Settings</u> in the chapter "Using Report-Writer."
- The .need statement tests for a given number of lines on a page to see if a page break is appropriate.
- The .newpage statement skips to a new page, and optionally sets a page number.
- The .noformfeeds statement suppresses the addition of formfeed characters to the end of pages in the report.
- The .pagelength statement defines the page length, in lines.
- The .pagewidth statement defines the page width, in characters.
- The .rightmargin statement sets the right margin of the report for use with the .right and the .center statements.
- If the right margin is not explicitly specified, Report-Writer determines this default automatically from an analysis of the other report formatting statements, For details, see Automatic Determination of Default Settings in the chapter "Using Report-Writer."

.Formfeeds/.Noformfeeds

Force or suppress the addition of formfeed characters to the end of each page written in the report.

Syntax .formfeeds | .ffs | .ff

.noformfeeds | .noffs | .noff

There are no parameters to either statement.

Description

For printers that support formfeeds, it is often most convenient to use the ASCII formfeed character to support pagination. You can use the .formfeeds and .noformfeeds statements to override the default setting for formfeeds, which is determined by the operating system.

The default for formfeeds is:

Windows

.formfeeds 🍱

UNIX

.formfeeds 🍱

VMS

.noformfeeds 🍱

You specify the .formfeeds or .noformfeeds statement at the start of your report specification statements, before any .header or .footer statements.

Specify .formfeeds to override a .noformfeeds default. This forces Report-Writer to send formfeed characters at the start of the report and at the end of each page in the report. You can suppress the initial formfeed by specifying the .nofirstff statement in your report specification or by including the -nofirstff flag when using the report command. For more information, see .Nofirstff and Report.

If the report contains page footer formatting statements, Report-Writer sends the formfeed character after the page footer. Otherwise, Report-Writer sends the formfeed character after the last line of the page, as determined from the default or specified page size. For details on specifying page size, see the .Pagelength statement. When writing to a screen, Report-Writer ignores the .formfeeds statement.

Specify .noformfeeds to override a .formfeeds default and suppress formfeeds.

You can override these statements and the formfeed defaults at runtime by specifying the -b|+b flag on the report command line.

Example 1 To turn on formfeeds and override a .noformfeeds default, specify:

.formfeeds

Example 2 To turn off formfeeds and override a **.formfeeds** default, specify:

.noformfeeds

.Leftmargin

Sets a left margin for the report.

Syntax

.leftmargin | .lm [[+|-] n | expression]

In the preceding syntax, *expression* evaluates to a numeric value that is the position of the left margin for the report. The optional plus sign (+) or minus sign (-) must be stated explicitly and cannot be a part of the *expression*.

Description

The .leftmargin statement sets the left margin of the report to a specific position or a position that is the value of a numeric expression. Subsequently, when new lines are written, new text output begins at the left margin position. To set the left margin for the entire report, place the statement in the .header report section. The .leftmargin value is also used by the .left and .center statements to determine the default position for those statements.

Report-Writer evaluates any expressions used as parameters to the .leftmargin statement during runtime.

Note: If you do not specify a left margin position, Report-Writer determines the default value for the left margin from your other specifications for the writing of the report, as discussed in Automatic Determination of Default Settings.

The value specified for the .leftmargin statement must be greater than or equal to zero (0), less than the specification for the right margin and less than the page width (as specified with the -I flag on the report command, or with the .pagewidth statement).

The parameters for the .leftmargin statement are listed below:

Parameter	Description
+ -	If sign is present, the new position is calculated relative to the current position. If no sign is present, it is set to the absolute position.
n	The position of the new left margin of the report. The default value is discussed in <u>Automatic Determination of Default Settings</u> .

Parameter	Description
expression	A numeric expression that evaluates to the position of the new leftmargin of the report. All variables that are part of the expression must be preceded by a dollar sign (\$).

Example 1 Have new lines begin at position 5 (the sixth character position).

.lm 5

Example 2 Move the left margin to the right by the number of characters specified by

the value of the variable width.

.lm +\$width

Example 3 Set the left margin to be the sum of the value of variable width and 3.

.lm \$width+3

.Need

Ensures that a specified number of text lines is printed together on the same page.

Syntax

.need | .ne nlines| expression

In the preceding syntax, expression evaluates to a numeric value that is the total number of lines in the text block to remain together.

Description

The .need statement allows you to ensure that groups of text lines are not broken across pages of the report. Report-Writer performs conditional page breaks, to keep the specified or variable-specified lengths of text blocks together. You can use this statement to make sure that Report-Writer keeps all lines of text in the headers, and such, on the same page. For examples of placing the .need statement, see the appendix "Report-Writer Report Examples."

Report-Writer evaluates any expressions used as parameters to the .need statement during runtime.

The parameters for the .need statement are as follows:

Parameter	Description
nlines	The number of lines in the text block to remain together.
expression	A numeric expression that evaluates to the total number of lines in the text block to remain together. Precede all

Parameter	Description
	variables that are part of the expression by a dollar sign (\$).

Example 1

Make sure that the break header is on the same page.

```
.need 3
.print 'Header for account:',acct
.newline
.print '-----'
.newline 2
```

Example 2

In this example, the report ensures the label information can be printed on varying sized label forms. The value of *label_size* is the number of lines per label. The printing of the company name is dependent on a record meeting the criteria of the condition.

```
.need $label_size
.if company != '' .then
    .println company
    .let address_lines = 4
.else
    .let address_lines = 3
.endif
.println name
.println address
.println city, state, zip
.newline $label_size - $address_line.
```

.Newpage

Initiates an immediate page break, with an optional change in the page number.

Syntax

```
.newpage | .np [[+|-] pagenumber | expression]
```

In the preceding syntax, *expression* evaluates to a numeric value that is the *pagenumber* to be assigned as the next page in the report. The plus sign (+) or minus sign (-) must be stated explicitly and cannot be a part of the expression.

Description

You can place the .newpage statement at any point in your report specification. Report-Writer performs an immediate page break by skipping enough lines to get to the end of the page, then prints the page footer, sets the new page number, and writes a page header at the top of the new page. Report-Writer determines the new page number by incrementing the old page number, or by setting, incrementing, or decrementing the old page number to the specified value. If pagenumber is not specified, Report-Writer determines the default page number by incrementing the current page number by one.

At the end of the report, Report-Writer performs a .newpage statement automatically, if a page footer is specified (in this case, no page header appears on the next page). Also, if Report-Writer encounters a .newpage statement as the first printing action of the report, it does not print a page footer for that page.

Report-Writer evaluates any expressions used as parameters to the .newpage statement during runtime.

The parameters for the .newpage statement are listed below:

Parameter	Description
+ -	If a sign is present, the new position is calculated relative to the current position. If no sign is present, it is set to the specified value.
pagenumber	The page number to be assigned to the next page in the report.
expression	A numeric expression that evaluates to the page number to be assigned as the next page in the report. All variables that are part of the expression must be preceded by a dollar sign (\$).

Examples

Example 1 Skip to a new page, incrementing the current page number by 1.

.newpage

Example 2 Reset the page number to 22.

.newpage 22

Example 3 Reset the page number to the current page plus the value of skip_page.

.newpage +\$skip_page

.Nofirstff

Suppresses the initial formfeed prior to the start of the report when formfeeds are enabled.

Syntax

.nofirstff

There are no parameters for this statement.

Description

When ASCII formfeeds have been enabled by default, by the .formfeeds statement, or by the +b flag for the report command, Report-Writer generates an initial formfeed in addition to one at the end of each page of the report. The initial formfeed is useful for printers with continuous-form paper. To avoid generating this blank page at the beginning of your report, you can use the .nofirstff statement in your report specification to suppress the initial form feed.

You need only specify this statement once in your report source file, preferably immediately after any .formfeed statement and prior to all statements that generate printed text (such as .print, .println, .newline, and .newpage). This statement should not appear in any .detail, .footer, or .header section other than .header report.

If specified in an .include file, its placement in the file must follow the same placement rules as in the report specification source file.

You can omit this statement and use the -nofirstff flag on the report command line at runtime instead. You can also override the .nofirstff statement at report runtime by specifying the -firstff flag. For more information, see the description of the Report command.

Example

To suppress the initial formfeed when formfeeds have been explicitly enabled:

- .formfeeds
- .nofirstff

.Pagelength

Sets a new default page length in number of lines per page.

Syntax

.pagelength | .pl {nlines | expression}

In the preceding syntax, *expression* evaluates to a numeric value that is the page length for the report.

Description

The .pagelength statement controls where page breaks occur. The report formatter subtracts the number of lines in the footer (specified in the .footer page section of the specifications) from the total page length of *nlines*. Page length is the total number of body text lines for the page.

During the running of the report, Report-Writer checks to see if the total count of body text lines has been written to the current page. If not, no action is taken. If so, Report-Writer writes a page footer and header, and the report continues. If the .formfeeds statement or formfeed default is in effect, Report-Writer performs a formfeed at the end of each page footer.

The value used in the .pagelength statement should be greater than the combined number of lines specified in the heading and footing for the page.

You can override the pagelength statement at runtime by specifying the -vpagelength flag on the report command line. If both the -v flag and the .pagelength statement are present, the -v flag overrides the .pagelength value.

Report-Writer evaluates any expression used as a parameter to the .pagelength statement during runtime.

The parameters for the .pagelength statement are as follows:

Parameter	Description
nlines	The number of lines per page. The default is 61 lines per page if the report is written to a file, or the length of your screen if the report is written to the screen. To suppress all pagination (eliminate all page breaks), specify pagelength as zero (0).
expression	A numeric expression that evaluates to the new page length of the report. Precede all variables that are part of the expression with a dollar sign (\$).

Examples

Example 1 Set a new page length for screens with 24 lines.

.pl 24

Example 2 Set the page length to be the value of variable page size.

.pl \$page_size

Example 3 Suppress report pagination.

.pl 0

.Pagewidth

Sets a new default page width in number of characters or positions per line.

Syntax

.pagewidth | .pw width

In the preceding syntax, width can be expressed as a variable.

Description

The .pagewidth statement controls where line breaks occur. With the .pagewidth statement, you specify total number of characters specified per line through a constant or variable.

If you specify a variable for *width*, Report-Writer evaluates the variable during the loading of the report specification, before retrieving any data.

The value used in the .pagewidth statement must be greater than or equal to the width determined from the .leftmargin and .rightmargin values. The .rightmargin value must be greater than the .leftmargin value. If you are using a .position statement in your specification, its value must be less than the value of .pagewidth.

While running the report, Report-Writer checks to see if the total count of characters goes beyond the .pagewidth value. If so, an error message appears on the screen, or if possible, the report executes within the assigned width.

You can override this statement at runtime by specifying the -I flag on the report command line. Otherwise, the report reflects the .pagewidth setting. If there is no .pagewidth statement and the -I flag is not specified, Report-Writer uses 132 as the default width, and tries to execute the report within that width. If this is not possible, an error message appears on the screen.

All reports created and saved through RBF automatically generate a page width comment that RBF uses to set the page width when you run the report. Delete the page width comment from an archived RBF report specification and add an explicit .pagewidth statement instead. If you fail to delete the page width comment when specifying the page width explicitly, Report-Writer can truncate the text.

The parameters for the .pagewidth statement are listed below:

Parameter	Description
width	The number of characters per line (<i>n</i> characters). The default is 132 characters per line if the report is written to a file, and the width of your screen if the report is written to the screen.
\$ widthvariable	Variable whose value is the report page width (n characters). Precede the variable with a dollar sign (\$).

Example 1 Set a new page width for a printer.

.pw 132

Example 2 Set page width for a screen where the width is the value of variable

term_width.

.pw \$term_width

.Rightmargin

Sets a right margin for the report.

Syntax

.rightmargin | .rm [[+|-] n | expression]

In the preceding syntax, expression evaluates to a numeric value that is the position of the right margin for the report. The plus sign (+) or minus sign (-) must be stated explicitly and cannot be a part of the expression.

Description

The .rightmargin statement sets the right margin of the report to a specific position or a position that is the value of a numeric expression. To set the right margin for the entire report, place the statement in the .header report section. The .rightmargin value is used by the .right and .center statements to determine the default position for those statements. If text would ordinarily go beyond the right margin, it is wrapped around to the start of the next line.

Report-Writer evaluates any expressions used as parameters to the .rightmargin statement during runtime.

If you do not specify a value, Report-Writer determines the default value for the right margin by the printing statements in the report, as discussed in Automatic Determination of Default Settings. The value specified for the rightmargin statement must be greater than the specification for the left. margin and less than the page width (as set by the -I flag on the report command).

The parameters for the .rightmargin statement are listed below:

Parameter	Description
+ -	If sign is present, the new position is calculated relative to the current position. If no sign is present, it is set to the absolute position n .

Parameter	Description
n	The position of the new right margin of the report. If signed, the new position is calculated relative to the current position. If unsigned, it is set to absolute position n .
expression	A numeric expression that evaluates to the position of the new rightmargin of the report. All variables that are part of the expression must be preceded by a dollar sign (\$).

Example 1 Specify margins such that the default position used by .center is 50.

```
.leftmargin 10
```

.center

.print 'This title is centered on column 50'

Example 2

Move the right margin left by the number of characters specified by the value of the variable *width*.

.rm \$width

Example 3

Set the right margin to be the sum of the value of variable width and 3.

.rm \$width+3

.noformfeeds

Report Structure Statements

These statements are used in setting up the structure of the report:

- The .detail statement designates a group of formatting statements for each data row in the report.
- The .footer statement designates a group of formatting statements for the report footer, for the page, for one of the break or sort columns.
- The .header statement designates a group of formatting statements for the heading of the report, for the page, or for one of the break or sort columns.

.Detail

Specifies the start of action to be taken when each data row is processed.

Syntax .detail | .det

The .detail statement has no parameters.

[.]rightmargin 90

Description

The .detail statement signifies the start of a group of report formatting statements that Report-Writer executes each time it processes a data row for the report. Report-Writer executes these formatting statements after any break headers that can be caused by the data row, but before any break footers.

Report-Writer also uses the formatting statements specified in the .detail block as the basis for determining the default margins of the report and the default positions of columns. For more information, see Automatic Determination of Default Settings in the chapter "Using Report-Writer."

```
.print acctnum(b16), tdate(b16),
.tab +8
.print transnum ('nnnn'), deposit, withdrawal
.print cum(acctnum), sum(amt.balance)
.newline
```

.Footer

Identifies the start of a block of formatting statements that are executed at the end of a break.

Syntax

```
.footer | .footing | .foot
        report | page | columnname
```

In the preceding syntax, columnname can be expressed as a variable.

Description

The .footer statement starts the block of text formatting statements that define the action to be taken at the end of a break in the report. The following table shows the results obtained by specifying each of the options in the .footer statement:

Option	Result
report	Prints the footer at the end of the report.
page	Prints the footer at the bottom of each page.
columnname (or a variable as the column)	Prints the footer at the end of a group of data rows with identical values for that break column.

If you specify a variable for columnname, Report-Writer evaluates the variable during the loading of the report specification, before retrieving any data.

Report-Writer considers all statements between one .footer statement and any subsequent .header, .footer, or .detail statement to be part of the first footer action.

Note: When using a variable for *columnname*, specify the same variable identically in corresponding .break, .sort, and .header statements.

The parameters for the .footer statement are listed below:

Parameter	Description
columnname	A break column name specified in the list of the .sort or .break statement. Specify the column name as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
\$columnvariable	Variable whose value is the name of a column. Precede the variable with a dollar sign (\$).

Examples

Example 1

Specify printing a page number at the bottom of each page

```
.footer page
    .newline
    .center
    .print '-,' page_number (f2), '-'
    .newline
```

Example 2

Print the sum of column named "wholesale cost" (a delimited identifier), at the end of the report

.Header

Identifies the start of a block of formatting statements to be executed at the top of a break.

Syntax

```
.header | .heading | .head
    report | page | columnname
```

In the preceding syntax, *columnname* can be expressed as a variable.

Description

The .header statement starts the block of text formatting statements that define the action to be taken at the start of a break in the report. The following table shows the results obtained by specifying each of the options in the .header statement:

Option	Result
report	Prints the header before the start of the report.
page	Prints the header at the top of all pages except the first page.
columnname (or a variable as the column)	Prints the header before a new value of a break column.

If you specify a variable for columnname, Report-Writer evaluates the variable during the loading of the report specification, before retrieving any data.

When you create a report header, put the .header report statement and the formatting statements associated with it before any other .header statements. Report-Writer considers all statements between one .header statement and any subsequent .header, .footer, or .detail statement as part of the first header action.

Note: When using a variable for *columnname*, specify the same variable identically in corresponding .break, .sort, and .footer statements.

The parameters for the .header statement are listed below:

Parameter	Description
columnname	A break column name specified in the .sort or .break statements. Specify the column name as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
\$columnvariable	Variable whose value is a name of a column specified in a .sort or .break statement. Precede the variable must with a dollar sign (\$).

Examples

Example 1 Specify a page header.

```
.header page
          .print 'Accounts Receivable Aging
Report by Client'
          .newline
```

Specify a report header that prints the current date, the current time and the name of the report at the start of the report.

Example 3

Specify a break header for the column "last name."

```
.delimid
.query
    select "last name", "first name"
        from names_tbl
.sort "last name"
.header "last name"
    .newpage
```

Column and Block Statements

You can use column and block statements to set up an explicit print position, column width, and format for the values contained in the named database column or for a report *block* (as defined by a .block statement).

Use the .position and .width statements to assign the starting print position and column width for a column or block, which are used in conjunction with text positioning statements such as .tab and .right justification. For more information, see Text-Positioning Statements. If you do not explicitly specify column print positions, column widths, and column formats with these statements, then Report-Writer assigns defaults automatically from an analysis of the other report formatting statements. For more information, see Automatic Determination of Default Settings in the chapter "Using Report-Writer."

Use the following column and block statements:

The .block and .endblock statements allow you to treat sections of the report as blocks.

This allows you to refer to positions on previous as well as on subsequent lines in the report. These statements can be used in conjunction with the .top and .bottom statements to align blocks of data horizontally adjacent to each other rather than in vertical sequence.

- The .bottom statement, used while in block mode, moves the current position to the bottom line of the current block.
- The .format statement explicitly specifies a print format (such as character string or standard decimal notation) for a column.
- The .position statement sets up an explicit starting print position for a column, which can be used with the .tab, .right, .left or .center statements.
- The .tformat statement temporarily changes the print format for a column, only for the next value to be printed.
 - This statement is used for such functions as printing a value of a column on the first line of a page or of a group only, or including a currency symbol only on the first printing of a column value.
- The .top statement, used while in block mode, moves the current position to the top line of the current block.
- The .width statement sets up an explicit width for a column, to be used with the .right or .center statements.
- The .within and .endwithin statements allow you temporarily to set the report margins to the confines of a specific column, using its position and width.

.Block/.Endblock

Sets Report-Writer into and out of block mode, which allows you to refer to positions on previous as well as subsequent lines in the report.

Syntax

.block | .blk other formatting statements

.endblock | .endblk | .end block

There are no parameters to either statement.

Description

The .block and .endblock statements switch Report-Writer into and out of block mode, allowing you to use advanced capabilities of Report-Writer in formatting complex reports. While in block mode, you can move not only across the page (through the .tab statement) and down the page (through the .newline statement), but also back up the page (through the .top statement).

Block mode gives you the capability of logically printing information in your report, and then putting summary information ahead of the detailed information. Do this by switching Report-Writer into block mode, printing out some number of lines, moving to the top of the block to add summary information, and then printing out the entire block by leaving block mode.

By using this statement in conjunction with the .within and .endwithin statements, described later in this chapter, you can describe column headings and subtotaling in a more natural and convenient fashion than is possible if you had to describe each line completely before going to the next line.

All formatting statements are allowed within block mode, except for the newpage and .need statements. Additionally, you can use the .top and .bottom statements only while in block mode to move the current position within the block.

Report-Writer permits a default maximum of 310 explicit .newline statements within any one block, as protection against misspecified columns. You can override this default by setting the -wmxwrap parameter in the report command.

Examples

Example 1

Assume the following sequence of Report-Writer statements:

```
.block
.print 'Line 1' .newline
.print 'Line 2' .newline
.top
.tab 10 .pr 'more line 1' .newline
.endblock
```

You would get the following output:

```
Line 1 more line 1 Line 2
```

Example 2

Assume the following sequence of Report-Writer statements:

```
.sort region, state
.header region
      .need 4
      .block
          .print 'Region: ', region .nl
.detail
     .tab 5
      .print state(c15)
     .tab 30
     .print tot_18to65('n,nnn,nnn')
      .newline
.footer region
      .top
      .lineend
      .tab + 5
      .print 'Count of states: '
      .println count(state) (f3)
.end block
```

You would get the following output:

```
Region: East South Central Count of states: 4
Alabama
                            2,528,938
Kentucky
                            2,971,232
Mississippi
                            1,393,283
Tennessee
                            3,283,432
Region: Mountain
                            Count of states: 8
                            1,604,948
Arizona
Colorado
                            2,112,352
Idaho
                            0,698,802
Montana
                            0,663,043
Nevada
                            0,448,177
New Mexico
                            0,915,815
Utah
                            1,031,926
Wyoming
                            0,323,024
```

.Bottom

Changes the current output line to the bottom line in the current block.

Syntax .bottom | .bot

There are no parameters to this statement.

Description

You can use the .bottom statement only while block mode is in effect (that is, after a .block statement, but before the corresponding .endblock statement). It moves the current output line to the current bottom line in the block. The character position on that line is one space beyond the last character printed on that line.

Example

Assume the following sequence of Report-Writer statements:

```
.print 'Line 1' .newline .print 'Line 2' .newline
    .top
    .tab + 2 .pr 'more line 1' .newline
    .bottom .lineend
    .print 'Last line in block' .newline
.endblock
```

You would get the following output:

```
Line 1 more line 1
Line 2 Last line in block
```

.Format

Sets up a default printing format for a column or set of columns.

Syntax

```
.format | .fmt columnname{, columnname} (format)
       {, columnname{, columnname} (format)}
```

In the preceding syntax, *columnname* and *format* can be expressed as variables. The comma (,) and the parentheses () must be stated explicitly and cannot be part of the *columnname* or *format* variable.

Description

The .format statement sets up a default format associated with a column to be used whenever Report-Writer prints the column or an aggregation of a column.

If you specify variables for the column and/or format, Report-Writer evaluates *columnvariable* and *formatvariable* during the loading of the report specification, before retrieving any report data.

Because the format for a column can determine the default width for that column (used in the .center, .right, and .left statements), you can use the .format statement to control the default width of a column. Report-Writer uses this statement to determine the default width *only in the absence* of the .width or .position statements, which also specify the default width for a column. You can use .tformat to override the format of a column during the run of the report.

If you do not specify a .format statement for a column, Report-Writer determines the print format by scanning the printing statements in the report. For more information about this process, see Specifying Report Specifications in the chapter "Using Report-Writer." If the printing statements do not specify a format, Report-Writer determines the default format as described in Automatic Determination of Default Settings of the chapter "Using Report-Writer."

By default, breaks use the formatted values for any column whose format has been specified in a .format statement. That is, a break occurs for such a column only when the formatted value changes. Otherwise, no break occurs, even if the unformatted value changes. To force Report-Writer to use the actual, rather than the formatted, values to determine breaks, specify the -t flag on the report command line. For more information, see the chapter "Using System Commands for the Forms-based Tools."

The parameters for the .format statement are listed below:

Parameter	Description
columnname	The name of a column in the report. You can specify the column name as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
format	A valid printing format, as described in <u>Format</u> <u>Specifications</u> . The format must be the correct type for the column(s).

Parameter	Description
\$columnvariable	Variable whose value is a name of a column. Precede the variable with a dollar sign (\$).
\$formatvariable	The variable whose value is a name of a printing format described in <u>Format Specifications</u> . The format must evaluate to the correct type for the column(s). Precede the variable with a dollar sign (\$).

Example 1

This example shows a .format statement that declares formats for several columns, followed by a .print statement that uses the formats specified in the .format statement to print the information.

```
.format trans, balance ('$$$,$$$,$$$.nn')
.print trans, balance
.newline
```

Example 2

This example shows a .format statement that declares formats for date columns where date_fmt evaluates to a date format and column names are delimited identifiers.

```
.format "trans date", "cur date" ($date_fmt)
```

.Position

Sets a default output position and optional width associated with a column.

Syntax

```
.position | .pos columnname { , columnname} (position [,width])
       {, columnname{, columnname} (position [, width])}
```

In the preceding syntax, columnname, position, and width can be expressed as variables. The comma (,) and parentheses () must be explicitly stated and cannot be part of the columnname, position, or width variable.

Description

The .position statement sets a default position in the output line associated with a column name for use with statements such as:

```
.right
.center
```

You can also use this statement to set an optional default width (the total number of characters in a column) when calculating positions in the .center and .right statements.

If you specify a variable for columnname, position, and/or width, Report-Writer evaluates the variable during the loading of the report specification, before retrieving any report data.

[.]tab

Normally, you do not need this statement because Report-Writer determines default positions and widths by analyzing the report formatting statements. For a full description of how Report-Writer determines the default settings, see Automatic Determination of Default Settings in the chapter "Using Report-Writer." If the determined default position for a column is not convenient, or you would like a different position associated with a *columnname*, you can override the default with the .position statement. Subsequently, you can use the .tab, .right, .left, or .center statements with a *columnname* to refer to this position.

If you do not specify a .position statement for a column, and *columnname* is not printed in the report, the default position is zero (0). If you specify a position, but no width is specified or evaluated for a column, Report-Writer determines the default width by looking at the default format for the column. You can optionally use the .width statement to specify the width of a column.

The parameters for the .position statement are as follows:

Parameter	Description
columnname	Name of a column in the report. You can specify the column name as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
position	Numeric location on the output line where the default column position should be. This value must be less than the maximum line size (as set by the .pagewidth statement in the report specification or by the -I flag on the report command line) and greater than or equal to zero (0).
width	The default width which is the total number of characters in the column to be used when calculating the positioning for .center and .right statements. If not specified, Report-Writer determines this numeric by looking at the default format for the column.
\$columnvariable	Variable whose value is the name for a column in the report. Precede the variable with a dollar sign (\$).
\$positionvariable	Variable whose value is the numeric location on the output line where the default column position should be. This variable must evaluate to a position less than the maximum line size (as set by the .pagewidth statement in the report specification or by the -I flag on the report command line) and greater than or equal to zero (0).
\$widthvariable	Variable whose value is the default width, which is the total number of characters in the column to be used when calculating the positioning for .center and .right

Parameter	Description
	statements. If not specified or evaluated, Report-Writer determines this value by looking at the default format for this column.

Example 1

The following example sets up default positions for columns, and prints out the data. The column "acct num" is a delimited identifier.

```
.position "acct num"(5), transact(20), balance(35)
   .format transact, balance ('$,$$$,$$$.nn')
.format "acct num"('nn-nnnnn-n')
   .tab acct .print acct
.tab transact .print transact % \frac{1}{2}\left( \frac{1}{2}\right) =\frac{1}{2}\left( \frac{1}{2}\right) +\frac{1}{2}\left( \frac{1}{2}
.tab balance .print balance
.newline
```

This results in a printout like this:

```
01-02234-4
               $1,345.24
                             $11,429.32
02-41989-1
                 $876.24
                             $10.553.08
```

Example 2

To vary the column positions and widths, use variables:

```
.position "acct num"($acct_pos, $acct_width),
    transact ($transact_pos, $transact_width),
    balance ($balance_pos, $balance_width)
```

.Tforma

Changes the format temporarily for the output of a column.

Syntax

```
.tformat | .tfmt columnname{, columnname} (format)
       {, columnname{, columnname} (format)}
```

In the preceding syntax, columnname and format can be expressed as variables. The comma (,) and the parentheses () must be stated explicitly and cannot be part of the *columnname* or *format* variables.

Description

The .tformat statement temporarily changes the format used to print out the value of a column. After Report-Writer prints the column using this format, the effect of the temporary format is discarded, and when Report-Writer prints the next value in the column, it uses the default format.

For example, reports often include columns containing currency data. If you want to print a leading dollar sign for the currency figure only the first time it appears on a page, you could use the .tformat statement to specify a format of \$\$\$,\$\$\$,\$\$n.nn for the column in the header action for page breaks. If the normal format for printing the column is zzz,zzz,zzn.nn, then Report-Writer prints the column with a leading dollar sign only the first time it is printed on each page.

Another common use of the .tformat statement is for blanking out the unchanged values of break columns in the detail action for a report. You use the B type format (described in the Blanking Format B section of the chapter "Report-Writer Expressions and Formats") to accomplish this. Specifying a B format, with an appropriate field width as the standard format for printing a column in the detail section, causes Report-Writer to print blanks instead of the value of that column as the default action.

To ensure that Report-Writer prints each *new* value in the column, specify a printing format in a .tformat statement in the break header for that column. Refer to the use of the .tformat statement for the date column in <u>Account Example</u> or the examples in this section.

If you specify a variable for *columnname*, *position*, and/or *width*, Report-Writer evaluates the variable during the loading of the report specification, before retrieving any report data.

The parameters for the .tformat statement are as follows:

Parameter	Description
columnname	The name of a column in the report. You can specify the column name as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
format	A valid printing format, as described in <u>Format</u> <u>Specifications</u> . The format must be the correct type for the column(s).
\$columnvariable	Variable whose value is a name of a column in the report. Precede the variable with a dollar sign (\$).
\$formatvariable	Variable whose value is a name of a printing format described in <u>Format Specifications</u> . The format must evaluate to the correct type for the column(s). Precede the variable with a dollar sign (\$).

Examples

Example 1

Print out the value of a break column only when it changes. The acct num column is a delimited identifier.

```
** In the detail section, blank out the
\ensuremath{^{**}} account number. When the account number
** changes, print it.
.header report
         .format "acct num"(b10),
          transact('$$$,$$$,$$$.nn')
.heading "acct num"
        .tformat "acct num"(c10)
.detail
         .print "acct num"
         .tab +2
         .print transact
         .newline
```

This is the sample report output for the above specification:

```
01-34567-8
                 $345.21
                  $14.10
                $1,143.23
04-35999-2
                   $1.99
                 $177.00
```

Example 2

Print dollar sign at top of page only. The variable thous_dollar evaluates to '\$\$\$,\$\$n' and thous evaluates to 'ZZZ,ZZn':

```
.declare thous dollar = c8 with value '\'$$$,$$n\''
            thous_dollar = c8 with value '\'zzz,zzn\''
.header page
            .print 'Top of page' .nl 2,
            .tformat salary($thous_dollar)
.detail
            .print name(c14), salary($thous)
             . . .
```

This is the sample report output for the above specification:

```
Top of page
Jones, A.
           $23,145
Jones, B.
             16,145
Jost, C.
             32,143
```

.Top

Changes the current output line to the top line in the current block.

Syntax

.top | .tp

There are no parameters to this statement.

Description

You can use the .top statement only while block mode is in effect (that is, after a .block statement, but before the corresponding .endblock statement). It moves the current output line to the first (topmost) line in the block.

The character position on the topmost line is the same as its previous position on the line when the last .newline statement affected the topmost line. To get to the left margin of the top line, use the .tab statement with no parameters. To get to the last nonblank character on the line, use the .lineend statement.

Example

Assume the following sequence of Report-Writer statements:

You would get the following output:

```
Line 1 more line 1
Line 2
```

.Width

Sets a default output width associated with a column.

Syntax

```
.width | .wid columnname{, columnname} (width)
{, columnname} (, columnname) (width)}
```

In the preceding syntax, *columnname* and *width* can be expressed as variables. The comma (,) and parentheses () must be explicitly stated and cannot be part of the *columnname* or *width* variable.

Description

The .width sets the default width, which is the total number of characters in a column when calculating positions in the .center and .right statements. Alternatively, you can specify the default width for a column as a parameter to the .position statement. If you specify variables for *columnname* and *width*, Report-Writer evaluates the variables during the loading of the report specification, before retrieving any report data.

Normally, you do not need the .width statement because Report-Writer determines default widths by analyzing the report formatting statements. For a full description of how Report-Writer determines the defaults, see <u>Automatic Determination of Default Settings</u> in the chapter "Using Report-Writer."

If the determined default width for a column is not convenient, or you would like a different width associated with a *columnname*, you can override the default with the .width statement. Subsequently, you can use the .right or .center statements with a *columnname* to use this width, in conjunction with the default position for this column, in calculating the placement of text.

If no width is specified for a column, Report-Writer determines the default width by looking at the default format for the column. The parameters for the .width statement are listed below:

Parameter	Description
columnname	The name of a column in the report. You can specify the column name as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
width	The width which is the total number of characters in the column to be used when calculating the positioning for the .center and .right statements. If not specified, Report-Writer determines this numeric by looking at the default format for the column.
\$columnvariable	Variable whose value is the name for a column in the report. Precede the variable with a dollar sign (\$).
\$widthvariable	Variable whose value is the default width, which is the total number of characters in the column to be used when calculating the positioning for .center and .right statements. If not specified or evaluated, Report-Writer determines this value is determined by looking at the default format for this column.

Example

To print the following columns of salaries, set up desired position, formats and widths:

```
Old Salary
New Salary
  $50,000.00 | $45,000.00
   $32,000.00 | $28,800.00
 | $35,000.00 | $31,500.00 |
      $100.00 |
                     $90.00 |
   $35,000.00 | $31,500.00
 | $25,000.00 | $22,500.00
 | $5,000.00 | $4,500.00 |
.declare salary_fmt = c14 with value '''$$$,$$$.nn'''
.declare salary_wid = integer with value '12'
.header report
    .position sal1(0), sal2(13)
    .format sal1, sal2 ($salary_fmt)
    .width sal1, sal2 ($salary_wid),
    .underline
    .center sal1 .print 'New Salary'
.center sal2 .print 'Old Salary'
    .newline
    .nounderline
.detail
    .left sal1 .print '|'
.right sal1 .print sal1
.print '|'
    .right sal2 .print sal2
    .print ' |'
    .newline
```

.Within/.Endwithin

Sets Report-Writer into (and out of) column formatting mode.

Syntax

In the preceding syntax, *columnname* or all can be expressed as a variable. The comma (,) must be stated explicitly and cannot be part of *columnname* variable.

Description

The .within and .endwithin statements switch Report-Writer into and out of column formatting mode. In column formatting mode, Report-Writer temporarily sets the margins of the report to the left and right margins for a given column, determined either by default (as described in Automatic Determination of Default Settings) or through the use of the .position, .width, and .format statements.

If you specify a variable as *columnname*, Report-Writer evaluates the variable during the loading of the report specification, before retrieving data.

Report-Writer processes all statements between the .within and the corresponding .endwithin statement using the margins for the specified column, rather than the margins for the report. If more than one column is specified or evaluated on the .within statement, or if the keyword all is used, Report-Writer applies the set of statements to each of the columns in turn.

These are the parameters for the .within and .endwithin statements:

Parameter	Description
columnname	The name of a column in the report within which other formatting statements are to be used. You can specify the column name as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
all	Indicates that all columns in the report are to be used.
\$columnvariable	Variable whose value is a column name or all. Precede the variable with a dollar sign (\$).

When using the .within and .endwithin block of statements for a set of columns, you can invoke a slightly different set of formatting statements within each column, differing only in the column referenced by a formatting statement. To accomplish this, two special names are available for use in formatting statements while in column formatting mode. You can use them to refer to the column that is currently being used.

Parameter	Description
w_column	Can be used anywhere <i>columnname</i> would normally be used on a formatting statement, such as in .print w_column or .print sum(w_column).
w_name	Refers to the name of the column currently being used in the within block. You can use it to print out the actual column names.

When used in a .within block, these special names can also be values of variables where appropriate. For instance, the value of the variable colname is w_name in the following example:

.tab \$colname

In another example, the value of the variable *colval* is w_column: sum(\$col)

For examples of the use of these special names, see the examples in this section or the appendix "Report-Writer Report Examples."

Because Report-Writer temporarily changes the margins of the report to the margins for a column while the .within statement is in effect, the positions referred to by the default values for the .left, .right, and .center statements are those of the column, rather than the full width of the report.

If the text you want to print spans more than one line per column in the .within section—that is, the text has more than one .newline command—then surround the .within section with the .block and .endblock statements. Report-Writer automatically executes a .top statement immediately before the .endwithin statement to simplify this type of specification.

Once you start to use the .within and .endwithin statements, you can find that the .position, .width, and .format statements take on additional usefulness.

Examples

Example 1

Assume the following sequence of Report-Writer statements, where two of the column names are delimited identifiers:

Report-Writer prints the names of the three columns similar to this:

```
last name first name address
```

Example 2

In the following example, the .within statements allow Report-Writer to print each column of the report in a similar format.

In the report header and footer section, a .block statement allows the centered titles and sums to use more than one line. In the detail section, only one line is used so a .block statement is not necessary. In the detail and the footer section for the report, the special name w_column is used.

```
Total
Population
                        18 to 65
11,113,976
                       9,600,381
  5,193,669
                       4,820,324
                       7,833,474
9,646,997
  8,875,083
 10,652,017
    712,567
                         698,802
    694,409
                         663,043
 19,953,134
                      17,761,032
    [detail omitted]
203,165,702
                     177,612,309
```

The following report example was used to create the two columns:

```
.name withinex
.query select tot_18to65 + tot_under18 + tot_over65
  as totpot, tot_18to65
  from pop
.header report
   .position totpot (2,15), tot 18to65(20,15)
   .format totpop, tot_18to65 ('zzz,nnn,nnn')
       .within totpop
           .right .println 'Total'
           .underline
           .right .println 'Population'
           .nounderline
       .endwithin
       .within tot_18to65
           .newline
           .underline
           .right
           .println '18 to 65'
           .nounderline
       .endwithin
   .endblock
.detail
       .within totpop, tot_18to65
           .right . println w_column
       .endwithin
.footer report
   .block
       .within totpop, tot\_18to65
          .right . println '----'
.right . print sum(w_column)
       .endwithin
   .endblock
```

Text Positioning Statements

You can use text positioning statements to specify a print position—absolute or relative to other positions—for any text to be printed. Most of these statements also accept as a value the name of a column for which a print position or column width has been set with the .position or .width statements. For a description, see Column and Block Statements.

Use the following text positioning statements:

- The .center statement centers text around the center of the page or around a specified alternate position.
 - It can be used with the name of a column to center the text within the specified or default margins for that column.
- The .left statement left justifies text to the left margin or to a specified position.

It can be used with the name of a column to left justify text within the specified or default margins for that column.

- The .lineend statement tabs to the end of the text on the current line before continuing to print.
- The .linestart statement tabs to the left margin before continuing to print.
- The .newline statement prints out the current line and skips to the start of a new line.
- The .right statement right justifies text to the right margin or to a specified position.
 - It can be used with the name of a column to right justify text within the specified of default margins for that column.
- The .tab statement tabs to an exact or relative position before continuing printing.

It can be used with the name of a column to tab to the specified or default print position for that column.

.Center

Centers the next text to be printed.

Syntax

.center | .cen | .ce [[+|-] n | columnname | expression]

In the preceding syntax, *expression* evaluates to the next print position where the text is right justified on a line or to the name of a column in the report. The plus sign (+) and minus sign (-) must be explicitly stated and cannot be part of the expression.

Description

The .center statement centers the text printed in the next .print statement. Report-Writer removes all leading and trailing blanks from the text before it places it in the output line.

Report-Writer evaluates any expressions that are used as parameters to the .center statement during runtime.

The parameters for the .center statement are listed below:

Parameter	Description
+ -	If sign is present, the position is moved <i>n</i> positions relative to the last output position. If unsigned, the position is the absolute position in the output line.
n	The position around which the next block of text is centered. The default value is the halfway point between the left and right margins of the report.

Parameter	Description
columnname	The name of a column in the report. You can specify the column name as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.
columnname (continued)	Report-Writer determines the position for the column either explicitly through the use of the .position statement, or implicitly as described in <u>Automatic Determination of Default Settings</u> in the chapter "Using Report-Writer." Report-Writer positions the text in the next .print statement around the center for the column. For more information, see the discussion following this table.
expression	A numeric or string expression. If the expression is numeric, it must evaluate to the position around which the next block of text is centered. If the expression is a string, it must evaluate to the name of a column in the report. Precede all variables that are part of the expression with a dollar sign (\$).

If you specify *n* (either relative or absolute), Report-Writer centers the text around that position. If you specify nothing, Report-Writer calculates the center of the page as the halfway point between the left and right margins of the report. If you specify .leftmargin and .rightmargin statements, you can calculate the center by the same method. However, if you are using the default values for the right and left margins (the right in particular), see Automatic Determination of Default Settings in the chapter "Using Report-Writer" for a discussion of how Report-Writer determines the margins.

If you specify centering with the *columnname* parameter or with an expression that evaluates to a *columnname*, Report-Writer centers the text in that column. Report-Writer determines the center of the column through both of the following:

- Default position of the column, as determined by the .position statement or by default
- Width of the column, as determined by default or by the width of the format specified in the .format statement, or as specified in the .width or the .position statements

The .center statement centers text around a position calculated as:

```
centering position =
default column position + (default format width / 2)
```

Report-Writer rounds the position to the next highest number if there is any fraction.

The .center statement has a somewhat different meaning when executed in column formatting mode (that is, inside a .within statement with default column widths and positions assumed). Because the .within statement temporarily resets the report margins to the left and right margins of a specified column's width and position, a .center statement so executed centers a text string within the column width, not within the report page margins. For more information about column formatting mode, see the .within/.endwithin statements in Column and Block Statements.

Examples

Example 1

Output the date centered on the page.

```
.center
.print 'Report Executed On:', current_date
```

Example 2

Output a heading for a column centered above the value of that column, where the column is the delimited identifier, bank balance.

.Left

Left justifies the next text to be printed.

Syntax

.left | .lft [[+|-] n | columnname | expression]

In the preceding syntax, *expression* evaluates to the next print position where the text is left justified on a line or to the name of a column in the report. The plus sign (+) and minus sign (-) must be explicitly stated and cannot be part of the expression.

Description

The .left statement left justifies the text printed in the next .print statement to one of the following locations:

- Specified position
- Position corresponding to a specified column
- Value of a numeric expression that evaluates to a specified position
- Value of a string expression or variable that evaluates to a column name

Report-Writer evaluates any expressions that are used as parameters to the .left statement during runtime.

You can specify all the values for these parameters as either absolute or relative to the last output position. Report-Writer removes all leading and trailing blanks from the text before placing the text in the output line.

The .left statement is the same as the .tab statement for all output except for text that contains leading blanks, such as formatted numbers.

The meaning of the .left statement is slightly changed when executed in column formatting mode (that is, when the .within statement is in effect and default column widths and positions are assumed). When executed under these circumstances, the .left statement positions text at the left margin of the column indicated in the .within statement. For more information about column formatting mode, see the .within/.endwithin statements in Column and Block Statements.

The parameters for the .left statement are as follows:

Parameter	Description
+ -	Optional sign that moves the output position <i>n</i> positions relative to the last position output. If sign is not present, the position is the absolute position in the output line.
n	Position to which the next text is left justified. The default value is the left margin of the report (set by the .leftmargin statement).
columnname	Name of a column in the report. You can specify the column name as a delimited identifier by enclosing it in double quotes ("), if you previously specified the .delimid statement.
	The position for the column is determined either explicitly through the use of the .position statement, or implicitly as described in <u>Automatic Determination of Default Settings</u> . If <i>columnname</i> is specified, Report-Writer left justifies the next output text and places it at the position associated with the named column.
expression	Numeric or string expression. If the expression is numeric, it must evaluate to the next print position on the line. If the expression is a string, it must evaluate to the name of a column in the report. Precede all variables that are part of the expression with a dollar sign (\$).

Example

Output the title as centered and the value of balance as left justified to position 40.

```
.position balance (40, 10)
.center balance
.print 'Balance'
.detail
.left balance
.print balance (f10.2)
```

.Lineend

Begins the next text to be printed following the last non-blank character on the current line.

Syntax

.lineend | .lnend

There are no parameters to this statement.

Description

The .lineend statement changes the current position in the output line so that Report-Writer places the text in the next .print statement immediately after the last non-blank character on the line. This is useful in some advanced reports that use the .tab statement extensively. The .lineend statement always moves the current position marker to a position within the current margins of the report.

Example

To print a list of items across the page on the first line of a block:

```
.block
    .println 'ITEMS:'
    ...
.detail
    .top
    .lineend
    .println ', ', item
```

.Linestart

Begins the next text to be printed at the current left margin.

Syntax

.linestart | .linebegin

There are no parameters to this statement.

Description

The .linestart statement changes the position of the current marker for the output line so that the next text printed by the .print statement appears at the current left margin. The left margin is set either by the .lm statement, by default, or by the left edge of the column currently in use while in a .within block. The .linestart statement is useful in reports that use the .tab statement extensively. The .linestart statement always restores the current position marker to a known position, at the beginning of the line.

Example

With .linestart you can return to the beginning of the current line.

```
center
.print 'Accounts Receivable for', dept name
.linestart
.print '(', dept_code, ')'
```

.Newline

Writes out the current line and optionally advances a number of lines on the output page.

Syntax

.newline | .nl [nlines | expression]

In the preceding syntax, expression evaluates to a numeric value that is the number of lines to advance from the current line in the report.

Description

The .newline statement must be specified to advance to a new line on the output page. Unlike some programming languages (for example, Fortran), a .print statement does not imply a new line at its completion. However, you can use the .println statement for this purpose. If you do not specify *nlines* or a numeric expression that evaluates to *nlines*, the default value of *nlines* is one (advance to the next line).

After Report-Writer executes .newline, it begins the next text output at the left margin, unless another text positioning statement overrides the default.

Report-Writer evaluates any expressions that are used as parameters to the .newline statement during runtime.

The parameters for the .newline statement are as follows:

Parameter	Description
nlines	The number of lines to advance. If you are advancing to the next line, you can specify the .newline statement without the <i>nlines</i> parameter.
expression	A numeric expression which evaluates to the number of lines to advance from the current line. Precede all variables that are part of the expression with a dollar sign (\$).

If the output of a new line reaches the end of the current page, or if there are fewer than *nlines* left on the current page, Report-Writer prints the page footer and page header, if they have been specified.

If the current line includes multi-line format strings, (Cn.w), the .newline statement advances to the bottom of the longest column printed during the formation of the line. For the Dictionary Example in the appendix "Report-Writer Report Examples," the .newline statement in the footer for "word" causes an advance to the line following the end of the definition.

When you invoke column formatting mode, .newline causes an advance to the next line at the left margin, as determined by the .within statement. For more information on column formatting mode, see the .within/.endwithin statements in Column and Block Statements.

Examples

Example 1 Print out one line of text:

```
.print 'This is a line'
.newline
```

Example 2

Print out a variable number of newlines:

```
.println name
.println address
.println city, state, zip
.nl $label_size - 3
```

.Right

Right justifies the next text to be printed.

Syntax

.right | .rt [[+|-] n | columnname | expression]

In the preceding syntax, expression evaluates to the next print position where the text is right justified on a line or to the name of a column in the report. The plus sign (+) and minus sign (-) must be explicitly stated and cannot be part of the expression.

Description

The .right statement right justifies the text printed in the next .print statement to one of the following locations:

- Specified position
- Position corresponding to a specified column
- Value of a numeric expression that evaluates to a specified position
- Value of a string expression or variable that evaluates to a column name

Report-Writer evaluates any expressions that are used as parameters to the .right statement during runtime.

You can specify all the values for these parameters as either absolute or relative to the last output. Report-Writer removes all leading and trailing blanks from the text before placing the text in the output line.

The parameters for the .right statement are as follows:

Parameter	Description
+ -	If sign is present, the position is moved <i>n</i> positions relative to the last output position. If no sign is present, the position is the absolute position in the output line.
n	The position to which the next block of text is right justified. The default value is the right margin of the report (set by the rightmargin statement).

Parameter	Description
columnname	The name of a column in the report. You can specify the column name as a delimited identifier by enclosing it within double quotes ("), if you have previously specified the .delimid statement.
	Report-Writer determines the column's position either explicitly through the use of the .position statement, or implicitly as described in <u>Automatic Determination of Default Settings</u> in the chapter "Using Report-Writer." Report-Writer right justifies the text in the next .print statement to the right edge of that column, as determined from the default position and width of that column. For more information, see the discussion following this table.
expression	A numeric or string expression. If the expression is numeric, it must evaluate to the next print position on the line. If the expression is a string, it must evaluate to the name of a column in the report. Precede all variables that are part of the expression with a dollar sign (\$).

If you specify n or a numeric expression that evaluates to n (either relative or absolute), Report-Writer right justifies the text to that position. If you specify nothing, Report-Writer right justifies the text to the right margin of the report. Report-Writer determines the right margin either from the .rightmargin statement, if specified, or by default as described in <u>Automatic Determination of Default Settings</u> in the chapter "Using Report-Writer."

If you specify right justification with the *columnname* parameter or through a string expression that evaluates to a *columnname*, Report-Writer right justifies the text to the right edge of that column, as determined from the following:

- Default position of the column, as determined from the .position statement or by default
- Width of the column, as determined by the default width or the width of the format specified in a .format statement for that column, or by the width specified in .width or the .position statements

The .right statement justifies to a position calculated as:

justification position = default column position + default width

The meaning of the .right statement is slightly changed when the .right statement is executed within column formatting mode (that is, when the .within statement is in effect and default column widths and positions are assumed). When the .right statement is so executed without a parameter, the current position becomes the right margin as defined by the .within statement, not the right margin of the report. For more information about column formatting mode, see the .within/.endwithin statements in Column and Block Statements.

Examples

Example 1

Output a page number, right justified on the right margin.

```
.print 'Page ', page_number('zn')
```

Example 2

Output a heading for column "bal," right justified to the right edge of the column.

```
.position bal (20)
.format bal('+++,+++.nn')
.right bal .print 'Balance'
.detail
    .tab bal .print bal ...
```

.Tab

Specifies the position on the line where the next text is printed.

Syntax

```
.tab | .tb | .t [[+|-] n | columnname | expression]
```

In the preceding syntax, expression evaluates to the next print position on a line or to the name of a column in the report. The plus sign (+) and minus sign (-) must be explicitly stated and cannot be part of the expression.

Description

The .tab statement moves the current position marker to one of the following locations:

- Specified position
- Position corresponding to a specified column
- Value of a numeric expression that evaluates to a specified position
- Value of a string expression or variable that evaluates to a column name

Report-Writer evaluates any expressions that are used as parameters to the .tab statement during runtime.

You can specify numeric values for these parameters as either absolute or relative to the last output position.

The	parameters	for	the	tab	statement	are	listed	below:

Parameter	Description
+ or -	If sign is present, the new position or column is calculated relative to the current position. If sign is not present, it is set to the evaluated position n .
columnname	The name of a column in the report. You can specify the column name as a delimited identifier by enclosing it within double quotes ("), if you have previously specified the .delimid statement.
	Report-Writer determines the position for the column either explicitly through the use of the .position statement, or implicitly as described in Automatic Determination of Default Settings . If columnname is specified, Report-Writer begins the next output text at the position associated with the named column.
expression	A numeric or string expression. If the expression is numeric, it must evaluate to the next print position on the line. If the expression is a string, it must evaluate to the name of a column in the report. Precede all variables that are part of the expression with a dollar sign (\$).

If you do not follow the .tab statement with *n*, a *columnname*, or an *expression*, then the .tab statement works like a .linestart statement, with the next text beginning at the left margin of the report. The .linestart statement is described further in this chapter.

The .tab statement takes on a slightly different meaning when executed in the column formatting mode sections of a report (that is, when the .within statement is in effect and default column widths and positions are assumed). When the .tab statement is executed without a parameter in column formatting mode, Report-Writer moves the current position to the left margin of the current line. The left margin is determined by the .within statement.

For more details on column formatting mode, see the .within/.endwithin statements in <u>Column and Block Statements</u>.

Examples

```
Example 1 To output "HERE" in character position 12 on a line, use:
.tab 12
.print 'HERE'

Example 2 To output Summary in column position $title_col, use:
.tab $title_col
.println 'Summary'
```

Example 3

To output the value of the daily balance column (a delimited identifier) in position 30, use:

```
.position "daily balance"(30)
    .tab "daily balance"
    .print "daily balance"('+++++.NN')
```

Example 4

To print two columns of figures separated by a bar:

```
.tab credit_sum
.right salary1
.print salary1,' |'
.right salary2
.print salary2
```

Example 5

To tab forward the amount specified by the value of \$col_width, use:

```
.tab +$col width
.print
```

Print Statements

Use these statements to print text or data values in a report:

- The .nullstring statement specifies a string of characters you want to print in the report whenever a null value is encountered in the data.
- The .print and .println statements print text or values at a default position, or at a position that was previously specified with the column and block and/or text positioning statements.
- The .ulcharacter statement sets up a different underline character than the default, for use with Report-Writer underlining statements.
- The .underline and .nounderline statements control underlining for sections of text.

Use an expression in the .print statement syntax to specify the text or value you want to print. Expressions can include any (or any combination) of the following:

- Column names from the data retrieval statement
- Variables
- Constants
- **Functions**
- Special report variables, such as the current_time, current_date, or page_number

You can optionally indicate the print format within the syntax of the .print statement, or you can specify it in a separate .format or .tformat statement for column values. For more information, see <u>Column and Block Statements</u>.

.Nullstring

Specifies an alternate null string.

Syntax

.nullstring | .nullstr 'null_string' | expression

Description

The .nullstring statement allows you to specify a string to print whenever a null value is to appear on the report. The string can be an expression that evaluates to a string at runtime. Because a data value of *null* means that there is really no data present to print, you can use the .nullstring to print a designated string that signifies the absence of the data.

The parameters for the .nullstring statement are as follows:

Parameter	Description
null_string	Any string of characters. Enclose the string in single quotes, so Report-Writer can properly handle leading and trailing blanks, which are important in some format specifications.
expression	A string expression that evaluates to any character string. Precede all variables that are part of the expression with a dollar sign (\$). For more information, see the chapter "Report-Writer Expressions and Formats."

Note: Ensure that the length of the *null_string* is less than or equal to the width of printed nullable columns. If a column is not wide enough to contain the *null_string*, then the empty string is printed instead.

If you do not specify a .nullstring statement, Report-Writer uses the default value of the II_NULL_STRING environment variable/logical, if defined. If not defined, it uses a default of the empty string (a string with no characters) to print a null value. You can specify several .nullstring statements in a report specification. The system uses the current .nullstring until another .nullstring statement is executed.

Example

Suppose phone_number is a nullable integer column whose value is null. If you issued the following print statements:

```
.nullstring 'N/A'
.print ' Phone number = ', phone_number .nl
.nullstr '?'
.print 'Phone number = ', phone_number .nl
```

Report-Writer would print the following if the value of phone-number were null:

Phone number = N/APhone number = ?

.Print and .Println

Prints literal text strings, columns from the database, or expressions on the report.

Syntax

.print | .pr | .p expression[(format)]{, expression[(format)]}

.println | .prln | .pln expression[(format)]{, expression[(format)]}

In the preceding syntax, format can be expressed as a variable (\$formatvariable). The parentheses () must be stated explicitly and cannot be part of the format variable. The comma (,) must be stated explicitly and cannot be part of the expression.

Description

The .print statement specifies text to be included in the body of the report. Text can be character strings printed directly, data items from the data table, variables, aggregates, or a combination of these. Report-Writer includes the text at the place in the report where it encounters the .print statement. By preceding the .print statement with the positioning statements such as .newline, .tab, .center, .right, or .left, you can specify the location of the text. By default, Report-Writer includes the text immediately after the last text output with the .print statement.

Report-Writer evaluates any print expressions that are used as parameters to the .print statement during runtime. You can include as many expressions as you want in the .print statement; Report-Writer adds them to the report in the order specified.

If the expression is a runtime variable for a column name (for example, .print \$account type), Report-Writer prints the name of the column as entered at runtime, rather than its data. To print the data rather than the column name, you use the select column list as resultcolumn list construct in the query and reference the *resultcolumn_list* name in the .print statement. For more information, see the .Query statement description in Report Setup Statements.

If you use the optional .println form of the statement, the current print position advances to the next line after the specified text is printed.

Data that formats into a single logical line can wrap to yield a default maximum of 310 physical lines as protection against omitted explicit .newline and/or .newpage statements. You can override this limit by specifying the -wmxwap parameter in the report command.

Important! Embedding tabs in a string can truncate the string if it is printed with a default format or with a format that is not large enough to allow the tab to be expanded into spaces. To print string sthat contain tabs, use a specified format wide enough for the expanded tab(s).

The parameters for the .print statement are as follows:

Parameter	Description			
expression	Any legal expression. For more information, see the chapter "Report-Writer Expressions and Formats." You can specify a column name in an expression as a delimited identifier by enclosing it in double quotes ("), if you have previously specified the .delimid statement.			
format	An optional printing format for the expression, as described in <u>Format Specifications</u> . The format must be the correct type for the expression. If you do not specify a format, Report-Writer uses one of the default formats listed in the chapter "Report-Writer Expressions and Formats."			
\$formatvariable	Variable whose value is the name for a printing format described in <u>Format Specifications</u> . The format must evaluate to the correct type for the column(s). Precede the variable with a dollar sign (\$). Report-Writer evaluates <i>\$formatvariables</i> , but not expressions, at load time.			

Examples

Example 1 Assume a report specification with the following literals:

It would print the following output:

Text may span several lines.

Because there was no specification statement such as a .tab or a .newline to separate the fields, the two text strings printed immediately adjacent to each other on the same line of the output.

Example 2

In this example, assume that page_numberis equal to 3.

```
.pr 'Page number:', page_number(zz)
```

Report-Writer would print the following text:

Page number: 3

Example 3

The following example shows the specifications you need to print a data value (represented by a delimited identifier for the column name) and an aggregate, using a numeric template for the aggregate where the value of *millions_fmt* is 'nnn,nnn,nnn.nn':

```
.print "acct bal", sum("acct bal")($millions fmt)
```

Example 4

A complex .print statement that displays a large number of data items can look like the following:

```
.print 'Values of the data are: ', var1,
                 var2(e20.4) cvar1(c40), ' and finally',
                 lastvar (' $$$,$$$,s$$.nnCR')
```

Note that in the previous example, the field, var1, was listed without a format. Report-Writer prints the value with the default format for the data type, according to the table in Default Formats, in the chapter "Report-Writer Expressions and Formats." It is acceptable to mix the default data formats with extremely complex templates. Using an acceptable default format saves you the time and effort of specifying every format in detail.

.Ulcharacter

Sets the underlining character to any single character when output is to a file or printer.

Syntax

.ulcharacter | .ulchar | .ulc 'c' | expression

Description

With the .ulcharacter statement, you can specify an alternate underlining character or an expression that evaluates to an underlining character during report runtime. Underlining occurs only in reports written directly to a file or printer. Report-Writer ignores underlines when displaying a report on the screen and in reports sent to a file or printer from the screen.

The parameters for the .ulcharacter statement are as follows:

Parameter	Description
С	Any single character, subsequently used as the underlining character. The default underlining character is the underscore (_) for reports written to a file or printer, and none for reports written to the screen.
expression	A character expression that evaluates to any single character, subsequently used as the underlining character. Precede all variables that are part of the expression with a dollar sign (\$). For more information, see the chapter "Report-Writer Expressions and Formats."

The character c must be a single character enclosed in quotes. That character remains in effect until Report-Writer encounters another .ulcharacter statement in the report.

Report-Writer prints underscoring (_) on the same line as the text. If any other character, such as a hyphen (-), is specified with the .ulcharacter statement, Report-Writer prints underlining as a second line immediately below the underlined text.

Example

To produce the following:

```
Underline me
--------
and me
=== ==
```

Use the following specifications:

```
.underline
    .ulcharacter '-' .pr 'Underline me' .newline
    .ulcharacter '=' .pr 'and me' .newline
.nounderline
```

.Underline and .Nounderline

Underlines text.

Syntax

```
.underline | .ul | .u
any printing statements
.nounderline | .noul | .nou
```

There are no parameters to either statement.

Description

To underline text in a report, put an .underline statement immediately before the spot where underlining begins, and .nounderline at the spot where it stops. You can underline anything that can be printed, including character strings, column values, parameter values, or aggregate values. Underlining occurs only in reports written directly to a file or printer. Report-Writer ignores underlines when displaying a report on the screen and in reports sent to a file or printer from the screen. By default, the underlining character is an underscore (_). This can be changed with the .ulcharacter statement.

When underlining is in effect, only letters and digits are underlined. The .underline statement ignores all other characters, such as blanks, commas, and periods. Underscores print on the same line as the text. If the underlining character is anything other than an underscore, Report-Writer prints the underlining on the line below the one containing the text to be underlined.

Note: Printers that interpret carriage returns as a combination of both a carriage return and a line feed is not able to use the underscore (_) as the default underlining character. If your printer is configured this way, you should use the .ulcharacter command to reset the underline character to a hyphen (-) or some other character; otherwise, if you use the underscore as the underlining character, Report-Writer prints the underline above the text instead of below it.

Example

```
To produce the following line:
```

```
Numbers - 123,456 are underlined,
but punctuation is not!
```

Use the following specifications:

```
.underline
.print 'Numbers - 123,456 are '
.print 'underlined,'
.newline
.println 'but punctuation is not!'
.nounderline
```

Conditional and Assignment Statements

Use these statements to specify alternative blocks of statements or to assign values to variables:

- The .if, .then, and .else statements specify alternative blocks of statements to be executed under specified conditions.
- The .let statement assigns a value to a variable, which can be used in subsequent computations.

.lf

Specifies alternative blocks of statements to be executed under specified conditions.

Syntax

Description

The .if statement specifies alternative blocks of statements to be executed depending upon the value of the specified condition.

Report-Writer evaluates the conditions in the .if and .elseif clauses one after another. When a condition is met, Report-Writer executes the statements following the subsequent .then statement. If *none* of the specified conditions is met, Report-Writer does nothing. If none of the conditions is met and there is an .else clause included in the .if statement, Report-Writer executes the statements following the .else statement.

The parameters for the .if statement are as follows:

Parameter	Description
condition	A boolean expression that evaluates to true or false.
statement	Any action statement, including the .if statement (this excludes the setup and structure statements in the sections, Report Setup Statements and Report Structure Statements).

Both the expression in the *condition* and/or the parameters to *statement* can contain column names that are delimited identifiers enclosed in double quotes ("), if you have previously specified the .delimid statement.

Examples

Example 1

This example illustrates the use of the .if statement to take different actions based on the current condition of the Report-Writer environment. It tests the current character position, and starts a new line if the current position is past the end of a line:

```
.if position_number > 80 .then . \mbox{newline} \\ . \mbox{endif}
```

Example 2

This example tests the data and prints different things, depending on the value of some of the report data:

```
.if balance < 0 .then
        .print '(',-balance, ')'
        .tab +1
        .print balance
.endif
```

Example 3

This example tests a column value and uses .if statements to translate a numeric code number from the database to a text string for the report, and to selectively print column values accordingly. Notice that both the conditional expression and the .then statements reference column names that are delimited identifiers.

```
.print 'Furniture: ', "furniture sales"
.elseif "dept code" = 3 .then
      .print 'Jewelry: ', "jewelry sales"
.else
      .print 'Misc: ', "misc sales"
.endif
```

.Let

Assigns the value of an expression to a declared variable.

Syntax

.let variablename [:] = expression

Description

The .let statement evaluates the expression and assigns its value to the declared variable. You can place it in any .header, .footer, or .detail section.

Report-Writer evaluates the .let statement after the query. Therefore, if you initialize a variable in a .declare statement and then change the value with a .let statement, the initialized value remains active until after the query, regardless of where the .let statement occurs in your report specification.

The data type of the expression must be coercible to the data type of the variable to which it is assigned. For example, an integer expression can be assigned to a floating point variable, and a legal date expression string to a date variable; however, a date expression cannot be assigned to an integer variable. When in doubt, use an explicit coercion function. For a list of functions available to Report-Writer, see Built-in Functions.

When the data types in an assignment are incompatible, Report-Writer displays an error message and retains the previous value of the variable. The report continues to run.

The parameters for the .let statement are as follows:

Parameter	Description
variablename	A variable name declared in a .declare statement. The <i>variablename</i> cannot be a special report variable, column, or delimited identifier.
expression	An expression. The <i>expression</i> cannot be a Boolean or conditional one, because there cannot be variables of data type Boolean. The <i>expression</i> can contain column names that are delimited identifiers enclosed in double quotes ("), if you have previously specified the .delimid statement.

Examples

Example 1

The following .declare statement defines two data variables, *age* and *birthday*. These are then used in .let statements showing a number of possible assignments that could be made.

```
.declare
    age = integer,
    birthday = date
.let age := 6.2
.let age = $age+1 /* one year older*/
.print $age .n1
.let birthday := '29-jul-1954'
.let age := interval ('years',
    date ('9-jul-1987') - $birthday)
.print $age .n1
```

If these assignments were made in sequence, as shown, the output would be as follows:

7 32

Example 2

The following example prints the age in the current row of a column whose name is the delimited identifier, age at retirement.

```
.let age = "age at retirement" .print $age .n1
```

Statements Syntax Summary

Statement Category	Accepts Variables or an Expression*	Default, If Not Specified
.block .blk other formatting statements .endblock .endblk .end block	No	None
.bottom .bot	No	None
.break brk columnname { , columnname}	No	None
.center .cen .ce [[+ -] n columnname expression]	Expression	Page center**
.cleanup SQL_statement; {SQL_statement;}	No	None
.data .dat .table .view [schema.] tablename viewname synonym	Variables	None
<pre>.declare variablename = datatype [with null not null] [with prompt 'promptstring'] [with value 'valuestring'] {, variablename = datatype}</pre>	No	None
.delimid	No	Delimited identifiers not recognized
.detail .det	No	None
.footer .footing .foot report page columnname	Variables	None
<pre>.format .fmt columnname{, columnname} (format) { columnname{, columnname} (format)}</pre>	Variables	Determined by data type of column
.formfeeds .ffs .ff .noformfeeds .noffs .noff	No	
<pre>.if condition .then {statement} {.elseif condition .then {statement}} [.else {statement}] .endif</pre>	No	None
.include filename	No	None
.left .lft .lt [[+ -] n columnname expression]		Left margin**
.leftmargin .lm [[+ -] n expression]	Expression	0
.let variablename [:] = expression	Expression (right of the equal sign)	None

Statement Category	Accepts Variables or an Expression*	Default, If Not Specified
.lineend .lnend	No	None
.linestart .lnstart .linebegin	No	None
.longremark .lrem remark_text .endremark .endrem	No	None
.header .heading .head report page columnname	Variables	None
.name .nam reportname	No	None
.need .ne nlines expression	Expression	None
.newline .nl [nlines expression]	Expression	1
.newpage .np [[+ -] pagenumber expression]	Expression	Current page number + 1
.nullstring .nullstr 'null_string' expression	Expression	None
.output .out filename	Variables	Screen
.pagelength .pl {nlines expression}	Expression	Files: 61 lines Screens: screen length
.pagewidth .pw width	Variables	Files: 132 characters Screens: screen width
<pre>.position .pos columnname{, columnname} position[, width]) {, columnname{, columnname} (position[,width])}</pre>	Variables	None
<pre>.print .pr .p expression [(format)] {, expression [(format)] or .println .prln .pln expression [(format)] {, expression [(format)]}</pre>	Expression (Note: Formats can only take variables)	None
<pre>.query .quer /* for SQL users * / select [all distinct] column_list [as resultcolumn_list] from [schema.]table view synonym [corr_name] {, [schema.]table view synonym [corr_name]} [where search_condition] [group by column {, column}] [having search_condition] {union select} [order by]</pre>	Variables	None
.query .quer /* for QUEL users * / {range_statement(s)}	Variables	None

Statement Category	Accepts Variables or an Expression*	Default, If Not Specified
retrieve [unique] (target_list) [where qual] [sort by order by] sort-list		
<pre>.right .rt [[+ -] n columnname expression]</pre>	Expression	Right margin**
.rightmargin .rm [[+ -] n expression]	Expression	100 or determined by detail statement
.setup SQL statement; {SQL statement;}	No	None
.shortremark .srem remark-text	No	None
<pre>.sort .srt {columnname[:sortorder] {, columnname[:sortorder]}}</pre>	Variables	None
.tab .tb. .t [[+ -] n columnname expression]	Expression	None
<pre>.tformat .tfmt columnname{, columnname} (format) {, columnname{, columnname} (format)}</pre>	Variables	None
.top .tp	No	None
.ulcharacter .ulchar .ulc 'c' expression	Expression	Files: underscore (_) Screens: hyphen (-)
.underline .ul .u any printing statements .nounderline .noul .nou	No	No underline
<pre>.width .wid columnname{, columnname} (width) {, columnname}{, columnname} (width)}</pre>	Variable	Determined by format
.within .wi columnname{, columnname} all other formatting statementsendwithin .endwi .end within	Variable	None

^{*} If an expression is used, it must evaluate to the type of object indicated in the statement; for example, a number or column name. Variable names must be preceded by a dollar sign (\$) to evaluate them. Any punctuation must be explicitly stated and cannot be a part of the expression. Statements that take variables only (not expressions) are evaluated during the load of the report specifications, while those that take expressions are evaluated each time the statement is executed.

^{**} The default value if the statement is specified with no parameter.

Chapter 13: Using VIFRED

The VIFRED is a visually oriented tool for creating or modifying the appearance of forms. With VIFRED, you can create custom forms or edit and enhance default forms in the following ways:

- Set the default display style to full-screen or pop-up, or change the dimensions of a form, field, or data area
- Specify the order in which fields appear in the window or are accessed
- Create lines, boxes, and other trim, as well as instructions and information for the end user that make the form more attractive or easier to understand
- Edit a field's default title to more accurately describe its purpose, or specify color, underlining, blinking, or other attributes for a field
- Define fields that scroll horizontally, are display-only or query-only
- Make entry in a field mandatory, specify an automatic default value, or establish validity checks to verify that the information entered into a field meets certain criteria
- Change error messages that appear if a user enters incorrect data


Use these customized forms with QBF to display, add, or modify data in your database, or in applications that you design using ABF, Vision, or an embedded guery language.

The three chapters on VIFRED provide information as follows:


- This chapter provides instructions for starting VIFRED, creating default forms, managing forms, and creating QBFNames.
- The chapter "VIFRED Form Components" explains how to create and edit individual form components.
- The chapter "VIFRED Field Specifications" provides details on specifying field attributes.

VIFRED Frames and Operations

When you choose Forms from the Ingres Menu, the Forms Catalog frame appears. From this primary forms frame, you can access all other VIFRED frames. The following two figures contain maps of the various VIFRED frames and operations:



For a menu map of the JoinDef Edit frame's menu options, see the chapter "Using JoinDefs in QBF." The following figure is a menu map of the Forms Layout frame:



Starting VIFRED

You can start VIFRED from the operating system or from the Ingres Menu.

Starting VIFRED from the Operating System

You use the vifred command to start VIFRED from the operating system. For more information, see the chapter "Using System Commands for the Formsbased Tools."

Starting VIFRED from the Ingres Menu

To start VIFRED from the Ingres Menu, choose Forms. VIFRED displays the Forms Catalog frame, shown below, which provides access to all other forms-editing frames in VIFRED.

Starting VIFRED in Expert Mode

Expert mode allows you to enter VIFRED without displaying the full list of existing forms in the Forms Catalog frame. Instead, you type the name of the form you want to work with in the Name column of a blank Catalog frame.

You can also use expert mode with pattern matching to have VIFRED retrieve a range of forms from which you can choose. For example, to retrieve and display a list of all the forms that begin with the letter s you would type s* in the Name column.

To start VIFRED in expert mode:

- From the operating system enter the command:
 vifred [dbname | v_node::dbname] [/server-type] -e
- 2. VIFRED displays an empty Forms Catalog frame.
- 3. In the Name column, type the name of the form you want to work with, or pattern-matching characters to select several forms at once.
- 4. Choose the operation that you want to perform.


If you entered a single form name in the Name column, VIFRED performs the chosen operation. If you used pattern matching, VIFRED displays all the forms that match your specification. To select from the displayed list:

- h. Place the cursor on the name of the form to select it.
- i. Choose the operation to perform.

VIFRED Forms Catalog Frame

The Forms Catalog frame lists all VIFRED forms owned by the user or the DBA and stored in the current database. It displays a menu of operations that you can perform on these forms.

The Forms Catalog frame in the following figure displays the owner (creator) and a brief description of the form beside the name of each form.



To locate the name of a form, scroll through the list or type the first letter of the form that you are searching for. If you type the first letter, VIFRED places the cursor on the next form in the list that begins with that letter.

This table shows the operations on the Forms Catalog frame:

Operation	Description
Create	Displays a pop-up form showing the sources for creating a new form.
Destroy	Destroys the form highlighted by the cursor. You can only destroy forms that you own.
Edit	Displays the Form Layout frame for editing or viewing the form selected by the cursor.
Rename	Renames the form selected by the cursor. You can only rename forms that you own.
MoreInfo	Obtain more information about the selected form. The additional information includes the time the form was created and a short and long description of the form.

Operation	Description	
Utilities	Provides access to the following forms management operations:	
	Compile - Compiles a form definition for use with an embedded query language as a C source file (or VMS macro).	
	Print - Creates a picture of the form that can be printed on a line printer.	
	QBFNames - Creates, renames, or deletes QBFNames.	
Go	Starts QBF using the form highlighted by the cursor. For more information, see Running QBF from VIFRED .	
Help, End, Quit	Standard operations.	

In addition to these operations, you can also use system-level commands such as copyform, compform, delobj, and printform to manage VIFRED forms.

Creating New and Duplicate Forms

Create a new form with the Create operation on the Forms Catalog frame. The Create operation offers you the choice of duplicating an existing form (which you can then edit), beginning with a completely blank form, or creating a default form from a table or JoinDef.

To create a form:

1. Choose the Create operation on the Forms Catalog frame. VIFRED displays a pop-up. This table lists the choices available on the pop-up:

Operation	Description
Duplicate	Creates a form from an existing form.
Blank	Creates a form starting with a blank window.
Table	Creates a default form based on a table.
JoinDef	Creates a default form based on a JoinDef.

2. Choose one of the operations on the pop-up menu. For additional instructions, see the appropriate section that follows.

Duplicating Forms

Create a new form by duplicating an existing form in the current database. Modify it with the Duplicate operation on the Forms Catalog frame, following the same steps used to create a default form. For details, see Creating Default Forms.

To duplicate a form from another database, use the copyform system-level command to copy the form into the intended database. This command also allows you to change the name and ownership of the form.

Creating Blank Forms

You can create blank forms that:

- Do not access data, but rather act as logo windows, information windows, and help windows.
- Are interactive forms linked to procedures written in a database programming language such as 4GL and embedded SQL. An example of this is an application login window in which users enter their name and password.
- Access and display database data through procedures written in programming languages.

To create a blank form:


- 1. Choose Blank from the Creating a Form pop-up menu.
- 2. Choose the Select operation on the Forms Catalog frame.
 - VIFRED displays a blank form in the Form Layout frame, which is described in the next section.
- 3. Choose the Save operation on the Form Layout frame to save and store the form under a name you give it.

After creating the form, you can modify it, as discussed later in this chapter, or add components to it, as discussed in the chapter "VIFRED Form Components."


Creating Default Forms

To create a default form based on a table or JoinDef, or a form that duplicates an existing form in the current database:

1. Choose Duplicate, Table, or JoinDef from the Creating a Form pop-up.



After making your selection, another pop-up similar to the one shown here appears.



- 2. Chose one of the following procedures:
 - If necessary, use the ListChoices operation to display a list of available choices and select an item from the list.
 - If you are basing the default form on a JoinDef, enter the JoinDef name on the appropriate pop-up. This pop-up contains the additional menu option, Edit. If you want to edit or create the JoinDef, choose the Edit operation to access QBF. VIFRED returns you to the default form creation process when done.
 - If you are basing the default form on an existing form or table, enter the form or table name on the appropriate pop-up. You can specify more than one table by separating the table names with spaces or commas.
- 3. In addition, if you are basing the form on a table, specify one of the display formats listed in the following table:

Selection Description			
tablefield	Displays several rows on a form that can be scrolled horizontally or vertically if all columns and rows do not fit in the window at one time.		
simplefields	Displays one record at a time.		

4. Choose the OK operation. VIFRED displays the appropriate form in the Form Layout frame, which is described in the next section.

If you based the form on a table or JoinDef, VIFRED displays a default form, with one field on the form for every data column in the table or JoinDef. The titles, internal names, and data display formats of these fields are based on the underlying data columns. For special issues regarding the long varchar, byte, byte varying, and long byte data types and delimited identifiers, see the note following this procedure.

5. Choose the Save operation on the Form Layout frame to save and store the form under a name you give it.

After creating a form you can modify it, as described in this chapter, or add components to it.

Note: VIFRED does not create fields or table field columns on a default form for columns of data types long varchar, byte, byte varying, and long byte in the associated database table or tables.

If your table uses delimited identifiers, column-to-field name conversions in default forms can result in form field name collisions. This is because VIFRED allows delimited identifiers for column names, but not for field names. It must strip out certain characters in the database column name to make the new field name conform to regular identifier rules. For example, if the database table has separate columns named Column1 (regular identifier) and "Column 1" (delimited identifier), VIFRED converts both column names to the same default field name, Column1.

Creating Forms that Use Multiple Tables

To create a form that uses columns from multiple database tables, use one of the following techniques:

 Create a default form based on an existing table. When the Create a Form Based on a Table pop-up appears, enter more than one table name, separated by spaces or commas. VIFRED automatically creates fields with the appropriate internal names and data display formats.

- Use a query language to create a multi-table view or use QBF to create a JoinDef; then create a default form for that view or JoinDef. VIFRED automatically creates the fields with the appropriate internal names and data display formats.
- Create a blank form and create the fields you want, specifying appropriate data display formats; then use a programming language to link those fields to data columns in multiple tables by way of the fields' internal names.

You can use the GetTableDef operation to create a table field on the form that contains internal names and data display formats automatically corresponding to the columns in the database tables. You cannot use GetTableDef to create simple fields.

Form Layout Frame

After you create a form with the Create operation on the VIFRED Forms Catalog frame, VIFRED places you on the VIFRED Form Layout frame. You can also access the Form Layout frame by placing the cursor on the name of a form listed in the VIFRED Forms Catalog frame and choosing the Edit operation.

The Form Layout frame is the basic frame for modifying and enhancing an existing form.

Alignment Guides

You can use the following alignment guides on forms displayed in the Form Layout frame:

Ruler marks in the form's margins

- Straight edge alignment guides
- Location operation

An example of the alignment guides are shown here.



Margin Rulers

The right and bottom margins of your form contain optional ruler marks every fifth column or row, and a decimal digit every tenth column or row, to help you determine the coordinates of components on your form. The margins containing the rulers are initially positioned off the screen on fullscreen forms. To see them, you need to scroll the form by moving the cursor to the edge of your window, or use the Move operation to move the form's margins. For instructions on moving the margins, see Moving the Margins of a Form.

You can turn ruler marks on or off by choosing the Rulers operation on the Form Layout frame. On the pop-up menu, set Rulers to y (yes) or n (no). The default is n (no).

Straight Edges

The Form Layout frame contains optional horizontal and vertical straight edge alignment guides to help you line up the components on your form. The vertical and horizontal straight edges appear initially in the last column and row of the form. If the form is larger than your window, you must scroll the form by moving the cursor off-screen to gain access to them. If a straight edge is touching a form component, such as trim or a field, the form component temporarily takes precedence and obscures that part of the straight edge.

You move straight edges with the Move operation, as you would a piece of trim or other form component. For best results, use a monitor with a line graphics character set.

You can turn straight edges on or off by choosing the Rulers operation on the Form Layout frame. On the pop-up menu, set Straight edges to y (yes) or n (no). The default is n (no).

Location Operation

When working with forms, you sometimes need to know the precise row and column location of a place in your window. For example, to specify a fixed position for a pop-up form with the StartRow and StartColumn attributes, you must know the row and column designation of that place in your window.

The Location operation on the Form Layout frame displays the current row and column location of the cursor, relative to the boundaries of your window, regardless of the placement and orientation of the form.

To find the row and column location of any place in your window:

- 1. On the Form Layout frame, place the cursor at the chosen spot.
- 2. Choose the Location operation.

VIFRED marks the cursor location with a plus sign (+) and displays a message giving the row and column location.

Layout Frame Menu Options

This table summarizes the operations that you can use on the Form Layout frame:

Operation	Description		
Create	Displays a new menu that enables you to create new components on a form.		
Delete	Deletes the component where the cursor is positioned.		
Edit	Displays another menu that enables you to edit the trim or field component where the cursor is positioned.		
Move	Moves a component or changes the margin. This operation displays a new menu. For more information on changing the overall margins of a form, see Setting Form Size and Position .		

Operation	Description			
Undo	Reverses the results of the last operation you performed. Undo does not reverse the FormAttr operation on the Form Layout frame or the EditAttr operation on the Edit submenu.			
Order	Changes the order in which the form's fields are accessed when an end user presses the Tab key. This operation displays a new menu for ordering fields.			
Save	Displays a new menu that allows you to save your new or updated form in the database. The Save operation is independent of exiting. You can save one form and begin work on another without leaving VIFRED. For more information, see Saving Forms .			
FormAttr	Changes the default attributes of the form as a whole, such as fullscreen or pop-up display style. For more information, see Specifying a Form's Display Attributes .			
Location	Displays a message giving the current row and column position of the cursor, relative to your window boundaries, and marks the cursor location with a plus sign (+). For details, see <u>Location Operation</u> .			
Groupmove	Moves an entire group of components on a form at once.			
Rulers	Turns rulers and straight edges on or off. For more information, see <u>Margin Rulers</u> and <u>Straight Edges</u> .			
Help, End, Quit	Standard operations.			

Specifying a Form's Display Attributes

Form attributes are specifications that apply to the form as a whole (in contrast to field attributes, which are specifications that apply to individual fields). All form attributes are related to the following form characteristics:

- Display style
- Size and screen position


You designate a form's attributes with the Form Layout frame's FormAttr (form attribute) operation. When you choose the FormAttr operation, VIFRED displays the Form Attributes pop-up frame. Use this frame to specify attributes for the form currently displayed in the Form Layout frame.

The *display style* of your current form determines which attributes appear on the Form Attribute pop-up frame. VIFRED provides two basic display styles for forms:

- Fullscreen
- Pop-up

For more information on display styles, see Choosing a Form's Display Style.

This figure shows the Form Attributes frame for a fixed-position pop-up style form.



The following table lists and summarizes all of the attributes that appear on Form Attributes frames for both fullscreen and pop-up forms. Only those attributes that apply to the style of your form appears on your Form Attributes frame.

Attribute	Description	For	
Style	The display style of the form, either fullscreen or pop-up	All forms	
Size	Size of the form in rows and columns All forms (disonly)		
Screen Width	Displays the screen in the terminal's current width (default), narrow width (usually 80 columns), or wide width (usually 132 columns)	Fullscreen forms	
Position	How the pop-up form is positioned (either fixed position or floating position)	Pop-up display-style forms	

Attribute	Description	For	
Border	Whether the pop-up form has an automatic border	Pop-up display-style forms	
StartRow	The row containing the form's upper left corner	Fixed-position pop-up display-style forms	
StartColumn	The column containing the form's upper left corner	Fixed-position pop-up forms	

The following sections provide more detailed information about the attributes in the Form Attributes table.

Choosing a Form's Display Style

You use the FormAttr operation on the Form Layout frame to choose a form's display style. Display style determines whether the form appears alone in the window or as a pop-up form, which can overlay another form.

Fullscreen

Forms in normal or *fullscreen* display style appear one at a time on your screen. Each time VIFRED displays a new form, it removes the previous form from the screen. The term *fullscreen* refers to the fact that only one form can be displayed at a time, not the size of the form. A fullscreen form can be any size you want, either larger or smaller or the same size as your screen. The default size is the width of your screen, at form-creation time.

Pop-up

Forms in *pop-up* display style can be displayed without removing previously displayed forms from the window. A pop-up style form temporarily covers over some or all of the previous form. Thus, by using pop-up style forms you can have multiple forms, or portions of forms, visible at the same time. The cursor is only active in one form at a time—always the last form activated.

You can make pop-ups any size up to the size of your window, but they are most useful when you make them small enough to be displayed without completely obscuring previous forms. When specifying the size of a pop-up form, allow space for a border, if you choose to use one. For more information, see Setting Form Size and Position.

You can specify that a pop-up style form appear at a specific window location or automatically float to a position near to but not obscuring the field in the previous form that contains the cursor.

Pop-up style forms can be used for a wide variety of purposes:

- To display information such as messages and prompts.
- To display lists of acceptable values during data entry. For example, if a user is not sure of the values that go into a particular field, a pop-up form can be invoked to show those values.
- To display lists of currently existing tables, reports, JoinDefs, QBFNames, and other objects.
- To allow users to easily interrupt one operation, perform another operation on a pop-up form, and then return to the first operation without having to load and traverse many different menus.

For example, suppose you are appending records to a table and someone asks for information contained in another table. You can code an application so that, by invoking a pop-up retrieval form for the other table, the user can perform a query (on the pop-up form) and then return to the original task by removing the pop-up form.

When using pop-up forms in an application, the application code controls the appearance and disappearance of the pop-up. When your application code displays a normal fullscreen form, it clears the previous form from the screen. When your application code displays a pop-up form, the previous form remains in your window.

Changing a Form's Style

To change a form's style:

- 1. Choose the FormAttr operation on the Form Layout frame. VIFRED displays the Form Attributes pop-up frame.
- 2. Type an f for fullscreen or a p for pop-up in the Style field and press the Return key.

VIFRED automatically displays the attributes on the Form Attributes popup that are available for the new style. If you change a fullscreen form to a pop-up form, VIFRED sets the default value of the Border attribute to Y (yes) and the Screen Width to the default setting, Current, which is the default width as set at run time.

If you started with a form that was as large or larger than your screen—for instance, a default fullscreen form—you must delete some lines from the form to make room for the pop-up form's border, which requires two lines, before changing it to a pop-up. If you change the Border attribute to N (no) for a form that occupies your entire screen, you still need to reduce its size by two lines to change it to a pop-up, in case a user turns on the borders at run time.

Specifying Borders for Pop-up Forms

The Border attribute tells VIFRED whether to include an automatic border around a pop-up display-style form. The Border attribute is not available for fullscreen forms.

By default, a border is specified. To change the specification, enter n for no border or y for yes to include a border in the Border attribute field on the Form Attributes pop-up.

Allow space for the border when sizing your pop-up, or when creating a popup by changing the style of a fullscreen form that occupies the entire screen. A border requires two lines and two columns in addition to the other components on your form. A borderless pop-up requires the same allowance, in case a user turns on borders at run time.

You cannot specify display attributes such as brightness, inverse video, or color for borders created with the Border attribute. If you want to define your own border, you can use the Box/Line operation to draw a box around the inside edges of the form. This allows you to specify display attributes for the box.

Setting Form Size and Position

You can use the FormAttr operation on the Form Layout frame to:

- Determine the size of your form with the Size attribute.
- Change the spacing or size of characters for a fullscreen form when displayed on your screen, by setting the Screen Width attribute.
- Position a pop-up form with the Position, StartRow, and StartColumn attributes.

 Position a pop-up form with the VisuallyAdjust operation on the Form Attributes frame.

You can also use the Move operation on the Form Layout frame to change the size of your form by moving its margins.

Setting Size and Position Attributes

To change a form's size or the position of a pop-up form:

- 1. Choose the FormAttr operation on the Form Layout frame. VIFRED displays the Form Attribute pop-up frame.
- 2. Enter the change in the appropriate field on the Form Attribute frame, as described in the following subsections, and press the End key.

In most cases, you do not need to type the entire word or words for the option you want. The first one or two letters suffice.

Size

The Sizefield on the Form Attributes frame is a display-only field and reflects the current size of the form, as determined by editing on the Form Layout frame, or in the case of pop-up display-style forms, by the VisuallyAdjust operation.

When using this information to plan the location of a pop-up form, remember to account for the additional lines and columns required for a specified border. The pop-up and its border must be small enough to entirely fit within the window.

Screen Width

You can display a fullscreen form in one of the following widths, with accordingly larger or smaller character fonts and spacing:

- Current width
- Narrow width (usually 80 columns)
- Wide width (usually 132 columns)

The default is current screen width, as specified in the termcap entry corresponding to your TERM_INGRES setting. The narrow width is typically 80 columns, and the wide width is typically 132 columns, depending on your screen size and type.

To create forms wider than 80 columns, or to otherwise adjust the size of a form, see <u>Moving the Margins of a Form</u>.

Position Mode

The Position mode attribute is only displayed for pop-up display-style forms. Use this attribute to specify whether the pop-up style form is fixed or floating when it appears in the window.

Mode	Description
Fixed	If you specify this mode, you also can fill in the StartRow and StartColumn attribute fields, which specify the row and column position of the pop-up form's upper left corner. The form always pops up at that location regardless of which field is current or where the cursor is.
Floating	Whenever you invoke the pop-up display-style form, VIFRED positions the form in the window relative to the current field (the field containing the cursor). VIFRED places the pop-up form as close to the current field as possible without obscuring it.

To change the Position mode attribute:

- 1. Put the cursor in the Position mode field on the Form Attributes frame.
- 2. Type in fi for Fixed or fl for Floating and press End.

If you choose Fixed mode, you must set the size and position of the form, as discussed in the following sections.

StartRow and StartColumn

The StartRow and StartColumn attributes only display for fixed-position popup display-style forms.

Use the StartRow and StartColumn attributes to specify the location of a fixed-position pop-up style form. You use these two attributes to specify the screen row and column of the upper left corner of the form. For example, to place the upper left corner of the form at the 10th column of the 5th row, enter 5 in the StartRow field and 10 in the StartColumn field.

Both StartRow and StartColumn are screen-relative, not form-relative. That is, they refer to locations on the user's screen regardless of the position of any underlying forms or the position of the cursor. When you use fullscreen-style forms that are larger than your screen, you must scroll around the fullscreen form. Fixed-position pop-up style forms always appear at the same place in the window no matter how the underlying fullscreen form is displayed.

By default, the initial StartRow and StartColumn specifications are set to Row 1, Column 1.

Moving the Margins of a Form

You can use the Form Layout frame Move operation to create forms wider than 80 columns or to change the boundaries or margins of the form. When you use forms that are larger than your window, the form scrolls when you move the cursor to the edge of your window.

To use the Move operation:

 Place the cursor on the right margin marker and choose the Move operation. A new set of menu operations appear. The new operations are listed in the following table:

Operation	Description	
Place	Moves (contracts) the margin to a specified location within the current boundaries.	
Expand	Expands (increases) the current form boundaries by moving the form's margin outward to the right or further down.	
Help, End	Standard operations.	

- 2. Use the Place and Expand operations in conjunction with each other:
 - a. Use Expand to extend the right or bottom margin in large increments.
 - b. Use Place to fine-tune the new margin setting, positioning the margin at the specific point you want, within the confines of the expanded margins.

Each time you use Expand or Place, the Move operation is completed and VIFRED returns you to the previous menu. You must then use the Move operation again to perform another expand or place operation.

Expanding the Right Margin

To create a form wider than the default width (determined by the column width of your screen):

- 1. Place the cursor on the margin of the form. The margin is a vertical broken line containing ruler marks, if rulers have been turned on.
 - Typically, VIFRED uses the entire column width of your screen, which places the right margin immediately off-screen to the right. If the right margin is off-screen, you can move the cursor to it with your cursor keys.
- 2. Choose the Move operation on the Form Layout frame.
- 3. Choose the Expand operation on the Move submenu to extend the margin.

The Expand operation adds one-fourth of your monitor's current screen width to the form. If you use Expand once on an 80-column screen, you extend the right margin to column 100. Using it a second time extends the margin to column 120. You can choose the Expand operation as often as you like.

Expanding the Bottom Margin

Follow the same procedure to expand the bottom margin as you do to expand the right margin, except that you start by placing the cursor on the bottom margin. Each time you expand the bottom margin, the margin moves down by one guarter of your monitor's screen height in lines. If you use Expand once on a 24-line screen, you extend the bottom margin down by 6 lines.

Placing the Margin of a Form

The Place operation moves the margin inward to a position within the confines of the current margins. You cannot use the Place operation to move a margin outward from its current position, nor can you use it to move the margin so far towards the center of the form that some portion of a form component extends outside of the margins. In this case, the Place operation moves the margins as close to the desired location as possible, without having any form components extending past the margins. Under no circumstances does the Place operation squeeze components closer together.

To use the Place operation:

- 1. Place the cursor on the margin.
- Choose the Move operation on the Form Layout frame.
- 3. Relocate the cursor to the spot where you want the margin to be, within the boundaries of the current margins.
- 4. Choose the Place operation to move the margin to the new location.

For example, to position the margin at column 110 on an 80-column screen, use the Expand operation to extend the margin to column 100, and again to extend the margin to column 120. Then position the cursor at column 110 and choose Place.


Visually Adjusting a Form

You use the VisuallyAdjust operation on the Form Attributes frame with pop-up display-style forms only. You can:

- Preview the way a pop-up form looks in the window.
- Expand or shrink the size of a pop-up form by moving the cursor.
- Move a fixed-position pop-up to a place you designate with the cursor.

If you want, you can use this operation to change the size of a fullscreen form by changing its style to a pop-up first. You can then use the VisuallyAdjust operation to alter the form's size. When done, change the form's style back to fullscreen.

When you choose the VisuallyAdjust operation, VIFRED displays the Visual Adjust frame.



The operations on the Visual Adjust frame vary according to whether the popup style form is fixed-position or floating:

- **Fixed-Position** When displayed for a fixed-position pop-up style form, such as the one shown in the above figure, the Visual Adjust frame includes the Move operation, and the pop-up form is positioned at its specified window location.
- **Floating** When displayed for a floating pop-up style form, the Visual Adjust frame does *not* include the Move operation (because the floating pop-up has no fixed position), and VIFRED positions the pop-up style form in the center of the window.

These operations are summarized in the following table:

Operation	Description	
Resize	Use anchor point and cursor to expand or contract the outer margins of the form.	
Move	Applies to fixed-position pop-up style forms only. Moves the upper left corner of the pop-up form to the cursor location, using the Place operation on the Move submenu (same as the Move submenu on the Form Layout frame).	
Help, End	Standard operations.	

Adjusting Pop-up Form Size

You can use the Resize operation on the Visually Adjust frame to change the size of a pop-up style form. Using the Resize operation is easier if the form has a border, because the pop-up form margins are not displayed during the VisuallyAdjust operation. You can specify a border for the form on the Form Attributes frame, and then remove it after adjusting the size.

You can move the cursor in any direction to adjust the size of a form.

To change the size of a pop-up style form:

- 1. Choose the VisuallyAdjust operation on the Form Attributes frame. Choose the Resize operation on the Visual Adjust frame. VIFRED marks one of the form corners with a plus sign. This is the anchor point. The cursor automatically shifts to the diagonal corner.
- 2. Move the cursor to a new location and then press the Menu key. VIFRED redraws the form boundaries using the anchor point and the cursor's new location as the diagonal corners of the form.
 - If necessary, you can rotate the anchor point and cursor to different corners of the form so as to change the orientation of your modifications.
- To shift the anchor point, press the Tab key. Each time you press the Tab key, the anchor point and cursor rotate clockwise to a new corner of the form. By shifting the cursor and anchor point to new corners, you can expand or contract the form in any direction, provided you maintain the basic orientation of the cursor to the anchor point. VisuallyAdjust does not allow you to invert the form by moving the cursor to the opposite side of the anchor point.
- 4. When you have adjusted the form to the correct size, press the Menu key to return to the Visual Adjust frame menu.
- 5. Choose the End operation to return to the Form Attributes frame. VIFRED shows the form's new margins as dashed lines. These are the margins of the form's usable area, not counting any form border.

When you are adjusting a pop-up form's size, the form's margins must enclose all of the form's components without truncating any of them. If you attempt to reduce a form's margins in such a way that a form component would be partially or entirely outside of the form margin, VIFRED draws the new margin as close to the component as possible while still keeping the component entirely within the boundary. If VIFRED does not let you make a form as small as you want because a component is in the way, you must use the Form Layout frame's Move operation to move the form's components closer together. Then, return to the Form Attributes frame and finish adjusting the form's size.

Moving a Fixed-Position Pop-up Style Form

To reposition a fixed-position pop-up style form:

- Choose the VisuallyAdjust operation from the Form Attributes frame to display the Visual Adjust frame.
- 2. Choose the Move operation. This highlights the four corners of the form and places the cursor at the upper left corner.
- 3. Move the cursor to the spot where you want to locate the new form's upper left corner.
- 4. Choose the Place operation to redraw the form in the new location.
- 5. Return to the Form Attributes frame by choosing the End operation. The form's new row and column location are displayed in the StartRow and StartColumn fields.


Saving Forms

The Save operation on the Form Layout frame and other VIFRED editing frames instructs VIFRED to save a form you created or modified with VIFRED.

The Save operation is independent of exiting VIFRED. You can save a form and begin editing the same form or a different form without having to exit and reenter VIFRED.

To save a new form:

1. Choose Save on the Form Layout frame. VIFRED displays the Save frame.



The following table details each of the operations available the Save frame:

Operation Description		
Save	Saves the form under the specified name with optional Short and Long Remarks.	
Cancel Cancels the Save operation.		
Help, End	Standard operations.	

- 2. To save the form, enter a form name (up to 32 characters) in the space in the main window of the Save frame. The first character must be a letter or an underscore; case is not significant.
- 3. After entering the form's name, choose the Save operation on the Save frame.

You can save the same form under different names. Each time you save a form under a different name, VIFRED creates a copy of that form and retains the original form as it was before you began to edit it. You can then edit the different copies. However, if you enter a name that is already in use, VIFRED asks for confirmation before overwriting the old form.

VIFRED stores forms in the system catalogs. VIFRED and other programs can recall forms from the data dictionary for later use.

When you save the form, VIFRED creates a QBFName linking the form to its underlying table or JoinDef. The QBFName is the same as the name you give the form. Thus the form, in its default state or as modified by you, is available as a query target in QBF. You can assign several different QBFNames to the same form and use it with different tables or JoinDefs. For more information on QBFNames, see QBFNames Operation.

You can use the default QBFName for a default form to perform QBF queries on the table or JoinDef without additional programming.

Save Submenu

Once a form has been saved the first time, choosing the Save operation on the Form Layout frame displays a submenu rather than the Save frame. Choose one of the operations listed in the following table:

Operation	Description
EditInfo	Displays the Save frame so you can change the form's name or Short or Long Remarks before saving the form again.
Save	Saves the form under its current name with current Short and Long Remarks.
Cancel	Cancels the Save operation.
Help	Standard operation.

Save Changes Pop-up

If you try to end or quit without saving a new or changed form, VIFRED displays a pop-up form like the one shown in the following figure.



Select Yes to save the new or changed form or No to end or quit without saving the changes.

Destroying Forms

You can only destroy (delete) forms that you own.

To destroy a form from within VIFRED:

- 1. In the VIFRED Forms Catalog frame, position the cursor on the name of the form you want to delete.
- Choose the Destroy operation and enter y when VIFRED prompts you for confirmation.

You can also use the delobj command on the operating system command line to delete a form or other objects.

Editing Existing Forms

The Edit operation on the VIFRED Forms Catalog frame allows you to modify an existing VIFRED form. The Edit operation on the Form Layout frame allows you to edit the individual components, such as trim or field attributes, of the form displayed in the Form Layout frame.

To edit an existing form:

- 1. In the VIFRED Forms Catalog frame, place the cursor on the name of the form you want to edit.
- 2. Choose the Edit operation.

VIFRED displays the form to edit in the Form Layout frame. The operations available on this frame are summarized in a table in The Form Layout Frame. The table includes references to where the operation is discussed in this guide in more detail.

Renaming Forms

You rename forms in the VIFRED Forms Catalog frame. You can only rename forms that you own.

To rename a form:

- 1. In the VIFRED Forms Catalog frame, place the cursor on the name of the form you want to rename.
- 2. Choose the Rename operation.
- 3. Enter the new name for the form when VIFRED prompts you for it.

Compiling Forms

The Compile operation on the Utilities submenu generates a form definition for use with embedded SQL or other embedded query languages. Alternatively, you can use the compform system-level command to compile a form.

The Compile operation reduces start-up time when you use the form in an embedded SQL program. Consult the appropriate embedded language guide for more information.

To use the Compile operation:

- 1. In the Forms Catalog frame, place the cursor on the name of the form to be compiled and choose the Utilities operation.
- 2. Choose the Compile operation from the Utilities submenu.
 - VIFRED prompts you for a file name under which to store the compiled form in your current directory.
- 3. Enter the file name and press Return.

VMS

This procedure results in a C language data structure describing the form, stored in the file under the name you provide.

For VMS this produces VMS macro code.

Printing Forms

You can print a form by using the Print operation on the Utilities submenu, or the printscreen or printform commands at the operating system prompt.

The Print operation creates a picture of the form, which you can then print on a line printer. Follow these steps to perform the print operation:

- 1. Place the cursor on the row containing the name of the form in the Form Catalog frame and choose the Utilities operation.
- 2. Choose the Print operation from the Utilities submenu.
- At the prompt, type the name of a file.
 VIFRED then places a picture of the form in that file, and appends a description of each field and the trim to the form.
- 4. Use your operating system print commands to print the file.

The Print operation prints all fields, including those that have been assigned the Invisible field attribute.

The FRS printscreen command sends a copy of the form currently displayed (including any character representation of data in the form) to a file or printer, depending on how the II_PRINTSCREEN_FILE environment variable/logical has been set. (For more information, see the *System Administrator Guide* for the system on which your database resides). Because the FRS printscreen command prints the current screen display, it does not print fields which have been assigned the Invisible attribute.

The printform command lets you print a form without entering VIFRED. It works like the Print operation on the Utilities submenu.

QBFNames Operation

A QBFName is a special identifier that links a customized VIFRED data display or entry form with a particular database table or JoinDef. Choosing a QBFName as a query target in QBF allows you to automatically display and use the customized form when accessing its associated table or JoinDef.

When you use VIFRED to create a new form based on a database table or JoinDef, VIFRED automatically assigns a default QBFName to the new form that associates it with this table or JoinDef. The default QBFName is the same as the name of the form. Using the QBFNames operation on the Utilities submenu, you can change this default to another name, if you want. You can also create additional QBFNames for this same form that link it to additional tables and JoinDefs for use in QBF. This process does not create additional *copies* of the form, but rather allows you to use *one form* with many similar tables and JoinDefs through use of its various QBFNames.


If you archive a table containing outdated information and create a new table to use instead, you can continue to use the VIFRED form created for the old table by linking it to the new table through a different QBFName. For example, suppose a form called taskform was given the QBFName taskform1 when it was assigned to the Tasks table. You can now give it the new QBFName taskform2 when you assign it to the Newtasks table.

A single table or JoinDef can be associated with many different forms through the use of QBFNames. For example, if you are using the same table or JoinDef for more than one application, you must create a separate form in each application that differs from the others in the way the fields are displayed and arranged, the assignment of mandatory fields, and the instructions displayed in the window. VIFRED assigns a different QBFName to each separate form and links it to the common table or JoinDef.

QBFNames Catalog Frame

The QBFNames operation applies only to the form that is currently highlighted by the cursor in the VIFRED Forms Catalog frame. To display the QBFNames Catalog for a particular form, choose the QBFNames operation after choosing Utilities on the Forms Catalog frame.

The QBFNames Catalog frame contains a list of QBFNames associated with the form identified at the top of the frame.



You can use the operations available in this window to manipulate QBFNames on the list.

Operation	Description Assigns an additional QBFName to the selected form.			
Create				
Destroy	Removes the QBFName in the row containing the cursor.			
Edit	Edits the QBFName in the row containing the cursor.			
Rename	Renames the QBFName selected by the cursor.			
MoreInfo	Obtains more information about the selected QBFName. The additional information includes the time the QBFName was created and a long description of the QBFName.			
Go	Runs QBF using the QBFName.			
Help, End	Standard operations.			

Assigning Additional QBFNames to Forms

To assign additional QBFNames to a form, follow these steps:

- 1. Choose Create from the QBFNames menu. VIFRED prompts for the new name to use with QBF.
- 2. Enter a name between 1 and 32 characters long and press Return. The first character must be a letter or an underscore. VIFRED displays a new menu.
- 3. Choose Table to link the form to a table, or JoinDef to link the form to a JoinDef. VIFRED prompts for the name of the table or JoinDef to which you want to link the form.

- 4. Type the name of the table or JoinDef and press Return. You can optionally enter a table as schema.tablename. If you omit the schema name, VIFRED assumes the owner is the same as the current user ID.
 - VIFRED displays the QBFName Save frame.
- 5. Fill out the frame with information about the new QBFName and then choose the Save operation. The new QBFName appears in the table of QBFNames.

Running QBF from VIFRED

You can test default forms by running QBF from within VIFRED. To run QBF from within VIFRED:

- On the VIFRED Forms Catalog frame, place the cursor on the name of the form that you want to use as a QBF query target.
- Choose the Go operation.

VIFRED checks to see if a QBFName with the same name as the form exists. If one already exists, it starts QBF using that QBFName as the query target.

If VIFRED does not find a QBFName, it prompts you for the name of a table. Enter the table name and press Return to start QBF. If you press the Return key without entering a table name, VIFRED cancels the operation.

When you exit QBF you automatically return to VIFRED.

Exiting VIFRED

The Quit operation exits the VIFRED. If you started VIFRED from the Ingres Menu, you return there automatically. If you started VIFRED from the operating system, you return to the operating system prompt.

You can select the Quit operation from the Form Layout frame or from the Forms Catalog frame.

If you are in the Form Layout frame, the Quit operation does not automatically save the work done in VIFRED. If you have made any changes to the form since the last save, VIFRED displays a pop-up form asking you if you want to save the changes. Select Yes to save the changes or No to exit without saving the changes.

If you are in the VIFRED Forms Catalog frame, enter Quit or End (which exits the current frame) to exit VIFRED immediately.

Chapter 14: VIFRED Form Components

This chapter describes the parts of a form and how to use the VIFRED Form Layout frame operations to:

- Create and edit trim, boxes, and lines
- Create and edit simple fields and table fields
- Delete form components
- Change the tabbing order of fields on the form
- Move form components

Parts of a Form

VIFRED forms have two basic components:

- Fields—Used for entering or displaying data.
- *Trim*—Everything on the form other than fields. Trim can include instructions, general information, and lines or other decoration. Trim plays no direct part in data entry or manipulation.

Fields

A field is a space for data entry or display on a form. It usually corresponds to a column in a database table, but also can be used for other purposes in an application, such as displaying instructions or the results of computations, or for entry of user names and passwords.

There are two kinds of fields:

- Simple fields—In which data is displayed one item at a time.
- Table fields—In which multiple rows and columns of data are displayed simultaneously.

If you create a form for a table, you choose one of these formats. On forms associated with JoinDefs, the JoinDef specification determines which data is displayed in simple fields and which is displayed in table fields.

Both simple fields and table fields consist of an internal name, data window, attributes, and an optional title, as described in the following sections.

Internal Name

The internal name of a field is the name by which VIFRED identifies the field. This does not have to be the same as the field's title that users see on the form. The internal name of the field identifies the field to application procedures written in a programming language or created with Vision or Applications-By-Forms. The application code uses the field's internal name to move values to and from the field.

Data Window

The data window is the space in a field where data is entered or displayed. The display format of the data window controls how the data appears when displayed on the form. For a data entry field, you can specify a data input template as the display format to control the way in which the user enters data in that field. If a field corresponds to a data column in a table, the display format for that field must be appropriate for the data type and length declared for the column in the database table. While data type and data display format are related, they are distinct and different entities. *Data type* identifies the kind of data. *Display format* refers to how the data is presented or entered on a form.

A single data type can have many different display formats, and some display formats can be applied to more than one type of data. For example, numeric type data can be displayed as whole integers, decimal numbers, and in scientific notation. The scientific notation display format can be used with both numeric and monetary data types.

Attributes

Attributes are screen effects such as color, blinking, underlining, and uppercase and lowercase changes, as well as other information about each field.

Title

The field's title, which is optional, is the name of the field that appears on the form. The title provides a short description of the data that appears in the field's corresponding data window. A field's title can be different from its internal field name.

On a default form created by VIFRED from a table or JoinDef, VIFRED initially creates a field title that is similar to the field's internal name, with these exceptions: VIFRED capitalizes the first letter of every word in the title, removes any underscores to create multiple words, and adds a colon (:) at the end of the field title. You can change the field's title if you want.

Using Operations on the Form Layout Frame

You create, edit, or otherwise manipulate the individual components of a form from within the Form Layout frame. The chapter "Using VIFRED" provides an example of the Form Layout frame and discusses the frame in detail, including:

- Use of form alignment guides
- Use of the FormAttr operation for making changes to the form as a whole

The following table summarizes the operations on the Form Layout frame that you use for creating and manipulating individual form components:

Operation	Description
Create	Displays a new menu that enables you to create new components on a form.
Delete	Deletes the component where the cursor is positioned.
Edit	Displays another menu that enables you to edit the trim or field component where the cursor is positioned.
Move	Moves a component on a form. This operation displays a new menu. You can also use this operation to move a form's margins.
Undo	Reverses the results of the last operation you performed. Undo does not reverse changes made with the EditAttr, FormAttr, or GroupMove operations on the Table Field frame.
Order	Changes the order in which the form's fields are accessed when an end user presses the Tab key. This operation displays a new frame.
Save	Displays a new menu that allows you to save your new or updated form in the database. The Save operation is independent of exiting. You can save one form and begin work on another without leaving VIFRED. For more information, see Saving Forms .
FormAttr	Available only for making changes to the form as a whole.
Location	Displays a message giving the current row and column position of the cursor, relative to your window boundaries, and marks the cursor location with a plus sign (+).
GroupMove	Moves an entire group of components on a form at once.
Rulers	Turns rulers and straight edges on or off.
Help, End, Quit	These are standard operations.

For detailed instructions on using these operations to manipulate the contents of forms, see the sections that follow.

Create Operation

Choosing the Create operation while you are in the Form Layout frame displays another menu with the following choices:

Operation	Description
Trim	Creates a new trim element.
Field	Creates a simple field.
TableField	Creates a table field.
NewLine	Inserts a blank line.
Box/Line	Creates a box/line feature at the cursor's location.
DuplicateField	Creates a field based on an existing field in the current form or in another form in the database.
Help, End	These are standard operations.

The following sections discuss each of these operations in detail.

Creating and Editing Trim

With the exception of boxes, each trim element is contained in a single line, which is treated as a single unit of trim. For multi-line trim elements, use the Create and Trim operations for each separate line of trim you want to create.

After creating trim, you can change the way it displays in the window by giving it attributes. For instance, you can make it blink, display in reverse video, or heighten its brightness. For instructions, see Specifying Display Attributes for Trim.

Creating Trim

To create new lines of trim:

- Position the cursor where you want a new trim element to be inserted.
- ◆ Choose the Create operation on the Form Layout frame. The original cursor location appears in your window with a flashing plus sign (+).
- Now choose the Trim operation from the Create submenu.

- VIFRED displays the message:
 - Enter trim (press <MENU KEY> when done)
- Type the desired trim. Use text or any other printable character.
- The trim begins at the cursor position and continues as far as you type, up to the right margin of the form. If you need to extend the right margin, use the Move operation on the Form Layout frame.
- Press the Menu key to complete the operation.

Editing Trim

To edit the text of trim:

- 1. Position the cursor on the trim element you want to modify.
- 2. Choose the Edit operation on the Form Layout frame
- 3. Choose the Trim operation on the Create submenu.
- 4. Enter your corrections.

When you choose the Edit Trim operation, you enter overstrike mode. In this mode, the characters you type replace the existing character (if any) at the cursor position.


You can switch to insert mode by pressing the Mode key as defined for your keyboard. In insert mode, characters entered at the cursor position push existing characters to the right. Pressing the Mode key toggles you back and forth between insert and overstrike mode.

When you are finished editing the trim element, press the Menu key to return to the original menu.

Specifying Display Attributes for Trim

To specify display attributes for trim:

- 1. Position the cursor on the trim you want to modify.
- 2. Choose the Edit operation on the Form Layout frame.
- Choose the Attributes operation from the Edit submenu. VIFRED displays the Attributes for Trim frame.



You can set most of the following attributes for boxes and lines, as well as for trim, unless otherwise noted:

Attribute	Description
Reverse Video	Reverses screen contrast from bright characters on dark background to the opposite, or vice versa.
Blinking	Makes the trim, box, or line blink on and off.
Underline	Underlines the selected trim (not for boxes or lines).
Brightness Change	Toggles the brightness for the trim, box, or line.
Color	Specifies the color of the trim, box, or line.

Except for color, these attributes are either on or off, as indicated by y or n in the column labeled Set. The default condition is n (off).

- 4. To change an attribute in the Set list, position the cursor on the line for that attribute and type y (yes) or n (no).
- 5. If you have a color display, type the appropriate color code in the Color field.

Color capabilities vary widely among monitors and can be customized by changing the color specifications in the termcap file entry for your TERM_INGRES setting. Check the appropriate termcap file entry or your monitor documentation for color code assignment information.

6. Select End to return to the Form Layout frame.

Creating New Blank Lines on the Form

You can add new blank lines to your form to make room for additional components or to improve the form's appearance. To insert new blank lines in your form, use the Create NewLine operation.

This operation inserts new lines at the cursor location. When you create a new line, you push all components on lines below the cursor position down one line. This can have the effect of expanding the bottom margin of the form.

New blank lines are created on the Form Layout frame. To create a new line:

- 1. Place the cursor at the location on the form where you want the new blank line inserted. You cannot create a new line if the cursor is positioned inside a multi-line field.
- 2. Select the Create operation.
- 3. Select the NewLine operation. This inserts a new line at the cursor location and pushes all components below the new line down by one line.

Creating and Editing Boxes and Lines

You can draw boxes and lines on your form for informational and aesthetic purposes. You can use boxes and lines to visually group form components, to provide borders for both normal and pop-up style forms, and to add color and graphic design elements.

You draw boxes and lines with the Create Box/Line operation. Vertical lines are actually boxes that have a vertical length of any amount and a horizontal width of only one column. Horizontal lines are boxes that have a horizontal width of any amount and a vertical length of only one column.

While you can also draw horizontal lines on your form with the Create Trim operation using keyboard keys such as the underscore character or dash, the effect is different than that achieved by using the Box/Line operation. The Box/Line operation allows you to set line attributes (described in Enhancing Boxes and Lines) and also allows you to correctly create intersecting lines. Boxes and lines have the following characteristics:

- Boxes can be of any size up to the size of your form.
- Boxes and lines are the only trim components that can occupy more than one line on your form.
- Boxes can enclose other form components.
- Boxes can be nested within each other and overlap each other.

If a box line intersects some other form component, the other component overwrites that portion of the box or line that it overlaps. It appears as if the component is lying on top of part of the box. The form is not harmed by having a component overlap part of a box line.

Box/Line Operation or Attribute Boxes

The Simple Fields Attributes operation allows you to automatically place a box around a simple field. Similarly, the FormAttr operation allows you to automatically place a box around a pop-up style form. These automatic box operations have no connection to creating a box with the Create Box/Line operation.

You can use the Create Box/Line operation instead of the automatic operations to place boxes around simple fields or pop-up style forms if you want. By using the Box/Line operation, you are able to specify the display attributes of the box; the automatic operations do not have that capability.

You can also use the Create Box/Line operation to place a box around a field that has been automatically enclosed by a box already, or to place a box immediately inside the border of a pop-up style form. In this case the field or form would then be displayed with two boxes, one nested within the other.

Creating a Box or Line

To create a box or line:

- 1. Place the cursor where you want one of the corners of the box to be.
- 2. Choose the Create operation. The original cursor location that marks one corner of the box is displayed with a flashing plus sign (+).
- 3. Now choose the Box/Line operation, and the following message displays:

 Move cursor to position the opposite
 corner (press <MENU KEY> when done)
 - The NewLine operation inserts a new blank line into the form at the cursor location. To create a visible line, choose the Box/Line operation.
- 4. Move the cursor to where you want the diagonally opposite corner of the box to be. For example, if the plus sign marks the upper left corner of the box, move the cursor to where you want the lower right corner to be. The locations of other form components do not matter, with one exception. If you position the diagonal corner so that part of the box's line passes through another component, that portion of the box line is hidden behind the other component.

To form a vertical line, place the cursor directly above or below the original cursor mark. This creates a box that has vertical length and a horizontal width of 1. To create a horizontal line, place the cursor to the right or left of the original cursor mark. This creates a box that has horizontal width and a vertical height of 1.

Now press the Menu key. Lines connecting the two corners of the box appear on your form.

To set display attributes of the box, or to change its size, see the following section.

To move a box or line, use the Move operation, described in Moving Components on a Form. To delete a box or line, use the Delete operation, as described in Deleting Form Components.

Enhancing Boxes and Lines

Use the Edit operation to change the size and shape of a box or line, or to specify display attributes.

To edit a box or line:

1. Place the cursor anywhere on the box or line. The cursor must be on one of the lines that forms the box, not inside the box.

On terminals that use an underscore character as a cursor, you cannot get the cursor exactly on a horizontal line or horizontal side of a box because the line is drawn in the center of that row's character cell and the underscore is at the bottom of the cell. In this case, make sure that the cursor is in the same character cell (that is, the proper row).

Place the cursor at a point on the box or line that is unique to that box or line to clearly indicate which component you want to change. For example, if you place the cursor at the point where two boxes intersect, the Edit operation cannot tell which box you must change, and arbitrarily chooses one.

2. Choose the Edit operation. The four corners of the box (at each end of a line) display in reverse video and the Edit menu for boxes displays the following choices:

Operation	Description
Resize	Expands or contracts one or more sides of the box, or horizontal or vertical line.
Attributes	Specifies display attributes for the box, or horizontal or vertical line.
Help, End	These are standard operations.

Resizing a Box or Line

To change the size of a box:

- 1. Choose the Resize operation on the Edit submenu.
 - The upper left corner is marked with a flashing plus sign (+). This is the anchor point. The cursor automatically shifts to the diagonally opposite corner.
- Move the cursor to a new location. You can move the cursor in any direction.
- 3. Press the Menu key to redraw the box, using the anchor point and the cursor's new location as the diagonally opposite corners of the box.
- 4. When finished resizing the box, press the End key to return to the Form Layout frame.
- 5. To save your changes, choose the Save operation.

There are no restrictions on where you can move the cursor in the form. For example, you can flip a box by moving the cursor from the lower right corner (relative to the anchor point) to a new position above and left of the anchor point.

By rotating the anchor point to a different corner of the box you can change the orientation of your changes. To shift the anchor point, press the Tab key. Each time you press Tab, the anchor point and cursor rotate clockwise to a new corner of the box. By shifting the cursor and anchor point to new corners, you can expand or contract the box in any direction.

Specifying Display Attributes for Boxes and Lines

You specify display attributes for a box or line the same way you do for trim:

- 1. Position the cursor on the box or line you want to modify.
- 2. Choose the Edit operation from the Form Layout frame.
- Choose the Attributes operation from the Edit submenu. VIFRED displays the Attributes for Box/Line frame, with the same choices as on the Attributes for Trim frame.

For details, see Specifying Display Attributes for Trim.

When boxes with different display attributes overlap each other, the most recently created attribute overwrites the older attribute at the intersection.

Creating and Editing Simple Fields

If you are working with a default form, VIFRED automatically places a field on the form for every data column in the associated table or JoinDef and creates the appropriate link between the field and its data column. If you prefer to create your own simple fields, you can do so with the Create Field operation. However, the only way you can link such a user-created field to a data column in a table is to write application code that links the field's internal name to a data column in the table. If you are not familiar with this type of programming, we recommend that you work with default forms created from JoinDefs or tables, rather than creating your own fields.

Creating a New Simple Field

To create a simple field, you must create the following components:

- Internal name of the field
- Display or input format of the field
- Attributes of the field (or leave them in their default state)
- Optional field title

If you create a field title, VIFRED automatically creates a default internal name for the field. If you do not create a field title, you can use the Attributes operation to create an internal field name.

For more information on internal field names, see Parts of a Form and Creating Field Titles and Default Internal Names.

To create a simple field on a form, follow these steps:

- 1. Position the cursor where you want to insert a new field.
- 2. Choose Create from the Form Layout frame and then choose Field from the Create submenu.

VIFRED displays another menu with the following operations:

Operation	Description
Title	Creates a title for the field (optional).
DisplayFormat	Creates the data window and data display or input format for the field.
Attributes	Sets the attributes of the field.
Cancel	Cancels field creation and returns to the Form Layout frame.
Help, End	These are standard operations.

- 3. On the Field submenu, choose Title (if you are creating a field title), DisplayFormat, and Attributes in sequence to create the field's components.
 - For specific instructions, see the following sections.
- 4. After creating the field's optional title, display or input format, and attributes, select End to complete the creation of a field.
 - VIFRED displays the field on the form with the specified components.
- 5. Use the Save operation to permanently keep a form definition. If you exit without saving the form, all your changes are lost. For more information, see <u>Saving Forms</u>.

Creating Field Titles and Default Internal Names

When you create a title for a simple field, VIFRED automatically creates an internal name for the field. The *field title* on the form has no significance other than display. The *internal field name* is the code name for the field that you use when writing application code in a programming language or with Applications-By-Forms or Vision to manipulate the form. For more information on internal field names, see <u>Parts of a Form</u>.

If you do not want to create a field title, you can use the Attributes operation to create only an internal name for a field, as described in Creating Your Own Internal Field Names.

The title and internal name of a field are initially similar (up to the legal limits of internal names), but can be changed separately. This enables you to change the name of the field on a form without changing its underlying internal name or the application code that controls activity in the field. It is common practice in VIFRED to change a form's field titles, but not its internal field names. If you need to do so, you can change the internal name with the Attributes operation as described in Creating Your Own Internal Field Names or in the chapter "VIFRED Field Specifications."

To create a title and default internal name for a new simple field:

- 1. Choose Create on the Form Layout frame; then choose Field on the Create submenu.
- 2. Place the cursor where you want the first character of the field's title to appear on the form.
- Choose the Title operation. VIFRED displays the message: Enter title (press <MENU KEY> when done)
- 4. Enter the title, and press the Menu key to return to the previous menu.

This creates a field title, which is displayed on the form, and a field internal name (with non-legal characters automatically removed) that is not visible on the form.

Creating Your Own Internal Field Names

You must not attempt to create your own internal field name unless you are a programmer familiar with the ramifications of doing so. An alternative would be to create a field title with the Title operation and let VIFRED create a default internal field name for you. For more information, see Creating Field Titles and Default Internal Names.

To create your own internal field name, you use the Attributes operation, as follows:

- 1. Choose the Attributes operation on the Create Field submenu of the Form Layout frame. The Attributes for Field frame appears.
- 2. Enter the internal name in the Internal Name field.

The name you enter must comply with VIFRED naming conventions. For more information, see Naming and Name Use Conventions.

Creating Data Windows and Display Formats

The data window is the part of the field where data is displayed or entered. For a more detailed explanation, see Parts of a Form.

To create a data window when creating a new field:

- 1. Position the cursor at the point on the form in the Form Layout frame where you want the new window to be.
- 2. Choose the DisplayFormat operation on the Create Field submenu. VIFRED displays the message:
 - Enter format (press < MENU KEY > when done)
- Enter a display or input format. For example, type in c10 to create a character field that can display a maximum of 10 characters, or type in a format template. For more information, see the discussion following this procedure.
- 4. When done, press the Menu key.

If the field is to correspond to a data column in a table, make sure that the data window display format you specify is appropriate for the data type and length declared for that column when the table was created.

Note: You cannot create a field with a display format that can display data from a column of long varchar, byte, byte varying, and long byte data types. If the field is to be a data entry field, you can specify a data input template for the display format. The data input template indicates to the user how the data must be entered and causes VIFRED to check the input, character by character, to see if it matches the template. If the user's entry does not match the template format, VIFRED disallows the entry, and requires the user to either re-enter the character in that position or re-enter the data from the beginning of the field, depending on the particular input template. For more information, see Input Masking in Data Entry Fields.

The following table gives some simple examples of data display and input formats. Keep in mind that some of the display format symbols are the same as data type symbols, yet they perform very different functions.

Display	Description
i8	Numeric data, whole numbers only. Up to 8 digits can be entered or displayed.
f10.2	Numeric data with decimal numbers. Field can display 10 characters including the decimal point, with two places shown to the right of the decimal point.
c10	Character data. Field is 10 characters wide.
s'aa\-zzzzzz'	Data input template for a part number, where a indicates an alphabetic character, z represents a numeric character, and \- is a dereferenced hyphen (-).

Input Masking in Data Entry Fields

VIFRED provides optional input masking for data entry fields. Input masking allows VIFRED to check a user's entry, character by character as it is being entered, against a specified data input format template. If any character does not match the template requirements, VIFRED beeps and does not put that character into the field. The user must type a valid character to continue.

To specify input masking, you need to use one of the following format templates:

- Absolute date and time templates
- Numeric templates
- String templates

You must also ensure that input masking has been turned on for that field. Do this by setting the Input Masking attribute to y (yes) in the Attributes for Field frame. Turning on input masking affects how the field interacts with the user when the application is executing and the kind of data the user can enter. If input masking is off, VIFRED uses the template to check a user's entry only upon exiting the field. Turning on input masking has no effect on fields that do not contain input templates.

Creating Multi-line Character Fields

You can create character fields that contain more than one line. When you enter data or display it in a multi-line field, it wraps around to the next line each time a line is filled.

To specify a multi-line character field, enter the display format as follows:

- The letter c for character data
- The total number of characters that can be entered in the field, followed by a period (.)
- The maximum number of characters that can be entered on any given line

VIFRED automatically figures the number of lines needed to meet your specification. For example, the display format, c100.20, creates a field of five lines, each of which are 20 characters long.

When creating display-only fields, you can use the following parameters with the c format to specify different types of justification:

- The f parameter wraps text to the next line without breaking the line in the middle of a word (it breaks between words instead). For example, cf100.25 creates a field of four 25-character lines with text wrapped to the next line, with breaks between words.
- The j parameter right justifies text. For example, cj100.25 creates a field of four 25-character lines with spaces entered between the words to right justify each line.

When used with either the cf or cj format, the e parameter preserves trailing blanks in multi-line fields; for example, cje100.25 is the same as cj100.25, except that trailing spaces are preserved.

Note: The f and j parameters are primarily intended for use with display-only fields. If you use them for data entry fields, VIFRED justifies the text only after the user exits the field. Therefore, spaces between words are lost or added after the user has finished typing the entry and exits the field, which can cause some text to be truncated.

Specifying Simple Field Attributes

Attributes control the features of a field, such as:

- How the field looks on the form
- How, and if, data must be entered in the field
- Default values
- Whether data shown in the field can be changed
- Validation checks for new data
- Field scrolling
- Internal field name

While creating a new simple field, specify field attributes by choosing the Attributes operation on the Create Field submenu of the Form Layout frame. You can also specify attributes for a simple field at a later time by placing the cursor in the field and choosing the Edit operation on the Form Layout frame, followed by the Attributes operation on the Edit submenu. VIFRED then displays the Attributes menu.

For instructions on setting the Name attribute for a new field's internal name, see <u>Creating Your Own Internal Field Names</u>. For more information on changing an existing internal field name or specifying other field attributes, see <u>Specifying Field Attributes</u>.

Editing Simple Fields

To edit a simple field from within the VIFRED Layout frame, position the cursor on the field you want to edit and choose the Edit operation. The menu contains the following choices, corresponding to the elements of the field:

Operation	Description
Title	Changes the title of the field
DisplayFormat	Changes the data window and data display or input format of the field
Attributes	Sets or changes the attributes of the field
Help, End	These are standard operations

Editing Field Titles

If you choose Title while editing a simple field, the cursor moves to the first character of the title. Type the new title over the existing text in the window.

By default, you are in overstrike mode so that the characters you type replace the characters at the cursor position. To insert characters without overstriking, press the key defined as the Mode key on your keyboard to change to insert mode.

When in insert mode, move the cursor with an arrow key to where you want to insert characters, and type the insertions. Increasing the width of a component shifts existing components to the right.

Editing the Data Window

Basic data window display formats are indicated on a form by a single letter followed by underscore (_) characters showing the width of the field. The data window of each field on a form begins with the first letter of the display format, as follows:

- **c** = character format
- **d** = date template
- **f** = floating-point format
- **g** = floating-point format
- **n** = floating-point format
- i = integer format
- **e** = scientific notation format

The underscore line following these letters represents the number of characters allowed in the field. For example, c_____ denotes a character display type that is 10 characters wide. For long character fields, wraparound lines can be shown by multiple lines of underscoring.

For floating-point numbers, the underscores also indicate how many decimal places to display. For example, f____, denotes a floating-point display type with a maximum of four digits to the left of the decimal point and two digits to the right of the decimal point.

For date, numeric, and string input templates, the entire template appears in the field.

To edit the data display format in the data window:

1. Place the cursor on the field and choose the Edit operation; then, choose the DisplayFormat operation.

Any single-letter display format identifier changes to the more specific letter-number-parameter display format identifier. For example, if the cursor is on a field shown as c_{-----} , the display format identifier can change to $+c10_{----}$.

- 2. Type the new format over the existing format. For example, to change a display format from 10 alphanumeric characters to 15, type c15 over c10.
- 3. When you are finished, press the Menu key.

If you change a field's data display format to a type that is not compatible with the field's data type, VIFRED automatically changes the field's data type to match the display format. This can create problems if you use the field to access data in tables. If you do not also change the data type of the underlying table, a mismatch results between the field data type and the table data type.

Editing the Attributes of a Field

To view or change attributes in one field on an existing form:

- 1. Position the cursor on the field and choose the Edit operation.
- 2. Choose Attributes. VIFRED displays the Attribute menu.

For more information on attributes, see **Specifying Field Attributes**.

Creating and Editing Table Fields

You can create a table field on your form that contains:

- Default columns corresponding to the columns in an existing database table or tables
- Default columns that you modify
- Columns that you specify from scratch

To create a table field, start with the instructions in Creating a New Table Field, which follows. The remaining topics in this section include information on creating and editing the columns for the table field.


Creating a Table Field

To create a new table field on a form:

- 1. In the Form Layout frame, place the cursor where you want the upper left corner of the table field to be.
- 2. Choose the Location operation to mark the location of the cursor with a plus sign (+).

3. Choose the Create operation; then choose the TableField operation on the Create submenu.

VIFRED displays the Table Field frame.



You can enter the following information on the Table Field form:

Options	Description
Name of Table Field	The internal name of the table field.
Display Lines? (y/n)	Displays or suppresses lines between rows of the table field. The default is to display lines.
Number of Rows to Display	The number of rows to display in the table field. The default is 4.
Highlight Current Row? (y/n)	Displays or suppresses highlighting of current row when cursor is in a table field. The default is no highlighting.
Display Column Titles? (y/n)	Displays or suppresses appearance of column titles. The default is to display column titles.
Invisible Field? (y/n)	Prevents on-screen display of the entire table field. You cannot place the cursor in this field with the Tab or Return keys.
Title of a Column	The title of the column that the user sees when the form displays.
Column Internal Name	The internal name by which VIFRED identifies the column. By default, the internal name is the same as the column title (with non-legal characters removed).
Display Format	The display format for the column's data.

The following table summarizes the operations available on the Table Field frame. These operations are discussed in detail in the sections following this procedure.

Operation	Description
Insert	Inserts a new column into the table field.
Delete	Deletes an existing column from the table field.
EditAttr	Displays the Attribute menu of a specific column for viewing or changing attributes.
Move	Changes the order of columns in the table field.
GetTableDef	Retrieves the description of a table for use in defining table-field columns.
Cancel, Help, End	These are standard operations.

- 4. In the field, Name of Table Field, type a name of up to 32 characters. For more information, see Naming and Name Use Conventions.
- 5. In the field, Number of Rows to Display, type the number of rows that you want displayed in the new table field or press Tab to keep the default value of 4. A table field can display up to 99 rows.
- 6. In the Display Lines field, choose whether to display lines between the rows of the table field. Type n (no) if you do not want to display lines or press Tab to keep the default value of y. Displaying separation lines leaves less room for data rows.
- 7. In the Highlight Current Row field, choose whether to highlight the current row the cursor is on whenever the cursor is in the table field. The highlighted row moves with the cursor. This Highlight Current Row function is only available through VIFRED; it cannot be turned on and off dynamically from an application.
- 8. In the Display Column Titles field, choose whether to display column titles. Choosing n turns off the display of column titles. If you turn off the display of column titles, you can create column titles as trim and use the Box/Line capability to create lines on the form, or you can omit column titles on your form.
- 9. In the field, Invisible Field, choose whether you want to prevent the on-screen display of the entire table field. Invisibility applies to the entire table field. You cannot place the cursor on an invisible field with Tab or Return.
- 10. To create the columns in your table field, you can either use the GetTableDef operation to create default columns, or create your own columns, as follows:

- If you are creating a table field that corresponds to one or more tables in the database, you can choose the GetTableDef operation to create default columns based on the database tables, as discussed in Creating Default Table Field Columns with GetTableDef.
- When you have created the columns for your Table Field, use the Insert, Delete, EditAttr, and Move operations on the Table Field frame to edit them, as you want. For more information, see the discussions following this procedure.
- 11. When you finish entering specifications for the new table field:
 - Select the End operation to return to the Form Layout frame. Your new table field appears.
 - To cancel the creation of a new table field, choose the Cancel operation instead of the End operation.
- 12. Use the Save operation to permanently retain the form definition. If you exit without saving the form, all your changes are lost.

Creating Default Columns with GetTableDef

If the table field you are creating corresponds to an existing table or tables in the database, you can use the GetTableDef operation to create default columns. VIFRED automatically creates internal names and data display types that match the columns in the corresponding table or tables.

You can then use the default columns as is, or as a starting template, rather than individually entering column titles, display formats, and internal names on the Table Field form.

To use the GetTableDef operation:

- 1. Place the cursor in the table field on the Table Field frame.
- 2. From the Table Field frame, choose GetTableDef from the menu. VIFRED prompts you for a table name.
- 3. Enter the name of the table or tables, including the schema name, if appropriate.

To enter multiple table names, separate the names by a comma; for example, staff, managers, tasks. VIFRED lists all columns from each table in the table field in the order that they appear in the table, and in the order of table names that you specify.

The specifications for the table appear on the Table Field frame.

4. If you want to, edit the specifications with the Insert, Delete, EditAttr, and Move operations on the Table Field frame. For more information, see the discussions following this procedure.

Creating Columns

If you do not want to use the GetTableDef operation to create default columns for your table field, as explained in the previous discussion, you can create your own columns by entering an optional title and a mandatory internal name and display format for each column to be included in the table field.

The order in which you list columns in the Table Field frame is the order in which the columns appear across the form's table field from left to right when you are finished creating it. To change the order, see Changing the Sequence of Columns.

You must enter values for the Column Internal Name and Display Format columns on the Table Field frame. Titles of columns are optional.

To create your own columns for the table field:

- 1. If you want to enter an optional title, position the cursor at the first blank line in the Title of a Column section of the Table Field frame and type a title for the first column.
- Use the Tab key to move the cursor to Column Internal Name. If you leave this column blank, VIFRED uses the column title you entered in step 1 as the internal name (excluding non-legal characters). For more information on the distinction between the internal name and the field title, see <u>Parts</u> of a Form.
- Press Tab to move the cursor to Display Format. The display format
 controls how data is displayed or entered in the field. Specify the column
 display or input format by typing in the appropriate format code and
 optional parameters.
- 4. When done, press the Menu key.

If the field is to correspond to a data column in a table, the display format you specify must be appropriate for the data type and length declared for that column when the table was created. For more information on how display formats and data types are related, see Parts of a Form.

If the field is to be a data entry field, you can specify a data input template as the display format. The data input template indicates to the user how the data must be entered, and causes VIFRED to check the input, character by character as it is entered, to see if it matches the template. If the user's entry does not match the template format, VIFRED disallows the entry, and the user must either re-enter the character in that position or re-enter the data from the beginning of the field, depending on the particular input template. For more information, see <u>Input Masking in Data Entry Fields</u>.

The following table gives some simple examples of data display and input formats. Keep in mind that some of the display format symbols are the same as data type symbols, yet they perform very different functions.

Display	Description
i8	Numeric data, whole numbers only. Up to 8 digits can be entered or displayed.
f10.2	Numeric data with decimal numbers. Field can display 10 characters including the decimal point, with two places shown to the right of the decimal point.
c10	Character data. Field is 10 characters wide.
s'aa\-zzzzzz'	Data input template for a part number, where a indicates an alphabetic character, z represents a numeric character, and \- is a dereferenced hyphen (-).

Editing a Table Field

To edit a table field, position the cursor anywhere in the table field and choose the Edit operation. VIFRED displays the Table Field frame.

The operations on the Edit menu are the same as those in creating a table field. To edit a table field, type new information over the existing field contents. For specific information on the components of table fields, see the table, Table Field Form Options.

When you are finished editing the table field, select the End operation to return to the Form Layout frame. VIFRED displays the changed table field.

To cancel your changes, choose the Cancel operation. VIFRED returns you to the Form Layout frame without recording your changes. The only exception to this is if you have used the EditAttr operation to make changes in a table field. In this case, because VIFRED has already recorded the attribute changes, you must re-enter the original values and choose End to return to the Form Layout frame with the equivalent of the original table field displayed.

Adding Columns

There are two ways to add columns to a table field on the Table Field frame:

- Use the GetTableDef operation to append columns from a table; then use the Delete operation to remove any unwanted columns.
- Use the Insert operation to insert or append columns.

For more information on the GetTableDef operation, see <u>Creating Default Columns with GetTableDef</u>.

When you choose the Insert operation on the Table Field frame, VIFRED inserts a new row before the row on which the cursor is currently resting. VIFRED then fills this row with the following default column specifications:

- NEW1 for column title, c1 for display format
- new1 for column internal name

Type the new title, column internal name, and display format over these default values.

Additional rows added using Insert are given successively numbered titles and internal names. NEW1/new1 are followed by NEW2/new2, NEW3/new3, and so on.

New data columns created with the Insert operation are not linked to and do not affect the data columns in the underlying table.

You can only link new data columns on the VIFRED form to data columns in tables by writing application code in a programming language, or with Vision or Applications-By-Forms, that links the field's internal name to the database table column. If you are not familiar with this sort of programming, we recommend that you work with default forms created from JoinDefs or tables, or add columns with the GetTableDef operation. With these methods VIFRED automatically creates the appropriate links between field and data column.

Deleting Columns

To delete columns from a table field in the Table Field frame, position the cursor on the row for the column you want to delete and choose the Delete operation. VIFRED only removes the deleted column from the form, not from the database table.

Editing Column Titles and Internal Name

To edit column titles and internal names, position the cursor on the title or internal name in the table field on the Table Field frame. Then type over any current entries you want to change.

Changing a field's internal name affects data transfer to and from the field. We recommend that you change an internal field name only if you are an experienced programmer familiar with the ramifications of such a change.

Changing Column Attributes

You can change any column attribute for one column at a time. To change one column's attributes, follow these steps:

- 1. In the Table Field frame, position the cursor on the name of the column whose attributes you want to change.
- 2. Choose EditAttr. VIFRED displays the Attributes for Field frame.
- 3. Change the desired attributes. Display attributes for a table-field column apply to the entire column. For example, if you set the Blinking attribute, the entire column blinks. For more information, see Specifying Field Attributes.

VIFRED changes the attributes for the column immediately.

4. When finished specifying attributes, choose the End operation to return to the previous frame.

Once you have used the EditAttr operation, you cannot use the Cancel operation to cancel the changes, because VIFRED has already made them permanent. To change an attribute, choose the Edit operation on the Form Layout frame and repeat this procedure.

Changing the Sequence of Columns

You can change the sequence of columns in a table field by using the Move operation on the Table Field frame to change the order in which columns are listed in the form.

Follow these steps to change the sequence of columns in a table field:

- 1. In the Table Field frame, position the cursor on the row containing the specifications for the column you want to move.
- 2. Choose Move. A new menu appears.
- 3. Position the cursor to where you want to move the column specification. The column specification currently at that location is pushed down one row when the operation is completed.
- 4. Choose Place. VIFRED positions the column specification in the new location.

Creating Duplicate Fields

You can create a simple field or table field that is based on an existing field. The existing field can be from:

- The form being edited
- Another form in the database

To create a duplicate field:

- 1. On the Form Layout frame, place the cursor in the location where you want to create the duplicate field.
- 2. Select the Create operation from the Form Layout frame menu.

A blinking plus sign (+) appears where you want to create the duplicate field.

3. Select the DuplicateField operation from the Create submenu.


If the current form has fields, VIFRED displays a pop-up containing a list of the fields. If the current form does not have fields, VIFRED displays a list of the forms to which you have access.

The pop-up displays a maximum of 10 fields at a time. To see additional field names, scroll through the list.


4. To select a field from the current form, proceed to Step 5.

To select a field from another form, select the ListForms operation (if the pop-up listing the forms to which you have access is not displayed).

VIFRED displays the Forms in the Database pop-up.



Place the cursor on the desired form and choose the Select operation.



VIFRED displays a pop-up listing the fields on the selected form.

5. Place the cursor on the desired field and choose the Select operation.

If the internal name of the selected field is the same as the existing field, VIFRED prompts you for a new name. Type an internal name for the new field and press Return.

For an explanation of internal field names, see Parts of a Form.

Deleting Form Components

To delete any component, move the cursor to it and choose the Delete operation. Note the following specific instructions:

- You cannot delete a *line* if it contains any components.
- To delete a box created with the Box/Line operation, place the cursor on one of the box's borders, not inside the box.

You can immediately use the Undo operation to reverse the Delete operation if you change your mind about deleting a component.

Changing the Tabbing Order of Fields on a Form

The Layout frame editing operations include the Order operation. Use the Order operation to specify the tabbing order on the form. Tabbing order is the order in which the cursor moves from field to field on your form when someone is using it in QBF or in an application. By default, the cursor tabs from left to right across the screen. However, you can use the Order operation to specify any tabbing order you want.

When you choose the Order operation, VIFRED displays the fields with their current tabbing order. The following table lists the Order menu choices:

Operation	Description
Edit	Enables you to type a new sequence number over the current one.
DefaultOrder	Restores the default order.
Cancel	Cancels any changes you have entered and returns to the Layout menu.
Help, End	These are standard operations.

Default tabbing order is left to right, top to bottom. To change the tabbing order, follow these steps:

- 1. Choose the Order operation on the Form Layout frame. A new menu appears. A sequence number at each field indicates its position in the tabbing order.
- 2. Move the cursor to the field you want to change.
- Choose the Edit operation. VIFRED displays the message: Change sequence number (press <MENU KEY> when done)
- 4. Type a new, unique sequence number over the current one and press the Menu key.
- 5. Choose the End operation to return to editing.

If you attempt to exit the Order menu while two fields have the same sequence number assigned, VIFRED issues the error message:

Non-unique field order number(s) found

If a field has no field order number, VIFRED assigns it the next available number. VIFRED searches for fields with no field order number in the default tabbing order, left to right, top to bottom.

To restore the default order, choose the DefaultOrder operation. To cancel changes made since entering the Order menu, choose the Cancel operation.

Moving Components on a Form

The Form Layout frame menu provides the following two operations that move components on your form:

- Move
- GroupMove

The Move operation enables you to create forms wider than 80 columns, change the margins of the form, or reposition trim elements, boxes, vertical lines, fields, table fields, or field names on the form. This Move operation affects entire components as a whole. For example, the Move operation moves an entire table field as a unit. As an exception, you can specify that you only want to move a simple-field title or simple-field data window independent of the other part by using the Move submenu line. For more information, see Moving Titles and Display Windows.

Depending on whether you choose to move trim, a simple field, a table field, or the margin, various menus appear, as shown in the following table:

Operation	Menu Options
Trim	Place Left Center Right Shift
Box/Line	Place
Simple Fields	Place Left Center Right Shift Title Format
Table Field	Place Left Center Right Shift
Margins	Place Expand

Using the GroupMove operation, you can move several unrelated form components at once.

Moving a Single Component

To move a form component:

1. Position the cursor on the component to be moved and choose Move from the Form Layout menu.

The menu of Move operations appropriate for the selected component appears with the component highlighted in reverse video:

- If the cursor is on a trim component, the entire component appears in inverse video.
- If the cursor is on a table field or box, the corners of the field or box appears in inverse video.

- If the cursor is on either a title or data field or a simple field, both parts appears in inverse video.
- To move the component to a specific place on the form, relocate the cursor to the place where you want the component moved and choose the Place or Shift operation, as described in the following sections.

To center or justify a component in relation to the form margin, select the Center, Left, or Right operations, as described in Centering and Justifying Components.

If you move a component to the bottom of the form and there is not enough vertical space in the form to accommodate it, VIFRED automatically moves the bottom margin of the form down enough rows to allow the component to fit. The right margin, however, does not automatically move to the right to accommodate a moved component.

If you are not satisfied with the results of any Move operation, choose the Undo operation. Because Undo reverses the last operation performed, you must use the Undo operation before performing any other operation.

Place

To use the Place operation:

- 1. Position the cursor on the component you want to move and choose Move.
- 2. Position the cursor where you want to place the beginning character of the component and choose Place.

If you are moving a table field or a box, position the cursor where you want to place the upper left corner of the component.

Except for boxes and lines, if the selected position for the component would cause it to overlap another component on the form, VIFRED adjusts the position of the other component, moving it to the right if possible, and moving it down if necessary. Otherwise, the Place operation does not preserve spacing between components.

The Place operation allows boxes and lines to overlap each other. However, boxes that you create around fields as field attributes, rather than as part of the Box/Line operation, cannot overlap.

Shift

The Shift operation works the same way as the Place operation, except that it preserves spacing between components to the right.

If you shift a component to a spot where it overlaps some other component, you push the other component and all components to the right of it the same amount of space to the right. If there is not enough space to push the components to the right, VIFRED pushes one or more of them down.

Centering and Justifying Components

Use the Left, Center, and Right operations to position certain components to the far left, the center, or the far right of the form, respectively.

To use the Left, Center, or Right operation:

- 1. Position the cursor on the component to be moved and choose the Move operation.
- 2. Choose the Left, Center, or Right operation. If you do not see the Left, Center, and Right operations when you choose the Move operation, they are not available for the component on which the cursor rests.

Moving Titles and Display Windows

Normally a field's title and display window move as a unit. However, you can move them separately, if you want.

When you place the cursor on a simple field and choose the Move operation, the menu displayed at the bottom of your window contains two operations not found on Move menus for other components.

Operation	Description
Title	Moves only the title.
Format	Moves only the format of the data window.

To move the field's components separately:

- Choose the Title operation to move only the title of a simple field.
- Choose the Format operation to move only the format of the data display window of a simple field.

Once you choose either Title or Format, the Place and Shift operations apply only to the part of the field you have specified.

Moving a Group of Components at Once

You can use the GroupMove operation on the Form Layout frame to define a *bounding box* around a group of unrelated form components and move them as a unit to a new location on the form. The operation preserves relative spacing between components and from each component to the upper left corner of the defined bounding box.

Once completed, you cannot use the Undo operation to reverse a group move. During the process, you can abandon the move as described within the following procedure.

To move an entire group of form components at once:

1. Position the cursor where it defines the upper left corner of the group of components you want to move. Then Choose the GroupMove operation on the Form Layout frame menu.

VIFRED marks the current cursor position at the upper left corner of the group with a blinking plus sign (+) and displays the following message:

Move cursor to position the opposite corner press <MENU KEY> when done)

2. Position the cursor diagonally opposite the marked corner so that it defines the lower right corner of the group of components to be moved. The components to be moved must be contained within the area defined by the upper left and lower right corners.

If you want to cancel the operation at this point, either:

- Move the cursor to its previously marked upper left corner, so that no bounding box is defined
- Define a bounding box that encompasses none of the components completely.

VIFRED highlights the group of components and displays this submenu:

Place Help End

3. Position the cursor at the upper left corner of the place to which you want to move the components and select the Place operation on the submenu.

Otherwise, if you want to cancel the operation, select End.

If the location you specified is the same as the starting position, or if the move would overlap other form components, VIFRED cancels the operation.

Otherwise, VIFRED immediately moves the group of components. If necessary, VIFRED expands the form to accommodate the move.

4. To preserve your changes, choose the Save operation on the Form Layout frame.

Chapter 15: VIFRED Field Specifications

This chapter describes how to use the VIFRED to specify field attributes for simple fields and table field columns on a form. Attributes are features that can be applied to a field's data window. Attributes can affect both the visual aspects of a field and the behavior of a field.

Specifying Field Attributes

When you create a default form or individual fields on a form, VIFRED assigns certain default attributes to those fields. You can view or change these attributes with the Attributes operation on the Edit menu.

Default Attributes

Fields on VIFRED forms assume these default attributes:

- Fields on default forms assume the data type and internal field name attributes from the underlying column in the database table.
- Defaults for required attributes in fields on custom-created (non-default) forms are set initially by VIFRED or by the user during form creation.
- Attributes in the Set list of the Attributes for Field frame are initially set to n (no) for fields on custom-created (non-default) forms.

A field created with VIFRED on a default form assumes default attributes according to the corresponding attributes of the underlying data column. For example, if the underlying data column accepts nulls, the default attribute of the field is set to accept nulls. By default, field attributes that have no corresponding data column attribute are set to off, designated by n in the Set list on the Attributes for Field form. The default for color is zero (0).

When you create a field with the Create Field operation, the default for each of the attributes in the Set list is n (no). The default for color is zero (0). The user sets other required attributes while creating the field.

When applied to a column in a table field, the Reverse Video, Blinking, Underline, Brightness Change, and Invisible attributes affect the entire column. For example, if a column has the Underline attribute set, every data value displayed in the column is underlined.


Setting Attributes for a Field or Column

To view or change attributes for a particular field:

- 1. Use one of the following, as appropriate:
 - For a simple field, place the cursor on the name of the field in the Form Layout frame and choose the Edit operation, and then choose the Attributes operation on the Edit submenu.
 - For a table field column, place the cursor on the row in the Form Layout frame that identifies the particular column for which you want to set attributes. Choose the Edit operation; then choose the EditAttr operation on the Table Field frame.


The Attributes for Field frame displays the current attributes of the selected field. The frame for a simple field varies slightly from the frame for a table field.

The following figure shows the Attributes for Field frame for a simple field:



The Attributes for Field frame includes an Attribute Set list on the left side of the frame. These attributes are either on or off, as indicated by y or n in the column labeled Set. The default condition is n (off). The attributes in this list vary slightly between simple fields and table fields.

This frame also includes some additional attributes that you set by typing in values, or that apply only to certain types of fields. These attributes appear on the right half of the frame. In this particular example, which shows the attributes for a text field of data type varchar, the Scrollable?(y/n) field appears near the bottom right half of the window. This field applies only to fields created for character data, and does not appear when you are setting the attributes of a numeric, date, or money data type field.



The following figure shows the Attributes for Field frame for a column in a table field:

- 2. To change an attribute in the Set list, position the cursor on the line for that attribute, and type y (yes) or n (no) in the Set column. For a description of each attribute in the Set list, see Attributes in the Set List.
- 3. To change an attribute that requires a text entry or that appears on the right side of the Attributes frame, press the Tab key to reach the appropriate field and type in the new value. For a description of each attribute specification field, see Attributes in the Set List.
- 4. When done, choose the End operation to exit the Attributes for Field frame and return to the Form Layout frame.
- 5. Save your form with the Save operation before exiting the Form Layout frame; otherwise the attributes you specified are lost.

The following table lists the menu choices you can use to change the attributes of additional fields without leaving the Attributes for Field frame:

Operation	Description
Next	Displays the attributes for the next field.
Previous	Displays the attributes for the previous field.
MoreEdit	Displays a pop-up form that allows you to edit validation information or a derivation formula.

Operation	Description
ListChoices	Displays a pop-up form with the choices available for the selected field. To make a selection, click on the choice or place the cursor on your choice and choose the Select operation.
Help, End	These are standard operations.

Attributes in the Set List

The following table summarizes the attributes in the Set list on the Attributes for Field frame for both simple fields and table field columns. Some of the attributes apply only to simple fields or only to table field columns.

Attribute	Description
Box Field	Automatically encloses the field in a box (simple fields only).
Keep Previous Value	The last value entered in this field appears as a default value (simple fields only).
Mandatory Field	Data entry is required for this field.
Reverse Video	Reverses screen contrast from bright characters on dark background to the opposite, or vice versa.
Blinking	Makes the field blink on and off. Microsoft Windows does not support blinking. Instead, the background color changes in intensity to represent the blinking attribute.
Underline	Underlines the characters in the field.
Brightness Change	Toggles the brightness of a field.
QueryOnly	Can enter data in this field only if form is in Query or Fill mode.
ForceLower Case	Changes any uppercase letters entered to lowercase.
ForceUpper Case	Changes any lowercase letters entered to uppercase.
No Auto Tab	Turns off automatic tabbing when the end of a field is reached to prevent the user from accidentally typing over the next field.
NoEcho	Prevents on-screen display of data typed into this field.

Attribute	Description
DisplayOnly	Prevents entry of data into this field; allows only display of data. You cannot place cursor in this field with Tab or Return keys.
Invisible	Prevents on-screen display of a simple field or table field column. You cannot place cursor in this field with the Tab or Return keys.
Inputmasking	Turns input masking on or off for use with input templates in data entry field display formats. Input masking checks user input against a format template, character by character, as the user enters the data.

An Alternative to the BoxField Attribute

Instead of using the BoxField attribute on the Attributes for Field frame to automatically enclose a simple field in a box, you can use the Box/Line operation on the Create submenu of the Form Layout frame to manually draw a box around the field. This permits you to specify display attributes for the box you draw.

Setting the Invisible Attribute

You can use the Invisible attribute to prevent a simple field or table field column and the data in it from being displayed in the window.

There is a difference between making an entire table field invisible and making a table field column invisible:

- Making a table field invisible prevents the entire table field from appearing in the window. To make an entire table field invisible, enter y in the Invisible Field?(y/n) field on the Table Field frame, which is described in Creating and Editing Table Fields.
- Making a table field *column* invisible prevents only the column from appearing in the window. To make a table field column invisible, type y next to the Invisible attribute in the Set Attributes list of the Attributes for Field frame.

When you use a form with invisible table field columns or invisible simple fields, the invisible field does not appear in the window. However, the invisible field or column does appear on the Form Layout frame in VIFRED and in printform output.

As with the DisplayOnly attribute, you cannot place the cursor in invisible fields with Tab or Return. The cursor skips over these fields to the next field.

Turning Input Masking On or Off

Input masking enables VIFRED to check a user's input in data entry fields on a character-by-character basis, as the user enters the data. If input masking is set to off, VIFRED checks the entry only when the user attempts to exit the field.

To turn on input masking, set the Inputmasking attribute to y (yes) in the Set list on the Attributes for Field frame.

In addition to turning on input masking, you must also specify an allowable input display format for the field or tablefield column. You can use only the following display formats with input masking:

- Date template
- Numeric template
- String template

For more information on display formats and input masking, see the chapter "Working with Data Types and Data Display Formats."

Required and Other Attributes

In addition to those in the Set list, other field attributes appear on the Attributes for Field frame, as summarized in the following table.

The following attributes require specifications:

- Internal Name
- Data Type
- Nullable
- Color
- Scrollable (if showing)

These attributes are discussed in more detail following the table:

Attribute	Description
Internal Name	Specifies the name by which a field is known to VIFRED. On a default form, the default internal name is the table column name. On a form created by the user, the default internal name is the title entered by the user (with any non-legal characters removed). The character limit is 32 (for databases compliant with ANSI/ISO Entry SQL-92 standards, see Naming and Name Use Conventions). A specification in this field is required. You initially enter this specification during the Create Field or Create Table Field procedure.
Data Type	This specifies the data type of the column in the database table that corresponds to the field on the form. A specification in this field is required. VIFRED automatically supplies an initial entry when the field is created, for fields on a default form or table field columns created with the GetTableDef operation.
Nullable	A y indicates a NULL value is valid. An n indicates that the NULL value is invalid. A specification in this field is required.
Default Value	Enters a specified value in a field automatically when a form is used. The character limit is 50. This attribute applies to simple fields only, and is required. Not displayed for derived fields.
Validation Check to Perform	Checks entered data to see if it meets the criteria established for the field. The default is no validation. The character limit is 240. Not displayed for derived fields.
Validation Error Message	Error message to be displayed when data entered is not valid. The default is none and the character limit is 100. Not displayed for derived fields.
Derived	If set to y, makes this field a derived field, whose value is calculated from a derivation formula that you specify.
Derivation Formula	Contains the formula used to calculate the value of a derived field. Displayed only if the Derived field is set to y. This is a scrollable field, which can contain up to 240 characters and displays 50 characters at a time.
Color	Changes current color (on color terminals and monitors), using a numeric code. The default is zero (0) or default color. A specification in this field is required.

Attribute	Description
Scrollable	Y defines a text field as scrollable. The default is n (non-scrollable). Displayed only for a character data type (single line, non-justified format). A specification in this field is required.
Scroll size	Sets the length of the scrollable field. Displayed only when the Scrollable field is set to y.

Changing the Internal Name of a Field

The field's internal name is the name by which it is known to VIFRED. To change this name, move the cursor to the space beside Internal Name for Field, type the new name over the current name, and press Return.

Internal names can contain a maximum of 32 characters. For naming conventions in databases compliant with ANSI/ISO Entry SQL-92 standards, see Name Use Conventions.

Changing a field's internal name affects data transfer to and from the field. We recommend that you change an internal field name only if you are an experienced programmer familiar with the ramifications of such a change.

Changing a Field's Data Type

You can change a field's data type by entering a new data type in the Data Type field of the Attributes form.

Fields on your form that correspond to data columns in tables must have the same data type as the data column in the table.

When you specify any of the character data types in the Attributes for Field frame, you cannot specify the length (number of characters) of the field, because VIFRED obtains the size of character fields from the field's display format. In this way VIFRED ensures that the data type size and format size are always the same.

Keep in mind that while VIFRED changes a field's data type to match a new display format, the reverse is not true. Thus, if you change a field's data type, you must make sure that the display format matches. When you select the Attributes for Field frame's End operation, VIFRED checks the compatibility of field data types and field display formats. VIFRED displays an error message if it finds an incompatibility. You must correct the problem before you can leave the Attributes for Field frame or edit the attributes of other fields or columns.

Setting Nullable Data Types

You can specify that a data type is nullable or non-nullable by entering y for nullable or n for non-nullable in the Nullable field. A nullable data type accepts a null value. For more information on null values, see Nulls.

If the form field for which you are specifying attributes is to be linked to a data column in a table, the null specification on the Attributes for Field frame must match the null specification of the data column in the table.

Changing the Color

You can change the color of a field for displays that support color and have been defined to Ingres as such in the termcap file entry designated by TERM_INGRES. To change the color of a field, move the cursor beside Color on the Attributes form and type the code number of your choice over the current number. Color capabilities vary widely among monitors and can be customized by changing your termcap file entry. To determine the color codes for your monitor, check the termcap file entry or see your monitor documentation.

Scrollable Fields

In a scrollable field, only part of the data in a text field is displayed on a form. The visible display window of a scrollable field is narrower than the underlying field. VIFRED truncates the display to show only as many characters that fit in the window. Access the entire field by scrolling horizontally with the left and right arrow keys, or, if you are entering data, by continuing to type in data beyond the end of the field.

Scrollable fields allow large amounts of data to be displayed in a small area of a form. Only fields that have a data type of varchar, char, text, or c with single-row, non-justified display formats can be designated as scrollable fields.

You can use the Attributes operation to make a field scrollable. You must create the form and fields first with the Create operation, which establishes the size of the display window. And then, access the Edit Attributes frame to assign the width of the underlying field.

To create a scrollable field on a form:

- 1. Use the Create operation to create a form with a text field, single line, with no justification. On the field you want to make scrollable, enter the text data type and character size; for example, 5.
- 2. Select End. You have established that this is a text field and the size of the display window of the scrollable field.

- First, select the Edit and then the Attributes operation, for a simple field, or the EditAttr operation for a table field in a column. The Edit Attributes frame appears. For more information on these frames, see the preceding two figures.
- 4. The field, Scrollable?(y/n), appears at the bottom. Enter y (yes) to indicate that this is a scrollable field.
- 5. The field, Scroll size, appears. Type in the number of characters in the scrolling size or underlying width of the field—for example, 20. The display window of the resulting scrollable field shows five characters, while the underlying field contains 20 characters.

You can change an existing scrollable field to a non-scrollable field at this point by changing the value of the Scrollable(y/n) field to n.

You can also change a scrollable field to a non-scrollable field at this point by changing the data type to a non-text type, as scrollable fields must be text fields.

You can apply other field attributes at any point in this process. A scrollable field can have any other attribute except NoEcho.

It is not recommend that you make a scrollable field DisplayOnly, because the end user can only read the first section of the data that is displayed in the window, and cannot access the rest of the information in the field. The only exception to this is when all of the columns in a table field are unreachable due to being DisplayOnly or QueryOnly. The end user can then place the cursor on the fields in the first column, whether it is scrollable, and scroll up and down, thus accessing all the rows in this column.

Setting Default Values for a Field

If you want a value to appear automatically in a field when a user sees a form, you can set a default value. Default values can be character strings or simple numeric values. For example, a point-of-sale application might contain a field for the name of the store or branch office. You can set a default to automatically enter the name of the store in that field at each location.

The default value must match the data type of the field. Default values can contain up to a maximum of 50 characters.

You can enter a default value that enters the current date in a field with a date data type when the end user tabs out of the field. There are two default date values that can be used for this purpose:

- Today enters the current date when the end user tabs out of the field.
- Now enters both the current date and the current time when the end user tabs out of the field.

Specifying a Validation Check

A validation check is set by the designer of a form. It instructs VIFRED to evaluate the data entered in the field. If the data passes the validation check, it is accepted; if it does not pass the validation check, VIFRED displays an error message and asks the user to enter the correct data. You cannot specify a validation check for derived fields.

If you leave the validation field empty (the default), no validation is performed.

Note: If you are writing an application that is used with a mouse, keep in mind that users can click randomly around the fields on the form. Set up field validations accordingly.

Validation checks can contain a maximum of 240 characters.

You can specify a validation check in either of these two main styles for any valid data type:

- Comparison operator validation checks
- Comparison to a set of values

To enter or change the validation criteria, move the cursor to the space beside Validation Check to Perform on Field on the Attribute menu and type the new string over the current one. This field displays 50 characters at a time, but is scrollable. Use the MoreEdit operation to view or edit the entire validation string.

VIFRED does not check the syntax of a validation check until you attempt to save the form with the VIFRED Save operation. At that time, if VIFRED finds that the validation check you specified is illegal, you must correct it before you can save the form.

Note also that you can use Vision, Application-By-Forms, or an embedded query language to create validations that are more sophisticated than those you can specify with VIFRED.

Comparison Operator Validation Checks

The format for a comparison operator validation check is a string containing one or more comparison operators. Comparison operator validation checks have the following conventional syntax:

```
fieldname comparisonoperator constant
fieldname comparisonoperator otherfieldname
fieldname IS NULL
fieldname IS NOT NULL
```

The fieldname is the internal name of the field being validated; otherfieldname is the internal name of some other field containing a value to be compared against. In a validation string for a table-field column, you use tablefieldname instead of fieldname, as follows:

tablefieldname.internalcolumnname comparisonoperator constant

The following table lists valid comparison operators for SQL.

Operator	Description
=	Equal to
!=	Not equal to
<>	Not equal to
<	Less than
<=	Less than or equal to
>	Greater than
>=	Greater than or equal to
LIKE	SQL string equal to

Character String Comparisons

You can enter character strings as validation checks for fields designated as character data types. Always enclose character string validation checks in double quotation marks, except for the LIKE operator, which accepts strings with single quotation marks.

Validation checks on character strings can include pattern-matching characters. The following pattern-matching characters are valid for all operators except the LIKE operator:

Character	Description
*	(Asterisk) Matches zero or more undefined characters. For example, S* equals any character string beginning with the letter S.
?	(Question mark) Matches exactly one undefined character. For example, T?P equals TAP, TIP, TOP, etc.
[]	Matches any characters between the brackets including ranges. For example, [ACL]* equals any string that begins with A, C, or L. ?[N-X] equals any two-character string that begins with any letter and has any letter between N and X as the second character.
%	(Percent sign) Matches zero or more undefined characters (similar to the * character described above).
_	(Underscore) Matches one undefined character (similar to the ? character described above).

Example character string validations:

```
dept = "sales"
emptable.fname = "*son"
```

Date and Money Comparisons

Enter comparison constants for abstract data types such as date and money in double quotation marks, as if they were character strings. For example:

```
date = "1-Jan-1988"
projecttable.budget > "$1000000"
```

The money data type is not supported by OpenSQL. For SQL, OpenSQL and QUEL equivalents, see the appendix "Data Types."

NULL Value Comparisons

To compare for the null value, use IS NULL. To compare for any value but the null value, use IS NOT NULL. For example:

```
salary IS NOT NULL
```

The following rules govern null values in an expression:

- A NULL value in an expression with relational or arithmetic operators causes the expression to evaluate to NULL.
- If you use the logical AND operator and either expression is FALSE, then the result is FALSE. If one expression is TRUE and the other is NULL, then the result is NULL. The result is only TRUE if both expressions are TRUE.

If you use the logical OR operator and either expression is TRUE, then the result is TRUE. If one expression is FALSE and the other is NULL, the expression is NULL. The result is FALSE only if both expressions are FALSE.

If you use the logical NOT operator with an expression that evaluates to a null value, the result is still null.

Numeric Comparisons

Numeric constants do not have to be enclosed in quotes. The following example requires that the number entered in the Salary field be larger than zero:

```
salary > 0
```

This example requires that the number entered in the Age field be larger than or equal to 18 and less than or equal to 70:

```
age >= 18 AND age <= 70
```

A complex numeric expression must be enclosed in parentheses to clarify the way the expression must be evaluated.

The following example requires that the number entered in the Hourly_rate field either equal 30 or fall within the range of 40 to 50:

```
hourly_rate = 30 OR (hourly_rate >= 40 AND
hourly_rate <= 50)</pre>
```

Comparisons Against Other Fields

You can compare a value against whatever value is currently contained in another field. The following example requires that the name entered in the Lastname field not be the same as the name entered in the Firstname field:

```
lastname!= firstname
```

This example requires that the date entered in the Duedate field be equal to or greater than the date entered in the Orderdate field:

```
duedate => orderdate
```

Comparison to a List of Values

By using the keyword in, you can compare a value against an arbitrary list of values using the following format:

```
fieldname in [list]
```

The fieldname parameter is the internal name of the field and list is the list of valid values. The values in *list* must be of the same data type as values admissible in the field. They must be separated by commas and enclosed in mandatory brackets ([]).

If the field has a character data type, you must enclose the character string values in double quotation marks and you can use valid pattern-matching characters. Leading blanks are not significant.

The following example requires that the name entered in the Lname field be either Jones, or Ortega, or Bridges:

```
lname in ["Jones", "Ortega", "Bridges"]
```

This example requires that the character string entered in the Address field contain the characters BI, or Av, or end in R plus one other letter, or end with St:

```
address in ["*Bl*", "*Av*", "*R?", "*St"]
```

This example requires that the amount entered in the Salary column of the Emptable table field be either 1000, 1100, 1200, 1300, 1400, or 1500:

```
emptable.salary in [1000, 1100, 1200, 1300, 1400, 1500]
```

Comparison to a Lookup Table

The keyword in can also be used to compare data entered in a field to a set of stored values in a database table. This is the easiest way to compare against a large number of values or against values that can be changed from time to time.

When your form is initialized in QBF or your own application, the current set of data from the lookup table is read into main memory. The column entries in the lookup table at the time of form initialization represent the data values used for comparison. Values added to, or deleted from, the lookup table column after the form is initialized are not reflected in the set of data used for comparison.

To compare against values in a lookup table, use the following format:

```
fieldname| tablefield.column in
```

```
[schema.]tablename.columnname
```

If the *schema*, *tablename*, or *columnname* after the in keyword is a delimited identifier, you must enclose it within double quotes:

```
fieldname|tablefield.column in
```

```
["schema name".]"table name"."column name"
```

Parameters in the preceding syntax are defined in the following table:

Parameter	Description
fieldname	Internal name of the field being validated
tablefield.column	Internal name of the tablefield and column being validated
schema	Optional parameter identifying the schema to which the table belongs and its implied owner
tablename	Name of a table in the current database
columnname	Name of a column in the specified lookup table

The following example requires that the value in the Zipprefix field match the values found in the Prefix column of the Zip table:

```
zipprefix in zip.prefix
```

This example requires that the names entered in the Manager column of the Emptable tablefield match names contained in the Name column of the Employee table:

```
emptable.manager in employee.name
```

The user can place the cursor in a field that is validated by a lookup table or by a *fieldname in list* validation check, as described in Comparison to a List of Values. In either case, choosing the Help Field operation at this point displays the acceptable values from the lookup table.

Boolean Operators in Validation Checks

This chapter has discussed the following validation comparison types:

- Simple relational operator comparisons
- Comparison to a list of values
- Comparison to a lookup table

You can create more complex validation checks by using Boolean operators to connect any of these validating comparison types. The syntax for using the Boolean operators is:

expression OR expression expression AND expression NOT *expression*

The parameter expression is any of the previously discussed validation comparison types. For example, the following validation check forces a user to enter a number into the Code field that is either less than 21 or is 25, 30, or 35:

code < 21 or code in [25, 30, 35]

To allow additional flexibility, you can use parentheses to group Boolean expressions to achieve the desired semantics in the validation check. For instance, the following example forces a user to enter a number into the code field that is less than or equal to 20000 into the Salary field unless the Grade field is greater than or equal to 7. In this case, the user can enter a number up to 30000:

salary <= 20000 or (grade >= 7 and salary <= 30000)

Operator	Description	
AND	Boolean conjunction	
OR	Boolean disjunction	
NOT	Boolean negation	

Negation (NOT) has precedence over conjunction (AND) and disjunction (OR); AND and OR have equal precedence.

Some example character strings with Boolean operators are:

manager = "Jones" OR manager = "Ortega" AND NOT manager = "Fisher"

Creating a Validation Error Message

You can specify the error message that a user sees when the user enters a value in the field that does not pass the validation check.

To specify an error message for this field's validation check, enter the text of the message in the Validation Error Message field. A validation error message can contain a maximum of 100 characters. The Validation Error Message field, which is scrollable, displays 50 characters at a time.

You can specify different validation error messages for each field that contains a validation check. If no error message is specified for a field with a validation check, VIFRED supplies a generic default message.

Derived Fields

A *derived field* is a field whose value is based on the value of another field, called the *source field*, or constants. For example, your form could contain the following fields:

- Price (price of an item)
- Quantity Sold (total number of items sold)
- Total Amount Sold (value in the Price field multiplied by the value in the Quantity Sold field)

The Total Amount Sold field is a derived field, and the Price and Quantity Sold fields are its source fields.

Both simple fields and table field columns can be derived fields. VIFRED calculates the value of a derived field from a derivation formula, which you specify. For details, see <u>Guidelines for Specifying Derivation Formulas</u>.

The derived field must be nullable when:

- One of its source fields is nullable
- The derivation formula contains an aggregate

Derived fields cannot have the following attributes:

- Default values
- Mandatory
- Force upper or lower case
- Display only
- Scrollable

Using Forms with Derived Fields


The derived fields on a form are active when you view, add, or modify rows. You cannot place values directly into a derived field on a form. However, if the value of a source field changes, VIFRED recalculates the value of the derived field.

When you create a new row by moving the cursor down, the values for derived columns automatically display, if they can be calculated.

Specifying a Derived Field

To specify a derived field:

1. On the Attributes for Field form, tab to the Derived field and type y (yes). This figure shows the Attributes for Field frame for a simple field:



VIFRED displays the Derivation Formula field (as shown in the following figure) and removes the Validation Check to Perform field and the Validation Error Message field, because you cannot enter a validation check and message for derived fields:



2. Using the guidelines given in <u>Guidelines for Specifying Derivation</u> Formulas, which follows, enter a derivation formula up to 240 characters long.

The Derivation Formula field, which is scrollable, displays 50 characters at a time. Use the MoreEdit operation to view or edit the entire derivation formula.

When you save the form, VIFRED checks for data type compatibility, including nullability, between the various sources, operators, and the derived field itself. If it finds incompatibilities, VIFRED displays an error message and does not save the form. At this time, VIFRED also checks for circular references, as described in Circular References in Derivation Formulas.

Guidelines for Specifying Derivation Formulas

The derivation formula provides the calculation for determining the value of a derived field. When specifying a derivation formula, follow these guidelines.

A simple field can be derived from:

- Other simple fields, including other derived fields
- Aggregates of table field columns (cannot be derived directly from a table field column)
- A table field column can be derived from other columns in the same table field. A table field column cannot be derived from a simple field or aggregate value.
- You can use arithmetic operators, aggregates, and constants in derivation formulas, as explained in the following sections.

Arithmetic Operators in Derivation Formulas

You can use the following arithmetic operators in derivation formulas (in descending order of precedence) for both simple fields and table field columns:

- (minus sign)
- ** (exponentiation)
- *, / (multiplication, division)
- +, (addition, subtraction)

You can use parentheses () to change the order of evaluation.

Aggregates in Derivation Formulas

You can use aggregate functions in derivation formulas for simple fields, but not in derivation formulas for table field columns. To derive a value for a simple field based on an aggregate of a table-field column, use the following syntax:

aggfunction (tablefieldname[*].columnname)

This table lists the aggregates that can be used in derivation formulas, the data types that can be used with each aggregate, and the data type of the derived field:

Aggregate	Data type of source field:	Data type of derived field:
count	any	integer

Aggregate	Data type of source field:	Data type of derived field:
sum	integer	same as source
	float	
	money	
	date (intervals only)	
avg	integer	same as source except for integer
	float	
	money	
	date (intervals only)	
max	any	same as source
min	any	same as source

If a derivation formula contains a reference to an aggregate of a table field column, and the table field contains invalid values or is empty (has no values), the value of the aggregate is:

- Zero (0), if the aggregate is count
- Null, if the aggregate is avg, sum, max, or min

If the formula contains references to other fields that contain invalid values, VIFRED blanks out the derived field.

Constants in Derivation Formulas

You can use constants in derivation formulas for simple fields and for table field columns. For example, you can specify the derivation formula for Field_A as:

2 * field b

Supported data types for constants in derivation formulas are char, varchar, c, text, integer, floating point, date, and money. Specify dates, money, and non-numeric strings in single quotation marks, as:

'3-6-90' + field b

Dates in Derivation Formulas

You can perform the following arithmetic operations on date data types in derivation formulas:

- interval + interval = interval
- interval + absolute = absolute
- interval interval = interval
- absolute absolute = interval
- absolute interval = absolute

Circular References in Derivation Formulas

A circular reference occurs when Field_A depends on Field_B which, in turn, depends on Field_A. VIFRED does not allow circular references in derivation formulas. VIFRED checks for circular references at form initialization and at form save times. If it finds a circular reference, VIFRED displays an error message. You must correct the problem before VIFRED can save the form.

Examples of Derivation Formulas

The following formulas are valid derivation formulas for simple fields:

```
Field_3 - Field_2
  (Field_3 - Field_1) * (Field_5 - Field_4)
  Field_2 + sum(TableField1[*].Column2)
  Lastname + ',' + Firstname
'today' + '30 days'
'today' - '1 yrs 2 mos 3 days 12 hrs 24 mins 14 secs'
```

The following formulas are valid derivation formulas for table fields:

```
(TableField_1.Column1 + TableField_1.Column2) /2
Order_items.price * Order_items.quantity
Order_items.price *.90
```

Improving Performance of Derived Fields

To improve performance in applications that use derived fields, follow these recommendations:

- Use aggregates primarily to derive table field aggregates of approximately 50 rows or less.
- Avoid deep nesting of dependencies; that is, do not create a derivation formula where Field_A depends on Field_B, which depends on Field_C, and so forth.

Chapter 16: Interactive Query Language Terminal Monitor

This chapter describes the Interactive Terminal Monitor. In the Interactive Terminal Monitor, you enter query language statements on a blank form in a window and then press a function key or make a choice from a menu to execute the query.


The Interactive Terminal Monitor includes a full-screen editor for entering and editing interactive query language statements. When you execute a statement, the Interactive Terminal Monitor immediately displays the result in the window. If the statement cannot be executed, a detailed error message appears. Like other Ingres tools, the Interactive Terminal Monitor also includes context-sensitive Help windows.

The Interactive Terminal Monitor gives you more direct and more extensive control over data management functions than do other Ingres forms-based tools, such as QBF or the Tables utility.

The Interactive Terminal Monitor supports interactive forms-based releases of the query languages, Interactive SQL (ISQL) and Interactive QUEL (IQUEL). Choosing one of the guery languages from within Ingres Menu automatically starts the Interactive Terminal Monitor.

Notes:

- On Windows, Ingres character-based utilities like the Terminal Monitor will display characters correctly only if run under the supplied Ingres command prompt, which has the correct code page and font settings.
- On UNIX, Ingres character-based utilities like the Terminal Monitor will display characters correctly only if the console window on which they are run has the correct code page set, which must match the character set value set in II CHARSETxx for the database.



The map in the following figure illustrates the access path and the available Terminal Monitor operations:

Capabilities of the Interactive Terminal Monitor

Using a query language in the Interactive Terminal Monitor, you can:

- Define data structures in your database
- Manipulate data in your database

Data definition includes the creation of tables, views, and indexes. *Views* are virtual tables that provide alternative ways to access the data in database tables. *Indexes* contain keys to speed access to data in other tables. Data definition statements define the structure of data. For example, you can use query language statements in the Interactive Terminal Monitor to create a new table, naming its columns, and specifying the data type and length of each field. Or you can create a table based on an existing table, copying certain data from the old table into the new.

You can use the Interactive Terminal Monitor to manipulate data in the following ways:

- Insert (add) data
- Update data

- Delete data
- Retrieve data

These activities can be performed on one or more tables with a single statement. You can also perform global operations on a table. For example, you can add several rows of new data to a table at once, or you can update the value of a particular column in all the existing rows. In addition, you can perform computations on existing data. For example, you can add 15 percent to every employee's hourly rate.

You can narrow the scope of an update or retrieval, or any other function, to rows containing specific values in a column. You can also qualify the scope of a function with various operators and set functions. For example, you can retrieve records for employees whose names begin with S, display an average hourly rate for the employees of a certain manager, or add 15 percent to the hourly rates of everyone except managers.

For complete query language statement syntax and details of using a query language for data manipulation, see your query language reference guide.

Starting the Interactive Terminal Monitor

You can start the Interactive Terminal Monitor from the operating system or from the Ingres Menu. For information on starting the Interactive Terminal Monitor from the operating system, see the chapter "Using System Commands for the Forms-based Tools."


Follow these steps to start the Interactive Terminal Monitor from the Ingres Menu:

- 1. Choose the Queries operation from Ingres Menu.
- Choose SQL or QUEL (if your system supports Interactive QUEL).

The Interactive Terminal Monitor frame displays in the window. See the figure in the following section.

Entering Query Language Statements

The Interactive Terminal Monitor frame's input screen (in the following figure) consists of a blank window and a menu of operations. Enter and edit your query language statements in the frame's window, which is your workspace. The cursor initially appears in the upper left corner of the window.



The workspace is essentially a single-column table field, within which you have access to all cursor movement keystrokes, forms-based operations, and forms-based functions. You can also use the default editor on your computer system to edit your work, by selecting the Edit operation from the main menu. The default editor is determined by the ING_EDIT environment variable/logical, as discussed in the *System Administrator Guide* for the system on which your database resides.

The input window retains all the statements you enter in the workspace unless you explicitly edit or clear them.

Menu Operations

The following operations are available on the Interactive Terminal Monitor frame:

Operation	Function
Go	Executes the query language statements and immediately begins displaying the results.
Resume	Displays the results of the last query language statements you executed (shows the previous output window, as it appeared when you exited the output window).

Operation	Function
Complete	Executes the statements in the workspace, but does not display the results until all processing is completed. This command displays the end of the query's output.
Blank	Clears the workspace of any statements you have entered.
Edit	Edits the statements in the workspace with the standard system editor.
File	Calls the submenu of file operations to write the information in the window into a file or read information from an existing file.
OnError	Indicates whether errors terminate or continue the processing of SQL statements, and lets you change the setting.
LineEdit	Displays a submenu to insert, delete, split, or join lines in the input window.
Help	Gets help about this frame, including help about the syntax and usage of the interactive query language.
Quit	Leaves the Interactive Terminal Monitor.

The Edit operation writes the workspace contents to a temporary file and invokes your default system text editor on that temporary file. When you finish editing the temporary file and exit from the editor, the newly edited text in the workspace on the Interactive Terminal Monitor frame displays. You can then execute the statements or continue editing or adding text in the input window.

The LineEdit operation enables you to insert, delete, split, or join lines in the input window. When you select the LineEdit operation, you access a submenu that displays the following line editing functions:

Operation	Description
InsertLine	Inserts a blank line above the line on which the cursor is positioned.
DeleteLine	Deletes the line on which the cursor is positioned.
SplitLine	Divides a line into two lines at the point where the cursor is positioned.
JoinLines	Moves the next line to the end of the line on which the cursor is positioned.
Help, End	These are standard operations.

The Help operation includes complete summaries of how to use statements in the particular database language you have chosen. If available for your terminal, you can use the key mapped to the string-search function (the Windows Find operation) to search for database language keywords to find helpful hints on syntax and usage.

Reading from and Writing to a File

In addition to statements that you type directly into the workspace on the Interactive Terminal Monitor frame, you can enter database language statements into the frame from existing text files. Similarly, you can preserve a script you have written in the workspace by saving it to a file.

Entering Statements from a File

To enter query language statements from a file into the workspace:

- 1. Choose the File operation on the Interactive Terminal Monitor input frame.
- 2. Choose the Read operation on the File submenu, and the following prompt displays:

Enter name of file to read:

3. Type the file name. If the file to be read is not in the current (working) directory, you must include the full file name specification.

The contents of the file you named displays.

If you have already entered database language statements into the workspace, the file contents are added above the current row, as designated by the cursor location.

Writing Statements to a File

To write the contents of your workspace into a file:

- 1. Choose the File operation on the Interactive Terminal Monitor input frame.
- 2. Choose the Write operation on the File submenu, and the following prompt displays:

Enter name of file to be written:

3. Type a file name. The workspace contents are written to that file and the workspace contents are preserved for further editing.

Executing Query Language Statements

After specifying query language statements in the workspace, execute them to receive output.

For example, suppose you entered the following ISQL statement in your workspace:

select * from staff

When you choose the Go or Complete operation, the following message displays while retrieving the data:

Run the request

The resulting data displays in the output window for the Interactive Terminal Monitor frame, as shown in the following figure. In this example, all rows from the Staff table in the current database have been retrieved, but not all of the data can fit in the window at the same time.



A Start of Output banner appears at the top of the output window if the data extends beyond the first window:

Start of Output Column 1/80 Line 1

The Column and Line indicators in the Start of Output banner indicate the portion of your output that is currently visible in the window, as determined by a theoretical column and row grid. Each grid column is one character wide. The first number in the Column indicator shows which output column currently appears at the left margin of your window. The number after the slash indicates the total width of the output. In this case, Column 1/80 indicates that the first column of the output appears at the left margin and the total output is 80 columns wide. The Line indicator shows the current line, at the top of the output area.

The database language statements you entered in the input window appear on the output window after the banner. Each statement line is preceded on the same line by a number and a greater than (>) character. In the preceding figure, the ISQL statement is preceded by 1>.

The rest of the output window contains the data and messages returned by the request. You can scroll the rows of output up and down or left and right in the output window, using your mouse or the keys mapped to the scrolling functions. To go directly to the end of the output, use the key mapped to the Bottom FRS key operation; to go to the top of the output, use the key mapped to the Top FRS key operation.

This figure shows the frame contents at the end of the output.



If the query runs to completion, the Line indicator in the End of Output banner at the top of the output shows the current line at the top of the output area (in this case, Line 24), as well as the total number of lines in the output, including trim, blank lines, and explanatory text (in this case, 42 lines).

An End of Request banner also appears if you:


- Execute the Go operation and all output from the request displays in one window.
- Execute the Complete operation, which runs the request to completion and displays the last portion of the output.
- Scroll the cursor to the last window of data in the output.

The operations available in the output window are described in this table:

Operation	Description
Print	Sends the output to a default or named printer.
File	Sends the output to a file.
Help, End	These are standard operations. You use the End operation to return to the input window.

The File operation in the output window differs from the File operation in the input window. In the output window, the File operation sends the query output results to a file; in the input window it sends the query language statements to a file. For more information on the Print and File operations, see Printing or Filing Output.

When you return to the input window, your original query reappears, as shown in this figure.



To edit the current request or execute it again, use the Go or Complete operations. To return to the point at which you last inspected the current output, use the Resume operation. Or, clear the workspace with the Blank operation and enter a new request.

Printing or Filing Output

To print or file the currently displayed window, use the printscreen function key.

To print the results of your query or to store the results in a file, use the Print or File operations in the output window of the Interactive Terminal Monitor frame. These are the same operations you use with RBF. See the following sections in the chapter "Producing a RBF Report:"

- Sending Reports from a Screen to a File
- Sending Reports from a Screen to a Printer

Error Messages

If a query language statement contains errors, an error message is displayed. The error message includes information on statement syntax. The erroneous part of the statement can be pointed out, as shown in the following figure. The error message indicates that the statement select in line one was typed incorrectly.

```
Ingres ingmenu

End of Output

Line 1/7

1> slect * from staff

E_US0PC4 Syntax error on line 1. Last symbol read was: '*'.

(Fri Sep 18 13:52:00 1998)

End of Request - Terminated by Errors

Print(SH-F1) File(SH-F2) Help(F1) End(F10)
```

If the OnError setting is set to CONTINUE, the query continues after the error message appears. If set to TERMINATE, then the remaining portion of the query is terminated after the error message appears. Choose End to return to the input window and edit your erroneous entry, or clear the frame with the Blank operation and correctly retype your request.

To change the OnError setting:

- 1. Choose the OnError operation on the Interactive Terminal Monitor input frame. A pop-up window appears, offering choices of CONTINUE and TERMINATE.
- 2. Choose CONTINUE if you want queries to continue after an error message appears. Choose TERMINATE if you want the remaining portion of a query to terminate when an error message appear.

Chapter 17: Using System Commands for the Forms-based Tools

System-level commands are provided for starting the Ingres forms-based tools, and several other commands are provided that are useful for managing reports, forms, and forms objects such as JoinDefs and QBFNames.

This chapter provides the syntax and comprehensive explanations of many commands you can use in conjunction with the Ingres tools discussed in this guide. For commands that apply to other Ingres tools, such as Report-Writer or ABF, see Forms-based Application Development Tools User Guide or the System Administrator Guide.

Syntax Conventions

Enter system-level commands at the operating system prompt or from the Run dialog in Microsoft Windows. They consist of one or more required command words, usually followed by one or more parameters or flags, as follows:

command [flags] dbname|v_node::dbname [/server_type] {[flags] [parameters]} [-uusername] [-Ggroupid]

If your database resides on a remote system, specify v_node, the name of the remote host where the database resides. If you are accessing a distributed database or a non-Ingres database through an Enterprise Access product, specify the /server_type parameter.

Enclose the -Ggroupid parameter in double quotes ("-Ggroupid") to preserve the case of the -G flag. For example, to invoke the Ingres Menu with a groupid of sales, you must use double quotes around the -G designation:

ingmenu dbname "-Gsales" 1

If the username, groupid, or another command parameter is a delimited identifier, enclose it in double quotes ("), dereference any embedded quotes, and use the appropriate number and type of delimiting quotes to pass it through your operating system. For more information, see the System Administrator Guide.

VMS

Report-Writer Command Syntax

The following is an example of standard syntax for Report-Writer commands that you enter on the operating system command line:

command dbname|v_node::dbname [/server_class] cmd_parameters
[-s] [-uusername] [-Ggroupid]

If your database resides on a remote system, specify *v_node*, the name of the remote host where the database resides. If you are using an Enterprise Access product, then specify */server_class*.

Execute commands from the Bourne shell. In some instances, the C shell can be confused by parameters that contain double quotes. In addition, you cannot escape the dollar sign (\$) within double quotes in the C shell, if necessary.

Enclose the -G*groupid* parameter in double quotes ("-G*groupid*") to preserve the case of the -G flag. **\binom{1}**

If the *username*, *groupid*, or another command parameter is a delimited identifier, specify it in its editable format. For more information, see <u>Specifying Delimited Identifiers</u>. For instructions on passing the delimited identifier and its quotes through your operating system, see the *System Administrator Guide*.

Standard Flags and Parameters

A *flag* is a letter preceded by a hyphen (-) that determines various options for commands. Unless flags are indicated in uppercase letters within this chapter, you can type them in either uppercase or lowercase. Flags that must be entered in uppercase, such as -G*groupid*, need special input syntax if the host operating system is case-insensitive.

A parameter can be a command, the name of an object, or a value that specifies a particular use for a command. A parameter can follow a flag, another parameter, or the system-level command itself. A parameter is generally specified in syntax as a generic name, such as dbname, to indicate that you must type a specific value (in this case, the name of a database). The most common parameters are database names and table names.

The following table describes the parameters and flags that are used consistently in the system-level commands for the forms-based tools. These descriptions are usually not repeated under the individual command sections in this chapter.

Parameter	Description
cmd_parameters	Report-Writer parameters specific to each command

UNIX

VMS

Parameter	Description
command	Report-Writer command that you enter on the system command line
dbname	Name of an Ingres database. This parameter must precede all other non-flag parameters (with the exception of <i>v_node</i> in <i>v_node</i> ::dbname).
-Ggroupid	The -G flag associates the session with the specified <i>groupid</i> (user group identifier). Each user group identifier has permissions defined for it, such as the permission to update a particular table. When you use the -G flag, these permissions are applied to your session. If the groupid is a delimited identifier, enclose it in double quotes. For information on passing these quotes through the operating system, see the <i>System Administrator Guide</i> for the system on which your database resides.
	To use this flag, you must be a member of the specified groupid's user list, an system administrator, or a user with the security privilege. If you are not, the session is disconnected and displays a message.
	The system administrator establishes user groups and assigns users to them. If you are assigned a default user group identifier, you do not have to use this flag; the user group permissions are automatically applied to your session.
VMS	In VMS, enclose the entire -Ggroupid flag and parameter within double quotes ("-Ggroupid").
	If the groupid is a delimited identifier, enclose it in dereferenced double quotes. For information on dereferencing these quotes, see the <i>System Administrator Guide</i> .
-s	Report-Writer flag that suppresses status messages but not prompts.
/server_class	If applicable, the Report-Writer code to identify the type of database or Enterprise Access product being used on the remote host. A preceding slash (/) is required.

Parameter	Description
server_type	Name of one of the servers or Enterprise Access products (for example, db2, or the distributed server_type, star). If you are accessing a database through an Enterprise Access product, the server_type is mandatory. For Ingres Enterprise Access product server types, see the Enterprise Access product documentation.
-u username	Recognizes you as the user with the login username. The -u flag must be followed immediately by a valid user login ID. If the user name is a delimited identifier, enclose it in double quotes. For information on passing these quotes through the operating system, see the <i>System Administrator Guide</i> for the system on which your database resides.
	This parameter can only be used by the DBA for a database or by a user with the security privilege.
VMS	In VMS, enclose the entire -u <i>username</i> flag and parameter within double quotes ("-u <i>username</i> ").
v_node	Name of the computer on which your database is stored, as known to Ingres Net. If you are accessing a database on a remote node, the <i>v_node</i> is mandatory; it must be followed by two colons (::) and the <i>dbname</i> parameter, with no intervening space.

Compform

Compiles a form that is already stored in a database and places the compiled form in a text file.

Syntax

compform dbname|v_node::dbname[/server_class] form filename [-**u**username] [-Ggroupid]

If your database resides on a remote system, specify v_node, the name of the remote host. If you are using an Enterprise Access product, specify /server_class.

VMS

Enclose the -G groupid flag and parameter in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

Description

When you are developing applications, you often must compile a form for use with embedded SQL or other embedded query languages. Compiling a form reduces start-up time when the form is then used in an embedded query language program.

To compile the form without starting VIFRED, use the compform command at the operating system prompt, instead of the Compile operation on the VIFRED Utilities menu.

To describe the form, the compform command produces a C language structure, by default.

In VMS, compform produces macro code by default.

You can compile only one form at a time.

This table lists valid command flags and parameters:

Parameter	Description
form	Name of the form to be compiled.
filename	Name of the text file into which the compiled form is placed.
-m	Flag that compiles a form into VAX/VMS macro code. This flag is set by default and is normally included in the symbol for the compform command on VAX/VMS machines. You must remove this flag to compile the form into C language code.

VMS

VMS

Compiling a Form into Object Code

Before you can link the compiled form to your application, you must translate the compiled form into object code. The command for this operation depends on whether the compiled form is in C programming language format or macro format.

Windows

If the text file is in C language format and the file name is empform.c, the following command translates the form into object code:

cl -c empform

The compform command automatically generates the correct header file include statement for a compiled form in C language format.

UNIX

If the text file is in C language format and the file name is empform.c, the following command translates the form into object code:

```
cc -c empform.c
```

If the symbol for the C language compiler at your installation is not cc, substitute the appropriate compiler symbol in place of cc.

The compform command automatically generates the correct header file include statement for a compiled form in C language format. \blacksquare

VMS

The command for this operation depends on whether the compiled form is in C programming language or macro format.

If the compiled form is in macro format in a text file named empform.mar, the following command translates it into object code:

```
macro empform.mar 🔳
```

Example

The following example compiles the employees form, which is stored in the projects database on a local node, into a C language data structure and places it in the empform.c file:

```
compform projects employees empform.c
```

If your database resides on a remote system—for instance, the projects database on the hq node—specify the database as hq::projects rather than projects.

Copyform

Copies a form, QBFName, or JoinDef from one database to another.

Syntax

To copy the object from the database to a text file:

```
copyform dbname|v_node::dbname[/server_class]
    form {form} | -q qbfname {qbfname} |
        -j joindef {joindef} filename [-s]
        [-uusername] [-Ggroupid]
```

To copy the object from the text file to the database:

If your database resides on a remote system, specify v_node , the name of the remote host. If you are using an Enterprise Access product, specify $/server_class$.

VMS

Enclose the -G*groupid* flag and parameter in double quotes ("-G*groupid*") to preserve the case of the -G flag. ■

Description

Moving forms from one database to another can be useful, particularly if you create a prototype application in one database and then move the application to another database in production mode. The copyform command invokes a VIFRED utility that copies a form, a QBFName, or a JoinDef from one database to another in a two-step process, as follows:

- 1. Use the first syntax of copyform to copy one or more forms, QBFNames, or JoinDefs from a database to a text file.
- 2. Use copyform with the -i flag, as in the second syntax, to copy the objects from the text file into a database.

You can also use copyform to change the ownership of a form, QBFName, or JoinDef. To do so, copy the desired object into a text file and then copy the form back into the database under a new owner.

Only one type of object (form, QBFName, JoinDef) can be specified in a single copyform statement.

When using copyform to copy a form, it does not copy any QBFNames or JoinDefs associated with that form. Similarly, when you copy a JoinDef, it copies only the JoinDef. When copying a QBFName, however, any forms and JoinDefs associated with that QBFName are copied, because these are part of the QBFName definition.

The following table lists valid flags and parameters:

Parameter	Description		
form	Name of the form(s) to be copied. You can specify up to 100 forms.		
-q qbfname	Flag and parameter that copies the specified QBFName (or multiple QBFNames), along with any forms and JoinDefs associated with the specified QBFName. The space between the -q flag and <i>qbfname</i> is required.		
-j joindef	Flag and parameter that copies the specified JoinDef (or multiple JoinDefs). The space between the -j flag and <i>joindef</i> is required.		

Parameter	Description		
filename	Name of the text file to which the objects are copied, or the name of the text file previously created by copyform containing the objects to be copied into the database.		
-i	Required flag for the input step, indicating that the contents of the named file are to be copied to the database		
-r	Flag that suppresses the verification prompt for overwriting existing objects. Overwrites any object in the database having the same name and owner as the object in the file.		
-S	Status message flag. Suppresses status messages.		

Copying Forms to a Text File

If you do not enter values for *dbname* or *filename*, the copyform command prompts you for the missing values.

If you do not specify a form name on the command line, copyform issues the following prompt:

Specify Forms? [y/n]

In response to this prompt, type y for yes. The copyform command then asks you for form names:

Form? (end with Return)

In response to this prompt, type the form names one at a time. To end a list of form names, press the Return key.

The copyform command begins to copy the forms from the database. At this point copyform is only copying the form's definition to a text file. The format of this text file is not useful for determining what is actually in the form. Most of the file consists of the entries from the system catalogs in text format. Because these catalogs are interdependent, do not alter or edit this file, or you can cause the irrecoverable destruction of the form.

Copying QBF Names and JoinDefs to a Text File

You can also use the copyform command to copy a QBFName or a JoinDef definition from a database to a text file. The -q flag causes copyform to treat any names typed on the command line as QBFNames or to prompt for only QBFNames. The -j flag causes copyform to treat any names typed on the command line as JoinDef names or to prompt only for JoinDef names.

When using the copyform command, you can specify only one class of names at a time. For example, you cannot specify a form name and a QBFName in the same command. If you specify only the database name and the text file name on the command line, copyform prompts you for the class of name that you enter:

Specify Forms? [y/n]

If you answer no to this prompt, copyform asks:

Specify Qbfnames? [y/n]

If you answer no to the QBFName prompt, copyform then asks:

Specify Joindefs? [y/n]

If you answer no to this prompt, the copyform command does nothing. Specify a form name, QBFName, or JoinDef name. To end a list of QBFNames or JoinDef names, press Return, just as you end a list of form names.

If you specify the -q flag on the command line, copyform prompts you only for QBFNames. If you specify the -j flag on the command line, copyform prompts you only for JoinDef names.

When copyform copies a QBFName from a database, it copies the QBFName definition, the form definition, and JoinDef (if applicable) referenced by the OBFName.

Copying Forms, QBFNames, and JoinDefs to a Database

Use the copyform command with the -i flag to copy forms, QBFNames, and JoinDefs from a file into the database. You can only copy in files that were previously created with the copyform command. The -i flag is a required parameter and tells copyform that this is an input operation.

The -r flag, if specified, suppresses the verification prompt for replacing existing forms, QBFNames, and JoinDefs. If one of these objects (form, QBFName, or JoinDef) exists in the database under the same name and owner, the -r flag tells Ingres to automatically overwrite the object. If the -r flag is not specified, you are prompted for verification before it overwrites any object.

Examples

In the following examples, if your database resides on a remote system—for instance, the projects database on the hq node—specify the database as hq::projects rather than projects.

Example 1

The following command line copies out a form called employees from the projects database into a text file called empform.txt:

copyform projects empform.txt employees

Example 2 The following command line copies out a JoinDef called emp_join from the

projects database into the empinfo.txt file:

copyform projects empinfo.txt -j emp join

Example 3 To force copyform to prompt you for a list of QBFNames from the projects

database, use the following command line:

copyform projects empdata.txt -q

Example 4 The following command copies the text file empform.txt into the newemp

database:

copyform -i newemp empform.txt

Copyrep

Allows you to copy Report-Writer report specifications from one database to another.

Syntax

copyrep dbname|v_node::dbname [/server_class] txtfile report {report}
[-f] [-s] [-uusername] [-Ggroupid]

If your database resides on a remote system, specify v_node , the name of the remote host where the database resides. If you are using an Enterprise Access product, then specify $/server_class$.

The -G groupid parameter must be enclosed in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

If the *username* or *groupid* is a delimited identifier, enclose it in double quotes ("), dereference any embedded quotes, and use the appropriate number and type of delimiting quotes to pass it through your operating system. For more information, see the *System Administrator Guide*.

Description

VMS

The copyrep command copies a report specification, or set of report specifications, from a database to a text file. You can then save the report specification in a different database with the sreport command.

The copyrep command also provides a method for externally storing the report specifications in simple files. It allows you to copy any number of report specifications to a single text file. The new copies of the reports are named within the file, but now contain no owner restrictions. Therefore, you can copy reports owned by one user from a database into a file and then copy them back into the database from the file as another user, effectively changing their owner.

If you omit any of the parameters except those preceded by a hyphen, the copyrep command prompts you for the missing values. If you do not specify any reports, the command prompts you for the reports to be copied. Enter the report names one per line, and end the prompted list of reports by pressing Enter or Return (without entering a report name on that line).

The following table contains the flags and parameters specific to copyrep command:

Parameter	Description	
txtfile	Name of a text file in which to write the report specifications.	
report	Name of one or more reports that are to be written to the text file.	
-f	Flag that writes the report out in the same format as the RBF Archive operation. For reports created with RBF, this strips out many of the RBF formatting instructions.	

The file created by this command is almost the same as the file created with the Archive operation accessed in the Reports Catalog frame of RBF. For reports originally created outside of RBF and saved with the sreport command, the output to the file created by the copyrep is identical to the RBF Archive operation, except that comments are stripped out.

For reports created in RBF, the copyrep command differs from the Archive operation in that it retains all information pertaining to RBF in the copied file, rather than removing any RBF formatting statements as the Archive operation does. However, although RBF statements are retained, once you have copied the report specification to a text file, it cannot be edited in RBF.

Use the -f flag to mimic the Archive method, which strips many of the RBF statements out of a RBF report, making it easier to edit in Report-Writer. However, if you use the -f flag, or if you use Report-Writer to edit a RBF report created by the copyrep command, you cannot edit the RBF report in future RBF sessions.

Example

Suppose you want to move a report that you own called emphours from the emp database into the newemp database, and assign it a new owner. The following statement performs the first part of the task, copying the report into a text file called emphours.rw:

copyrep emp emphours.rw emphours

The next part of the task uses the sreport command to copy the report in the text file emphours.rw into the database newemp under a different owner:

```
sreport newemp emphours.rw -uuser2
```

Note: You must be the DBA for the newemp database or have the security privilege to use the -u flag.

Delobj

Deletes from the database a specified object or all objects owned by the invoker or named user.

Syntax

```
delobj dbname|v_node::dbname [/server_class]
     [-report|-form|-joindef|-graph|-application|-qbfname]
     objectname{, objectname} [-wildcard] [-silent]
     [-include filename] [-uusername] [-Ggroupid]
```

or

```
delobj dbname|v_node::dbname [/server_class] -all
     [-silent] [-uusername] [-Ggroupid]
```

If your database resides on a remote system, specify *v_node*, the name of the remote host. If you are using an Enterprise Access product, specify */server_class*.

VMS

Enclose the -G groupid flag and parameter in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

Description

The delobj command deletes the specified object from the database. You can use this command to delete:

- A named object
- A list of objects that you specify on the command line
- All objects that match a wild card specification
- Several objects whose names are listed in a file

If you use the -all option, you can use only those parameters and flags specified in the alternative syntax for -all. Using any other parameters results in an error.

If you use the -wildcard flag, you can include the SQL wild card characters, underscore (_) and percent sign (%), in the objectname to specify pattern matching. To specify an explicit underscore or percent sign in an object name when the -wildcard flag is present, precede the character with a backslash (\) to dereference it. You can also use brackets ([]) to specify a pattern match. For more information on pattern matching, see the System Administrator Guide.

Use the -include filename option to specify an ASCII file you have previously created, which contains the names of objects to be deleted. This file can contain a static list of objects, or it can contain object names generated as output from a select statement that specifies date, value, or other criteria to determine which objects must be included in the list.

The file must adhere to the following format rules:

- Lines must be terminated by ASCII CR, LF, or FF characters.
- Line length must be 256 bytes or less; exceeding this limit produces unpredictable results.
- A line can contain any combination of object names, white space (tabs and spaces), and comment text.
- Object names must be delimited by white space or comments.
- Comment text must be introduced by a number sign (#) and continue to the end of the line. Nested comments and comments that span multiple lines are disallowed.

Parameter	Description		
objectname	Name of an object to be deleted.		
-wildcard	Allows the use of SQL wild cards in <i>objectname</i> . The default is to disallow wild cards.		
-include	Reads the names of objects to be deleted from the file specified by the <i>filename</i> parameter.		
filename	Name of an ASCII file containing the names of objects be deleted. Must be used in conjunction with the -incluoption, and must be preceded by a space.		
-silent	Suppresses status messages, but not prompts.		
-all	Deletes all reports, forms, joindefs, graphs, applications and QBFNames owned by the invoker or specified user.		

Examples

In the following examples, if your database resides on a remote system—for instance, the admin database on the hq node—you must specify the database as hq::admin rather than admin.

Example 1 Deletes a JoinDef named emptasks from the admin database.

delobj admin -joindef emptasks

Example 2 Deletes all objects owned by the invoker from the admin database.

delobj admin -all

Example 3 Deletes all forms that begin with the letters old from the admin database.

delobj admin -form old% -wildcard

Example 4 Deletes all reports listed in the oldrpts.txt file from the admin database.

delobj admin -report -include oldrpts.txt

Example 5 Some examples of possible entries in the oldrpts.txt file are:

Example of a comment in an included file oldrpt # Comment following a report name # Comment closely following a report name oldrpt sales_old # Deletes only the report, sales_old sales_1 # Deletes salesA1, sales B1, and so on # Deletes reports beginning with "sales" sales% sales\[1-9\] # Deletes reports sales1 through sales9 proj3 proj7 # Example of reports separated by a space rpt2 rpt1 # Example of reports separated by a tab

Ingmenu

Starts the Ingres Menu.

Syntax

ingmenu dbname|v_node::dbname[/server-_class] [-e] [-uusername] [-Ggroupid]

If your database resides on a remote system, specify v_node , the name of the remote host. If you are using an Enterprise Access product, specify /server_class.

VMS

Enclose the -Ggroupid flag and parameter in double quotes ("-Ggroupid") to preserve the case of the -G flag. 3

Description

Invokes the Ingres Menu, a forms-based interface for accessing any Ingres forms-based tool.

This table describes the flags and parameters you can use with the ingmenu command:

Flag	Description		
-e	Flag that invokes the command in expert mode, causing the catalogs to be displayed empty initially. This allows you to enter the name of a specific object directly, rather than select it from a list.		

Examples

Example 1 Invoke the Ingres Menu on the employee database:

ingmenu employee

Example 2 Invoke the Ingres Menu in expert mode with empty catalogs, on the projects

database on the hq node:

ingmenu hq::employee -e

Iquel

Starts Interactive QUEL (IQUEL) in the Interactive Terminal Monitor.

Syntax

If your database resides on a remote system, specify v_node, the name of the remote host. If you are using an Enterprise Access product, specify /server_class.

VMS

Enclose the -Ggroupid flag and parameter in double quotes ("-Ggroupid") to preserve the case of the -G flag.

Description

The iquel command invokes the forms-based Interactive Terminal Monitor for use with the IQUEL interactive query language. For more information on query languages, see your query language reference guide.

For valid iquel command flags, see the <u>Isql</u> command. They are the same for both commands.

Isql

Starts Interactive SQL (ISQL) in the Interactive Terminal Monitor.

Syntax

If your database resides on a remote system, specify v_node, the name of the remote host. If you are using an Enterprise Access product, specify /server_class.

VMS

Enclose the -G groupid flag and parameter in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

Description

The isgl command invokes the forms-based Interactive Terminal Monitor for use with the ISQL interactive query language. For more information on query languages, see the query language reference guide.

The following table lists valid SQL option flags that specify the format of output or affect the behavior of the DBMS. You can specify a maximum of 12 flags.

Flag	Description	
-c/V	Set the minimum field width for printing character columns to $\it N$. The default is 6.	
-fkxM.N	Set floating point output column width to M characters (total), including N decimal places, and (if warranted) $e+ -xx$ and the decimal indicator character itself. The value of k can be 4 for float4 or 8 for float8. The value of x can be E, F, G or N (uppercase or lowercase) to specify an output format. E indicates exponential format. F or N indicates the floating point format. G indicates the floating point format and guarantees decimal alignment.	
	If you specify F, N, or G and the number is too large for the format indicated by the flag, it is displayed in exponential format. To prevent this format overflow, M must be greater than or equal to $N+7$.	
	The default display format for both float4 and float8 is n10.3, unless your computer supports the IEEE standard for floating point numbers, in which case the display format for float4 and float8 is n11.3.	
-i <i>kN</i>	Set integer output column width to N. The value of k can be 1, 2, or 4 for integer1, integer2, or integer4, respectively. The default for N is 6 for integer1 and integer2 fields, and 13 for integer4 fields.	
-t <i>N</i>	Set the minimum field width for printing text columns to $\it N$. The default is 6.	
-1	Locks the database for your exclusive use so that no one else can open the database while you are in it. If you attempt to take an exclusive lock on a database that is in use, the system informs you that the database is temporarily unavailable.	
-n <i>M</i>	Sets modify mode on the index command to <i>M. M</i> must be one of the following storage structures: isam, cisam, btree, cbtree, hash and chash. The default is isam.	

	Flag	Description
	-Rroleid	Specifies a role identifier for the session and applies the role identifier's permissions to your session. The system administrator defines a role identifier; the DBA grants database permissions to the role ID.
		The <i>roleid</i> must be an existing role identifier. If the role identifier requires a password, you are prompted for the password. If you specify the -R flag but omit both the role identifier and password, you are prompted for both. If no password is defined for the specified <i>roleid</i> , press the Return key when prompted for the password.
		Ingres does not validate either roleid or password if you are a system administrator, DBA for the specified database, or a user that has the db_admin privilege.
VMS		This flag must be specified in double quotes: "-Rroleid"
	+U -U	Enables/disables user updating of the system catalogs and secondary indexes. This flag takes an exclusive lock on the database. To update system catalogs, you must have the update system tables privilege obtained through accessib.
VMS		This flag must be specified in double quotes: "+U" "-U" ■
	+ W - W	Specifies wait/don't wait for the database. If you specify +w, Ingres waits, provided that certain processes are running (sql-l, sql-U, verifydb, rollforwarddb or sysmod) on the given database. Upon completion of those processes, Ingres proceeds. If you specify -w and the database is not available, a message is returned and execution is stopped. If you omit the w flag and the database is unavailable, then an error message is returned if Ingres is running in the foreground (more precisely, if the standard input is from a terminal). Otherwise, the wait option is invoked.
VMS		This flag is not valid in batch mode. The flag defaults to -w.
	-xk	Sets arithmetic handling mode. The value of k must be f or w. An f indicates that all arithmetic exceptions (floating overflow and underflow, integer overflow and divide by zero) must be treated as fatal errors. In this mode, the detection of an arithmetic exception terminates query processing. A w indicates that warning messages must be generated for arithmetic exceptions. In this mode, the query is run to completion, and a summary of exceptions detected is generated. The default condition is to ignore exceptions.

Flag	Description
+Y -Y	Same as +U -U flag, except does not take an exclusive lock on the database.
	Specify this flag in double quotes: "+Y" "-Y" ■

VMS

Examples

Example 1 Invoke ISQL in the Interactive Terminal Monitor on the employee database

on the hq remote node:

isql hq::employee

Example 2 Open the empdata database on a local node.

isql empdata

Example 3 Open empdata, display float4 columns in G format with two decimal places

and integer1 columns with three spaces.

isql -f4g12.2 -i13 empdata

Printform

The printform command places an image and description of a form and its fields into a text file.

Syntax

If your database resides on a remote system, specify v_node , the name of the remote host. If you are using an Enterprise Access product, specify $/server_class$.

VMS

Enclose the -G groupid flag and parameter in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

Description

The printform command works like the Print operation on the Utilities submenu of the Forms Catalog frame (described in the section, Printing Forms, of the chapter "Using VIFRED"). It sends an image and a description of a single form to a text file. To send a copy of the file to your printer, use your operating system print commands.

The image sent to the text file contains all fields on the form, including those that have been assigned the Invisible attribute.

Refer to Attributes in the Set List for an explanation of the Invisible attribute.

Parameter	Description
filename	Name of a text file to which the image of the form is sent.

Example

The following example prints the employees form, which is stored in the projects database on a local node, into the emp.prf file:

printform projects employees emp.prf

If your database resides on a remote system—for instance, the projects database on the hq node—specify the database as hq::projects rather than projects.

Qbf

Starts QBF.

Syntax

```
qbf dbname|v_node::dbname [/server-type] [-mmode]
  [-t] |-f | -j | -l [querytarget] [-e] [-s]
  [-uusername] [-Ggroupid]
```

If your database resides on a remote system, specify v_node , the name of the remote host. If you are using an Enterprise Access product, specify $/server_class$.

VMS

Enclose the -G groupid flag and parameter in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

Description

The system-level qbf command starts QBF. QBF is an interactive, visually oriented system for querying and manipulating data in tables in an Ingres database.

The database name specified in a qbf command line must already exist.

If you specify a valid database but do not specify a query target, QBF starts in the query definition phase at the Start-Up frame.

If you specify a valid database, a query target, and appropriate command line flag, QBF starts in the query execution phase. A frame is displayed that is appropriate for the query target you specified.

If you specify a query target on the command line, you must own all the tables that underlie the query target or have the proper permissions to access them. If you specify a JoinDef for the query target, you or the database administrator must own it.

Use the qbf command with a specific mode flag (-mappend, -mupdate, or -mretrieve) to enter and remain in a particular query execution function. In this situation, you must also include a *querytarget* flag in the qbf command.

Use qbf without a mode flag to give yourself access to all query execution functions (Append, Retrieve, Update), and the ability to switch query targets or return to the Start-Up frame or query definition phase.

Use the -t query target flag to specify that data be displayed in table format.

Parameter	Description
-mmode	Mode flag. Bypasses the query definition phase of QBF, going directly to a function of query execution, where mode is retrieve, append, update, or all. The all mode is the default mode, which allows you to perform the Append, Retrieve, and Update functions.
	If you use the -m <i>mode</i> flag, you must also specify a query target. If you use the -m <i>mode</i> parameter and fail to specify a query target on the command line, QBF prompts you for the query target name.
-t	Table flag. This is the default flag if no query target flag is specified. It specifies that the query target is a table, starts QBF with the specified table, and specifies that the table-field format can be used to query the table. If a query target is not specified, using the -t flag causes QBF to begin operation by displaying the Tables catalog.

Parameter	Description
-f	Form flag. Specifies that the query target is a QBFName and starts QBF with the specified custom form. If a query target is not specified, using the -f flag causes QBF to begin operation by displaying the QBFName catalog.
-j	JoinDef flag. Specifies that the query target is a JoinDef and starts QBF with the specified JoinDef. If a query target is not specified, using the -j flag causes QBF to begin operation by displaying the JoinDef catalog.
-1	Look flag. Specifies that QBF must look for the query target first among QBFNames, then among JoinDefs, and last among tables. If you use the -I flag without specifying a query target, QBF prompts you for the query target name.
querytarget	Starts QBF in the query execution phase and specifies the table, view, synonym, JoinDef, or QBFName that you want to query. If you do not specify a querytarget, QBF starts in query definition phase. If the query target is a table, view, or synonym, you can qualify it with a valid schema name in the format, schema.querytarget. If the table name, view name, or synonym is a delimited identifier, enclose it in double quotes.
-e	Flag that invokes the command in expert mode, causing the catalogs to be displayed empty initially. This allows you to enter the name of a specific object directly, rather than select it from a list.
-S	Status message flag. Suppresses status messages, but not prompts.

Examples

Example 1 Start QBF in append mode on a custom form in the newdb database on a local node:

qbf newdb -mappend -f myform

Example 2 Retrieve rows from the projtasks JoinDef of the operations database on the hq remote node:

qbf hq::operations projtasks -j -mretrieve

Query

Starts the query execution phase of QBF.

Syntax

If your database resides on a remote system, specify v_node, the name of the remote host. If you are using an Enterprise Access product, specify /server_class.

VMS

Enclose the -G groupid flag and parameter in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

Description

The system-level query command starts the query execution phase of QBF. The database name specified in a query command line must already exist.

The flags and parameters for the query command are the same as for the qbf command, except that querytarget is a required parameter. Unless you specify otherwise with the -t, -f, or -j flag, the query command uses the same order for looking up the query target as the -l flag in the qbf command: QBFName, then JoinDef, then table. Use the query or the qbf command with a specific mode flag (-mappend, -mupdate, or -mretrieve) to enter and remain in a particular query execution function. Use the query command without the -mmode flag to access all query execution functions (Append, Retrieve, Update) for the specified query target.

Examples

Example 1 Start QBF in append mode using the newdb database on a local node and a query target that is a JoinDef:

query newdb -mappend -j staffinfo

Example 2 Update records with the projtasks JoinDef of the operations database on the hq remote node:

query hq::operations projtasks -j -mupdate

Rbf

Starts RBF.

Syntax

If your database resides on a remote system, specify v_node , the name of the remote host. If you are using an Enterprise Access product, specify $\textit{/server_class}$.

Enclose the -G groupid flag and parameter in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

VMS

Parameter	Description
reportname	Name of an existing report specification, as saved during a previous Reprt-By-Forms session.
schema	Valid name of the schema to which the table, view, or synonym belongs. If the schema name is a delimited identifier, enclose it in double quotes. For information on passing these quotes through the operating system, see the <i>System Administrator Guide</i> for the system on which your database resides.
tablename	Name of the table, view, synonym, or JoinDef on
viewname	which you want to base the report. If you do not specify a report, table, view, synonym, or JoinDef
synonym	name on the command line, RBF prompts for one. If
JoinDef	the table name, view name, or synonym is a delimited identifier, enclose it in double quotes. For information on passing these quotes through the operating system, see the <i>System Administrator Guide</i> for the system on which your database resides.

Parameter	Description
-r	Indicates that the name specified after dbname is a report rather than a table or view.
	If RBF finds a report specification for the specified report, it places you in the Report Layout frame, where you can edit the report specification. If RBF does not find a report specification of the specified name, it displays an error message.
-m[<i>style</i>]	Indicates that the name specified after dbname is a table or view name, rather than a report specification name. RBF creates a default report specification for the specified table or view.
	To specify the style of your report, use the optional style parameter. The style can be tabular, column, block, labels, indented, or default. The column style is the same as the tabular style. You cannot specify the Master/Detail report style on the command line.
	If you do not specify a style or if you choose the default style, RBF selects tabular or block, depending on the width of your report. If all the report columns fit on a page, it selects tabular; otherwise, it selects block. When determining the default style, RBF uses 132 characters as the default report width. To specify a wider report, use the -I flag.
	If you do not use the -r or -m flag, RBF searches first for a report specification, and then a table or view, of the specified name. If it finds a report specification, it places you in the Report Layout frame. If it finds a table or view, it creates a report specification for it. If RBF does not find a report, table, or view of the specified name, it displays an error message.
-lpagewidth	Directs RBF to use the page width (line length) specified by <i>pagewidth</i> when generating default reports. By default, RBF uses a page width of 132 characters for the labels style, and 80 characters for the block style, 100 characters for the wrap style. All other styles have no default page width. If you do not specify a page width for these styles, RBF makes the report as wide as necessary to accommodate the data.
	If you execute a report specification that contains a Report-Writer .pagewidth statement, the report width specified with the -I flag overrides it.

Parameter	Description
-e	Flag that invokes the command in expert mode, causing the catalogs to be displayed empty initially. This allows you to enter the name of a specific object directly, rather than select it from a list.
-S	Status message flag. Suppresses informational messages, but not prompts.

Examples

Example 1 Start RBF for the sales table in the newdb database on the hq remote node:

rbf hq::newdb sales

Example 2 Start RBF for the emp table owned by hr (Human Resources) in the personnel

database on a local node and create a default Tabular report that is 200

characters wide:

rbf personnel hr."perm emp" -mtabular -1200

For information on passing the delimited identifier's surrounding quotes through your operating system, see the *System Administrator Guide* for the

system on which your database resides.

Example 3 Start RBF for the emp table in the personnel database on a local node and

create a default report specification, letting RBF choose the Tabular or Block

style, depending on the width of the report:

rbf personnel emp -m

Example 4 Start RBF for emp table in the personnel database on a local node and create

a Labels report:

rbf personnel emp -mlabels

Example 5 Start RBF for the personnel database on a local node and display the emplist

report specification for editing:

rbf personnel emplist -r

or

rbf personnel emplist

If you do not use either the -r or -m flag, Rport-By-Forms searches for a report specification first, and then a table or view, of the specified name.

Report

Executes a report specification for Report-Writer.

Syntax

report dbname | v node::dbname | / server class | reportname | [schema.]tablename | [schema.]viewname | [schema.]synonym [(variablename=value{, variablename=value})] [-foutputfile] [-oprinter [-ncopies]] [-r | -m[style] | -ireportspecfile] [-uusername] [-Ggroupid] [-lpagewidth] [-vpagelength] [**-q**mxquer] [**-w**mxwrap] [-d] [-s] [-h] [-5] [-6] [+b|-b] [-nofirstff | -firstff] [+t|-t]

If your database resides on a remote system, specify v node, the name of the remote host where the database resides. If you are using an Enterprise Access product, then specify /server class.

If the (variablename=value) parameter includes characters that are treated specially by your operating system (such as parentheses in Windows NT and UNIX or slashes in VMS), the entire parameter must be enclosed within double quotes to pass it through the operating system. For details, see Passing Parameters on the Command Line in this chapter.

Windows

Enclose the (variablename=value) parameter within double quotes.

UNIX

Execute this command from the Bourne shell and enclose the (variablename=value) parameter within double quotes.

VMS

Enclose the -Ggroupid parameter in double quotes ("-Ggroupid") to preserve the case of the -G flag.

If any parameter is a delimited identifier, specify it in editable format. For more information, see Specifying Delimited Identifiers. Also, use the appropriate number and type of delimiting quotes to pass it through your operating system. For more information, see Passing Delimited Identifiers later in this chapter.

Description

The report command executes the report specifications that correspond to the reportname parameter in the .name statement or to a default report for a table in the database.

This command actually produces the report. When you type the report command at your screen, the following actions occur:

- Report-Writer checks the report system catalogs to see if a report of the given name is stored in the database. If one is found, it reads the specifications for the report and checks for errors. If errors occur, it does not run the report.
 - If no report with the given name is found, the name is assumed to be a table name, view name, or synonym referring to a table. Report-Writer formats a default report for the specified table and executes it. If no table or report with the given name is found, an error message appears on the screen.
- 2. If the specification is error-free, Report-Writer replaces variables for the setup and layout statements with their specified values. Then it runs the .query statement in your report specification (if specified) and extracts the report data.
- 3. Finally, Report-Writer sorts the report data, if required, and formats and outputs the report. If no report with the given name is found, the name is assumed to be a table name. Report-Writer formats a default report for the specified table and runs it. If no table or report with the given name is found, an error message appears on the screen.
- 4. If any column in the table on which the report is based is of an unsupported data type, such as long varchar, byte, byte varying, and long byte, Report-Writer ignores and does not print that column when printing the report.

Note: If Report-Writer encounters subsequent references to a column of an unsupported data type, such as in sort operations, it issues an error message and terminates the report.

Report-Writer prompts you for *reportname*, *dbname*, and values for any variables declared with prompts or undeclared variables, if you have not already specified their values on the command line. If specified, you must place the *dbname*, the *reportname*, *tablename*, *viewname*, or *synonym*, and any *variablename=valuestring* parameters in the order shown previously in the Syntax section.

You can qualify the table, view, or synonym name as belonging to another user by specifying it as *schema.objectname*.

You can specify the following parameters as delimited identifiers enclosed in double quotes (") if recognition of delimited identifiers has been enabled in the report specification with the .delimid statement:

- schema
- tablename, viewname, or synonym
- value in the variablename=value clause

The -r and -m flags are especially useful if you have reports and tables with the same name and must be more specific about which you want. Use the -r flag to force Report-Writer to only check for reports with the name you specify. Use the -m flag to force Report-Writer to only check for tables with the name you specify. For further details, see the following table.

Additionally, you can use the -m flag to specify the style of default report to be produced.

The following parameters are specific to the report command:

Parameter	Description
reportname	Name of a report that appears in a .name statement in a report specification that has been stored in the Reports Catalog. A report name cannot be specified if you are using the -i flag.
schema	Collection of objects to which the table, view, or synonym belongs. The schema also implies the user that owns the object. Must be followed immediately by a period (.) and the appropriate object name, with no intervening space. If it is a delimited identifier, specify it in its editable format. For more information, see Specifying Delimited Identifiers . For instructions on passing the delimited identifier and its quotes through your operating system, see Passing Parameters on the Command Line .
tablename viewname synonym	Name of the table or view, or a synonym for a table, in your database on which the report is based. If it is a delimited identifier, specify it in its editable format. For more information, see Specifying Delimited Identifiers . For instructions on passing the delimited identifier and its quotes through your operating system, see Passing Parameters on the Command Line . A table, view, or synonym name cannot be specified if you are using the -i flag.
variablename	Name of a variable used in the report specification. This variable can either be used in the specified query or referred to in a Report-Writer statement. Variable/value combinations on the command line must be separated by blanks, commas (,) or tabs. Specify a space (or tab) before the opening parenthesis of the variable/value list.

Parameter	Description
value	Value that replaces every occurrence of the corresponding variable name in the report specification. If <i>values</i> is a delimited identifier, specify it in its editable format. For more information, see the <u>Specifying Delimited Identifiers</u> . If <i>value</i> is a string, date, or delimited identifier, enclose the entire value within single or double quotes (as appropriate for your query language). Report-Writer removes the quotes when it processes the string. For more information about passing values to Report-Writer, see <u>Passing Parameters on the Command LinePassing Parameters on the Command LinePassing Parameters on the Command Line.</u>
-foutputfile	Flag that directs the formatted report to <i>outputfile</i> for subsequent output. If you do not specify an output file with this option, the -f flag writes the report to the file specified in the .output statement in the report specification file. If you specify neither <i>outputfile</i> nor a file in the .output statement, the -f flag writes the report to your screen.
-oprinter [-ncopies]	Flag requesting that the report be sent to the specified printer. If you do not specify a printer with this flag, Report-Writer assumes the following default system print command to send the report to the default printer: print
UNIX	The UNIX default system print command is lpr. $ eals$
	Because Report-Writer creates a temporary file to print the report, additional memory can be required for printing large reports. Report-Writer deletes the file as soon as it prints the report.
VMS	We recommend that you initialize the printer queue to print the job flag page, which includes the name of the report. Otherwise, the flag page prints the temporary file name. Because this file name has no connection to the report name, it is difficult to distinguish a report by the flag page. For ease of use, you can initialize a printer queue specifically for reports.
-r	Flag indicating that the name specified after <i>dbname</i> is a report rather than a table, view, or synonym. If it does not find a report with the given name, Report-Writer displays an error message. If -r is not specified, it looks for a report of the given name, and if none is found, and a table, view, or synonym of the given name does exist, Report-Writer sets up a report for the specified table.

Parameter	Description
-m[style]	Flag indicating that the name specified after <i>dbname</i> is a table or view name, or a synonym for a table, rather than a report. Report-Writer formats a default report for the specified table and does not check first for a report of the same name.
	To specify the style of your report, use the optional <i>style</i> parameter. The <i>style</i> can be wrap, tabular, column, or block. The column style is the same as the tabular style.
	If you do not specify a style, Report-Writer chooses either tabular or block, depending on the width of your report. If all of the report columns fits on one page, it selects tabular; otherwise, it selects block. When determining the default style, Report-Writer uses 132 characters as the default report width. To specify a wider report, use the -I flag.
	If neither the -r nor the -m flag is specified, Report-Writer looks first for a report of the given name. If not found, it looks for a table, view, or synonym of that name, and if one exists, sets up a default report for the specified table.
-ireportspecfile	Flag and parameter requesting that Report-Writer run the report using the report specifications found in the specified source file. When you use this flag, Report-Writer does <i>not</i> save the specified source file in the database. If you want to save the report specifications in the database, use the sreport command to place the report source file in the database.
	The specified file can contain report specifications for only one report; however, the report can contain .include statements that include other files when saving the report. This flag cannot be used in conjunction with the -m or -r flag. Additionally, if you use this flag, a report, table, view, or synonym name cannot be specified on the command line.
- I pagewidth	Flag and parameter that sets <i>pagewidth</i> as the maximum number of characters for each line of output. The <i>pagewidth</i> must be a positive integer. This flag overrides the .pagewidth statement in the report specification file. By default, Report-Writer uses a line length of 80 characters for the block style, and 100 characters for the wrap style. The tabular and column styles have no default line length. You need this option only if your report contains unusually long lines.

Parameter	Description
- v pagelength	Flag and parameter that sets <i>pagelength</i> as the number of lines for each page of output. The <i>pagelength</i> must be a positive integer. This flag overrides any .pagelength statement in the report specification file. The default is 61 lines per page if the report is written to a file.
Windows	Add .formfeed to the header page, or start the report with the +b option to control the lines per page. \blacksquare
UNIX	If written to a screen, the report defaults to your screen length per page. \blacksquare
- q mxquer	Flag and parameter that sets the maximum length of the query specified in the .query statement, after all substitutions for runtime parameters have been made. By default, the maximum query size is 2048 characters. You need this option only for particularly long queries.
- w mxwrap	Flag and parameter that sets the maximum number of lines allowed within an invocation of the .block statement. By default, 310 .newline statements are permitted. This maximum is provided as a protection against misspecified columns, and is rarely needed.
	To protect against omitted explicit .newline and/or .newpage statements, data that formats into a single logical line can wrap to yield a default maximum of 310 or <i>mxwrap</i> lines.
-d	Flag requesting that the report continue to run even if .setup or .cleanup statement errors are detected by the DBMS. However, the -d flag does not affect error handling. For example, if Report-Writer is unable to access a table required for the report, the report fails because it could not find the table for the query.
	The -d flag is particularly useful if you are required to run reports iteratively for development or testing purposes. In such cases, you can be aware of the errors, but choose to bypass them for the time being.
	For details on error handling and transactions, see the rules for the .setup and .cleanup statements in the chapter "Report-Writer Statements."

Parameter	Description
-h	Flag providing a null set of data for a report that retrieves no rows. Report-Writer executes all .header and .footer sections, but suppresses the .detail section. This feature allows you to include the following .if statement in the report footer to output a positive acknowledgment that no rows were found:
	<pre>.if count(column) = 0 .then .println 'No data matched the query specifications.' .endif</pre>
-5	Flag requesting report compatibility with Ingres release 5, if available at your installation. The default is that the flag is not specified.
	If the -5 flag is set, the + -t option defaults to +t to ensure compatibility. The +t option requests that Report-Writer use floating-point arithmetic in all computations except those involving only integer-valued columns. Report-Writer converts integer values to floating point before using them in computation. For expressions that involve only integer columns, convert the columns explicitly to get floating point arithmetic.
	The month part of the current_date function appears in uppercase if no format is specified. Normally, the system displays the month names in lowercase letters. For example, if the -5 flag is set, what is now displayed as "01-feb-1998" is displayed as "01-FEB-1998".
-6	Flag requesting that Report-Writer report distinct rows when executing SQL default reports or SQL reports that contain *data, .table, .view, or .sort statements. Without -6 specified, Report-Writer reports duplicate rows in the SQL reports previously described. The -6 flag does not apply to QUEL reports, which always retrieve distinct rows.
-b +b	Flag that forces or suppresses formfeeds by overriding any .formfeed or .noformfeed statement occurring in the report specification file. If turned on (+b), it forces formfeeds at the end of each page. If turned off (-b), it suppresses formfeeds for the end of each page. For more information on the -nofirstff and -firstff flags, see the following description.

Parameter	Description	
-nofirstff -firstff	Mutually exclusive flags that specify whether an initial formfeed is suppressed, only when formfeeds are enabled. The -nofirstff flag suppresses the initial formfeed, if formfeeds are enabled. The -firstff flag specifies an initial formfeed only by overriding a .nofirstff statement in the report specification when formfeeds are enabled; it cannot enable an initial formfeed by itself. Specify only one of these flags on the command line; specifying both generates a fatal error.	
-t +t	Flag that specifies whether actual or rounded values must be used in aggregates. If turned on (+t), causes aggregates to occur over rounded values for any floating point column whose format has been specified in a .format statement as numeric F or template. Each value in the column is rounded to the precision given by its format. If turned off (-t), aggregates use the actual underlying values. The -t flag is the default.	

Examples

Example 1 Run a default report based on the vendor table in the purchasing database,

using a default format and redefining the page width, and send the output to

the named printer:

report purchasing vendor -m -180 -olaser2

Example 2 Run the report contained in the source file, po_rep.rw, against the

purchasing database and store the results in the po_sum.out file:

report purchasing -ipo_rep.rw -fpo_sum.out

Example 3 Run a default report in column format on the clients table owned by mktgmgr

in the sales database and eliminate duplicate rows:

report sales mktgmgr.clients -mcolumn -6

Example 4 Run the report named recpay against the accounting database and pass in

the value of the variable, title:

report accounting recpay
 (title = 'AccountsReceivable')

For more parameter passing examples, see the following section, <u>Passing Parameters on the Command Line</u>.

Passing Parameters on the Command Line

This section describes how to pass parameters to Report-Writer from the command line for reports based on SQL queries. You cannot pass parameters that contain delimited identifiers on the command line if your report specification contains a QUEL query.

If necessary, for details on debugging your query, see the section on the II_EMBED_SET printgry option in your *System Administrator Guide*.

Passing Numeric Variables

Suppose your report specification contains the following code:

```
.declare deptno = integer
.query select firstname, lastname, deptid from employees
       where deptid = $deptno
```

To pass in a value for the numeric variable, \$deptno, on the command line, enclose the *variablename=value* clause in parentheses ():

Windows **VMS**

UNIX

report personnel emp (deptno=504) report personnel emp "(deptno=504)" 3

Note for QUEL Users

Regardless of whether your report specification uses an SQL or a QUEL query, you pass values for numeric variables in the same way. Your report specification code would look like this for QUEL:

```
.declare deptno = integer
.query
range of e is emp
retrieve (e.firstname,e.lastname,e.deptid)
        where e.deptid = $deptno
```

Passing String and Date Variables

The report specification must enclose the string and date variables, \$dname and \$ddate, in quotes that are appropriate for your query language (in this case, single quotes for SQL), as shown in the following example:

```
.declare dname = varchar(20),
         ddate = date
.query select firstname, lastname, deptid from employees
     where deptname = '$dname' and hiredate >= '$ddate'
```

The previous example retrieves data for employees in the named department, \$dname, who were hired on or after a specified date, \$ddate.

If the variable is quoted appropriately for your query language (single quotes for SQL or double quotes for QUEL) in the report specification, use the following syntax for specifying a string or date value on the report command line:

report dbname tablename (variablename='value')

Each string or date value must be enclosed in single quotes to identify it to Report-Writer as a string. Report-Writer strips off these quotes before assigning the value to the variable in the query. Additionally, enclose the entire *variablename=value* clause in parentheses (). If it contains any characters treated specially by your operating system (such as parentheses in Windows NT and UNIX or slashes in VMS), the parenthetical clause must be enclosed within double quotes to pass it through the operating system.

For example:

```
report personnel emp "(dname='BL', ddate='01/01/98')"
```

If the report specification omits the query language-specific quotes around the variable (for example, where deptname = \$dname instead of where deptname = '\$dname'), these quotes must be supplied to the query. To do so, include them in the string or date value on the command line within the single quotes required to identify the string to Report-Writer. You must dereference the embedded single quotes required by SQL. To dereference single quotes within a single-quoted string you double them ("). Additionally, if the parenthetical clause contains characters special to your operating system, enclose the entire parameter within double quotes. For example:

Note for QUEL Users

The report specification must enclose the string and date variables, \$dname and \$ddate, in double quotes for QUEL, as shown in the following example:

This example retrieves data for employees in the named department, \$dname, who were hired on or after a specified date, \$ddate.

If the report specification omits the query language-specific quotes around the variable (for example, where e.deptname = \$dname as opposed to where e.deptname = "\$dname"), these quotes must be supplied to the query by including them within the string or date value on the command line, inside the single quotes that identify the string to Report-Writer. Additionally, if the parenthetical clause contains characters special to your operating system, enclose the entire parameter within double quotes and escape any double quotes within the parameter according to the rules for your operating system.

Windows

In Windows NT, you escape double quotes by preceding them with a backslash (\). For example:

```
report personnel emp "(dname='\"BL\"',
   ddate='\"01/01/91\"')" I
```

UNIX

In UNIX, you escape double quotes by preceding them with a backslash (\). For example:

```
report personnel emp "(dname='\"BL\"',
    ddate='\"01/01/91\"')" 3
```

VMS

In VMS, you escape double quotes by preceding them with another double quote. For example:

```
report personnel emp "(dname='""BL""',
   ddate='""01/01/91""')" 3
```

Passing an Entire Where Clause

In the following examples, the where clause itself is a variable for the report. You pass the entire where clause to Report-Writer from the operating system command line in the variablename=value clause. The .query section in the report specification might look like this:

```
.QUERY select * from tablename where $wherevar
```

In this case, the value in the variablename=value syntax is a string containing the search qualifications. Enclose valuestring in single quotes to identify to Report-Writer as a string, as shown in the following example:

```
report accounting recpay (wherevar='valuestring')
```

If the parenthetical clause contains characters special to your operating system, enclose the entire parameter within double quotes:

```
report accounting recpay "(wherevar='valuestring')"
```

The valuestring can include a variable and a value. If the value in the valuestring is a character string or date, it must be enclosed in quotes that are appropriate for your query language (single quotes for SQL). Dereference single quotes within the single-quoted valuestring by doubling them (").

For instance, in the following example enclose the date string, 12/31/98, in a double set of single quotes to dereference them inside the quotes surrounding the valuestring:

```
report accounting recpay
        (wherevar='date = ''12/31/98''')
```

If your operating system requires it, enclose the entire parameter within double quotes:

```
report accounting recpay
         "(wherevar='date = ''12/31/98''')"
```

The resulting valuestring is:

```
date = '12/31/98'
```

Note for QUEL Users

The entire where clause is passed to Report-Writer from the operating system command line in the variablename=valuestring clause. The .query section in the report specification might look like this for QUEL:

```
.QUERY retrieve tablename.all where $wherevar
```

The valuestring can include a variable and a value. If the value in the valuestring is a character string or date, it must be enclosed in quotes that are appropriate for your query language (double quotes for QUEL). For instance, in the following example enclose the date string, "12/31/93" in double quotes within the single-quoted valuestring:

```
report accounting recpay
            (wherevar='date = "12/31/98"')
```

If your operating system requires it, enclose the entire parameter within double quotes and escape any embedded double quotes.

To dereference double quotes in Windows NT, precede them with a backslash (\). For example:

```
report accounting recpay
    "(wherevar='date = \"12/31/98\"')" 🍱
```

To dereference double quotes in UNIX, precede them with a backslash (\). For example:

```
report accounting recpay
   "(wherevar='date = \"12/31/98\"')" ■
```

To dereference double quotes in VMS, double them. For example:

```
report accounting recpay
"(wherevar='date = ""12/31/98""')" 3
```

The resulting valuestring is:

```
date = "12/31/98"
```

Windows

UNIX

VMS

Passing Multiple Parameters

To pass multiple parameters in a where clause, you follow the same rules for the use of parentheses and quotes as described in the Passing an Entire Where Clause section. For example, suppose your report specification contains the following code:

```
.declare wherevar = varchar(100)
.query select * from employees
       where $wherevar
```

You would enter the following command on the command line:

```
report personnel emp (wherevar='deptid=504 and
        mgr=''Jones'' and hiredate>=''01/01/95''')
```

If your operating system requires it, enclose the entire parameter within double quotes:

```
report personnel emp "(wherevar='deptid=504 and
        mgr = ''Jones' and hiredate >= ''01/01/95''')"
```

Note for QUEL Users

To pass multiple parameters in a where clause, follow the same rules for the use of parentheses and quotes as described in the Passing an Entire Where Clause section. For example, suppose your report specification contains the following code:

```
.declare wherevar = varchar(100)
.query range of e is emp
        retrieve (e.all)
        where $wherevar
```

You would enter the following command on the command line:

```
report personnel emp (wherevar='deptid=504 and
        mgr="Jones" and hiredate>="01/01/91"')
```

If your operating system requires it, enclose the entire parameter within double quotes and escape any embedded double quotes:

```
report personnel emp (wherevar='deptid=504 and
    mgr="Jones" and hiredate>="01/01/91"')
report personnel emp "(wherevar='deptid=504 and
    mgr="Jones" and hiredate>=\"01/01/91\"')"
report personnel emp "(wherevar='deptid=504 and
    mgr="Jones" and hiredate>=""01/01/91""')"
```

Windows





Passing Delimited Identifiers

Suppose the value in the valuestring is a delimited identifier. For example, you want a list of employees with some other information about each employee that is to be determined at runtime by entering a column name.

To accomplish this, your report code looks like this:

```
.declare info = varchar (20)
.query select firstname, lastname, $info as otherinfo
    from emp
```

The information you want to select from the database is in a column whose name is a delimited identifier.

To specify the delimited identifier as a value on the command line, you must:

1. Specify the column name as a delimited identifier in editable format. For more information, see Specifying Delimited Identifiers.

```
"phone #"
```

2. Enclose the delimited identifier and its surrounding quotes within single quotes to identify it to Report-Writer as a string value in the *variable=value* clause:

```
info='"phone #"'
```

3. Enclose the *variable=value* clause in parentheses. If the parameter contains any characters treated specially by your operating system (such as parentheses in Windows NT), enclose the entire parameter within double quotes and escape any embedded double quotes to pass them through the operating system.

Windows

Escape the double quotes surrounding a delimited identifier by preceding them with a backslash (\):

```
report personnel emp "(info='\"phone #\"')" ■
```

UNIX

Escape the double quotes surrounding a delimited identifier by preceding them with a backslash (\):

```
report personnel emp "(info='\"phone #\"')"
```

VMS

Escape the double quotes surrounding a delimited identifier by preceding each with another double quote:

```
report personnel emp "(info='""phone #""')" 🍱
```

For more information on how to pass delimited identifiers on the command line, see the *System Administrator Guide*.

Passing String Values with Embedded Quotes

Suppose the database value for which you are entering a comparison *value* contains embedded single or double quotes, as for example:

```
"Big John's" Barbecue
```

Suppose the where clause is specified in the report as:

```
where $wherevar
```

You want to specify a value for the variable so that Report-Writer produces the following SQL query:

```
where clientname='"Big John''s" Barbecue'
```

Follow this procedure:

1. Determine how the value appears in the database:

```
"Big John's" Barbecue
```

2. Enclose the string value in quotes that are appropriate for your query language (single quotes in SQL). Dereference any embedded quotes (including apostrophes) according to the rules of your query language (in SQL, precede a single quote or apostrophe with another single quote):

```
'"Big John''s" Barbecue'
```

3. Enclose the entire *valuestring* within single quotes to identify it to Report-Writer as a string. Dereference any embedded single quotes within this string by preceding each single quote with another single quote. This includes any single quotes (or apostrophes) from the original value, as well as those required by your query language in the previous step.

```
'clientname=''"Big John''''s" Barbecue'''
```

4. Enclose the entire parameter within parentheses. If the parameter contains any characters treated specially by your operating system (such as parentheses in Windows NT and UNIX or slashes in VMS), enclose the entire parameter within double quotes and escape any embedded double quotes to pass them through the operating system.







```
report accounting receivables "(wherevar=
'clientname=''\"Big John''''s\" Barbecue"''')" ■
report accounting receivables "(wherevar=
'clientname=''\"Big John''''s\" Barbecue"''')"
report accounting receivables "(wherevar=
'clientname=''"Big John''''s"" Barbecue"''')"
```

Note for QUEL Users

To specify a value for the variable so that Report-Writer produces the following QUEL query:

```
where clientname="\"Big John's\" Barbeque"
```

Follow this procedure:

1. Determine how the value appears in the database:

```
"Big John's" Barbeque
```

2. Enclose the string value in quotes that are appropriate for your query language (double quotes in QUEL). Dereference any embedded quotes according to the rules of your query language (in QUEL, precede a double quote with a backslash):

```
"\"Big John's\" Barbeque"
```

3. Enclose the entire *valuestring* within single quotes to identify it to Report-Writer as a string. Dereference any embedded single quotes (or apostrophes) within this string by preceding each one with a single quote.

```
'clientname="\"Big John''s\" Barbeque"'
```

4. Enclose the entire parameter within parentheses. If the parameter contains any characters treated specially by your operating system (such as parentheses in Windows NT and UNIX or slashes in VMS), enclose the entire parameter within double quotes and escape any embedded double quotes to pass them through the operating system.

Windows

UNIX

VMS

Prompted Runtime Variables as Parameters

Use variables in your report specification that prompt the user for a value at runtime. For string or date values, the report specification must be coded to include quotes around the variable that are appropriate for the query language. If these quotes are included in the report specification, the user can enter the value, as is, without the surrounding quotes. For example, suppose the report specification contains either the following statements:

```
.declare clientname with prompt 'Enter client's name:'
.query select balance from receivables
    where name = '$clientname'
```

Or, these QUEL statements:

At runtime, the user can enter:

report accounting receivables

Report-Writer displays the prompt:

Enter client's name:

The user can respond:

Enter client's name: Lakeside Inn

If the report specification omits the query language-specific quotes around a string or date variable, the user must enter these quotes along with the value on the command line. For example, suppose the report specification contains the following where clause for an SQL or QUEL query:

where name = \$clientname

The user must respond to the prompt:

Enter client's name: 'Lakeside Inn'

If the value is a delimited identifier or contains embedded quotes, the user must follow their query language's rules for dereferencing quotes within the string.

Sending Reports to and from a Screen

Instead of sending your report directly to a printer, you can send it to the screen. From the screen, you can send the entire report to the printer or to a file. Or, you can send only the contents of the current window to the printer or to a file.

When you send a report to the screen, Report-Writer ignores any underline characters. Similarly, if you send a report from the window to the printer or to a file, underlining cannot occur in the printed or stored report output. To preserve underlining, send the report to the printer or file directly, rather than from the screen.

Sending a Report to a Screen

To send a report to your screen, you specify the -f flag, without specifying an output file on the command line nor in an .output statement within the report specification. When you send a report to your screen, Report-Writer displays the first page of the report, as shown in the following figure. If the report contains more than a single page, you can scroll through the report by using the ScrollUp, ScrollDown, ScrollLeft, and ScrollRight keys.

Note: Report-Writer creates a temporary file whenever you send a report to the screen. If your report is large, your computer can require additional memory. Report-Writer automatically deletes the file as soon as the report is displayed.

The report window contains the following menu operations:

Operation	Description	
Print	Sends the report to a printer.	
File	Sends the report to a file.	
Help, End	Standard Ingres operations.	

After sending a report to a screen, you can:

- Use the Printer operation to send the report to a printer. For instructions, see <u>Sending Reports from a Window to a Printer.</u>
- Use the File operation to send the report to a file. Ffor instructions, see <u>Sending Reports from a Window to a File.</u>
- Use the printscreen FRS command to send the currently displayed portion of the report to a file or printer. For instructions, see <u>Sending the Current</u> <u>Window to a File or Printer</u>.

When sending a report from the window to a file or printer, you can send the entire report or only the executed portion. The executed portion is the portion that you have viewed in your window.

Sending Reports from a Window to a Printer

To send a report from a window to a printer:

1. Select the Print operation from the report menu. The Sending a Report to a Printer pop-up appears.



2. To send the report to a printer other than the default, type the printer name in the Printer field.

To send the report to the default printer, tab past this field. The default is to send the report to the default printer specified in the environment variable or logical, ING_PRINT.

- 3. In the Copies field, type the number of copies to print.
 - The default is 1 and the maximum is 999.
- 4. In the File Name field, type the name of a file to which Report-Writer must send an interim copy of the report. After sending the report to this file, Report-Writer sends the report to a printer and then deletes the file.
 - Enter a file name or full directory path name. If you enter only a file name, the report is sent to your working directory.
- 5. To print the entire report, choose the OK operation. (If you have not run the report to completion, Report-Writer executes the entire report before sending it to the printer.)

To print only the executed portion of the report, choose the PrintPartial operation.

Sending Reports from a Window to a File

To send a report from a window to a file:



OK(F9) Cancel(F7) FilePartial(SH-F3) Help(F1)

1. Select the File operation from the report menu. The Sending a Report to a File pop-up appears.

- 2. In the File Name field, enter the name of the file to which you want to send the report.
 - Enter a file name or full directory path name. If you enter a file name only, the report is sent to your working directory.
- 3. To file the entire report, choose the OK operation. (If you have not run the report to completion, Report-Writer executes the entire report before sending it to the file.)

To file the executed portion of the report only, choose the FilePartial operation.

Sending the Current Window to a File or Printer

The *current window* refers to the content displayed in a window at any one time. For example, this might be one page of a report. Depending on whether you have set the II_PRINTSCREEN_ FILE environment variable/logical, Report-Writer either prompts you to direct the window contents to a file or to the printer, or it automatically sends the window contents to a specified file or to the printer. For more information on setting II_PRINTSCREEN_FILE, see the *System Administrator Guide*.

To send the current window contents to a file or printer:

- 1. Press the key(s) mapped to the printscreen command.
- 2. If you have set II_PRINTSCREEN_FILE to a specific file name or to printer, Report-Writer sends the current window contents to the specified file or to the line printer, accordingly.

If II_PRINTSCREEN_FILE has not been set, a file name prompt appears. Enter the name of a file or the word printer, as in the following example:

Enter file name: distrpt

Report-Writer sends the window output to the file you specified or to the line printer, if you specified printer.

Examples

Example 1 Run a default report based on the vendor table in the purchasing database,

using a default format and redefining the page width, and send the output to

the named printer:

report purchasing vendor -m -180 -olaser2

Example 2 Run the report contained in the source file, po_rep.rw, against the

purchasing database and store the results in the po_sum_out file:

report purchasing -ipo_rep.rw -fpo_sum.out

Example 3 Run a default report in column format on the clients table owned by mktgmgr

in the sales database and eliminate duplicate rows:

report sales mktgmgr.clients -mcolumn -6

Example 4 Run the report named recpay against the accounting database and pass in

the value of the variable, title:

Windows

VMS

UNIX

report accounting recpay (title = 'Accounts Receivable') ■ report accounting recpay "(title = 'Accounts Receivable')" 🔳

For more passing parameters examples, see <u>Passing Parameters on the</u> Command Line.

Sreport

Checks and stores a Report-Writer report specification in the database.

Syntax

```
sreport [v_node::]dbname [/server_class] txtfile [-s]
[-uusername][-Ggroupid]
```

If your database resides on a remote system, specify *v_node*, the name of the remote host where the database resides. If you are using an Enterprise Access product, then specify */server_class*.

The -G groupid parameter must be enclosed in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

If any parameter is a delimited identifier, enclose it in double quotes ("), dereference any embedded quotes, and use the appropriate number and type of delimiting quotes to pass it through your operating system. For more information, see the *System Administrator Guide*.

Description

The sreport command reads in a file of Report-Writer source code formatting statements from a base text file, as well as from any files specified with an .include statement. As it reads the files, sreport performs basic syntax error checking, and, if error-free, stores the report specification in the Reports Catalog of the database you specify.

Note: If you update the text file specified in an .include statement, you must execute the sreport command against each report specification that contains the .include statement. This procedure is required in order for the report specification to reflect the changes in the text file.

The sreport command requires valid values for both *filename* and *dbname*. If you do not enter these parameters, sreport prompts you for them.

If the report specification contains syntax errors, sreport prints appropriate error messages. If a report in the text file has the same name as an existing report in the Reports Catalog, the older report definition is replaced. If no prior report exists, Report-Writer adds the report to the Reports Catalog. You can then use the specifications to run a report using either the report command or the Go option from the RBF catalog frame.

VMS

If you use sreport to save a report created in RBF, it can strip out many of the RBF formatting statements, which makes it easier to edit the report specification in Report-Writer. However, you cannot edit the saved report specification in RBF.

The following parameters are specific to the sreport command:

Parameter	Description
txtfile	Name of a text file from which report specifications are to be read. You must specify the full path name of the file if it is not in the current directory. If you do not explicitly specify an extension for the file, sreport assumes the default extension of .rw.

Examples

Example 1

The following sreport command stores report specifications in the repspec.rw file in the Reports Catalog of a database named mydb:

sreport mydb repspec.rw

Example 2

The following sreport command specifies a database name of myowndb and uses sreport's prompting facility to store the report specification located in the myrep.rw file:

sreport myowndb

Report-Writer prompts you for the file name:

Filename

Enter the name of a file containing report specifications:

myrep.rw

Example 3

This example uses sreport's prompting facility to store the report specification from the myrep.rw file in the Reports Catalog for the myowndb database:

sreport

At the Database prompt, enter a database name:

Database myowndb

At the Filename prompt, enter a file name:

Filename myrep

Vifred

Starts the VIFRED.

Syntax

vifred dbname|v_node::dbname [/server-type]
 [[-f] formname|-t tablename|-j joindef]
 [-e] [-uusername] [-Ggroupid]

If your database resides on a remote system, specify v_node , the name of the remote host. If you are using an Enterprise Access product, specify $/server_class$.

VMS

Enclose the -G groupid flag and parameter in double quotes ("-G groupid") to preserve the case of the -G flag. \blacksquare

Description

The system-level vifred command starts the VIFRED, an Ingres forms-based tool for editing forms.

Parameter	Description		
-f formname	Displays the specified form for use with VIFRED. The -f flag can be omitted, because by default any name specified here is assumed to be a form name.		
-t tablename	Displays a default form based on the table indicated by <i>tablename</i> or by a synonym specified as <i>tablename</i> . If no flag is specified, the name is understood to be a form. You can qualify the table name or synonym with a valid schema name in the format, <i>schema.tablename</i> . If the table name is a delimited identifier, enclose it in double quotes.		
-j	Displays a default form based on the JoinDef indicated by <i>joindef</i> . If no flag is specified, the name is understood to be a form.		
-e	Flag that invokes the command in expert mode, causing the catalogs to be displayed empty initially. This allows you to enter the name of a specific object directly, rather than select it from a list.		

Examples

Example 1 Start VIFRED at its initial Forms Catalog frame in the employee database on

a local node:

vifred employee

Example 2 Start VIFRED and display the finance form in the admin database on the hq

remote node for editing (equivalent to selecting a form and choosing the Edit

operation on the VIFRED Forms Catalog frame):

vifred hq::admin finance

Example 3 Start VIFRED and begin to create a default form for the lastname table in the

> employee database on a local node (equivalent to choosing the Create operation on the VIFRED Forms Catalog frame, and then choosing the Table

operation on the Create submenu):

vifred employee -t lastname

Example 4 Start VIFRED and begin to create a default form for the tasks JoinDef from

> the employee database on a local node (equivalent to choosing the Create operation on the VIFRED Forms Catalog frame, and then choosing the JoinDef

operation on the Create submenu):

vifred employee -j tasks

Chapter 18: Working with Data Types and Data Display Formats

This chapter explains the difference between data types and data display formats, and provides important information about each. Data types determine the way data is stored in the database. Data display formats determine the way data is displayed on forms or in reports.

The first part of this chapter describes data types, including an overview of some of the operations you can perform on data stored as different data types.

The second part of the chapter describes data display and input formats. This section explains the relationship between data types and data display formats. It also provides the syntax and a brief description of each data display format, as well as an overview of the different data display format categories. Lastly, it contains a thorough discussion of data display format templates for use in display-only and data entry fields, including the use of data input templates for character-by-character validation.

Data Types

Data types control the type of information a column can contain and determine how the Data Manager carries out particular operations. By assigning the correct data type to each column in a table, you can implement and execute many operations more easily.

Data types are significant in working with a relational database because when you add or change data in a column, the new data must be of the type specified for that column when the table was created. For example, you cannot accidentally store a date in a salary field designated for the money data type.

There are four fundamental data types:

- Character (or text)
- Numeric
- Date
- Money

These data types may not all be compatible with Enterprise Access products. The character and numeric data types are broken into subsets. For example, integers can be stored as 1-byte, 2-byte, and 4-byte integers. Data types are named differently in SQL and QUEL. For more information, see the appendix "Data Types" for OpenSQL and QUEL data types.

Data Type	Description		
c(n)	Fixed-length string of up to n printable ASCII characters, with non-printable characters converted to blank; n represents the lesser of the maximum configured row size and 32,000.		
char(n)	Fixed-length string of up to n ASCII characters, including any non-printable characters; n represents the lesser of the maximum configured row size and 32,000.		
varchar(n)	Variable-length ASCII character string of up to <i>n</i> characters; <i>n</i> represents the lesser of the maximum configured row size and 32,000.		
text(n)	Variable-length string of up to n ASCII characters; n represents the lesser of the maximum configured row size and 32,000.		
float(n)	n-byte floating point; converted to a 4-byte or 8-byte floating point data type.		
float4	4-byte floating point; for numbers including decimal fractions, from 0.29x10**-38 to 1.7x10**38 with 7 digit precision.		
float8	8-byte floating point; for numbers including decimal fractions, from 0.29x10**-38 to 1.7x10**38 with 16 digit precision.		
decimal	Exact numeric data type defined by its precision (total number of digits) and scale (number of digits to the right of the decimal point). Precision must be between 1 and 31. Scale can be zero (0) up to the maximum scale.		
integer1	1-byte integer; for whole numbers ranging from -128 to +127.		
integer2 or smallint	2-byte integer; for whole numbers ranging from -32,768 to +32,767.		
integer4 or	4-byte integer; for whole numbers ranging from		
integer	-2,147,483,648 to +2,147,483,647.		
money	8 byte monetary data; from -\$999999999999999 to +\$999999999999999999999999999999999999		
date	12 bytes; dates ranging from 1/1/1582 to 12/31/2382 for absolute dates and -800 years to +800 years for time intervals.		

A user-defined data type (UDT) is perceived and treated as a character string.

Some forms utilities do not support the long varchar, byte, byte varying, and long byte data types. For more information, see each specific product for a discussion of how long varchar, byte, byte varying, and long byte is handled.

Character

Four different data types define text:

- С
- char
- text
- varchar

You enter character data as alphanumeric strings. You must enclose the string in single quotes ('). To include an explicit single quote (or apostrophe) within a character string, dereference it by preceding it with another single quote. For example:

```
'Enter your supervisor''s initials'
```

You can include double quotes within a single-quoted character string without dereferencing them:

```
'according to the "experts"'
```

In displaying a query result, SQL displays character data as alphanumeric strings without the surrounding single quotes. SQL differentiates between uppercase and lowercase data in character strings. For example, suppose you use this string in an SQL statement:

```
'Bee. Charles'
```

It is evaluated differently from any of the strings below:

```
'BEE, CHARLES'
'bee, charles'
'Bee, charles'
```

C

The $\bf c$ data type consists of a string of up to $\bf n$ printable ASCII characters. It converts non-printable characters to blanks; n represents the lesser of the maximum configured row size and 32,000. Blanks are ignored when comparing strings of the c data type. For example, it treats the following two examples identically:

```
newtable and oldtable
newtableandoldtable
```

Char

The char data type consists of a string of up to n printing ASCII characters, including any non-printable characters; n represents the lesser of the maximum configured row size and 32,000. Between c and char, the char data type is preferred, as it is compatible with ANSI SQL.

Text

The text data type consists of up to n characters in the ASCII extended set or blanks; n represents the lesser of the maximum configured row size and 32,000. All ASCII characters except the ASCII null character (null) or the hex $\$ 0 are allowed.

Varchar

The varchar data type consists of up to n characters in the ASCII extended set or blanks; n represents the lesser of the maximum configured row size and 32,000. All ASCII characters are permitted, including non-printable control characters, such as the NULL character. A varchar column is defined as varchar(n) where n is the maximum number of characters stored in the column. Between text and varchar, the varchar data type is preferred as it is compatible with ANSI SQL.

Comparing Character Strings

When comparing two character strings, it is important to consider the range of ASCII characters permitted by a given data type. Including non-printable characters in varchar or char comparison strings affects the outcome of the comparison.

Blanks are not ignored in comparisons by either text or varchar. However, the way blanks are handled by the two data types differs. In comparing strings of unequal length, varchar effectively adds blanks at the end of the shorter string to bring it to the same length as the longer string. The text data type does not add blanks; it considers a shorter string as less than a longer string if all characters up to the length of the shorter string are equal.

As an example of the way this affects comparisons, consider the following two strings:

abcd\001 abcd Assume that \001 represents one ASCII character, Control-A. If these are compared as text, the first string is greater than the second. However, if they are compared as varchar, the first string is less than the second, because the blanks added by varchar to the shorter string have a higher ASCII value than 001.

The following table summarizes the various character data types, where nrepresents the lesser of the maximum configured row size and 32,000:

Aspect	С	char	text	varchar
Length	1-n	1-n	1-n	1-n
Nullable	Yes	Yes	Yes	Yes
Legal characters	Printable characters only	All ASCII characters	All ASCII characters except nul and \0	All ASCII characters
Storage	Fixed length	Fixed length	Variable length	Variable length
Blanks significant?	No	Yes	Yes	Yes
Comparison of short to long	Blanks ignored	Blank padding of short length to long	No padding; blanks included	Blank padding of short length to long

Date

Date data type columns hold absolute dates, absolute times, or time intervals. Date data types can contain any valid date between January 1, 1582 and December 31, 2382. When used in database language commands, date data types are enclosed in quotation marks as are text types.

An absolute date is a time, such as 12:30 on November 13. There are many ways of expressing absolute dates and time.

For example, you can express the date December 25, 1998, in any of the following ways:

mm/dd/yy 12/25/98 dd-mmm-yyyy 25-Dec-1998 mm-dd-yyyy 12-25-1998 yyyy.mm.dd 1998.12.25 mm/dd 12/25 mm-dd 12-25 mmddyy 122598

mm/dd/yy hh:mm:ss ampm 12/25/98 10:30:30 am

You can express the time 10:30 a.m. as:

hh:mm:ss ampm tz 10:30:00 am pst

You can also use now or today to mean the current date and time (now), or current date only (today).

Various conventions for date and time are recognized. For example, it assumes a 24-hour clock unless you specify p or p.m. The program adjusts dates and times to the designated time zone, such as Pacific Standard Time.

For information on how to specify various date display formats, see <u>Data Display and Input Formats.</u>

International Conventions

International date and time conventions can also be adapted. For example, dates in Sweden and Finland are expressed as a year, followed by the month, followed by the day. The standard German date format can be expressed as *ddmmyy*, *ddmmyyy*, *dd.mm.yy*, and *dd.mm.yyyy*. The date format is set by the system variable II_DATE_FORMAT.

The time zone is set with the system variable, II_TIMEZONE_NAME. These dates are stored in Greenwich mean time. The conversion between Greenwich and your local time is a value set with II_TIMEZONE_NAME. For more information, see the *System Administrator Guide* for the system on which your database resides.

Relative Times and Dates

Relative time and date intervals are also handled, which are units of time not fixed as absolutes. An example of a relative time interval is:

5 years 8 months 14 days

You can use the interval and date functions to carry out operations on dates in SQL or in the Interactive Terminal Monitor. The interval function calculates the difference between two dates. The date conversion function transforms strings into dates.

Floating Point

The floating point data type consists of numeric data with decimal points and/or exponents.

Floating point data can contain an integer portion, a decimal point, and a fractional portion and/or scientific notation, in this format:

```
[+|-]{digit}[.digit{digit}][e|E[+|-]{digit}]
```

For example:

2.3e-02

You can change the default decimal point indicator, the period (.), to another character, such as the comma (,), used in European decimal format, by using the II_DECIMAL system variable. For more information, see the *System* Administrator Guide and the set decimal command in your guery language reference guide.

On output, a mantissa of 1 is supplied when an exponent is missing a mantissa.

The floating point range and precision vary greatly among the various operating systems and hardware.

Decimal

A numeric constant is considered to be a decimal data type if it has a decimal point but no exponent, and you are working with Ingres.

Under the following circumstances, a decimal data type is treated as type float

- The total number of digits exceeds 31
- You have set the II_NUMERIC_LITERAL environment variable/logical to float

Integer

Integer data types are numbers containing no fractional part. For example, ages can be designated as integer data types. Integers are classified as 1-byte, 2-byte, and 4-byte, depending on the range of numbers to be stored within a given column.

If you enter integer data outside the range of an integer 4 data type, the integer is converted to floating point. For instance, an entry of 5000000000 exceeds the range of an integer4, and so is stored as float.

Money

The money data type contains decimal currency data. Great flexibility is provided with regard to the money data type. Using system variables, you can adopt the conventions of your local currency. These include:

- Currency symbol
- Decimal separator
- Number of decimal places

For more information, see the *System Administrator Guide* for the system on which your database resides.

On input and output, money data is rounded to dollars and cents, pounds and pence, or other currency units. Arithmetic operations on money values retain precision as established by the II_MONEY_PREC environment variable/logical.

You can enter up to 14 digits into a column specified for the money data type. When displayed, money data can appear as up to 20 characters, allowing room for commas, currency signs, and place holder symbols.

Nulls

Nullability is an attribute of stored data. A null represents inapplicable or missing data. It is most useful when working with numeric data used in aggregate computations such as totals and averages. An example of nullable text is an unfilled Home Address field on a personnel form for a new employee when not all information is known.

You can determine which of your tables' columns are to be nullable. In this way, missing data, default values, or empty strings cannot be assigned a value of zero.

It is important to distinguish between ASCII NULL character and column nullability. The NULL character, ASCII octal \000, is a value permitted in certain character data types. Nullability is a condition or status that is available to all the data types. A user assigns nullability to a specific column in a table while creating the table.

Data Display and Input Formats

Data display formats offer alternative ways to display or enter data that is stored in the database as a particular data type. The display format controls the width of the data display window on a form or the width of a field or column in a report.

In RBF, you specify the data display format for each column or field in a report on the Report Layout Frame. In VIFRED, you specify the data display format when you create the data window for a simple field or when you specify columns on the Table Field frame. This section explains the relationship between data types and data display formats, and describes data display and input formats in detail.

Data Types and Display Formats

When you create a column in a database table, you assign a data type to control the way data is stored in that column. Sample data types for Ingres databases include char, integer, date, and money. When you create a report or form, you can specify a display format to determine the way that data appears on a form or in a report.

You can assign any one of several different display formats for data stored in a database table as a given data type. For example, a number stored as an integer data type can be displayed as a whole number, in decimal notation, in scientific notation, or as a right-justified number. The data display format must be of a type that is compatible with the data type for the corresponding column in the database table.

Even though some data types and display formats have the same name and abbreviated symbol, they perform different functions. For example, there is a floating point (f) data type and a floating point (f) display format. You can display a floating point data type in formats other than the floating point format. You can also use the floating point display format for numeric data stored as data types other than floating point.

Specify any display format that is appropriate for the data type in both display-only and data entry fields. After the user enters data in a data entry field as instructed by the application, the data is redisplayed in the specified format. An input masking format, or input template, is a special display format you can use in data entry fields only. It controls how a user enters data on a form, character by character. Date, numeric, and string templates are allowed as input masking formats in data entry fields.

The following table lists the valid display and input formats for any data type in each data type category. The letter in parentheses is the code or symbol by which you specify the display format.

Data Type Category	Valid Display and Input Formats		
	Display Formats	Input Masking Formats	
Character	Character (c)	String template	
Numeric	Integer (i) Floating Point (f) Scientific (exponential) Notation (e) Decimal or Scientific (g) Numeric template	Numeric template	
Money	Right-justified decimal or scientific (n) Numeric template	Numeric template	
Date	Character (c) Date (d)	Date template (d), with some restrictions	

Display Format Syntax

The display format symbols are often combined with numbers designating the character width of the field. For example, the display format f6 denotes a floating point display format containing up to six digits. Similarly, f6.2 denotes a floating point display format of up to six whole numbers and a maximum of two decimal digits.

The following table shows the format symbol, compatible data types, and syntax for each display format, and briefly describes the function of each:

Format Symbol	Data Type	Display Syntax	Display Format Description
С	character date	[+ * -]c[f j] [e] <i>n</i> [. <i>w</i>]	Character format, which determines the size and shape of character fields.
d	date	[+ * -]d 'template'	Date template, specifying an absolute date and time or time interval.

Format Symbol	Data Type	Display Syntax	Display Format Description
e	decimal float integer money	[+ * -]ew[.d]	Scientific (exponential) notation format, which displays numbers as [-]m.dddddE e[+ -]ppp (or [-]m.dddddE e[+ -]pp for VMS), in which m represents the mantissa, d represents a digit in the fraction, and p is an exponential digit. When specifying the width of the field (w), be sure to include five spaces for E+ppp (or four spaces for E+pp in VMS).
f	decimal float integer money	[+ * -]fw[.d]	Floating point format, which displays a number in standard decimal format.
g	decimal float integer money	[+ * -]gw[. <i>d</i>]	Displays the number in floating point (f) format if there is room; otherwise, displays it in scientific notation. In scientific notation, it aligns data on the decimal point and justifies it as specified.
i	decimal float integer money	[+ * -]iw	Integer format, which displays the number as an integer.
n	decimal float integer money	[+ * -] <i>nw[.d]</i>	Identical to g format except it aligns all output on the decimal point and right justifies it, in both floating point and scientific notation.
numeric template	decimal float integer money	[+ * -}['{c}']	Numeric template containing character codes indicating the characters allowed in each position.
string template	c char text varchar		String character template containing character codes indicating the characters allowed in each position.

RBF and VIFRED can use the same data display formats as Report-Writer, with two exceptions:

- B format is not allowed
- Variable length format c(0) is not allowed

You can use either uppercase or lowercase letters for symbols in most data display formats. However, case can be significant in date, numeric, and text templates. For details, see the sections on each of these template types later in this chapter: Numeric Templates, Date and Time Templates, and String Input Templates

The following table describes the optional parameters you can use with the data display formats shown in the preceding table:

Code	Description
+ * -	Precedes the format letter to indicate right (+), center (*), or left (-) justification. If no sign is used, the default is left justification for both character and numeric columns.
c	Any one of the special numeric or character template code characters allowed in that type of template. For definitions of these codes, see the sections on character and numeric templates later in this chapter.
d	Specifies the precision (the number of digits to display after the decimal point) in any of the numeric formats. To allow room in the display field for the decimal point and a plus (+) or minus (-) sign, this number must be at least 2 less than the value of w (maximum column width).
e	When used with the wrapping character options (cfe and cje), preserves trailing white space on every line of a multi-line text string, which is otherwise trimmed by default. If you use it with the cj format, the margin justification includes the significant white space. In some instances, this makes the text appear unjustified. For more information, see Creating Multi-line Character Fields .
f	When used with the c format for multi-line text strings, wraps text to the next line, with breaks occurring between words. Most useful in display-only fields. Results in data entry fields can be unpredictable. For additional information, see Creating Multi-line Character Fields .
j	When used with the c format for multi-line text strings, right-justifies the text, with breaks between words, and pads the line with blanks, so that all lines end evenly at the right margin. Most useful in display-only fields. Results in data entry fields can be unpredictable. For additional information, see Creating Multi-line Character Fields .
n	The maximum number of characters allowed in the data window.

Code	Description
w	When used in a character format (c) designation, specifies the number of characters displayed on each line. If n is greater than w, the data window occupies more than one line. The default of w is the value of n.
	When used in a numeric format (e, f, g, i, or n), specifies the maximum column width, including all punctuation, symbols, decimal points, and decimal digits. For example, to display \$15.44 the w value must be at least 6 (for example, f6.2). For columns in e, g or n format, be sure that w is wide enough for representations in scientific notation.

For example, i9 specifies an integer format nine characters wide, and +i9 specifies a right-justified integer format nine characters wide.

To specify a floating point format for a column that is a total of nine characters wide, and for which you want to show two decimal places, enter f9.2. Allowing for the decimal point and a plus or minus sign, a display format of f9.2 permits a maximum of five digits to the left of the decimal point and two to the right of

Default Data Display Formats

The following table lists default display formats for each SQL data type. For more information, see the appendix "Data Types" for OpenSQL and QUEL data type equivalents.

SQL Data Type	For Forms and most Reports	For Block Style Reports
c1 - c35	c1 - c35	c1 - c35
c36 - cx	cj0.35	cj0.35
char(1) - char(35)	c1 - c35	c1 - c35
char(36) - char(x)	cj0.35	cj0.35
text(1) - text(35)	c1 - c35	c1 - c35
text(36) - text(x)	cj0.35	cj0.35
varchar(1) - varchar(35)	c1 - c35	c1 - c35
varchar(36) - varchar(x)	cj0.35	cj0.35
integer1	f6	f10
smallint (integer2)	f6	f10

SQL Data Type	For Forms and most Reports	For Block Style Reports
integer (integer4)	f13	f10
decimal (31.31 - 31.0)	Based on size. For example, decimal (5.1) defaults to f7.1, allowing additional digits for the decimal point and an optional plus (+) or minus (-) sign.	
float4	n10.3	f10.3
float (float8)	n10.3	f10.3
date	c25	c25
money	\$nn	\$nn

Note: 'x' represents the lesser of the maximum configured row size and 32,000.

Note: All character data types are fully supported in non-Ingres databases accessed through Enterprise Access products, in which case the column size limit can be greater than 2000 bytes. Other data types may not be supported by all Enterprise Access products.

If your computer supports the IEEE standard for floating point numbers, the range and accuracy of floating point numbers reflect that standard.

Displaying Character Data

Character data includes any of the character data types (varchar, char, c, text). You can display character data types only in:

- Character (c) display format (in display-only and data entry fields)
- String template display format (in data entry fields only)

For the character (c) data display format, the default is left justification To justify the contents of a single-line field to the right, left, or center, precede the data display symbol with a plus sign (+), asterisk (*), or minus sign (-), respectively. For example, entering +c5 specifies a right-justified text field of five or fewer characters. You can use justification symbols with any data type.

If you specify a value for w as well as n, you can display text in column format. When character fields contain more than one line, the first line of the field is filled with characters and the second line is filled. This can produce line breaks in the middle of a word. For display-only fields, you can use the f or i option to specify that lines must break at the end of a word instead of in the middle. For example, cf80.20 specifies a text field containing a total of 80 characters with no line containing more than 20 characters and with breaks between words.

To right justify the contents of a display-only multi-line character field, use the j flag. The j flag performs the same function as the f flag, except that it pads the line with blanks between words to make the right margin of each line come out even, like a column of text in a newspaper.

The f and j flags are most useful in display-only fields. If used in a data entry field, the word wrap or justification operation is performed only after the user has exited the field. This can cause truncated text or other unpredictable results, because a word can wrap to the next line or the line is padded with extra blanks after the user has already exited the field.

Displaying Numeric and Money Data

For the money and various numeric data types, a default display format and field width is set that is appropriate for the data type and width of the corresponding database column. If these defaults do not meet your needs, you can edit the data display format accordingly.

However, if you make the width of a column on a report or a data window in a form too small for the value that is to be printed or displayed there, the field is filled with asterisks. For example, if you attempt to print or display the value 667298 in a field with a data display format set at i5, five asterisks are printed or displayed in the field instead.

When you use Ingres programs to enter data into a table from a field that has a numeric display format, such as integer (i), the value entered is checked to make sure it can be stored correctly in the corresponding database column. For example, the value for an integer1 column must be between -127 and +127. In customized applications, this checking is not always automatic; you may need to use your application code to perform the check.

For floating point and decimal numbers, which have decimal fractions, you can specify the number of places to the right of the decimal point. When the data is displayed, it rounds the value to fit the number of specified places, if necessary. To specify scientific notation, use the format symbols e, g, or n.

Make sure that the display format is wide enough to include symbols such as plus (+) and minus (-) if your data uses them. When using a form for queries, you can make the display window wider than the underlying column to allow two extra spaces for comparison operators.

You can also use a numeric template for the specialized display of numeric data. Specify characters in the template that tell Ingres what to do with each digit in the data that is being displayed or entered. When using a numeric template, the width of the field on a form or in a report is determined by the number of characters in the template. For example, the template \$\$\$,\$\$\$.nnDb allows for a maximum of 6 digits to the left of the decimal point plus a comma, and 2 digits to the right of the decimal point plus a two-character Credit/Debit symbol. For more information, see Numeric Templates.

Displaying Date Data

A *complete absolute date* includes day, month, year, and time according to a 24-hour clock. The default display format for a date data type is c25, which displays absolute dates in a field 25 characters wide, in the format:

Mon Apr 01 1988 22:50:43

If the date to be displayed does not include the time of day, you can specify a correspondingly smaller display width for the field.

By using a date template such as d'SUN Feb 3 1901' to specify the display format, you can display dates and times in a wide variety of formats. For more information, see <u>Date and Time Templates</u>.

Using Format Templates

This section provides information about data display format templates, including how the templates function when input masking is turned on.

Format Templates

A format template is a picture of how you want the data to look when it is displayed or entered in a single-line field.

For numeric and string data types, a format template consists of character set definitions and special characters. These represent the type and order of the characters that are displayed, or the valid characters that the user can enter in that field. To the system, each character set definition in the template represents one or more characters to be displayed or validated, depending on whether the field is a display-only or data entry field. To the user, the template provides visual clues about the type and format of the data that must be entered in a data entry field.

For date data types, a format template provides an actual date in a variety of formats. In data entry fields, the user follows the form of the example date in the field to enter the actual date that he or she wants to enter.

Input Masking with Format Templates

In data entry fields, you can optionally use input masking in conjunction with format templates to ensure that the user always enters valid characters in the correct order and position. The format template determines whether a character is valid; what is valid in one template may be invalid in another.

Without input masking, the validity of the user's entry is checked when the user attempts to leave the field. However, if input masking has been turned on for that field and its display format is a format template, the validity of the input is checked as the user enters the data, character by character. The input template is made up of special character codes that indicate what kind of input is allowed for that position in the template. If the user enters an invalid character for that position, the system beeps and requires the user to make a correct entry before continuing. For input templates, data entry mode is overstrike only; insert mode is not allowed. The user can correct entries with the Backspace and Delete keys.

To turn on input masking, you specify a numeric, date, or string template as the display format and set the Input Masking attribute for the field to y (yes) on the VIFRED Attributes for Field frame.

When specifying format templates, you must enter an appropriate template for the data type of the corresponding column in the database table. For example, a numeric template is appropriate for a field corresponding to a column of data type smallint, integer, float, or money, but is not appropriate for a field corresponding to a column of date or character data. For date fields that represent a fixed date value, you must select an absolute date/time template. The following sections tell you how to specify a format template for numeric, date, and string fields, including input masking for data entry fields.

Numeric Templates

In addition to other display formats for numeric columns, numeric templates for specialized needs are provided.

The general syntax of a numeric template is:

' { c} '

The character c is one of the special template characters. Use one special character for each space of the column width. For example, '\$\$\$\$' specifies that the column is four digits wide and a dollar sign must be printed to the left of whatever number is displayed in the field. You must delimit the template with single (') or double (") quotation marks; single quotes are recommended for consistency with requirements for quoting string constants.

You can include any printable character explicitly in a numeric template by preceding it with a backslash (\). For example, to include the percent symbol in a template, enter \%. The backslash is ignored and the character immediately following the backslash is read or displayed.

When input masking is off, checking is only performed when you exit Ingres.

Input Masking with Numeric Templates

When input masking is on, 0.00 is displayed in the entry field for any numeric template, including at least one zero to the left and two zeros to the right of the decimal point. It displays as many zeros to the right of the decimal point as are needed to match the template. The cursor is positioned at the decimal point for input. Enter the number as you do on a calculator, with each digit pushing previously entered digits to the left. Each digit is checked against its corresponding position in the template as you enter it. After the user enters a decimal point, digits are checked and displayed as entered, from left to right, on the right side of the decimal point. Left-justification for numeric templates is not supported with input masking.

Note: Decimal data types are not supported with input masking.

When input masking is on, the user cannot enter a negative number unless the format template includes a negative indicator.

Special Numeric Template Characters

The special template characters and the actions they specify are described in the following table:

Code	Description
n	If a digit in the number corresponds to the position of n, displays or accepts the digit. If no digits remain, displays or enters zero (0) to the left of the preceding character. If a field is specified <i>without</i> n in the numeric positions and a value of zero (0) is encountered, enters blanks in the field.
Z	If a digit in the number corresponds to the position of z, displays or accepts the digit. If no digits remain, displays or enters a space to the left of the preceding character. This is used for standard blank-padded numeric fields.
\$	(Dollar sign) If a digit in the number corresponds to the position of a dollar sign, displays or accepts the digit. If no digits remain, displays a floating dollar sign immediately to the left of the last evaluated digit. A dollar sign displays only once in the output field. If a dollar sign has been displayed in a previous position, a space is displayed in this position. This can be used either to place a dollar sign directly to the left of the number, or to place a dollar sign in a fixed position in the field when used with other template characters.
-	(Minus sign—preceding or trailing) For preceding: If a digit in the number corresponds to the position of a minus sign, displays or accepts the digit. If no digits remain and the number is negative, a floating minus sign displays immediately to the left of the last evaluated digit. A minus sign displays only once in the output field. If a minus sign has already been displayed in a previous position, or if the number is positive and no digits remain, a space displays in that position.
	For trailing: Displays a minus sign in this position if the number is negative; displays a space if the number is positive.

Code	Description
+	(Plus sign—preceding or trailing)
	For preceding: If a digit in the number corresponds to the position of a plus sign, displays or accepts the digit. If no digits remain, displays a floating sign (+ or -) to the left of the last evaluated digit. A plus or minus sign displays only once in the output field. If a sign has already been displayed in a previous position, a space displays in that position.
	For trailing: Displays a plus sign in this position if the number is negative; displays a space if the number is positive.
ı	(Comma) Displays a comma if the number contains any digits to the left of this position. If no digits remain, displays a space. This is used for inserting commas to break up large numbers.
	(Decimal Point) Displays or accepts a decimal point in this position. The template can contain only one decimal point.
*	(Asterisk) If no digits remain, displays an asterisk. This is useful to fill a number on the left with asterisks (for example, for checks).
space	Displays a blank space in this position. This is identical to specifying a backslash followed by a space, and is provided for convenience only. Do not use spaces as thousands separators in place of commas and a decimal point if your template contains floating characters (+ - \$ [] () < > { }). Floating characters work correctly only with commas and the decimal point as separators.
\c	(Backslash) Displays in the specified position any character c preceded by a backslash. This allows you to insert hyphens, slashes, or other characters into the number. (The backslash itself is not displayed.)
CR	(Two characters) If the number is negative, inserts the characters CR (for credit). If positive, displays two blanks. You can specify the characters in either uppercase or lowercase (or one of each).
DB	(Two characters) If the number is negative, inserts the characters DB (for debit). If positive, displays two blanks. You can specify the characters in either uppercase or lowercase (or one of each).
() [] < >	(Parentheses, brackets, or angle brackets) If the number is negative, displays it within the specified symbol.

Numeric Template Examples

The following examples demonstrate the use of numeric templates. This table uses a caret (^) in the output column to represent a space, so that you can better interpret the results:

Format	Example Data	Report Output (^ indicates a blank space)
'ZZZZZZZZ'	123	^^^123
'zZzZz.Zz'	0	^^^^^
'zzzzzzzz.nn'	0	^^^^^
'+++,+++,	23456	^^^++23,456
',NN'	23456.789	^^^^23,456.79
',,ZZ'	-3142.666	^^^^3,142.67
'\$\$\$,\$\$\$,\$\$\$.nnCr'	235122.21	^^\$235,122.21Cr
'\$\$\$,\$\$\$,\$\$\$.nnDb'	-235122.21	^^\$235,122.21Db
'\$zz,zzz,zzn.nn'	1234.56	\$^^^^1,234.56
'\$**,***,***.nn'	12345	\$****12,345.00
'+\$\$,\$\$\$,\$\$\$.nn'	54321	^^^+\$54,321.00
'nnn\-nn\-nnnn'	023243567	023-24-3567
'(zzzzz)'	-123	(^^123)

Date and Time Templates

You can specify a date (d) format template for a field or column with a date data type. The syntax of a date template is:

[+|-]d 'template'

The d indicates this is a date template, and the *template* parameter indicates exactly how a specific date is displayed or entered. You must delimit the template with single (') or double (") quotation marks; single quotes are recommended for consistency with requirements for quoting string constants.

The date is left-justified by default. You can right justify it by specifying the optional plus (+) sign.

When input masking is off, the *template* can be a string of characters specifying either the absolute date and time format or specifying a time interval format, for either a display-only or data entry field.

Absolute Date and Time Templates

You can specify absolute date and time templates by entering an example date that indicates exactly how you want each date and time element to be displayed or entered. You can specify any one of many variations of the following representative date and time for your date template:

Sunday, 1901 February 3 at 4:05:06 p.m.

You can use any or all parts of the representative date in your date template, as in the following examples:

```
d'Sun, Feb 3, 1901'
d'02/03/01 16:05:06'
d'04:05:06p'
d'3/01
```

Note: For the output of these examples and others, see <u>Absolute Date and</u> Time Examples.

An absolute date and time template overrides any date format specified by the II_DATE_FORMAT environment variable/logical. For more information on II_DATE_FORMAT, see the *System Administrator Guide* for the system on which your database resides.

Specifying the Template

You can use the following representations of components in a date and time template, with the exceptions noted in the table that follows:

- Sunday, Sun, or Su represents a day of the week
- 1, 01, or 1901 represents the year
- 2, 02, February, Feb, or Fe, represents the month
- 3 or 03 represent the day of the month
- 4, 04, or 16 (24-hour time) represent the hour

- 5 or 05 represent minutes
- 6 or 06 represent seconds
- p or p.m. represent the designations am or pm

This is easy to remember because Sunday is the first day of the week, and arguments 1, 2, 3, 4, 5 and 6 are the year, month, day, hour, minute, and second, respectively.

The following rules apply when using the representative date components to indicate position and style:

Component	Usage Rules
Day	You can specify the day as an ordinal number by suffixing it with the appropriate abbreviation: st, nd, rd, or th. For example, the template 3rd day of February 1901 produces a date such as 15th day of January 1998.
	If input masking is on, you cannot use the full name of the day, Sunday, or ordinal numbers and their abbreviations. If you use the single digit 3 for the day, you must precede it with a space. For more information, see Input Masking for Absolute Dates.
Month	You can use either a single or double digit for the month. Use a 2 (single digit) for the month to display the months of January through September as a single digit and the months of October through December as a double digit. For example, if you specify 2 for the month, July appears as month 7 and November appears as month 11. Use 02 for the month to display or enter all months as two-digit numbers. In this case, July appears or is entered as 07.
	If input masking is on, you must precede the single digit 2 with a space in your template. You cannot use the full name of the month, February. For more information, see Input Masking for Absolute Dates .
Year	If you use the single digit 1 in the template to indicate the year, the years zero through nine are displayed or entered with only one digit; double-digit years are displayed as two digits. For example, specifying 1 for the year displays 2004 as 4 and 2014 as 14. If you use the four digits 1901, all four digits of the year are displayed. Thus, 2004 is displayed as 2004.
	If input masking is on, you must precede the single digit 1 with a space in your template. For more information, see Input Masking for Absolute Dates .

Component	Usage Rules
Time	You can specify 24-hour (military) time by using 16 instead of 4 for the hour. You cannot use p or p.m. with 24-hour time.
Order	You can arrange the arguments in various combinations in any order. For example, 03/02/01 displays first the day (3), the month (2), and the year (1), with each element separated by slashes. The date January 15, 1998 appears as 15/01/98. If your template is Sun 03/02/01, the date January 15, 1998 appears as Saturday 15/01/98. Similarly, 1901.02.03 first displays the year, the month, and the day, separated with periods, resulting in 1998.01.15.
Constant characters	Separators and other constant characters in your template, such as forward slashes (/) and periods (.), are displayed exactly as indicated in the template.
Reserved characters	If you want to use one of the special reserved template characters or symbols as an explicit character in your template, you must precede it with a backslash (\). For example, if you want to use the numeral 2 in the date template as a constant rather than as the template symbol for the month number, you must enter it as \2.
	If input masking is on, you cannot use the vertical bar () as a special alignment character.

Ingres displays as a string constant any word you include in a date template other than the month name of February (or its allowed abbreviations), the weekday of Sunday (or its allowed abbreviations), and the time designation p or p.m.

You can combine any of the values given to specify your template, but be aware that some combinations of those values can lead to incorrect outputs. For example, you can display the numeric day of the year by specifying the day and year but leaving out the month. Therefore, 3/1901 in the template results in dates like 9/1998 for January 9, 1998, and 121/1998 for April 30, 1998. Also note that you can display just the numeric representation for month and year by leaving out the day-year and day-month. This results in outputs such as 3 for March 6, 1998, when specifying the template 02, and 98 for April 4, 1998, when specifying the template 01. However, when you use templates with 03, leaving out the month and the year, the template *does not* return the day of the month; instead, it returns the number of days since January 1, 1582 (Gregorian calendar), which leads to outputs like 151943 for February 1, 1998.

Numbers requiring more than one digit use up preceding blanks or zeroes. If there are no preceding blanks or zeroes left, the number expands to the right. A succeeding number does not use up a single blank immediately following a letter, word, or number. Columns of numbers can be lined up by preceding them with an appropriate number of blanks or zeroes.

Because full month and weekday names (as well as numbers without preceding blanks or zeros) are of differing lengths, date columns using these components in the format do not usually line up when displayed in columns. Follow February or Sunday with a vertical bar (1) to specify that for shorter month names or weekdays, an appropriate number of blanks is substituted for the vertical bar to line up the components. When you follow a single digit in your template with a vertical bar, each single-digit entry is automatically preceded with a space, to line up single and double-digit entries.

For example, the template Sunday, | February | 3, | 1901 produces dates like:

January 15, 1998 Wednesday, May 4, 1998 Saturday, November 20, 1998

Any character preceded by a backslash (\) is printed as it appears.

Absolute Date and Time Examples

The following table demonstrates the use of absolute date and time templates:

Format Template	Example Data	Output
d'2/3/1'	25-oct-1998	10/25/98
D'2/3/1'	5-jun-1909	6/5/9
d' 2/ 3/01'	25-oct-1998	10/25/98
d' 2/ 3/01'	5-jun-1909	6/ 5/09
d'03-02-01'	5-oct-1998 07:24:12	05-10-98
d'010203'	5-oct-1997	971005
d'1\ 2\ 3'	5-oct-1997	97 10 5
d'FEBRUARY, 1901'	1-sep-2134 09:13:02	SEPTEMBER 2134
d'FEBRUARY, 1901'	7-may-1962 13:08:42	MAY 1962
d'Sunday'	5-oct-1998	Wednesday
d'SUN Feb 3 16:05 1901'	13-oct-1998 07:24:03	THU Oct 13 07:24 1998

Format Template	Example Data	Output
d'FEB 03 4:05:06 p.m.'	12-dec-1998 22:13:03	DEC 12 10:13:03 p.m.
d'04:05:06 PM'	5-oct-1998 14:08:45	02:08:45 PM
d'04:05:06 PM'	5-oct-1998 07:29:12	07:29:12 AM
d 16:05 pst	5-oct-1998 14:08:45	14:08 pst
d'3/01'	5-oct-1998	278/98
d'February 3rd'	29-jul-1954	July 29th
d'3rd day of 1901'	11-may-1999	131st day of 1999

Input Masking for Absolute Dates

With input masking turned on, the only valid date template is the absolute date and time template. Input masking does not allow you to use date interval templates. Other restrictions apply, as discussed in the table in the section, Absolute Date and Time Templates.

There must be adequate room in the date input template for all the digits required by the template. For example, you must provide enough space to enter both single-digit and double-digit days of the month.

To use single digits for the day, month, or year in your input template, you must either:

 Precede the digit with a space to allow space for possible double-digit entries

or

■ Be sure that the data consists only of a single digit for that component

For example, assume that you specify a format representing the month/day/year with no leading blanks or zeros in front of the digits: d'2/3/1'

If you turn input masking on, this template is unacceptable because all of the entries can be at least two digits (00/00/00 or 00/00/0000) and the preceding format only allows for the one digit in each part. To specify a format in this manner that is acceptable when input masking is on, you can precede each single digit with a space (d' 2/ 3/ 1') or with a zero (d'02/03/01'). Specifying d' 2/3/1' causes a blank-filled date to display in the field prior to user entry; specifying '02/03/01' displays a zero-filled date prior to user entry.

If you specify a template that is incorrect for use with input masking and turn on input masking, the template is used, if it is otherwise correct, without activating input masking. It does not generate an error message. However, it can compare the entered data to the template only when the user attempts to exit the field. If you correct the template, and input masking is still on, input masking is automatically activated or the next data entered.

You must enter data from left to right in a date field that has input masking turned on. Only numbers in the numeric portions of the template and alphabetic characters in the non-numeric portions (month and day names) are accepted. If you try to enter an incorrect keystroke in a position, you hear a beep and the keystroke is not entered. The entire date and time string is validated only when you exits the field.

Time Interval Templates

Time interval templates show the amount of elapsed time rather than an absolute date or time.

Note: You cannot use input masking with time interval templates.

As in the absolute date format, you specify a time interval with a quoted string containing one of many possible representations of a sample time interval, such as 1 year or 1 yr 3 day. The selection and arrangement of the time interval elements within the template indicate the way you want time intervals to be displayed or printed. You must use the following representative time interval as the basis for your template:

1 year 2 months 3 days 4 hours 5 minutes 6 seconds

You can use all or only some of these units in your template, and arrange them in any order. You can use the plural or singular form of any unit, as well as the singular or plural form of the abbreviations, yr, mo, hr, min, and sec.

To specify a time interval, use the d'template', where template contains one or more time interval keywords (for example, minutes) preceded by the appropriate digit from the representative time interval string, as in: d'5 minutes'

This format displays results followed by the keyword; for example:

9 minutes

Format	Example Data	Report Output
d'1 year'	3 years 5 mos 16 days	3 years
d'2 MONTHS, 3 DAYS'	3 years 5 mos 1 days	41 MONTHS, 1 DAY
d'1 yr 3 day'	1 yrs 5 mos 16 days	1 yr 168 days
d'4 hours 6 seconds'	23 hrs 8 mins 53 secs	23 hours 533 seconds
d'04:05 \hours'	23 hrs 0 mins 53 secs	23:01 hours
d'3 days 4 hours'	23 hrs 8 mins 53 secs	0 days 23 hours
d' 1 yr 2 mos 3 days'	200 yrs 11 mos 28 days	200 yrs 11 mos 28 days
d' 1 yr 2 mos 3 days'	5 yrs 1 mos 3 days	5 yrs 1 mo 3 days

There are 30.4376875 days in a month and 365.2425 days in a year. When calculating a date interval, the smallest unit of time is rounded up.

Numbers requiring more than one digit use up preceding blanks or zeroes. If there are no preceding blanks or zeroes to the left, the number expands to the right. A succeeding number does not use up a single blank immediately following a letter, word, or number. You can line up columns of numbers by preceding them with an appropriate number of blanks or zeroes (note the last two examples).

The word immediately following a number is made singular if the number is one, or plural if the number is zero or greater than one. You can prevent this by preceding the word with a backslash (\). Any character preceded by a backslash is printed as you enter it.

String Input Templates

String input templates allow you to specify the type, order, and number of characters a user can enter in a data entry field. You can define string input templates only on single-line character data entry fields. This template is not available for display-only fields, multi-line character entry fields, or entry fields with non-character data types.

The general syntax of a string input template is:

s'{*c*}'

The s indicates this is a string template and the *c* represents any of the special template characters. You use one special character for each space in the field or column width, up to a possible width of 100. For example, s'naaannn' specifies that the field or column is 7 characters wide and that numbers (n) must be entered in the first and fifth through seventh positions, with alphabetic characters (a) in the second, third, and fourth positions.

You must delimit the template with single (') or double (") quotation marks; single quotes are recommended for consistency with requirements for quoting string constants.

Creating a String Template

To create a string template that suits your needs, you can use any combination of special characters that are pre-defined by Ingres, constant characters, and user-defined custom character sets. A custom character set is a definition of allowable user input for one of the five special characters, i, j, k, I, and m. You can define up to 12 different custom character sets in a single template.

Special Characters

There are a number of special characters that you can use in a string template. Each special character represents a set of characters from which the user can choose, to enter at the specified position.

For example, the special characters a and z represent alphabetic characters and digits, respectively. Assume that you enter a template that looks like this: $\frac{1}{2} \sum_{i=1}^{n} \frac{1}{2} \sum_{i=1}^{n} \frac{1}{2$

aaazz

With this template, users can make entries such as Afm35 or pRt44 but not entries such as 2acm5 or C342d. They must enter alphabetic characters in the first three places and numeric characters in the last two places.

The following table describes the special characters that you can use in a string template:

Special Character	Description
a	Represents any alphabetic character.
h	Represents any hexadecimal digit.
n	Represents any digit (the default is 0).
0	Represents any printable character (only 7 bit).
р	Represents any printable character.
q	Represents any character that can be the first character in an Ingres name.
r	Represents any character that can be the second or subsequent character in an Ingres name.
S	Represents any character (only 7 bit).
t	Represents any character.
х	Represents both alphabetic and numeric characters.
z	Represents digits (the default is a space).
i	Represents a user-defined character.
j	Represents a user-defined character.
k	Represents a user-defined character.
1	Represents a user-defined character.
m	Represents a user-defined character.

Using templates, you can enforce mandatory entry (the user must make an entry), force the case of an entry, and insert a default entry if the user fails to make an entry.

All of the special characters support mandatory entry. For information about using this feature, see Forcing Mandatory Entry. To force the case of a user's entry or insert a default if the user does not make an entry, use a user-defined special character. The pre-defined special characters do not support forced case or default entries.

Escape Character

In addition to the special characters, a template can also include constant (literal) characters. To indicate that a character is to be read as a literal in a template, precede the character with the escape character, a backslash (\).

Custom Character Sets

In some instances, you may want to limit a user's entries to some set of characters that are broader or narrower than those available using the pre-defined special characters. To accommodate these needs, you can define up to 12 custom character sets per template. If the set you want is small—for example, one or two characters—you can use the following syntax:

[*c*{ *c*}]

The c represents the valid character or characters. You can include any number of valid characters. Simply use this syntax in the template in the positions where you want the specified characters. You must include the brackets. For example, the following template allows the user to enter only the letters a, b, or c in the first position:

[abc]nnn

If you want to specify a range of characters, use the following syntax: [c-c2]

The c represents the beginning character in the range and c2 represents the ending character.

For either syntax, the user must enter one of the specified characters in the specified position.

In either syntax version, the case of the characters is unimportant for alphabetic characters. You can use an uppercase or lowercase character to represent the character. To force the user's entry to either case, use the special formatting character that specifies forced case. For more information, see Specifying Uppercase or Lowercase.

When defining a character set for a single position in this manner, you cannot enforce mandatory entry in that position. To enforce mandatory entry, you must define the character set with a user-defined special character. For information on defining character sets with user-defined special characters, see <u>User-defined Characters</u>.

If you are defining a large character set or are using the set in several places in your custom template, it is probably more convenient to define a special character to represent the set and use that character in the template. For more information, see <u>User-defined Characters</u>.

User-defined Characters

In addition to the predefined special characters for string templates, you are given five special characters whose meaning you can define. This is done by associating one of the user-defined special characters with a custom character set. This feature makes it easy to define a custom character set and specify that set in several positions in your custom template.

To use a user-defined special character, you define the special character at the first instance of its use in the template and put the special character in the template for subsequent occurrences.

The special characters reserved for user definition are i, j, k, l, and m.

In the same way that each of the predefined characters are defined to represent some set of characters, you can define each of these special characters to represent some set of one or more characters. To do this, use the following syntax:

 $[c=c1{c2}]$

The c is one of the five special characters (i, j, k, l, or m) and c1 and c2 represent the characters that you want to include in the set of characters defined for the special character. You can include any number of characters in the set.

You can also specify a range of characters for your special character: [c=c1-c2]

In this case, *c* represents the special character, *c1* represents the beginning of the range, and *c2* represents its end.

When you include a user-defined special character in a template, the first instance of the character in the template must be its definition. For subsequent occurrences, you just use the special character. For example, assume that you want to build a template in which the special character j represents the numbers 4 and 6. An example of such a template is:

[j=46]aazaj

The above template describes a field of six characters, of which the first and last must be either a 4 or a 6. Another example is:

nn[j=46]njj

This example describes a field of six characters also, in which the third, fifth, and sixth must be either a 4 or a 6.

Predefined Characters for Custom Character Sets

You are also given a set of predefined special characters that you can use in the definition of a custom character set. These characters represent a pre-defined set of characters and can appear only in a custom character set definition. You cannot place them directly in a template definition. These special characters are useful because you can force the case or apply a default to any of the characters represented by these built-in special characters. (The pre-defined special characters described in The Special Characters do not allow you to apply forced case or a default to any of the characters that they represent.)

The following table lists the predefined special characters that you can use in a custom character set definition:

Character	Description
#	The pound sign represents any digit.
@	The at sign represents any alphabetic character.
*	The asterisk represents any printable character.
+	The plus sign represents any printable character (only 7 bits).
&	The ampersand represents any character that can be the first character in a name.
%	The percent sign represents the second and subsequent characters in a name.
:	The colon represents any hexadecimal digit.

Use these characters when you want to force the case of an entry or provide a default for the entry. For example, to specify a four-letter entry, use a template that looks like this:

2222

However, assume that you want the first position to be an uppercase letter. Because you cannot force case on the special character a, you must use the special character @ instead:

[@/u]aaa

If you want to include any of these special characters as literals in the template, use the escape character with the character. For example, you want the user to enter a two-figure percentage value. A template looks like this: nn\%

Specifying a Default Character

To specify a default character for a position, include the following syntax in your character set definition:

//c

The c is the default character. For example, assume that you want the user to enter a 4-digit number. They must enter at least two numbers, but if they fail to enter the final two numbers, you want the number 1 in each of those positions. Your template looks like this:

nn[#//1][#//1]

The n forces entry of a digit in those positions. The other two positions allow entry of a digit, but insert the specified default if the user does not make an entry.

When you specify a default character for a position, with one exception, the default character is inserted whenever the user inserts a space in that position or fails to make an entry into that position. The exception occurs when the space is a valid entry for that position. In such instances, the space is placed in the position. If a space is not a valid entry, the default character is placed in the position.

The specified default character is always considered to be a valid character for the position, even if it is not part of the character set defined for that position by the template.

Specifying Uppercase or Lowercase

To force the case of the user's entry, use the following in the special character definition:

- For uppercase /U or /u
- For lowercase /L or /l

You can only include one case specification in each special character definition. For example, assume that you want the user to enter a part number that consists of an uppercase letter, from A - D, followed by three numbers.

Your template looks like this:

[a-d/U]nnn

or

[a-d/u]nnn

The user can make entries in lowercase or uppercase, and the data appears in the field in uppercase.

Forcing Mandatory Entry

You must use a special character, either built-in or user-defined, if you want to enforce mandatory entry. Mandatory entry means that the user cannot leave the field without supplying a valid entry for that position. If they attempt to leave the field without providing a valid entry, they receive an error message and the cursor is positioned at the beginning of the template.

To specify mandatory entry, you use an uppercase special character. For example, assume that you want the user to enter a part number that has a two-letter code followed by two numbers and one final letter, and that the first two letters are mandatory. Your template looks like this:

AAnna

Perhaps the part number uses a restricted letter set, for example A-D. Your template looks like this:

[K=a-d] Knnk

The user must enter one of the letters from A to D in the first two positions; this is enforced by the uppercase K. Making an entry in the final position is optional, but if done, must be a letter from A to D also.

Examples of User-Defined Character Sets

The following table shows some examples of user-defined character sets:

Example	Description
[\#-*]	All of the characters found between # and * in the ASCII collating sequence.
[A0\[\]/u]	The letter a, forced to uppercase, the digit 0 and brackets.
[#abc]	Any character acceptable in your installation as a digit and the letters a, b, and c
[&*\\$]	Any character acceptable in your system as the first character in a name and the characters * and \$.
[abc//a]	The characters a, b, and c, with a default of a if the user fails to make an entry or enters a space.

Examples of String Templates

The following table shows some examples of string templates:

Example	Description
nnn\-nn\-nnnn	This template, with embedded dashes, lets the user enter 9 digits.
AA\-nnnn	This template specifies two alphabetic characters and four digits, a dash separating the alphabetic and numeric characters. The alphabetic characters are mandatory.
nn\%	This template specifies two digits and places a percent following the digits.
[e/u][x/u]nnnn \-[#//0][#//0]	This template specifies that the user enter an e and x in the first and second positions, respectively, followed by four digits and an additional two more digits. The template forces uppercase on the first two positions, inserts zeros by default in the last two positions if the user does not make entries into those positions, and puts a dash before the final two positions.
N\'[j=a-m/l]jjj\'	This template specifies a five-character entry. The first position is a digit and is a mandatory entry. The final four positions can be any character between a and m, inclusive. The final four positions are set off by single quotes and are forced to lower case.

Appendix A: Defining Your Terminal

This appendix describes how to define your terminal and lists the names for many commercially available terminals on which you can run Ingres.

Defining your terminal allows you to use the forms-based utilities and the many features of Ingres. Your computer system can support a wide variety of terminals, each with its own particular characteristics.

The Termcap File

The termcap file contains a description of all terminals supported by Ingres, including their color capabilities and available function, control, and arrow keys. Each supported terminal has a termcap description that is based on the vendor's specifications for that device. This appendix lists supported terminals. For unsupported terminals, you must write your own termcap descriptions. For more information, see the appendix "Writing Termcap Descriptions."

When you start the Forms Run-time System, it uses the TERM_INGRES environment variable/logical to determine the user's terminal type and verifies basic terminal attributes. The terminal type defined by TERM_INGRES tells the Forms Run-time System, which terminal description to read from the Ingres termcap file. The type is checked only once for each session, so the user must exit the current session to reset TERM_INGRES to change terminal types.

Forms Run-time System key definitions can be changed dynamically by the installation, terminal type, user, and application key mapping files. For more information on key mapping, see the appendix "Defining Function and Control Keys."

How to Define Your Terminal

To define your terminal to Ingres, you enter the setenv command at the operating system prompt to define the TERM_INGRES environment variable/logical. Once the forms system has started, TERM_INGRES cannot be reset until the session has ended. It is a good idea to include the command that defines TERM_INGRES in the automatic login procedures on your individual account on the computer.

Defining Your Terminal: Windows

To define your terminal for Windows NT/95/98/2000, use the following command:

ingsetenv TERM_INGRES termname

The parameter *termname* is the designation for your terminal type. For more information, see <u>Terminal Names</u>.

For example, if you are working on an IBM compatible PC, <u>Terminal Names</u> shows you that "IBMPC" is the correct *termname* designation.

Defining Your Terminal: UNIX

To define your terminal in UNIX, select the appropriate command for your shell.

For the C shell:

setenv TERM INGRES termname

For the Bourne shell:

TERM_INGRES=termname
export TERM_INGRES

The parameter *termname* is the designation for your terminal type. For more information, see Terminal Names.

For example, if you have a VT100 terminal, and you want to be able to use the arrow keys as cursor movement keys and the keypad keys as definable function keys, consulting <u>Terminal Names</u> tells you that vt100i is the proper designation.

To define your terminal accordingly to Ingres, enter one of the following commands:

C shell:

setenv TERM_INGRES vt100i

Bourne shell:

TERM INGRES=vt100i export TERM INGRES

Thereafter, you can use the VT100 default assignment of keys for cursor movement and executing forms commands in Ingres.

The vt100nk is another terminal designation available for VT100 terminals. This terminal designation is particularly suited to applications that require use of the keypad for numeric input. This designation gives the user access to the arrow keys and the top four function keys on the numeric keypad. The other keys on the keypad are available for numeric input.

If your UNIX system provides full support for VT220 terminals, you can define a VT220 terminal as vt220 and use the VT220 keystrokes. Some UNIX systems do not provide full support for VT220 terminals. In this case, you must set a VT220 terminal to emulate a VT100, using the VT100 keystrokes, as discussed previously.

Defining Your Terminal: VMS

To define your terminal in VMS, use the following command:

define TERM INGRES termname

The parameter termname is the designation for your terminal type. For more information, see **Terminal Names**.

For instance, if you have a VT100 terminal, and you want to be able to use the arrow keys as cursor movement keys and the keypad keys as definable function keys, consulting Terminal Names tells you that vt100i is the proper designation. To define your terminal accordingly to Ingres, execute the following command:

define term_ingres vt100i

In most VAX/VMS installations, VT100 and VT220 terminals are prevalent. We recommend the vt100i designation for VT100 terminals and the vt220i designation for VT220 terminals.

Terminal Names

The Forms Run-time System must function correctly on the terminals listed here. However, not all of these terminals have been tested to determine the functionality of the Forms Run-time System. If you have any problems with the terminal designations, please notify technical support.

If you cannot locate your terminal on this list, look through the entries in the termcap file to find an entry that meets your needs:

Terminal Type	Menu Key	Name
ADDRINFO	ESC	addrinfo
ADDS CONSUL 980	ESC	a980
ADDS REGENT 100	ESC	regent100
ADDS REGENT 20	ESC	regent20
ADDS REGENT 25	ESC	regent25
ADDS REGENT 40	ESC	regent40
ADDS REGENT 60	ESC	regent60
REGENT 60 w/no arrow keys	ESC	regent60na
ADDS REGENT SERIES	ESC	regent
AMPEX DIALOGUE 80	ESC	ampex
ANN ARBOR	ESC	aa
ANN ARBOR AMBASSADOR 48 with destructive backspace	ESC	aaadb
ANN ARBOR AMBASSADOR/48 lines	ESC	aaa
ANSI PC console with function keys	PF1	ansinf
ANSI PC console with no function keys	PF1	ansif
BDS1 in Wyse-50 mode	ESC	bds1
BDS1 in Wyse-50 mode with function keys	PF1	bds1f
BEEHIVE SUPER BEE	ESC	sb1
FIXED SUPERBEE	ESC	sb2
BEEHIVE IIIm	ESC	bh3m
BULL QUESTAR 210	ESC	Q210
BULL QUESTAR 210 with function keys	F1	Q210f

Terminal Type	Menu Key	Name
BULL QUESTAR 305/310	ESC	Q310
BULL QUESTAR 305/310 in 132-column mode	ESC	Q310-w
BULL QUESTAR 305/310 with function keys	PF1	Q310f
BULL QUESTAR 305/310 in 132-column mode with function keys	PF1	Q310-wf
BULL X-TERMINAL running WindowView with function keys	F1	bwvf
CONCEPT 100	ESC	c100
CONCEPT 100 slow	ESC	c100s
CONCEPT 100 slow reverse video	ESC	c100rvs
C100 reverse video	ESC	c100rv
C100 with 4 pages	ESC	c1004p
C100 reverse video with 4 pages	ESC	c100rv4p
C100 with no arrows, reverse video, 4 pages	ESC	c100rv4pna
C100 with printer port, reverse video, 4 pages	ESC	c100rv4ppp
CDC	ESC	cdc456
CDC456tst	ESC	cdc456tst
CDI1203	ESC	cdi
COMPUCOLORII	ESC	compucolor
CYBERNEX mdl-110	ESC	mdl110
DATAMEDIA 1520	ESC	dm1520
DATAMEDIA 1521	ESC	dm1521
DATAMEDIA 2500	ESC	dm2500
DATAMEDIA 3025a	ESC	dm3025
DATAMEDIA 3045a	ESC	dm3045
DATAMEDIA dt80/1	ESC	dt80
DATAMEDIA dt80/1 in 132 character mode	ESC	dt80132
DATAPOINT 3360	ESC	datapoint
DEC VT100 with function keys activated	PF1	vt100f
DEC VT100 with function keys activated (3.0 release)	PF1	vt100k

Terminal Type	Menu Key	Name
DEC VT100 with numeric keypad	PF1	vt100nk
DEC VT100 without function keys activated	ESC	vt100
DEC VT100 in 132-column mode with function keys activated	PF1	vt100fw
DEC VT100 in 132-column mode with function keys activated (3.0 release)	PF1	vt100kw
DEC VT100 in 132-column mode with numeric keypad	PF1	vt100nkw
DEC VT100 with function keys activated and Return key mapped to Nextitem instead of Clearrest (works like vt100f, but Return does not clear to end of field)	PF1	∨t100i
DEC VT100 in 132-column mode with function keys activated and Return key mapped to Nextitem instead of Clearrest (works like vt100fw, but Return does not clear to end of field)	PF1	vt100iw
DEC VT100 in 132-column mode without function keys activated	PF1	vt100w
DEC VT100 with no initialization	ESC	vt100n
DEC VT125	ESC	vt125
DEC VT220	PF1	vt220
DEC VT220 with Return key mapped to Nextitem instead of Clearrest	PF1	vt220i
DEC VT220 in 132-column mode	PF1	vt200w
DECVT220 in 132-column mode with Return mapped to Nextitem instead of Clearrest	PF1	vt220iw
DEC VT241	PF1	vt241
DEC VT50	ESC	vt50
DEC VT50h	ESC	vt50h
DEC VT52	ESC	vt52
DEC VT132	ESC	vt132
DECTERM EMULATOR with function keys and mouse support	PF1	decterm
DELTA DATA 5000	ESC	delta
DIGILOG 333	ESC	digilog
ENVISION	PF1	envision

ENVISION with color GENERAL TERMINAL 100A (formerly INFOTON 100)	PF1	
GENERAL TERMINAL 100A (formerly INFOTON 100)		envisionc
	ESC	i100
HAZELTINE 1500	ESC	h1500
HAZELTINE 1510	ESC	h1510
HAZELTINE 1520	ESC	h1520
HAZELTINE 1552	ESC	h1552
HAZELTINE 1552 reverse video	ESC	h1552rv
HAZELTINE 2000	ESC	h2000
HEATHKIT h19	ESC	h19
HEATHKIT h19 ansi mode	ESC	h19A
HEATHKIT with keypad shifted	ESC	h19bs
HEATHKIT with keypad shifted, underscore cursor	ESC	h19us
HEATHKIT with underscore cursor	ESC	h19u
HEWLETT PACKARD 2392 in hp mode, 80 columns	PF1	hp2392
HEWLETT PACKARD 2393 in hp mode, 80 columns	PF1	hp2393
HEWLETT PACKARD 2394 in hp mode, 80 columns	PF1	hp2394
HEWLETT PACKARD 700/92 in hp mode, 80 columns	PF1	hp70092
HEWLETT PACKARD 700/94 in hp mode, 80 columns	PF1	hp70094
HEWLETT PACKARD 700/96 in hp mode, 80 columns	PF1	hp70096
HEWLETT PACKARD 700/98 in hp mode, 80 columns	PF1	hp70098
HEWLETT PACKARD 2621	ESC	2621
HEWLETT PACKARD 2621 with 45 keyboard	ESC	2621k45
HEWLETT PACKARD 2621 with labels	ESC	2621wl
HEWLETT PACKARD 2621 with no labels	ESC	2621nl
HEWLETT PACKARD 2621 48 lines	ESC	big2621
HEWLETT PACKARD 2626	ESC	hp2626
HEWLETT PACKARD 2640a	ESC	2640
HEWLETT PACKARD 2648a graphics terminal	ESC	hp2648
HEWLETT PACKARD 264x series	ESC	2640b
HEWLETT PACKARD 264x series	ESC	hp

Terminal Type	Menu Key	Name
IBM 3101-10	ESC	ibm
IBM PC	ESC	ibmpc
INFOTON 400	ESC	i400
INFOTON KAS	ESC	infotonKAS
ISC modified owl 1200	ESC	intext
ISC8001	ESC	8001
LSI adm2	ESC	adm2
LSI adm3	ESC	adm3
LSI adm3a+	ESC	adm3a+
LSI adm31	ESC	adm31
LSI adm3a	ESC	adm3a
LSI adm42	ESC	adm42
MICRO BEE SERIES	ESC	microb
MICROTERM ACT IV	ESC	microterm
MICROTERM ACT V	ESC	microterm5
MICROTERM MIME1	ESC	mime
FULL BRIGHT MIME1	ESC	mimefb
HALF BRIGHT MIME1	ESC	mimehb
MICROTERM MIME2A (emulating an enhanced SOROC iq120)	ESC	mime2as
MICROTERM MIME2A (emulating an enhanced VT52)	ESC	mime2a
MIME1 emulating 3A	ESC	mime3a
MIME1 emulating enhanced 3A	ESC	mime3ax
NETRONICS	ESC	netx
PERKIN ELMER 1100	ESC	fox
PERKIN ELMER 1200	ESC	owl
SOL	ESC	sol
SOROC 120	ESC	soroc
SOUTHWEST TECHNICAL PRODUCTS CT82	ESC	swtp
SUN CMDTOOL with function keys	PF1	sun-cmdf

Terminal Type	Menu Key	Name
SUN CMDTOOL no function keys	ESC	sun-cmd
SUN CONSOLE	ESC	sun
SUN CONSOLE with function keys	F2	sunf
SUN MICROSYSTEMS SUN TYPE5 keyboard for shelltool/commandtool	PF1	suntype5
SUN TERMINAL EMULATER	PF1	vt100te
SUNTOOLS CONSOLE emulator	R11	sunm
SUPER BEE with insert character	ESC	superbeeic
TEKTRONIX 4105	PF1	tk4105
TEKTRONIX 4105 with color	PF1	tk4105c
TEKTRONIX 4105 with 24 lines and color and function keys	PF1	vt4105c
TEKTRONIX 4106 with function keys	PF1	tk4106
TEKTRONIX 4107 with function keys	PF1	tk4107
TEKTRONIX 4115 with function keys	PF1	tk4115
TELERAY 1061	ESC	t1061
TELERAY 1061 with fast PROMs	ESC	t1061f
DUMB TELERAY 3700	ESC	t3700
TELERAY 3800 series	ESC	t3800
TELETEC DATASCREEN	ESC	teletec
NEW TELEVIDEO 912	ESC	912b
NEW TELEVIDEO 920	ESC	920b
OLD TELEVIDEO 912	ESC	tvi912
OLD TELEVIDEO 920	ESC	tvi920
VISUAL 200 no function keys	ESC	vi200f
VISUAL 200 reverse video	ESC	vi200rv
VISUAL 200 reverse video using insert character	ESC	vi200rvic
VISUAL 200 using insert character	ESC	vi200ic
VISUAL 200 with function keys	ESC	vi200
VT100f in 132 mode that supports 80/132 size change	PF1	vt100fwc

Terminal Type	Menu Key	Name
VT100f that supports 80/132 size change	PF1	vt100fc
VT100f in Xterm with sizing on startup and mouse support	PF1	vt100fx
VT100f with nextitem mapped and 80/132 size change	PF1	vt100ic
VT100f in 132 mode with nextitem and 80/132 size change	PF1	vt100iwc
VT200 in 7 bit with nextitem and reset to 8 bit	PF1	vt200-8i
VT200 in 7 bit, 132 cols, nextitem and reset to 8 bit	PF1	vt200-8iw
VT200 in 80 mode with nextitem and 80/132 support	PF1	vt200ic
VT200 in 132 columns and reset to 8 bits on exit	PF1	vt200-8w
VT200 in 132 mode with nextitem and 80/132 support	PF1	vt200iwc
VT220 that resets to 8 bits on exit	PF1	vt200-8
VT220 in 7 bit that supports 80/132 size change	PF1	vt200c
VT220 in 7 bit 132 mode and supports 80/132 switching	PF1	vt200wc
VT240 with function keys	PF1	vt240
VT241 terminal in 80 mode	PF1	vt241
VT241 terminal in 132 mode	PF1	vt241w
VT3XX running as a vt200 in 132 mode	PF1	vt300w
VTU 0010	ESC	hn10
VTU 0010 with function keys	F1	hn10f
VTU 0040	ESC	hn40
VTU 0040 with function keys	F1	hn40f
VTU 0050	ESC	hn50
VTU 0050 with function keys	F1	hn50f
XEROX 1720	ESC	x1720
XITEX sct-100	ESC	xitex
ZENTEC 30	ESC	zen30

Appendix B: Defining Function and Control Keys

This appendix explains how to define function and control keys in Microsoft Windows (function, control, and arrow keys in UNIX and VMX) to the FRS for use in user-designed applications or to customize your keyboard for use with the Ingres forms-based tools. FRS is a built-in screen management system for all forms-based tools, as well as for custom applications that use forms.

When designing custom applications, the actual keystrokes that you employ to perform various functions can differ from those used with the Ingres formsbased tools. If you want to maintain consistency with key definitions in these forms-based tools, you can use Ingres conventions when programming menu items, cursor movement, and other operations performed by users.

This appendix also describes how to define keys to the FRS to customize the end user's environment while the user is running either forms-based tools or specialized Ingres applications. Ordinarily, such customizing is implemented by the application developer, rather than by end users of applications.

Use mapping files to map menu item operations, cursor movement, and all other operations, to function or control keys, and (in UNIX and VMS) arrow keys on your keyboard. Once the mapping has been specified, you or the end user can execute the operation by pressing the specified key. If the keyboards at your installation do not support function keys, you can still map operations to control keys or (in UNIX and VMS) arrow keys. The end user can enter a control character to execute the operation.

This appendix includes environment-specific Key Mapping Overview and Troubleshooting sections.

Key Mapping Overview (PC Environment)



These files define keyboard key usage in the FRS for Ingres on a PC:

- Termcap file
- FRS default key-mapping file (or personal variation of this file)
- Application key-mapping files

The first two files define and map the overall use of keys in the FRS for a standard PC. Application key-mapping files define and map the use of keys within a specific application that an Ingres user can design.

Termcap File

The Ingres termcap file for the PC environment contains:

- Statements that define the basic capabilities of your PC to the FRS. For more information, see the appendix "Writing Termcap Descriptions."
- Escape sequences that associate keys on your keyboard with internal program function, arrow, and control keys

Ingres defines physical keys and key combinations in the termcap file by associating their escape sequences with a set of 40 internal program function keys (pf1 through pf40), the arrow keys (up, down, right, and left), and some ASCII control keys. For example, F1 on an IBM PC AT keyboard is assigned to the internal function key, pf1, the Shift+F1 key combination is assigned to internal function key, pf11, and the Insert key is assigned to the ASCII control key, controlE. The internal function and control keys are then mapped to Ingres operations in a mapping file. This makes it possible to map predefined Ingres operations to many more physical keys than the standard set of function keys on your PC keyboard.

ASCII control keys that have been mapped to operations but have *not* been defined in the termcap file can be invoked by pressing the appropriate Ctrl+key combination. However, the following control keys are reserved by the operating system for its own use and must not be mapped to any operations in any key mapping file:

- Ctrl+C
- Ctrl+P
- Ctrl+S

The termcap file supports the enhanced keyboard function keys, F11, F12, Shift+F11, Shift+F12, Ctrl+F11, and Ctrl+F12. Depending on the key-mapping file you use, these keys can or cannot be assigned to Ingres functions.

The following table shows the key assignments for your PC in the termcap file:

Internal Ingres Key Name	PC Key
controlE	Insert
controlH	Backspace
controlY	Home
controlZ	End
Up arrow	Up arrow
Down arrow	Down arrow
Right arrow	Right arrow
Left arrow	Left arrow
pf1	F1
pf2	F2
pf3	F3
pf4	F4
pf5	F5
pf6	F6
pf7	F7
pf8	F8
pf9	F9
pf10	F10
pf11	Shift+F1
pf12	Shift+F2
pf13	Shift+F3
pf14	Shift+F4
pf15	Shift+F5
pf16	Shift+F6
pf17	Shift+F7
pf18	Shift+F8
pf19	Shift+F9
pf20	Shift+F10
pf21	Alt+F1
pf22	Alt+F2

Internal Ingres Key Name	PC Key
pf23	Alt+F3
pf24	Alt+F4
pf25	Alt+F5
pf26	Alt+F6
pf27	Alt+F7
pf28	Alt+F8
pf29	Alt+F9
pf30	Alt+F10
pf31	F11 and Ctrl+F1
pf32	F12 and Ctrl+F2
pf33	Shift+F11 and Ctrl+F3
pf34	Shift+F12 and Ctrl+F4
pf35	Alt+F11, Ctrl+F5, and Ctrl+F11
pf36	Alt+F12, Ctrl+F6, and Ctrl+F12
pf37	PgUp
pf38	PgDn
pf39	Delete
pf40	Escape

FRS Mapping File

A mapping file defines the use of the program function and control keys in the FRS. The mapping file associates a pf or control key with a particular Ingres function by mapping it to a FRS object. There are different types of FRS mapping objects. A FRS object can be an:

- FRS command
- Menu item
- FRS Key

An example of a FRS object is the FRS command, menu. FRS commands are built-in functions of the FRS, such as moving to the menu line or moving to the next field, that enable the user to view and edit the data on a form. The FRS defines the behavior of each FRS command. For instance, the menu command moves the cursor to the menu line.

The FRS mapping file maps these functions to the pf keys and other internal keys associated with the physical keys on your keyboard. The entire mapping sequence in the FRS mapping file and the termcap file can be depicted as:

```
FRS mapping object = pf or control key = keyboard key
```

For example, the key mapping sequence for the menu command can be represented as:

```
menu FRS command = pf2 program function key = F2 key
```

The actual mapping statement in the FRS mapping file would be:

```
menu = pf2 (F2)
                   /* Menu (menu key) */
```

The key name shown in parentheses is a *label* that indicates to the user which physical key to press. The functionality of each key mapping is shown as a comment statement between the characters /* and */.

This mapping scheme provides flexibility in assigning functions to keyboard keys, without requiring editing of the termcap file. You can easily assign any FRS mapping object to a different key by changing the mapping statement in the FRS mapping file, or by overriding it with a statement in a mapping file of higher precedence. For more information, see Application Mapping Files.

You can also substitute your own personal key mapping file for the FRS mapping file. To do so, set the Ingres KEYS environment variable to the substitute file in a batch file, such as your autoexec.bat file, using the following syntax:

```
set INGRES KEYS=fullpathname\filename
```

This can be useful if multiple users share the same PC and want to customize their key map assignments individually.

Mapping File Example

The following is an example of an FRS mapping file:

```
/* This is an example of a mapping file */
menuitem2 = pf3 (F3)
menuitem3 = controlE (^E)
 frskey7 = pf8
previousfield = controlP (Sh-Tab)
 rubout = controlDEL (Backspace)
controlA = off
/* this turns control-A off */
pf7 = off
```

The first line of this sample file is a *comment*. Comments can appear anywhere in a mapping file. Their purpose is to provide information to someone looking at the file; they are ignored by the FRS.

The next five lines are examples of *mapping statements*. All mapping statements follow the same basic syntax. To the left of the equal sign is a mapping object, which specifies the operation or function to which the key is being mapped. To the right of the equal sign is the internal program function key or control key that maps to, and activates, the mapping object. For instance, the following statement specifies that the second item on each menu line (menuitem2) map to program function key pf3:

```
menuitem2 = pf3 (F3)
```

The parentheses to the right of the internal function or control key contain a label. The label tells the user what key to press to activate the menu selection or operation. The label appears on the menu line, if appropriate, or in the Help Keys operation display. If no label is specified in the mapping statement, Ingres displays an appropriate default label. Although you can put any text you want here, you must make sure the label indicates the physical key to which the internal function key is mapped in the termcap file, so that the end user presses the correct key to invoke the operation. In the preceding example, a user invokes the operation specified by the second item on any menu by pressing F3.

The following statement enables the user to move the cursor to the previous field on a form by pressing Sh-Tab, which is mapped internally to the controlP function:

```
previousfield = controlP (Sh-Tab)
```

The Ingres controlP function has been mapped internally to Sh-Tab, rather than to the Ctrl+p key combination, because Ctrl+p is trapped by the operating system. For more information, see The Termcap File.

The last two statements in the example are known as disabling statements. A disabling statement is used to disable a control or function key. For example, the following statement turns off the key mapped to the pf7 program function key (which is associated with function key F7 in the termcap file):

```
pf7 = off
```

This means that the function key F7 has no effect in a forms program governed by this map file, and merely beeps when pressed.

For more information on FRS objects and the syntax required to map them to keys, see FRS Mapping Objects and Mapping File Syntax.

Standard FRS Mapping Files

Depending on your PC keyboard and environment, you can use the following standard FRS mapping files provided with the forms-based tools:

- frs.map, for a PC without function keys
- ibmpc.map, for an ANSI standard PC

Ingres always reads and uses the frs.map file as the basic key mapping file. You cannot change this by setting an environment variable. However, you can point to an additional mapping file from within the termcap file by setting the map= entry to the following file:

ibmpc.map

Mappings in the termcap-specified key map file take precedence over mappings in the frs.map file. All other key mappings in the frs.map file remain active.

The ibmpc.map mapping file is designed to accommodate PC computers with older keyboards having only ten function keys. This mapping file assigns functions to only ten PC function keys.

You can edit the mapping files or create an alternate mapping file. However, keep in mind the physical key assignments in the termcap file, because the label assigned to a pf key must match the physical key associated with that pf key.

The following table depicts the FRS object-to-key mappings in the standard FRS mapping files. For reference purposes, the table displays the mapping file settings in tabular form and alphabetical order, within the three groups of FRS objects (FRS keys, menu items, and FRS operations).

FRS Object & Function	frs.map	ibmpc.map
frskey1	N/A	pf1
Help (invoke help facility)		(F1)
frskey2	N/A	pf6
Quit (exit the system)		(F6)
frskey3	N/A	pf10
End (return to previous frame)		(F10)
frskey4	N/A	pf9
Go (execute function)		(F9)
frskey5	N/A	pf37
Top (move to top of table field)		(Home)
frskey6	N/A pf38	pf38
Bottom (move to bottom of table field)		(End)
frskey7	N/A	pf5
Find (search table field for specified string	string) (F5)	

FRS Object & Function	frs.map	ibmpc.map
frskey8	N/A	pf3
Save object in database		(F3)
frskey9	N/A	pf7
Undo or Forget (undo last action or forget changes made in frame)		(F7)
frskey10	N/A	pf8
List the available choices		(F8)
menuitem1	N/A	pf11
Select first menu item		(Sh+F1)
menuitem2	N/A	pf12
Select second menu item		(Sh+F2)
menuitem3	N/A	pf4
Select third menu item - often edit		(F4)
menuitem4	N/A	pf14
Select fourth menu item		(Sh+F4)
menuitem5	N/A	pf15
Select fifth menu item		(Sh+F5)
menuitem6	N/A	pf16
Select sixth menu item		(Sh+F6)
menuitem7	N/A	pf17
Select seventh menu item		(Sh+F7)
menuitem8	N/A	pf18
Select eighth menu item		(Sh+F8)
menuitem9	N/A	pf19
Select ninth menu item		(Sh+F9)
menuitem10	N/A	pf20
Select tenth menu item		(Sh+F10)
clear	controlX	controlX
Clear remainder of field	(Ctrl-X)	(Ctrl+X)
clearrest	N/A	
Clear remainder of field (and move to next field?)	:	

FRS Object & Function	frs.map	ibmpc.map
deletechar	N/A	pf36
Delete the character under the cursor		(Delete)
downline	controlG	
Move down one line	(down arrow)	
duplicate	controlA	controlA
Auto-duplicate value while in fill mode	(Ctrl-A)	(Ctrl+A)
editor	controlV	controlV
Start default text editor on field	(Ctrl-V)	(Ctrl+V)
leftchar		controlR
Move left one space within a field		(left arrow)
menu		pf34
Moves cursor to the menu (ring menus require the Esc key)		(Esc)
mode	controlE	pf35 (Ins)
Switch between insert and overstrike mode	(Ctrl+E)	
newrow	controlN	controlN
Move to first column of next row in table field	(Ctrl+N)	(Ctrl+N)
nextfield	controll	controll
Move cursor to next field	(Tab)	(Ctrl+I)
nextitem	N/A	
Move cursor to next field without clearing this field		
nextword	controlB	
Move to next word in this field	(Ctrl+right arrow)	
previousfield	controlP	controlP
Move cursor to previous field	(Sh+Tab)	(Sh+Tab)
previousword	controlR	
Move to previous word in this field	(Ctrl+left arrow)	

FRS Object & Function	frs.map	ibmpc.map
printscreen	controlF	
Sends a copy of the currently displayed form to a file or the printer, depending on how the II_PRINTSCREEN_FILE environment variable/logical has been set. For more information, see the <i>System Administrator Guide</i> for the system on which your database resides.	(CtrI+F)	
redraw controlW		ControlW
Redraw the screen	(Ctrl+W)	(Ctrl+W)
rightchar	controlL	controlL (right arrow)
Move right one space within a field	(right arrow)	
rubout	controlH	controlH (Backspace)
Delete character immediately to left of the cursor	(Backspace)	
crolldown		pf39
Previous screen or set of rows in table field		(PgDn)
scrollleft	controlO (Ctrl+PgDn)	controlO (Ctrl+O)
Scroll left on a form		
scrollright	С	ControlU
Scroll right on a form		(Ctrl+U)
scrollup		pf40
Next screen or set of rows in table field		(PgUp)
shell		
Spawns a DOS shell		
upline	controlK	
Move up one line	(up arrow)	

Application Mapping Files

An application created with 4GL or one of the embedded query languages can use its own set of key mappings, invoked by the set_frs frs or set_forms frs (for 4GL) statements. Applications developers can use these statements in an application to read in a key-mapping file that is specific to that application or to map a FRS key to a function or control key explicitly in the application code.

An application mapping file takes precedence over the FRS mapping file. When an application starts up, the FRS merges all mapping files and resolves any conflicts between mapping statements by giving precedence to the statement in the mapping file of highest precedence. The FRS always honors the most recent reference to any mappable key in the file with the higher level of precedence.

For more information on application key mapping, see the Forms-based Application Development Tools User Guide.

Key Mapping Overview (UNIX and VMS Environments)



Before you can take advantage of the function key feature, the terminal must be defined to Ingres so that physical keys on the terminal become associated with logical functions. Through this mapping, the physical keys can execute various operations that are either built into the forms system or programmed inside the forms-based tools and custom applications.

These files are involved in defining keyboard key usage in the FRS:

- Termcap file
- Key mapping files

The locations (escape sequences) and availability of function (PF), control, and arrow keys are unique to the type of terminal you are using. Control keys are available on all ASCII terminals, but only certain types of terminals also support function keys.

The termcap file contains a description of all terminals supported by Ingres, including their available function, control, and arrow keys. When you start the FRS, it reads the appropriate terminal type description from the termcap file. Before using Ingres, make sure your terminal has been defined to the FRS in the termcap file.


Once the terminal has been defined in the termcap file, you can change FRS key definitions dynamically in the key mapping files at the installation, terminal type, user, and application mapping levels. This appendix describes the key mapping process in detail.

Role of the Termcap File

Fundamental changes to the FRS's interpretation of keystrokes for a particular terminal require modification of that terminal's termcap description. For example, if you want the FRS to permanently interpret a Down Arrow key as nextfield for the VT100i, you must change the termcap description for VT100i. Key map files cannot accomplish such changes directly.

Certain termcap files allow you to define the terminal to recognize function keys. For example, to use function keys with a VT100 or VT100-like terminal, the terminal must be defined as vt100i.

The vt100i definition turns the terminal's keypad into a set of 18 function keys, as shown in the following figure.



In the figure, the numbers correspond to the numbers that appear on the keys, while those in parentheses correspond to which function key that key is (for example, key #7 is the fifth function key (PF5).

VMS

Function keys do not work as expected if the user has issued the following VMS command:

set term/uppercase

This is because this VMS set term command translates all characters received from the terminal into uppercase characters. The escape sequences

for function keys are defined with lowercase characters in the termcap description. To correct this situation, create a new termcap description to define function key escape sequences with uppercase characters.

By default, a VT220 terminal uses function keys; therefore this terminal must be defined as vt220i. A VT220 can also emulate a VT100 terminal. If the terminal itself is set this way, it is appropriately defined to Ingres as vt100i. Other types of terminals with function keys can be defined to accept function key mappings by editing the termcap file descriptions for the terminal types. For more information, see the appendix "Writing Termcap Descriptions."

Users of terminals defined as vt100i or vt220i can also use arrow keys to move the cursor. For these terminals, the arrow keys are defined by default in the Ingres code to perform standard arrow key actions; for example, uparrow = upline and downarrow = downline. The use of arrow keys on any other terminal type can require the editing of its termcap file description.

No special terminal definition is required for control keys. Certain control keys, however, are reserved by the operating system for its own use and must not be mapped to any operations. These can include, but are not limited to:

- Control-C
- Control-O
- Control-Q
- Control-S
- Control-T
- Control-X
- Control-Y

Also, if your terminal uses escape sequences to define function keys (the case for terminals defined as vt100i and vt220i and most other terminals), you must also consider Escape as reserved.

Mapping Files

Typically, entries within mapping files define a connection between logical FRS mapping objects, which can be accessed by the forms system, and program function (pf) keys, control keys, and arrow keys on a keyboard.

There are different types of FRS mapping objects. A FRS object can be any one of the following:

- FRS command
- Menu item
- FRS Key

An example of an FRS object is the FRS command menu. FRS commands are built-in functions of the FRS, such as moving to the menu line or moving to the next field, that enable the user to view and edit the data on a form. The FRS defines the behavior of each FRS command. For instance, the menu command moves the cursor to the menu line.

A mapping file maps these functions to the function, control, and arrow keys that are defined for your terminal in the termcap file. The key mapping sequence in the mapping file and the termcap file can be depicted as follows:

```
In the mapping file as:
```

```
FRS mapping object = pf, control, or arrow key
```

In the termcap file as:

```
pf, control, or arrow key = escape sequence
```

For example, the key mapping sequence for the previous field command can be represented as follows:

```
In the mapping file as:
```

```
menu FRS command = pf1
```

In the termcap file as:

```
pf1 = escape sequence for pf1
```

The actual mapping statement in the FRS mapping file is:

```
menu = pf1 (PF1) /* Menu (menu key) */
```

The key name shown in parentheses is a *label* that indicates to the user which physical key to press. The functionality of each key mapping is shown as a comment statement between the characters /* and */.

This mapping scheme provides flexibility in assigning functions to keyboard keys, without requiring editing of the termcap file. You can easily assign any FRS mapping object to a different key by changing the mapping statement in the mapping file, or by overriding it with a statement in a mapping file of higher precedence. For more information, see <u>Levels of Mapping</u>.

Mapping File Example

The following example of a mapping file illustrates the full range of statements available to specify any sort of mapping:

```
/* This is an example of a mapping file */
menuitem2 = pf3  (Key 3)
 menuitem3 = controlE (^E)
 frskey7 = pf8
previousfield = controlP
nextfield = rightarrow
rubout = controlDEL
controlA = off
/* this turns control-A off */
pf7 = off
```

The first line in the mapping file sample is a *comment*. Comments can appear anywhere in a mapping file. Their purpose is to provide information to someone looking at the file; they are ignored by the FRS.

The next five lines are examples of *mapping statements*. All mapping statements follow the same basic syntax. To the left of the equal sign is a mapping object, which specifies the operation or function to which the key is being mapped. To the right of the equal sign is the internal designation for the function, control, or arrow key that maps to, and activates, the mapping object. For instance, the following statement specifies that the second item on each menu line (menuitem2) maps to program function key pf3:

```
menuitem2 = pf3 (Key 3)
```

This mapping statement contains a label within parentheses to the right of the internal program function key. The specified label appears next to the second menu item on the user's screen to indicate what key to press to activate the menu selection (in this case, key 3). The label also appears in the Help Keys operation display. If no label is specified in the mapping statement, an appropriate default label is displayed on the menu line and in the Help Keys display. If you specify the label explicitly, it must indicate the physical key on the keyboard that generates the correct escape sequence, as defined in the termcap file, for the specified program function key, control key, or arrow key.

The following statement enables the user to move the cursor to the previous field on a form by pressing Control-P:

```
previousfield = controlP
```

This mapping statement does not contain a label.

The last two statements in the example are known as disabling statements. A disabling statement is used to disable a function, control, or arrow key. For example, the following statement turns off the key mapped to the pf7 program function key:

```
pf7 = off
```

This means that the key has no effect in a forms program governed by this map file, and merely beeps when pressed.

For more information on FRS objects and the syntax required to map them to keys, see FRS Mapping Objects and Mapping File Syntax topics.

Levels of Mapping

The FRS allows you to define key mappings for function, control, and arrow keys on four separate levels:

- Installation
- Terminal type
- User (environment)
- Application

This allows you to tailor key definitions to the specific requirements of the environment, the terminal type, the user, and the application. The installation-level mapping has the lowest precedence, and is overridden by all other mappings. Through terminal type-level mapping, a default can exist for all terminals of a given type, such as VT100s or VT220s. This default is overridden by any conflicting user or application mappings. The user-level mapping is next in precedence, allowing each individual user a good degree of latitude in the use of function, control, and arrow keys. Application-specific mappings have the highest precedence to provide the same environment to all users of an application and to ensure data integrity both in the form and the database.

When the FRS starts up, the four levels of mapping are merged and conflicts are resolved based on the precedence outlined previously. Any additional mapping specified by the program during the running of an application is merged in the same manner and takes precedence over conflicting mappings. While the four levels of mappings can coexist, any of the levels can be omitted. Because it is possible that a function, control, or arrow key is defined at more than one of the four levels, the FRS always honors the most *recent* reference to any mappable key from a file of higher-level precedence.

The following sections discuss each of the various levels at which mapping occurs and how to specify the mapping file for each level.

Installation-Level Mapping

As mentioned previously, installation-level mapping has the lowest precedence. It provides an underlying default, common to all terminal types, which can be overlaid with mappings for specific terminal types, as well as individual users and applications.

A default installation-level mapping file is shipped with Ingres. Because this default file references only control keys and not function keys, it must be usable for all Ingres terminal types.

UNIX

VMS

The complete file specification for this mapping file is:

```
$II_SYSTEM/ingres/files/frs.map X
```

```
II_SYSTEM:[ingres.files]frs.maps
```

It contains the following statements:

```
/* Move cursor to next field */
 nextfield = controlI (Tab)
/* Move cursor to previous field */
 previousfield = controlP (^P)
/* Move up one word within field */
 nextword = controlB (^B)
/* Move back one word within field */
 previousword = controlR (^R)
/* Switch between insert and */
/* overstrike mode*/
 mode = controlE (^E)
/* Redraw the screen */
 redraw = controlW (^W)
/* Delete character under the cursor */
 deletechar = controlD (^D)
/* Delete character to left of cursor */
 rubout = controlDEL (Delete)
/* Start default text editor on field */
 editor = controlV (^V)
/* Move left one space within a field */
 leftchar = controlH (^H)
/* Move right one space within a field */
 rightchar = controlL (^L)
/* Move down one line *
 downline = controlJ (^J)
/* Move up one line */
 upline = controlK (^K)
/* Move to first column of next row */
/* in table field */
 newrow = controlN (^N)
/* Clear the field */
 clear = controlX (^X)
/* Clear out rest of field */
/* and move to next field */
 clearrest = controlM (Return)
/* Scroll up on the form */
 scrollup = controlF (^F)
/* Scroll down on the form */
 scrolldown = controlG (^G)
/* Scroll left on a form */
 scrollleft = control0 (^0)
/* Scroll right on a form */
 scrollright = controlU (^U)
/* Auto-duplicate value while in fill mode*/
 duplicate = controlA (^A)
```

While you can edit this file to customize your installation's default mappings, you must *not* change the name of this file. The FRS automatically looks for the file when starting up. If you do modify this file, be sure to map only those keys that are available for all terminal types at your installation.

Notice that the file does not specify a menu key. This is because the FRS command menu automatically defaults to Escape.

Terminal-Type Level Mapping

The next higher level of mapping is terminal type. Each terminal type used at your installation needs its own mapping file, because function key support varies from terminal to terminal. Combined with the installation mapping, this file provides a common terminal default for the function and control keys, which can be altered by mappings at higher levels to fit the needs of an application or an individual user. Arrow keys are defined by default in the termcap file.

The terminal-type mapping file must be placed in the following directory: \$II SYSTEM/ingres/files/

UNIX

VMS

II_SYSTEM:[ingres.files]

You can specify the terminal-type mapping file name with the mf capability in the termcap file description for each terminal type in use at an installation. You can also point to a termcap file by using the II_TERMCAP_FILE environment variable/logical.

Default mapping files for VT100 and VT220 terminals are shipped with Ingres. You can edit these files if desired. (The termcap file descriptions for the vt100i and vt220i terminal definitions already have the names of their mapping files specified; therefore, there is no need to edit those termcap descriptions.)

Terminal Type vt100i Map File For VT100 terminals defined as the vt100i terminal type, the mapping file location is:

UNIX

VMS

\$II_SYSTEM/ingres/files/vt100i.map

II_SYSTEM:[ingres.files]vt100i.map

It contains the following statements:

```
/* Menu Key */
  menu = pf1 (PF1)
/* Help facility */
 frskey1 = pf2 (PF2)
/* Quit from program */
  frskev2 = pf4 (PF4)
/* End current screen and return */
/* to previous screen */
  frskey3 = pf3 (PF3)
/* Go or execute function */
  frskey4 = pf18 (Enter)
/* Put cursor on top of form or */
/* table field*/
  frskey5 = controlK (^K)
/* Put cursor on bottom of form or */
/* table field*/
 frskey6 = controlJ (^J)
/* Find next occurrence of string*/
/* in this column of table field
  frskey7 = controlF (^F)
/* Save object in database */
  frskey8 = pf16 (0)
/* Cancel and undo */
 frskey9 = pf17 (.)
/* ListChoices */
  frskey10 = pf7 (9)
/* Scroll page or form left */
  scrollleft = controlL (^L)
/* Scroll page or form right */
  scrollright = controlH (^H)
/* Previous screen or set of rows */
/* in table field */
  scrolldown = pf8 (-)
^{\prime *} Next screen or set of rows in ^{*\prime}
/* table field */
  scrollup = pf12 (,)
/* Print contents of current screen */
/* to file or printer */
  printscreen = controlG (^G)
/*<sup>'</sup>Select first menu item */
 menuitem1 = pf13 (1)
/* Select second menu item */
  menuitem2 = pf14 (2)
/* Select third menu item */
 menuitem3 = pf15 (3)
/* Select fourth menu item */
 menuitem4 = pf9 (4)
/* Select fifth menu item */
  menuitem5 = pf10 (5)
/* Select sixth menu item */
  menuitem6 = pf11 (6)
/* Select seventh menu item */
 menuitem7 = pf5 (7)
/* Select eighth menu item */
menuitem8 = pf6 (8)
/* Move cursor to next field */
/* defined to controlI in frs.map */
/* Move cursor to previous field */
/* defined to controlP in frs.map */
/* Move up one word within field */
 nextword = controlU (^U)
/* Move back one word within field */
/* defined to controlR in frs.map */
/* Switch between insert and overstrike */
/* mode defined to controlE in frs.map */
/* Redraw the screen defined to controlW */ /* in frs.map */
```

UNIX

VMS

Terminal Type vt220i

Map File

UNIX

VMS

```
/* Delete the character under the cursor */
/* defined to controlD in frs.map */
/* Delete character immediately to left */
/* of cursor--defined to controlDEL */
/* in frs.map */
/* Start default text editor on field */
/* defined to controlV in frs.map */
/* Move to first column of next row */
/* in table field defined to controlN */
/* in frs.map */
/* Clear the field */
 clear = controlX (^X)
 /* Clear the field */
 clear = controlB (^B) ■/* Move to nextitem in form. If on */
/* regular field, move to next field. */
/* If in table field, move to next column */
/* if NOT in last accessible column.*/
/* Move to next row if in last accessible */
/* column of table field. */
 nextitem = controlM (Return)
/* Auto-duplicate value while in */
/* fill mode defined to controlA */
/* in frs.map */
The default file for VT220 terminals is located in:
$II_SYSTEM/ingres/files/vt220i.map
II_SYSTEM:[ingres.files]vt220i.map
```

The VT220 mapping file contains these statements:

```
/* Menu Key */
 menu = pf1 (PF1)
/* Help facility */
 frskey1 = pf15 (Help)
/* Quit from program */
 frskev2 = pf4 (PF4)
/* End current screen and */
/* return to previous screen */
 frskey3 = pf3 (PF3)
/* Go or execute function */
 frskey4 = pf16 (Do)
^{\prime *} Put cursor on top of form or ^{*}/
/* table field */
 frskey5 = controlK (^K)
/* Put cursor on bottom of form or */
/* table field */
 frskey6 = controlJ (^J)
/* Find next occurrence of string */
/* in this column of table field */
 frskey7 = pf21 (Find)
/* Save function */
 frskey8 = pf10 (PF10)
/* Undo and cancel */
 frskey9 = pf2 (PF2)
/* Bring Up ListChoices */
 frskey10 = pf20 (PF20)
/* Scroll page or form left */
 scrollleft = controlL (^L)
/* Scroll page or form right */
 scrollright = controlH (^H)
/* Previous screen or set of rows */
/* in table field */
 scrolldown = pf25 (Prev Screen)
/* Next screen or set of rows */
/* in table field */
 scrollup = pf26 (Next Screen)
/* Print contents of current screen */
/* to file or printer */
 printscreen = pf8 (PF8)
/* Select first menu item */
 menuitem1 = pf11 (PF11)
/* Select second menu item */
 menuitem2 = pf12 (PF12)
/* Select third menu item */
 menuitem3 = pf13 (PF13)
/* Select fourth menu item */
 menuitem4 = pf14 (PF14)
/* Select fifth menu item */
 menuitem5 = pf17 (PF17)
/* Select sixth menu item */
 menuitem6 = pf18 (PF18)
/* Select seventh menu item */
 menuitem7 = pf19 (PF19)
/* Remove character under cursor */
 deletechar = pf23 (Remove)
/* Switch between insert and overstrike */
 mode = pf22 (Insert Here)
/* Move cursor to next field defined */
/* to controlI in frs.map */
/* Move cursor to previous field */
/* defined to controlP in frs.map */
/* Move up one word within field */
 nextword = controlU (^U)
/* Move back one word within field */
/* defined to controlR in frs.map */
/* Redraw the screen defined to */
```

UNIX

VMS

```
/* controlW in frs.map */
/* Delete character immediately to left */
/* of cursor defined to controlDEL */
/* in frs.map */
/* Start default text editor on field */
/* defined to controlV in frs.map */
/* Move to first column of next row in */
/* table field defined to controlN */
/* in frs.map */
/* Clear the field */
 clear = controlX (^X) ■
/* Clear the field */
 clear = controlB (^B) ■
/* Move to nextitem in form. If on */
/* regular field, move to next field. */
/* If in table field, move to next column */
/* if NOT in last accessible column.*/
/* Move to next row if in last accessible */
/* column of table field. */
 nextitem = controlM (Return)
/* Auto-duplicate value while in fill */
/* mode defined to controlA in frs.map */
```

User-Level Mapping

Next higher in precedence are the individual user's mappings. Of the four levels, user-level mapping is probably the least frequently used; the combination of mappings at the other three levels suffices for most users.

To make the user-level mapping file known to the FRS, the user must execute the following command at the operating system level:

UNIX

For the C shell:

```
setenv INGRES KEYS full pathname/file name
```

For the Bourne shell:

```
INGRES_KEYS=full_pathname/ file_name
export INGRES_KEYS
```

The parameter *full-pathname/file_name* is the full pathname and file name for the mapping file. To eliminate the need to invoke this command for each terminal session, you can include this command in the file .login (C shell) or .profile (Bourne shell).

VMS

define INGRES_KEYS file_specificatio

The file_specification parameter is the full specification for the mapping file. To eliminate the need to invoke this command for each terminal session, you can include this command in the login.com file.

Application-Level Mapping

An application created with 4GL or one of the embedded query languages can use its own set of mappings, invoked by the set_frs frs or set_forms frs (for 4GL) statements. Applications developers can use these statements in an application to read in a key-mapping file that is specific to that application or to map an FRS key to a function, control, or arrow key explicitly in the application code.

Application-level mappings take precedence over all other mappings. For more information on application key mapping, see the Forms-based Application Development Tools User Guide.

Obtaining Information on Mappings

Within a forms-based system, such as QBF, a user can invoke the Help menu operation to find out the current settings for function and control keys, including (if UNIX or VMS) arrow keys. For more information, see online help. Within an embedded query language or 4GL application, you can get information about function, control, and arrow key mappings and other information about the FRS by using the inquire_frs command (inquire_forms in 4GL).

You can use this command to find out which key is mapped to a specific mapping object, the name of the application mapping file, or the current setting (on or off) of the menu map (the display of key labels on the menu line).

Windows

The button bar menu does not display associated function or control keys. Use the Help Keys operation to see these key mappings, or use the Menu and arrow keys to move the input focus bar to a menu item; the associated key appears in the message window on the bottom line of the main window.

kП

You can also obtain information about the user's terminal type so that application mapping can be coded conditionally, according to the particular user's terminal. (For complete information on inquire_frs and inquire_forms, see the Forms-based Application Development Tools User Guide.)

FRS Mapping Objects

You can map function and control keys (and arrow keys in UNIX or VMS) to several types of objects. These mappings allow the keys to be used to perform menu item operations, cursor movement, and virtually any other functions available in a forms application.

The three types of mapping objects are:

- FRS commands
- Menu items
- FRS keys

The following sections describe each type of mapping object in detail.

FRS Commands

FRS commands are built-in functions of the forms system that enable the user to view and edit the data on a form. Because they are actually built into FRS, they are available both in the Ingres forms-based tools, such as QBF, and in customized forms applications built with Vision, ABF, or the embedded query languages.

Through key mapping, you can link such capabilities as deleting a character, moving to the menu line, or scrolling within a table field, to program function and control keys (and arrow keys in UNIX or VMS), which are defined to Ingres as specific keyboard keys. For example, the following statement maps the redraw FRS command to controlW, which is defined to Ingres on most keyboards as the physical key, Control-W:

redraw = controlW

FRS commands allow you to write terminal-independent application programs while taking advantage of available mapping keys. The application does not specify which control or escape sequences the user must generate at the keyboard to run a block of code; it just specifies which FRS command runs that block of code. FRS commands cannot be executed directly in program code; they are only available to the user through key mapping. You can map any function or control key to any FRS command. You can also map any arrow keys to any FRS command.

Command Definitions

The following table lists the FRS commands and their definitions. When used as a mapping object, an FRS command name must be typed exactly as shown:

FRS Command	Meaning
clear	Clears field or menu input.
clearrest	Clears rest of field, beginning from current cursor position. Then moves to next field if cursor is not in a table field, to next column if not in last column of table field, to first column of next row if in last column of table field.
deletechar	Deletes character under cursor.
downline	Moves down one line in field or next row in table field.
duplicate	Enters a value in a simple field that duplicates a value in the previous row of a table. For more information, see Duplicating Previous Entries .
editor	Starts text editor on field.
leftchar	Moves left one character within field.
menu	Goes to the menu line (the Menu key).
mode	Switches between insert and overstrike editing mode.
newrow	Moves to first column of next row in table field.
nextfield	Goes to the next field on the form.
nextitem	Moves to next field if cursor is not in a table field, to next column if not in last column of table field, to first column of next row if in last column of table field. Unlike clearrest, does not clear rest of current field.
nextword	Moves forward one word within a field.
previousfield	Goes to the previous field on the form.
previousword	Moves backward one word within a field.
printscreen	Sends a copy of the currently displayed form to a file or the printer, depending on how the II_PRINTSCREEN_FILE environment variable/logical has been set. For more information, see the <i>System Administrator Guide</i> for the system on which your database resides.
redraw	Redraws the frame.
rightchar	Moves right one character within field.
rubout	Deletes character immediately to left of cursor.
scrolldown	Scrolls down in current table field or form, leaving cursor on same field.
scrollleft	Scrolls form left, leaving cursor on same field.
scrollright	Scrolls form right, leaving cursor on same field.

Windows

UNIX

VMS

FRS Command	Meaning
scrollup	Scrolls up in current table field or form, leaving cursor on same field.
upline	Move up one line in field or previous row in table field. $ lap{1}{3}$
shell	In UNIX and VMS, spawns (creates) a shellIn UNIX, spawns a Bourne shell only. ■
upline	In VMS, creates a DCL process.
	In UNIX and VMS, move up one line in field or previous row in table field. ■

Default mapping files are provided that assign keys to some or all of the FRS commands. For default mappings in the PC environment, see Mapping a FRS Mey. For default FRS command mappings in the UNIX or VMS environment, see the following section, Default Assignments.

Default Assignments



Ingres provides several default mapping files that contain key assignments for the FRS commands. The first is an installation-level mapping file, valid for all terminal types. The other two are default-mapping files for the VT100 and VT220 terminals. These mapping files assign default control or function keys to the FRS commands. The installation file assigns control keys to most of the FRS commands. The terminal-type files expand and, in certain instances, override the installation mappings.

The following table lists the FRS commands and their default installation-level and terminal-type level assignments for the vt100i and vt220i terminal types. Consult your system administrator to determine whether the defaults listed in the table are valid for your installation and terminal type. Check the files directory for other mapping files supplied with Ingres.

Note: The system administrator has the ability to modify the default mapping files provided with Ingres. If the files have been modified, the mappings for the FRS commands can differ from the following table. The system administrator can also create mapping files for other terminal types besides vt100i and vt220i. These terminal-type files would then override the installation-level file.

Mapping files for VT100 and VT220 terminals have been optimized to avoid unnecessary remapping functions that are already designated in the installation-level frs.map file. If you modify the frs.map file, be careful to ensure the reliability of the mapping files for the VT100 and VT220 terminals.

FRS Command	Installation (UNIX and VMS)	VT100i (VMS)	VT220i (VMS)
Clear	CONTROL-X	CONTROL-B	CONTROL-B
Clearrest	RETURN	N/A	N/A
Deletechar	CONTROL-D	CONTROL-D	REMOVE
Downline	CONTROL-J	down_arrow	down_arrow
duplicate	CONTROL-A	CONTROL-A	CONTROL-A
editor	CONTROL-V	CONTROL-V	CONTROL-V
leftchar	CONTROL-H	left_arrow	left_arrow
menu	ESC	PF1	PF1
mode	CONTROL-E	CONTROL-E	INSERT HERE
newrow	CONTROL-N	CONTROL-N	CONTROL-N
nextfield	TAB	TAB	TAB
nextitem	no default	RETURN	RETURN
nextword	CONTROL-B	CONTROL-U	CONTROL-U
previousfield	CONTROL-P	CONTROL-P	CONTROL-P
previousword	CONTROL-R	CONTROL-R	CONTROL-R
printscreen	(no default)	CONTROL-G	PF8
redraw	CONTROL-W	CONTROL-W	CONTROL-W
rightchar	CONTROL-L	right_arrow	right_arrow
rubout	DEL	DEL	DEL
scrolldown	CONTROL-G	PF8	PREV SCR
scrollleft	CONTROL-O	CONTROL-L	CONTROL-L
scrollright	CONTROL-U	CONTROL-H	CONTROL-H
scrollup	CONTROL-F	PF12	NEXT SCR
shell	no default	no default	CONTROL-B
upline	CONTROL-K	up_arrow	up_arrow 🛚

Menu Items

You can also map a function or control key (or arrow key in UNIX or VMS) to any of the items appearing on a menu line. This mapping occurs by position within the menu line.

The syntax for specifying a menu item is:

```
menuitemN = internal_key_name (key _label)
```

The N indicates the position of the menu item in the line and is in the range 1 to 25. Alternatively, you can also designate menuitemN as menuN in a mapping statement.

For example, the following statement maps the second item on the menu line to function key 3:

Windows

UNIX

VMS

```
menuitem2 = F3 M
menuitem2 = pf3 M
```

This statement causes F3 (Windows) or PF3 (UNIX or VMS) to perform the operation indicated by the second menu item. As the end user moves to a new frame and the menu changes, F3 or PF3 continues to correspond to the item in the second position on the new menu line.

By default, the menu line or Help Keys operation automatically displays the current mappings between the menu items and their associated function and control keys (and arrow keys in UNIX or VMS). It uses either the label provided in the mapping file, or a default label if none has been specified in the mapping file.

For example, assuming such mappings have been specified, a menu can appear like this:

```
Help(PF2) Add(PF3) Editor(control-E) End(PF4)

or
Help(F1) Add(F3) Editor(Ctrl-e) End(F4)
```

The button bar menu does not display associated function or control keys. Use the Help Keys operation to see these key mappings.

In this example, pressing PF2 or F1 is equivalent to moving to the menu line and typing Help. Similarly, PF3 or F3 substitutes for Add; Ctrl-E substitutes for Editor; and PF4 or F4 substitutes for End.

The text in parentheses in the mapping statement and on the menu line shows the corresponding function or arrow or control key and is known as a *label*. The label is specified in the mapping file. For more information, see <u>Mapping File Syntax</u>. An application can specify that the entire *menu map*, as the collective set of labels is known, be turned off so that no labels appear. For example, if the menu map for the preceding example were turned off, the menu line appears like this:

Help Add Editor End

However, the function and control keys still retain their correspondence with the menu items, even though that correspondence is no longer displayed.

For more information on how to turn off the menu map, see the *Forms-based Application Development Tools User Guide*. The relevant statements are set_forms in 4GL and set_frs in the embedded query languages.

FRS Keys

FRS keys enable you to map function and control keys (including arrow keys) directly to a program operation. While a function, control, or arrow key can always map to a menu item operation by *position*, you can map the key directly to the operation itself.

For instance, you might not want every operation to appear as a menu item, particularly if the operation is available across all the frames in an application. By requiring that certain repeated operations be invoked only through function or control or arrow keys, you can shorten long menu lines and use the menu primarily for operations that are unique to each frame.

Because not all keyboards have the same set of function keys, it makes little sense to assign an operation directly to a particular key inside an application. Instead, you equate operations with logical FRS keys. The FRS keys can then be mapped to function, control, or arrow keys at any of the four mapping levels.

FRS keys invoke operations only when specified in the application. A mapping file, by itself, merely assigns the FRS key to a function or control or arrow key; it cannot define the meaning of the FRS key. A FRS key must be equated with an operation when you write the application. For instructions on how to do this, see the *Using Forms-based Application Development Tools User Guide*. The Ingres forms-based tools also use FRS keys extensively. For more information, see Predefined FRS Keys.

You can define the same operation for both a menu item and a FRS key. The end user can then activate the operation either with the key that is mapped to the menu item's position or with the key that is mapped to the FRS key. This means the user is always be able to invoke the menu item with the same function key, even if the item's position on the menu line changes from frame to frame. Whenever an operation has been associated with both a menu item and an FRS key, the label for the menu item indicates the function or control or arrow key that maps to the corresponding FRS key, *not* the function or control or arrow key that maps to the item's position on the line.

Mapping a FRS Key

For the end user to invoke an operation through an FRS key, two conditions must be met:

- The application program must provide the operation code and specify that it be invoked or activated by a FRS key.
- The FRS key must be mapped to a physical key on the user's keyboard.

Mapping the FRS key to a function or control key is handled identically to mapping a menu item or FRS command. If an FRS key defined in an application is *not* mapped to a function or control or arrow key, the end user has no way of accessing that FRS key's operation, unless the operation itself has also been defined for a menu item.

An FRS key is designated by the keyword frskey, followed by an integer in the range 1 to 40. For example, the following statement maps FRS key 7 to function key 2:

frskey7 = f2

By pressing PF2 or F2, the user invokes the operation to which FRS key 7 has been defined, within the current frame.

Predefined FRS Keys

The Ingres forms-based tools consistently equate certain FRS keys with standard menu item operations. Because of this, the end user can always use the same function or control or arrow key to perform that operation, no matter what its position on the menu line. Because the end user does not need to refer to the menu item's label, these operations are usually located at the end of the menu line, allowing those operations that are unique to a particular frame to appear first. For example, if frskey1 is mapped to controlH, the end user can always get help by pressing Ctrl-h.

FRS key operations are predefined in the applications code for the Ingres forms-based tools as shown in the following table. The terminal level key-mapping files contain default key assignments for these FRS keys. For more information, see FRS Mapping File (for Windows environment) and Terminal-Type Level Mapping (for UNIX and VMS environments).

FRS Key	Menu Item	Meaning	
frskey1	Help	Accesses as help facility.	
frskey2	Quit	Exits the system.	
frskey3	End	Exits the frame, returning to previous frame.	
frskey4	Go/Next	Executes function.	

FRS Key	Menu Item	Meaning	
frskey5	Тор	Moves to top of table field.	
frskey6	Bottom	Moves to bottom of table field.	
frskey7	Find	Searches table field for specified string.	
frskey8	Save	Saves object in database.	
frskey9	Undo/Cancel	Undoes last action or cancels changes made in frame.	
frskey10	ListChoices	Lists the available choices for the selected field.	

An application developed with an embedded query language or 4GL cannot automatically have the same FRS key-menu item linkage. By using this table as a model for associating FRS keys with program operations, an application developer can help provide a consistent end-user interface for all custom applications that is also consistent with key usage in the Ingres forms-based tools.

Specifications written using the function key facility provided in earlier releases of Ingres continues to operate correctly. If desired, such specifications can be placed in a mapping file containing statements using the new function/control/arrow key mapping facility. In a future release, however, the function key facility is phased out; therefore, it is not documented here.

Mapping File Syntax

Mapping files are the main method for mapping function, control, and arrow keys to menu items, FRS commands, and FRS keys. Mapping files can exist at each level of mapping in your environment. For example, you can have an installation-wide mapping file, terminal-type mapping files for every terminal type in your organization, user mapping files for each user, and application mapping files for every Ingres application.

In Windows, you can have several applications mapping files in addition to the FRS mapping file.

The syntax for the mapping files is the same across all levels of mapping. A mapping file can consist of three components:

- Mapping statements
- Disabling statements
- Comments

Mapping statements designate the actual mappings. These are the most commonly used. The mapping statements can also designate labels for menu items, if you do not use the default labels.

Disabling statements disable the use of function or control keys (and arrow keys in UNIX and VMS).

Comments provide explanatory text.

The statements in a mapping file can appear in any order, except for the placement of disabling statements. For details, see <u>Disabling Statements</u>. Each statement must fit entirely on one line. Alphabetic characters within a mapping file can appear in either uppercase or lowercase, with no difference in meaning. Blank lines are ignored.

Mapping Statements

A mapping statement has the following syntax:

mapping_object = pfN|controlX|uparrow|downarrow|
leftarrow|rightarrow [(label)]

Parameter	Description	
mapping_object	A menu item, FRS command, or FRS key, designated through mapping.	
pf <i>N</i>	Designates a function key. N must be in the range 1 to 40. (Note that the maximum number of definable keys set in the termcap file for your terminal can be less than 40. You must raise this limit to set additional keys.)	
controlX	Designates a control key. X can be any single letter of the alphabet, or the designations del to indicate the Delete key as in controldel or esc to indicate the Escape key as in controlesc (if the Escape key is not reserved on your terminal). This guide designates control keys in user instructions as Control-X, where X is the key used in combination with the Control key.	
	On most keyboards, pressing Control-I is equivalent to pressing the Tab key, and pressing Control-M is equivalent to pressing the Enter key in Windows or the Return key in UNIX or VMS.	

Parameter	Description	
uparrow downarrow leftarrow rightarrow	Designates the up arrow, down arrow, left arrow, and right arrow keys.	
label	Designates any alphanumeric string. It appears in place of the default label for a menu item. It also appears in the Keys operation of the Help facility.	

A single mapping object cannot be mapped to be invoked by pressing either two different function, control, or arrow keys on the same screen. Each function or control key (and each arrow key in UNIX or VMS) can correspond to only a single mapping object at a time. If you map one mapping object to more than one physical key, or multiple mapping objects to the same key, one mapping overrides the others.

If the conflicting mappings occur within the same mapping file, only the first mapping within the file is considered to be valid. If the conflict occurs between different mapping files, the key mapping in the file of higher precedence overrides the other mappings. For a discussion of precedence in key mapping, see Key Mapping Overview (PC Environment) or Key Mapping Overview (UNIX and VMS Environments).

The appearance of an exception to this rule occurs when both of the following conditions exist:

- A menu item is mapped to a function or control key (or arrow key in UNIX or VMS) by the menu item's position
- A FRS key that has the same function as the menu item is mapped to a different function or control key (or arrow key in UNIX or VMS)

This only appears to be an exception, because the two mapping objects (the menu item and the FRS key) perform the same function although they are actually separate FRS objects that are mapped to two different function, control, or arrow keys.

The following examples illustrate mapping statements:

Windows

```
frskey8 = pf16 (Sh+F6)
menuitem1 = pf13 (Sh+F3)
menuitem2 = pf3 (F3)
menuitem3 = controlE (^E)
previousfield = controlP (Sh+Tab)
nextfield = controll (Tab)
menuitem4 = pf9 (F9)
rubout = controlDEL
```

In this example, Sh+F6 on your PC keyboard maps to the operation associated with frskey8, Sh+F3 activates the first item on the menu line, F3 activates the second, Ctrl+E activates the third menu item, Sh+Tab moves the cursor to the previous field on the form, and Delete deletes the character immediately to the left of the cursor. Any previous mappings that do not conflict with these statements remain in effect. (When mapping *menu items*, the action to be taken after the key is pressed is determined by the application and can differ between applications.)

Notice the effect of including an explicit label in a mapping statement. Assume a frame's menu includes the following operations:

```
Help Add Editor End
```

Assume, also, that the frame containing these menu items also specifies that the Help operation be invoked either by selecting the Help menu item (in this case, menuitem1) or by pressing the key mapped to frskey8. The preceding mapping file example, with its labels, would result in the following key associations:

```
Help(Sh-F6) Add(F3) Editor(^E) End(F9)
```

Note the case of the Help menu item, which the application also allows to be invoked by frskey8. As shown in the mapping file example, two different keys could be used to invoke this item—Sh+F3 (the key associated with the first menu item) and Sh+F6 (the key associated with frskey8). In a case like this, the label for the FRS key always takes precedence over the label for the menu item for key assignments displayed on the menu line or in the Help Keys operation. All other labels in the example are those associated with the menu item's position on the menu line.

```
frskey8 = pf16 (0)
menuitem1 = pf13 (1)
menuitem2 = pf3 (PF3)
menuitem3 = controlE (^E)
previousfield = controlP
nextfield = rightarrow
menuitem4 = pf9 (4)
rubout = controlDEL
```

In this example, PF16 (the 0 on a VT100 keypad) maps to the operation associated with frskey8, PF13 (the 1 on a VT100 keypad) activates the first item on the menu line, PF3 activates the second menu item, Control-E activates the third menu item, Control-P moves the cursor to the previous field on the form, Right Arrow moves the cursor to the next field, and Delete deletes the character immediately to the left of the cursor. Any previous mappings that do not conflict with these statements remain in effect. (When mapping *menu items*, the action to be taken after the key is pressed is determined by the application and can differ between applications.)

UNIX

Notice the effect that including an explicit label has on the appearance of a menu line. Assume a frame's menu includes the following operations:

```
Help Add Editor End
```

Assume, also, that the frame containing these menu items also specifies that the Help operation be invoked either by selecting the Help menu item or by pressing the key mapped to frskey8. The previous mapping file example, with its labels, would cause the menu to appear as follows:

```
Help(0) Add(PF3) Editor(^E) End(4)
```

Note the case of the Help menu item, which the application also allows to be invoked by frskey8. Two different labels from the map file could be used for this item—1 (the label for the first menu item), or 0 (the label for frskey8). In a case like this, the label for the FRS key always takes precedence over the label for the menu item. All other labels on the menu are those associated with the menu item's position in the menu line.

Disabling Statements

Turn off any of the function or control keys (or arrow keys in UNIX or VMS) by using one of the following methods:

- Replace the original mapping statement with a disabling statement in the same mapping file
- Comment out the original mapping statement and place a disabling statement in the same mapping file
- Place a disabling statement in a key map file of higher precedence than the original mapping statement

If you do not want to edit or comment out the original mapping statement, leave the original mapping statement as is and place the disabling statement in a mapping file of higher precedence. For example, to disable a key mapped to an object in an installation-level or terminal-type mapping file, put a disabling statement in a user or application-level mapping file. To disable a key mapped to an object in a user-level mapping file, put a disabling statement in an application-level mapping file.

Once disabled, a key remains disabled until used in a mapping statement within a mapping file of higher precedence. For a discussion of precedence in key mapping, see Key Mapping Overview (PC Environment) or Key Mapping Overview (UNIX and VMS Environments).

A disabling statement has the following syntax:

pfN|controlX|uparrow|downarrow|rightarrow|leftarrow = off

Windows

The following statements disable Control-A and PF7 when placed in a mapping file or position of higher precedence than any assignment statement for these keys:

```
controlA = off
pf7 = off
```

UNIX

The following statements disable Control-A, PF7, and the Right Arrow key when placed in a mapping file or position of higher precedence than any assignment statement for these keys:

```
controlA = off
pf7 = off
rightarrow = off 

3
```

While these statements are in effect, using these disabled keys produces a beep from the terminal.

To disable a FRS command in a UNIX or VMS environment, map the FRS command to a control or function key (or to an arrow key), and then disable that key.

Comments

Comments are delimited by /* and */. They can appear anywhere, including on the same line as a statement. The whole comment must appear within a single line, as shown:

```
/* This is a comment */
controlA = off /*this turns Control-A off*/
```

Mapping File Errors

When the FRS starts up, the mapping files for the various levels of mapping are merged and conflicts between files are resolved based on a specific precedence. When the FRS detects errors in a mapping file, you can find detailed error messages in the ingkey.err file in the user's current directory. After exiting the application, the user can look at the error file to determine the nature of the errors.

Troubleshooting (PC Environment)

Windows

This section describes some of the problems you can encounter when defining function and control keys, and provides general hints about how to solve them. Note, however, these are only general guidelines; this section is by no means comprehensive.

Restrictions and Limitations

When defining function and control keys, beware of the following restrictions and limitations.

- The FRS has the following internal limitations: 40 program function (pf) keys, 40 FRS keys, and 25 menu items.
- The following control keys are reserved by the operating system for its own use and must not be mapped to any other operations: Ctrl+C, Ctrl+Q, Ctrl+S, and Ctrl+P.

Although Ctrl+P is trapped by the operating system before it reaches FRS, you can assign FRS objects to its internal designation, controlP, because controlP is mapped to the Sh+Tab key combination in the termcap file.

- FRS commands cannot be mapped to an FRS key. This is syntactically illegal because FRS commands and FRS keys both appear on the left side of the equals sign in the mapping statement.
- Positional menu item mapping cannot be turned off. You can see this if you look at the mapping file, for example:

```
menuitem1 = pf13 (Sh-F3)
```

If you assign a FRS key to an activation block, that key's label appears on the menu line or in the Help Keys operation in place of the default key's label. The default key, however, still works.

```
"Go", key frskey5 =
begin
... [first menu item] end;
```

In the previous example, both Sh+F3 and whatever is mapped to frskey5 triggers the Go operation, even though you only see the frskey5's label on the menu or in the Help Keys display. To deactivate this, you must assign another FRS function to the F key now assigned to menuitem1:

```
frskey10 = pf13 (Sh-F3)
```

Normally, you must use an unused FRS key for this function.

Currently, map files are the only way to turn off a function or control key (for example, controlV = off). Keys cannot be turned off by the Ingres/4GL or embedded guery language set command.

Troubleshooting Checklist

1. Have you checked the contents of the map error files in the working directory (ingkey.err or app_ingkey.err)?

The error messages written to this file indicate map file problems. For example, if the same key is referenced twice, the warning error message is written to this file. If this file is empty, an error occurred before the map file was parsed, and an error message was sent to your screen.

For example, no forms statements can be executed prior to starting the FRS. If a set mapfile statement preceded ## forms or exec frs forms in the embedded query language program, the error message is written to the screen.

2. Have any of the key map file path names become invalid?

For example, if the file system was moved to a new device, the file pathnames referred to by INGRES_KEYS or set mapfile are now invalid or perhaps file permissions were changed and the FRS cannot open the map files.

3. Are lower-level key definitions showing through on the user's menu line?

This is the result of the key map merging by the FRS. This most often occurs when you forget to remap or turn off an intended key in the application map file or do not realize that INGRES_KEYS is also pointing to a map file.

Troubleshooting (UNIX and VMS Environments)



This section describes some of the problems you can encounter when defining function, control, and arrow keys, and provides general hints about how to solve them. Please note, however, these are only general guidelines; this section is by no means comprehensive.

Restrictions and Limitations

When defining function, control, and arrow keys, beware of the following restrictions and limitations:

- The FRS has the following internal limitations: 40 function keys (PFn or Fn), 40 FRS keys, and 25 menu items.
- The FRS imposes no restrictions on which function, control, or arrow keys can be mapped or remapped; however, certain control keys can be captured by the operating system before they reach the FRS. For example, the operating system reserves: Control-C, Control-O, Control-Q, Control-S, Control-T, Control-X, Control-Y.
- FRS commands cannot be mapped to a FRS key. This is syntactically illegal because FRS commands and FRS keys both appear on the left side of the equals sign in the mapping statement.
- TERM_INGRES cannot be reset dynamically by the application once the Forms System has been initialized.

Positional menu item mapping cannot be turned off. In the vt100i termcap description, the application key pad is assigned by default to positional menu items. 1 on the key pad is assigned to the first menu item. You can see this if you look at the mapping file, for example:

```
menuitem1 = pf13
```

If you assign a FRS key to an activation block, that key's label appears on the menu line in place of the default key's label. The default key, however, still works.

```
"Go", key frskey5 =
begin
... [first menu item]
end;
```

In the above example, both 1 and whatever is mapped to frskey5 triggers the Go operation, even though you only see the frskey5's label. To deactivate this, you must assign another FRS function to the PF key now assigned to menuitem1:

```
frskey10 = pf13
```

Normally, you must use an unused FRS key for this function.

- Currently, map files are the only way to turn off a function, control, or arrow key (for example, controlV = off). Keys cannot be turned off by the 4GL or embedded query language set command.
- Keyboard review for the DEC VT series:

TERM_INGRES	Top Row Keys	Alternate Keypad	Menu Key
vt100	disabled	disabled	Escape
vt100k	disabled	disabled	PF1
vt100nk	disabled	numerics	PF1
vt100i	disabled	Functions (PFn)	PF1
vt200i	Functions (Fn)	numerics	PF1

- On a VT220, F1 through F6 are reserved by the terminal. These cannot be mapped in map files.
- Escape is considered reserved for vt100, vt220, and all other terminals that use Escape sequences to define function keys.

Troubleshooting Checklist

1. Have you checked the contents of the map error files in the working directory (ingkey.err or app_ingkey.err)?

The error messages written to this file indicate map file problems. For example, if the same key is referenced twice, the warning error message is written to this file. If this file is empty, an error occurred before the map file was parsed, and an error message was sent to the terminal screen.

For example, no forms statements can be executed prior to starting the FRS. If a set mapfile statement preceded ## forms or exec frs forms in the embedded query language program, the error message is written to the terminal.

2. Are the terminal's physical setup or emulation characteristics compatible with the current TERM_INGRES and key map definitions?

For example if you are using a terminal, a problem occurs if a VT220 terminal is setup as a VT220 but TERM_INGRES is set to vt100i whose map file references PF keys.

3. Is the user's TERM_INGRES terminal type compatible with the active key definitions?

If not, mapping can seem to be broken when an OpenIngres tool or application starts up; for example, if TERM_INGRES is set to vt100nk but INGRES_KEYS points to vt200.map.

4. Is the INGRES_KEYS environment variable/logical set unintentionally?

This often happens when applications are moved to a new machine where INGRES_KEYS is defined, unlike the previous environment.

5. Have any of the key map file path names become invalid?

For example, if the file system was moved to a new device, the file pathnames referred to by INGRES_KEYS or set mapfile are now invalid or perhaps file permissions were changed and the FRS cannot open the map files.

6. Are lower-level key definitions showing through on the user's menu line?

This is the result of the key map merging by the FRS. This most often occurs when you forget to remap or turn off an intended key in the application map file or do not realize that INGRES_KEYS is also pointing to a map file.

Appendix C: Writing Termcap Descriptions

For various reasons, you must modify your termcap file. If you are using Ingres in a UNIX or VMS environment, and your terminal is not defined in the standard termcap file, you must provide information about the terminal's characteristics to use the forms system.


Whatever your environment, you can modify the termcap file to optionally define some advanced features of your terminal that can make basic functions easier to use.

This appendix describes how to:

- Write new termcap descriptions
- Add entries to an existing termcap description to take advantage of your terminal's additional capabilities

Modifying the Termcap File

The following read-only termcap file, which contains information about your terminal's characteristics, is supplied with Ingres:



The termcap file is based closely on the standard UNIX termcap file, except that it contains extra commands that allow the terminal to work with the forms system. A correctly written termcap description allows the forms programs to work properly, although it does not support all of the advanced features that the terminal provides, such as certain video attributes.

By following the guidelines in this appendix, you can:

 Edit an existing termcap description to define your terminal's advanced features to Ingres **Windows**

Write a new termcap description for a terminal not currently described in the termcap file

You can use terminals that are in the currently supported termcap file for UNIX and VMS environments (listed in an appendix in this guide) without having to do any of the special programming described here.

In a PC environment, the termcap file contains nine primary records, as described in the following table:

Record	Output	
pccolor	Color monitor	
pcwin	Microsoft Windows colors	
pcfont	Color monitor; similar to pccolor, but with multiple fonts	
pcfonts	Color monitor; same as pcfont, but with different fonts	
pcgaudy	Color monitor; similar to pccolor, but with gaudier colors	
pc43	Color monitor with 43-line windows; same as pcgaudy, but for 43-line windows	
pcmono	Monochrome monitor	
pcansic	Not for use with Microsoft Windows	
pcansim	Not for use with Microsoft Windows	

Each record in the PC termcap file contains a number of command strings that define terminal behavior. The only modifications you make to these records are to define some of the advanced features of your PC or to define the size of your monitor.

Setting the II_TERMCAP_FILE Variable

Whether editing an existing termcap description or writing a new one, you must edit a copy of the termcap file that is not currently in use. You can set the II TERMCAP FILE environment variable/logical to point to a working copy of the termcap file. This allows you to edit a new version of the termcap file in any directory that you want, without interfering with other users or the original distribution copy of the termcap file.

Use the command appropriate to your system to tell Ingres to use an alternate termcap file:

Windows

For the C shell:

UNIX

setenv II TERMCAP FILE = fullpathname/filename

set II TERMCAP FILE=fullpathname\filename 🔳

For the Bourne shell:

```
II TERMCAP FILE = fullpathname/filename
export II_TERMCAP_FILE \(^{\textbf{Z}}\)
```

VMS

```
define II_TERMCAP_FILE=file_specification 1
```

If this name is defined, any forms program starts up with that file instead of the standard distribution file.

Format of a Termcap Description

Each termcap entry can be up to 2 KB long, including comment lines.

Consider the following sample termcap description for a fictitious terminal called rti100:

```
R1|rti100|rti fictitious terminal:\
    :co#132:li#25:\
    :am:bs:\
    :is=\E[0m:cm=\E|%2;%2:
```

It has an abbreviated name R1 and a long name rti fictitious terminal. (To use this with the forms system, set the TERM_INGRES environment variable/logical to rti100.) The rti100 screen is 132 columns wide and 25 lines high. It has automatic margins (am) and uses Control-H for the backspace character (bs). The description contains an initialization string (is) and a cursor positioning string (cm).

As shown in this example, the first line of a termcap description is the list of names. All names must be separated by a vertical bar (1). There must be a colon (:) between the last name and the first capability.

If the termcap description is more than one line (as it is for clarity), then each line except the last must end with a backslash (\setminus) to signify continuation. Capabilities, which can be presented in any order, must be separated by colons (:). The last line must end with a colon (:) to signify that it is the end of the description. You can place tabs at the beginning of lines for readability.

Special Characters

The following table describes special symbols used in the termcap description:

Symbol	Function
:	Separates capabilities.
	Separates names.
\	Continues to next line (when at the end of line).

Symbol	Function		
\E	Is the Escape character.		
100	Pauses for 100 milliseconds (when before a command).		
#	Indicates that capability is a number that immediately follows.		
=	Sets capability to a string that follows		
^X	Is Control-X for any X; thus, ^g is Control-G, h is Control-H, etc.		
\n	Is the Newline character.		
\r	Is the Return character.		
\t	Is the Tab.		
\b	Is the Backspace.		
\f	Produces a Formfeed.		
\072	Is a colon (072 is the octal value for :). In general, any character can be specified as a three-digit octal value of the ASCII character by preceding it with a backslash.		
@	When placed after a command, it means do <i>not</i> apply this command. It is used in descriptions that have the tc command. For more information, see the table in <u>Eleven Basic Commands</u> .		

Names

Names have a special format that you must follow. The first name must be two letters long. The second name is the common name to which you must set TERM_INGRES. The last name can be a concise description of the terminal's brand and model number. The last name can contain blanks, though the other names can not have blanks.

All names must be separated by a vertical bar (|). Additional names can be placed between the second name and the last name. The additional names can be used as alternative names for TERM_INGRES.

Note: Names must always be checked for uniqueness. You must check through the termcap file before writing a new description to make sure that the names you want to use have not already been selected. A duplicated name is not recognized; only the first one is used.

Capabilities

Capabilities are designated by commands, which must be separated by colons. All commands are two letters long. String and numeric commands are followed by additional information that is read by the forms system. The three types of commands are:

- String
- Numeric
- Boolean

Strings contain sequences of characters. The command must be followed by an equal sign. For example, up=\EA indicates that the command up (which stands for the sequence to move the cursor up) is set to the sequence Escape-Α.

Some string commands can be preceded by a time delay, which is referred to as padding. Padding may be required by older, slower terminals (such as the HDS AVT), which require a delay to execute some screen commands, such as clearing the screen. Padding ensures that the terminal has time to execute those commands without losing characters. Modern terminals and terminal emulators will almost never require padding.

The two types of padding are nonproportional (or straight) padding, and proportional padding (to the number of lines affected). To specify straight padding, put the needed time of delay (in milliseconds) before the command. To specify proportional padding, place an asterisk (*) after the amount of time. For example, on the concept 100 terminal, the ta command (tab character) takes a straight time delay of 8 milliseconds, and the cd command (clear display) takes a proportional delay of 16 milliseconds. The termcap entries look like this:

Straight padding:

ta=8\t

Proportional padding:

cd=16*\EarC

Numeric commands are followed by a number sign (#). For example, co#80 indicates that there are 80 columns on the screen. (co is the command which specifies the number of columns on the screen.)

Boolean commands signify the existence of a capability by their presence. They are not followed by any sequence or other symbols.

Writing New Termcap Descriptions

We recommend that you start by reading the terminal manufacturer's technical guide to find the information for the 11 basic capabilities described in <u>Eleven Basic Commands</u> in this chapter. You must also have the terminal in front of you so that you can check the operation of the terminal as you are working on the termcap description. When you have included the 11 basic capabilities in the description, try the terminal to see if it works. Once you get it working, you can try adding additional features listed under Commands for Advanced Features.

Note: Users not familiar with programming or lacking general knowledge about terminals can find creating new terminal descriptions difficult. Terminal programmer's guides can be difficult to understand. Ask for help from an experienced programmer to create new termcap entries. Our technical support personnel can give only general guidance on creating termcap descriptions, because they cannot have access to the terminal for checking out your problems.

If you have problems, first check to make sure that you entered the sequences from the guide correctly and that the format of the termcap description is correct. If it still does not work, check to see if there are some additional capabilities that need to be added to make it work. Also, certain terminals require special initialization commands. Check the technical guide to see which additional sequences you must add to the initialization string.

One way of preparing termcap descriptions is to examine the termcap entries for similar terminals. If you are trying to write a description for a terminal that is similar to one in the termcap file, you can use the tc command to indicate that all attributes for the new terminal are to be taken from the description of a terminal already in the termcap file. Then, you only need to specify the few differences.

Alternatively, you can manually copy the capabilities from a similar terminal and see if it works. Most terminals conform to a system of specifying escape sequences called the ANSI standard. Thus, if you have an ANSI standard terminal, you must be able to get about 90 percent of the capabilities by copying them from another ANSI terminal. The VT100 is an example of an ANSI terminal that has capabilities similar to many different terminals. For this reason, this document contains numerous references to the VT100 sequences in its examples.

Finally, if your terminal has a VT100 emulation mode, you can save time by jumping to VT100 emulation mode and using the VT100 termcap description. In most cases, it is necessary to make a termcap description. In other cases, the terminal works with a termcap description that is identical to the VT100 except that it contains the VT100 emulation sequence in its initialization string. If your terminal has VT100 emulation mode, we recommend that you try it, as a VT100 supports the most advanced features of the forms system.

Eleven Basic Commands

There are 11 commands that all terminals must have to work properly. Termcap descriptions that have only these 11 basic descriptions usually work, although they lack extra features such as function keys and video attributes. These 11 descriptions form the core of the termcap description.

Windows

Although the Ingres forms-based tools are generally run on an 80 x 25 monitor, Ingres runs on a monitor larger than 80 x 25 (to a maximum of 200 x 100). Applications can be created to use the entire larger-size screen. To enable use of a larger screen, change the co and li entries in the termcap file to the correct values for your screen.

Command	Description	
со	The number of columns on the screen. Without this command there is no way to know how wide to make a form. This command is numeric and must always be followed by a number.	
	VT100 Example: co#80	
li	The number of rows down the screen. This command is numeric and must always be followed by a number.	
	VT100 Example: Ii#24	
bs	This terminal can backspace using Control-H. This is a Boolean command. Include it if your terminal can backspace using Control-H.	
bc	Sequence to use if the terminal does not use Control-H. You cannot use bc and bs together.	
cd	Clears to the end of the display. Sequences to clear everything from the cursor down.	
	VT100 Example: cd=\E[J	
ce	Clears to the end of the line. Sequences to clear everything from the cursor to the end of the line. (Not used in Windows environment.)	
	VT100 Example: ce=\E[K	
cl	Clears the entire screen. (Not used in Windows environment.)	
	VT100 Example: cl=\E[;H\E[2J	
cm	Moves the cursor to an Ingres-specified location. For more information and examples of this command, see the discussion following this table.	

Command	Description		
nd	Nondestructive space. This string specifies the command for moving the cursor right one space without overwriting the contents of the screen at that point.		
	VT100 Example: nd=\E[C		
is	Terminal initialization string. This includes any sequences needed to set up the terminal prior to running a forms program. (Not used in Windows environment.)		
	VT100 Example:		
	is=\E\E[?3I\E[?4I\E[?7I\E[?8h		
	The example terminal initialization string given under the command is above does five things:		
	\E puts the terminal in keypad numeric mode.		
	\E[?3I puts terminal into 80-column mode.		
	\E[?4l puts terminal into jump mode.		
	\E[?7I turns wraparound off.		
	\E[?8h turns on autorepeat.		
	The command is not always needed. However, for most terminals it is necessary for tailoring the setup to your needs.		
tc	Entry of a similar terminal. It allows you to use all the capabilities listed for another terminal without rewriting them. This command is actually optional, but is so useful that it has been listed as one of the basic commands. This capability must always be the <i>last</i> capability in the description. This rule, which exists so that duplicated commands can be unambiguously defined, is the only exception to the general rule that commands can be presented in any order.		
	Example:		
	(tek4115): dk tk4115 tek-4115 tektronix4115:\:ld@:tc=vt100f:		
	In this example, the tek4115 is given all the commands from the vt100f description, except the 1d command to initialize the boxing characters. Proper use of this command can make writing termcap descriptions much easier.		

Cursor Motion Command

The cursor motion (cm) command sends the cursor motion string (called the cursor position string in some guides) to the terminal when the cursor is moved from one location to another. As such, the string must accept two parameters: an x-coordinate and an y-coordinate, whose values are obtained by counting the number of rows/spaces from the top-left corner of the screen. Because these values must be sent along with the string at run time, special place markers must be left in the string to tell the forms system where to place the x and y coordinates.

To implement this, find the cursor-addressing scheme described in the guide for your terminal. Then substitute the special place marker characters (described below) in the spot where numbers are expected. Also, be sure to include any special modifiers (described below) in the description if they are needed.

The following tables list place markers and cursor-addressing options (modifiers):

Place Marker	Description		
%2	Place marker for a decimal integer of two places.		
%3	Place marker for a decimal integer of three places.		
%.	Place marker for a binary value character.		
%+ N	Place marker for a binary value character, with the value of the character ${\it N}$ added to it.		
%%	Produces a single %.		
%r	Reverses the order of the coordinates. Normally the column marker is substituted into the first place marker. If your terminal cursor positioning string expects the row first, include a %r before the first place marker in the cursor motion sequence.		
%B	BCD (16*(x/10)) + (x mod 10) Parameter values are transformed according to this formula.		
%n	Perform an exclusive OR on the row and column values with the octal value 0140 before generating the string for cursor motion. (This is used only for the DM2500 terminal.)		
%D	Reverse coding (x-2*(x mod 16)) Parameter values are transformed according to this formula. (This is used only for Delta Data terminals.)		

Example 1: rti100, a Fictitious Terminal

The cursor motion string listed in the user's guide for the rti100 (a fictitious terminal) is ESC|x;y, where x and y are two-digit integers specifying the column and the row, respectively. The rti100 is an example of a terminal that uses a (0,0) origin, so x and y must be one less than the whole number that represents the position on the screen. Thus, to move the cursor to column 8 row 17 on the rti100, you would enter ESC|07;16. The termcap entry is:

cm=\E|%2;%2

The \E maps to ESC and %2 is the place marker that maps to a decimal integer of two places.

Example 2: vt100

The cursor motion string for the VT100 is ESC[x;yH], where x and y are two-digit integers specifying the column and row, respectively. The VT100, as opposed to Example 1 above, positions the cursor relative to a origin of (1,1). Thus, to move the cursor to column 8 row 17 on the VT100, enter ESC[08;17H]. The termcap entry is:

cm=\E[%i%2;%2H

The \E maps to ESC, %2 maps to a decimal integer of two places, and the %i signifies that the VT100 uses a (1,1) origin. The default setting for the cm string is for a (0,0) origin. If your terminal uses a (1,1), origin you must explicitly state that by placing a %i somewhere inside the cm string.

Example 3: Datamedia 3045

The cursor motion string for Datamedia 3045 is ESC Y y x; where y and x are characters whose binary values are offset by 20 hex. (For this terminal, the row must be given before the column.)

To move the cursor to the position (19,11) on this terminal, you must include the sequence ESCY2*. The ESCY is the first part of the sequence. The 2 is the ASCII character with hexadecimal value 32, which is the same as 12 hex plus the 20 hex offset. Note that 12 hex corresponds to column 19 on the screen. The * is the ASCII character with a hexadecimal value of 2A, which equals 0A hex plus the 20 hex offset. Again, 0A hex corresponds to row 11 on the screen.

The cm string for this terminal is:

cm=\EY%r%+%+

The \E maps to ESC, %r is a modifier that tells the forms system that the row and column parameters are reversed, and %+ is the place marker for a character offset by a blank (which has the ASCII value of 20 hex).

Example 4: Delta Data 5000

The cursor motion string for the delta data 5000 is Control-Oxy, where x and y are characters whose binary values must be offset by 3A hex, and converted according to the reverse coding formula:

 $(x-2*(x \mod 16))$

The cm string for this terminal is:

cm=^0%D%+9%D%+9

The ^O stands for Control-O, %D indicates that the parameters must be transformed according to the reverse coding formula, and %+9 is the place marker for a character offset by 3A hex (ASCII character 9).

Terminal	Entry Listed in Guide	Example Usage on Terminal Mode	Example of the Termcap Description
rti100	ESC x;y	ESC 02;07	cm=\E %2;%2
vt100	ESC[x;yH	ESC[03;08H	cm=5\E[%i%2;%2H
dm3045	ESCYyx	ESCY2*	cm=\EY%r%+%+
delta	Control-Oxy	Control-ORS	cm=^0%D%+9%
			D%+9

Commands for Advanced Features (PC Environment)



The Ingres termcap commands included in this section are used to define some of your PC's advanced features to Ingres. These are features that make your PC easier to use and more attractive, but they are not essential for the basic functions of Ingres.

The commands listed here include:

- Video attributes such as inverse video and blinking
- Color attributes

Commands Used to Program Video Attributes

The four basic modes are: underscore, blinking, reverse video, and high intensity (bold).

All the commands below are combinations of the four basic modes:

Command	Description	Windows Display Code
rv	Turns on reverse video.	rv=71
bl	Turns on blinking mode.	b1=9F
bo	Turns on high intensity (bold) mode.	bo=1E
us	Turns on underscore mode.	us=1F
za	Turns on reverse video, blinking, high intensity, and underscore modes.	za=F0
zb	Turns on high intensity and underscore modes.	zb=1E
ZC	Turns on high intensity and blinking modes.	zc=9E
zd	Turns on high intensity and reverse video modes.	zd=70
ze	Turns on underscore and blinking modes.	ze=9F
zf	Turns on underscore and reverse video modes.	zf=71
zg	Turns on blinking and reverse video modes.	zg=F1
zh	Turns on high intensity, blinking, and underscore modes.	zh=9E
zi	Turns on blinking, underscore, and reverse video modes.	zi=F1
zj	Turns on high intensity, blinking, and reverse video modes.	zj=F0
zk	Turns on high intensity, underscore, and reverse video modes.	zk=70

Commands Used for Color

The following commands are used to define color in monitors that support color. They are mapped to the color codes, from 0 to 7, as defined for the VIFRED form.

The ya command specifies the default colors for background and foreground objects. The other color-related commands indicate colors for fields as specified in the VIFRED attributes form. The following is an example of the format in which you specify the background and foreground colors: :ya=1F

In this example, the 1 specifies a background color of blue and the F specifies a foreground color of white.

Alternatively, you can express these color specifications in the embedded query language with the set_frs statement and in 4GL with the set_forms statement. For more information, see your query language reference guide or the Forms-based Application Development Tools User Guide.

For each color specification, you can also specify a default font. For more information, see Specifying Fonts.

All the commands are strings and can have optional padding. The commands are described in the following table:

Command	Description	Windows Display Code
ya	Default color (0)	ya=1F
yb	Alternate color #1	yb=1F
ус	Alternate color #2	yc=1A
yd	Alternate color #3	yd=1E
ye	Alternate color #4	ye=30
yf	Alternate color #5	
уд	Alternate color #6	yg=0F:\
yh	Alternate color #7	yh=2F:\

The following chart shows codes for color displays:

Codes for Background	Codes for Foreground
0 = black	O = black
1 = blue	1 = blue
2 = green	2 = green
3 = cyan	3 = cyan
4 = red	4 = red
5 = magenta	5 = magenta

Codes for Background	Codes for Foreground
6 = yellow	6 = brown
7 = white	7 = light grey
8 = blinking black	8 = dark grey
9 = blinking blue	9 = light blue
A = blinking green	A = light green
B = blinking cyan	B = light cyan
C = blinking red	C = light red
D = blinking magenta	D = light magenta
E = blinking yellow	E = yellow
F = blinking white	F = white

For all systems, the ya entry is used for the normal attribute (that is, no underscore, reverse video, high intensity, or blinking).

For color systems, the us, rv, bo, bl and the za through zk entries are used only with color 0 (entry ya). These attributes work for other colors as you would expect if the flags are set for a field. For example, white on red becomes red on white if reverse video is set, and light green on black becomes green on black if change intensity is set.

Some of the termcap color commands that are used by Ingres forms are shown in the following table:

Command	Forms and Menus
ya	Background for Ingres forms and the ring menu line when the menu is active
yb	Tablefields in Ingres forms
yc	Some simple fields in certain Ingres forms
yd	Some simple fields in certain Ingres forms
us	Some simple fields in certain Ingres forms
bo	Some simple fields in certain Ingres forms

Specifying Fonts

For each of the ya through yh termcap strings, Ingres allows you to set both a color and a font. Wherever the specified color is used, the specified font is used as well. You can specify a different font for each entry if you want. The following fixed fonts are available:

- OEM (Windows OEM_FIXED_FONT)
- ANSI (Windows ANSI_FIXED_FONT)
- SYSTEM (Windows SYSTEM_FIXED_FONT)

You must use one of these three fixed fonts for both the ya and the yb entry. For the other entries, you can use any fixed or proportional font loaded in your Windows system. However, for data entry fields, it is best to use one of the three fixed fonts provided, because the cursor placement is based on these fixed fonts.

Note: Underlining in stock fixed fonts (OEM, ANSI, and SYSTEM) is not possible on a PC monitor, due to a Windows font limitation. On form fields for which the Underline attribute has been set, leading and trailing blanks display underscore characters to indicate underlining for these fonts. Text appears with full underlining, however, in fields with fonts that support it.

Specify fonts by adding a comma after the background/ foreground color information in the ya through yh entries, followed by the font name. OEM is the default if you do not specify a font. You can specify the point size for the font by placing a comma after the font name, followed by the point size. Following is a sample from the termcap file:

```
:ya=1F,ANSI:\
:yb=1F,0EM:\
:yc=1F,MS Serif,14:\
:yd=1F,Times New Roman:\
:ye=1F,Courier:\
:yf=1F,Courier new:\
:vg=1F,MS Sans Serif:\
:yh=1F,SYSTEM,15:\
```

The default point size for a proportional font is the largest size that fits on a line, where the line size is determined by the font for the ya entry. The point size specified for ya determines the spacing for all lines on a form. You must increase the line size if you are using a taller font for an entry other than ya.

To do so, use a large enough point size for ya, as in the following example:

```
:ya=1F,SYSTEM,16:\
:yb=1F,0EM:\
:yc=1F,MS Serif,16:\
:yd=1F,Times New Roman:\
:ye=2F,Courier:\
:yf=4F,Courier new:\
:yg=0B,MS Sans Serif:\
:yh=1F,Courier,18:\
```

The default pixel and point sizes for the fixed fonts on a SVGA 800 x 600, 20-inch monitor are shown in the following table:

Font	Pixels	Points
OEM	12	9
ANSI	13	10
SYSTEM	15	11 📱

Commands for Advanced Features (UNIX and VMS Environment)



The termcap commands included in this section are used to define some of the advanced features of your terminal. These are features that make the terminal look good and make it easier to use but are not essential for the basic functions.

The advanced features commands include:

- Video attributes such as inverse video and blinking
- Color attributes
- Boxing characters
- Commands to set up function and arrow keys
- Command to specify a default FRS key mapping file
- Commands to optimize cursor movement

Commands Used to Program Video Attributes

The four basic modes are: underscore, blinking, reverse video, and high intensity. All the commands in the following table are combinations of the four basic modes:

Command	Description	VT100 Example
rv	Turns on reverse video.	rv=1\E[7m
bl	Turns on blinking mode.	bl=1\E[5m
bo	Turns on high intensity mode.	bo=1\E[1m
us	Turns on underscore mode.	us=2\E[4m
ea	Turns off all special display characteristics.	ea=1\E[m
za	Turns on reverse video, blinking high intensity, and underscore modes.	za=1\E[1;4;5;7m
zb	Turns on high intensity and underscore modes.	zb=1\E[1;4m
ZC	Turns on high intensity and blinking modes.	zc=1\E[1;5m
zd	Turns on high intensity and reverse video modes.	zd=1\E[1;7m
ze	Turns on underscore and blinking modes.	ze=1\E[4;5m
zf	Turns on underscore and reverse video modes.	zf=1\E[4;7m
zg	Turns on blinking and reverse video modes.	zg=1\E[5;7m
zh	Turns on high intensity, blinking, and underscore modes.	zh=1\E[1;4;5m
zi	Turns on blinking, underscore, and reverse video modes.	zi=1\E[4;5;7m
zj	Turns on high intensity, blinking, and reverse video modes.	zj=1\E[1;5;7m
zk	Turns on high intensity, underscore, and reverse video modes.	zk=1\E[1;4;7m

Commands Needed for Boxing Characters

Not all terminals have special boxing characters. If your terminal does not have them, hyphens (-) and vertical bars (|) are used instead. Using boxing characters, however, greatly improves the appearance of forms using table fields.

Command	Description	VT100 Example
Id	Initializes terminal to draw solid lines.	ld=\E)0
ls	Interprets subsequent characters for drawing solid lines.	ls=\016
le	Interprets subsequent characters as regular characters.	le=\017
qa through qk	Boxing characters; see the next table.	

The table below describes the boxing characters qa through qk mentioned in the previous table:

Command	Description	VT100 Example
qa	Lower right corner of a box	qa=j
qb	Upper right corner of a box	qb=k
qc	Upper left corner of a box	qc=l
qd	Lower left corner of a box	qd=m
qe	Crossing lines	qe=n
qf	Horizontal line	qf=q
qg	Left T (stem points right)	qg=t
qh	Right T (stem points left)	qh=u
qi	Bottom T (like upside down T)	qi=v
qj	Top T (like a regular T)	qj=w
qk	Vertical line	qk=x

Commands Needed for Function Keys

The following table describes the commands the termcap files use to activate function keys:

Command	Description	
ke	Takes the terminal out of keypad transmit mode.	
ks	Puts the terminal in keypad transmit mode.	
kn	The number of function keys available; for example, this is specified as kn#18 on the VT100. You can have a maximum value of 40 for the number of function keys.	
ky	This terminal has cursor and function keys. This is a Boolean command. It must be present if you want to use function keys. Using it disables the ESC key and sets the first function key, PF1, to the Menu function.	
k0 through KD	Strings sent by function keys; see the next table for the specifics on each command.	

The following table describes the commands that you can set to send strings by using function keys. These commands allow the Forms Runtime to recognize when a function key is pressed. You must still to map the function key to a forms action in your FRS key mapping file. For example, the key mapping file would use "pf3" to reference function key 3, the k2 command.

Command	Function Key Number	VT100 Example
kO	function key 1	k0=\EOP
k1	function key 2	k1=\E0Q
k2	function key 3	k2=\EOR
k3	function key 4	k3=\EOS
k4	function key 5	k4=\E0w
k5	function key 6	k5=\E0x
k6	function key 7	k6=\E0y
k7	function key 8	k7=\EOm
k8	function key 9	k8=\E0t
k9	function key 10	k9=\E0u
kA	function key 11	kA=\E0v
kB	function key 12	kB=\E01

Command	Function Key Number	VT100 Example
kC	function key 13	kC=\E0q
kD	function key 14	kD=\EOr
kE	function key 15	kE=\E0s
kF	function key 16	kF=\E0p
kG	function key 17	kG=\EOn
kH	function key 18	kH=\EOM
kI	function key 19	none
kJ	function key 20	none
kK	function key 21	none
kL	function key 22	none
kM	function key 23	none
kN	function key 24	none
kO	function key 25	none
kP	function key 26	none
kQ	function key 27	none
kR	function key 28	none
kS	function key 29	none
kT	function key 30	none
kU	function key 31	none
kV	function key 32	none
kW	function key 33	none
kX	function key 34	none
kY	function key 35	none
kZ	function key 36	none
KA	function key 37	none
КВ	function key 38	none
KC	function key 39	none
KD	function key 40	none

Commands Needed for Arrow Keys

The arrow key commands are all strings:

Command	Description	VT100 Example
ku	Sent by terminal up arrow key	ku=\EOA
kd	Sent by terminal down arrow key	kd=\EOB
kr	Sent by terminal right arrow key	kr=\EOC
kl	Sent by terminal left arrow key	kl=\EOD

Commands Used for Color

You can use these commands to turn on color in terminals or monitors that support color. These are mapped to the color codes, from 0 to 7, as defined for the VIFRED form. Some terminals, such as the VT2410, are capable of only four colors.

The ya command specifies the default color for foreground objects, and the other commands indicate colors for fields as specified in the VIFRED attributes form. Alternatively, you can express these color specifications in the embedded query language with the set_frs statement and in 4GL with the set_forms statement. For more information, see your query language reference guide or the Forms-based Application Development Tools User Guide.

All the commands are strings and can have optional padding. The commands are described in the following table:

Command	Description	Envision Example
ya	Default foreground color (0)	2\Ea7
yb	Alternate foreground color #1	2\Ea1
ус	Alternate foreground color #2	2\Ea2
yd	Alternate foreground color #3	2\Ea3
ye	Alternate foreground color #4	2\Ea4
yf	Alternate foreground color #5	2\Ea5
уд	Alternate foreground color #6	2\Ea6
yh	Alternate foreground color #7	2\Ea7

E3|envisionc|envision230|this has the color definitions:\

Example: Envision :ya=2\Ea7:yb=2\Ea1:yc=2\Ea2:yd=2\Ea3:\

:ye=2\Ea4:\:yf=2\Ea5:yg=2\Ea6:\

:yh=2\Ea7:tc=vt100k:

Commands to Specify Display Width

The following commands define terminal display width:

Command	Description	VT100 Example
yn	Number specifying narrow width of terminal	yn#80
yo	Number specifying wide width of terminal	yo#132
ур	Narrow cm string	yp=\E[%i%2;%2H
yq	Wide cm string	yq=\E[%i%2;%3H
yr	String to switch to narrow width	yr=\E[?31
ys	String to switch to wide width	ys=\E[?3h

Command to Specify FRS Mapping File for Terminal

You can use the mf command to specify a default FRS key mapping file for a terminal. You must include the name of a file in the OpenIngres files directory (not the full directory specification or path name of the file). This file contains the default FRS key mapping for the terminal.

:mf=vt100i.map: Example: vt100i

Commands to Optimize Cursor Movement

These commands generally improve the way the forms system moves the cursor around the form. They are usually optional.

Command	Description	
am	This terminal has automatic margins. This Boolean command is important on forms that run to the edge of the screen.	
do	Down one line. Inclusion of this command helps the forms system move the cursor faster.	
sr	Scroll reverse. This command makes the form scroll backwards instead of jumping if you are moving up on a long form.	
cs	Change scrolling region. This command improves the appearance of the cursor movements when scrolling on a long form. The forms system still works if this is not defined, but it does not look as nice. This command is very similar in form to the cm command; however, the cs command's parameters are the upper and lower limits of scrolling instead of the position on the screen. Otherwise, all the place markers and modifiers are the same. If you use the cs command, you must also include the sr command.	

cs=5\E[%2;%2r 🍱 Example: vt100

Commands for Special Situations

The termcap commands in this section are seldom, even rarely, required for the forms system.

Commands from the UNIX Termcap File

Because the termcap file is based upon the UNIX release, some additional UNIX entries have been included in the termcap file, but are usually not needed by the forms system. The following table provides a list of these additional UNIX termcap entries:

Name	Туре	Description
bt	str	Back tab. Padding can be required on this command.
ho	str	Sequence to move the cursor to the home position. This command is used if and only if the terminal does not possess a cursor positioning string (cm).
II	str	Last line, first column (if no cm).
ms	bool	Safe to move while in standout and underline mode.
рс	str	Pad character (rather than null).
sf	str	Scroll forward. Padding can be required on this command.
ta	str	Tab, other than Control-I or with padding. Padding can be required on this command.
te	str	String to end programs that use cm.
ti	str	String to begin programs that use cm.
ve	str	Sequence to end open/visual mode.
VS	str	Sequence to start open/visual mode.
hz	str	Hazeltine; cannot print apostrophes.
nc	bool	No correctly working carriage return (DM2500, H2000).
xb	bool	Beehive (f1=ESC, f2=Control-C)
xn	bool	A newline is ignored after a wrap (Concept).
xr	bool	Return acts like ce \r \n (Delta Data).
XS	bool	Standout not erased by writing over it (HP 264?).
xt	bool	Tabs are destructive, magic so character (Teleray 1061).

Examples of Termcap Descriptions

This section includes several examples of termcap entries that have been tested. The examples illustrate the format of termcap entries and include commentary on each description. If you want to learn more about the termcap process, compare these descriptions with the guides for the particular terminals.

DEC VT100 (All-Inclusive)

This description contains all the features previously described. This example is longer than most termcap descriptions.

```
d7|vt100k|vt-100k|pt100k|vt100 with everything:\
   :co#80:li#24:cl=20\E[;H\E[2J:bs:cm=5\E[%i%2;%2H:\
   :nd=2\E[C:\
   :up=2\E[A:ce=3\E[K;cd=50\E[J:us=2\E[4m:ue=2\E[m:\]]
   :is=\E\E[?31\E[?41\E[?71\E[?8h:ks=\E[?1h\E=:\A]])
   :ke=\E[?11\E:ku=\EOA:kd=\EOB:kr=\EOC:kl=\EOD:\
   :ld=\E)0:\
   : qa=j:qb=k:qc=l:qd=m:qe=n:qf=q:qg=t:qh=u:qi=v: \\ \\
   :qj=w:qk=x:\
   :ls=\016:le=\017:\
   :cs=5\E[\%2;\%2r:bl=1\E[5m:be=1\E[m:\]
   :bo=1\E[1m:eb=1\E[m:rv=1\E[7m:re=1\E[m:\
   :za=1\E[1;4;5;7m:zb=1\E[1;4m:zc=1\E[1;5m:\
   :zd=1\E[1;7m:\
   :ze=1\E[4;5m:zf=1\E[4;7m:zg=1\E[5;7m:\
   :zh=1\E[1;4;5m:\
   :zi=1\E[4;5;7m:zj=1\E[1;5;7m:zk=1\E[1;4;7m:\
   :kh=\E[H:ky:k0=\EOP:k1=\EOQ:k2=\EOR:k3=\EOS:pt:\
   :sr=5\EM:\
   :k4=\E0w:k5=\E0x:k6=\E0y:k7=\E0m:\
   :k8=\E0t:k9=\E0u:kA=\E0v:\
   :kB=\E01:kC=\E0g:kD=\E0r:kE=\E0s:kF=\E0p:\
   :kG=\EOn:kH=\EOM:\
   :kn#18:mf=vt100k.map:
```

DEC VT100 (Simple)

Here is the VT100 using only basic features. This description lacks many of the niceties found in the longer description above, but it illustrates that minimal descriptions that provide basic functioning are relatively easy to write.

```
d8|vt100s|simple vt100 entry:\
    :co#80:li#24:cl=20\E[;H\E[2J:bs:\
    :cm=5\E[%i%2;%2H:nd=2\E[C:\
    :is=\E\E[?31\E[?41\E[?71\E[?8h:\
    :up=2\E[A:ce=3\E[K:cd=50\E[J:
```

Envision 230

This termcap description illustrates the use of the tc command. This description contains all the features of the VT100 except that it does not employ the VT100 initialization string. Also note the large number of names; this example covers three different varieties of Envision terminal. If you need to write descriptions for terminals similar to known terminals, this example is particularly pertinent.

```
E1|envision|envision230|envision220:\
    :is@:tc=vt100k:
```

Concept 100

This description was taken from the BSD UNIX termcap description. It is not programmed for Ingres function keys or boxing characters. The Concept 100 is an example of a terminal for which writing descriptions is particularly difficult. It has several nonstandard features. Note the use of the xn command, a command written specifically for terminals like the Concept 100.

```
c1|c100|concept100:\
    :is=\EU\Ef\E7\E5\E8\E1\ENH\EK\E\200\Eo&\200:\
    :al=3*\EarR:am:bs:cd=16*\arC:ce=16\EarS:\
    :cl=2*arL:\
    :cm=\Ea%+:%+:co#80:dc=16\EarA:dl=3*\EarB:\
    :ei=\E\200:\:eo:im=\EarP:in:ip=16*:li#24:mi:\
    :nd=\E=:se=\Ed\Ee:so=\ED\EE:ta=8\t:ul:\
    :up=\E;:\
    :vb=\Ek\EK:xn:
```

Datamedia 3045

This description, which was also taken from the BSD UNIX termcap description, contains the rather tricky cm string discussed in The Eleven Basic Commands section. This description has not been programmed to use Ingres function keys or boxing characters.

```
D4|3045|dm3045|datamedia 3045a:\
    :is=\EU\EV:\
    :am:bs:cd=2\EJ:ce=\EK:cl=2\EM:\
    :cm=\EY%r%+%+:co#80:\
    :dc=6\EB:dm=:ed=:ei=\EP:ho=\EH:ic=:\
    :im=\EP:ip=6:\
    :k0=\Ey\r:k1=\Ep\r:k2=\Eq\r:k3=\Er\r:\
    :k4=\Es\r:\
    :k5=\Et\r:k6=\Eu\r:k7=\Ev\r:k8=\Ew\r:\
    :k9=\Ex\r:\
    :kh=\EH:ku=\EA:kr=\EC:li#24:nd=\EC:\
    :pc=\177:pt:\
    :eo:ul:up=\EA:xn:
```

Appendix D: Data Types

This appendix describes data types and their equivalents.

Data Types in SQL, OpenSQL, and QUEL

The following table gives equivalents for SQL, OpenSQL, and QUEL data types:

SQL	OpenSQL	QUEL	Description	
c(n)	not used	c(<i>n</i>)	A fixed-length string of up to <i>n</i> printable ASCII characters, with nonprintable characters converted to blank; <i>n</i> represents the lesser of the maximum configured row size and 32,000.	
char(n)	char(<i>n)</i>	char(n)	A fixed-length string of up to <i>n</i> ASCII characters, including any nonprintable characters; <i>n</i> represents the lesser of the maximum configured row size and 32,000.	
varchar(n)	varchar(n)	varchar(<i>n)</i>	A variable-length string of up to <i>n</i> ASCII characters; <i>n</i> represents the lesser of the maximum configured row size and 32,000.	
text(n)	not used	text(n)	A string of up to <i>n</i> ASCII characters (excluding nonprintable characters); <i>n</i> represents the lesser of the maximum configured row size and 32,000.	
float4	not used	f4	4-byte floating point; for numbers including decimal fractions, from 0.29x10** -38 to 1.7x10**38 (7 digit precision).	

SQL	OpenSQL	QUEL	Description
float8	float	f8	8-byte floating point; for numbers including decimal fractions, from 0.29x10**-38 to 1.7x10**38 (16 digit precision).
decimal	decimal	not used	Exact numeric data type defined by its precision (total number of digits) and scale (number of digits to the right of the decimal point). Precision must be between 1 and 31. Scale can be 0 up to the maximum scale.
integer1	not used	i1	1-byte integer; for whole numbers ranging from -128 to +127.
integer2 or smallint	smallint	i2	2-byte integer; for whole numbers ranging from -32,768 to +32,767.
integer4 or integer	integer	i4	4-byte integer; for whole numbers ranging from -2,147,483,648 to +2,147,483,647.
money	not used	money	8 byte monetary data from -999999999999999999999999999999999999
date	not used	date	12 bytes; dates ranging from 1-jan-1582 to 31-dec-2382 for absolute dates and -800 years to 800 years for time intervals.

An SQL user-defined data type (UDT) is perceived and treated as a character string. User-defined data types are not supported in OpenSQL or QUEL.

Some forms utilities do not support the long varchar, byte, byte varying, and long byte data types. For more information, see the documentation for each specific product for details about long varchar, byte, byte varying, and long byte data types.

Appendix E: Calling Ingres Tools from Embedded SQL and OpenSQL

This appendix provides a listing of the parameters for each Ingres tool. Some of these parameters correspond to arguments passed to the particular tool, others to specific command line flags. For each call, the flags parameter can be used to pass the values of all flags, including those that do not have defined parameter names. Within the string containing the value for flags, each distinct flag must be separated by a blank space.

Call Statement

The embedded SQL and OpenSQL call statement enables your applications to call an Ingres tool (such as QBF) or the operating system. The syntax to call an Ingres tool is as follows:

```
exec sql call subsystem (database = dbname {, parameter = value});
```

To call the operating system, the syntax is as follows:

```
exec sql call system (command = command string);
```

The value for a particular parameter can be specified with or without quotes or within a string variable. If there is no value for a particular parameter name, specify an empty, quoted string.

Examples

Following are sample calls to Ingres tools from embedded SQL and OpenSQL:

```
exec sql call qbf (database = 'empdb',
    table = 'employee');
exec sql call rbf (database = 'empdb',
    flags = '-s -mblock emptable');
exec sql call report (database = :dbvar,
    name = :namevar, mode = :modevar);
exec sql call system (command = 'mail');
```

In the third example, dbvar, namevar, and modevar are host language string variables.

Tools and Parameters

Each Ingres tool accepts parameters that are specified when the tool is called from an embedded SQL or OpenSQL program. Many of these parameters have the same effect as flags used when the tool is called from the operating system command line.

The maximum number of parameters for the call statement is 29, and the combined length of the parameters must not exceed 2043 bytes.

A parameter that does not take an argument must be set to an empty string, specified by an empty pair of quotes. For example, the silent parameter of the report call is equivalent to the -s flag on the report command line. Because -s does not take an argument, specify the silent parameter in the following way:

```
exec sql call report
  (database = 'mydb', name = 'employee', silent = ' ' );
```

These parameters are described in the following sections.

For more information on each command, see the chapter "Using System Commands for the Forms-based Tools."

Abf Command

The abf command accepts the following parameters:

Parameter	Description
application	Name of the application.
flags	Can be used for any flags on the command line. Flags must be separated by a blank.

Ingmenu Command

The ingmenu command to call Ingres Menu accepts the flags parameter, which can be used for any flags on the command line. Flags must be separated by a blank.

Isql Command

The isql command to call the interactive Terminal Monitor for SQL accepts the flags parameter, which can be used for any flags on the command line. Flags must be separated by a blank.

Qbf Command

The qbf command accepts the following parameters:

Parameter	Description
qbfname	Equivalent to the -f flag. Invoke QBF using the specified qbfname. If name is blank, start at Catalogs frame for qbfnames.
joindef	Equivalent to the -j flag. Invoke QBF using the specified JoinDef. If the name is blank, start at Catalogs frame for JoinDefs.
tblfld	Equivalent to the -t flag. Invoke QBF on the specified table, using a table field format to display the data. If the name is blank, start at Catalogs frame for tables.
lookup	Equivalent to the -I flag. Invoke QBF using the specified name. QBF can look up the name in the following order: QBFName, JoinDef name, table name.
silent	Equivalent to the -s flag. Suppresses verbose messages.
mode	Equivalent to the -m flag. Enter QBF directly in the specified mode. Possible values for this parameter are retrieve, append, update, or all.
table	Name of the table on which QBF is being invoked. This parameter must be omitted if one of the joindef, qbfname, tblfld, or lookup parameters has been used.
emptycat	Equivalent to -e flag. If set, catalogs are displayed empty, and the user can enter names directly.
flags	Can be used for any flags on the command line. Flags must be separated by a blank.

Rbf Command

The rbf command accepts the following parameters:

Parameter	Description
silent	Equivalent to the -s flag. Suppresses status messages.
report	Equivalent to the -r flag. Indicates that a report, rather than a table, is being specified. The name of the report is the value for this parameter.
style	Equivalent to the -m flag. Indicates that a table, rather than a report, is being specified. Optional values for this parameter are column, wrap and block. The name of the table is given as the value for the table parameter.
table	The name of a table or view for which a default report is to be formatted.
emptycat	Equivalent to -e flag. If set, the Catalog form is displayed empty, and the user can enter names directly.
flags	Can be used for any flags on the command line. Flags must be separated by a blank.

Report Command

The report command of Report-Writer accepts the following parameters:

Parameter	Description
file	Equivalent to the -f flag. Directs the formatted report to the specified file for output.
silent	Equivalent to the -s flag. Suppresses status messages.
report	Equivalent to the -r flag. Indicates that a report, rather than a table, is being specified. The name of the report is the value for this parameter.
style	Equivalent to the -m flag. Indicates that a table, rather than a report, is being specified. Optional values for this parameter are column, wrap, and block. The name of the table is given as the value for the name parameter.
name	Name of a table or view in the database for which a default report is to be formatted.

Parameter	Description			
param	The list of parameters for the report. Each element in the list must be of this form:			
	name =value			
	Blanks or tabs must separate Name/value combinations. The entire list must be enclosed within quotes. In addition, if <i>name</i> is a character report parameter, then value must be enclosed in quotes. (Values of numeric report parameters cannot, however, be quoted.) The inner quotes that surround <i>value</i> must then be de-referenced according to host language rules so they can be passed through to the report command.			
	For example, assume that you want to call the Report-Writer from within embedded SQL or OpenSQL with the equivalent of this system-level command:			
	report newdb -r myrpt (bin='f01'			
	wstation='u1' type=12 sect=11)			
	Note that bin and wstation are character parameters and that type and sect are numeric parameters.			
	You could call the report by placing the parameters in a program variable.			
	For example:			
	<pre>exec sql call report (database = 'newdb', report = 'myrpt', param = :parmvar);</pre>			
	The variable, parmvar, must contain the value:			
	bin="f01" wstation="u1" type=12 sect=11			
	Double quotes must surround the constant string values within the variable. If your host language requires the de-referencing of double quotes, be sure to do so, according to the rules of your host language.			
forcerep	Equivalent to the -h flag. Report-Writer can put headers and footers, even if no data is found for the report.			
formfeed	Equivalent to the +b flag. Report-Writer forces formfeeds at page breaks, overriding any settings in the report formatting commands.			
noformfeed	Equivalent to the -b flag. Report-Writer suppresses formfeeds, overriding any settings in the report formatting commands.			
pagelength	Equivalent to the -v flag. Sets the page length, in lines, for the report, overriding any .PL commands in the report.			

Parameter	Description
brkfmt	Equivalent to the +t flag (default). If set, breaks and calculations for dates and numbers are based on the displayed data, rather than the internal database values.
nobrkfmt	Equivalent to the -t flag. If set, breaks and calculations for dates and numbers are based on the internal database values, rather than the displayed values.
flags	Can be used for any flags on the command line. Flags must be separated by a blank.

Sql Command

The sql command accepts the flags parameter, which can be used for any flags on the command line. Flags must be separated by a blank.

Sreport Command

The sreport command of the Report-Writer accepts the following parameters:

Parameter	Description
file	Name of a text file containing report formatting commands for one or more reports.
silent	Equivalent to the -s flag. Suppresses status messages.
flags	Can be used for any flags on the command line. Flags must be separated by a blank.

System Command

The system command has only one argument, command. It executes the operating system level command specified by *command_string*. If *command_string* is null, empty, or blank, then it transfers the user to the operating system.

Vifred Command

The vifred command accepts the following parameters:

Parameter	Description
form	Equivalent to the -f flag. Invoke VIFRED on the specified form.
table	Equivalent to the -t flag. Invoke VIFRED with a default form for the specified table.
joindef	Equivalent to the -j flag. Invoke VIFRED with a default form for the specified JoinDef.
emptycat	Equivalent to -e flag. If set, an empty Catalogs form is displayed, and the user can enter names directly.
flags	Can be used for any flags on the command line. Flags must be separated by a blank.

Appendix F: Report-Writer Report Examples

This appendix contains five complete sample reports, as listed below. The Population and Dictionary reports have two alternative sets of specifications.

- The POPULATION report demonstrates a common type of report with subtotaling. POP2 shows an alternative set of formatting statements for producing the same output.
- The ACCOUNT report demonstrates a complex report that might be used in accounting applications.
- The DICTIONARY report demonstrates the use of character printing options within Report-Writer. DICT2 shows an alternative set of formatting statements for the same output.
- The LABEL report demonstrates the formatting of mailing labels that print three across on a page, generated from a list of names and addresses.
- The BOOKS report demonstrates the use of joining tables for producing a report.

Each report example contains the following information:

- Table definition for the report
- Data for the report
- Listing of the report formatting statements used in the report code
- Sample listing of the report itself

For the sake of clarity, the formatting statements appear in the examples as uppercase letters, although they can actually be specified in either uppercase or lowercase letters.

Population Example

The POPULATION example demonstrates the use of Report-Writer in formatting a report of census data, by region and state, for the United States. The base tables for this report are as follows:

- "Region" contains region names associated with region abbreviations
- "State" contains state names, as well as state abbreviations, and associated region abbreviations
- "Pop" contains population data for each state for different census years

Additional details for each of these table layouts are provided in the tables that follow:

Region Table Definition

Column Name	Type	Length	Nulls	Defaults
regabbrev	char	3	yes	no
region	char	20	yes	no

Region Data for the Sample Report

regabb	region
ENC	East North Central
ESC	East South Central
M	Mountain
MA	Middle Atlantic
NE	New England
Р	Pacific
SA	South Atlantic
WNC	West North Central
WSC	West South Central

State Table Definition

Column Name	Туре	Length	Nulls	Defaults
regabbrev	char	3	yes	no
stateabbrev	char	2	yes	no
state	char	20	yes	no

State Data for the Sample Report

regabb	Statab	state	
ENC	IL	Illinois	
ENC	IN	Indiana	
ENC	MI	Michigan	
ENC	ОН	Ohio	
ENC	WI	Wisconsin	
ESC	AL	Alabama	

regabb	Statab	state
ESC	KY	Kentucky
ESC	MS	Mississippi
ESC	TN	Tennessee
MA	NJ	New Jersey
MA	NY	New York
MA	PN	Pennsylvania
M	AZ	Arizona
M	СО	Colorado
M	ID	Idaho
M	MT	Montana
M	NV	Nevada
M	NM	New Mexico
M	UT	Utah
M	WY	Wyoming
NE	CN	Connecticut
NE	ME	Maine
NE	MA	Massachusetts
NE	NH	New Hampshire
NE	RI	Rhode Island
NE	VT	Vermont
Р	AK	Alaska
Р	CA	California
Р	HI	Hawaii
P	OR	Oregon
P	WA	Washington
SA	DE	Delaware
SA	DC	District of Columbia
SA	FL	Florida
SA	GA	Georgia
SA	MD	Maryland

regabb	Statab	state
SA	NC	North Carolina
SA	SC	South Carolina
SA	VA	Virginia
SA	WV	West Virginia
WNC	IA	Iowa
WNC	KS	Kansas
WNC	MN	Minnesota
WNC	MO	Missouri
WNC	NB	Nebraska
WNC	ND	North Dakota
WNC	SD	South Dakota
WSC	AR	Arkansas
WSC	LA	Louisiana
WSC	ОК	Oklahoma
WSC	TX	Texas

Population Table Definition

Column Name	Туре	Length	Nulls	Defaults
year	integer	4	yes	no
stateabbrev	char	2	yes	no
tot_18to65	integer	4	yes	no
tot_under18	integer	4	yes	no
tot_over65	integer	4	yes	no

Population Data for the Sample Report

year	statab	tot_18to65	tot_under18	tot_over65
1970	IL	9600381	1425674	87921
1970	IN	4820324	357464	15881
1970	MI	7833474	991066	50543
1970	ОН	9646997	970477	34543
1970	WI	4258959	128224	30548

year	statab	tot_18to65	tot_under18	tot_over65
1970	AL	2528983	908247	6935
1970	KY	2971232	241292	6182
1970	MS	1393283	815770	7859
1970	TN	3283432	631696	8559
1970	NJ	6349908	770292	47964
1970	NY	15790307	2166933	233500
1970	PN	10737732	1016514	39663
1970	AZ	1604948	53344	112608
1970	СО	2212352	66411	28496
1970	ID	698802	2130	11635
1970	MT	663043	1995	29371
1970	NV	448177	27762	12799
1970	NM	915815	19555	80630
1970	UT	1031926	6617	20730
1970	WY	323024	2568	6824
1970	CN	2835458	181177	15074
1970	ME	985276	2800	3972
1970	MA	5477624	175817	35729
1970	NH	733106	2505	2070
1970	RI	914757	25338	6630
1970	VT	442553	761	1016
1970	AK	236767	8911	54704
1970	CA	17761032	1400143	791959
1970	НІ	298160	7573	462828
1970	OR	2032079	26308	32998
1970	WA	3251055	71308	86806
1970	DE	466459	78276	3369
1970	DC	209272	537712	9526
1970	FL	5711411	1049578	28454
1970	GA	3387516	1190779	11280
			-	

year	statab	tot_18to65	tot_under18	tot_over65
1970	MD	3193021	701341	28037
1970	NC	3891510	1137664	52885
1970	SC	1794430	789041	7045
1970	VA	3757478	865388	25628
1970	WV	1666870	73931	3436
1970	IA	2782762	32596	9018
1970	KS	2122068	106977	17533
1970	MN	3736038	34868	34065
1970	MO	4177495	480172	18834
1970	NB	1432867	39911	10715
1970	ND	599485	2494	15782
1970	SD	630333	1627	33547
1970	AR	1561108	357225	4962
1970	LA	2539547	1088734	13025
1970	ОК	2275104	177910	106218
1970	TX	9696569	1419677	80484

The following text discusses the report formatting statements for the POPULATION report. The POP2 example, which follows the report output, provides a description and listing of a slightly different set of statements that produce the same output:

- The .query statement shows the database query needed to set up the data in the form required to write the report. Essentially, the guery sets up a table with one row for each state, including the columns region (name of region), state (name of state), tot (the total population of the state), tot_under18, tot_18to65, and tot_over65 (populations of three age groups).
- The query contains a variable, \$year, which is used in the where clause to select data for only one census year. In the example shown, you can select the data for 1970 by running the report with the command: report rwsqldb pop (year=1970)

You must enclose the entire *variable=value* clause and its delimiting parentheses within double quotes to pass it through Windows NT or UNIX. For more information, see Passing Parameters on the Command Line in the chapter "Report-Writer Commands and Utilities."

report rwsqldb pop "(year=1970)"

You can also run the report with the command: report

In this case Report-Writer prompts you for the report name, database name, and value for \$year.

- The .sort statement specifies a sorting of the data by region, and within region, by state. This also defines potential break actions for changes in value of region and state.
- The .format statement sets up a default format for a set of columns in the report. These are used not only for the printing of the actual data but also for the printing of subtotals based on that data. The four numeric columns (tot, tot_under18, tot_18to65, and tot_over65) have the same format specification. Actually, the .format statement is not strictly needed, but provides a convenient way to specify the same format for a number of columns.
- The .header report statement precedes a set of formatting statements that execute at the start of the report and write out the centered title at the top of the report. The dollar sign preceding year in the print statement for the second line of this title indicates that year is a variable entered at run time. The statements in this section also print underlined column headings. Report-Writer determines the locations of the headings from the positions of the column names given as variables to the .right (right justify) statements. Report-Writer determines the column positions from print locations for the associated columns in the .detail statements.
- The .header region statement precedes a set of formatting statements that execute at the start of each region. The .need statement insures that at least four lines are available on a page before printing the heading for region. This assures that Report-Writer prints the heading and the detail lines for at least two states on a page.
- The .detail statement precedes a set of formatting statements to be processed for every row created by the query. The statements in this section create rows for each state and specify printing of the actual population data. By analyzing these statements, Report-Writer determines the positions of the columns used throughout the report in the .rt statements.
- The .footer statement precedes a set of formatting statements to be processed after Report-Writer has read the last state in each region and has processed the requisite .detail formatting statements. This report specification uses a .need statement to insure that the two lines in the footer both print on the same page. The statements in this section print a region heading, followed on the same line with the values of some subtotals for the region. The formats used in printing the subtotals are those specified in the .format statement at the start of the report.

- The statements following the .footer report statement are almost identical to those following the .footer region statement, except for the heading and length of the dashed line separators. The values of the subtotals, however, are different because of the different context.
- The statements following the .header page statement specify the title at the top of the second page of the report, as well as a re-specification of the column headings.
- The .footer page statement starts the block of statements that print at the bottom of each page, including the current page number. Because the .right statemen has no parameters, the text is justified to the right margin (determined as the rightmost position printed in the formatting statements in the report).

```
/* POPULATION - Population Report
.NAME pop
.OUTPUT pop.out
. LONGREMARK
The POPULATION report demonstrates a fairly common type
of report with subtotaling.
. ENDREMARK
.QUERY
       select region.region, state.state,
            pop.tot_18to65 + pop.tot_under18 + pop.tot_over65 as tot,
           pop.tot_18to65, pop.tot_under18, pop.tot over65
       from region, state, pop
       where state.statabbrev = pop.statabbrev
           and state.regabbrev = region.regabbrev
           and pop.year = $year
.SORT region, state
.DECLARE year = varchar(4) with prompt 'Enter Year:'
.FORMAT tot, tot_18to65, tot_under18, tot_over65 (' zzz,zzz,zzz')
.HEADER report
       .NEWLINE 3
       .UL .CE .PR 'Population of the United States, by Age Group' .NOU .NEWLINE .CE .PR 'Data for the Year - ', $year(c4) .NL 2 .U .RT tot .PR 'Total Pop' .RT tot_18to65 .PR '18 to 65'
       .RT tot_under18 .PR 'Under 18' .RT tot_over65 .P 'Over 65'
       .NOU .NL 2
.HEADER region
       .NEED 4 .PR 'Region: ', region .NL
       .NEED 2 .T5 .PR state(c20)
       .T+11 .PR tot, tot 18to65, tot under18, tot over65 .NL
.FOOTER region
       NEED 2 .RT tot .PR '-----' .RT tot_18to65 .P '-----'
.RT tot_under18 .P '-----' .RT tot_over65 .P '-----'
.NL .PR 'Totals: ', region (c0) .T tot
       .PR sum(tot), sum(tot 18to65), sum(tot under18), sum(tot over65)
       . NL 2
.FOOTER report
       .NEED 2
       .RT tot .PR '-----' .RT tot_18to65 .P '-----'
.RT tot_under18 .P '-----'
       .RT tot_over65 .P '-----' .NL
.PR 'USA Totals' .T tot
       .PR sum(tot), sum(tot_18to65), sum(tot_under18), sum(tot_over65)
       .NL
.HEADER page
       .NL 3 .PR 'Population by State and Region: ', $year .NL 2
       .U. RT tot .P 'Total Pop' .RT tot_18to65 .P '18 to 65' .RT tot_under18 .P 'Under 18' .RT tot_over65 .P 'Over 65' .NOU
       .NL 2
```

```
.FOOTER page
      . NL
      .PR 'Source: US Department of the Interior, Bureau of the
         Census.
.RIGHT .PR 'Page', page_number('zN') .NL 4
Population of the United States, by Age Group
Data for the Year - 1970
                  Total Pop
                                18 to 65
                                             Under 18
                                                         <u>Over 65</u>
Region: East North Central
                                             1,425,674
  Illinois
                  11,113,976
                                9,600,381
                                                         87,921
  Indiana
                  5,193,669
                                4,820,324
                                             357,464
                                                         15,881
  Michigan
                  8,875,083
                                7,833,474
                                             991,066
                                                         50,543
  Ohio
                  10,652,017
                                9,646,997
                                             970,477
                                                         34,543
  Wisconsin
                                4,258,959
                                             128,224
                                                         30,548
                  4,417,731
Totals: East North Central
                                40,252,476
                                             36,160,135 3,872,905 219,436
Region: East South Central
  Alabama
                  3,444,165
                                2,528,983
                                             908,247
                                                         6,935
  Kentucky
                  3,218,706
                                2,971,232
                                             241,292
                                                         6,182
  Mississippi
                  2,216,912
                                1,393,283
                                             815,770
                                                         7,859
  Tennessee
                  3,923,687
                                3,283,432
                                             631,696
                                                         8,559
Totals: East South Central
                                             10,176,930 2,597,005 29,535
                                12,803,470
Region: Middle Atlantic
                                                         47,964
  New Jersey
                  7,168,164
                                6,349,908
                                             770,292
  New York
                  18,190,740
                                15,790,307
                                             2,166,933
                                                         233,500
  Pennsylvania
                  11,793,909
                                10,737,732
                                             1,016,514
                                                         39,663
Totals: Middle Atlantic
                            37,152,813
                                            32,877,947 3,953,739 321,127
Region: Mountain
                  1,770,900
                                1,604,948
                                             53,344
                                                         112,608
  Arizona
  Colorado
                  2,207,259
                                2,112,352
                                             66,411
                                                         28,496
  Idaho
                  712,567
                                698,802
                                             2,130
                                                         11,635
  Montana
                  694,409
                                663,043
                                             1,995
                                                         29,371
  Nevada
                  488,738
                                448,177
                                             27,762
                                                         12,799
  New Mexico
                  1,016,000
                                915,815
                                             19,555
                                                         80,630
                  1,059,273
                                1,031,926
                                             6,617
                                                         20,730
  Utah
  Wyoming
                  332,416
                                323,024
                                             2,568
                                                         6,824
Totals: Mountain 8,281,562
                                7,798,087
                                             180,382
                                                         303,093
Region: New England
                  3,031,709
  Connecticut
                                2,835,458
                                             181,177
                                                         15,074
  Maine
                  992,048
                                985,276
                                             2,800
                                                         3,972
  Massachusetts
                  5,689,170
                                5,477,624
                                             175,817
                                                         35,729
                                733,106
  New Hampshire
                  737,681
                                             2,505
                                                         2,070
  Rhode Island
                                             25,338
                  946,725
                                914,757
                                                         6,630
                  444,330
                                442,553
                                                         1,016
  Vermont
                                             761
                                11,841,663
                                             11,388,774 388,398
                                                                    64,491
Totals: New England
Source: US Department of the interior, Bureau of the Census.
```

source. Of Department of the Interior, bureau of the Census.

Page 1

Population by State and Region: 1970

Pogion: Pocific	Total Pop	18 to 65	Under 18	Over 6	5
Region: Pacific Alaska California Hawaii Oregon Washington	300,382 19,953,134 768,561 2,091,385 3,409,169	17,761,032 298,160 2,032,079	8,911 1,400,143 7,573 26,308 71,308	791,95 462,82 32,998 86,806	9 8
Totals: Pacific	26,522,631		1,514,243		
Region: South At Delaware District of Co Florida Georgia Maryland North Carolina South Carolina Virginia West Virginia	548,104 lumbia 6,789,443 4,589,575 3,922,399 5,082,059	3,387,516 3,193,021 3,891,510 1,794,430 3,757,478 1,666,870	209,272 1,049,578 1,190,779 701,341 1,137,664 789,041 865,388 73,931	28,454 11,280 28,037 52,885 7,045 25,628 3,436	
Totals: South At 169,660		30,671,337			
Region: West Nor Iowa Kansas Minnesota Missouri Nebraska North Dakota South Dakota	2,824,376 2,246,578 3,804,971 4,676,501 1,483,493 617,761	3,736,038 4,177,495 1,432,867 599,485	34,868 480,172 39,911 2,494	17,533 34,065 18,834 10,715 15,782	
Totals: West Nor		16,319,187	15,481,048		
Louisian 13,025	1,923,295 a 2,559,232 11,196,730	3,641,306	357,225 2,539,54 177,910 1,419,67	7 : 7 :	4,962 1,088,734 106,218 30,484
Totals: West S		19,320,563		28 :	3,043,546204,689
USA Totals	203,165,702				2,880,820

Source: US Department of the interior, Bureau of the Census.

Pop2 Example

The POP2 example shows an alternative set of formatting statements for producing the same output as POPULATION. This report makes use of the .block and .endblock statements, as well as the .within and .endwithin statements, in producing the report. These statements are useful for reports which contain several columns for which the same set of statements is repeated as is the case with the tot, tot_18to65, tot_under18, and tot_over65 columns in POPULATION.

Page 2

All of the statements in POP2 are identical to the statements in POPULATION with the exception of those in the .footer region and .footer report sections. In these sections, instead of spelling out the format of the subtotals line by line, the block and column formatting statements can be used to duplicate the same set of statements for each of several columns. In detail, the statements are:

- The .block statement sets the Report-Writer into block mode, which allows you to write a two-dimensional block of text, in which you can write text on several lines, return to the first line in the block, and then write more text on the first lines in the block.
- The .within statement sets the Report-Writer into column formatting mode. Because the statement is followed by four column names (tot, tot_18to65, tot_under18, and tot_over65), Report-Writer executes all statements between the .within and its corresponding .endwithin statement four times, using the margins for each of the columns in turn.
- The string of hyphens ("----") prints, right justified, within each of the four columns in the first line of the block. Because this is a .printline statement, the current output line moves down one line in the block after the string prints. A sum prints on the second line of the block, right justified within each of the columns. Because this sum uses the special name w_column, Report-Writer calculates and prints a separate sum for each of the columns in turn.
- The .endwithin statement ends the set of formatting statements to be done within each column. Because block mode is in effect, a .top statement automatically executes immediately before the .endwithin statement. This ensures that the statements for each of the columns prints across the page, rather than stair-stepping down the page.
- Immediately following the .endwithin statement is the .top statement, which moves the current output line back to the first line in the current block (which contains all of the strings of hyphens ("-----"). The .newline statement moves the current position to the second line in the block (as block mode is still in effect), and Report-Writer prints the Totals: region string. The .endblock statement causes Report-Writer to print the block, consisting of two lines, and to leave block mode. The last .newline statement inserts a blank line.
- The statements within the .footer section are identical, except for the string, USA Totals. Because of the context, "sum(w_column)" refers to totals for the entire report, rather than for the region.

The statements in this example are not quite as intuitive as those in the POPULATION report specification, but they show an important capability for formatting reports with column-oriented statements.

```
/* POP2 - Population Report using .WITHIN */
.NAME pop2
.OUTPUT pop2.out
. LONGREMARK
POP2 shows an alternative set of formatting statements
 (.BLOCK and .ENDBLOCK and .WITHIN and .ENDWITHIN)
 for producing the same output as the POPULATION report. The same set of
statements is repeated for the columns: totpop, tot 18to65, tot under18,
tot over65. All statements in POP2 are the same as POPULATION with the
\operatorname{\mathsf{exception}} of those in the ".FOOT region" and ".FOOT report" sections.
. ENDREMARK
. QUERY
      select region.region, state.state,
           pop.tot_18to65 + pop.tot_under18 + pop.tot_over65 as tot,
               pop.tot_18to65, pop.tot_under18, pop.tot_over65
      from region, state, pop
      where state.statabbrev = pop.statabbrev
           and state.regabbrev = region.regabbrev
           and pop.year = $year
.SORT region, state
.DECLARE year = varchar(4) with prompt 'Enter Year:'
.FORMAT tot, tot_18to65, tot_under18, tot_over65 (' zzz,zzz,zzz')
.FORMFEEDS
.HEADER report
      .NEWLINE 3
      .UL .CE .PR 'Population of the United States, by Age Group' .NOU
      .NEWLINE .CE .PR 'Data for the Year - ', $year(c4) .NL 2
      .U .RT tot .PR 'Total Pop' .RT tot_18to65 .PR '18 to 65' .RT tot_under18 .PR 'Under 18' .RT tot_over65 .P 'Over 65'
      .NOU .NL 2
.HEADER region
  .NEED 4
  .PR 'Region: ', region .NL
.DETAIL
      .NEED 2 .T5
      .PR state(c20) .T+11 .PR tot, tot 18to65, tot under18, tot over65
       .NL
.FOOTER region
      .NEED2
      . BLOCK
                      .WITHIN tot, tot_18to65, tot_under18, tot_over65
                      .RT .PRINTLINE '-----
                       .RT .PRINTLN sum(w column)
                .ENDWITHIN
                .TOP .NEWLINE .PR 'Totals: ', region(c0)
      .ENDBLOCK .NEWLINE
.FOOTER report
      .NEED2
               .WITHIN tot, tot_18to65, tot_under18, tot_over65
      .BLOCK
                   .RT .PRINTLINE '----
                   .RT .PRINTLN sum(w column)
                .END WITHIN
                .TOP .NEWLINE .PR 'USA Totals'
      .ENDBLOCK .NEWLINE
.HEADER page
      .NL 3 .PR 'Population by State and Region: ', $year .NL 2 .U .RT tot .P 'Total Pop' .RT tot_18to65 .P '18 to 65' .RT tot_under18 .P 'Under 18' .RT tot_over65 .P 'Over 65'
      .NOU .NL 2
.FOOTER page
      . NL
      .PR 'Source: US Department of the Interior, Bureau of the
             Census.'
      .RIGHT .PR 'Page', page_number('zN') .NL 4
```

QUEL User Notes

Windows

UNIX

VMS

For the \$year variable, you can select the data for 1970 by running the report with the command:

```
report rwqueldb pop (year=1970) In report rwqueldb pop '(year=1970)' In report rwqueldb pop (year=1970)
```

The QUEL version of the query for this example is shown below. This query is identical for both the POPULATION and POP2 examples.

Account Example

The ACCOUNT example shows a fairly complex report that could be written from some accounting data. For each account, the report prints the name and address of a customer, followed by a listing of transactions in an account. The report lists deposits in one column, withdrawals in another, and a running balance in a third. The following base tables are used:

- The table, "customer table," which contains the name and address of a customer
- The "account" table, which associates an account number with a customer name and address (because a customer can have more than one account)

This table also contains the balance of an account as of an arbitrary date. In actual accounting applications, this balance must be updated outside of Report-Writer.

■ The "transact" table, which contains a description of all transactions for an account

This table contains columns, transnum (the transaction number), acct num (the account number), tdate (the date of the transaction), amount (the dollar amount of transaction), and type (the type of transaction: 0 for deposits, 1 for withdrawals).

The following tables provide additional details on each of the database table layouts:

Customer Table Definition

Column Name	Type	Length	Nulls	Defaults
"c name"	char	20	yes	no
address	char	20	yes	no
city	char	20	yes	no
state	char	2	yes	no
zip	integer	4	yes	no
balance	decimal	(12,2)	yes	no

Customer Data for the Sample Report

"c name"	Address	city	state	zip
P.J. Megabucks	1 Panorama Lane	Hilltop	СТ	12345
C. Richard Runn	123 Primer Path	Reading	PA	23456

Account Table Definition

Column Name	Туре	Length	Nulls	Defaults
name	char	20	yes	no
"acct num"	integer	4	yes	no
balance	decimal	(12,2)	yes	no

Account Data for the Sample Report

name	acctnum	balance
P.J. Megabucks	749025436	234657.00
C. Richard Runn	488219082	1245.00

Transact Table Definition

Column Name	Туре	Length	Nulls	Defaults
acctnum	integer	4	yes	no
tdate	date		yes	no
transnum	integer	4	yes	no
type	integer	4	yes	no
amount	decimal	(12,2)	yes	no

Transact Data for the Sample Report

acctnum	Tdate	transnum	type	amount
749025436	01-jul-1998	0101	0	100000.00
749025436	01-jul-1998	0102	1	50500.00
749025436	01-jul-1998	0103	1	24.56
749025436	01-jul-1998	0104	1	10100.00
749025436	15-jul-1998	0105	0	50000.00
749025436	17-jul-1998	0106	1	10143.54
749025436	17-jul-1998	0107	1	243.56
749025436	22-jul-1998	0108	1	100.00
749025436	23-jul-1998	0109	1	25000.00
749025436	23-jul-1998	0110	0	100000.00
488219082	25-may-1998	0101	1	200.00
488219082	03-jul-1998	0102	0	250.00
488219082	05-jul-1998	0103	1	320.34
488219082	05-jul-1998	0104	0	65.23
488219082	08-jul-1998	0105	1	100.00
488219082	10-jul-1998	0106	1	56.32
488219082	16-jul-1998	0107	1	24.71
488219082	20-jul-1998	0108	1	120.00
488219082	25-jul-1998	0109	1	31.16

The following text discusses the report formatting statements:

The .delimid statement enables recognition of delimited identifiers used as a table name (customer table) and column names (c name and acct num).

- The .declare section declares the variables \$min_limit and \$max_limit, to be given values in response to a run-time prompt, and \$final_balance, with an initial value of 0.00.
- The query, shown after the .longremark section, provides data for the report. This query retrieves the transact table, with data from the other tables joined in. The specification also shows the calculation of the columns amt, withdrawal, and deposit. The withdrawal value is set to amount if type is 1; otherwise, it is set to zero. The depositvalue is set to amount if type equals 0; otherwise, it is set to zero. The value of amt is calculated as a signed value of amount, which is negative for withdrawals and positive for deposits. The amt value is used in calculating the running balance.

- The .sort statement describes the order of the data. In the example output, only one account appears for each name, although this sort order would print additional accounts for each name if they existed in the data.
- The .formfeeds statement inserts form feed characters at the start of the report and at the end of each page of the report. Because no .pagelength statement is specified, a default page size of 61 lines is assumed. The default is determined by the output for the report. The output can be to a screen, file, or printer.
- The .format statements provide default formats for some of the output columns. The hyphen (-) in the format for acct num forces hyphens in specific places in the output.
- The .header statement begins the set of formatting statements to be executed at the start of each new name. The .newpage statement tells Report-Writer to skip to the top of a new page and to set the page number to the value 1 at the start of each new name. The next statements print the address and skip some lines.
- The .head acct num block prints the opening balance, column headings, and sets a temporary format for acct num (so that it is printed for the first transaction only). Report-Writer determines the positions associated with the columns from a scan of the formatting statements in the .detail section, including a position for the amt column, which is somewhat hidden in the cumulative sum function.
- The .head tdate block sets a temporary format for tdate, so that Report-Writer prints the date only the first time it encounters that particular date value.
- The .detail block prints out the lines in the report. It also determines the default margins and column positions from an analysis of these statements. The formats for tdate and acct num, which specify nonprinting formats, can be overridden by the .tformat statements specified in the header text for tdate and acct num.

The "cum("acct num") sum(amt,balance)" aggregate specifies the calculation and printing of the running balance. The first part, "cum("acct num")" specifies that the running balance is a cumulative aggregate, which is initialized at the most recent break in "acct num." The rest, "sum(amt,balance)," specifies that the cumulative aggregate is a sum of "amt," and that the cumulative is to be initialized to the value of "balance" when the report starts (at the most recent break in "acct num"). The format to be used is specified as the default for "amt" because the aggregate specification is not followed by a parenthesized format.

■ The .foot acct num block prints out summations of the withdrawal and deposit columns and the closing balance of the account, as calculated in the "sum(amt,balance)" aggregate. Report-Writer calculates the closing balance as the sum of amt for a specific acct num (because of the context), and then initializes it to the value of balance at the start of "acct num." Remember that the figure is negative for withdrawals and positive for deposits. Because the aggregate specification is not followed by a parenthesized format specification, the .format statement for amt at the beginning of the report is used as the default format for the aggregate.

The .if-.elseif-.endif block prints a "Balance below ..." or "Balance exceeds ..." message if the customer's closing balance is less than the established minimum (\$min_limit) or greater than the established maximum (\$max_limit).

- The .foot name block specifies the printing of an ending statement.
- The .head page block describes the heading shown at the top of each page. The .newpage statement in the .head name statements forces the printing of the page header on the first page (which normally does not happen).
- The .foot page block tells Report-Writer to skip some lines at the end of each page.

The pages following the report specification contain sample reports generated with the following values:

- In the first example, $$min \ limit = 500.00 \ and <math>$max \ limit = 100,000.00$
- In the second example, $min_limit = 1,000.00$ and $max_limit = 250,000.00$

```
/* ACCOUNT - example of bank statement report. */
.NAME account_delim
.OUTPUT account delim.out
. LONGREMARK
The ACCOUNT_DELIM report shows a fairly complex report that could be
written for some accounting data. For each account, the report prints
the name and address of a customer, followed by a listing of
transactions in an account. Deposits are listed in one column,
withdrawals in another, and a running balance is listed in a third.
 The report orders the transactions in LIFO date order. It also
demonstrates the use of:
    o schema.tablename
    o delimited identifiers
    o decimal datatypes
. ENDREMARK
.DELIMID
. DECLARE
      min limit = decimal(12,2) with prompt
             'Enter minimum balance flag level: ',
      \max limit = decimal(12,2) with prompt
              'Enter maximum balance flag level: '
      final_balance = decimal(12,2) with value '0.00'
.QUERY
               "c tbl"."c name", "c tbl".address, "c tbl".city,
"c tbl".state, "c tbl".zip,
      SELECT
               a. "acct num", a.balance,
               t.transnum, t.tdate,
               t.amount * t.type AS withdrawal,
t.amount * (1 - t.type) AS deposit,
(t.amount * (1 - t.type)) - (t.amount *
                     t.type) AS amt
                transact t, account a, dave. "customer table" "c tbl"
      FROM
                a."acct num" = t.acctnum and "c tbl"."c name" = a.name
      WHERE
           "c name", "acct num", tdate:d, transnum
"acct num" (' nn\-nnnnnn\-n '),
. SORT
.FORMAT
           tdate (d'01/02/03'),
           withdrawal, deposit, amt, balance (' $$$,$$$,$$s.zz')
.HEAD "c name"
      . NEWPAGE
      .NL 3
      .PRINT "c name"
      . NL
      .PRINT address
      .PRINT city (c0), '', state (c0), '', zip ('nnnnn')
       .NL 4
.FOOT "c name"
      .NL 3
       .PRINT 'End of accounts for: ', "c name"
      . NL
.HEAD "acct num"
      .NL 3
      .PRINT 'Account: ', "acct num"
      .PRINT 'Opening balance:', balance
      .NL 2
      .\,\mathsf{UL}
           .CE "acct num"
                .PRINT 'Account'
           .CE tdate
                .PRINT 'Date'
           .CE transnum
               .PRINT 'Transaction'
                .RT deposit
                .PRINT 'Deposit'
                .RT withdrawal
```

```
.PRINT 'Withdrawal'
               .RT amt
               .PRINT 'Balance'
          .NL
      . NOU
      .TFORMAT "acct num" (' nn\-nnnnnn\-n ')
.FOOT "acct num"
      .NL 2
      .PRINT 'Account', "acct num", 'totals.'
      .TAB deposit
      .PRINT sum(deposit)
      .TAB withdrawal
      .PRINT sum(withdrawal)
      .NL 2
      .LET final_balance = sum(amt, balance)
      .RT amt
      .PRINT 'Closing balance:', $final_balance (' $$$,$$$,$$.zz')
      .IF $final balance < $min limit .THEN
           .PRINT '*** Balance below established minimum of ',
              $min limit, ' ***'
      .ELSEIF $final_balance > $max_limit .THEN'
           .PRINT \ '*** Balance exceeds established maximum of \ ' ,
              $max limit,' **
      .ENDIF
.HEAD tdate
      .TFORMAT tdate (d'01/02/03 ')
.DETAIL
      .PRINT "acct num" (b16), tdate (b16),
      .TAB +8
      .PRINT transnum ('nnnn'), deposit, withdrawal
      .TAB +5
      .PRINT cum("acct num") sum(amt, balance)
      . NL
.HEAD page
      .NL 2
      .PRINT 'Customer: ', "c name"
      . CE
          .PRINT 'Date: ', current date (d'February 3, 1901'),
           .RT
          .PRINT 'Page ', page_number
          .NL 4
.F00T page
      .NL 3
Customer: P.J. Megabucks Date: July 27, 2000
                                                      Page 1
P.J. Megabucks
1 Panorama Lane
Hilltop CT 12345
Account: 74-902543-6
                               Opening balance:
                                                   $234,657.00
<u>Account</u>
                          Transaction
                                        <u>Deposit</u>
                                                      <u>Withdrawal</u>
              <u>Date</u>
                                                                  Balance
74-902543-6
                         0109
                                        $25,000.00
                                                      $288,545.34
              93/07/23
                                        $100,000.00 $388,545.34
                          0110
               93/07/22
                                        $100.00
                                                      $313,545.34
                         0108
                                        $10,143.54
              93/07/17
                         0106
                                                      $313,888.90
                          0107
                                        $243.56
                                                      $313,645.34
                                        $50,000.00
                                                                   $324,032.44
              93/07/15
                         0105
                                        $100,000.00 $274,032.44
                          0101
                                        $50,500.00
               93/07/01
                         0102
                                                      $184,157.00
                                        $24.56
                                                      $174,032.44
                         0103
                          0104
                                        $10,100.00
                                                      $174,057.00
                                        $250,000.00 $96,111.66
Account 74-902543-6 totals.
Closing balance:
*** Balance exceeds established maximum of 250000.00 ***
                                                             $388,545.34
End of accounts for: P.J. Megabucks
```

```
Customer: C. Richard Runn
                               Date: July 27, 2000 Page 1
C. Richard Runn
123 Primer Path
Reading PA 23456
Account: 48-821908-2
                               Opening balance:
                                                   $234,657.00
                                       <u>Deposit</u>
    Account
              Date
                         <u>Transaction</u>
                                                     <u>Withdrawal</u>
                                                                  Balance
    48-821908-2
                         93/07/25
                                                                    $707.70
                                        0109
                                                     $31.16
              93/07/20
                         0108
                                        $120.00
                                                     $738.86
              93/07/16
                         0107
                                        $24.71
                                                     $858.86
              93/07/10
                         0106
                                                     $883.57
                                        $56.32
              93/07/08
                         0105
                                        $100.00
                                                     $939.89
              93/07/05
                         0103
                                        $320.34
                                                     $974.66
                         0104 $65.23
                                                     $1,039.89
              93/07/03
                         0102 $250.00
                                                     $1,295.00
                                        $200.00
              93/05/25
                         0101
                                                     $1,045.00
Account 48-821908-2 totals.
                                                     $852.53
                                        $315.23
              Closing balance:
                                  $707.70
End of accounts for: C. Richard Runn
```

QUEL User Notes

You cannot use delimited identifiers, schema or owner qualification for table names, or the decimal data type in QUEL queries. Therefore, to create a QUEL version of this report, you have to set up the tables without delimited identifiers as column or table names. The balance column is data type float8 rather than decimal (12,2). You are not able to use owner qualification for the customer table.

An equivalent QUEL query for a similar example would be:

Dictionary Example

The DICTIONARY example shows an example of a report that lists a glossary of Ingres terms, with a listing of related keywords. This demonstrates the use of some of the word-processing functions available in Report-Writer. The following base tables are used:

■ The "ddef" table, which contains names of terms and definitions of those terms

■ The "dref" table, which contains a list of terms and their related keywords

Additional details on each of these table layouts are provided in the tables that follow:

Dref Table Definition

Column Name	Туре	Length	Nulls	Defaults
word	char	20	yes	no
definition	char	250	yes	no

Ddef Data for the Sample Report

Word	Definition
aggregate function	An aggregate operator which first groups rows on the basis of the value of a column or list of columns called the by-list, before computing the aggregate for each value of the by-list.
aggregate operator	An aggregate operator is a computation performed on a column across all rows in a table. Common aggregate operators are SUM, COUNT, and AVG. Aggregate operators can have qualifications to limit the number of rows used in the calculation.
attribute	Another term for a column in a table.
buffer	Another term for the Ingres workspace.
column	All data in Ingres is saved in the form of tables made up of rows and columns. In traditional database terminology, a column is a field in a record.
comparison operator	A symbol which specifies the kind of comparison to make in a qualification, such as > (for greater than), or = (for equality check).
compressed	Any of the Ingres internal storage structures can be compressed. Compression reduces the storage required for a table, by deleting all trailing blanks in character columns.

Dref Table

Column Name	Туре	Length	Nulls	Defaults
Word	char	20	yes	no
Ref	char	20	yes	no

Dref Data for the Sample Report

Word	Ref	
aggregate function	aggregate operator	
aggregate function	aggregation	
aggregate function	by list	
aggregate function	computation	
aggregate operator	aggregate function	
aggregate operator	aggregation	
aggregate operator	computation	
Attribute	column	
Buffer	workspace	
Column	attribute	
Column	domain	
Column	field	
comparison operator	qualification	
comparison operator	restriction	
Compressed	character strings	
Compressed	compression	
Compressed	storage structures	·

The following text discusses the report formatting statements:

- The guery used to create the data for the report joins words and definitions with a list of the related keywords. Therefore, the data returned to the report contains one row for each related keyword. The .detail section statement pertains to the related keywords, and the .head word statement pertains to the word itself and the definition.
- Report-Writer sorts the data by word, and within word, by related keyword.
- The report specification sets the left and right margins to specific values because the default margins calculated for the report do not reflect the required margins of the report.
- The .head report section statement performs a page break and prints a page header at the top of the page.

- The .head statement for "word" prints out the underlined word and the newspaper style printing of the definition. The cj0.50 format specifies a column format 50 spaces wide, with right justification, with printing occurring until the end of the string. The .t80 statement then moves to position 80 (5 spaces to the right of the edge of the definition), and sets the left margin of the report to that position. This causes all printing to wrap around between the left margin (80) and the right margin (100). No .newline statement is given, so that the next printing occur at column 80 of the top line of the definition.
- The .detail section statement prints out the next related keyword for "word," until the next word is found. Because the format specified for ref is c20, it exactly fits within the temporary margins, and wrap-around format causes each keyword to appear on a separate line. Remember that the .lm0 statement in the header text for "word" resets the left margin for printing a new word and definition.
- The .foot statement for "word" finishes the text for one "word" by printing out all the lines in the definition and related keyword list, and prints a blank line.
- The .head page section statements print out a title, page number, and column headings.

```
/* DICTIONARY - text example */
.NAME dict
.OUTPUT dict.out
. LONGREMARK
The DICTIONARY report demonstrates the use of character printing options
within the Report-Writer. It lists a glossary of Ingres terms,
with a listing of related keywords. This demonstrates the use of some
of the word-processing functions available in the Report-Writer.
. ENDREMARK
. QUERY
    select ddef.word, ddef.definition, dref.ref
    from ddef ddef, dref dref
    where ddef.word = dref.word
.SORT word, ref
.LM 0
.RM 100
.HEAD report
    .NEWPAGE 1
.HEAD word
    .NE 3 .LM 0
    .UL .PR word(c25) .NOU
    .P definition(cj0.50)
    .T80 .LM80
.DETAIL
    .P ref(c20)
.FOOT word
    .NL 2
.HEAD page
    .NL 2
    .P 'Dictionary of Ingres Terms'
    .RT .P 'Page', page_number .NL 2
.UL .P 'Word' .T definition .P 'Definition'
.T80 .P 'Related Term' .NOU .NL 2
.FOOT page
.NL 3
```

Dictionary of Ingres Terms	Page 1	Related Term
Word	Definition	
aggregate function	An aggregate operator which first groups rows on the basis of the value of a (list of) column(s) (called the "by-list"), before computing the aggregate for each value of the "by-list."	aggregate operator aggregation by list computation
aggregate operator	An aggregate operator is a computation performed on a column across all rows in a table. Common aggregate operators are SUM, COUNT, and AVG. Aggregate operators can have qualifications to limit the number of rows used in the calculation.	aggregate function aggregation computation
attribute	Another term for "column" in a table.	column
buffer	Another term for the Ingres "workspace".	workspace
column	All data in Ingres is saved in the form of tables made up of rows and columns. In traditional database terminology, a "column" is a "field" in a record.	attribute domain field

comparison operator	A symbol which specified the kind of comparison to make in a qualification, such as ">" (for greater than), or "=" (for equality check).	qualification restriction
compressed Any of the Ingres internal storage structures can be compressed. Compression reduces the storage require a table, by deleting all trailing blanks in charact columns.		character strings compression storage structure

Dict2 Example

The previous DICTIONARY report uses some margin tricks to accomplish what can perhaps more easily be accomplished with the block mode of Report-Writer. Instead of letting the margins and wrap-around format accomplish the task of moving down the page, you can use the more natural .newline statement in block mode to do this. The DICT2 report is the same as the DICTIONARY report, except for differences in the .head and .foot for "word," and a slight change in the .detail section.

The changed statements are:

- In the .header for "word," the report specification sets Report-Writer into block mode. This allows you to move down the page in a more orderly fashion than would otherwise be possible. The underlined word prints on the first line of the block. The newspaper-style printing of the definition causes some number of lines within the block to be written, depending on the length of the definition. However, when it has finished printing, the current output line is the top line in the block. You are now ready to print the detail lines, which contain the keywords for a term.
- Within the .detail section of the report, the specification statements cause Report-Writer to tab to column 80, and print the next value of "ref." The .newline statement moves the current output line down one line in preparation for the next value of "ref." Because it is in block mode, Report-Writer saves all text after the header for "word" until it encounters the .endblock statement.
- The .end block statement in the .footer section for "word" prints out the current block containing the word, its definition, and a list of related keywords. A .newline statement adds another blank line.

The DICT2 report accomplishes the same output as the DICTIONARY report, but in a somewhat more natural fashion.

```
/* DICT2 - text example, using .BLOCK */
.NAME dict2
.OUTPUT dict2.out
. LONGREMARK
The DICT2 report shows an alternative set of formatting statements for
producing the same output as the DICTIONARY report. The DICTIONARY
report uses some margin tricks to accomplish what can perhaps more
easily be accomplished with the block mode of the Report-Writer. Instead
of letting the margins and wraparound accomplish the task of moving down
the page, within block mode, you can use the more natural .NEWLINE
statement. Differences between the two reports is limited to the ".HEAD word" and ".FOOT word" and a slight change in the ".DETAIL" section.
. ENDREMARK
.QUERY
             select ddef.word, ddef.definition, dref.ref
             from ddef ddef, dref dref
             where ddef.word = dref.word
.SORT word, ref
.LM 0
.RM 100
.HEAD report
              .NEWPAGE 1
.HEAD word
              .NEED 3
              .BLOCK
              .UL .PR word(c25) .NOU
              .PR definition(cj0.50)
.DETAIL
              .T80 .PR ref(c20) .NL
.FOOT word
              .END BLOCK
              .NL
.HEAD page
              .NL 2
              .P 'Dictionary of Ingres Terms'
             .RT .P 'Page', page_number .NL 2
.UL .P 'Word' .T definition .P 'Definition'
              .T80 .P 'Related Term' .NOU .NL 2
.FOOT page
              .NL 3
```

QUEL User Notes

The QUEL version of the query for this example is shown below. This query is identical for both the DICTIONARY and DICT2 examples.

```
/* DICTIONARY - text example */
.NAME dict
. QUERY
        range of d is ddef
        range of r is dref
        retrieve (d.word, d.definition, r.ref)
        where d.word = r.word
```

Label Example

The LABEL example shows a report that prints mailing labels three across the page. The base table, subscriber, is a mailing list containing the name, post office box, address, city, state and zip code for each label. If there is no post office box for the label, the field is left blank.

Additional details on the base table layout are provided in the following tables:

Subscriber Table Definition

Column Name	Туре	Length	Nulls	Defaults
name	char	20	yes	no
po_box	char	20	yes	no
address	char	20	yes	no
city	char	20	yes	no
state	char	2	yes	no
zip	integer	4	yes	no

Subscriber Data for the Sample Report

name	po_ box	Address	city	state	zip
Betty Clark		2556 Carey Rd	Boston	MA	01002
Ming Ho		1020 The Parkway	Mamaroneck	NY	10543
Pat McTigue		Route 146	Trumbell	СТ	04239
T. Shigio	1234	201 Emperor Lane	Rye	NY	10101
Marvin Blumbert		17 Saville Row	Carmel	CA	93001
Carlos Ramos		2459 39th Ave	San Francisco	CA	94121
AnastassiosVasos		722 Fourth St.	Gualala	CA	95035
Mario Verducci	x-207	General Delivery	Middletown	WA	98112

The following text discusses the report formatting statements:

- Report-Writer sorts the data by zip code.
- The report first begins a block so that the labels can be printed across the page.

- The labels are assumed to be \$lbl_width wide and \$lbl_length number of lines long. The value of \$lbl_width must be greater than the actual number of characters printed and less than the page width, \$pg_columns. The number of lines actually printed depends on the number of .newline statements in the report. Because \$lbl_length is used to determine page breaks, it must be less than the number of lines per page, \$pg_lines.
- Report-Writer creates a label by printing all fields of the table across four lines. If the field for the post office box is blank, the corresponding line cannot be printed.
- Some labels are best printed one set per page. This is useful if FF is used and the lines per page on the printer is set to the number of lines on the label. To print one set per page, adjust the value of \$pg_lines to be equal to the \$lbl_lines + 1.
- Report-Writer moves the left margin for the next label one label's width to the right of the previous left margin, if doing so does not cause the label to move beyond the right margin (for example, if only 1 or 2 labels have been formatted for a line which can fit three). When no more room exists on the line, the block of labels ends, the .endblock statement moves the report to the top of the next block of labels, the left margin is reset to 0 and a new block of labels begins. When the report runs out of data the block automatically ends, whether or not there is space left in the block buffer.
- This report uses declared variables without prompts. This means that the values of the variables must be passed in from the command line. The following report was run using these commands typed on a single line:

```
report rwsqldb labels (pg_lines=11, pg_columns=79,lbl_width=25,
lbl_length=5)
report rwsqldb labels "(pg_lines=11, pg_columns=79, lbl_width=25,
lbl_length=5)"
```

Windows

UNIX

```
** LABEL. Write out three across mailing labels
** with suppression of blank PO boxes.
*/
.NAME labels
.OUTPUT labels.out
.SHORTREMARK Prints data in mailing label format:
. LONGREMARK
Requires parameters pg_columns, pg_lines, lbl_width, and lbl_length passed in on the command line. They will not be prompted for. The
following values will result in three labels across and two down:
 (pg_lines=11,pg_columns=79,lbl_width=25,lbl_length=5) By varying the
values you can vary the layout of the labels.
. ENDREMARK
.QUERY select name, po_box, address, city, state, zip
         from subscriber
.SORT zip
. DECLARE
         pg_columns = int, /* number of characters across the page */
         pg_lines = int, /* number of lines per page */
lbl_width = int, /* the number of characters across one label*/
          lbl_length = int /* the number of lines in one label */
.PL $pg_lines
.PW $pg columns
.RM $pg_columns
.LM 0
.HEADER report
          .NEED $1b1_length
          . BLOCK
.HEADER page
          .NEED $1bl length
          .BLOCK
.DETAIL
          .TOP
          .LINESTART
          .PRINTLN name
          .IF po_box != ' ' .THEN
                            .PRINTLN 'PO Box ', po_box
          .ENDIF
          .PRINTLN address(cf0.30)
         .PRINTLN city (c0),',',state(c0),' ',zip('nnnnn')
.IF left_margin + ($lbl_width * 2) < right_margin .THEN
                   .LM + $lbl width
              .ELSE
                   .ENDBLOCK
                   .NL
                   .NEED $1bl_length
                   .BLOCK
                   .LM 0
          .ENDIF
.FOOTER page
          . ENDBLOCK
.FOOTER report
          . ENDBLOCK
```

Completed Report:

Betty Clark Pat McTigue Ming Ho 2556 Carey Rd. Route 146 1020 The Parkway Trumbell, CT 04239 Mamaroneck, NY 10012 Boston, MA 01002 T. Shigio Marvin Blumbert Carlos Ramos PO Box 1234 2459 39th Ave 17 Saville Row 201 Emperor Lane Carmel, CA 93001 San Francisco, CA 94121 Rye, NY 10101 Mario Verducci Anastassios Vasos 722 Fourth St. PO Box X-207 Gualala, CA 95035 General Delivery Middletown, WA 98112

QUEL User Notes

The QUEL version of the query for this example is:

```
** LABEL. Write out three across mailing labels
** with suppression of blank PO boxes.
.NAME label
.QUERY
        range of s is subscriber
        retrieve (s.name, s.po_box, s.address, s.city,
                s.state, s.zip)
```

Creating Reports Using Several Tables

There are times when you want to use Report-Writer to produce a report from related information scattered across several tables that share one or more column definitions. You can do this by creating a temporary table or view based on multiple tables in the .setup section, using SQL statements. You can then drop the table or view, or update a status, in the .cleanup section of the same report.

Joining Tables for a Report

Suppose you want to assemble a report from a database of the books in your personal library. You decide upon a report design to present title, author, and subject information like this:

TITLE OF BOOK Subject1 Author1 Author2 Subject2 Subject3

In your database, you have designated three separate tables to hold this information—one for titles (title), one for authors (name) and one for subject information (subject):

Book Table Definition

Column Name	Туре	Length	Nulls	Defaults
id	integer	4	yes	no
title	varchar	20	yes	no

Book Data for the Sample Report

id	title
1001	The C Programming Language
1002	Computer Programming Arch.
1003	The INGRES Papers
1004	Database Systems
1005	The Quiet American

Author Table Definition

Column Name	Туре	Length	Nulls	Default
Id	integer	4	yes	no
name	varchar	15	yes	no

Author Data for the Sample Report

Admor Data to	пе запріє кероп	
ld	title	
1001	Ritchie	
1001	Kernighan	
1002	Eckhouse	
1002	Levy	
1003	Stonebraker	
1004	Ullman	
1005	Greene	

Subject Table Definition

Column Name	Туре	Length	Nulls	Default
Id	integer	4	yes	no
Subject	varchar	15	yes	no

Subject Data for the Sample Report

id	Subject	
1001	С	
1001	Programming	
1001	Language	
1002	Architecture	
1002	Assembler	
1002	Computer	
1002	Programming	
1003	Database	
1003	Ingres	
1003	Computer	
1004	Database	
1004	Management	
1005	Vietnam	

Using a Union Clause

Now you must combine these tables to produce the data shown in the following table:

id	title	name	subject	code
1001	The C Programming Language	Kernighan		1
1001	The C Programming Language	Ritchie		1
1001	The C Programming Language		С	2
1001	The C Programming Language		language	2
1001	The C Programming Language		programming	2

The easiest method is to use a union clause, as is shown in the .query section of the following report example:

```
.NAME books1
.OUTPUT books1.out
. LONGREMARK
        The BOOKS report demonstrates the use of joining tables
        for producing a report.
. QUERY
        select b.id, b.title, a.name, '' as subject, 1 as code
        from book b, author a
        where b.id = a.id
        union
        select b.id, b.title, '' as name, s.subject, 2 as code
        from book b, subject s
        where b.id = s.id
.SORT title, code
.BREAK title, code /* title and code will be break columns */
.RIGHTMARGIN 80 /* Initialize right margin */
. DECLARE
        authors_column = integer,
        subject column = integer,
        title_string = varchar(8)
.HEADER report
        /* Initialize variables */
        .LET authors_column = 5
        .LET subject column = 20
.HEADER title
        /* Reset margin and print title of book */
        /* start a block after printing the master info */
        .LEFTMARGIN 0
        .ULCHARACTER '='
        .UNDERLINE
        .PRINT title .NEWLINE
        .NOUNDERLINE
        .BLOCK
.HEADER code
        /* goto the top of the block each time code changes */
        /* set margin to the correct column for the code type */
        .ULCHARACTER '-'
        .IF code = 1 .THEN
                 .LEFTMARGIN $authors_column
                 .LET title string = 'Authors'
        .ELSEIF code = 2 .THEN
                .LEFTMARGIN $subject_column
.LET title_string = 'Subject'
        .ENDIF
        .UNDERLINE
        .PRINT $title_string .NEWLINE
        .NOUNDERLINE
.DETAIL
        /* test the value of code to see which column to print */
        .IF code = 1 .THEN
                 .PRINT name .NEWLINE
        .ELSEIF code = 2 .THEN
                 .PRINT subject .NEWLINE
        .ENDIF
.FOOTER title
        .ENDBLOCK /* end the block at the end of the master info */
        .NEWLINE
```

Completed Report:

```
Computer Programming and Arch.
Authors
               Subjects
  Eckhouse
               architecture\\
               assembler
  Levy
               Computer
              programming
```

QUEL User Notes

In QUEL, you specify a join of several tables with a retrieve statement. In QUEL, you would use these queries to join the tables:

```
destroy tempbooksq\p\g
range of b is book\p\g
\range of a is author\p\g
range of s is subject\p\g
create tempbooksq (
               = i4,
      id
               = varchar(30),
      title
               = varchar(15) not null with default,
      name
               = varchar(15) not null with default,
      subject
      code
               = i1
      )\p\g
      append tempbooksq (b.all, a.name, code=1)
         where b.id = a.id\p\g
      append tempbooksq (b.all, s.subject, code=2)
         where b.id = s.id\p\g
```

Avoiding Awkward Page Breaks

Assume you have invested in a new bookcase and have expanded the size of your personal library by many volumes. Now when you combine your three tables, you create a much larger union than before:

id	Title	name	subject	code
1001	The C Programming Language	Kernighan		1
1001	The C Programming Language	Ritchie		1
1001	The C Programming Language		С	2
1001	The C Programming Language		language	2
1001	The C Programming Language		programming	2

id title	name	subject	1	code
			-	
1001 The C Programming Language	Kernighan		ı	1
1001 The C Programming Language	Ritchie	I	-	1
1002 Computer Programming and Arch.	Eckhouse	1	- 1	1
1002 Computer Programming and Arch.	Levy	1	- 1	1
1003 The INGRES Papers	Stonebraker	1	1	1
1004 Database Systems	Ullman	I	1	1
1005 The Quiet American	Greene	I	-	1
1001 The C Programming Language	1	C	1	2
1001 The C Programming Language	1	language	-	2
1001 The C Programming Language	1	programming	1	2
1002 Computer Programming and Arch.	1	architecture	-	2
1002 Computer Programming and Arch.	1	assembler	1	2
1002 Computer Programming and Arch.	1	computer	1	2
1002 Computer Programming and Arch.	1	programming	1	2
1003 The INGRES Papers	I	Database	1	2
1003 The INGRES Papers	I	INGRES	1	2
1003 The INGRES Papers	I	computer	ı	2
1004 Database Systems	1	Database	ı	2
1004 Database Systems	1	management	ı	2
1005 The Quiet American	1	Vietnam	ı	2
			-	

If you create a report from such variable blocks of data, you must issue very specific instructions to Report-Writer about where and where not to place page breaks; otherwise, you find that some of your data has been incongruously parceled across two pages. In cases where you use Report-Writer to generate a report from a single, unjoined table, you would use a simple .need statement to establish proper page breaks. For more information, see the .need statement in Page Layout and Control Statements.

In this case, when generating a report from a joined table, you must use variable parameters to the .need statement to assure proper page breaks, as follows:

- 1. Change the selection statement in your .query section to a creation of a view in your .setup section.
- 2. Create two new tables in your .setup section based on that view which contain information about the number of authors or subjects per book.
- 3. Join the two new tables with the view in the .query section.
- 4. Alter the report specifications to use the new information for paging.

Note: The .setup and .cleanup sections can only use the SQL language. For the QUEL implementation of this example, see the QUEL Users Notes section below.

The reason for the three-step process is that SQL requires a special method for the calculation of *num_sub* and *num_auth*. In SQL, when you perform a set function on a set of data and group rows together, you cannot place in the select clause any column not also listed in the group by clause, except as an argument to a set function. When a select statement includes a group by clause, any columns listed in the select clause must be single-valued per group.

Here is the revised specification file for the report, with the new .setup, .cleanup and .query sections:

```
.NAME books2
.OUTPUT books2.out
. LONGREMARK
      The BOOKS2 report demonstrates using setup and cleanup to
      produce temporary tables.
. ENDREMARK
. SETUP
      create view tempbooks as
            select b.id, b.title, a.name, '' as subject, 1 as code
                  from book b, author a
                  where b.id = a.id
            union
            select b.id, b.title, '' as name, s.subject, 2 as code
                  from book b, subject s
where b.id = s.id;
      create table subj_count as
            select id, num_sub=count(subject)
            from tempbooks
            where code = 2
            group by id;
      create table auth_count as
            select id, num_auths=count(name)
            from tempbooks
            where code = 1
            group by id;
.CLEANUP
      drop tempbooks;
      drop subj_count;
      drop auth_count;
. QUERY
                  b.id, b.title, b.name, b.subject, b.code,
      select
                  a.num_auths, s.num_sub
      from tempbooks b, subj_count s, auth_count a
      where b.id = a.id and \overline{b}.id = s.id
.PAGELENGTH 20
.SORT title, code
.BREAK title, code /* title and code will be break columns */
.RIGHTMARGIN 80
                  /* it is important to set the right margin here */
. DECLARE
      lines in title = integer,
      authors_column = integer,
      subject column = integer,
      title string = varchar(8)
.HEADER report
        /* Initialize variables */
        .LET lines_in_title = 4
        .LET authors column = 5
        .LET subject_column = 20
.HEADER title
        /* Request the maximum number of lines needed to print all */
        /* book information on one page. */
        .IF num sub num auths .THEN
                .need num_sub + $lines_in_title
        .ELSE
                .need num_sub + $lines_in_title
        .ENDIF
        /* Reset margin and print title of book */
        /* start a block after printing the master info */
        .LEFTMARGIN 0
        .ULCHARACTER '='
        .UNDERLINE
        .PRINT title .NEWLINE
        .NOUNDERLINE
        .BLOCK
.HEADER code
        /* goto the top of the block each time code changes */
```

```
/* set the margin to the correct column for the code type */
       . TOP
       .ULCHARACTER '-'
       .IF code = 1 .THEN
.LEFTMARGIN $authors_column
       .LET title_string = 'Authors'
.ELSEIF code = 2 .THEN
               .LEFTMARGIN $subject column
                      .LET title_string = 'Subject'
       .ENDIF
       .UNDERLINE
       .PRINT title\_string .NEWLINE
       .NOUNDERLINE
.DETAIL
       /* test the value of code to see which column to print */
       .IF code = 1 .THEN
               .PRINT name .NEWLINE
       .ELSEIF code = 2 .THEN
               .PRINT subject .NEWLINE
       .ENDIF
.FOOTER title
       .ENDBLOCK /st end the block at the end of the master info st/
       .NEWLINE
Computer Programming and Arch.
Authors Subject
   Eckhousearchitecture
   Levyassembler
       Computer
       Programmind
Database Systems
  Authors Subject
   Ullman Database
      Management
The C Programming Language
Authors Subject
   -----
   Kernighan C
   Ritchie language
       Programming
The INGRES Papers
Authors Subject
   Stonebraker Database
       INGRES
       Computer
The Quiet American
=== ===========
   Authors Subject
   Greene Vietnam
```

QUEL User Notes

When you generate a report from a joined table, you must simulate the .need statement to assure proper page breaks. In QUEL, this involves making the same alterations to the report specifications file as shown in the text, but no additional tables need to be constructed.

Here is the query statement for the final report specification:

```
.NAME booksq
.OUTPUT booksq.out
. LONGREMARK
     The BOOKSQ report uses previously executed QUEL
     statements to create a temporary table, tempbooksq
     which is the join of books, authors and subject.
. ENDREMARK
.QUERY
     range of b is tempbooksq
     retrieve (b.all,
          num_auths=count(b.subject by b.id where
              b.code=1),
          num_sub=count(b.subject by b.id where b.code=2)
```

Appendix G: Troubleshooting Report-Writer

This appendix contains suggestions for troubleshooting if you have problems with your report specification in the following areas:

- Parameter substitution
- Queries
- Comments
- Default positioning values
- Performance

Parameter Substitution

Report-Writer parameter substitution problems commonly fall into the following areas:

- Failure to declare variables
- Failure to always precede variable references with a dollar sign (\$)
- Special characters in the variable string
- Embedded quotes in the variable string

Always declare all variables. Although Report-Writer recognizes any name preceded by a dollar sign (\$) as a variable, undeclared variables assume default types and characteristics that are often incompatible with their intended use. If a variable has not been declared, you can assign it a value only by using a command line parameter or by entering a value in response to a run-time prompt. You cannot specify a value for an undeclared variable with a .let statement. Also, unless the variable has been declared, attempting to pass a parameter with a null value to Report-Writer can produce incorrect results.

Always specify variable instances by including the leading dollar sign (\$). If the dollar sign is not present, and the variable has the same name as an identifier, such as a column or table name, Report-Writer assumes the variable is an identifier.

Check to make sure you have dereferenced any special characters in the variable's value string, such as embedded dollar sign (\$), SQL or QUEL wild cards, and so forth. Special characters in a variable's value string can cause unexpected results. They can be stripped and/or processed by your system's command line processor, or misinterpreted by Report-Writer. Some characters require multiple dereferencing, if the character is meaningful to both the native system's command line processor and Report-Writer.

Check to make sure you have correctly handled quotes in the variable string. Embedded quotes in the variable's value string present problems similar to those of special characters, and you must handle them in the same manner. Because of the potential confusion with delimited identifiers, we strongly advise you to always use single rather than double quotes to surround a variable value string. This greatly reduces the number of double quotes that must be escaped and standardizes the dereferencing of quotes, because string constants must always be delimited by single quotes.

To determine a variable's actual substituted value, use a test report such as this:

This report prints the value of the variable as it can be used by Report-Writer. Date and format template variables behave similarly to string constants. Numeric variables behave in a much simpler manner, because they cannot contain characters that can be confused with comment or string delimiters. The above example works equally well for parameters specified on the command line and variables for which the user is prompted.

An alternate method of determining if the parameter value string is the cause of the failure is to save the report specification with the sreport command. If this fails, then the problem lies in the existing syntax. If this succeeds, then the problem most likely results from the effects of substituting the parameter value string.

The .setup, .cleanup, and .query statements differ from other statements in that parameter substitution can occur within quoted strings. For example, suppose your query contained the following where clause:

```
WHERE object name = '$match name'
```

If you substitute the value "ABC" for \$match_name, the resulting where clause would be:

```
WHERE object_name='ABC'
```

Other statements, such as .println, treat a variable within a quoted string as a constant, as shown by the following results:

Statement	Printed Result
.PRINTLN '\$match_name'	\$match_name
.PRINTLN \$match_name	ABC

Queries

Problems related to query processing usually result from misstating the query or from syntax errors or ambiguities as a consequence of parameter substitution.

You can easily test the form and structure of the query by using a terminal monitor utility. Its diagnostics are sometimes more detailed than those of Report-Writer, particularly where syntax is concerned.

Note: If your Report-Writer code includes a .sort statement, add an order by clause to the select statement when testing the guery in a terminal monitor.

The single most useful means for determining query behavior is the II_EMBED_SET environment variable/logical. If you include the value printgry in its value string, execution of the report produces an "iiprtqry.log" file in the current directory. This log contains the text of all gueries sent to the database, as formulated after all variable substitutions have occurred. The actual report query appears towards the end of the log file (after all queries related to Report-Writer's access of the Ingres catalogs). For information on setting this environment variable, see the System Administrator Guide.

Comments

In general, you must format comments as follows:

- Avoid comment nesting
- Separate comment delimiters from the comment text and from each other by white space, as in the following example:

/* Comment Text /* Unavoidable nested comment */ */

Do not use comment delimiters without intervening white space:

/*CommentText/*Unavoidable nested comment*/*/

Within a .query statement, place comments before any from clause:

```
.QUERY

/*

** explanation of query

*/
SELECT col1

FROM table
```

• Avoid placing comments *after* the from clause in a .query statement:

```
SELECT col1
FROM table
/*
** explanation of query
*/
```

Reports created in RBF can contain RBF-generated comments after the from clause in the .query statement that are preserved and used by Report-Writer. Placing your comments *prior* to the from clause avoids any potential confusion with the RBF-generated comments, because Report-Writer removes all such comments before saving the report specification to the database. This also saves room in the database. Report-Writer assumes that comments occurring *after* the from clause are RBF-generated comments and saves them along with the report specification.

Default Print Positions

For other than very simple, default style reports, you must always specify values for .pagewidth, .pagelength, .leftmargin, and .rightmargin. If you do not specify these and other print positions explicitly, Report-Writer determines default positions from an analysis of your other report formatting statements. The results can or cannot compare favorably to your expectations. For an explanation of how Report-Writer determines default positioning values, see Automatic Determination of Default Settings in the chapter "Using Report-Writer."

Within a single line, you must specify .position and non-relative .tab statements in ascending order, from left to right:

```
.print 'A' .tab 10 .print 'B' .tab 20 .print 'C' .tab 50
```

Specifying these statements in a different order can cause Report-Writer to calculate an incorrect right margin, which could result in unexpected wrapping or truncation of text.

Formfeeds



UNIX

VMS

The default for formfeeds in Report-Writer reports is:

- .formfeeds 🔳
- .formfeeds 🍱
- .noformfeeds 🔳

The following Report-Writer statements and command line flags for the report command turn formfeeds on or off in your report, overriding the default behavior for Report-Writer in your environment:

- .formfeeds (.ffs, .ff) statement
- .noformfeeds (.noffs, .noff) statement
- +b | -b command line flags

Additionally, if formfeeds are enabled, you can specify no initial formfeed prior to the first page of your report with the following Report-Writer statement or report command line flag:

- .nofirstff statement
- -nofirstff command line flag

The following report command line flag overrides the .nofirstff statement if formfeeds are enabled, but has no effect otherwise:

-firstff

If you are having trouble with formfeeds, use the following tables to determine the combined result of the system default, the formfeed statements in your report specification, and the formfeed run time command line flags.

The following table indicates the resulting behavior when formfeeds are enabled or disabled:

	No Fla UNIX WinNT	g Set VMS	+b Flag	-b Flag
No formfeed statement specified	On	Off	On	Off
.formfeeds specified	On	On	On	Off
.noformfeeds specified	Off	Off	On	Off

The following table indicates whether an initial formfeed can occur when formfeeds are enabled:

	No Flag Set	-nofirstff	-firstff
No initial formfeed statement specified	Yes	No	Yes
.nofirstff specified	No	No	Yes

The following table indicates whether an initial formfeed can occur when formfeeds are disabled:

	No Flag Set	-nofirstff	-firstff
No initial formfeed statement specified	No	No	No
.nofirstff specified	No	No	No

Performance Problems

Approaches to solving performance problems are inherently implementationdependent. The following observations and recommendations are specific to the release of Report-Writer associated with this manual. They can have little or no effect on other releases, and can in some cases degrade performance.

Performance problems can be related to the manner in which the guery is stated, or to extensive expression usage and/or the use of functions in the body of the report specification.

Query Problems

The performance of the query itself can easily be tested using a terminal monitor utility, and must never differ from its performance within Report-Writer.

Conversion Functions

Conversion functions that occur as part of query processing can execute faster by up to two orders of magnitude compared to conversion function execution within the body of the report specification. Of the following two sample reports, the first report handles the conversion function most efficiently, assuming the function is being applied unconditionally to all rows retrieved.

Examples

```
Example 1
```

Example 2

```
.NAME query_convert
.QUERY
   SELECT uppercase(col1) AS uc_col1
        FROM test_table
.DETAIL
   .PRINT uc_col1
    .NL
.NAME rw_body_convert
. QUERY
   SELECT col1
        FROM test_table
.DETAIL
        .PRINT uppercase(col1)
```

Memory Usage

Report-Writer must allocate memory to control execution of each .print statement. Limiting the number of .print statements, as shown in Example 1, can result in significant run-time memory savings compared to Example 2.

Examples

Example 1

```
.NAME small_memory
.QUERY
    SELECT col1, col2, col3, col4
         FROM test_table
.DETAIL
        .PRINT col1, col2, col3, col4
```

Example 2

```
.NAME large_memory
.OUERY
   SELECT col1, col2, col3, col4
         FROM test_table
.DETAIL
        .PRINT col1
        .PRINT col2
        .PRINT col3
        .PRINT col4
        .NL
        .noformfeeds
```

Index

delimited identifiers, 10-10, 11-2, 12-2 dereferencing, 11-6 escaping from operating system, 17-26, 17-29 - (hyphen) parameter passing, 17-25, 17-26, G-1 .ulcharacter, 12-59 reserved words, 11-4 i flag (delobj command), 17-9 string variables and, 17-26 include flag (delobj command), 17-9 system-level commands, 17-19, 17-25 pattern matching, 5-11 underlining character, 12-59 # # (number sign) termcap descriptions, C-3 - (minus sign) arithmetic, 11-15 exponent, 11-6 justification with, 11-19, 12-27, 12-29, 12-32, 12-48, 12-50, 12-53, 18-10 numeric templates, 11-31, 18-13 \$ (dollar sign) subtraction, 11-15 numeric templates, 11-31, 18-13 unary, 11-6, 11-15 report formats, 10-14, 12-17 variable names, 11-10, 12-8, G-1 % ' (single quotation mark) constants and, 11-4, 11-5 % (percent sign) parameter passing, 17-25, G-1 delobj (command), 17-9 string literals and, 18-2 pattern match character, 5-10 string variables and, 17-25 () (parentheses) != (not equal to) numeric templates, 11-32, 18-14 comparison operator, 11-15 parameter passing, 17-25 system-level commands, 12-17, 12-20, 17-19, 17-25, 17-29, 17-30 variable names, 11-10 " (double quotation marks)

constants and, 11-4, 11-6

* (asterisk)	examples, 12-4 footers, 12-4 headers, 12-4 overview, 10-6, 10-13, 12-3		
centering, 11-19 comment indicator, 12-6 displayed in a field, 18-10 exponentiation, 11-15 integer data display, 18-10 justification with, 18-10 multiplication, 11-15	.center (Report-Writer statement) .ce abbreviation, 12-48 .cen abbreviation, 12-48 described, 12-48 examples, 12-49 overview, 10-7, 10-8, 12-26, 12-48		
numeric, 11-31 numeric templates, 18-13 wild card character, 11-16, 15-8	.cleanup (Report-Writer statement) autocommit, 12-6 described, 12-4 examples, 12-6, F-27 overview, 10-6, 10-13, 12-3		
(comma) numeric templates, 11-31, 18-13 value separator, 10-10, 12-2 variable names, 11-10	.data (Report-Writer statement) .dat abbreviation, 12-6 .table synonym, 12-6 .view synonym, 12-6 described, 10-6, 10-13, 12-3, 12-6 examples, 12-7 QUEL and, 12-19		
(period) decimal indicator, 11-6, 11-31, 18-5, 18- 13	.declare (Report-Writer statement) .let (Report-Writer statement) and, 12-20, 12-61 described, 12-7 examples, 12-9, F-14 overview, 10-6, 10-13, 12-3, 12-20 using with variables, 10-14		
numeric templates, 11-31, 18-13 owner qualification, 2-9 block (Report-Writer statement) .blk abbreviation, 12-37 .within/.endwithin sections, 12-46 described, 12-37 examples, 12-37, F-10 overview, 10-7, 10-8, 12-36 bottom (Report-Writer statement) .bot abbreviation, 12-38 described, 10-8, 12-36, 12-37, 12-38	delimid (Report-Writer statement) described, 12-10, 12-11 example, F-14 overview, 12-3 QUEL and, 12-11		
	.detail (Report-Writer statement) .det abbreviation, 12-33		
	described, 12-33 examples, F-5, F-14, F-20, F-22 overview, 10-7, 10-22, 12-33		
examples, 12-38	.else (clause), 12-60		
break (Report-Writer statement)	.elseif (clause), 12-60		
.brk abbreviation, 12-3 .sort (Report-Writer statement), 12-4, 12- 25	elseif (Report-Writer statement). example, F-15		
described, 12-3	.endblock (Report-Writer statement) .end block synonym, 12-37		

endblk abbreviation, 12-37 described, 12-37 examples, 12-37, F-10, F-22, F-24	overview, 10-9, 12-60 using with conditions, 10-20
overview, 10-8, 12-36	.include (Report-Writer statement) described, 12-12
.endif (Report-Writer statement), 12-60, F-15 .endremark (Report-Writer statement) .endrem abbreviation, 12-13	example, 12-13 modified files, 17-35 overview, 10-6, 10-14, 12-3
described, 12-13, 12-14 examples, 12-14 overview, 10-6, 12-3	.left (Report-Writer statement).lft abbreviation, 12-50.tab (Report-Writer statement) versus, 12-
.endwithin (Report-Writer statement) .end within synonym, 12-45 .endwi abbreviation, 12-45 described, 12-45	50 described, 12-50 example, 12-51 overview, 10-8, 12-48
examples, 12-46, F-10 overview, 10-8, 12-37	.leftmargin (Report-Writer statement) .lm abbreviation, 12-27
.footer (Report-Writer statement) .foot abbreviation, 12-34 .footing synonym, 12-34	described, 12-27 example, 12-28 overview, 10-7, 12-26
breaks, 12-4 described, 12-34 examples, 12-34, F-5, F-15, F-21 overview, 10-7, 12-33	.let (Report-Writer statement).declare (Report-Writer statement) and,12-61described, 12-61, 12-62
.format (Report-Writer statement) described, 12-39 examples, 12-40, F-5, F-14	example, 12-62 overview, 10-9, 12-60 using with variables, 10-21
overview, 10-7, 12-36 using with columns, 10-22	.lineend (Report-Writer statement) .lnend abbreviation, 12-51
.formfeeds (Report-Writer statement) .ff abbreviation, 12-26 .ffs abbreviation, 12-26	described, 12-51 example, 12-51 overview, 10-8, 12-48
described, 12-26 examples, 12-27, F-14 overview, 10-7, 12-26 troubleshooting, G-3, G-4 using with pagination, 10-16	.linestart (Report-Writer statement) .linebegin synonym, 12-51 .lnstart abbreviation, 12-51 described, 12-51 examples, 12-52
.header (Report-Writer statement) .head abbreviation, 12-35 .heading synonym, 12-35 described, 12-34 example, 12-35, F-5, F-14, F-15, F-20, F- 21, F-22 overview, 10-7, 12-33	overview, 10-8, 12-48 .longremark (Report-Writer statement) .lrem abbreviation, 12-13 described, 12-13 example, 12-14, F-14 overview, 10-6, 10-14, 12-3 .name (Report-Writer statement)
.if (Report-Writer statement) described, 12-60 example, 12-61, F-15	.nam abbreviation, 12-14 described, 12-14 example, 12-14

overview, 10-6, 10-13, 12-3	described, 12-30
.need (Report-Writer statement) .ne abbreviation, 12-28	example, 12-31, F-14 overview, 10-7, 10-16, 12-26
described, 12-28 example, 12-29, F-32 overview, 10-7, 12-26 using with pagination, 10-16 .newline (Report-Writer statement)	.pagewidth (Report-Writer statement) defaults, 10-21 described, 12-31 example, 12-32 overview, 10-7, 10-16, 12-26
nl abbreviation, 12-52 default limit, 12-37 described, 12-52 example, 12-52, F-10, F-22, F-24 overview, 10-8, 12-48	.position (Report-Writer statement) .pos abbreviation, 12-40 described, 12-40 example, 12-41 overview, 10-7, 10-8, 10-18, 12-36
.newpage (Report-Writer statement) .np abbreviation, 12-29 described, 12-29	.print (Report-Writer statement) described, 10-8, 12-56, 12-57 example, 12-58
example, 12-30, F-14, F-15 overview, 10-7, 12-26 using with pagination, 10-16	.println (Report-Writer statement) .pln abbreviation, 12-57 .prln abbreviation, 12-57
.nofirstff (Report-Writer statement) described, 12-30 troubleshooting, G-3, G-4	described, 12-57 example, 12-58, F-10
.noformfeeds (Report-Writer statement) .noff abbreviation, 12-26 .noffs abbreviation, 12-26 described, 12-26 example, 12-27 overview, 10-7, 12-26	.query (Report-Writer statement) .quel synonym, 12-15 column breaks, 12-4 described, 12-15 example, 12-18, F-5 overview, 10-6, 10-13, 12-3 QUEL queries, 12-19
troubleshooting, G-3, G-4 .nounderline (Report-Writer statement) .nou abbreviation, 12-59 described, 12-59 example, 12-60	.right (Report-Writer statement) .rt abbreviation, 12-53 described, 12-53 example, 12-54, F-6 overview, 10-7, 10-8, 12-26, 12-36, 12-48
overview, 10-9, 12-56 .nullstring (Report-Writer statement) .nullstr abbreviation, 12-56 described, 12-56	rightmargin (Report-Writer statement) described, 12-32 example, 12-33 overview, 10-7, 12-26
examples, 12-57 overview, 10-8, 12-56 .output (Report-Writer statement)	.rw filename extension .include (Report-Writer statement), 12-12 sreport (command), 17-35
described, 12-14 example, 12-15 overview, 10-6, 10-13, 12-3	setup (Report-Writer statement) described, 12-22 example, 12-23, F-27
.pagelength (Report-Writer statement) .pl abbreviation, 12-30	overview, 10-6, 10-13, 12-3 .shortremark (Report-Writer statement)

.srem abbreviation, 12-24	/
described, 12-24 example, 12-24	
overview, 10-6, 10-14, 12-3 .sort (Report-Writer statement) .srt abbreviation, 12-25 described, 12-25 example, 12-26, F-5, F-14 overview, 10-6, 10-13, 12-3	/ (slash) comment indicator (with asterisk), 10-6, 12-3, 12-6, B-28 server type syntax, 2-7
	/* (comment indicator) report specification, 10-14
.tab (Report-Writer statement) .left (Report-Writer statement) versus, 12- 50	<u>:</u>
described, 12-54 example, 12-55 overview, 10-7, 10-8, 10-22, 12-36, 12-48	: (colon) variable names, 11-10
.tformat (Report-Writer statement) described, 12-41 example, 12-42, F-14	: (colon) report cleanup and setup sections, 12-5
overview, 10-7, 12-36	: (colon) report cleanup and setup sections, 12-22
.then (clause), 12-60	: (colon)
.top (Report-Writer statement) .tp abbreviation, 12-43	.sort (Report-Writer statement), 12-25
described, 12-43 examples, 12-43, F-10	: (colon) .let (Report-Writer statement), 12-61
overview, 10-8, 12-36, 12-37	:= (assignment operator), 12-61
.ulcharacter (Report-Writer statement)	
ulc abbreviation, 12-59. described, 12-59	;
example, 12-59 overview, 10-9, 12-56	
.underline (Report-Writer statement) .u abbreviation, 12-59	; (semicolon) report cleanup and setup sections, 12-5, 12-22
.ul abbreviation, 12-59 described, 12-59	statement separator, 12-5, 12-22
example, 12-60 overview, 10-9, 12-56	?
.width (Report-Writer statement)	
described, 12-44 example, 12-45 overview, 10-7, 10-8, 10-18, 12-36	? (question mark) wild card character, 11-16, 15-8
.within (Report-Writer statement) .wi abbreviation, 12-45 described, 12-45	<u>I</u>
examples, 12-46, F-10 overview, 10-8, 12-37	[] (brackets), 1-3

[] (square brackets)	+
comparisons in validation checks, 15-10	
delobj (command), 17-9	(plus sign)
numeric templates, 11-32, 18-14 pattern matching, 5-10, 11-16, 15-8	+ (plus sign) addition, 11-15
pattern matering, 5-10, 11-10, 15-6	arithmetic, 11-15
	exponent, 11-6
\	justification with, 11-19, 12-27, 12-29, 12-
	32, 12-48, 12-50, 12-53, 18-10
	numeric templates, 11-31, 18-13
\ (backslash)	unary, 11-6, 11-15
dereference character, 11-6, 17-29 numeric templates, 11-32, 18-12, 18-14	-+b flag
parameter passing, 17-26	report (command), 17-24, G-3, G-4
string continuation character, C-2	
string literals, 11-5, 11-6	<
text match indicator, 5-10, 12-17	<u> </u>
time interval templates, 11-26	
wild card characters, 5-10	< (less than)
	comparison operator, 11-15
	< > (angle brackets)
	numeric templates, 11-32, 18-14
(underscore)	<= (less than or equal to)
_ (underscore) .ulcharacter, 12-59	comparison operator, 11-15
delobj (command), 17-9	
pattern matching, 5-10	_
reports, 8-27	=
underlining character, 12-60	
_date (function), 11-17	= (equal to)
_time (function), 11-17	comparison operator, 11-15
	= (equals sign)
	assignment operator, 12-61
{	QBF blank retrieves, 5-13
{ } (braces), 1-3	
() (braces), i s	
	> (greater than)
	comparison operator, 11-15
(vertical bar), 1-3	>= (greater than or equal to)
date templates, 11-25	comparison operator, 11-15
separators C-2	

5	defined, 8-11		
-5 flag report (command), 17-23	moving, 8-24 non-unique, 11-11, 11-13 reports, 10-21 Selecting an Aggregate pop-up, 8-14 simple, 11-11, 11-13 syntax, 11-12, 11-36 unique, 8-19, 11-11 views and, 3-2		
-6 flag report (command), 12-7, 12-25, 17-24	Aggregate operation Create submenu, 8-8		
A	aligning RBF report components, 8-6		
	All (clause), 12-46		
ABF	am/pm (with date data type), 18-4		
abf (command), E-1 calling, E-1 starting, 2-6 abs (function), 11-17	anchor point boxes, 14-7 rotating, 14-7 vertical lines, 14-7		
	and (logical operator), 5-7, 11-16		
absolute dates/times, 11-7, 18-15, 18-19 AddDetail operation	ANSI/ISO Entry SQL-92 compliant databases regular identifiers, 2-17		
Update frame, 5-19 adding blank lines to forms, 14-4 boxes and lines to forms, 14-5 columns to reports, 8-11	any (aggregate function) reports, 8-12		
	append Append operation, 5-1 data, 5-1		
columns to tables, 3-11 components to reports, 8-8 duplicate fields to a form, 14-18	Append operation QBF Execution Phase Frame, 5-1		
headers and footers to reports, 8-9 records in QBF, 5-1 report sections, 8-9 simple fields to forms, 14-7 table fields to forms, 14-12, 14-16 trim to forms, 14-3 trim to reports, 8-10	appending Append operation, 5-1 in QBF, 5-1 QBF, 4-6 with table- and simple-field formats, 5-1 applications		
aggregate functions average (avg), 11-12	Ingres Menu operation, 2-6 mapping customized, B-8, B-19		
breaks, 11-11, 11-13 count (cnt), 11-12 Create an Aggregate pop-up, 8-13	archiving report definitions, 8-32		
cumulative, 11-11 Cumulative Aggregation pop-up, 8-14 data selection, 11-11	arithmetic dates, 11-15 expressions, 11-34 operations, 11-15		

operators, 11-15 overflow/underflow, 17-13 arrow keys mapping, B-1 scrolling with, 15-6 asc (keyword), 12-25	numeric templates, 11-32, 18-14 owner qualification, 2-9 preceding delimited identifiers, 11-4 separating Report-Writer statements, 10- 10, 12-2 system-level commands, 12-17, 12-20, 17-19, 17-25, 17-29, 17-30
ascending sort sequence	blinking, C-12
retrieving information, 5-14 assignment (statement) overview, 10-21	Blinking attribute Attributes for Field frame, 15-3 Box Attributes frame, 14-4
atan (function), 11-17	block style reports, 10-5, 10-18
attributes Color, C-9 derived fields, 15-12 editing, 15-1, 15-6 field, 2-11, 14-11, 15-6 form, 15-1 video, C-8	blocks .block/.endblock statements, 12-37 .top (Report-Writer statement), 12-43 .top/.bottom statements, 12-38 block style report, 7-8 formatting, 12-37 printing, 12-37
Attributes operation	bold, C-12
VIFRED, 14-8, 14-11 autocommit, 12-5, 12-22, 12-23	bold typeface, 1-3 menu operations, 1-2
automatic joins, 6-6 average (aggregate function), 11-12 unique, 8-12 using in reports, 8-12	boolean .if (Report-Writer statement), 12-61 break, 11-18 expressions, 11-16, 11-36 is null (operator), 11-16 not (operator), 11-16
В	not null (operator), 11-16 or (operator), 11-16
Blank operation defined, 2-13 Retrieve frame, 5-4 Table Create frame, 3-4 Terminal Monitor frame, 16-3, 16-6 Update frame, 5-18	Bottom (FRS command) Terminal Monitor frame, 16-5
	Bottom operation predefined menu option, B-24
	Box Field attribute Attributes for Field frame, 15-3
blanks blank form creation, 13-4 Blank operation, 5-18 cf format, 11-22 cj format, 11-22 comparisons containing, 18-3 flag separator, E-1 inserting, 11-33	Box/Line operation anchor point, 14-7 attribute boxes vs, 14-5 attributes, 14-4 compared to keystroke lines, 14-5 creating, 14-5 Edit operation, 14-6 enhancing, 14-6

expanding the box, 14-6	C	
horizontal lines, 14-6 intersections, 14-6 plus sign, 14-5 rotating anchor point, 14-7 underscore character, 14-6 using, 14-6 vertical lines, 14-6 boxes boxing characters, 14-5 commands, C-12	c (data type) conversion function, 11-17 default report column format, 11-19 C (data type) data types for report columns, 11-8 described, 18-1, 18-2, 18-3 storage forma, 18-6 storage format, D-1	
break (function), 11-18	c (function), 11-17	
break Columns pop-up, 8-4 BreakOptions operation, 8-21	C format, 11-21 call (statement) restrictions on parameters, E-1	
breaks .header (Report-Writer statement), 12-35 .need (Report-Writer statement), 12-28 .sort (Report-Writer statement), 12-25 actions, 10-2 aggregate function, 11-11, 11-13 Break Columns pop-up, 8-4 break header, 10-11 defined, 8-21, 10-2 detail, 10-3, 10-11 formatted values and, 12-39 headers and footers, 7-10, 8-10 indented reports, 7-8, 8-4 page, 12-29, F-31 reports, 7-5 sort columns, 8-10 start-of-report, 10-3 tabular reports, 7-7	calling call (statement), E-1 IQUEL, 17-10 ISQL, 17-11 operating system, E-4 QBF, 4-2, 4-6, 17-14 RBF, 17-16 VIFRED, 13-2, 17-36 Cancel operation Create a Table frame, 3-4 defined, 2-13 Form Layout frame, 14-16 Join Specification frame, 6-12 predefined menu option, B-25 Save Report frame, 8-32 case character strings, 18-2	
bright, C-12	names, 2-17 system-level commands, 17-1	
Brightness Change attribute Attributes for Field frame, 15-3 Box Attributes frame, 14-4 buffers updates, 5-21 byte (data type), 11-9, 18-2, D-2	uppercase (function), 11-18 catalog frames empty, 17-10, 17-15, 17-18, 17-36 Forms Catalog Frame, 13-3 JoinDefs, 6-8 QBF, 4-3, 4-6 VIFRED, 13-2	
byte varying (data type), 11-9, 18-2, D-2	catalogdb (command) listing databases, 2-2	
	catalogs (system), 2-2	

Center operation Move submenu, 8-24	colors (in graphs) termcap descriptions, C-15
centering .center (Report-Writer statement), 12-48 reports, 11-19 text, 10-8, 12-48	Column operation Create submenu, 8-8 Move submenu, 8-25
ChangeDisplay operation, 6-16	column style reports, 10-5
	ColumnOptions frame, 8-18
char (data type) conversion function, 11-17 data types for report columns, 11-8	ColumnOptions operation Report Layout frame, 8-7
default report column format, 11-19 described, 18-1, 18-2 storage format, D-1	columns (in reports) breaks, 11-18, 12-3, 12-25 Create a Column pop-up, 8-11
char (function), 11-17	creating, 8-11 data types, 11-8
character data storage format, 18-6	defaults, 10-22, 11-21 deleting, 8-16
character fields display function, 15-6	delimited identifiers, 11-2, 11-3, 11-8, 12- 10 editing, 8-17
character strings C format, 11-21 T format, 11-34 variables, 11-10	format, 10-7, 12-36 headings, 8-16, 12-37 justification, 12-49, 12-50, 12-54 line advancing, 12-52
charextract (function), 11-17	margins, 12-45 moving, 8-24
Choose a Report Style pop-up, 9-3	position_number variable, 11-10 positioning, 10-18, 10-22, 12-40
clanks B format, 11-21 inserting, 11-21	print formats, 12-41 printing, 12-57 referencing, 11-8, 12-16, 12-19 sorting, 8-21, 10-15
clear (FRS command), B-20	temporary formats, 10-19, 12-39, 12-41
clearing screen, 2-13, 16-6	w_column variable, 11-10, 12-46 w_name variable, 11-10, 12-46 width, 10-23, 12-40, 12-44, 12-45
clearrest (FRS command), B-20	columns (in tables)
coercibility data types, 6-3	adding, 3-11 copying specifications for, 3-8
color attribute, C-9	defaults, 3-6, 3-10 defined, 3-1
Color attribute Box Attributes frame, 14-4	delinied, 3-1 deleting, 3-11, 6-16 delimited identifiers, 2-17
colors (in fields), 15-6	hiding, 6-16
colors (in forms) termcap descriptions, C-15	join, 6-2, 6-11, 6-12 key numbers, 3-5, C-5 maximum number, 3-2 moving, 3-8

naming, 3-2, 3-5, 14-15 protecting, 6-13 unique, 3-8 unique keys, 3-8 commands system-level, 17-1	.nullstring (Report-Writer statement), 12- 56 date, 11-7 numeric, 11-6 reports, 11-5 string, 11-4, 11-5
comment blocks archived reports, 8-33	control characters Q0 format, 11-33
comments debugging, G-2 delimiters, 10-14, G-2 mapping files, B-4, B-11, B-28 nesting, 12-6, G-2 report specification, 10-6, 12-3, 12-6	control keys mapping, B-20
	conventions query languages, 1-2 syntax, 1-3, 17-1 system-level commands, 1-2, 17-1
comparison operators and, 5-7	conversion functions, 11-35, G-4
defined, 11-15 list, 11-15 QBF, 5-6 validation check, 15-8	copyform (command) described, 17-4 duplicating forms, 13-4
compform (command), 17-3	copying
compiled forms compform (command), 17-3 linking, 17-3 VIFRED, 13-19	column specifications in tables, 3-8 copyform (command), 13-19, 17-3, 17-4 copyrep (command), 17-7 forms, 13-4, 13-19, 17-4 reports, 17-7, 17-35
compiling Embedded SQL, 13-19 operations, 13-19	sreport (command), 17-35 copyrep (command) described, 17-7
Complete operation	examples, 17-8
Terminal Monitor frame, 16-3, 16-4, 16-6	correlation names, 6-10, 11-2, 11-3
computation aggregation, 11-11 breaks, 11-13	cos (function), 11-17
	count (aggregate function), 8-12, 11-12
date expressions, 11-15	CR abbreviation for credit, 11-32, 18-14
exponential notation, 11-6 reports, 11-15	Create a Column pop-up, 8-11
concat (function), 11-17	create an Aggregate pop-up, 8-13
conditional statements .if (Report-Writer statement), 12-60 boolean/logical functions, 11-16 overview, 10-20, 12-60, 12-61	create index (statement) described, 3-3
	Create operation Form Layout frame, 13-8, 14-2
constants .declare (Report-Writer statement), 12-7 .let (Report-Writer statement), 12-61	forms, 13-4 Forms Catalog frame, 13-3, 13-4 JoinDefs Catalog frame, 6-9, 6-14

Report Catalog frame, 7-2 Report Layout frame, 8-7 scrollable fields, 15-6 Table Utility frame, 3-3, 3-4 VIFRED, 14-3 VIFRED forms components, 14-3, 14-8	appending, 5-1 constants, 11-5 defining, 16-2 deleting, 5-18, 5-20 display, 5-15 display format symbols, 14-12 display formats, 18-6 editing, 5-18 entry errors, 5-2 expressions, 11-5 formatting, 11-18 manipulating, 16-2 retrieving, 5-3 runtime selection, 8-20, 9-2 sources for reports, 7-5 updating, 5-18
createdb (command), 2-3 creating columns in reports, 8-11 creating a Report pop-up, 8-1 databases, 2-3 forms, 13-18 report sections, 8-9 reports, 8-4, 10-2 tables, 3-4	
Creating a Report Layout Section pop-up, 8-9	data dictionary, 2-2
creating a Report pop-up, 8-1 cumulative (keyword) aggregate functions, 11-12 cum abbreviation, 11-12 cumulative Aggregation pop-up, 8-14 currency formats, 18-5 current_date (report variable), 11-10 current_time (report variable), 11-10 current_time (report variable), 11-10 cursor activating on terminals, C-16 moving, 2-15, C-8, C-16	data display format case, 18-8 data types vs, 18-6 date templates, 18-11 dates, 18-11 f flag, 18-10 floating point numbers, 18-11 incompatible data types, 14-12 integers, 18-10 j flag, 18-10 j ustification of character data, 18-10 numeric templates, 18-11 scrollable fields, 15-6 symbols, 18-6 syntax summary, 11-36 data integrity
D	unique keys, 3-8
d display format parameter numeric print format E, 11-27 numeric print format F, 11-28 numeric print format G, 11-28 numeric print format N, 11-30 -d flag report (command), 12-5, 12-23, 17-23 D format, 11-23 data	data types data types abstract, 11-8 byte, 11-9, 18-2, D-2 byte varying, 11-9, 18-2 c, 11-8, 11-19 c (data type), 18-1, 18-2, 18-3, D-1 changing in fields, 15-6 char, 11-8, 11-19, 18-1, 18-2, 18-3, D-1 character, 11-8, 18-1, 18-2, 18-6 coercible, 6-3 compatibility, 12-62
.query, 12-15	conversion, 12-62

date, 11-7, 11-8, 11-20, 18-1, 18-2, 18-4, 18-7, 18-11, D-2 decimal, 11-7, 11-8, 11-20, 18-2, 18-5, D-2 described, 18-1 display formats vs, 14-1, 14-16, 18-6 displaying formats, 14-12, 18-6 entering, 3-5 float, 11-7, 11-8, 11-20, 18-5 float4, 11-8, 11-20, 18-1, D-1 float8, 11-8, 11-20, 18-2, D-1 floating point, 18-5, 18-6, 18-11, D-1 integer1, 11-8, 11-20, 18-2, D-2	destroying, 2-3 distributed access, 2-1, 2-6, 2-7 Enterprise Access products, 2-1, 2-6, 2-7 Ingres Star database access, 2-6 local access, 2-1, 2-6 location, 2-1, 2-6 maintaining, 2-3 relational, 6-1 remote access, 2-1, 2-6, 2-7 restoring, 2-3 Star access, 2-1 Star Server access, 2-7 syntax for access, 2-6 system catalogs, 2-2
integer2, 11-8, 11-20, 18-2, D-2 integer4, 11-9, 11-20, 18-2, D-2 integrity, 5-21	date (data type), 11-8, 11-20, 18-1, 18-2, 18-4, 18-7, D-2
long byte, 11-9, 18-2, D-2	date (function), 11-17, 18-4
long varchar, 11-9, 12-7, 12-19, 17-19, 18-2, D-2 long varying, D-2	date format, 11-23 conversion function, 11-17, 18-4
money, 11-8, 11-20, 18-1, 18-2, 18-5, 18-	date_gmt (function), 11-17
6, 18-10, D-2 numeric, 11-6, 11-8, 18-1	date_part (function), 11-17
OpenSQL, D-1	date_trunc (function), 11-17
precision, 18-1 QUEL, 11-9, 11-21, D-1 reports, 11-5, 11-8, 11-9, 18-6 smallint, 18-2 SQL, 18-1, D-1 string, 11-5 text, 11-8, 11-20, 18-1, 18-2, 18-3, 18-6, 18-10, D-1 unsupported, 12-7, 12-16, 12-19, 17-19 user-defined type (UDT), 18-2, D-2 varchar, 11-8, 11-20, 18-1, 18-2, 18-3, D-1	dates absolute, 11-7, 18-14, 18-15, 18-19 arithmetic operations, 11-15 constants, 11-7 converting, 18-4 current, 15-7 current_date variable, 11-10 current_day variable, 11-10 data type, 18-1, 18-2, 18-4, 18-7, 18-11, 18-14 date (function), 11-17 date_gmt (function), 11-17
data windows defined, 2-10 specifying size, 18-9	date_part (function), 11-17 date_trunc (function), 11-17 display formats, 18-11
database administrator (DBA), 2-3	formats, 11-23, 18-14 functions, 11-36
databases _SQL-92 compliant, 11-1 accessing, 2-6 accessing non-Ingres, 2-1, 2-6, 2-7 ANSI/ISO Entry SQL-92 compliant, 2-17 creating, 2-3 defined, 2-2	interval (function), 11-25, 18-4 interval function, 18-19 reports, 7-6, 8-15, 8-28 storing, 11-7 templates, 11-23, 18-15, 18-16 DB abbreviation for debit, 11-32, 18-14

Dbname parameter, 2-7, 17-2	VIFRED, 15-7
Ddtes	Define term_ingres, A-2
intervals, 11-7 deadlock causes, 5-3, 5-21	Delete operation Forms Layout frame, 13-8, 14-2, 14-19 report components, 8-7, 8-16
debugging queries, G-2 reports, G-1	Report Layout frame, 8-7 Table Create frame, 3-4 Table Field menu, 14-14
decimal (data type), 11-7, 11-8, 11-20, 18-2,	deletechar (FRS command), B-20
18-5, D-2	DeleteLine operation Terminal Monitor frame, 16-3
decimals E format, 11-27 F format, 11-27 G format, 11-28 N format, 11-29 Numeric templates, 11-30 printing standard notation, 11-27, 11-28, 11-30	deleting columns, 3-11, 8-16 Delete operation, 6-14, 6-17 delobj (command), 17-8 Edit Report Layout pop-up, 8-15 report components, 8-15 report sections, 8-15 reports, 7-2, 17-8
declared variables runtime, 12-8	delimited identifiers
Declared Variables frame, 9-2	command parameters, 17-1 distinguishing from format templates, 11-4
default forms, 13-4	distinguishing from strings, 11-4, 12-16
default report format block style, 10-5	enabling, 12-10, 12-11 object ownership, 11-3 QUEL and, 11-2, 12-11
default values Field attribute, 15-5	reserved words, 11-4 special characters in, 2-17
DefaultOrder operation, 14-19, 14-20	using, 2-17, 11-8
defaults arithmetic exceptions, 17-13 autocommit, 12-5, 12-22 column, 3-6, 3-10, 10-22 column format, 10-22	delimiters comment, 10-14 delimited identifiers, 10-10, 11-2, 12-2 Report-Writer statement, 10-10, 12-2 string literal, 11-5
column position, 10-18, 10-22 column width, 10-23 formats, 10-21	delobj (command) description, 17-8 examples, 17-9
joins, 6-6 mapping files, B-12 margins, 10-22, 11-20	dereferencing backslash (\), 11-6
menu item mapping, B-23 pagewidth, 10-21	derivation formulas described, 15-5, 15-13
print format, 11-19, 12-39, 12-40, 12-41 reports, 10-5, 10-7, 10-21, 11-19, 12-36	Derived attribute, 15-5
rules, 6-15 terminal-type mapping, B-14	derived fields behavior, 15-12

RBF, 8-17
VIFRED, 14-8
displaying reports, 17-31
DisplayOnly scrollable fields, 15-7
distributed databases, 2-6 accessing, 2-1, 2-7
dow (function), 11-17
downline (FRS command), B-20
duplicate (FRS command), B-20
Duplicate operation Creating a Form frame, 13-4, 13-5, 14-18
duplicates -6 flag, 17-24 fields, 14-18 removing, 12-7
suppressing in reports, 8-21 suppressing in tables, 3-8 table rows, 12-7
E format exponential notation, 11-6 overview, 11-27 Edit operation described, 8-16, 8-17 Form Layout frame, 13-8, 14-2, 14-16 Forms Catalog frame, 13-3 JoinDefs Catalog frame, 6-9 Order frame, 14-19 Report Catalog frame, 7-3 Report Layout frame, 8-7 Terminal Monitor frame, 16-3 VIFRED forms components, 14-3, 14-4, 14-7 EditAttr operation Table Field menu, 14-14, 14-17, 15-1
E format exponential notation, 11-6 overview, 11-27 Edit operation described, 8-16, 8-17 Form Layout frame, 13-8, 14-2, 14-16 Forms Catalog frame, 13-3 JoinDefs Catalog frame, 6-9 Order frame, 14-19 Report Catalog frame, 7-3 Report Layout frame, 8-7 Terminal Monitor frame, 16-3 VIFRED forms components, 14-3, 14-4, 14-7 EditAttr operation

attributes, 15-1 canceling edits, 8-29 columns in reports, 8-17 Edit operation, 8-16	Examine operation obtaining information on tables, 3-9 system catalogs, 2-2 Table Utility frame, 3-3, 3-9
forms, 13-1, 13-18, 14-3, 14-4 insert and overstrike modes, 2-15 JoinDefs, 6-18	examining tables, 3-9
report formats, 8-16 table fields, 14-16	examples reports, F-1
trim, 8-16, 14-3	exp (function), 11-17
Editor (FRS command), B-20 embedded SQL compiling forms, 17-3	Expand operation described, 13-14 Report Margin submenu operation, 8-26 VIFRED, 13-14
End operation defined, 2-13 output frame, 16-6 predefined menu option, B-24	expert mode pattern matching, 13-2
Enter key, 2-14	exponential notation, 11-6, 11-15, 18-5, 18-6, 18-11
Enterprise Access products accessing databases, 2-1, 2-7, 17-2	G format, 11-28 N format, 11-30
product differences, 1-2 environment variables/logicals II_DATE_FORMAT, 18-15 II_EMBED_SET, G-2 II_NULL_STRING, 12-57 II_NUMERIC_LITERAL, 11-7, 18-5 II_SCROLL_MSG, 5-16 ING_PRINT, 17-33 setting, 2-1 TERM_INGRES, A-1 Equijoin, 6-3 error messages checking, 2-16 Save operation, 5-21 suppressing, 12-6 Terminal Monitor, 16-6	expressions abstract, 11-8 arithmetic, 11-34 boolean, 11-36 character, 11-8 columns, 11-8 conditional, 11-15 data type resolution, 11-35 date, 11-36 format specifications, 11-18 numeric, 11-8, 11-35 printing in reports, 12-57 QUEL conversion functions, 11-35 report variables, 11-34 string, 11-35 string constants, 11-5 types of data, 11-5
errors -5 flag, 17-23	F
-d flag, 12-5, 12-23, 17-23 handling, 12-6, 12-23 report error log, 9-1 runtime processing, 12-5, 12-6, 12-23	-f flag copyrep (command), 17-8 report (command), 12-15
escape sequences Q0 format, 11-33	-f flag report (command), 17-21

F format, 11-27	components, 14-7
Field Attribute menu, 15-3	creating, 14-7
	data display format, 14-9
field attributes	data window, 2-10, 14-9, 14-11, 14-12
Attributes frame, 15-1	default QBFName, 14-7
blinking, 15-3	default values, 15-5, 15-7
box, 15-3	derived, 15-12
Box/Line vs, 15-4	described, 2-10, 14-1
brightness change, 15-3	duplicate, 14-18
color, 15-5, 15-6	editing, 14-11
columns in table fields, 15-1	enclosing in boxes, 15-3
data type, 15-5	form components, 14-1
default value, 15-5	internal names, 2-11, 14-8, 15-6
defaults, 15-1	JoinDef displays, 6-6
derivation formula, 15-5	justification, 14-10
derived field, 15-5	mandatory, 15-3
display only, 15-3	names vs titles, 14-8
finishing, 15-2	order, 14-19
force lower case, 15-3	prioritizing in retrievals, 5-13
force upper case, 15-3	scrollable, 15-6
inputmasking, 15-4	simple, 2-10, 14-7
internal field name, 15-5	simple in VIFRED, 14-11
internal name, 15-6	tabbing order, 14-19, 14-20
invisible, 15-3	table fields, 2-10, 14-13
keep previous value, 15-3	titles, 2-11, 14-8
list, 15-3, 15-4	validation, 2-18
no auto tab, 15-3	width, 18-9
no echo, 15-3	File operation
now value, 15-7	input frame, 16-3
nullable, 15-5	Terminal Monitor input frame, 16-4
nullable data types, 15-6	Terminal Monitor output frame, 16-6
query only, 15-3	· ·
reverse video, 15-3	filename extensions
scroll size, 15-5	.rw, 12-12
scrollable, 15-5	FilePartial operation
setting, 15-1	filing reports, 9-5, 17-33
setting default values, 15-7	
simple fields, 15-1	files
table fields, 15-1	including external, 12-12
today value, 15-7	Report-Writer, 17-7
underline, 15-3	Find operation, B-24
validation check, 15-5	predefined menu option, B-24
validation error message, 15-5	·
Field operation	-firstff flag
VIFRED, 14-8	report (command), G-3, G-4
	flags parameter
fields	system-level commands, 17-1
attributes, 2-11, 14-11	•
blank, 5-13	float (data type)
changing display, 15-6	default column format, 11-20

described, 18-5 numeric constants, 11-7, 11-8 precision, 11-20, 18-1	column, 10-19, 10-20, 10-22, 11-20, 12-39, 12-40, 12-41 defaults, 10-21, 11-19
float4 (data type), 11-8, 11-20, 18-1	display, 14-9, 14-16 expressions, 11-18
float4 (function), 11-17	Format operation, 14-22
float8 (data type), 11-8, 11-20, 18-2, D-1	overriding, 12-39, 12-41 report data, 11-18
float8 (function), 11-17	report date and time stamp, 8-28
floating point +- flag (arithmetic), 17-24 -5 flag, 17-23 arithmetic, 17-23 data type, 18-5, 18-6, 18-11, D-1 display format, 11-27, 18-6, 18-11 footers	report page numbers, 8-28 FormAttr operation attributes, 13-9 Form Layout frame, 13-9, 14-2 pop-up location, 13-10 pop-up position, 13-10 pop-up vs fullscreen, 13-9, 13-10
.header (Report-Writer statement), 12-35 break, 10-3, 10-11 columns, 10-3 deleting, 8-15 reports, 7-9, 10-3	forms assigning QBFNames, 13-21 centering components, 14-21 compiling definitions as C source files, 13- 19, 17-3
Force Lower Case attribute, 15-3	components, 14-1 copying, 13-4, 13-19, 17-4
Force Upper Case attribute, 15-3	creating, 13-18
form feed (command), 8-28	creating blank, 13-4 creating from existing forms, 13-4
Form Layout frame, 14-1	creating from multiple tables, 13-6
format operation, 14-22 format specifications B format (blank), 11-21 C format (character), 11-21 D format (date), 11-23 E format (numeric), 11-27 F format (numeric), 11-27 G format (numeric), 11-28 N format (numeric), 11-29 numeric templates, 11-30 Q0 format (control characters), 11-33 T format (character string), 11-34 format templates distinguishing from delimited identifiers, 11-4	default, 4-7, 13-4 default forms, 13-5 deleting, 13-18 deleting lines/components, 14-19 described, 2-9 display mode, 13-6 editing, 13-1, 13-18 fields, 2-10, 14-1 justifying components, 14-21 linking to JoinDefs, 13-20 linking to tables, 13-20 moving components, 14-21, 14-21 moving parts of a field, 14-21 ownership, 13-4, 17-5 pop-up display, 13-10 printing, 13-19, 17-13 QBF, 4-5
formats .format (Report-Writer statement), 10-22, 12-39, 12-40 .tformat (Report-Writer statement), 12-41 block, 12-37	renaming, 13-3, 13-20 saving, 13-17 trim, 2-10, 14-1 forms (Ingres Menu operation), 2-5

Forms Catalog frame, 13-4 Forms in Database pop-up, 14-18 frames described, 2-9 reports, 8-5 from (clause), 12-15 FRS	JoinDef Catalog frame, 6-9 JoinDef Definition frame, 6-9, 6-17 predefined menu option, B-24 Report Catalog frame, 7-3 Report MoreInfo frame, 7-4 Retrieve frame, 5-4 Terminal Monitor frame, 16-3, 16-4, 16-6 graphics boxes, C-12
commands, B-20, C-16 defined, B-1 FRS keys, B-23 key definition, B-1	graphs Ingres Menu operation, 2-6 group by (clause), 12-15, F-33
FRS commands top, 16-5	Н
FullPrompt operation specifying variables, 9-2 fullscreen form Pop-up form vs, 13-10	-h flag report (command), 17-23 having (clause), 12-15
function keys activating on terminals, C-13 defined, 2-14, B-1 functions	headers deleting, 8-15 page header, 8-27 reports, 7-9
aggregate, 11-11 boolean, 11-36 built-in, 11-17 conversion, 11-17, 11-35, G-4 date, 11-17, 11-36, 18-4 interval, 18-4 numeric, 11-17, 11-35 string, 11-17, 11-35	Heading operation Create submenu, 8-8 headings break header, 10-3, 10-11 columns, 10-3 creating additional lines, 8-14 deleting, 8-16 editing, 8-16 moving, 8-24
G	page header, 10-11 reports, 8-6, 10-3, 10-11
G format, 11-28 GetTableDef operation	Help (statement) delimited identifiers, 2-18 displaying user tables, 2-2
copying column specifications in tables, 3-8 Create a Table frame, 3-4 Join Specification frame, 6-12, 6-13 Table Field menu, 14-14 VIFRED, 14-15	Help operation, 2-15, B-24 defined, 2-13 keys option, 2-15 menu option, 2-15 Terminal Monitor frame, 16-3, 16-4
Go operation defined, 2-13	Help screens, 2-15

Ingres Menu menu maps, 2-4 hex (function), 11-17 Ingres Menu hexadecimal Tables operation, 2-5 constants, 11-6, 11-33 Ingres Menu hierarchical control break Forms operation, 2-5 report style, 7-8 Ingres Menu JoinDefs operation, 2-5 Ingres Menu Reports operation, 2-6 -i flag Ingres Menu report (command), 12-14, 17-22 Graphs operation, 2-6 II_DATE_FORMAT, 18-15 Ingres Menu Applications operation, 2-6 II_DECIMAL, 18-5 Ingres Menu II_EMBED_SET Queries operation, 2-6 printqry, G-2 Ingres Menu II_MONEY_PREC, 18-5 starting from command line, 2-6 II_NULL_STRING, 12-57 Ingres Menu II_NUMERIC_LITERAL, 11-7, 18-5 JoinDefs operation, 6-6 II_PATTERN_MATCH, 5-10 Ingres Menu Forms operation, 13-2 II_PRINTSCREEN_FILE, 2-15 Ingres Menu II_SCROLL_MSG, 5-16 Queries operation, 16-2 II_TERMCAP_FILE, C-2 Ingres Menu II_TIMEZONE, 18-4 calling, E-2 indented report style, 7-8 Ingres Menu ingmenu (command), E-2 indexes defined, 3-2 Ingres tools destroying, 3-9 starting from command line, 2-6 examining, 3-9 Ingres Menu ING_PRINT, 17-33 Tables operation, 3-3 ingmenu (command), 17-10, E-2 initializing variables, 10-14, 11-9, 12-9 Ingres Menu input masking forms-based tools access, 2-3 numeric templates, 18-12 setting on or off, 15-4 Ingres Menu turning on/off, 18-12 using, 2-3 Inputmasking attribute, 15-4 Ingres Menu capabilities, 2-4 Inquire_forms (statement), B-19

insert editing mode, 2-15, 14-3	regular identifiers, 2-17
Insert operation defined, 2-13 Table Create frame, 3-4 Table Field menu, 5-2, 14-14, 14-16	ISQL calling, E-2 invoking, 16-2, 17-11 isql (command), E-2 Isql (command), 17-11
inserting blank lines, 2-13	italics, 1-3
InsertLine operation Terminal Monitor frame, 16-3	J
int1 (function), 11-17	<u>•</u>
int2 (function), 11-17	J display format parameter
int4 (function), 11-17	character string print format C, 11-22
integer (data type), 11-7, 18-2, 18-5, 18-6, 18-10, D-2	JoinDef basis for form, 13-4
integer1 (data type), 11-8, 11-20, D-2	catalog, 6-8, 6-9 Change Display frame, 6-17
Integer1 (data type), 18-2	copying to/from text files, 6-18
integer2 (data type), 11-8, 11-20, 18-2, D-2	creating, 6-6 data source for reports, 7-5
integer4 (data type), 11-9, 11-20, 18-2, D-2	defined, 6-1
integers display format, 18-10	Definition frame, 6-9 delimited identifiers, 2-18 destroying, 6-18
integrity constraints, 5-3	display, 6-16, 6-17 editing, 6-12
internal field name columns, 14-15 field attribute, 2-11, 15-6 table fields, 14-13	editing forms, 6-18 fields in display, 6-6 join columns, 6-11 Join Specification frame, 6-11 joins (command), 6-8
internal field name attribute, 15-5	limitations on sort priority, 5-15
interval (function), 11-17, 18-4	Master/Detail, 6-3, 6-5 naming, 6-10
invisible field attributes, 15-4	overview, 6-1 ownership, 17-5
Invisible attribute, 15-3	query target, 4-2, 17-36 rules, 5-21, 6-2
IQUEL entering statements, 16-2 invoking, 16-2, 17-10 Iquel (command), 17-10	saving, 6-17 single table, 6-13 testing, 6-17 Update and Delete Rules frame, 6-14 updating, 5-18, 5-21
is not null (comparison operator), 11-17	viewing sort results, 5-15
is null (comparison operator), 11-16	JoinDef Definition frame, 6-10, 6-13
ISO Entry SQL 92 compliant databases delimited identifiers, 2-18	JoinDefs Catalog frame, 6-8

JoinDefs operation Ingres Menu, 2-5, 6-6 QBF Start-up frame, 4-6	distinct, 12-15 Report-Writer, 11-4
joining multiple tables, F-27	L
table to itself, 6-1, 6-13, 6-14 JoinLines operation Terminal Monitor frame, 16-4	-I flag report (command), 12-32, 17-22
joins defaults, 6-6 equi-joins, 6-3 natural, 6-6 outer joins, 6-3 types, 6-3 validation checks, 6-13 viewing columns, 6-12	labels mapping files, B-11, B-23 report example, F-24 report style, 7-9 restrictions on customizing, 7-9 LastQuery operation Retrieve frame, 5-4 Update frame, 5-18
Joins operation JoinDef Definition frame, 6-9, 6-13 justification fields, 18-10	Layout operation adding report sections, 8-8, 8-9 deleting report sections, 8-15 Report Layout frame, 8-7
reports, 11-19, 12-50, 12-51, 12-53	layouts Creating Report Layout Section pop-up, 8- 9 default report, 7-11
	left (function), 11-17
Keep Previous Value attribute, 15-3 key numbers, 3-5	Left operation Move submenu, 8-24
keyboard keys	left_margin (report variable), 11-10
arrow, 15-6, C-14 cursor movement with, 2-15 Enter, 2-14	leftchar (FRS command), B-20 length (function), 11-17
help list, 2-14 mapping, 2-14 Menu, 2-11	limits call (statement) parameters, E-1
Mode, 2-15 Tab, 2-14	Line operation submenu, 8-9
terminal considerations, A-2 VT100 mappings, A-2	line_number (report variable), 11-10
keys help list, 2-15	LineEdit operation Terminal Monitor frame, 16-3
unique, 3-8	lines
Keys operation, 2-15	.center (Report-Writer statement), 12-48 .left (Report-Writer statement), 12-50, 12-
keywords all, 12-15	51 .lineend (Report-Writer statement), 12-51

newline (Report-Writer statement), 12-31.	17-19, 18-2, D-2
12-52, 12-53 .right (Report-Writer statement), 12-53 .tab (Report-Writer statement), 12-54	lowercase (function), 11-17
adding to reports, 8-15 blank, 2-13	M
Box/Line operations, 14-5 displaying between rows, 14-14 maximum in report block, 12-37, 12-57 size, 18-9 text positioning, 12-48 wrapping, 12-57	-m flag report (command), 17-20, 17-21 Mandatory Field attribute Attributes for Field frame, 15-3
ListChoices operation defined, 2-13 JoinDef Definition frame, 6-9 JoinDef Specification frame, 6-12 predefined menu option, B-25 Retrieve frame, 5-4 Table Create frame, 3-4 Update frame, 5-18	mapping described, B-1 disabling, B-11, B-28 file errors, B-29 files, B-10, B-29 FRS commands, B-20 FRS keys, B-10, B-23 getting more information about, B-19 menu items, B-22
ListForms operation, 14-18	querying settings, B-19
listing choices for fields, 2-13	statements, B-25 syntax of statements, B-25, B-28
local databases accessing/terminating access to, 2-6	margins .leftmargin (Report-Writer statement), 12- 27, 12-28
locate (function), 11-17	.rightmargin (Report-Writer statement),
Location operation Form Layout frame, 13-9, 14-2 VIFRED, 13-8	12-32, 12-33 defaults, 10-22, 11-20, 12-27 expanding, 8-26
log (function), 11-17	forms, 13-14 left_margin variable, 11-10
logical operators, 11-16 and, 5-7 or, 5-7 logicals	page footer, 10-18 page header, 10-18 reports, 8-25, 10-17 right_margin variable, 11-10 temporary, 12-45
II_EMBED_SET, G-2 II_NULL_STRING, 12-57 II_NUMERIC_LITERAL, 11-7, 18-5	Master/Detail report style, 7-8
II_SCROLL_MSG, 5-16 ING_PRINT, 17-33 setting, 2-1 TERM_INGRES, A-1	Master/Detail JoinDefs creating, 6-3 in reports, F-27 retrieving with, 6-5
long byte (data type), 11-9, 18-2, D-2	sorting, 5-15, 5-16 Master/Master JoinDefs
	19143161/19143161 301112613

creating, 6-3 sorting, 5-14, 5-15	JoinDefs Catalog frame, 6-9 Report Catalog frame, 7-3
matching patterns in QBF, 5-10	mouse requirements, 2-15
maximum (aggregate function) reports, 8-12	Move operation Form Layout frame, 13-8, 13-13, 14-2, 14
memory usage, G-5	20, 14-21 moving columns in tables, 3-8 moving report components, 8-24
menu (FRS command), B-20	Report Layout frame, 8-7, 8-24
menu key, 2-11	Table Create frame, 3-4 Table Field menu, 14-14, 14-18
menu option, B-24	moving
menus exiting, 2-13 keys, B-22	report components, 8-24
menu items, B-22, B-23 menu maps, 2-4, B-23	N
using, 2-11, 2-13	
messages disabling warning, 17-2	n character in numeric templates, 11-31, 18- 13
minimum (aggregate function) using in reports, 8-12	-n flag report (command), 17-21
mod (function), 11-17	n format character string print format T, 11-34
mode block, 12-37 column formatting, 12-49, 12-50, 12-52, 12-54, 12-55 insert, 2-15 -m flag (mode/style), 17-20 overstrike, 2-15	N format character string print format C, 11-22 naming columns, 3-2, 3-5 conventions, 2-17, 11-1 correlation names, 6-10
mode (FRS command), B-20	JoinDefs, 6-10 tables, 3-5
mode key, 2-15	variables, 11-10, 12-16
modify (statement)	natural joins, 6-6
key columns, 3-6 money (data type) data types for columns, 11-8	nesting .include (Report-Writer statement), 12-12 comments, 12-6
default column formats, 11-20 described, 18-1, 18-2, 18-5	NewLine operation, 14-5
editing defaults, 18-10 storage format, 18-6, D-2	NewQueryTarget operation QBF Execution Phase frame, 4-7
money (function), 11-18	newrow (FRS command), B-20
MoreInfo operation	Next operation

Attributes frame, 15-3 predefined menu option, B-24 Report MoreInfo frame, 7-3 Retrieve frame, 5-15 Update frames, 5-19	numeric (data type) described, 18-1 E format, 11-27 F format, 11-27 G format, 11-28 numbers, 11-6
nextfield (FRS command), B-20	printing, 11-27
nextitem (FRS command), B-20	reports, 11-6, 11-27 storage format, 18-6
NextMaster operation Retrieve frame, 5-17 Update frame, 5-19	templates, 11-30, 18-12 numeric constants, 11-6
NextTable (command), 6-16	numeric expressions
nextword (FRS command), B-20	F format, 11-27 functions, 11-35
No Auto Tab attribute, 15-3	N format, 11-29
No Echo attribute, 15-3	numeric templates input masking and, 18-12
nodes accessing remote, 2-7 v_node name, 2-7	NxtDetail operation Update frame, 5-19
NoEcho (keyword) scrollable fields, 15-7	0
-nofirstff flag	
report (command), G-3, G-4	
•	-o flag report (command), 17-21
report (command), G-3, G-4	9
report (command), G-3, G-4 nonprinting characters, 11-6, 11-33	report (command), 17-21
report (command), G-3, G-4 nonprinting characters, 11-6, 11-33 not (logical operator), 11-16 not null (clause), 12-8 Now date constant, 15-7, 18-4	report (command), 17-21 object_key (function), 11-18
report (command), G-3, G-4 nonprinting characters, 11-6, 11-33 not (logical operator), 11-16 not null (clause), 12-8	report (command), 17-21 object_key (function), 11-18 objects (user interface) naming conventions, 2-17, 11-1
report (command), G-3, G-4 nonprinting characters, 11-6, 11-33 not (logical operator), 11-16 not null (clause), 12-8 Now date constant, 15-7, 18-4 null strings .nullstring (Report-Writer statement), 12-	report (command), 17-21 object_key (function), 11-18 objects (user interface) naming conventions, 2-17, 11-1 referencing, 2-17 OnError operation
report (command), G-3, G-4 nonprinting characters, 11-6, 11-33 not (logical operator), 11-16 not null (clause), 12-8 Now date constant, 15-7, 18-4 null strings .nullstring (Report-Writer statement), 12- 56 alternate, 12-56 reports, 8-27 null values defined, 3-6, 18-5	report (command), 17-21 object_key (function), 11-18 objects (user interface) naming conventions, 2-17, 11-1 referencing, 2-17 OnError operation Terminal Monitor frame, 16-3, 16-7 OpenSQL
report (command), G-3, G-4 nonprinting characters, 11-6, 11-33 not (logical operator), 11-16 not null (clause), 12-8 Now date constant, 15-7, 18-4 null strings .nullstring (Report-Writer statement), 12-56 alternate, 12-56 reports, 8-27 null values defined, 3-6, 18-5 displaying, 8-27 nullability .declare (Report-Writer statement), 12-8 data types, 15-6	report (command), 17-21 object_key (function), 11-18 objects (user interface) naming conventions, 2-17, 11-1 referencing, 2-17 OnError operation Terminal Monitor frame, 16-3, 16-7 OpenSQL data types, D-1 operating system
report (command), G-3, G-4 nonprinting characters, 11-6, 11-33 not (logical operator), 11-16 not null (clause), 12-8 Now date constant, 15-7, 18-4 null strings	report (command), 17-21 object_key (function), 11-18 objects (user interface) naming conventions, 2-17, 11-1 referencing, 2-17 OnError operation Terminal Monitor frame, 16-3, 16-7 OpenSQL data types, D-1 operating system conventions for different, 1-2 operations aborting, B-25 menus, 2-11

described, 11-14	page_length (report variable), 11-10
functions, 11-17 logical, 11-16	page_number (report variable), 11-10
wild card pattern matching, 11-16	page_width (report variable), 11-10
or (comparison operator), 5-7	pages (in reports)
or (logical operator), 11-16	.formfeeds/.noformfeeds (Report-Writer
order by (clause), 12-4, 12-15	statement), 10-16, 12-26 .need (Report-Writer statement), 10-16, 12-28
Order Menu VIFRED, 14-19	.newpage (Report-Writer statement), 10- 16, 12-29
Order operation Form Layout frame, 13-9, 14-2, 14-19 Retrieve frame, 5-4, 5-13 Update frame, 5-18	.pagelength (Report-Writer statement), 10-16, 12-30, 12-31 .pagewidth (Report-Writer statement), 12- 31, 12-32
outer join, 6-3	breaks, 11-18, 12-28, 12-29, F-32 footer, 10-11
outputting reports, 8-26, 9-1, 17-18	form feeds, G-3, G-4 header, 10-11
overflow, 17-13	length, 8-27, 10-17, 12-30 line_number variable, 11-10
overriding column position, 12-40	numbering, 7-6, 8-15, 8-28, 12-29 page_length variable, 11-10
overstrike editing mode, 2-15, 14-3	page_number variable, 11-10 pagination, 10-16, 10-17
ownership	width, 10-16, 10-18, 10-21, 12-31
changing for reports, 17-7 delimited identifiers, 2-17, 2-18, 11-3 forms, 13-4, 17-5 JoinDefs, 17-5 QBFNames, 17-5	parameters passing, 17-25, G-1 runtime, 11-9, 12-20 system-level commands, 17-2
qualifying, 2-9 specify schema, 12-2, 12-7, 12-16	passing parameters, 17-25
synonyms, 2-9, 10-10, 12-2, 12-3 tables, 2-9, 6-10, 10-10, 12-2, 12-3 views, 2-9, 10-10, 12-2, 12-3	patterns matching, 5-10, 11-16
Ownership specify schema, 10-10	performance troubleshooting problems, G-4
., ,	permissions accessing database objects, 2-8
P	Place operation
pad (function), 11-17	described, 13-13 move submenu, 3-8 Move submenu, 8-24, 8-25
padding, C-3	Report Margin submenu operation, 8-26 VIFRED, 14-18
page (keyword), 11-12	·
page break, 12-29	pm/am (with date data type), 18-4

	forms, 13-19, 17-13
active form, 13-11	left justification, 12-50
adjusting size, 13-15	nonprintable character, 11-6, 11-33
anchor point, 13-16	null values, 12-56
borders, 13-11, 13-16	numbers, 11-27
controlling, 13-11	printform (statement), 17-13
default location, 13-13	printscreen (statement), 2-15
designating, 13-10	reports, 9-7, 12-57, 17-18
FormAttr operation, 13-9	right justification, 12-53
normal vs, 13-10	screen contents, 2-15
position, 13-10	strings, 12-57
size, 13-11, 13-16	tabs, 12-58
types, 13-11	text, 12-57
VisualAdjust operation, 13-15	text positioning, G-3
non un formo	variables, 12-16, 12-57
pop-up forms Poy/Line operation 13 13	DrintDartial aparation
Box/Line operation, 13-12 uses, 13-11	PrintPartial operation printing reports, 9-6, 17-33
uses, 13-11	printing reports, 9-6, 17-33
position_number (report variable), 11-10	printscreen (FRS command), 13-19, B-7, B-20 reports displayed on screen, 17-34
Preview operation	
Report Catalog frame, 7-3	privileges
preview reports	database object access, 2-8
defined, 7-4	
running, 9-2	
Provious operation	Q
Previous operation Attributes frame, 15-3	
Report MoreInfo frame, 7-4	-q flag
	y nay
Report Morenilo Iranie, 7-4	, -
previousfield (FRS command), B-20	report (command), 17-22
·	report (command), 17-22 Q0 format, 11-6, 11-33
previousfield (FRS command), B-20 previousword (FRS command), B-20	report (command), 17-22 Q0 format, 11-6, 11-33 QBF
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17-	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10-	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10- 17	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1 described, 4-1
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17-32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10-17 block mode, 12-37	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1 described, 4-1 execution phase, 17-15
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10- 17 block mode, 12-37 centered, 12-48	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1 described, 4-1 execution phase, 17-15 Execution Phase frame, 4-6, 5-3
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10- 17 block mode, 12-37 centered, 12-48 columns, 10-18, 12-16, 12-57	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1 described, 4-1 execution phase, 17-15 Execution Phase frame, 4-6, 5-3 forms, 4-5
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10- 17 block mode, 12-37 centered, 12-48 columns, 10-18, 12-16, 12-57 control characters, 11-33	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1 described, 4-1 execution phase, 17-15 Execution Phase frame, 4-6, 5-3 forms, 4-5 logical operators, 5-7
previousfield (FRS command), B-20 previousword (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10- 17 block mode, 12-37 centered, 12-48 columns, 10-18, 12-16, 12-57 control characters, 11-33 dates, 11-23	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1 described, 4-1 execution phase, 17-15 Execution Phase frame, 4-6, 5-3 forms, 4-5 logical operators, 5-7 phases, 4-1
previousfield (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10- 17 block mode, 12-37 centered, 12-48 columns, 10-18, 12-16, 12-57 control characters, 11-33 dates, 11-23 default formats, 11-19, G-3	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1 described, 4-1 execution phase, 17-15 Execution Phase frame, 4-6, 5-3 forms, 4-5 logical operators, 5-7 phases, 4-1 Qbf (command), 17-14
previousfield (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10- 17 block mode, 12-37 centered, 12-48 columns, 10-18, 12-16, 12-57 control characters, 11-33 dates, 11-23 default formats, 11-19, G-3 escape characters, 11-33	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1 described, 4-1 execution phase, 17-15 Execution Phase frame, 4-6, 5-3 forms, 4-5 logical operators, 5-7 phases, 4-1 Qbf (command), 17-14 QBF operation, 4-6
previousfield (FRS command), B-20 Print operation sending reports from screen to printer, 17- 32 Terminal Monitor output frame, 16-6 Utilities frame, 13-4 printing formfeeds (Report-Writer statement), 10- 17 block mode, 12-37 centered, 12-48 columns, 10-18, 12-16, 12-57 control characters, 11-33 dates, 11-23 default formats, 11-19, G-3	report (command), 17-22 Q0 format, 11-6, 11-33 QBF Append Operation, 5-1 calling, 4-6, E-2 calling from Ingres Menu, 4-2, 4-6 calling from operating system, 4-2 comparison operators, 5-6 data types, 4-5 definition phase, 4-1 described, 4-1 execution phase, 17-15 Execution Phase frame, 4-6, 5-3 forms, 4-5 logical operators, 5-7 phases, 4-1 Qbf (command), 17-14

QBFName (ownership), 17-5 qf (command), E-2	starting Terminal Monitor, 2-6, 16-2 Update frame, 5-19
Retrieve frame, 5-4 running from VIFRED, 13-21 starting, 2-6, 17-14	query targets, 4-2
update (function), 5-18 wild card characters, 5-9	query (command) described, 17-15
QBF Execution Phase Frame, 5-18 Update operation, 5-18	flags/parameters, 17-16 QBF, 17-15
QBF Start-up frame JoinDefs operation, 4-6	query languages interactive, 2-6
QBFNames operation, 4-6 Tables operation, 4-6	Query Only attribute, 15-3
QBFNames	Query operation Table Utility frame, 3-3
assigning to forms, 13-19, 13-21 defined, 6-18 delimited identifiers, 2-18 frame in VIFRED, 13-20 Menu in VIFRED, 13-20 query targets, 4-2, 17-36	query targets default formats, 5-1 displaying catalog frames, 4-6 forms, 4-7 search order, 4-7 VIFRED, 17-36
QBFNames operation QBF Start-up frame, 4-6 Utilities frame, 13-4	Quit key Forms Layout frame, 13-21
VIFRED, 13-19 qualifying object names with owner, 2-9	Quit operation defined, 2-13 end vs, 2-13 predefined menu option, B-24
OUEL data types, 11-9, D-1 delimited identifiers, 11-2, 11-4 specifying queries in reports, 12-15 table owner qualification, 12-3 transaction handling, 12-5, 12-22	Terminal Monitor frame, 16-3 quitting applications from submenus, 2-13
	R
queries debugging, G-2 definition phase, 4-1 executing, 4-6, 16-4, 17-15 execution phase, 4-1, 4-2, 17-14, 17-15 performance, G-4 printing/filing results, 16-6 QBF, 4-2 report specification, 12-15 sorting results, 5-13 targets, 5-1 variables, 10-2, 12-16, 12-18, 12-20	-r flag report (command), 17-20, 17-21 range variables, 6-10 RBF calling, E-2 command syntax, 17-16 copyrep (command), 17-8 overview, 7-1 pop-ups, 7-4
Queries operation Retrieve frame, 5-15	Report-Writer, 10-1 rf (command), E-2

role, 7-1 Save Report frame, 8-30 sreport (command), 17-35 starting from Ingres Menu, 2-6, 7-2 starting from operating system, 17-16	report specification archiving, 8-32, 17-7, 17-35 creating, 8-1 default, 7-6, 8-1, 8-4 defined, 7-4
rbf (command) flags and parameters, 17-18 starting RBF, 17-16	editing, 18-20 format, 10-9, 12-1 getting information, 7-4 getting information about, 7-3
read mode, 12-22	list, 7-2
Read operation Terminal Monitor frame, 16-4	loading, 8-5 ownership, 7-2 saving, 8-8
redraw (FRS command), B-21	syntax checking, 17-35
Redraw key, 2-16	ReportOptions operation
redrawing the screen, 2-16, B-21	Report Layout frame, 8-7
referencing columns, 11-8	reports adding footers, 8-9 archiving, 8-32
remarks (long), 12-13	block mode capabilities, 12-37, 12-38, 12-
Remarks (long), 12-14	43 block style, 10-5
remarks (short), 12-24	block-style, 7-8
remote data manager, 17-1, 17-7, 17-18, 17-35	breaks, 7-5, 10-2, 10-3, 12-3, 12-4 catalog, 10-4 centering, 12-48
remote databases, 2-6 accessing, 2-1, 2-7	column style, 10-5 column-style, 7-7
remote nodes, 2-6, 2-7	comments in specifications, 10-6, 12-3, 12-6, 12-13, 12-14, 12-24
Rename operation Catalog Frame menu, 13-19 Forms Catalog frame, 13-3 JoinDefs Catalog frame, 6-9 Report Catalog frame, 7-3	conditions, 12-60, 12-61 constants, 11-5 copying, 17-7 creating, 7-2, 10-4, 10-6, 12-3 creating report components, 8-8
report (command) described, 10-5, 17-18	customizing, 7-6, 10-2 data formats, 11-18 data selection, 10-2, 12-6
report (keyword), 11-12	dates, 7-6, 8-28
Report Catalog frame, 7-2	default, 10-5, 10-21, 11-19
Report Layout frame described, 8-5, 8-8 menu operations, 8-7	default destination, 9-1 default layout, 7-11 default report specification, 7-6 deleting, 7-2, 17-8
report Moreinfo Frame, 7-3	deleting components, 8-15 deleting sections, 8-15
Report operation Table Utility frame, 3-3	designing, 10-5, 12-1 destinations, 9-1 detail, 7-10

display formats, 8-17, 12-39, 12-41, 18-6 editing components, 8-16, 8-17 error log, 9-1 footers, 7-10 formatting, 10-18 from files outside database, 17-22 headers, 7-9 headings, 8-6 hierarchical control break, 7-8	storing, 17-35 styles, 7-6, 8-3, 10-5 tabular style, 7-7, 10-5 testing, 10-5 time, 7-6, 8-28 underlining, 8-27 variables, 9-2, 10-14, 11-34, 12-61, 12-62 wrap style, 10-5 wrap-style, 7-7
indented style, 7-8 Ingres Menu operation, 2-6 joined tables, F-27 justification, 12-50, 12-53 labels style, 7-9 layouts, 10-2, 10-6, 10-18, 12-26 margins, 12-27, 12-28 Master/Detail style, 7-8	Report-Writer assignment (statement), 12-61, 12-62 block mode, 12-37 calling, E-3 commands, 17-1 conditional statements, 12-60, 12-61 described, 10-1
moving components, 8-24 naming, 12-14 nulls, 8-27 output file, 12-14 outputting options, 8-26, 17-20, 17-31	expressions syntax summary, 11-34 features, 10-1 functions, 11-17 overview, 7-1 report (command), E-3 reserved words, 11-4
page numbers, 7-6, 8-28 pagination, 10-16, 10-17, 12-26, 12-27, 12-28, G-3, G-4 preview, 7-4, 9-2 printing, 9-1, 10-18, 17-18	running, 10-5 sample report, F-1 special report variables, 11-10 specification summary, 10-11
producing, 9-1, 17-18 query language, 8-31 remarks, 12-13, 12-14, 12-24 report (command), E-3	statement delimiters, 10-10, 12-2 statement syntax summary, 12-62 troubleshooting, G-1 Report-Writer statements
Report Catalog frame, 7-2 report specification, 7-4 running, 17-18 running in background (batch), 9-1, 9-7 runtime data selection, 9-2	.block, 12-37, F-10 .bottom, 12-38 .break, 12-3, 12-4 .center, 12-48 .cleanup, 12-4, F-27
runtime parameters, 12-20 runtime variables, 12-16, 12-18 sections, 7-9 sending from screen to file, 17-34	.data, 12-6 .declare, 12-7, F-14 .delimid, 12-10, 12-11, F-14 .detail, 12-33, F-5, F-14, F-20, F-22
sending from screen to printer, 17-33, 17-34 sending to file or printer, 9-1, 17-32 sending to screen, 12-15 setup procedures, 10-6, 12-3, E-3	.elseif, F-15 .endblock, 12-37, F-10, F-22, F-24 .endif, 12-60, F-15 .endremark, 12-13, 12-14 .endwithin, 12-45, F-10
setup statements, 10-13, 10-14 sorting, 8-18, 10-2, 12-25 sources of data, 7-5, 8-1 specification, 10-4, 10-11, E-3	.footer, 12-34, F-5, F-6, F-15, F-21 .format, 12-39, 12-40, F-5, F-14 .formfeeds, 12-26, 12-27, F-14, G-3, G-4 .header, 12-34, F-5, F-6, F-14, F-15, F-20,
statistics, 9-1	F-21, F-22

.if, 12-60, 12-61, F-15 .include, 12-12 .left, 12-50, 12-51 .leftmargin, 12-27, 12-28 .let, 12-61, 12-62 .lineend, 12-51 .linestart, 12-51 .longremark, 12-13, 12-14, F-14 .name, 12-14 .need, 12-28, 12-29, F-5, F-32 .newline, 12-37, 12-52, F-10, F-22, F-24 .newpage, 12-29, 12-30, F-14, F-15	Order operation, 5-13 Query operation, 5-15
	retrieve operation search conditions, 5-5
	Retrieve operation QBF Execution Phase frame, 5-3
	retrieving data with Terminal Monitor, 16-2, 16-4 QBF, 4-6, 5-3 Retrieve operation, 5-3
.nofirstff, G-3, G-4	reverse, C-12
.nofirstffd, 12-30	reverse video, C-12
.noformfeeds, 12-26, 12-27, G-3, G-4 .nounderline, 12-59 .nullstring, 12-56, 12-57 .output, 12-14, 12-15	Reverse Video attribute Box Attributes frame, 14-4 described, 15-3
.pagelength, 12-30, 12-31, F-14	right (function), 11-17
.pagewidth, 12-31, 12-32 .position, 12-40 .print, 12-57	right margins forms, 13-14
.println, 12-57, F-10 .query, 12-15, 12-19, F-5 .right, 12-53, F-6	Right operation Move submenu, 8-24
right, 12-33, 1-0.	right_margin (report variable), 11-10
.setup, 12-22, F-27	rightchar (FRS command), B-21
.shortremark, 12-24	
.sort, 12-25, F-5, F-14	rounding
.tab, 12-54	-5 flag, 17-23
.tformat, 12-41, F-14 .top, 12-43, F-10 .ulcharacter, 12-59 .underline, 12-59	rows displaying lines between, 14-14 number displayed, 14-13
.width, 12-44 .within, 12-45, F-10 types, 10-6, 12-3	rows (in reports), 12-7 distinct vs duplicate, 12-25 sort order, 12-25
Report-Writer system catalogs, 10-4, 17-35	rows (in table fields)
reserved words, 11-4	number, C-5
Resize operation VIFRED, 13-16, 14-7	rows (in tables) appending, 5-1 defined, 3-1
restrictions call (statement) parameters, E-1	deleting, 5-20 duplicates, 3-8
Resume operation Terminal Monitor frame, 16-3, 16-6	protecting, 6-13 updating, 5-18 width, 3-1
retrieve frame Next operation, 5-15	rubout (FRS command), B-21

Rulers operation VIFRED Form Layout frame, 13-8	forms, 13-17 JoinDefs, 6-17 report definitions, 8-8
rules deleting, 6-14, 6-15 JoinDef, 6-2, 6-14 Rules operation, 6-13, 6-14 updating, 6-14, 6-15	Save Changes to Report pop-up, 8-32 Save operation, 6-17 Saving a Form pop-up, 13-18 table updates, 5-21 VIFRED, 13-17
Rules operation JoinDef Definition frame, 6-9 JoinDef Specification frame, 6-12	Saving a Form pop-up, 13-18
Run a Report pop-up, 9-2 runtime	schema defined, 10-10, 12-2 delimited identifiers, 2-17, 11-2, 12-10 object owner qualification, 2-8, 2-9, 2-17
data selection, 8-20	3-10, 6-10, 10-10, 11-3, 12-2
runtime system data selection, 12-8 variables, 12-16, 12-18	screen, C-12 boxing characters, C-12 clearing, C-5 color, C-15 printing contents, 2-15
S	refreshing, 2-16
-s flag	returning to previous, 2-13 types, A-2 video attributes, C-12
report (command), 12-6, 12-23, 17-2	Scroll size attribute, 15-5
sample reports account, F-12	Scrollable attribute, 15-5
described, F-1 dictionary, F-19 label, F-24 population, F-1	scrollable fields defined, 15-6 DisplayOnly, 15-7 NoEcho, 15-7
Save Changes to Report	scrolldown (FRS command), B-21
pop-up, 8-32 Save operation described, 13-9, 14-2	scrolling, C-16 keys, 2-15 table fields, 5-16
Form Layout frame, 13-9, 14-2 Forms Layout frame, 13-17	scrollleft (FRS command), B-21
JoinDef Definition frame, 6-9	scrollright (FRS command), B-21
predefined menu option, B-25 Report Layout frame, 8-8, 8-30	scrollup (FRS command), B-21
Report MoreInfo frame, 7-4 Save Report frame, 8-31 Update frame, 5-19, 5-21	search conditions retrievals, 5-5
Save Report frame fields, 8-30	search order query targets, 4-7
saving	select (clause), 12-15, F-33

select (statement) report queries, 12-15	SimpleFields operation Forms Catalog frame, 13-6
system catalog queries, 2-2	sin (function), 11-17
Select a Destination pop-up, 9-3	size (function), 11-17
selecting an Aggregate pop-up, 8-14	smallint (data type) default column format, 11-20 described, 18-2
Sending a report to a file pop-up, 17-33	integer2 (data type), D-2 OpenSQL, D-2
Sending a Report to a File pop-up, 9-5, 9-6	Sort Columns pop-up, 8-10 sorting
Sending a report to a printer pop-up, 17-32	.header (Report-Writer statement), 12-35 aggregate functions, 11-11
Sending a Report to a Printer pop-up, 9-5	breaks, 11-11 columns, 10-15, 10-16 defining report sort order, 8-18
separation lines displaying, 14-14	order, 5-13 preview reports, 7-4
separators multiple values for a parameter, 10-10,	reports, 10-2, 12-25 rows, 5-18
12-2 sequence numbers in fields, 14-19	special characters numeric templates, 11-30 Q0 format, 11-33 string templates, 18-20
server	·
specifying in database access syntax, 17-2 type, 2-3, 2-6, 2-7	specifications column, 14-15 data format, 11-18
set autocommit (statement) overriding default commit behavior, 12-5, 12-22	SplitLine operation Terminal Monitor frame, 16-4
set functions, 11-11	SQL .cleanup, 12-4
Set lockmode (statement) reports, 12-22	.setup, 12-4 .setup, 12-22 autocommit, 12-5, 12-22
shell (FRS command), B-21	data types, 11-8, 18-1, D-1 invoking, 17-13
shift (function), 11-17	parameter passing, 17-25
Shift operation Move submenu, 8-24, 8-25	specifying queries in reports, 12-15 sql (command), E-4 Sql (command), 17-13
simple fields	transaction handling, 12-5, 12-22
defined, 2-10 JoinDefs, 6-11 viewing retrieved information, 5-15	SQL-92 standard database requirements, 11-1
Simple fields	sqrt (function), 11-17
logical operators, 5-8	squeeze (function), 11-18

include (Report-Writer statement), 12-12 bypassing, 17-22 described, 17-35 role, 10-4	trim (function), 11-18 with prompt (clause), 12-8 with value (clause), 12-8 word wrapping, 11-22
syntax check, 17-35 troubleshooting with, G-2	style parameter, 17-21
sreport(command), E-4	styles Choose a Report Style pop-up, 9-3
star	report, 7-6
accessing distributed database, 2-1	subtopics, 2-15
Star server accessing distributed database, 2-7	sum (aggregate function) reports, 8-12, 8-13
starting Ingres tools, 2-3 Interactive query languages (ISQL and IQUEL), 16-2 QBF, 4-7 RBF, 7-2 Terminal Monitor, 16-2 VIFRED, 13-2	synonyms defined, 3-2 delimited identifiers, 11-2, 11-3 destroying, 3-9 examining, 3-9 ownership, 2-9, 10-10, 12-2, 12-3 using, 2-8, 12-7
statement separator Report-Writer, 10-10, 12-2	syntax aggregate functions, 11-36 conventions, 1-3
statement syntax, 1-3 statements block, 17-23 syntax, 10-9, 12-1	database access, 2-6 Report-Writer espressions summary, 11-34 Report-Writer statement summary, 12-62 system-level commands, 17-1
types, 10-6, 12-3	syntax descriptions, 1-3
straight edge alignment guides RBF, 8-6	system catalogs database, 2-2
string templates creating custom template, 18-20	system variables setting, 2-1
custom character set examples, 18-24 defining, 18-20	system-level commands, 17-1
described, 18-20 examples, 18-25 mandatory entry, 18-24	systems administrator, B-21 exiting, B-24
strings, B-24 C format, 11-21 constants, 11-4, 11-5	<u>T</u>
delimiters, 11-5 functions, 11-35 hexadecimal, 11-6 literal, 18-2 printing, 12-57 reports, 11-5, 12-57	-t flag report (command), 12-39, 17-24 T format, 11-34

Tab key, 2-14	starting from IngresMenu, 3-3
tabbing order changing, 14-19	Tables Catalog frame listing user tables, 3-3
Table Field frame VIFRED, 14-13 table fields	Tables operation Ingres Menu, 2-5, 3-3 QBF Start-up frame, 4-6
components, 2-11 creating, 14-13 described, 2-10	tabs printing, 12-58
display modes, 14-15 editing, 5-20, 14-16	tabular formats for reports, 7-7, 10-5
inserting rows, 5-2 internal names, 14-13 JoinDefs, 6-11 logical operators, 5-7 moving columns, 14-18 retrieving information, 5-15 scrolling, 5-16 validating, 2-18	templates absolute date and time, 18-15, 18-16 creating custom string template, 18-20 date format, 11-23, 18-15, 18-16 defining string template, 18-20 numeric (data type), 11-30 string examples, 18-25 string templates, 18-20
table names, abbreviating, 6-10	temporary formats, 12-39, 12-41, 12-45
table_key (function), 11-18	TERM_INGRES, A-1
TableField operation Forms Catalog frame, 13-6 tables appending data, 5-1	termcap descriptions, C-12 advanced features, C-11 basic features, C-5, C-6 list of commands, C-5 writing, C-4
basis for form, 13-4 creating, 3-4 data source for reports, 7-5 delimited identifiers, 2-17, 11-2, 11-3, 12-	termcap file purpose, A-1, B-8
destroying, 3-9 examining, 3-9 joining, 6-1, 6-13, 6-14, F-27 master deleting records, 5-20 naming, 3-5 ownership, 2-9, 6-10, 10-10, 12-2, 12-3 query targets, 4-2 reports created from, 10-2, 10-15, 12-6	Terminal Monitor calling, E-4 delimited identifiers, 2-18 described, 16-1 error messages, 16-6 printing query results, 16-6 query languages, 16-1 startup, 16-2 writing statements to a file, 16-4
retrieving into/from, 6-13 single-table JoinDefs, 6-13 structure, 3-1	Terminal Monitor frame input screen, 16-4, 16-6 output screen, 16-4
synonyms, 2-8 Tables (utility) creating tables, 3-4 described, 3-1 starting from Ingres Menu, 2-5	terminals activating cursor, C-16 color, C-15 Concept 100, C-18 Datamedia 3045, C-18

Dec V1100, C-17 Envision 230, C-18 initializing, C-6	editing, 14-3, 14-4 form component, 14-1 moving, 8-24
mapping files, B-14, B-18 types functional with Ingres, A-2, A-7	trim (function), 11-18
video attributes, C-12 VT, A-2, B-8, B-14, B-18, C-17	Trim operation Create submenu, 8-8
text	VIFRED forms components, 14-3
positioning, 10-19 underlining, 12-59	troubleshooting Report-Writer reports, G-1
text (data type) data types for report columns, 11-8 default report column format, 11-20 described, 18-1, 18-2, 18-3 storage format, D-1	Underline attribute
text (function), 11-18	Box/Trim Attributes frame, 14-4 described, 15-3
text file report definition, 10-5, 12-1	underlining, C-12
text strings character data type, 18-2	.nounderline (Report-Writer statement),12-59.ulcharacter (Report-Writer statement),
time absolute, 11-7, 18-15, 18-19 current_time variable, 11-10 formats, 11-7	12-59 .underline (Report-Writer statement), 12 59 reports, 8-27, 12-59
functions, 11-17 intervals, 11-8 reports, 7-6, 8-28 templates, 11-25, 18-15, 18-16, 18-19	Underlining .ulcharacter (Report-Writer statement), 12-59
zones, 18-4	underscore, C-12
Title operation VIFRED, 14-8, 14-9, 14-22	Undo operation defined, 2-13 Form Layout frame, 13-9, 14-2, 14-21
titles fields, 2-11, 14-8	predefined menu option, B-25 Report Layout frame, 8-8
Today date constant, 15-7, 18-4	reversing deletions, 8-29
Top (FRS command) Terminal Monitor frame, 16-5	union select statements, 12-15, F-29
Top operation predefined menu option, B-24	unique keys preventing duplicate rows in tables, 3-8
transactions rolling back, 12-6	UNIX default printer command, 17-21
trim creating, 8-10, 14-3 defined, 2-10	delimiting parameters containing parentheses, 12-20, 17-19, 17-25 escaping double quotes, 17-26, 17-29 termcap file for, C-1, C-16

Update frame Delete operation, 5-19	maximum length, 15-7 syntax check, 15-8, 17-35
Update operation described, 5-18 exiting, 5-21 QBF Execution Phase frame, 5-18	table field columns, 15-8 Validation check, 15-5 valid comparison operators, 15-8
updating	Validation Check attribute, 15-5
JoinDefs, 5-18, 5-21 QBF, 4-6, 5-18	Validation Error Message attribute, 15-5
rows in tables, 5-18 rules, 6-14, 6-15 Update operation, 5-18	varchar (data type) conversion function, 11-18 data types for report columns, 11-8
upline (FRS command), B-21	default report column format, 11-20 described, 18-1, 18-2, 18-3
uppercase (function), 11-18	storage format, D-1
user	varchar (function), 11-18
mapping customized, B-18	variables
user identifiers schema names, 2-17 specifying effective user, 2-17	assigning values to, 12-7, 12-61, 12-62 dbname, 2-7 declaring, 12-8, G-1
user names delimited identifiers, 11-2, 11-3, 12-10 object ownership specification, 11-3 specifying effective user, 11-3	expressions, 11-9, 12-61 initialization, 11-9, 12-9 naming, 11-10, 12-16 passing, 17-25 printing, 12-16, 12-57
user-defined abstract data types, 18-2, D-2	query, 10-2, 11-10, 12-16, 12-18
user-defined default values, 3-10	range, 6-10 remote node, 2-7
Utilities operation Forms Catalog frame, 13-4 Report Catalog frame, 7-3	reports, 10-14, G-1 runtime, 10-14, 12-16, 12-57 run-time, G-1 server_type, 2-6, 2-7 special report, 11-10 system, 2-1 v_node, 2-7
-v flag	VAX/VMS
report (command), 12-31, 17-22	delimiting parameters containing
V_node, 2-7, 17-1, 17-7, 17-18, 17-35	parentheses, 12-20, 17-19, 17-25 escaping double quotes, 17-26, 17-29
validation	-G flag, 17-35 print queue initialization, 17-21
changing criteria, 15-7 check, 15-7	vchar (data type)
checks on joins, 6-13	default report column format, 11-20
comparisons, 15-8 creating criteria, 15-8	vchar (function), 11-18
delimited identifiers in, 2-18	video attributes
error message, 15-11	termcap descriptions, C-12

ViewDefaults operation, 3-10	utilities operation, 13-4
viewing database tables, 3-3, 3-9	validation checks, 2-18 Vifred (command), 13-2
views	vifred (command), E-4
data source for reports, 7-5	Vision
defined, 3-2	starting from Ingres Menu, 2-6
deleting, 3-9	
delimited identifiers, 11-2, 11-3, 12-10	VisuallyAdjust operation
examining, 3-9	described, 13-12
ownership, 2-9, 10-10, 12-2, 12-3	fixed-position pop-up forms, 13-15
reports, 10-15	floating pop-up forms, 13-15
·	Move operation, 13-16
VIFRED	Resize operation, 13-16
Attributes operation, 14-11	rotating anchor point, 13-16
Box/Line operation, 14-5	VT terminals, A-2, B-8, B-14, B-18, C-17
calling, 13-2, E-4	
Catalog frame, 13-3, 13-4	
components of form, 14-1	W
creating blank lines, 14-4	
creating form components, 14-3	
creating forms, 13-4	w display format parameter
data windows, 14-9 default forms, 13-5	blanking print format B, 11-21
destroying forms, 13-18	character string print format C, 11-22
exiting, 13-21	numeric print format E, 11-27
expert mode, 13-2	numeric print format F, 11-28
features, 13-1	numeric print format G, 11-28
field display formats, 18-11	numeric print format I, 11-29
Field operation, 14-8	numeric print format N, 11-30
fields, 14-7	-w flag
Form Layout frame, 13-7	report (command), 12-37, 12-57, 17-23
FormAttr operation, 13-9	
forms copying, 17-4	w_column (report variable), 11-10, 12-46
forms creating, 13-18	w_name (report variable), 11-10, 12-46
forms editing, 13-18, 14-1, 14-19	where (eleuse) 11 1 12 15
forms renaming, 13-19	where (clause), 11-1, 12-15
GetTableDef operation, 14-15	wild card characters
invoking, 17-36	asterisk (*), 11-16
menu operations summarized, 13-1	delobj (command), 17-9
multiple table forms, 13-6	QBF, 5-9
NewLine operation, 14-5	question mark (?), 11-16
overview of, 13-1	Report-Writer, G-1
QBFNames Catalog frame, 13-20	VIFRED, 15-8
role, 13-1	Windows NT
saving forms, 13-17	delimiting parameters containing
setting attributes on fields, 15-1	parentheses, 12-17, 12-20, 17-19, 17-25
starting from Ingres Menu, 2-5	17-29, 17-30
TableField operation, 14-13	escaping double quotes 17-26 17-29

with null (clause), 12-8
with prompt (clause), 12-8, 12-17
with value (clause), 12-8, 12-17
wrap
character string word wrapping, 11-22
line wrapping in reports, 12-57
report style, 7-7
wrap style reports, 10-5

Write operation
Terminal Monitor frame, 16-4

Z

z character in numeric templates, 11-31, 18-13