Quick Reference: Add a New Size Class (CTL, SSL, MX) to `size-class-master.xlsx`

The size class file of the Open Orders by MSA report macro (`build-open-orders-report.bas` v2.8; Config setting `SizeClassFile`). It sets the size class of every model in the report.
The same steps for all three families; only the table changes. Example: `4000&Over` (CTL), `XL Frame` (SSL), `>10-15` (MX), shaded **peach** in the pictures. Use the class names your size class slide gives.

1 Open the file, go to the Set-up tab

2 Find the table of the family

CTL	Table 1	column **A**	e.g. `4000&Over`
SSL	Table 2	column **C**	e.g. `XL Frame`
MX	Table 3	column **E**	e.g. `>10-15`

3 Type the class in the first empty yellow cell

- Spell it as the report should show it; one class per cell
- Largest class? It goes at the bottom, as in the example
- Belongs between two classes? Select the cells from that spot down to the last class, drag their border one cell down, then type in the gap. Never insert whole rows

4 Check Table 4 (column G)

The new class shows in its place in the list: it is now in the drop-down.

5 Give it to the models, on the Size Class tab

Pick the new class in column D for each model in it; a new model goes in the first empty row (Name of machine in column C, as the export spells it). Save and close.

6 Config: Check setup, then Build report

The Run Log counts the new classes (the example): `Size classes: 20 from the Set-up tab (CTL 7, MX 8, SSL 5)`

Do not: type in Table 4, change the green headers, insert or delete whole rows, or type a class twice or the word UNMAPPED. Up to 15 classes per table.

Set-up tab after step 3

	A	B	C	D	E	F	G
3	Table 1. Track loaders (CTL).		Table 2. Skid-steer loaders (SSL).		Table 3. Mini excavators (MX).		Table 4. Drop-down list (formulas).
4	**CTL size class**		**SSL size class**		**MX size class**		**Drop-down shows (do not type)**
5	0<2000		EX Small		>00-01		0<2000
6	2000<2300		Small Frame		>01-02		2000<2300
7	2300<2600		Med Frame		>02-03		2300<2600
8	2600<3000		Large Frame		>03-04		2600<3000
9	3000<3500		**XL Frame** (3)		>04-05		3000<3500
10	3500&Over				>05-06		3500&Over
11	**4000&Over** (3)				>06-10		4000&Over
12					**>10-15** (3)		>00-01
13							>01-02
14							>02-03
15							>03-04
16							>04-05
17							>05-06
18							>06-10
19					(4)		>10-15
20							EX Small
21							Small Frame
22							Med Frame
23							Large Frame
24							XL Frame

Size Class tab after step 5 (header and last rows)

	A	B	C	D	E
1	**HP**	**Rated Operating Capacity**	**Name of machine**	**Size Class**	**Notes**
26	24.8	7,403	E32	>03-04	as on the sheet; Rated Operating Capacity column hold
27	24.8	7,659	E35	>03-04	as on the sheet; Rated Operating Capacity column hold
28	33.2	7,893	E38	>03-04	as on the sheet; Rated Operating Capacity column hold
29	40.4	9,180	E40	>04-05	as on the sheet; Rated Operating Capacity column hold
30	42.6	9,830	E48	>04-05	as on the sheet; Rated Operating Capacity column hold
31			**E145** (5)	**>10-15**	**new model, new class**

Title	Project	Macro	Rev.	Date	Drawn	Sheet
Quick Reference	**Open Orders by MSA**	**v2.8**	**1**	**2026-10-16**	**Gust F.**	**1 of 1**