



Computer Networks

Quanlong Li



李全龙



Computer Networks





Chapter 3: Transport Layer

our goals:

- understand
 principles behind
 transport layer
 services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control

- learn about Internet transport layer protocols:
 - UDP: connectionless transport
 - TCP: connection-oriented reliable transport
 - TCP congestion control





Computer





Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control










Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
 - send side: breaks app messages into segments, passes to network layer
 - rcv side: reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
 - Internet: TCP and UDP











Transport vs. network layer

- network layer: logical communication between hosts
- transport layer: logical communication between processes
 - relies on, enhances, network layer services

household analogy:

- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes
- transport protocol = Ann and Bill who demux to inhouse siblings
- network-layer protocol = postal service






Networks





Internet transport-layer protocols

- reliable, in-order delivery (TCP)
 - congestion control
 - flow control
 - connection setup
- unreliable, unordered delivery: UDP
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees





Networks





Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control











Multiplexing/demultiplexing

multiplexing at sender:

handle data from multiple sockets, add transport header (later used for demultiplexing) demultiplexing at receiver:

use header info to deliver received segments to correct socket








3: Transport Layer





How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries one transport-layer segment
 - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format



李全龙

Computer Networks

3: Transport Layer






Connectionless demultiplexing

recall: created socket has host-local port #:

DatagramSocket mySocket1
= new DatagramSocket(12534);

- recall: when creating datagram to send into UDP socket, must specify
 - destination IP address
 - destination port #

- when host receives UDP segment:
 - checks destination port # in segment
 - directs UDP segment to socket with that port #












Connectionless demux: example







李全龙





Connection-oriented demux

- TCP socket identified by 4-tuple:
 - source IP address
 - source port number
 - dest IP address
 - dest port number
- demux: receiver uses all four values to direct segment to appropriate socket

- server host may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
- web servers have different sockets for each connecting client
 - non-persistent HTTP will have different socket for each request










Connection-oriented demux: example




three segments, all destined to IP address: B, dest port: 80 are demultiplexed to *different* sockets







Connection-oriented demux: example









Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control









UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service,UDP segments may be:
 - lost
 - delivered out-of-order to app
- connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others

- UDP used by:
 - streaming multimedia apps (loss tolerant, rate sensitive)
 - DNS
 - SNMP
- reliable transfer over UDP:
 - add reliability at application layer
 - application-specific error recovery!









UDP: segment header

32 bits dest port # source port # checksum length application data (payload)

UDP segment format

length, in bytes of UDP segment, including header

why is there a UDP?

- no connection establishment (which can add delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control: UDP can blast away as fast as desired









UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

sender:

- treat segment contents, including header fields, as sequence of 16-bit integers
- checksum: addition (one's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - NO error detected
 - YES no error detected. But maybe errors nonetheless? More later










UDP checksum-checking contents

Include 3 parts:

- Pseudo
- Pseudo head
- head

- UDP head
- Application data









Internet checksum: example

example: add two 16-bit integers

														0			
wraparound	1	1	0	1	1	1	0	1	1	1	0	1	1	1	0	1	 1 →
sum checksum														1 0			

Note: when adding numbers, a carryout from the most significant bit needs to be added to the result









Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control










Principles of reliable data transfer

- important in application, transport, link layers
 - top-10 list of important networking topics!



- (a) provided service
- characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)










Principles of reliable data transfer

- important in application, transport, link layers
 - top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)










Principles of reliable data transfer

- important in application, transport, link layers
 - top-10 list of important networking topics!




 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)







Reliable data transfer: getting started





李全龙





Reliable data transfer: getting started

we'll:

- incrementally develop sender, receiver sides of reliable data transfer protocol (rdt)
- consider only unidirectional data transfer
 - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver

state: when in this "state" next state uniquely determined by next event state 1 event actions event actions event actions event state 2




李全龙





rdt I.O: reliable transfer over a reliable channel

- underlying channel perfectly reliable
 - no bit errors
 - no loss of packets
- separate FSMs for sender, receiver:
 - sender sends data into underlying channel
 - receiver reads data from underlying channel



Computer



李全龙

Networks





rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
- the question: how to recover from errors

How do humans recover from "errors" during conversation?









rdt2.0: channel with bit errors


- underlying channel may flip bits in packet
 - checksum to detect bit errors
- the question: how to recover from errors:
 - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - sender retransmits pkt on receipt of NAK
- Automatic Repeat reQuest (ARQ) protocols
- new mechanisms in rdt2.0 (beyond rdt1.0):
 - error detection
 - feedback: control msgs (ACK,NAK) from receiver to sender
 - retransmission







rdt2.0: FSM specification



receiver

rdt_rcv(rcvpkt) && corrupt(rcvpkt) udt send(NAK) Wait for call from below rdt rcv(rcvpkt) && notcorrupt(rcvpkt) extract(rcvpkt,data) deliver_data(data) udt_send(ACK)




Computer Networks





rdt2.0: operation with no errors












rdt2.0: error scenario









rdt2.0 has a fatal flaw!

what happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate

handling duplicates:

- sender retransmits current pkt if ACK/NAK corrupted
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt










rdt2.1: sender, handles garbled ACK/NAKs









rdt2.1: receiver, handles garbled ACK/NAKs

rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) && has seq0(rcvpkt) extract(rcvpkt,data) deliver_data(data) sndpkt = make pkt(ACK, chksum) udt_send(sndpkt) rdt_rcv(rcvpkt) && (corrupt(rcvpkt) sndpkt = make_pkt(NAK, chksum) Wait for Wait foi 0 from 1 from below, not corrupt(rcvpkt) && below

sndpkt = make_pkt(ACK, chksum) udt_send(sndpkt)

rdt_rcv(rcvpkt) && notcorrupt(rcvpkt) && has_seq1(rcvpkt)

extract(rcvpkt,data) deliver_data(data) sndpkt = make pkt(ACK, chksum) udt send(sndpkt)

rdt_rcv(rcvpkt) && (corrupt(rcvpkt) sndpkt = make_pkt(NAK, chksum) udt_send(sndpkt)

rdt_rcv(rcvpkt) && not corrupt(rcvpkt) && has_seq0(rcvpkt)

sndpkt = make_pkt(ACK, chksum) udt send(sndpkt)



udt_send(sndpkt)

rdt_rcv(rcvpkt) &&

has_seq1(rcvpkt)







rdt2.1: discussion

sender:

- seq # added to pkt
- two seq. #' s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
 - state must remember" whether 'expected" pkt should have seq # of 0 or I

receiver:

- must check if received packet is duplicate
 - state indicates whether 0 or 1 is expected pkt seq#
- note: receiver can not know if its last ACK/NAK received OK at sender









rdt2.2: a NAK-free protocol


- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt







rdt2.2: sender, receiver fragments









rdt3.0: channels with errors and loss

new assumption:

underlying channel can also lose packets (data, ACKs)

checksum, seq. #,
 ACKs, retransmissions
 will be of help ... but
 not enough

stop and wait sender sends one packet, then waits for receiver response

- approach: sender waits
 "reasonable" amount of
 time for ACK
- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but seq. #'s already handles this
 - receiver must specify seq # of pkt being ACKed
- requires countdown timer






Computer



rdt3.0 sender











rdt3.0 in action



(a) no loss

(b) packet loss










rdt3.0 in action

(c) ACK loss

sender receiver send pkt0 pkt0 rcv pkt0 send ack0 ack0 rcv ack0 pkt1 send pkt1 rcv pkt1 ack1 send ack1 loss timeout_ resend pkt1 pkt1 rcv pkt1 (detect duplicate) ack1 send ack1 rcv ack1 0tkي send pkt0 rcv pkt0 send ack0 ack0

(d) premature timeout/ delayed ACK











Performance of rdt3.0

- rdt3.0 is correct, but performance stinks
- e.g.: I Gbps link, I5 ms prop. delay, 8000 bit packet:

$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

U sender: utilization – fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$


- if RTT=30 msec, IKB pkt every 30 msec: 33kB/sec thruput over I Gbps link
- network protocol limits use of physical resources!







rdt3.0: stop-and-wait operation












Pipelined protocols



(a) a stop-and-wait protocol in operation








Pipelined protocols

pipelining: sender allows multiple, "in-flight", yetto-be-acknowledged pkts

- range of sequence numbers must be increased
- buffering at sender and/or receiver



(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation




李全龙





Pipelining: increased utilization
















window

- The *range* of *permissible* seq-num for sent but not yet acked pkts over the range of seq number space
- window size is N
- window sliding:
 - as the protocol operates, this window slides forward over the seq number space

Computer

□ Two generic forms of pipelined protocols: go-Back-N, selective repeat









Pipelined protocols: overview

Go-back-N:

- sender can have up to N unacked packets in pipeline
- receiver only sends cumulative ack
 - doesn't ack packet if there's a gap
- sender has timer for oldest unacked packet
 - when timer expires, retransmit all unacked packets

Selective Repeat:

- sender can have up to N unack'ed packets in pipeline
- rcvr sends individual ack for each packet

- sender maintains timer for each unacked packet
 - when timer expires, retransmit only that unacked packet










Go-Back-N: sender

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack'ed pkts allowed



- ACK(n): ACKs all pkts up to, including seq # n "cumulative ACK"
 - may receive duplicate ACKs (see receiver)
- timer for oldest in-flight pkt
- timeout(n): retransmit packet n and all higher seq # pkts in window







GBN: sender extended FSM

```
rdt_send(data)
                       if (nextseqnum < base+N) {
                          sndpkt[nextseqnum] = make_pkt(nextseqnum,data,chksum)
                          udt_send(sndpkt[nextseqnum])
                          if (base == nextseqnum)
                            start timer
                          nextseqnum++
                       else
   Λ
                         refuse_data(data)
   base=1
   nextseqnum=1
                                           timeout
                                           start_timer
                             Wait
                                           udt_send(sndpkt[base])
                                           udt_send(sndpkt[base+1])
rdt_rcv(rcvpkt)
 && corrupt(rcvpkt)
                                           udt_send(sndpkt[nextseqnum-1])
                         rdt_rcv(rcvpkt) &&
                           notcorrupt(rcvpkt)
                         base = getacknum(rcvpkt)+1
                         If (base == nextseqnum)
                            stop_timer
                           else
                            start_timer
```










GBN: receiver extended FSM



ACK-only: always send ACK for correctly-received pkt with highest *in-order* seq

- may generate duplicate ACKs
- need only remember expectedseqnum
- out-of-order pkt:
 - discard (don't buffer): no receiver buffering!
 - re-ACK pkt with highest in-order seq #










GBN in action



Computer



李全龙





例3-I

□ 数据链路层采用后退**N**帧(*GBN*)协议,发送方已经发送了编号为**0**~**7** 的帧。当计时器超时时,若发送方只收到**0**、**2**、**3**号帧的确认,则发送方需要重发的帧数是多少?分别是那几个帧?

□解:根据*GBN*协议工作原理,*GBN*协议的确认是累积确认,所以此时发送端需要重发的帧数是4个,依次分别是4、5、6、7号帧。



3: Transport Layer





Selective repeat


- receiver individually acknowledges all correctly received pkts
 - buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender only resends pkts for which ACK not received
 - sender timer for each unACKed pkt
- sender window
 - N consecutive seq #'s
 - limits seq #s of sent, unACKed pkts







Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers



李全龙

Computer Networks





Selective repeat

sender

data from above:

if next available seq # in window, send pkt

timeout(n):

resend pkt n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark pkt n as received
- if n smallest unACKed pkt, advance window base to next unACKed seq #

receiver.

pkt n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt

pkt n in [rcvbase-N,rcvbase-I]

ACK(n)

otherwise:


ignore













李全龙


Computer Networks




Selective repeat: dilemma

example:


- * seq #' s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- duplicate data accepted as new in (b)
- Q: what relationship between seq # size and window size to avoid problem in (b)?



receiver window (after receipt)



receiver can't see sender side. receiver behavior identical in both cases! something's (very) wrong!











Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control









TCP: Overview RFCs: 793,1122,1323, 2018, 2581

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- pipelined:
 - TCP congestion and flow control set window size

full duplex data:

- bi-directional data flow in same connection
- MSS: maximum segment size
- connection-oriented:
 - handshaking (exchange of control msgs) inits sender, receiver state before data exchange
- flow controlled:

Networks

sender will not overwhelm receiver



李全龙

Computer

3: Transport Layer





TCP segment structure


URG: urgent data (generally not used)

ACK: ACK # valid

PSH: push data now (generally not used)

RST, SYN, FIN: connection estab (setup, teardown commands)

> Internet checksum' (as in UDP)



counting
by bytes
of data
(not segments!)

bytes rcvr willing to accept







TCP seq. numbers, ACKs


sequence numbers:

byte stream "number" of first byte in segment's data

acknowledgements:

- seq # of next byte expected from other side
- cumulative ACK
- Q: how receiver handles out-of-order segments
 - A: TCP spec doesn't say,
 - up to implementor

outgoing segment from sender












TCP seq. numbers, ACKs



simple telnet scenario



李全龙

Computer Networks





Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control









TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
 - pipelined segments
 - cumulative acks
 - single retransmission timer
- retransmissions triggered by:
 - timeout events
 - duplicate acks

let's initially consider simplified TCP sender:

- ignore duplicate acks
- ignore flow control, congestion control









TCP sender events:

data rcvd from app:

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
 - think of timer as for oldest unacked segment
 - expiration interval:
 TimeOutInterval

timeout:

- retransmit segment that caused timeout
- restart timer ack rcvd:
- if ack acknowledges previously unacked segments
 - update what is known to be ACKed
 - start timer if there are still unacked segments










TCP sender (simplified)












TCP: retransmission scenarios






李全龙

Computer Networks





TCP: retransmission scenarios



premature timeout







TCP round trip time, timeout

- Q: how to set TCP timeout value?
- longer than RTT
 - but RTT varies
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT










TCP round trip time, timeout

EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT

- exponential weighted moving average
- influence of past sample decreases exponentially fast
- * typical value: $\alpha = 0.125$





李全龙





TCP round trip time, timeout

- * timeout interval: EstimatedRTT plus "safety margin"
 - large variation in EstimatedRTT -> larger safety margin
- estimate SampleRTT deviation from EstimatedRTT:

```
DevRTT = (1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT| (typically, \beta = 0.25)
```

TimeoutInterval = EstimatedRTT + 4*DevRTT



estimated RTT

"safety margin"







TCP ACK generation [RFC 1122, RFC 2581]

event at receiver	TCP receiver action
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send duplicate ACK, indicating seq. # of next expected byte
arrival of segment that partially or completely fills gap	immediate send ACK, provided that segment starts at lower end of gap



李全龙





TCP fast retransmit

- time-out period often relatively long:
 - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
 - sender often sends many segments backto-back
 - if segment is lost, there will likely be many duplicate ACKs.

if sender receives 3
ACKs for same data
("triple duplicate ACKs"),
resend unacked
segment with smallest
seq #

 likely that unacked segment lost, so don't wait for timeout










TCP fast retransmit



fast retransmit after sender receipt of triple duplicate ACK









Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control









application

TCP flow control

application may remove data from TCP socket buffers

... slower than TCP receiver is delivering (sender is sending)

OS TCP socket receiver buffers TCP code IΡ code from sender

application process

receiver protocol stack

flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

李全龙



Computer Networks


3: Transport Layer





TCP flow control

- receiver "advertises" free buffer space by including rwnd value in TCP header of receiver-to-sender segments
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust RcvBuffer
- sender limits amount of unacked ("in-flight") data to receiver's rwnd value
- guarantees receive buffer will not overflow



receiver-side buffering



李全龙





Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control










Connection Management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters



```
Socket clientSocket =
  newSocket("hostname","port
  number");
```

```
connection state: ESTAB connection Variables:
    seq # client-to-server
        server-to-client
    rcvBuffer size
    at server,client

network
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```











Agreeing to establish a connection

2-way handshake:





- Q: will 2-way handshake always work in network?
- variable delays
- retransmitted messages (e.g. req_conn(x)) due to message loss
- message reordering
- can't "see" other side












Agreeing to establish a connection

2-way handshake failure scenarios:










Computer



TCP 3-way handshake








李全龙

Computer





TCP 3-way handshake: FSM









TCP: closing a connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = I
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled










TCP: closing a connection











Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control









Principles of congestion control

congestion:


- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - lost packets (buffer overflow at routers)
 - long delays (queueing in router buffers)
- a top-10 problem!









- two senders, two receivers
- one router, infinite buffers
- output link capacity: R
- no retransmission





maximum per-connection throughput: R/2



* large delays as arrival rate, λ_{in} , approaches capacity










- one router, finite buffers
- sender retransmission of timed-out packet
 - application-layer input = application-layer output: $\lambda_{\text{in}} = \lambda_{\text{out}}$
 - transport-layer input includes retransmissions : $\lambda_{in} \ge \lambda_{in}$








Networks






idealization: perfect knowledge

 sender sends only when router buffers available








李全龙



Idealization: known loss

packets can be lost, dropped at router due to full buffers

sender only resends if packet known to be lost













Idealization: known loss packets can be lost, dropped at router due to full buffers

sender only resends if packet known to be lost















Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered








李全龙





Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered



"costs" of congestion:

- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
 - decreasing goodput










- four senders
- multihop paths
- timeout/retransmit

Q: what happens as λ_{in} and λ_{in} increase?

A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput $\rightarrow 0$

















another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!



李全龙





Approaches towards congestion control

two broad approaches towards congestion control:

end-end congestion control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate for sender to send at









Case study: ATM ABR congestion control

ABR: available bit rate:

- "elastic service"
- if sender's path "underloaded":
 - sender should use available bandwidth
- if sender's path congested:
 - sender throttled to minimum guaranteed rate

RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
 - NI bit: no increase in rate (mild congestion)
 - Cl bit: congestion indication
- RM cells returned to sender by receiver, with bits intact










Case study: ATM ABR congestion control



- two-byte ER (explicit rate) field in RM cell
 - congested switch may lower ER value in cell
 - senders' send rate thus max supportable rate on path
- EFCI bit in data cells: set to I in congested switch
 - if data cell preceding RM cell has EFCI set, receiver sets
 CI bit in returned RM cell









Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control








TCP congestion control: additive increase multiplicative decrease



- * approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase cwnd by I MSS every RTT until loss detected
 - multiplicative decrease: cut cwnd in half after loss

AIMD saw tooth behavior: probing for bandwidth






李全龙

cwnd: TCP sender



TCP Congestion Control: details





sender limits transmission:

$$\frac{\text{LastByteSent-}}{\text{LastByteAcked}} \leq \text{cwnd}$$

 cwnd is dynamic, function of perceived network congestion

TCP sending rate:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

Key: cwnd modify

Two phases:

- ➤ Slow start
- ➤ Congestion avoidance





Computer





TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = I MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast

Slowstart algorithm


initialize: cwnd = 1
for (each segment ACKed)
 cwnd++
until (loss event OR
 cwnd > ssthresh)







TCP Slow Start











TCP Congestion Avoidance

- Increase cwnd linearly
- Resulting in increase of cwnd by I MSS every RTT

Congestion avoidance









TCP: detecting, reacting to loss

- loss indicated by timeout:
 - cwnd set to 1 MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to I (timeout or 3 duplicate acks)










TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?

A: when **cwnd** gets to 1/2 of its value before timeout.



Implementation:


- variable ssthresh
 (threshold)
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event







Summary: TCP Congestion Control





李全龙






TCP throughput

- avg. TCP thruput as function of window size, RTT?
 - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is ³/₄ W
 - avg. thruput is 3/4W per RTT

avg TCP thruput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec

Computer









TCP Futures: TCP over "long, fat pipes"

- example: I500 byte segments, I00ms RTT, want
 I0 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- → to achieve 10 Gbps throughput, need a loss rate of L = $2^{-10^{-10}}$ a very small loss rate!
- new versions of TCP for high-speed








TCP Fairness

fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K










Why is TCP fair?

two competing sessions:

- additive increase gives slope of I, as throughout increases
- multiplicative decrease decreases throughput proportionally





李全龙

Networks Computer





Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss

Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
 - new app asks for I TCP, gets rate R/I0
 - new app asks for 11 TCPs, gets R/2









Chapter 3: summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation, implementation in the Internet
 - UDP
 - TCP

<u>next:</u>

- leaving the network "edge" (application, transport layers)
- into the network "core"



