BR Substitution – Substitution Services

Robin Lamacraft 2017-04-19

SCOPE

This module must be used anywhere an Encoded String requires substitution variable syntax checking or when the Encoded String has the substitution variables replaced with data values. Substitution values have 2 forms, a <u>standardized language-independent</u> form and a <u>user-language dependent</u> form. Essentially substitution variables are always stored using the language independent form and the user has the option to view or edit the Encoded String in either form.

Substitution Variables are classified by 5 attributes:

- 1. The type of data value to be output (e.g. text, date, number, etc)
- 2. The method to compose that data
- 3. The owner record type of that data
- 4. The subject object type in the request chain to access the data
- 5. The number of steps in the request navigation path.

By holding these as classification fields in the Substitution Dictionary, the same dictionary can be used for all substitution operations.


ACTIONS

- 1. To define or modify a Substitution Dictionary entry: Create, Edit, Save and Select
- 2. <u>To define or modify a language-specific alias</u> for a substitution variable or part of it: Create, Edit, Save and Select
- 3. <u>To return a substation variable</u> in the language-independent form or language dependent form
- 4. On request with a HRE_ID of the subject type, return the data value of the substation variable.

USED BY

Any use of an encoded string.

DATA CONTROLLED BY THIS MODULE



1. **SubstDict** Table: One record per Substitution

SQL FIELD NAME SQL FIELD TYPE

NOTES

HRE COMMON FIELDS FIRST		HRE_ID is SubstDict_ID
LABEL_ID	INT8 NOT NULL	Label HRE ID for translated label of this Substitution Variable
DATA_TYPE_ID	INT8 NOT NULL	HRE Data Type ID
DATA_COMP_ID	INT8 NOT NULL	HRE Composition Method ID
OWNER_TYPE_ID	INT8 NOT NULL	HRE Owner Type ID of that data
SUBJ_TYPE_ID	INT8 NOT NULL	HRE Subject Object Type ID
PARTS	INT4	Number of elements in variable path
PART_TYPE	INT4	1= Start, 2= Middle, 3= Data
SUBST_VAR	VARCHAR(200)	Standard Form Substitution Variable

The PRIMARY INDEX of this table is the HRE_ID. (SubstDict)

2. **SubstTrans** Table: One record for each Substitution Translation

SQL_FIELD NAME	SQL_FIELD TYPE	NOTES
HRE COMMON FIELDS FIRST		HRE_ID is SubstTrans_ID
PARENT_ID	INT8 NOT NULL	Parent HRE SubstDict ID
LANG_ID	INT8 NOT NULL	HRE Language ID
TRANS	VARCHAR(400)	Translation for this SubstitutionVariable in this language

The PRIMARY INDEX of this table is the HRE_ID. (SubstTrans)

REQUIRED SERVICES

- 1. BR_EntityLink
- 2. BR_Translation.

WARNING CONDITIONS

1. Need details of the condition that raised the warning, example message and possible next steps.

ERROR CONDITIONS

1. Need to record the condition that raised the error, example message and possible next steps.