Virtual Memory




Learning Outcomes

- An understanding of page-based virtual memory in depth.
 - Including the R3000's support for virtual memory.



Memory Management Unit (or TLB)




The position and function of the MMU




Virtual Address Space

- Virtual Memory
 - Divided into equalsized pages
 - A mapping is a translation between
 - A page and a frame
 - A page and null
 - Mappings defined at runtime
 - They can change
 - Address space can have holes
 - Process does not have to be contiguous in physical memory








Typical Address Space Layout


- Stack region is at top, and can grow down
- Heap has free space to grow up
- Text is typically read-only
- Kernel is in a reserved, protected, shared region
- 0-th page typically not used, why?

Virtual Address Space


- A process may be only partially resident
 - Allows OS to store individual pages on disk
 - Saves memory for infrequently used data & code
- What happens if we access nonresident memory?







Proc 2 Address Space




Disk

Page Faults

- Referencing an invalid page triggers a page fault
 - An exception handled by the OS
- Broadly, two standard page fault types
 - Illegal Address (protection error)
 - Signal or kill the process
 - Page not resident
 - Get an empty frame
 - Load page from disk
 - Update page (translation) table (enter frame #, set valid bit, etc.)
 - Restart the faulting instruction






Shared Pages

- Private code and data
 - Each process has own copy of code and data
 - Code and data can appear anywhere in the address space


- Shared code
 - Single copy of code shared between all processes executing it
 - Code must not be self modifying
 - Code must appear at same address in all processes





Page Table Structure

- Page table is (logically) an array of frame numbers
 - Index by page number
- Each page-table entry (PTE) also has other bits





Page 12

5

4

7

2

PTE Attributes (bits)

- Present/Absent bit
 - Also called valid bit, it indicates a valid mapping for the page
- Modified bit
 - Also called *dirty bit*, it indicates the page may have been modified in memory
- Reference bit
 - Indicates the page has been accessed
- Protection bits
 - Read permission, Write permission, Execute permission
 - Or combinations of the above
- Caching bit
 - Use to indicate processor should bypass the cache when accessing memory
 - Example: to access device registers or memory



Address Translation


- Every (virtual) memory address issued by the CPU must be translated to physical memory
 - Every load and every store instruction
 - Every instruction fetch
- Need Translation Hardware
- In paging system, translation involves replace page number with a frame number



Virtual Memory Summary

virtual and physical mem chopped up in pages/frames

- programs use virtual addresses
- virtual to physical mapping by MMU
 - -first check if page present
 (present/absent bit)
 - -if yes: address in page table form MSBs in physical address
 - if no: bring in the page from disk→ page fault





Page Tables

- Assume we have
 - 32-bit virtual address (4 Gbyte address space)
 - 4 KByte page size
 - How many page table entries do we need for one process?



Page Tables

- Assume we have
 - 64-bit virtual address (humungous address space)
 - 4 KByte page size
 - How many page table entries do we need for one process?
- Problem:
 - Page table is very large
 - Access has to be fast, lookup for every memory reference
 - Where do we store the page table?
 - Registers?
 - Main memory?



Page Tables

- Page tables are implemented as data structures in main memory
- Most processes do not use the full 4GB address space
 - − e.g., 0.1 − 1 MB text, 0.1 − 10 MB data, 0.1 MB stack
- We need a compact representation that does not waste space
 - But is still very fast to search
- Three basic schemes
 - Use data structures that adapt to sparsity
 - Use data structures which only represent resident pages
 - Use VM techniques for page tables (details left to extended OS)




Two-level Page Table

2nd –level
 page tables
 representing
 unmapped
 pages are not
 allocated

Bits 10 10 12
PT1 PT2 Offset
(a)


Null in the top-level page table



Second-level



Two-level Translation







Example Translations



Alternative: Inverted Page Table



Alternative: Inverted Page Table



Inverted Page Table (IPT)

- "Inverted page table" is an array of page numbers sorted (indexed) by frame number (it's a frame table).
- Algorithm
 - Compute hash of page number
 - Extract index from hash table
 - Use this to index into inverted page table
 - Match the PID and page number in the IPT entry
 - If match, use the index value as frame # for translation
 - If no match, get next candidate IPT entry from chain field
 - If NULL chain entry ⇒ page fault



Properties of IPTs

- IPT grows with size of RAM, NOT virtual address space
- Frame table is needed anyway (for page replacement, more later)
- Need a separate data structure for non-resident pages
- Saves a vast amount of space (especially on 64-bit systems)
- Used in some IBM and HP workstations




Given n processes

- how many page tables will the system have for
 - 'normal' page tables
 - inverted page tables?



Another look at sharing...






Improving the IPT: Hashed Page Table

- Retain fast lookup of IPT
 - A single memory reference in best case
- Retain page table sized based on physical memory size (not virtual)
 - Enable efficient frame sharing
 - Support more than one mapping for same frame




Hashed Page Table



HPT: Frame number stored in table




Hashed Page Table





| ppn | offset |
|------|--------|
| 0x42 | 0x123 |

Sharing Example





| ppn | offset |
|------|--------|
| 0x42 | 0x123 |

Sizing the Hashed Page Table

- HPT sized based on physical memory size
- With sharing
 - Each frame can have more than one PTE
 - More sharing increases number of slots used
 - Increases collision likelihood
- However, we can tune HPT size based on:
 - Physical memory size
 - Expected sharing
 - Hash collision avoidance.
 - HPT a power of 2 multiple of number of physical memory frame



VM Implementation Issue


Performance?

- Each virtual memory reference can cause two physical memory accesses
 - One to fetch the page table entry
 - One to fetch/store the data
 - ⇒Intolerable performance impact!!

Solution:

- High-speed cache for page table entries (PTEs)
 - Called a translation look-aside buffer (TLB)
 - Contains recently used page table entries
 - Associative, high-speed memory, similar to cache memory
 - May be under OS control (unlike memory cache)







Translation Lookaside Buffer

- Given a virtual address, processor examines the TLB
- If matching PTE found (TLB hit), the address is translated
- Otherwise (TLB miss), the page number is used to index the process's page table
 - If PT contains a valid entry, reload TLB and restart
 - Otherwise, (page fault) check if page is on disk
 - If on disk, swap it in
 - Otherwise, allocate a new page or raise an exception



TLB properties

- Page table is (logically) an array of frame numbers
- TLB holds a (recently used) subset of PT entries
 - Each TLB entry must be identified (tagged) with the page # it translates
 - Access is by associative lookup:
 - All TLB entries' tags are concurrently compared to the page #
 - TLB is associative (or content-addressable) memory

| page # | frame # | V | W |
|--------|---------|---|---|
| • • • | • • • | • | • |
| | • • • | • | |



TLB properties

- TLB may or may not be under direct OS control
 - Hardware-loaded TLB
 - On miss, hardware performs PT lookup and reloads TLB
 - Example: x86, ARM
 - Software-loaded TLB
 - On miss, hardware generates a TLB miss exception, and exception handler reloads TLB
 - Example: MIPS, Itanium (optionally)
- TLB size: typically 64-128 entries
- Can have separate TLBs for instruction fetch and data access
- TLBs can also be used with inverted page tables (and others)



TLB and context switching

- TLB is a shared piece of hardware
- Normal page tables are per-process (address space)
- TLB entries are *process-specific*
 - On context switch need to *flush* the TLB (invalidate all entries)
 - high context-switching overhead (Intel x86)
 - or tag entries with address-space ID (ASID)
 - called a tagged TLB
 - used (in some form) on all modern architectures
 - TLB entry: ASID, page #, frame #, valid and write-protect bits



TLB effect

- Without TLB
 - Average number of physical memory references per virtual reference
 - = 2
- With TLB (assume 99% hit ratio)
 - Average number of physical memory references per virtual reference

```
= .99 * 1 + 0.01 * 2
= 1.01
```




Recap - Simplified Components of VM System, Page Tables for 3


Virtual Address Spaces (3 processes) processes Frame Table **CPU TLB** Frame Pool



Recap - Simplified Components of VM System


Virtual Address Spaces (3 processes)







Recap - Simplified Components of VM System





MIPS R3000 TLB

31 6 11 5 12 0 **ASID** 0 VPN EntryHi Register (TLB key fields) 31 12 10 8 11 0PEN Ν ٧ G 0

EntryLo Register (TLB data fields)

- N = Not cacheable
- D = Dirty = Write protect
- G = Global (ignore ASID in lookup)

- V = valid bit
- 64 TLB entries
- Accessed via software through Cooprocessor 0 registers
 - EntryHi and EntryLo



- kseg0:
 - 512 megabytes
 - Fixed translation window to physical memory
 - 0x80000000 0x9fffffff virtual = 0x00000000 - 0x1fffffff physical
 - TLB not used
 - Cacheable
 - Only kernel-mode accessible
 - Usually where the kernel code is placed

0xffffffff kseg2 0xC0000000 kseg1 0xA0000000 kseg0 0x80000000 kuseg 0x00000000



Physical Memory

1,000

0xC0000000

0xFFFFFFF

kseg2

kuseg:

- 2 gigabytes
- TLB translated (mapped)
- Cacheable (depending on 'N' bit)
- user-mode and kernel mode accessible
- Page size is 4K

0xA0000000

0x80000000

kseg0

kseg1

kuseg



0x0000000


 Switching processes switches the translation (page table) for kuseg 0xFFFFFFF kseg2 0xC0000000 kseg1 0xA0000000 kseg0 0x80000000 Proc 3 kuseg 0x0000000

Proc 1 kuseg

Proc 2 kuseg

kseg1:

- 512 megabytes
- Fixed translation window to physical memory
 - 0xa0000000 0xbfffffff virtual = 0x00000000 - 0x1fffffff physical
 - TLB not used
- NOT cacheable
- Only kernel-mode accessible
- Where devices are accessed (and boot ROM)





Physical Memory