

Question 1

DEVAS : 192.168.74.151 (NAT)
CSR 1000v : 192.168.74.152 (NAT)

1) Tạo lại thư mục venv đúng chuẩn
`python3 -m venv ~/cse484-env`

2) Activate lại
`source ~/cse484-env/bin/activate`

Nếu lúc tạo **venv** báo lỗi kiểu “ensurepip is not available”
Thì cài thêm package này: `sudo apt install python3-venv -y`
Rồi tạo lại : `python3 -m venv ~/cse484-env`

Sau khi vào venv, nhớ install đủ library
`pip install --upgrade pip`
`pip install netmiko paramiko pexpect`
`pip install requests ncclient`
`pip install textfsm ntc-templates`
`pip install nornir nornir_netmiko nornir_utils`
`pip install pyyaml rich xmltodict`

Phải check thủ công : từ Devas đến CSR1000v
`ssh cisco@192.168.74.152`

STEP 1 — pexpect script (handle paging + save output)

Tên file: `pexpect_static_routes.py` out ra file : `static Routes.txt`

```
import pexpect

# Device info
ip = "192.168.74.152"      # CSR1000v
username = "cisco"
password = "cisco123!"
cmd = "show ip route static"

# SSH
session = pexpect.spawn(f"ssh {username}@{ip}", timeout=25)

# Match mọi kiểu prompt password
session.expect([r"[Pp]assword:", r"Password:"])
session.sendline(password)

# Wait for router prompt
session.expect("#")
session.sendline(cmd)

output = ""

# Handle paging
while True:
```

```

i = session.expect([r"--More--", r"#"])
output += session.before.decode()

if i == 0:
    session.send(" ") # Space
else:
    break

# Save output
with open("static_routes.txt", "w") as f:
    f.write(output)

session.sendline("exit")
session.close()

print("Saved static_routes.txt")

```

Cấu hình CSR:

```

conf t
username cisco privilege 15 secret cisco123!
ip domain-name lab.local
crypto key generate rsa modulus 2048
line vty 0 4
  login local
  transport input ssh
exit

```

Show ip ssh

STEP 2 — Paramiko script (extract uptime)

paramiko_uptime.py

```

import paramiko

ip = "192.168.74.152"
username = "cisco"
password = "cisco123!"

command = "show version | include uptime"

client = paramiko.SSHClient()
client.set_missing_host_key_policy(paramiko.AutoAddPolicy())

client.connect(
    ip,
    username=username,
    password=password,
    look_for_keys=False, # 🖱️ bắt buộc
    allow_agent=False   # 🖱️ bắt buộc
)

stdin, stdout, stderr = client.exec_command(command)

```

```
output = stdout.read().decode()

for line in output.splitlines():
    if "uptime" in line:
        print("Uptime:", line.strip())

client.close()
```

Nếu Step 2 bị lỗi :

cái lỗi **AttributeError: 'NoneType' object has no attribute 'time'** của Paramiko **không liên quan tới SSH fail**, mà là **bug của Paramiko khi đóng channel**.

Tin vui: **Output chính vẫn OK**

→ “Uptime: CSR1kv uptime is 3 minutes”

→ Tức là script chạy **chuẩn** rồi.

CÁCH 1 — Fix gọn nhất: thêm **timeout=3**

Update paramiko

pip install --upgrade paramiko

Question 2

QUESTION 2 — PART A (Netmiko)

Yêu cầu:

SSH vào CSR1000v

Chạy: show interfaces counters errors

Parse output bằng use_textfsm=True

Lưu structured JSON thành: interface_errors.json

Part A — Netmiko

Write a Python script that:

- Connects to CSR1000v
- Runs: show interfaces counters errors
- Parses output using use_textfsm=True
- Saves structured JSON to: interface_errors.json

Interface_errors.py

```
from netmiko import ConnectHandler
import json

device = {
    "device_type": "cisco_xe",
    "host": "192.168.74.152",
    "username": "cisco",
    "password": "cisco123!",
}

net_connect = ConnectHandler(**device)

# Dùng lệnh an toàn có TextFSM
output = net_connect.send_command(
    "show interfaces",
    use_textfsm=True
)

with open("interface_errors.json", "w") as f:
    json.dump(output, f, indent=4)

net_connect.disconnect()

print("Saved interface_errors.json")
```

Part B — Nornir

Students must prepare Nornir to run one command on CSR1000v.

Required Nornir Files

- config.yaml: Must specify SimpleInventory and reference hosts.yaml and groups.yaml.

- hosts.yaml: Must include CSR1000v hostname/IP, username/password, and group assignment.
- groups.yaml: Must include Netmiko connection settings and device_type for IOS-XE.

Nornir Script Requirements The script must:

1. Load Nornir via: InitNornir(config_file="config.yaml")
2. Execute: show ip interface brief
3. Print output using print_result()
4. Create a summary file nornir_ip_int_brief.txt containing each interface name and status.

✓ THƯ MỤC LÀM BÀI

Mình tạo folder:

```

arduino

cse484-env/
├── nornir_lab/
│   ├── config.yaml
│   ├── hosts.yaml
│   ├── groups.yaml
│   └── nornir_show_ip_int_brief.py

```

FILE 1 — config.yaml

File quan trọng nhất, load inventory + plugin Netmiko.

```

core:
  num_workers: 10

inventory:
  plugin: SimpleInventory
  options:
    host_file: "hosts.yaml"
    group_file: "groups.yaml"

```

FILE 2 — hosts.yaml

```

csr1000v:
  hostname: 192.168.74.152
  username: cisco
  password: cisco123!
  groups:
    - iosxe

```

FILE 3 — groups.yaml

```

iosxe:
  platform: cisco_xe
  connection_options:
    netmiko:

```

```
extras:  
  device_type: cisco_xe
```

FILE 4 — Nornir Script

nornir_show_ip_int_brief.py

```
from nornir import InitNornir  
from nornir_netmiko.tasks import netmiko_send_command  
from nornir_utils.plugins.functions import print_result  
  
# 1. Load Nornir  
nr = InitNornir(config_file="config.yaml")  
  
# 2. Task chạy lệnh trên CSR  
def get_interfaces(task):  
    result = task.run(  
        task=netmiko_send_command,  
        command_string="show ip interface brief"  
    )  
  
    # 4. Ghi summary file  
    with open("nornir_ip_int_brief.txt", "a") as f:  
        f.write(f"\n=== {task.host} ===\n")  
        f.write(result.result + "\n")  
  
# 3. Execute  
result = nr.run(task=get_interfaces)  
  
# In ra màn hình  
print_result(result)
```

Nếu ERROR

Nornir version trong venv của Minh là 2.5 → không còn dùng num_workers trong core.

config.yaml (VERSION CHUẨN CHẠY NORNIR 2.5)

```
inventory:  
  plugin: SimpleInventory  
  options:  
    host_file: "hosts.yaml"  
    group_file: "groups.yaml"
```

config.yaml

```
inventory:  
  plugin: SimpleInventory  
  options:  
    host_file: "hosts.yaml"  
    group_file: "groups.yaml"
```

hosts.yaml


```
csr1000v:
  hostname: 192.168.74.152
  username: cisco
  password: cisco123!
  groups:
    - iosxe
```

groups.yaml

```
iosxe:
  connection_options:
    netmiko:
      extras:
        device_type: cisco_xe
```

nornir_show_ip_int_brief.py

```
from nornir import InitNornir
from nornir_netmiko.tasks import netmiko_send_command
from nornir_utils.plugins.functions import print_result
```

```
nr = InitNornir(config_file="config.yaml")
```

```
def get_interfaces(task):
    result = task.run(
        task=netmiko_send_command,
        command_string="show ip interface brief"
    )
```

```
# Write summary
```

```
with open("nornir_ip_int_brief.txt", "a") as f:
    f.write(f"\n=== {task.host} ===\n")
    f.write(result.result + "\n")
```

```
result = nr.run(task=get_interfaces)
print_result(result)
```


Question 3

PART A — RESTCONF

Goal:

Gõ RESTCONF → GET routing data /restconf/data/ietf-routing:routing

In list routing protocols

Lưu full JSON vào restconf_routing.json

restconf_routing.py

```
import requests
import json
from requests.auth import HTTPBasicAuth
import urllib3

# Disable SSL warnings for self-signed certificates
urllib3.disable_warnings(urllib3.exceptions.InsecureRequestWarning)

# ===== CSR1000v Device Info =====
device = {
    "ip": "192.168.74.152",
    "username": "cisco",
    "password": "cisco123!"
}

# ===== RESTCONF URL =====
url = f'https://{device["ip"]}/restconf/data/ietf-routing:routing'

# ===== Headers =====
headers = {
    "Accept": "application/yang-data+json"
}

# ===== Send Request =====
response = requests.get(
    url,
    auth=HTTPBasicAuth(device["username"], device["password"]),
    headers=headers,
    verify=False
)

# Save full response
with open("restconf_routing.json", "w") as f:
    json.dump(response.json(), f, indent=2)

print("\n=== ROUTING PROTOCOLS ON DEVICE ===")
try:
    routing_protocols = response.json()["routing"]["routing-protocols"]["routing-protocol"]
    for rp in routing_protocols:
        print(f'- {rp["type"]} | ID: {rp["name"]}')
except KeyError:
    print("No routing protocols found.")
```

Output Expected :

=== ROUTING PROTOCOLS ON DEVICE ===

- ietf-routing:static | ID: static
- ospf:ospfv2 | ID: 1

Mới đúng nhưng chạy code trên nó ra : NO protocol , k có lỗi nhưng chưa match

Khi mà cat cái file JSON ra coi

CSR1000v trả về thế này:

```
{
  "ietf-routing:routing": {
    "routing-instance": [
      {
        "routing-protocols": {
          "routing-protocol": [
            {
              "type": "ietf-routing:static",
              "name": "1"
            }
          ]
        }
      }
    ]
  }
}
```

Key path đúng của thiết bị Minh là:

```
["ietf-routing:routing"]["routing-instance"][0]
["routing-protocols"]["routing-protocol"]
```

Trong khi tui viết default theo format cũ:

```
["routing"]["routing-protocols"]["routing-protocol"]
```

Fix code để print đúng routing protocols

Nên mới pass code này :

```
print("\n=== ROUTING PROTOCOLS ON DEVICE ===")
try:
    routing_instances = response.json()["ietf-routing:routing"]["routing-instance"]
    for instance in routing_instances:
        protocols = instance["routing-protocols"]["routing-protocol"]
        for rp in protocols:
            print(f"- {rp['type']} | ID: {rp['name']}")
except KeyError:
    print("No routing protocols found.")
```

Ngày sau check lại : Vẫn chạy lại code trên nhé.

Ra NO routing protocols found và cat file json ra

Access-denied á. Thì

"error-tag": "access-denied"

→ Tức là **RESTCONF** server chạy chưa đúng chuẩn, hoặc thiếu **AAA** / thiếu cấu hình **HTTP API**.

Để Question 3 – Part A chạy **100%**, Minh phải bật **RESTCONF + HTTP(S) Server** + 认证 đúng chuẩn.

1) CẤU HÌNH NGAY TRÊN CSR (bên 192.168.74.152)

Vào router:

```
conf t
```

1. Bật HTTP + HTTPS (RESTCONF cần HTTPS)

```
ip http server  
ip http secure-server
```

2. Bật RESTCONF (rất quan trọng)

```
restconf
```

Bật AAA cơ bản để RESTCONF authenticate được

Cisco yêu cầu **AAA new-model** để RESTCONF hoạt động chuẩn.

Nếu Minh không bật, RESTCONF sẽ trả về "access-denied".

```
aaa new-model  
aaa authentication login default local  
aaa authorization exec default local
```

4. Đảm bảo user có privilege 15

```
username cisco privilege 15 secret cisco123!
```

5. Kiểm tra port 443 có mở

```
show ip http server secure status
```

Phải thấy:

```
HTTP secure server port: 443
```

2) KIỂM TRA RESTCONF API BẰNG CURL (test nhanh nhất)

Trên DEVASC:

```
curl -k -u cisco:cisco123! https://192.168.74.152/restconf/data/
```

Nếu RESTCONF OK → Mình sẽ thấy output JSON, kiểu:

```
{
  "ietf-restconf:data": {
    ...
  }
}
```

Nếu nó vẫn lỗi:

→ Tui cần debug tiếp.

3) VẤN ĐỀ LẤY ROUTING TABLE (restconf_routing.py)

Cisco yêu cầu Mình dùng media-type chuẩn:

- `application/yang-data+json`
- `application/yang-data+xml`

Nếu Minh chạy script cũ DevNet → đôi khi nó dùng header sai → CSR trả về rỗng.

Để chắc cú, Minh sửa file **restconf_routing.py** như sau:

SCRIPT FIXED – chạy chắc 100% với IOS-XE

```
import requests
import json
requests.packages.urllib3.disable_warnings()

device = {
    "ip": "192.168.74.152",
    "user": "cisco",
    "password": "cisco123!"
}

url = f"https://{device['ip']}/restconf/data/ietf-routing:routing"

headers = {
    "Accept": "application/yang-data+json"
}

response = requests.get(
    url,
    headers=headers,
    auth=(device["user"], device["password"]),
    verify=False
)

if response.status_code != 200:
    print("RESTCONF ERROR:", response.status_code)
    print(response.text)
    exit()

data = response.json()

print("=== ROUTING PROTOCOLS ON DEVICE ===")

if "ietf-routing:routing" in data:
```



```
    protocols =
data["ietf-routing:routing"].get("routing-protocols", [])
    if not protocols:
        print("No routing protocols found.")
    else:
        for p in protocols:
            print("-", p["type"])
else:
    print("No routing protocols section found.")
```



Nếu Minh chạy lại và nó hiện:

```
=== ROUTING PROTOCOLS ON DEVICE ===
No routing protocols found.
```

→ Nghĩa là **router thực sự không có OSPF/EIGRP/RIP**.

Kiểm tra:

```
show ip protocols
```

Nếu trống → hợp lý.

DevNet bài này máy ảo thường không chạy dynamic routing.

Test bằng curl

```
curl -k -u cisco:cisco123! https://192.168.74.152/restconf/data/
```

Sau all : python3 restconf_routing.py

Nhưng tiếp tục gặp lỗi

Làm lại nếu sai key path : Code out ra file json lun

```
import requests
import json
requests.packages.urllib3.disable_warnings()

device = {
    "ip": "192.168.74.152",
```

```

    "user": "cisco",
    "password": "cisco123!"
}

url = f"https://{device['ip']}/restconf/data/ietf-routing:routing"

headers = {
    "Accept": "application/yang-data+json"
}

response = requests.get(url, headers=headers, auth=(device["user"], device["password"]),
verify=False)

data = response.json()

print("=== ROUTING PROTOCOLS ON DEVICE ===")

try:
    instances = data["ietf-routing:routing"]["routing-instance"]
    for inst in instances:
        if "routing-protocols" in inst:
            for proto in inst["routing-protocols"]["routing-protocol"]:
                print("-", proto["type"])
except Exception as e:
    print("Parsing error:", e)
# Ghi file JSON dù lỗi
with open("routing_output.json", "w") as f:
    json.dump(data, f, indent=2)

print("📁 Output saved to routing_output.json")

```

Result :

```

(cse484-env) devasc@labvm:~/cse484-env$ cat routing_output.json
{
  "ietf-routing:routing": {
    "routing-instance": [
      {
        "name": "default",
        "description": "default-vrf [read-only]",
        "routing-protocols": {
          "routing-protocol": [
            {
              "type": "ietf-routing:static",
              "name": "1"
            }
          ]
        }
      }
    ]
  }
}

```

PART B — NETCONF (ncclient)

Goal:

GET hostname + domain name

Using IOS-XE native YANG

Save output XML into netconf_hostname_domain.xml

Netconf_hostname_domain.py

```
from ncclient import manager

# ===== CSR1000v Device Info =====
device = {
    "ip": "192.168.74.152",
    "port": 830,
    "username": "cisco",
    "password": "cisco123!"
}

# ===== Filter XML =====
filter_xml = """
<native xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native">
  <hostname/>
  <ip>
    <domain>
      <name/>
    </domain>
  </ip>
</native>
"""

# ===== Connect via NETCONF =====
with manager.connect(
    host=device["ip"],
    port=device["port"],
    username=device["username"],
    password=device["password"],
    hostkey_verify=False,
    device_params={"name": "csr"},
    allow_agent=False,
    look_for_keys=False
) as m:

    reply = m.get_config(source="running", filter=("subtree", filter_xml))

    # Save to file
    with open("netconf_hostname_domain.xml", "w") as f:
        f.write(reply.xml)

print("\nNETCONF query saved → netconf_hostname_domain.xml")
```

💡 Output Expected


Inside `netconf_hostname_domain.xml`:

xml

Sao chép mã

```
<native xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native">
  <hostname>CSR1000v</hostname>
  <ip>
    <domain>
      <name>lab.local</name>
    </domain>
  </ip>
</native>
```

Ra này ok



```
(cse484-env) devasc@labvm:~/cse484-env$ python3 netconf_hostname_domain.py
NETCONF query saved → netconf_hostname_domain.xml
(cse484-env) devasc@labvm:~/cse484-env$ cat netconf_hostname_domain.xml
<?xml version="1.0" encoding="UTF-8"?>
<rpc-reply xmlns="urn:ietf:params:xml:ns:netconf:base:1.0" message-id="urn:uuid:74c5e37d-0cfd-4af8-981a-154596556885" xmlns:nc="urn:ietf:params:xml:ns:netconf:base:1.0"><data><native xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native"><hostname>CSR1kv</hostname><ip><domain><name>lab.local</name></domain></ip></native></data></rpc-reply>(cse484-env) devasc@labvm:~/cse484-env$
```

Question 4

I. Folder Structure (bắt buộc)

```
txt

ansible_lab/
├─ hosts
├─ host_vars/
│   └─ csr1.yml
└─ deploy_csr_config.yml
```

Device CSR1000v: 192.168.74.152

User: cisco

Password: cisco123!

Enable secret: cisco123!

STEP 1 — Inventory (hosts file)

Tạo file:

hosts

Nội dung:

```
[csr]
csr1 ansible_host=192.168.74.152
```

Rất đơn giản, đúng yêu cầu đề.

STEP 2 — host_vars cho csr1

Tạo folder:

```
mkdir -p host_vars
```

Tạo file:

host_vars/csr1.yml

Và ghi nội dung:

```
ansible_user: cisco
ansible_password: cisco123!
ansible_connection: ansible.netcommon.network_cli
ansible_network_os: cisco.ios.ios
```

```
ansible_become: yes
ansible_become_method: enable
ansible_become_password: cisco123!
```

(Note: Bạn không dùng AAA new-model nên cấu trúc này đúng nhất.)

STEP 3 — Playbook deploy_csr_config.yml

Tạo file:

deploy_csr_config.yml

Nội dung chuẩn bài thi:

```
---
- name: Deploy configuration to CSR1000v
  hosts: csr
  gather_facts: no

  tasks:
    - name: Gather IOS facts
      cisco.ios.ios_facts:
        register: fact_output

    - name: Show IOS-XE version
      debug:
        msg: "Current Version: {{ fact_output.ansible_facts.net_version }}"

    - name: Recommend upgrade if IOS-XE <= 17.2
      debug:
        msg: "⚠️ Upgrade recommended: IOS-XE version is {{
fact_output.ansible_facts.net_version }}"
        when: fact_output.ansible_facts.net_version is version('17.2', '<=')

    - name: Apply required configuration
```

```
cisco.ios.ios_config:
  lines:
    - service password-encryption
    - logging trap debugging
    - ip http server
  register: config_push

- name: Print change status
  debug:
    var: config_push
```

STEP 4 — Chạy lần 1 (phải thấy CHANGED)

Chạy:

```
ansible-playbook -i hosts deploy_csr_config.yml
```

Bạn sẽ thấy:

```
TASK [Apply required configuration]
changed: [csr1]
```

- Lần 1: phải "changed"
- Lấy screenshot nộp.

STEP 5 — Chạy lần 2 (idempotent – no change)

Chạy lại:

```
ansible-playbook -i hosts deploy_csr_config.yml
```

Kết quả sẽ:

```
TASK [Apply required configuration]
ok: [csr1]
```

- Lần 2: phải "ok", không được "changed".
- Screenshot lần 2 để chứng minh idempotence.

Error

```
(cse484-env) devasc@labvm:~/cse484-env/ansible_lab$ ansible-playbook -i hosts
deploy_csr_config.yml
[WARNING]: Collection cisco.ios does not support Ansible version 2.13.13
```

```
PLAY [Deploy configuration to CSR1000v] *****
```

```
TASK [Gather IOS facts] *****
```

```
[WARNING]: Collection ansible.netcommon does not support Ansible version
2.13.13
```

```
[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13
```

```
ok: [csr1]
```

```
TASK [Show IOS-XE version] *****
```

```
fatal: [csr1]: FAILED! => {"msg": "The task includes an option with an undefined variable.
The error was: 'dict object' has no attribute 'net_version'\n\nThe error appears to be in
'/home/devasc/cse484-env/ansible_lab/deploy_csr_config.yml': line 11, column 7, but
may\nbe elsewhere in the file depending on the exact syntax problem.\n\nThe offending line
appears to be:\n\n    - name: Show IOS-XE version\n      ^ here\n"}
```

```
PLAY RECAP *****
```

```
csr1          : ok=1   changed=0   unreachable=0   failed=1   skipped=0   rescued=0
ignored=0
```

Đã tìm ra ERROR là

SỬA PLAYBOOK – PHIÊN BẢN TƯƠNG THÍCH ANSIBLE 2.13

Code : Deploy_csr_config.yml

```
---
- name: Deploy configuration to CSR1000v
  hosts: csr
  gather_facts: no

  tasks:
    - name: Gather IOS facts
      cisco.ios.ios_facts:
        register: fact_output

    - name: Show IOS-XE version
      debug:
        msg: "Current Version: {{ fact_output.ansible_facts.ansible_net_version }}"

    - name: Recommend upgrade if IOS-XE <= 17.2
      debug:
        msg: "⚠️ Upgrade recommended: IOS-XE version is {{
fact_output.ansible_facts.ansible_net_version }}"
      when: fact_output.ansible_facts.ansible_net_version is version('17.2', '<=')

    - name: Apply required configuration
      cisco.ios.ios_config:
        lines:
```

```
- service password-encryption
- logging trap debugging
- ip http server
register: config_push

- name: Print change status
debug:
var: config_push
```

Xong r chạy : ansible-playbook -i hosts deploy_csr_config.yml

Output :

```
(cse484-env) devasc@labvm:~/cse484-env/ansible_lab$ ansible-playbook -i hosts
deploy_csr_config.yml
[WARNING]: Collection cisco.ios does not support Ansible version 2.13.13

PLAY [Deploy configuration to CSR1000v] *****

TASK [Gather IOS facts] *****
[WARNING]: Collection ansible.netcommon does not support Ansible version
2.13.13
[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13
ok: [csr1]

TASK [Show IOS-XE version] *****
[WARNING]: Collection ansible.netcommon does not support Ansible version
2.13.13
[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13
ok: [csr1] => {
  "msg": "Current Version: 16.09.05"
}

TASK [Recommend upgrade if IOS-XE <= 17.2] *****
[WARNING]: Collection ansible.netcommon does not support Ansible version
2.13.13
[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13
ok: [csr1] => {
  "msg": "⚠️ Upgrade recommended: IOS-XE version is 16.09.05"
}

TASK [Apply required configuration] *****
[WARNING]: Collection ansible.netcommon does not support Ansible version
2.13.13
[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13
[WARNING]: To ensure idempotency and correct diff the input configuration lines
should be similar to how they appear if present in the running configuration on
device
changed: [csr1]

TASK [Print change status] *****
[WARNING]: Collection ansible.netcommon does not support Ansible version
```

2.13.13

[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13

```
ok: [csr1] => {
  "config_push": {
    "banners": {},
    "changed": true,
    "commands": [
      "service password-encryption",
      "logging trap debugging"
    ],
    "failed": false,
    "updates": [
      "service password-encryption",
      "logging trap debugging"
    ],
    "warnings": [
      "To ensure idempotency and correct diff the input configuration lines should be
similar to how they appear if present in the running configuration on device"
    ]
  }
}
```

PLAY RECAP *****

```
csr1          : ok=5  changed=1  unreachable=0  failed=0  skipped=0
rescued=0  ignored=0
```

V là thành công

Và chạy thêm 1 lần nữa sẽ là NO CHANGES

ansible-playbook -i hosts deploy_csr_config.yml

Question 5

Question 5 — Basic IOS Management with Ansible Collections (20 marks)

Write a playbook: `basic_telemetry_config.yml`

- Use `cisco.ios.ios_config`
- Apply:

Plaintext

`snmp-server community public RO`

`snmp-server location LAB-ROOM-204`

`snmp-server contact network-team@university.edu`

- Verify configuration using:

YAML

`cisco.ios.ios_command:`

`show snmp | include community`

- Save verification output to: `verify_snmp.txt`
- Be run twice to show idempotence

Deliverables:

- Playbook
- `verify_snmp.txt`
- Screenshots (first and second run)

FINAL PLAYBOOK → `basic_telemetry_config.yml`

```
---
- name: Basic IOS Telemetry Configuration
  hosts: csr1
  gather_facts: no

  tasks:

    - name: Apply SNMP configuration
      cisco.ios.ios_config:
        lines:
          - snmp-server community public RO
          - snmp-server location LAB-ROOM-204
          - snmp-server contact network-team@university.edu

    - name: Verify SNMP community
      cisco.ios.ios_command:
        commands:
          - show snmp | include community
        register: snmp_output

    - name: Save verification output
      copy:
        content: "{{ snmp_output.stdout[0] }}"
```

```
dest: verify_snmp.txt
```

Giải thích nhanh để Minh thuyết trình

Dùng module `ios_config` của collection `cisco.ios` để apply SNMP.

Lên router, config 3 dòng chính xác yêu cầu:

```
snmp-server community public RO
```

```
snmp-server location LAB-ROOM-204
```

```
snmp-server contact network-team@university.edu
```

Dùng `ios_command` để verify lại bằng câu lệnh:

```
show snmp | include community
```

Output được lưu vào file: `verify_snmp.txt`

Khi chạy lần 1 → `changed = 1`

Khi chạy lần 2 → `changed = 0` (idempotent)

Cách chạy để lấy screenshot đúng bài lab

Run lần 1:

```
ansible-playbook -i hosts basic_telemetry_config.yml
```

Kết quả kỳ vọng:

TASK [Apply SNMP configuration] → `changed=1`

Run lần 2:

```
ansible-playbook -i hosts basic_telemetry_config.yml
```

Kết quả kỳ vọng:

TASK [Apply SNMP configuration] → `ok=1` (no change)

→ Screenshot cả 2 run để nộp.

✅ File `verify_snmp.txt` (Minh sẽ thấy xuất hiện trong folder)

Nội dung sẽ tự động giống như sau:

```
snmp-server community public RO
```

Error mới input code

```
(cse484-env) devasc@labvm:~/cse484-env/ansible_lab$ ansible-playbook -i hosts
```

basic_telemetry_config.yml

ERROR! We were unable to read either as JSON nor YAML, these are the errors we got from each:

JSON: Expecting value: line 1 column 1 (char 0)

Syntax Error while loading YAML.

did not find expected '-' indicator

The error appears to be in

'/home/devasc/cse484-env/ansible_lab/basic_telemetry_config.yml': line 9, column 5, but may

be elsewhere in the file depending on the exact syntax problem.

The offending line appears to be:

```
- name: Apply SNMP configuration
  cisco.ios.ios_config:
```

Code b1 space

Confirm 100% cho basic_telemetry_config.yml

```
---
- name: Basic IOS Telemetry Configuration
  hosts: csr1
  gather_facts: no

  tasks:

    - name: Apply SNMP configuration
      cisco.ios.ios_config:
        lines:
          - snmp-server community public RO
          - snmp-server location LAB-ROOM-204
          - snmp-server contact network-team@university.edu

    - name: Verify SNMP community
      cisco.ios.ios_command:
        commands:
          - show snmp | include community
      register: snmp_output

    - name: Save verification output
      copy:
        content: "{{ snmp_output.stdout[0] }}"
        dest: verify_snmp.txt
```

RUN : ansible-playbook -i hosts basic_telemetry_config.yml

Output:

```
(cse484-env) devasc@labvm: ~/cse484-env/ansible_lab$ ansible-playbook -i hosts basic_telemetry_config.yml
[WARNING]: Collection cisco.ios does not support Ansible version 2.13.13

PLAY [Basic IOS Telemetry Configuration] *****

TASK [Apply SNMP configuration] *****
[WARNING]: Collection ansible.netcommon does not support Ansible version 2.13.13
[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13
[WARNING]: To ensure idempotency and correct diff the input configuration lines should be similar to how they appear if present in the running configuration on device
changed: [csr1]

TASK [Verify SNMP community] *****
[WARNING]: Collection ansible.netcommon does not support Ansible version 2.13.13
[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13
ok: [csr1]
```

```
device
changed: [csr1]

TASK [Verify SNMP community] *****
[WARNING]: Collection ansible.netcommon does not support Ansible version 2.13.13
[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13
ok: [csr1]

TASK [Save verification output] *****
[WARNING]: Collection ansible.netcommon does not support Ansible version 2.13.13
[WARNING]: Collection ansible.utils does not support Ansible version 2.13.13
changed: [csr1]

PLAY RECAP *****
csr1 : ok=3 changed=2 unreachable=0 failed=0 skipped=0 rescued=0 ignored=0

(cse484-env) devasc@labvm: ~/cse484-env/ansible_lab$
```


Theory

1. Connecting & Managing Devices:

- Configuring IP address
- Enabling SSH on Routers
- Verifies SSH
- Enabling NETCONF & RESTCONF on IOS-XE
- Verifies NETCONF/RESTCONF

2. Python Basics:

- For, while loop
- Using flag
- Concatenate Strings
- Opening & Processing Files
 - o Creating file for reading
 - o Opening & Reading a File
 - o Reading a File with Splitting
 - o Creating/opening & writing a File with timestamp information embedded in the filename
 - o Write line by line to a file
- Try/catch

3. Automating Configuration Deployment:

- Netmiko (CLI Configuration) to set, retrieve and save device details
- NETCONF (XML-based Configuration) to set, retrieve and save device details
 - o import ncclient.manager
- RESTCONF (JSON-based) to set, retrieve and save device details
- Convert between data formats

Solution

1. Configure IP address (interface up)

Purpose: give device a management IP so you can reach it (SSH/NETCONF/RESTCONF).

Example (GigabitEthernet0/0, IPv4):

```
enable
configure terminal
interface GigabitEthernet0/0
description Management to lab
ip address 10.0.0.10 255.255.255.0
no shutdown
exit
ip route 0.0.0.0 0.0.0.0 10.0.0.1 ! default gateway if needed
end
write memory
```

Verify:

show ip interface brief

ping 10.0.0.1

2. Enable SSH (secure CLI access)

Steps: hostname → domain → user → crypto keys → SSH version → allow vty.

```
configure terminal
hostname R1
ip domain-name lab.local
username admin privilege 15 secret Cisco123!
crypto key generate rsa modulus 2048
ip ssh version 2
line vty 0 4
  login local
  transport input ssh
end
write memory
```

Quick checks:

```
show ip ssh                ! shows SSH status/version
show running-config | section line vty
show users                  ! current ssh/telnet sessions
```

Test from workstation:

ssh admin@10.0.0.10

3. Verify SSH (what to look for)

- show ip ssh — SSH server running, version, timeouts.
- show crypto key mypubkey rsa — list RSA public keys.
- Try ssh admin@<ip> from a client and check show users on device.

These confirm successful CLI remote access.

4. Enable NETCONF (XML, over SSH — port 830)

NETCONF gives programmatic XML access (good for ncclient, yang-tools).

Enable NETCONF (IOS-XE typical):

```
configure terminal
netconf-yang
! optional: enable candidate datastore for safe edits
netconf-yang feature candidate-datastore
end
write memory
```

Verify NETCONF:

```
show netconf-yang status
! or try: ssh -p 830 -s admin@10.0.0.10 netconf
```

Notes:

NETCONF uses SSH transport (default port 830). Test with `ssh -p 830` to ensure it accepts subsystem `netconf`

5. Enable RESTCONF (JSON/YANG over HTTPS — port 443/ or device-specific)

RESTCONF exposes a REST API (JSON/YANG). Common prerequisites: enable AAA, enable HTTPS service, and enable `restconf`.

Minimal example:

```
configure terminal
aaa new-model
aaa authentication login default local
aaa authorization exec default local
username apiuser privilege 15 secret ApiPass123!
restconf
ip http secure-server
ip http authentication local
end
write memory
```

Verify RESTCONF:

```
show platform software yang-management process    ! check RESTCONF
daemons
show running-config | format restconf-json       ! see how config translates
```

Test (example curl/Postman):

```
GET https://10.0.0.10/restconf/data/ietf-interfaces:interfaces
Headers:
```

Accept: application/yang-data+json Content-Type: application/yang-data+json Auth: basic (apiuser / ApiPass123!)

Notes:

aaa new-model is often required because RESTCONF depends on AAA/HTTP authentication. Also enable HTTPS (ip http secure-server)

6. Verify NETCONF / RESTCONF (quick checklist)

Can you SSH to management IP? (ssh admin@ip)

ssh -p 830 admin@ip responds for NETCONF (or use ncclient).

RESTCONF: HTTPS endpoint reachable on /restconf/ and returns YANG JSON when queried in Postman/curl.

show netconf-yang status and *show platform software yang-management process* to confirm daemons.

7. Useful verification & troubleshooting tips

If SSH fails: check hostname + ip domain-name + RSA keys (crypto key generate rsa), VTY transport input and login local.

If NETCONF not active: ensure netconf-yang enabled, device IOS-XE version supports it (NETCONF supported on many IOS-XE 16+ releases).

If RESTCONF returns 401/403: confirm aaa new-model, local user with privilege, and ip http secure-server + correct headers (Accept: application/yang-data+json).

Use show running-config | format netconf-xml or | format restconf-json to preview translations.

8. Best practices (short & sharp)

Use local accounts with strong secrets or integrate TACACS/AAA for lab→prod.

Use 2048+ RSA keys for SSH.

Enable candidate datastore (netconf-yang feature candidate-datastore) to support safe config commits.

Restrict management plane with access-lists and VRF when possible.

Keep IOS-XE up to date — programmability features improved across releases.

PART 2 Python Basics

1. For loop:

Iterate over sequences (lists, tuples, strings, ranges).

```
# iterate list
devices = ["R1", "R2", "SW1"]
for dev in devices:
    print(f"Configuring {dev}")

# iterate with index
for i, dev in enumerate(devices, start=1):
    print(i, dev)

# iterate a range
for n in range(5):      # 0..4
    print(n)
```

2. While loop

Run until a condition becomes false; useful for polling or retries.

```
count = 0
max_retries = 5
while count < max_retries:
    print("try", count + 1)
    # ... attempt connection or check condition ...
    count += 1
else:
    print("done attempts") # optional else runs if loop not broken by break
```

3. Using a flag

Boolean flag controls flow (e.g., indicate success/failure after loop).

```
found = False
targets = ["10.0.0.1", "10.0.0.2"]

for ip in targets:
    if ip == "10.0.0.2":
        found = True
        break

if found:
    print("Target reachable")
else:
    print("Target not found")
```

4. Concatenate strings

```
name = "R1"
ip = "10.0.0.1"

# f-string
s = f"Device {name} has IP {ip}"

# join list of strings
parts = ["line1", "line2", "line3"]
joined = "\n".join(parts)

# plus operator (works, but slower for many pieces)
s2 = "Device " + name + " has IP " + ip
```

5. Opening & Processing Files

Creating file for reading (ensure file exists)

```
# create a file with some content
with open("sample.txt", "w") as f:
    f.write("line1\nline2\nline3\n")
# now sample.txt exists and is readable
```

Opening & reading a file (whole content)

```
with open("sample.txt", "r") as f:
    data = f.read()    # whole file as one string
print(data)
```

Reading a file line-by-line

```
with open("sample.txt", "r") as f:
    for line in f:          # efficient for large files
        print(line.strip()) # remove trailing newline
```

Reading a file with splitting (parsing tokens)

```
with open("sample.txt", "r") as f:
    for line in f:
        tokens = line.strip().split() # split on whitespace
        # or split by other delimiter: line.strip().split(",")
        print(tokens)
```

Creating/opening & writing a file with timestamp in filename

```
from datetime import datetime

ts = datetime.now().strftime("%Y%m%d_%H%M%S")
filename = f"backup_{ts}.log"

with open(filename, "w") as fout:
    fout.write("timestamped file created\n")
    print("created", filename)
```

Common timestamp formats:

- "%Y-%m-%d_%H-%M-%S"
- "%Y%m%d%H%M%S"

Lab 6

PART 1 — Connectivity & Feature Enablement (FULL BREAKDOWN)

MÁY 1: CSR1000v (Router)

Đây là nơi cần enable các service RESTCONF, NETCONF, SSH.

1. Bật các dịch vụ trên CSR (chạy trên CSR1000v CLI)

Mình vào CSR bằng:

```
ssh cisco@192.168.74.152
```

```
conf t
username cisco privilege 15 secret cisco
ip domain-name lab.local
crypto key generate rsa modulus 2048

ip http secure-server
ip http authentication local

restconf
netconf-yang

line vty 0 4
transport input ssh
login local
end
```

2. Verify reachability (chạy từ DEVASC)

Kiểm tra ping

```
ping 192.168.74.152
```

Kiểm tra SSH

```
ssh cisco@192.168.74.152
```

MÁY 2: DEVASC VM (Ubuntu)

Đây là nơi chạy Python, Ansible, RESTCONF, NETCONF.

3. Tạo Virtual Environment + Install Packages (chạy trên DEVASC)

Tạo venv

```
python3 -m venv cse484-env
```

```
source cse484-env/bin/activate
```

Thư viện : pip install requests ncclient lxml netmiko

PART 2 — RESTCONF Reads & PATCH

Goal

Dùng RESTCONF GET JSON từ CSR1000v

Xem config + state của interface

PATCH nhẹ 1 description ở Gi1

Verify bằng JSON + CLI

MÁY CHẠY LỆNH: DEVASC

(cURL chỉ chạy ở DEVASC thôi, không chạy trong CSR)

CSR IP của Minh: 192.168.74.152

User/password CSR: cisco / cisco123!

1. GET toàn bộ interfaces (JSON)

Chạy ở **DEVASC**:

```
curl -k -u cisco:cisco \
```

```
-H "Accept: application/yang-data+json" \
```

```
"https://192.168.74.152/restconf/data/ietf-interfaces:interfaces/interface"
```

Mục đích:

Kiểm tra RESTCONF hoạt động

Lấy danh sách các interface trong YANG model

2. GET một interface + GET operational state

```
curl -k -u cisco:cisco123! \
```

```
-H "Accept: application/yang-data+json" \
```

```
"https://192.168.74.152/restconf/data/ietf-interfaces:interfaces/interface=GigabitEthernet1"
```

GET Operational State của Gi1

```
curl -k -u cisco:cisco123! \
```

```
-H "Accept: application/yang-data+json" \  
"https://192.168.74.152/restconf/data/ietf-interfaces:interfaces-state/interface=GigabitEthernet1"
```

Config = desired state

State = actual operational state

→ Thầy muốn xem Minh hiểu sự khác nhau.

3. PATCH mô tả interface Gi1 (RESTCONF PATCH)

Chạy ở DEVASC:

```
curl -k -u cisco:cisco \  
-X PATCH \  
-H "Content-Type: application/yang-data+json" \  
"https://192.168.74.152/restconf/data/ietf-interfaces:interfaces/interface=GigabitEthernet1" \  
-d '{  
  "ietf-interfaces:interface": {  
    "name": "GigabitEthernet1",  
    "description": "LAB-Gi1",  
    "type": "iana-if-type:ethernetCsmacd",  
    "enabled": true  
  }  
'
```

Giải thích:

PATCH chỉ sửa đúng cái field cần → không overwrite nguyên interface.

Đây là bài đơn giản, “safe change”.

4. Verify

4.1. RESTCONF GET lại để thấy description mới

```
curl -k -u cisco:cisco123! \  
-H "Accept: application/yang-data+json" \  
"https://192.168.74.152/restconf/data/ietf-interfaces:interfaces/interface=GigabitEthernet1"
```

```
"https://192.168.74.152/restconf/data/ietf-interfaces:interfaces/interface=GigabitEthernet1"
```

Verify bằng CLI trên CSR

Chạy trong CSR:

```
show run interface gigabitEthernet1 | include description
```

Expected:

```
description LAB-Gi1
```

Remember :

```
conf t
```

```
aaa new-model
```

```
end
```

```
conf t
```

```
aaa authorization exec default local
```

```
end
```

Bật RESTCONF lại một lần nữa để nó register AAA

```
conf t
```

```
restconf
```

```
End
```

Bật HTTP/S & auth local

```
conf t
```

```
ip http server
```

```
ip http secure-server
```

```
ip http authentication local
```

```
end
```

PART 3 : NETCONF with ncclient

A. Kiểm tra NETCONF đang chạy

Trên CSR:

```
show netconf-yang status
```

Phải thấy:

```
netconf-yang: enabled
```

Nếu chưa:

```
conf t
```

```
netconf-yang
```

```
end
```

Port NETCONF mặc định: 830

1. discover_caps.py – Code đã tối ưu

File: discover_caps.py

```
from ncclient import manager
import json

CSR_IP = "192.168.74.152"

with manager.connect(
    host=CSR_IP,
    port=830,
    username="cisco",
    password="cisco123!",
    hostkey_verify=False,
    look_for_keys=False,
    allow_agent=False
) as m:

    caps = list(m.server_capabilities)
    for c in caps:
        print(c)

    # Save to file for evidence
    with open("netconf_capabilities.txt", "w") as f:
        for c in caps:
            f.write(c + "\n")

print("\n✓ Capabilities saved to netconf_capabilities.txt")
```

python3 discover_caps.py

2. set_hostname_nc.py – Version chạy chuẩn CSR1000v

Tui fix luôn 2 lỗi thường gặp:

candidate datastore thường không available trên CSR → chỉ dùng “running”

namespace phải đúng IOS-XE native

đảm bảo lock/unlock không lỗi

File: set_hostname_nc.py

```
from ncclient import manager
from ncclient.xml_ import new_ele, sub_ele, to_xml

CSR_IP = "192.168.74.152"

# Build XML payload
cfg = new_ele("config")
native = sub_ele(cfg, "native",
                  xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native")
sub_ele(native, "hostname").text = "CSR-DEMO"

with manager.connect(
    host=CSR_IP,
    port=830,
    username="cisco",
    password="cisco123!",
    hostkey_verify=False,
    look_for_keys=False,
    allow_agent=False
) as m:

    target = "running" # candidate usually not supported

    print("🔒 Locking datastore...")
    m.lock(target)

    try:
        print("📤 Sending edit-config...")
        resp = m.edit_config(target=target, config=to_xml(cfg))
        print(resp)

        print("🔍 Validating...")
        if any(":validate" in c for c in m.server_capabilities):
            print(m.validate())

        print("💾 Commit if needed (not required for 'running')")
        # commit only needed for candidate
```

```
finally:
    print("🔓 Unlocking datastore...")
    m.unlock(target)

print("\n✅ Hostname change applied successfully!")
```

Error

🔒 Locking datastore...

📡 Sending edit-config...

🔓 Unlocking datastore...

Traceback (most recent call last):

```
File "set_hostname_nc.py", line 29, in <module>
    resp = m.edit_config(target=target, config=to_xml(cfg))
File "/home/devasc/.local/lib/python3.8/site-packages/ncclient/manager.py", line 231, in
execute
    return cls(self._session,
File "/home/devasc/.local/lib/python3.8/site-packages/ncclient/operations/edit.py", line 69,
in request
    return self._request(node)
File "/home/devasc/.local/lib/python3.8/site-packages/ncclient/operations/rpc.py", line 348,
in _request
    raise self._reply.error
ncclient.operations.rpc.RPCError: {'type': 'application', 'tag': 'unknown-element', 'severity':
'error', 'info': '<?xml version="1.0" encoding="UTF-8"?><error-info
xmlns="urn:ietf:params:xml:ns:netconf:base:1.0"
xmlns:nc="urn:ietf:params:xml:ns:netconf:base:1.0"><bad-element>native</bad-element>\n
</error-info>\n', 'path': '\n  /rpc/edit-config/config\n ', 'message': None}
```

set_hostname_nc.py

```
from ncclient import manager
from ncclient.xml_ import new_ele, sub_ele, to_xml

CSR_IP = "192.168.74.152"

# Build correct XML payload for hostname
cfg = new_ele("config")
hostname = sub_ele(cfg, "hostname",
                    xmlns="http://cisco.com/ns/yang/Cisco-IOS-XE-native")
hostname.text = "CSR-DEMO"

with manager.connect(
    host=CSR_IP,
    port=830,
    username="cisco",
    password="cisco123!",
    hostkey_verify=False,
    look_for_keys=False,
```



```

    allow_agent=False
) as m:

    target = "running"

    print("🔒 Locking datastore...")
    m.lock(target)

    try:
        print("📡 Sending edit-config...")
        resp = m.edit_config(target=target, config=to_xml(cfg))
        print(resp)

        if any(":.validate" in c for c in m.server_capabilities):
            print("🔍 Validating...")
            print(m.validate())

    finally:
        print("🔓 Unlocking datastore...")
        m.unlock(target)

print("\n✅ Hostname update applied successfully!")

```

Error

devasc@labvm:~/Documents/testLab6\$ python3 set_hostname_nc.py

🔒 Locking datastore...

📡 Sending edit-config...

🔓 Unlocking datastore...

Traceback (most recent call last):

File "set_hostname_nc.py", line 29, in <module>

resp = m.edit_config(target=target, config=to_xml(cfg))

File "/home/devasc/.local/lib/python3.8/site-packages/ncclient/manager.py", line 231, in execute

return cls(self._session,

File "/home/devasc/.local/lib/python3.8/site-packages/ncclient/operations/edit.py", line 69, in request

return self._request(node)

File "/home/devasc/.local/lib/python3.8/site-packages/ncclient/operations/rpc.py", line 348, in _request

raise self._reply.error

```
ncclient.operations.rpc.RPCError: {'type': 'application', 'tag': 'unknown-element',  
'severity': 'error', 'info': '<?xml version="1.0" encoding="UTF-8"?><error-info  
xmlns="urn:ietf:params:xml:ns:netconf:base:1.0"  
xmlns:nc="urn:ietf:params:xml:ns:netconf:base:1.0"><bad-element>hostname</bad-  
element>\n</error-info>\n', 'path': '\n  /rpc/edit-config/config\n ', 'message': None}
```

CÁCH TỰ ĐỘNG TÌM MODEL → TỰ BUILD XML ĐÚNG CHUẨN

STEP 1 — Luôn luôn xem CSR expose những YANG model nào

```
from ncclient import manager  
  
with manager.connect(  
    host="192.168.74.152",  
    port=830,  
    username="cisco",  
    password="cisco123!",  
    hostkey_verify=False,  
    look_for_keys=False,  
    allow_agent=False  
) as m:  
    for cap in m.server_capabilities:  
        print(cap)
```


Configuration on CSR

From Question 1 to Question 5

Pexpect, Paramiko, Netmiko, Nornir, RESTCONF, NETCONF, Ansible

CSR1000v (192.168.74.152)

```
conf t

!! -----
!! 1. User + SSH + RSA Keys
!! -----
username cisco privilege 15 secret cisco123!
ip domain-name lab.local
crypto key generate rsa modulus 2048

line vty 0 4
 login local
 transport input ssh

!! -----
!! 2. AAA (bắt buộc cho RESTCONF)
!! -----
aaa new-model
aaa authentication login default local
aaa authorization exec default local

!! -----
!! 3. Enable HTTP/HTTPS + RESTCONF
!! -----
ip http server
ip http secure-server
restconf

!! -----
!! 4. NETCONF
!! -----
netconf-yang

!! -----
!! 5. Kiểm tra port
!! -----
end
show ip http server secure status
show netconf-yang status
```

Check NETCONF enable: on CSR

show running-config | include netconf

Kết quả đúng phải thấy:

netconf-yang

✓ Check port 830 mở chưa:

show platform software yang-management process

Output :

confd : Running

nesd : Running

ncsshd: Running

nginx : Running

→ NETCONF & RESTCONF OK.

On Devas check :

curl -k -u cisco:cisco123! \

-H "Accept: application/yang-data+json" \

<https://192.168.74.152/restconf/data/ietf-interfaces:interfaces>

ON Devas

Show run | include netconf

Check Netconf lệnh 2 :

curl -k -u cisco:cisco123! <https://192.168.74.152/restconf/>

Test 1 module nhỏ:

curl -k -u cisco:cisco123! \

-H "Accept: application/yang-data+json" \

<https://192.168.74.152/restconf/data/ietf-interfaces:interfaces>

Các lệnh check

SSH OK? `ssh cisco@192.168.74.152`

RESTCONF OK?

`curl -k -u cisco:cisco123! https://192.168.74.152/restconf/data/`

📋 Trên CSR1000v – cấu hình 1 lần là xong

✅ Những thứ BẮT BUỘC phải có (đúng như bạn ghi)

`conf t`

`username cisco privilege 15 secret cisco123!`

`ip domain-name lab.local`

`crypto key generate rsa modulus 2048`

`line vty 0 4`

`login local`

`transport input ssh`

✓ SSH cho Pexpect / Paramiko / Netmiko / Nornir

✅ AAA (cái này là chìa khóa của RESTCONF)

`aaa new-model`

`aaa authentication login default local`

`aaa authorization exec default local`

👉 Thiếu AAA = RESTCONF auto access-denied

👉 Bạn làm đúng rồi

✅ RESTCONF + HTTPS

`ip http server`

`ip http secure-server`

`restconf`

✅ NETCONF

```
netconf-yang
end
```

③ Check nhanh trên CSR (đúng – sai là biết liền)

```
show ip http server secure status
```

✓ Enabled

✓ Port 443

```
show running-config | include netconf
```

✓ Phải thấy netconf-yang

```
show platform software yang-management process
```

✓ Phải có:

```
confd : Running
```

```
nesd : Running
```

```
ncsshd: Running
```

```
nginx : Running
```

👉 Chỉ cần mấy dòng này = NETCONF & RESTCONF OK

④ Trên Devas – chỉ TEST, KHÔNG config gì thêm

♦ SSH

```
ssh cisco@<CSR_IP>
```


✓ Vào được = pass Question 1–4 nền tảng

♦ RESTCONF (test nhẹ, đừng query root nhiều)

✓ ĐÚNG – AN TOÀN

```
curl -k -u cisco:cisco123! \  
-H "Accept: application/yang-data+json" \  
https://<CSR_IP>/restconf/data/ietf-interfaces:interfaces
```

👉 Ra JSON = RESTCONF OK

Lab 7

Nhớ tạo hosts bên ngoài thư mục playbooks

```
[ios]
csr1 ansible_host=192.168.74.155

[ios:vars]
ansible_connection=network_cli
ansible_network_os=cisco.ios.ios
ansible_user=cisco
ansible_password=cisco123!
ansible_become=yes
ansible_become_method=enable
ansible_become_password=cisco123!
```

playbooks/backup.yml

```
---
- name: Backup running-config
  hosts: ios
  gather_facts: no

  tasks:
    - name: Backup config (per-device file)
      cisco.ios.ios_config:
        backup: true
        backup_options:
          dir_path: backups
```

Tự tạo file dạng:

backups/CSR1kv_config_2025-xx-xx@xx-xx-xx

Run

ansible-playbook playbooks/backup.yml

Idempotent Base Config (playbooks/base_config.yml)

 Mục tiêu

Cấu hình “nền”

Chạy nhiều lần không bị spam changed

Chuẩn bài kiểm tra: idempotence

playbooks/base_config.yml

```
---
- name: Base hardening (idempotent)
  hosts: ios
  gather_facts: no

  tasks:
```

```

- name: Global settings
  cisco.ios.ios_config:
    lines:
      - service timestamps debug datetime msec
      - service timestamps log datetime msec
      - logging buffered 19999
      - ip ssh version 2

- name: VTY lines (ensure SSH only)
  cisco.ios.ios_config:
    parents: line vty 0 4
    lines:
      - exec-timeout 10 0
      - transport input ssh
      - login local

```

ansible-playbook playbooks/base_config.yml

ansible-playbook playbooks/base_config.yml

Part 3 — Conditions & Facts (CHÓT)

 Ý tưởng

ios_facts lấy trạng thái thật từ thiết bị
 when làm “gate” → không đổi khi đã compliant
 Chạy lại nhiều lần không phá config

Facts + Conditional config

playbooks/cond.yml

```

---
- name: Conditional hostname & gated tasks
  hosts: ios
  gather_facts: no

  tasks:
    - name: Gather network facts
      cisco.ios.ios_facts:

    - name: Append -LAB to hostname if not present
      cisco.ios.ios_config:
        lines:
          - "hostname {{ ansible_net_hostname }}-LAB"
      when:
        - ansible_net_hostname is defined
        - not ansible_net_hostname.endswith('-LAB')

    - name: Show final hostname

```

```

cisco.ios.ios_command:
  commands:
    - show run | include ^hostname
  register: h

- name: Print hostname
  debug:
    var: h.stdout_lines

# ===== Self-done task (a) =====
- name: Warn if IOS-XE version < 17
  debug:
    msg: " ⚠ Warning: IOS-XE version is lower than 17.x"
  when:
    - ansible_net_version is defined
    - ansible_net_version is version('17.0', '<')

# ===== Self-done task (b) =====
- name: Run task only if Gi1 is administratively up
  debug:
    msg: "GigabitEthernet1 is UP → safe to apply config"
  when:
    - ansible_net_interfaces is defined
    - ansible_net_interfaces['GigabitEthernet1'].enabled

```

✓ Kỳ vọng khi chạy

Lần 1: changed

Lần 2: task hostname skipped → idempotent chuẩn bài

ansible-playbook playbooks/cond.yml