

Hermes Snap — Configuration Reference

All configuration is done through `snap set all-dev-hermesagent <key>=<value>`. The configure hook routes each key to the right place automatically:

- **API keys & tokens** → `/var/snap/all-dev-hermesagent/common/.env`
- **Settings** → `/var/snap/all-dev-hermesagent/common/config.yaml`

Quick Start

```
# Install
sudo snap install all-dev-hermesagent_0.12.0_amd64.snap --dangerous

# Set your API key (pick one provider)
sudo snap set all-dev-hermesagent openrouter-api-key=sk-or-your-key-here

# Set the model
sudo snap set all-dev-hermesagent model=openrouter/deepseek/deepseek-r1

# Dashboard is auto-enabled – open in browser
# http://<device-ip>:9119
```

LLM Provider API Keys

snap set command	Hermes config key	File
sudo snap set all-dev-hermesagent openai-api-key=sk-...	OPENAI_API_KEY	.env
sudo snap set all-dev-hermesagent openai-base-url=https://...	OPENAI_BASE_URL	.env
sudo snap set all-dev-hermesagent openrouter-api-key=sk-or-...	OPENROUTER_API_KEY	.env
sudo snap set all-dev-hermesagent anthropic-api-key=sk-ant-...	ANTHROPIC_API_KEY	.env
sudo snap set all-dev-hermesagent gemini-api-key=...	GEMINI_API_KEY	.env
sudo snap set all-dev-hermesagent deepseek-api-key=...	DEEPSEEK_API_KEY	.env
sudo snap set all-dev-hermesagent xai-api-key=...	XAI_API_KEY	.env
sudo snap set all-dev-hermesagent ollama-base-url=http://...	OLLAMA_BASE_URL	.env

Tool API Keys

snap set command	Hermes config key	File
sudo snap set all-dev-hermesagent exa-api-key=...	EXA_API_KEY	.env
sudo snap set all-dev-hermesagent tavily-api-key=...	TAVILY_API_KEY	.env
sudo snap set all-dev-hermesagent firecrawl-api-key=...	FIRECRAWL_API_KEY	.env
sudo snap set all-dev-hermesagent browserbase-api-key=...	BROWSERBASE_API_KEY	.env
sudo snap set all-dev-hermesagent browserbase-project-id=...	BROWSERBASE_PROJECT_ID	.env

Messaging Platform Tokens

snap set command	Hermes config key	File
sudo snap set all-dev-hermesagent telegram-bot-token=...	TELEGRAM_BOT_TOKEN	.env
sudo snap set all-dev-hermesagent telegram-allowed-users=...	TELEGRAM_ALLOWED_USERS	.env
sudo snap set all-dev-hermesagent discord-bot-token=...	DISCORD_BOT_TOKEN	.env
sudo snap set all-dev-hermesagent discord-allowed-users=...	DISCORD_ALLOWED_USERS	.env
sudo snap set all-dev-hermesagent slack-bot-token=...	SLACK_BOT_TOKEN	.env
sudo snap set all-dev-hermesagent slack-app-token=...	SLACK_APP_TOKEN	.env

Model & Settings

snap set command	Hermes config key	File
sudo snap set all-dev-hermesagent model=openrouter/deepseek/deepseek-r1	model	config.yaml
sudo snap set all-dev-hermesagent model-provider=openrouter	model.provider	config.yaml

snap set command	Hermes config key	File
sudo snap set all-dev-hermesagent model-name=deepseek-r1	model.name	config.yaml
sudo snap set all-dev-hermesagent personality="You are a helpful assistant"	personality	config.yaml
sudo snap set all-dev-hermesagent log-level=debug	logging.level	config.yaml

Service Control

snap set command	Effect
sudo snap set all-dev-hermesagent dashboard-service=enabled	Start the web dashboard (default: enabled)
sudo snap set all-dev-hermesagent dashboard-service=disabled	Stop the web dashboard
sudo snap set all-dev-hermesagent gateway-service=enabled	Start the messaging gateway (Telegram/Discord/Slack)
sudo snap set all-dev-hermesagent gateway-service=disabled	Stop the messaging gateway
sudo snap set all-dev-hermesagent agent-service=enabled	Start the AI agent daemon
sudo snap set all-dev-hermesagent agent-service=disabled	Stop the AI agent daemon
sudo snap set all-dev-hermesagent acp-service=enabled	Start the ACP adapter
sudo snap set all-dev-hermesagent acp-service=disabled	Stop the ACP adapter

CT Engine Integration

These are set automatically by the Control Tower during deployment:

snap set command	Description
sudo snap set all-dev-hermesagent ct-callback-url=http://...	CT callback endpoint (enables ct-engine)
sudo snap set all-dev-hermesagent ct-snap-name=all-dev-hermesagent	Snap identifier for CT

snap set command	Description
sudo snap set all-dev-hermesagent ct-node-id=node-001	Node identifier
sudo snap set all-dev-hermesagent ct-deployment-id=deploy-001	Deployment identifier

File Locations

Path	Contents
/var/snap/all-dev-hermesagent/common/.env	API keys and secrets
/var/snap/all-dev-hermesagent/common/config.yaml	Model, logging, personality settings
/var/snap/all-dev-hermesagent/common/	Full HERMES_HOME directory
/snap/all-dev-hermesagent/current/	Read-only snap installation

Services

Service	Command
snap logs all-dev-hermesagent.dashboard	Dashboard logs
snap logs all-dev-hermesagent.gateway	Messaging gateway logs
snap logs all-dev-hermesagent.agent	Agent daemon logs
snap logs all-dev-hermesagent.acp	ACP adapter logs
snap logs all-dev-hermesagent.ct-engine	CT Engine sidecar logs

Example: Full Setup

```
# 1. Install the snap
sudo snap install all-dev-hermesagent_0.12.0_amd64.snap --dangerous

# 2. Set API key
sudo snap set all-dev-hermesagent openrouter-api-key=sk-or-v1-abc123

# 3. Set model
sudo snap set all-dev-hermesagent model=openrouter/deepseek/deepseek-r1

# 4. Enable CT Engine (done automatically by Control Tower)
sudo snap set all-dev-hermesagent ct-callback-url=http://192.168.1.6:8080/callback

# 5. Dashboard is at http://<device-ip>:9119
# All further configuration is done through the dashboard UI
```

