Creating and Managing Tables

Objectives

After completing this lesson, you should be able to do the following:

- Describe the main database objects
- Create tables
- Describe the data types that can be used when specifying column definition
- Alter table definitions
- Drop, rename, and truncate tables

Database Objects

Object	Description
Table	Basic unit of storage; composed of rows and columns
View	Logically represents subsets of data from one or more tables
Sequence	Numeric value generator
Index	Improves the performance of some queries
Synonym	Gives alternative names to objects

Naming Rules

Table names and column names:

- Must begin with a letter
- Must be 1–30 characters long
- Must contain only A–Z, a–z, 0–9, _, \$, and #
- Must not duplicate the name of another object owned by the same user
- Must not be an Oracle server reserved word

The CREATE TABLE Statement

- You must have:
 - CREATE TABLE privilege
 - A storage area

```
CREATE TABLE [schema.]table (column datatype [DEFAULT expr][, ...]);
```

- You specify:
 - Table name
 - Column name, column data type, and column size

Referencing Another User's Tables

- Tables belonging to other users are not in the user's schema.
- You should use the owner's name as a prefix to those tables.

The DEFAULT Option

Specify a default value for a column during an insert.

```
... hire_date DATE DEFAULT SYSDATE, ...
```

- Literal values, expressions, or SQL functions are legal values.
- Another column's name or a pseudocolumn are illegal values.
- The default data type must match the column data type.

Creating Tables

Create the table.

```
CREATE TABLE dept
(deptno NUMBER(2),
dname VARCHAR2(14),
loc VARCHAR2(13));
Table created.
```

Confirm table creation.

DESCRIBE dept

Name	Null?	Туре
DEPTNO		NUMBER(2)
DNAME		VARCHAR2(14)
LOC		VARCHAR2(13)

Tables in the Oracle Database

- User Tables:
 - Are a collection of tables created and maintained by the user
 - Contain user information
- Data Dictionary:
 - Is a collection of tables created and maintained by the Oracle Server
 - Contain database information

Querying the Data Dictionary

See the names of tables owned by the user.

```
SELECT table_name
FROM user_tables ;
```

View distinct object types owned by the user.

```
SELECT DISTINCT object_type

FROM user_objects ;
```

 View tables, views, synonyms, and sequences owned by the user.

```
SELECT *
FROM user_catalog;
```

Data Types

Data Type	Description
VARCHAR2(size)	Variable-length character data
CHAR(size)	Fixed-length character data
NUMBER(p,s)	Variable-length numeric data
DATE	Date and time values
LONG	Variable-length character data up to 2 gigabytes
CLOB	Character data up to 4 gigabytes
RAW and LONG RAW	Raw binary data
BLOB	Binary data up to 4 gigabytes
BFILE	Binary data stored in an external file; up to 4 gigabytes
ROWID	A 64 base number system representing the unique address of a row in its table.



Creating a Table by Using a Subquery Syntax

 Create a table and insert rows by combining the CREATE TABLE statement and the AS subquery option.

```
CREATE TABLE table
        [(column, column...)]
AS subquery;
```

- Match the number of specified columns to the number of subquery columns.
- Define columns with column names and default values.

Creating a Table by Using a Subquery

Name	Null?	Туре
EMPLOYEE_ID		NUMBER(6)
LAST_NAME	NOT NULL	VARCHAR2(25)
ANNSAL		NUMBER
HIRE DATE	NOT NULL	DATE

The ALTER TABLE Statement

Use the ALTER TABLE statement to:

- Add a new column
- Modify an existing column
- Define a default value for the new column
- Drop a column



The ALTER TABLE Statement

Use the ALTER TABLE statement to add, modify, or drop columns.

```
ALTER TABLE table

ADD (column datatype [DEFAULT expr]
[, column datatype]...);

ALTER TABLE table

MODIFY (column datatype [DEFAULT expr]
[, column datatype]...);

ALTER TABLE table

DROP (column);
```

Adding a Column

New column

DEPT80

EMPLOYEE_ID	LAST_NAME	ANNSAL	HIRE_DATE
149	Zlotkey	126000	29-JAN-00
174	Abel	132000	11-MAY-96
176	Taylor	103200	24-MAR-98



"Add a new column to the DEPT80 table."

DEPT80

EMPLOYEE_ID	LAST_NAME	ANNSAL	HIRE_DATE	JOB_ID
149	Zlotkey	126000	29-JAN-00	
174	Abel	132000	11-MAY-96	
176	Taylor	103200	24-MAR-98	

Adding a Column

You use the ADD clause to add columns.

```
ALTER TABLE dept80
ADD (job_id VARCHAR2(9));
Table altered.
```

The new column becomes the last column.

EMPLOYEE_ID	LAST_NAME	ANNSAL	HIRE_DATE	JOB_ID
149	Zlotkey	126000	29-JAN-00	
174	Abel	132000	11-MAY-96	
176	Taylor	103200	24-MAR-98	

Modifying a Column

 You can change a column's data type, size, and default value.

```
ALTER TABLE dept80

MODIFY (last_name VARCHAR2(30));

Table altered.
```

 A change to the default value affects only subsequent insertions to the table.

Dropping a Column

Use the DROP COLUMN clause to drop columns you no longer need from the table.

```
ALTER TABLE dept80
DROP COLUMN job_id;
Table altered.
```

The SET UNUSED Option

- You use the SET UNUSED option to mark one or more columns as unused.
- You use the DROP UNUSED COLUMNS option to remove the columns that are marked as unused.

```
ALTER TABLE table

SET UNUSED (column);

OR

ALTER TABLE table

SET UNUSED COLUMN column;
```

```
ALTER TABLE table
DROP UNUSED COLUMNS;
```

Dropping a Table

- All data and structure in the table is deleted.
- Any pending transactions are committed.
- All indexes are dropped.
- You cannot roll back the DROP TABLE statement.

```
DROP TABLE dept80; Table dropped.
```

Changing the Name of an Object

 To change the name of a table, view, sequence, or synonym, you execute the RENAME statement.

```
RENAME dept TO detail_dept;
Table renamed.
```

You must be the owner of the object.

Truncating a Table

- The TRUNCATE TABLE statement:
 - Removes all rows from a table
 - Releases the storage space used by that table

TRUNCATE TABLE detail_dept;
Table truncated.

- You cannot roll back row removal when using TRUNCATE.
- Alternatively, you can remove rows by using the DELETE statement.

Summary

In this lesson, you should have learned how to use DDL statements to create, alter, drop, and rename tables.

Statement	Description
CREATE TABLE	Creates a table
ALTER TABLE	Modifies table structures
DROP TABLE	Removes the rows and table structure
RENAME	Changes the name of a table, view, sequence, or synonym
TRUNCATE	Removes all rows from a table and releases the storage space
COMMENT	Adds comments to a table or view

