
Following are the steps to reset a Windows 10 password:

 Boot from the Windows 10 DVD. Make sure that your PC setup is configured to boot from a DVD and that UEFI and Secure Boot are disabled.



Boot from Windows 10 DVD


2. Press SHIFT + F10 to open a command prompt.



Open a command prompt with SHIFT + F10

3. Replace the file utilman.exe with cmd.exe. Before you do this, you should make a copy of utilman.exe so that you can restore it later. Note that you can only restore this file if you boot again from the Windows DVD. Windows 10 is usually installed on drive D: if you boot from a DVD. You can verify this with "dir d:\windows\system32 \utilman.exe." If the system can't find utilman.exe, try other drive letters.


```
move d:\windows\system32\utilman.exe d:\windows\system32\utilman.exe.bak
copy d:\windows\system32\cmd.exe d:\windows\system32\utilman.exe
```



Replace utilman.exe with cmd.exe


 After you have replaced utilman.exe successfully, you can remove the DVD and restart your problematic Windows 10 installation:

```
1 wpeutil reboot
```




Reboot Windows 10

5. On the Windows 10 sign-in page, click the **Utility Manager** icon.



Click Utility Manager icon

Since we replaced the Utility Manager with the cmd.exe, a command prompt should open now. Don't worry about the error message.



Command prompt at sign-in page

6. You can now add a new user with the command below. We also have to add the user to the administrator group so that we regain full control of our Windows installation. Replace <username> with the account name of your choice. Note that the account name must not exist on this Windows installation. Don't let the Windows 10 screen saver distract you.

```
1 net user <username> /add
2 net localgroup administrators <username> /add
```




Add a new user and adding the user to the administrator group

Click the screen to make the sign-in page appear again. Your new account should show up, and you can sign in without a password.




Sign in with a new local account

You can now access the files associated with your Microsoft account in the C:\Users folder.



 If you worked with a local account instead of a Microsoft account, you can reset your password in Computer Management. Right-click the Start button, select Computer Management, and navigate to Local Users and Groups. Right-click your local account and select Set Password.



Reset Windows 10 password

A shorter way to reset the password of a local account is to replace the first command in step 6 with the following command. (In this case, you don't need to create a new user.)