实验名称	BGP 实验					
姓名	刘培源	学号	2023214278			

实验环境: Mac Parallel Desktop 19; Ubuntu 22.04

注:由于 Ubuntu 22.04 上已经不支持 quagga,因此本实验采用 FRRouting 实现;同时,FRRouting 针对了 Mac 的 Parallel Desktop 进行了适配。

- 1. 与实验二一样,在 host1 和 host2 上均配置两个网卡,采用桥接模式(Bridge Network: feth8302),用于配置 BGP。
- 2. 重要!!在 cd /etc/frr 和 sudo touch zebra.conf bgpd.conf 配置 zebra.conf 和 bgpd.conf 之前,一定要把/etc/frr/frr.conf 文件删除,因为 frr 默认把所有 的 configure 都集成到 frr.conf 里,若要分开配置,就得把它删了,再去分别 配置 zebra.conf 和 bgpd.conf(host1 和 host2 都要做同样设置)。
- 3. 在 zebra.conf 中输入 password zebra 配置 zebra, 在 bgpd.conf 中输入 password bgp, 并且将 daemons 中的 bgpd 设置为 yes, 截图如下:

```
# ATTENTION:

# When activating a daemon for the first time, a config file, even if it is # empty, has to be present *and* be owned by the user and group "frr", else # the daemon will not be started by /etc/init.d/frr. The permissions should # be u=rw,g=r,o=.

# When using "vtysh" such a config file is also needed. It should be owned by # group "frrvty" and set to ug=rw,o= though. Check /etc/pam.d/frr, too.

# The watchfrr, zebra and staticd daemons are always started.

# bgpd=yes ospfd=no ospf6d=no ripd=no ripd=no ripd=no lipd=no hrpd=no lipd=no hrpd=no etgrpd=no babeld=no sharpd=no babeld=no sharpd=no pbrd=no babeld=no fdd=no fdd=no fdd=no fdd=no fdd=no fdd=no fabricd=no vrrpd=no atthd=no patd=no patd=no patd=no fabricd=no vrrpd=no patd=no patd=no patd=no fabricd=no vrrpd=no patd=no pa
```

- 4. 然后在 host1 上通过如下命令进一步配置 zebra:
 - (1) sudo telnet localhost 2601
 - (2) enable
 - (3) configure terminal
 - (4) interface enp0s5
 - (5) ip address 192.168.0.1/24
 - (6) no shutdown
 - (7) interface enp0s6
 - (8) ip address 192.168.1.1/24
 - (9) no shutdown
 - (10) write

配置过程截图如下:

实验步骤

```
nat@nat-Parallels-ARM-Virtual-Machine:-/Desktop$ sudo telnet localhost 2601
Trying 127.0.0.1...
Connected to localhost.
Escape character is '^|.

Hello, this is FRRouting (version 8.1).
Copyright 1996-2005 Kunihiro Ishiguro, et al.

User Access Verification

Password:
nat-Parallels-ARM-Virtual-Machine> enable
nat-Parallels-ARM-Virtual-Machine# configure terminal
nat-Parallels-ARM-Virtual-Machine(config)# interface enp0s5
nat-Parallels-ARM-Virtual-Machine(config-if)# ip address 192.168.0.1/24
nat-Parallels-ARM-Virtual-Machine(config-if)# no shutdown
nat-Parallels-ARM-Virtual-Machine(config-if)# ip address 192.168.1.1/24
nat-Parallels-ARM-Virtual-Machine(config-if)# ip address 192.168.1.1/24
nat-Parallels-ARM-Virtual-Machine(config-if)# ip address 192.168.1.1/24
nat-Parallels-ARM-Virtual-Machine(config-if)# write
Configuration saved to /etc/frr/zebra.conf
```

配置完之后 zebra.conf 文件内容如下:

- 5. 接着在 host1 上通过如下命令配置 bgpd:
 - (1) sudo telnet localhost 2605
 - (2) enable
 - (3) configure terminal
 - (4) router bgp 100
 - (5) network 192.168.0.0/24
 - (6) neighbor 192.168.0.2 remote-as 200
 - (7) neighbor 192.168.0.2 description "two"
 - (8) write

配置过程截图如下:

```
nat@nat-Parallels-ARM-Virtual-Machine:-/Desktop$ sudo telnet localhost 2605
Trying 127.0.0.1...
Connected to localhost.
Escape character is '^]'.

Hello, this is FRRouting (version 8.1).
Copyright 1996-2005 Kunihiro Ishiguro, et al.

User Access Verification

Password:
nat-Parallels-ARM-Virtual-Machine> enable
nat-Parallels-ARM-Virtual-Machine# configure terminal
nat-Parallels-ARM-Virtual-Machine(config-router)# network 192.168.0.0/24
nat-Parallels-ARM-Virtual-Machine(config-router)# network 192.168.0.2 remote-as 200

% [BGP] Unknown command: network 192.168.0.2 remote-as 200
nat-Parallels-ARM-Virtual-Machine(config-router)# network 192.168.0.2 remote-as 200
nat-Parallels-ARM-Virtual-Machine(config-router)# neighbor 192.168.0.2 remote-as 200
nat-Parallels-ARM-Virtual-Machine(config-router)# neighbor 192.168.0.2 description "two"
nat-Parallels-ARM-Virtual-Machine(config-router)# write
Configuration saved to /etc/frr/bgpd.conf
```

配置完之后 bgpd.conf 文件内容如下:


```
nat@nat-Parallels-ARM-Virtual-Machine:-/Desktop$ sudo cat /etc/frr/bgpd.conf
!
! Zebra configuration saved from vty
! 2023/12/24 19:53:40
!
frr version 8.1
frr defaults traditional
!
hostname nat-Parallels-ARM-Virtual-Machine
password bgp
!
!
!
router bgp 100
netghbor 192.168.0.2 remote-as 200
neighbor 192.168.0.2 description "two"
!
address-family ipv4 unicast
network 192.168.0.0/24
exit-address-family
!
exit
!
!
!
```

6. 对于 host2 的设置,只有 ip 地址的设置有区别,下面直接展示 host2 上配置 完之后的 zebra.conf 和 bgpd.conf:

```
host@host-Parallels-ARM-Virtual-Machine:~/Desktop$ sudo cat /etc/frr/zebra.conf
!
! Zebra configuration saved from vty
! 2023/12/24 20:05:15
!
frr version 8.1
frr defaults traditional
!
hostname host-Parallels-ARM-Virtual-Machine
password zebra
!
!
!
interface enp0s5
ip address 192.168.0.2/24
exit
!
interface enp0s6
ip address 192.168.2.1/24
exit
!
!
no ip forwarding
no ipv6 forwarding
!
!
!
```

```
hostghost-Parallels-ARM-Virtual-Machine:-/Desktop$ sudo cat /etc/frr/bgpd.conf
!
! Zebra configuration saved from vty
! 2023/12/24 20:07:40
!
frr version 8.1
frr defaults traditional
!
hostname host-Parallels-ARM-Virtual-Machine
password bgp
!
!
!
router bgp 200
neighbor 192.168.0.1 remote-as 100
neighbor 192.168.0.1 description "one"
!
address-family ipv4 unicast
network 192.168.2.0/24
exit-address-family
!
exit
!
!
```

- 7. 在配置完成之后,分别在 host1 和 host2 上输入 sudo /etc/init.d/frr restart 来重启 frr 服务。
- 8. 在经过一段时间后,观察 host1 的路由表如下:




host2 的路由表如下:

Kernel IP routing table								
Destination	Gateway	Genmask	Flags	Metric	Ref	Use		
link-local	*	255.255.0.0	U	1000	0	0		
192.168.0.0	*	255.255.255.0	U	0	0	0		
192.168.1.0	192.168.0.1	255.255.255.0	UG	0	0	0		
192.168.2.0	*	255.255.255.0	U	0	0	0		


9. 至此 BGP 已经配置完成, wireshark 的数据分析在后面给出。

1. 观察 OPEN 报文

BGP 的 OPEN 报文截图如下




(1) 传输协议层 TCP 中的端口号是否为 179?




是的

(2) Marker 字段的值是否全为 1?所观察到的值代表什么含义?




是的,代表不使用验证。

(3) Length 字段的值?OPEN 报文各个字段的总长度?二者是否相等。




Length 字段的值为 114; 总长度也是 114, 二者相等。

(4) Type 字段的值是否与 OPEN 报文的类型值对应?




由图可知, 二者相对应。

(5) Version 字段是否为 4?



是的。

(6) 观察 My As 字段, Hold Time 字段, IP 地址字段, 确认这个 OPEN 报 文发送者所在的 AS 号, 建议的保持时间, 以及 IP 地址。




AS 号: 200

建议保持时间: 180


IP 地址: 192.168.2.1

2. 观察 KEEPALIVE 报文



3. 观察 UPDATE 报文, 重启 frr。

4. 观察 NOTIFICATION 报文。



1. 重启 quagga 出现的 UPDATE 消息都是成对的,即两个 bgp 对等体都向对方 那个发送了一个 UPDATE 消息。请结合这个具体的例子,思考产生这个现 象的原因。 答: 在重启 Quagga 时观察到的 BGP UPDATE 消息成对出现的现象,即两个 BGP 对等体相互发送了一个 UPDATE 消息,可以归因于 eBGP 的对等体特 性和 TCP 协议的传输机制。具体而言,eBGP 协议要求两个对等体间的通信 是互相独立的,这意味着每个对等体都需要主动发送信息以维持协议的状态 和数据的同步。同时,BGP 协议运行在 TCP 之上,这要求在数据传输前必 须完成 TCP 的三次握手过程,确保连接的可靠性。因此,在 Quagga 重启过 程中,两个 BGP 对等体都会通过发送 UPDATE 消息来重新建立连接并同步 路由信息,从而形成了成对的 UPDATE 消息现象。 2. 如何验证 BGP 声明的正确性? 思 考 答:验证 BGP 声明的正确性主要依赖于 BGP 消息中的 Marker 字段。BGP 题 协议设计了 Marker 字段作为一种安全机制,以确保接收到的消息是有效和 完整的。在 BGP 消息结构中, Marker 字段通常位于消息的开始位置, 用于 标识消息的开始并提供一种方法来验证消息的完整性。通过检查这个字段, 可以确认收到的 BGP 声明是否符合协议规范,从而确保 BGP 通信的可靠性 和数据的正确性。 1. 在 Parallel Desktop 上使用 Ubuntu 22.04 的 MacOS 用户注意实验步骤中的重 要!!部分。 经 验 总 结