## TTK4225 - Systems Theory, Autumn 2020

Damiano Varagnolo



Complex numbers - introduction

## Roadmap


- definition
- sum, subtraction, multiplication, division
- why is this important?

What is a complex number, and why did we introduce them?


## What is a complex number, and why did we introduce them?

#### In essence:

- a point in the Cartesian plane
- ② to be sure to find all the roots of polynomials (i.e., be able to write polynomials in convenient forms)




# The "imaginary unit"



$$i : i^2 = -1$$


# Simple operations with complex numbers: sums



$$z_1 = a_1 + ib_1 \qquad z_2 = a_2 + ib_2$$

$$z_1 + z_2 = (a_1 + ib_1) + (a_2 + ib_2) = (a_1 + a_2) + i(b_1 + b_2)$$


# Simple operations with complex numbers: subtractions



$$z_1 = a_1 + ib_1$$
  $z_2 = a_2 + ib_2$ 

$$z_1 - z_2 = (a_1 + ib_1) - (a_2 + ib_2) = (a_1 - a_2) + i(b_1 - b_2)$$


# Simple operations with complex numbers: multiplication



$$z_1 = a_1 + ib_1$$
  $z_2 = a_2 + ib_2$ 

$$z_1 z_2 = (a_1 + ib_1)(a_2 + ib_2) = (a_1 a_2 - b_1 b_2) + i(a_1 b_2 + a_2 b_1)$$


# Simple operations with complex numbers: inversion



$$z_1 = a_1 + ib_1$$

$$z_1^{-1} = \frac{a_1}{a_1^2 + b_1^2} - i\frac{b_1}{a_1^2 + b_1^2}$$


# Simple operations with complex numbers: division



$$z_1 = a_1 + ib_1$$
  $z_2 = a_2 + ib_2$ 

$$\frac{z_1}{z_2} = \frac{a_1 + ib_1}{a_2 + ib_2} = \frac{(a_1 + ib_1)(a_2 - ib_2)}{(a_2 + ib_2)(a_2 - ib_2)} = \frac{a_1a_2 + b_1b_2}{a_2^2 + b_2^2} + i\frac{b_1a_2 - a_1b_2}{a_2^2 + b_2^2}$$

# Simple operations with complex numbers: conjugation



$$z_1 = a_1 + ib_1$$


$$\overline{z_1} = a_1 - ib_1$$

• addition: 
$$z + \overline{z} = a + ib + a - ib = 2a$$
, thus  $\operatorname{Re}(z) = \frac{1}{2}(z + \overline{z})$ 


- addition:  $z + \overline{z} = a + ib + a ib = 2a$ , thus  $\operatorname{Re}(z) = \frac{1}{2}(z + \overline{z})$
- subtraction:  $z \overline{z} = a + ib a + ib = 2ib$ , thus  $\operatorname{Im}(z) = \frac{1}{2i}(z + \overline{z})$

- addition:  $z + \overline{z} = a + ib + a ib = 2a$ , thus  $\operatorname{Re}(z) = \frac{1}{2}(z + \overline{z})$
- subtraction:  $z \overline{z} = a + ib a + ib = 2ib$ , thus  $\operatorname{Im}(z) = \frac{1}{2i}(z + \overline{z})$
- multiplication:  $z\overline{z} = (a+ib)(a-ib) = a^2 + b^2$ , thus  $|z|^2 = z\overline{z}$


# Once again, graphically: addition




# Once again, graphically: subtraction



# Once again, graphically: conjugation



#### Polar coordinates




can be rewritten through r and  $\theta$  so that

$$a = r\cos\theta$$
 and  $b = r\sin\theta$ 

so that

$$z = r (\cos \theta + i \sin \theta)$$

#### Polar coordinates




Equations:

$$r = |z| = \sqrt{a^2 + b^2} = \sqrt{z\overline{z}}$$

$$\theta = \arg z = \operatorname{atan}(b, a) = \tan^{-1}\left(\frac{b}{a}\right)$$

#### Polar coordinates



Equations:


$$r = |z| = \sqrt{a^2 + b^2} = \sqrt{z\overline{z}}$$

$$\theta = \arg z = \operatorname{atan}(b, a) = \tan^{-1}\left(\frac{b}{a}\right)$$


#### Notation:

- ullet r= absolute value or modulus of z
- ullet  $\theta$  = argument, angle, or phase of z

## Problem: different $\theta$ 's lead to the same z




#### Problem: different $\theta$ 's lead to the same z




**Definition**: principal value of z= that value of  $\theta$  that is in  $[-\pi,\pi]$ 

# Usefulness of polar forms: the multiplication is immediate



$$z_1 z_2 = r_1 r_2 \left[ \cos \left( \theta_1 + \theta_2 \right) + i \sin \left( \theta_1 + \theta_2 \right) \right]$$

# Implication: the division is immediate



$$\frac{z_1}{z_2} = \frac{r_1}{r_2} \left[ \cos \left( \theta_1 - \theta_2 \right) + i \sin \left( \theta_1 - \theta_2 \right) \right]$$

# Usefulness of the multiplication: it enables Taylor expansions!

Taylor expansions: a tool to do not underestimate

## Usefulness of the multiplication: it enables Taylor expansions!

Taylor expansions: a tool to do not underestimate

$$z_1 z_2 = r_1 r_2 \left[ \cos \left( \theta_1 + \theta_2 \right) + i \sin \left( \theta_1 + \theta_2 \right) \right] \implies z^n$$
 well defined

## Usefulness of the multiplication: it enables Taylor expansions!


Taylor expansions: a tool to do not underestimate

$$z_1 z_2 = r_1 r_2 \left[ \cos \left( \theta_1 + \theta_2 \right) + i \sin \left( \theta_1 + \theta_2 \right) \right] \implies z^n$$
 well defined

E.g., thus

$$e^z = 1 + z + \frac{1}{2!}z^2 + \frac{1}{3!}z^3 + \dots$$

### The absolute value of a complex number




Meaning: Euclidean length of the vector. Very important for control, since very often we compute the absolute value of a transfer function at a specific  $s=i\omega$  (and very very often the transfer function is rational)

Thus, chain of implications highlighting the importance of complex numbers for control perspectives

# Thus, chain of implications highlighting the importance of complex numbers for control perspectives

#### 1: LTI systems have sinusoidal fidelity

$$u(t) = u_0 \sin(\omega t) \implies y(t) = u_0 |H(i\omega)| \sin(\omega t + \angle H(i\omega))$$



# Thus, chain of implications highlighting the importance of complex numbers for control perspectives

1: LTI systems have sinusoidal fidelity

$$u(t) = u_0 \sin(\omega t) \implies y(t) = u_0 |H(i\omega)| \sin(\omega t + \angle H(i\omega))$$

2: we very often consider rational H's

$$\implies K \frac{\prod (s - z_i)}{\prod (s - p_i)}$$

# Thus, chain of implications highlighting the importance of complex numbers for control perspectives

#### 1: LTI systems have sinusoidal fidelity

$$u(t) = u_0 \sin(\omega t) \implies y(t) = u_0 |H(i\omega)| \sin(\omega t + \angle H(i\omega))$$

#### 2: we very often consider rational H's

$$\implies K \frac{\prod (s - z_i)}{\prod (s - p_i)}$$

#### 3: we very often consider rational H's

this means that to compute  $|H(i\omega)|$  we need to do multiplications and divisions among the complex numbers  $s-\star_i$ 

Example:  $H(s) = \frac{1+2s}{1+2s+s^2}$ . What is  $|H(i\omega)|$ ?

$$|H(i\omega)| = \sqrt{H(i\omega)\overline{H(i\omega)}}$$

$$= \sqrt{\frac{1+2i\omega}{1+2i\omega-\omega^2} \cdot \frac{1-2i\omega}{1-2i\omega-\omega^2}}$$

$$= \sqrt{\frac{1+4\omega^2}{(1-\omega^2)^2+4\omega^2}}$$

$$= \sqrt{\frac{1+4\omega^2}{\omega^4+2\omega^2+1}}$$


# Complex functions

# Roadmap

- definition
- why are they important?

## Complex function: definition

$$f: \mathbb{C} \mapsto \mathbb{C}$$



### Complex function: caveats

$$f: \mathbb{C} \mapsto \mathbb{C}$$

is so that

$$f(z) = u(x,y) + iv(x,y)$$

#### Complex function: caveats

$$f: \mathbb{C} \mapsto \mathbb{C}$$

is so that

$$f(z) = u(x,y) + iv(x,y)$$

thus, also in polar representations,  $(r,\theta) \mapsto (r',\theta')$  with in general both r' and  $\theta'$  functions of both r and  $\theta$ 

# Example: if $f(z) = z^2 + 3z$ then what is f(1+3j)?

$$f(z) = (x+iy)(x+iy) + 3x + 3iy$$
  
=  $x^2 + 2ixy - y^2 + 3x + 3iy$   
=  $x^2 - y^2 + 3x + i(2xy + 3y)$ 

# Example: if $f(z) = z^2 + 3z$ then what is f(1+3j)?

$$f(z) = (x+iy)(x+iy) + 3x + 3iy$$
  
=  $x^2 + 2ixy - y^2 + 3x + 3iy$   
=  $x^2 - y^2 + 3x + i(2xy + 3y)$ 

thus

$$u(x,y) = x^2 - y^2 + 3x$$
  
$$v(x,y) = 2xy + 3y$$

# Example: if $f(z) = z^2 + 3z$ then what is f(1+3j)?

$$f(z) = (x+iy)(x+iy) + 3x + 3iy$$
  
=  $x^2 + 2ixy - y^2 + 3x + 3iy$   
=  $x^2 - y^2 + 3x + i(2xy + 3y)$ 

thus

$$u(x,y) = x^2 - y^2 + 3x$$
  
$$v(x,y) = 2xy + 3y$$

thus

$$f(1+3j) = u(1,3) + iv(1,3)$$
  
= 1<sup>3</sup> - 3<sup>2</sup> + 3 + i(2 \cdot 1 \cdot 3 + 3 \cdot 3)  
= -5 + 15i

Complex function: why are they important?

### Complex function: why are they important?

Recall: the forced evolution is given by

$$Y(s) = H(s)U(s)$$

with H(s) very often rational, i.e., ratio of polynomials.

#### Complex function: why are they important?

Recall: the forced evolution is given by

$$Y(s) = H(s)U(s)$$

with H(s) very often rational, i.e., ratio of polynomials. Essential tool for automatic control people: roots of complex polynomials

#### Primary definition: root of a complex number

if  $z \in \mathbb{C}$  and  $n \in \mathbb{N}$ , then the n complex roots of z are the n complex numbers  $z_0,\ldots,z_{n-1}$  for which  $z_k^n=z$ , i.e.,

$$\sqrt[n]{z} = \sqrt[n]{r} \left(\cos\frac{\theta + 2k\pi}{n} + i\sin\frac{\theta + 2k\pi}{n}\right)$$
 for  $k = 0, 1, \dots, n-1$ 

#### Primary definition: root of a complex number


if  $z\in\mathbb{C}$  and  $n\in\mathbb{N}$ , then the n complex roots of z are the n complex numbers  $z_0,\ldots,z_{n-1}$  for which  $z_k^n=z$ , i.e.,

$$\sqrt[n]{z} = \sqrt[n]{r} \left( \cos \frac{\theta + 2k\pi}{n} + i \sin \frac{\theta + 2k\pi}{n} \right)$$
 for  $k = 0, 1, \dots, n-1$ 


The intuition on how to get them follows from:

$$z_1 z_2 = r_1 r_2 \left[ \cos \left( \theta_1 + \theta_2 \right) + i \sin \left( \theta_1 + \theta_2 \right) \right]$$

#### Geometrically:



#### Geometrically:




these n roots always exist

### Roots of complex functions, example: quartic roots of 1

$$\sqrt[4]{1} = \{1, i, -1, -i\}$$

(note that only two of them are in  $\mathbb{R}$ )



#### IMPORTANT: ONE SHOULD CONSIDER THE PRINCIPAL VALUE

... otherwise one may artificially add  $2\pi k$  to the phase of  $w=\sqrt[n]{z}$  and have an infinite number of roots ...

Why are we using so much time on this?

#### Why are we using so much time on this?

Because we often have to do with objects of the type  $z^n + a_{n-1}z^{n-1} + \ldots + a_1z + a_0 = 0$ , thus we need to know what we are dealing with!

#### Why are we using so much time on this?

Because we often have to do with objects of the type  $z^n + a_{n-1}z^{n-1} + \ldots + a_1z + a_0 = 0$ , thus we need to know what we are dealing with! *Essential results:* 

- ullet n-order polynomials have always from 0 to n real roots
- $\bullet \ n\text{-order}$  polynomials have always n complex roots

#### Example

$$z^4 - 6iz^2 + 16 = 0$$

implies

$$z_1 = 2 + 2i$$
  $z_2 = -2 - 2i$   $z_3 = -1 + i$   $z_4 = 1 - i$ 

(to get the solution let y =  $z^2$ , and then do a bit of massaging)

?

# Complex exponentials

### Roadmap

- intuitions
- definition
- Euler's identities
- complex logarithms

#### In the previous episodes . . .

- complex sums and multiplications
- complex roots
- complex polynomials

#### In the previous episodes . . .

- complex sums and multiplications
- complex roots
- complex polynomials
- $\rightarrow$  generalizing everything, even the functions

#### Discussion

why are exponentials important in control?

#### Discussion

why are exponentials important in control?

Because they are the essence of the modes of LTI systems with rational transfer functions, and LTI systems are often good approximations of nonlinear systems around their equilibria

## First usefulness of complex exponentials: simplify notation even further

Question: can we write  $z = r(\cos \theta + i \sin \theta)$  in a more complex way?

## First usefulness of complex exponentials: simplify notation even further

Question: can we write  $z = r(\cos\theta + i\sin\theta)$  in a more complex way? I.e., how do we couple

$$e^z = 1 + z + \frac{1}{2!}z^2 + \frac{1}{3!}z^3 + \dots$$

with  $\sin$  and  $\cos$ ?

## First usefulness of complex exponentials: simplify notation even further

Question: can we write  $z = r(\cos\theta + i\sin\theta)$  in a more complex way? I.e., how do we couple

$$e^z = 1 + z + \frac{1}{2!}z^2 + \frac{1}{3!}z^3 + \dots$$

with  $\sin$  and  $\cos$ ? Of course, Euler's formula!

# Why does Euler's formula work? (so that one may remember it more...)

Starting point:

$$e^z = e^{x+iy} = e^x e^{iy}$$

# Why does Euler's formula work? (so that one may remember it more...)

Starting point:

$$e^z = e^{x+iy} = e^x e^{iy}$$

but

$$e^{iy} = 1 + iy + \frac{1}{2!}(iy)^2 + \frac{1}{3!}(iy)^3 + \dots + \frac{1}{k!}(iy)^k + \dots$$

# Why does Euler's formula work? (so that one may remember it more...)

Starting point:

$$e^z = e^{x+iy} = e^x e^{iy}$$

but

$$e^{iy} = 1 + iy + \frac{1}{2!}(iy)^2 + \frac{1}{3!}(iy)^3 + \dots + \frac{1}{k!}(iy)^k + \dots$$

$$= \underbrace{\left(1 - \frac{1}{2!}y^2 + \frac{1}{4!}y^4 - \frac{1}{6!}y^6 + \dots\right)}_{=\cos(y)} + i\underbrace{\left(y - \frac{1}{3!}y^3 + \frac{1}{5!}y^5 - \frac{1}{7!}y^7 + \dots\right)}_{=\sin(y)}$$

## Why does Euler's formula work? (so that one may remember it more...)

Starting point:

$$e^z = e^{x+iy} = e^x e^{iy}$$

but

$$e^{iy} = 1 + iy + \frac{1}{2!}(iy)^2 + \frac{1}{3!}(iy)^3 + \dots + \frac{1}{k!}(iy)^k + \dots$$

$$= \underbrace{\left(1 - \frac{1}{2!}y^2 + \frac{1}{4!}y^4 - \frac{1}{6!}y^6 + \dots\right)}_{=\cos(y)} + i\underbrace{\left(y - \frac{1}{3!}y^3 + \frac{1}{5!}y^5 - \frac{1}{7!}y^7 + \dots\right)}_{=\sin(y)}$$

thus

$$e^z = e^x \left(\cos y + i\sin y\right)$$

$$z = x + iy = r(\cos\theta + i\sin\theta)$$
  
 $z = re^{i\theta}$ 

with

$$r = \sqrt{x^2 + y^2}$$
  $\theta = atan \frac{y}{x}$ 

$$z = x + iy = r(\cos\theta + i\sin\theta)$$
  
 $z = re^{i\theta}$ 

with

$$r = \sqrt{x^2 + y^2}$$
  $\theta = atan \frac{y}{x}$ 

This confirms the intuition that multiplying z in the complex plane by  $e^{i\theta}$  means rotating z of  $\theta$  radiants <u>anti-clockwise</u> in  $\mathbb C$ 

$$z = x + iy = r(\cos\theta + i\sin\theta)$$
  
 $z = re^{i\theta}$ 

with

$$r = \sqrt{x^2 + y^2}$$
  $\theta = atan \frac{y}{x}$ 

This confirms the intuition that multiplying z in the complex plane by  $e^{i\theta}$  means rotating z of  $\theta$  radiants anti-clockwise in  $\mathbb C$ 

#### Examples

$$ze^{i\alpha} = re^{i\theta}e^{i\alpha} = re^{i(\theta+\alpha)}$$

$$z = x + iy = r(\cos\theta + i\sin\theta)$$
  
 $z = re^{i\theta}$ 

with

$$r = \sqrt{x^2 + y^2}$$
  $\theta = atan \frac{y}{x}$ 

This confirms the intuition that multiplying z in the complex plane by  $e^{i\theta}$  means rotating z of  $\theta$  radiants anti-clockwise in  $\mathbb C$ 

#### **Examples**

$$ze^{i\alpha} = re^{i\theta}e^{i\alpha} = re^{i(\theta+\alpha)}$$
  
 $zi = re^{i\theta}e^{i\frac{\pi}{2}} = re^{i(\theta+\frac{\pi}{2})}$ 

$$z = x + iy = r(\cos\theta + i\sin\theta)$$
  
 $z = re^{i\theta}$ 

with

$$r = \sqrt{x^2 + y^2}$$
  $\theta = atan \frac{y}{x}$ 

This confirms the intuition that multiplying z in the complex plane by  $e^{i\theta}$  means rotating z of  $\theta$  radiants anti-clockwise in  $\mathbb C$ 

#### **Examples**

$$ze^{i\alpha} = re^{i\theta}e^{i\alpha} = re^{i(\theta+\alpha)}$$
  
 $zi = re^{i\theta}e^{i\frac{\pi}{2}} = re^{i(\theta+\frac{\pi}{2})}$ 

that, by the way, implies (x + iy) i = -y + ix, i.e., a 90-degrees rotation

Starting point:

$$e^{iy} = \underbrace{\left(1 - \frac{1}{2!}y^2 + \frac{1}{4!}y^4 - \frac{1}{6!}y^6 + \ldots\right)}_{=\cos(y)} + i\underbrace{\left(y - \frac{1}{3!}y^3 + \frac{1}{5!}y^5 - \frac{1}{7!}y^7 + \ldots\right)}_{=\sin(y)}$$

(must be in this way, because "cos" is even, "sin" is odd).

Starting point:

$$e^{iy} = \underbrace{\left(1 - \frac{1}{2!}y^2 + \frac{1}{4!}y^4 - \frac{1}{6!}y^6 + \ldots\right)}_{=\cos(y)} + i\underbrace{\left(y - \frac{1}{3!}y^3 + \frac{1}{5!}y^5 - \frac{1}{7!}y^7 + \ldots\right)}_{=\sin(y)}$$

(must be in this way, because "cos" is even, "sin" is odd). But also

$$e^{-iy} = \underbrace{\left(1 - \frac{1}{2!}y^2 + \frac{1}{4!}y^4 - \frac{1}{6!}y^6 + \ldots\right)}_{=\cos(y)} - i\underbrace{\left(y - \frac{1}{3!}y^3 + \frac{1}{5!}y^5 - \frac{1}{7!}y^7 + \ldots\right)}_{=-\sin(y)}$$

Starting point:

$$e^{iy} = \underbrace{\left(1 - \frac{1}{2!}y^2 + \frac{1}{4!}y^4 - \frac{1}{6!}y^6 + \ldots\right)}_{=\cos(y)} + i\underbrace{\left(y - \frac{1}{3!}y^3 + \frac{1}{5!}y^5 - \frac{1}{7!}y^7 + \ldots\right)}_{=\sin(y)}$$

(must be in this way, because "cos" is even, "sin" is odd). But also

$$e^{-iy} = \underbrace{\left(1 - \frac{1}{2!}y^2 + \frac{1}{4!}y^4 - \frac{1}{6!}y^6 + \ldots\right)}_{=\cos(y)} - i\underbrace{\left(y - \frac{1}{3!}y^3 + \frac{1}{5!}y^5 - \frac{1}{7!}y^7 + \ldots\right)}_{=-\sin(y)}$$

thus

$$\sin y = \frac{1}{2i} (e^{iy} - e^{-iy})$$
  $\cos y = \frac{1}{2} (e^{iy} + e^{-iy})$ 

• 
$$e^{i\pi} = -1$$
,  $e^{\pi i/2} = i$ ,  $e^{-\pi i/2} = -i$ ,  $e^{-\pi i} = -1$ 

- $e^{i\pi} = -1$ ,  $e^{\pi i/2} = i$ ,  $e^{-\pi i/2} = -i$ ,  $e^{-\pi i} = -1$
- ullet exponentials are never equal to 0, i.e.,  $e^z \neq 0$  independently of z

- $e^{i\pi} = -1$ ,  $e^{\pi i/2} = i$ ,  $e^{-\pi i/2} = -i$ ,  $e^{-\pi i} = -1$
- exponentials are never equal to 0, i.e.,  $e^z \neq 0$  independently of z
- exponentials are periodic, i.e.,  $e^{z+2\pi i} = e^z$

#### Notation: "fundamental region of the exponential"

$$-\pi<\mathrm{Im}\left(z\right)\leq\pi$$

### Multiplications and divisions through the complex functions

$$z_1$$
 =  $r_1e^{i\theta_1}$  and  $z_2$  =  $r_2e^{i\theta_2}$  imply

### Multiplications and divisions through the complex functions

$$z_1 = r_1 e^{i\theta_1}$$
 and  $z_2 = r_2 e^{i\theta_2}$  imply

• 
$$z_1 z_2 = r_1 r_2 e^{i(\theta_1 + \theta_2)}$$

### Multiplications and divisions through the complex functions

$$z_1$$
 =  $r_1e^{i heta_1}$  and  $z_2$  =  $r_2e^{i heta_2}$  imply

- $z_1 z_2 = r_1 r_2 e^{i(\theta_1 + \theta_2)}$
- $\frac{z_1}{z_2} = \frac{r_1}{r_2} e^{i(\theta_1 \theta_2)}$

### Roots through the complex functions

$$w=z^n$$
 is s.t.  $w=re^{i\theta+2\pi k}$  and is equal to

$$z_k = r^{1/n} e^{i\left(\frac{\theta}{n} + \frac{2k\pi}{n}\right)}$$

(note that besides k = 0, 1, ..., n-1, for other k's we get the same roots as before)

#### Starting point: real logarithms

- if  $x \in \mathbb{R}$  then  $\ln(x)$  is s.t.  $e^{\ln(x)} = x$
- ullet x though must be strictly positive, since  $e^*$  cannot be negative nor null

#### Starting point: real logarithms

- if  $x \in \mathbb{R}$  then  $\ln(x)$  is s.t.  $e^{\ln(x)} = x$
- ullet x though must be strictly positive, since  $e^{*}$  cannot be negative nor null

#### Complex logarithms

• if  $z \in \mathbb{C}$  then  $\ln(z)$  is s.t.  $e^{\ln(z)} = z$ 

#### Starting point: real logarithms

- if  $x \in \mathbb{R}$  then  $\ln(x)$  is s.t.  $e^{\ln(x)} = x$
- ullet x though must be strictly positive, since  $e^*$  cannot be negative nor null

#### Complex logarithms

- if  $z \in \mathbb{C}$  then  $\ln(z)$  is s.t.  $e^{\ln(z)} = z$
- if  $z = re^{i\theta}$  then  $\ln(z) = \ln r + i\theta$


#### Starting point: real logarithms

- if  $x \in \mathbb{R}$  then  $\ln(x)$  is s.t.  $e^{\ln(x)} = x$
- ullet x though must be strictly positive, since  $e^*$  cannot be negative nor null

#### Complex logarithms

- if  $z \in \mathbb{C}$  then  $\ln(z)$  is s.t.  $e^{\ln(z)} = z$
- if  $z = re^{i\theta}$  then  $\ln(z) = \ln r + i\theta$

### Graphically:



### Very important difference

as soon as  $z = re^{i\theta}$  is s.t. r > 0 then

$$\ln\left(re^{i\theta}\right) = \ln r + i\theta$$

exists, thus the complex logarithm is defined for every  $z \neq 0!$ 

### Very important difference

as soon as  $z = re^{i\theta}$  is s.t. r > 0 then

$$\ln\left(re^{i\theta}\right) = \ln r + i\theta$$

exists, thus the complex logarithm is defined for every  $z \neq 0!$ 

#### Example

$$\ln(-10) = 2.30259 + i\pi.$$

LTI filters - motivations


### Roadmap

- sinusoidal fidelity
- how Fourier transforms help to analyse LTI systems
- introduction to Bode plots

### Recall: why are Fourier transforms important for control people?

Among others:  $H(i\omega)$  says how to apply the sinusoidal fidelity property, i.e., the fact that

$$u(t) = u_0 \sin(\omega t) \implies y(t) = u_0 |H(i\omega)| \sin(\omega t + \angle H(i\omega))$$



$$\dot{y} = ay + u$$
  $u(t) = \sin \omega t$   $\Longrightarrow$   $y(t) = y_0 e^{at} + e^{at} \int_0^t e^{-a\tau} \sin (\omega \tau) d\tau$ 

$$\dot{y} = ay + u \quad u(t) = \sin \omega t \implies y(t) = y_0 e^{at} + e^{at} \int_0^t e^{-a\tau} \sin(\omega \tau) d\tau$$

Using Rottmann, equation 132 on page 144:

$$\int e^{-a\tau} \sin(\omega t) d\tau = \frac{e^{-a\tau}}{a^2 + \omega^2} \left( -a \sin \omega \tau - \omega \cos \omega \tau \right) + C$$

$$\dot{y} = ay + u \quad u(t) = \sin \omega t \implies y(t) = y_0 e^{at} + e^{at} \int_0^t e^{-a\tau} \sin(\omega \tau) d\tau$$

Using Rottmann, equation 132 on page 144:

$$\int e^{-a\tau} \sin(\omega t) d\tau = \frac{e^{-a\tau}}{a^2 + \omega^2} \left( -a \sin \omega \tau - \omega \cos \omega \tau \right) + C$$

implies

$$y(t) = y_0 e^{at} + e^{at} \left[ \frac{e^{-a\tau}}{a^2 + \omega^2} \left( -a \sin \omega \tau - \omega \cos \omega \tau \right) \right]_{\tau=0}^{\tau=t}$$

$$\dot{y} = ay + u \quad u(t) = \sin \omega t \implies y(t) = y_0 e^{at} + e^{at} \int_0^t e^{-a\tau} \sin(\omega \tau) d\tau$$

Using Rottmann, equation 132 on page 144:

$$\int e^{-a\tau} \sin(\omega t) d\tau = \frac{e^{-a\tau}}{a^2 + \omega^2} \left( -a \sin \omega \tau - \omega \cos \omega \tau \right) + C$$

implies

$$y(t) = y_0 e^{at} + e^{at} \left[ \frac{e^{-a\tau}}{a^2 + \omega^2} \left( -a\sin\omega\tau - \omega\cos\omega\tau \right) \right]_{\tau=0}^{\tau=t}$$
$$= y_0 e^{at} + \frac{\omega}{a^2 + \omega^2} e^{at} + \frac{1}{a^2 + \omega^2} \left( -a\sin\omega t - \omega\cos\omega t \right)$$

### Sinusoidal fidelity of LTIs, in details

$$\dot{y} = ay + u \quad u(t) = \sin \omega t$$

#### implies

$$y(t) = y_0 e^{at} + \frac{\omega}{a^2 + \omega^2} e^{at} + \frac{1}{a^2 + \omega^2} \left( -a \sin \omega t - \omega \cos \omega t \right)$$


#### Notation:

- first term = free evolution
- second term = transient response (part of the forced response)
- third term = stationary response (part of the forced response)

### Why do we have free evolution, plus transient & stationary response?

Example: spring-mass system:


$$y(t) = y_0 e^{at} + \frac{\omega}{a^2 + \omega^2} e^{at} + \frac{1}{a^2 + \omega^2} \left( -a \sin \omega t - \omega \cos \omega t \right)$$



### Why do we have free evolution, plus transient & stationary response?

Example: spring-mass system:

$$y(t) = y_0 e^{at} + \frac{\omega}{a^2 + \omega^2} e^{at} + \frac{1}{a^2 + \omega^2} \left( -a \sin \omega t - \omega \cos \omega t \right)$$




Answer: even if we have  $y_0 = 0$ , the machine needs to "warm up"

LTI means sinusoidal fidelity, and sinusoidal fidelity for every sine means LTI


Idea: we can estimate H by repeating experiments with different sinusoidal u's!

$$y(t) \approx u_0 |H(i\omega)| \sin(\omega t + \angle H(i\omega))$$



Idea: we can estimate H by repeating experiments with different sinusoidal u's!

$$y(t) \approx u_0 |H(i\omega)| \sin(\omega t + \angle H(i\omega))$$




Good idea: check the "ETFE" system identification approach if you want to know more

# Idea: we can estimate h by first estimating H, and then inverse-Laplacing!

 $\dots$  actually not. There are better ways of doing this  $\rightarrow$  will be seen in courses that deal with system identification

### Our goal: arrive at Bode plots



(will see them better what they are in the next modules)

Frequency response of LTI filters

#### Roadmap

- decomposing the output of a LTI system
- what is called how

## Recap of how to decompose the output of a LTI system

$$y(t) = y_{\text{free}}(t) + y_{\text{forced,transient}}(t) + y_{\text{forced,stationary}}(t)$$

## Recap of how to decompose the output of a LTI system

$$y(t) = y_{\text{free}}(t) + y_{\text{forced,transient}}(t) + y_{\text{forced,stationary}}(t)$$

Example:

$$\dot{y} = ay + u \quad u(t) = \sin \omega t \quad \Longrightarrow \quad y(t) = y_0 e^{at} + \frac{\omega}{a^2 + \omega^2} e^{at} + \frac{1}{a^2 + \omega^2} \left( -a \sin \omega t - \omega \cos \omega t \right)$$

## Recap of how to decompose the output of a LTI system

$$y(t) = y_{\text{free}}(t) + y_{\text{tran}}(t) + y_{\text{stat}}(t)$$

#### with:

- free evolution: starts from  $y_0$  and vanishes as  $t \to +\infty$  if the system is asymptotically stable
- transient response: part of forced response that behaves in a similar way than the free evolution
- ullet stationary response: part of forced response such that if  $u(t) = \sin \omega t$  then

$$y_{\mathrm{stat}}(t) = A(\omega)\sin(\omega t + \varphi(\omega))$$

### A deeper look on the stationary response

$$u(t) = \sin \omega t \implies y_{\text{stat}}(t) = A(\omega) \sin (\omega t + \varphi(\omega))$$

### A deeper look on the stationary response

$$u(t) = \sin \omega t \implies y_{\text{stat}}(t) = A(\omega) \sin (\omega t + \varphi(\omega))$$

Objects that define the stationary response:

- ullet frequency  $\omega$
- ullet amplitude  $A(\omega)$
- phase  $\varphi(\omega)$

I.e.,  $A(\cdot)$  and  $\varphi(\cdot)$  are two functions of  $\omega$  and each system has its own ones

## A deeper look on the stationary response

$$u(t) = \sin \omega t \implies y_{\text{stat}}(t) = A(\omega) \sin (\omega t + \varphi(\omega))$$

Objects that define the stationary response:

- ullet frequency  $\omega$
- ullet amplitude  $A(\omega)$
- phase  $\varphi(\omega)$

I.e.,  $A(\cdot)$  and  $\varphi(\cdot)$  are two functions of  $\omega$  and each system has its own ones

 $A(\cdot)$  and  $\varphi(\cdot)$  define entirely how the system behaves after the initial transient vanished

very common misconception: A and  $\varphi$  do not define the behavior of the whole system. They define only the behavior after the transient has passed. I.e., they do not say what happens during the transient!

$$u(t) = \sin \omega t \implies y_{\text{stat}}(t) = A(\omega) \sin (\omega t + \varphi(\omega))$$

## Frequency response of a LTI system: formal definition

 $\coloneqq$  the stationary part of y(t) that results from a sinusoidal u(t)

### Frequency response of a LTI system "in time"

Question: how can we get y(t) from the frequency domain:

$$Y(s) = H(s) \frac{u_0 \omega}{s^2 + \omega^2}?$$

Answer = partial fraction decomposition, that leads to


$$y(t) = \underbrace{u_0 H\left(i\omega\right) \frac{e^{i\omega t}}{2i} - \frac{e^{-i\omega t}}{2i}}_{\text{stationary response}} + \underbrace{\sum_{i=1}^{n} \frac{(s-s_i) H(s) u_0 \omega e^{ts}}{s^2 + \omega^2}}_{\text{transient response}} \bigg|_{s=s}$$

with the sum being over the poles of H(s) (note that in the transient response the numerators are being computed using the residues theorem)

#### Back to the stationary response


thus the stationary response to  $u(t) = u_0 \sin \omega t$  is

$$y_{\text{stat}}(t) = u_0 H(i\omega) \frac{e^{i\omega t}}{2i} - \frac{e^{-i\omega t}}{2i}$$



## Back to the stationary response – using Euler formulas

$$y_{\text{stat}}(t) = u_0 |H(i\omega)| \sin(\omega t + \angle H(i\omega))$$



#### Notation

$$y_{\text{stat}}(t) = u_0 |H(i\omega)| \sin(\omega t + \angle H(i\omega))$$

- $H(i\omega) =$  "frequency response"
- $y_0/u_0$  =  $|H(i\omega)|$  = "amplitude response"
- $\angle H(i\omega) =$  "phase response"

?

#### Important to realize

- $\bullet$  H(s), i.e., the transfer function, tells us everything, since from it we can get the impulse response h(t) and from h(t) we can compute everything
- $H(i\omega)$ , i.e., the frequency response, tells us only what happens to the stationary response. Indeed  $H(i\omega)$  is only part of H(s)

?

# Bode plots

### Roadmap

- why and how to use Bode plots
- their main property: a sort of "additivity"
- examples
- remarks

## Summarizing


- using H(s) we can compute the whole y(t)
- ullet using  $H(i\omega)$  we can compute only  $y_{
  m stat}(t)$

## Summarizing

- using H(s) we can compute the whole y(t)
- using  $H(i\omega)$  we can compute only  $y_{\rm stat}(t)$


Good thing of  $H(i\omega)$  is that we can visualize it! (and visualizations help understanding and communicating with people)


# Bode diagrams, i.e., visualizing $H(i\omega)$ (and thus somehow also $y_{\mathrm{stat}}(t)$ )



Note: typically uses Decibels in the vertical axis, i.e.,  $|H(i\omega)|[\mathrm{dB}] = 20\log|H(i\omega)|$ , and a logarithmic horizontal axis

## Example: resonance





## Example: resonance, in more details, through a spring-mass system

$$\dot{\boldsymbol{x}} = \begin{bmatrix} 0 & 1 \\ -\frac{k}{m} & -\frac{f}{m} \end{bmatrix} \boldsymbol{x} + \begin{bmatrix} 0 \\ \frac{1}{m} \end{bmatrix} \boldsymbol{u} \qquad \boldsymbol{y} = \begin{bmatrix} 1 & 0 \end{bmatrix} \boldsymbol{x}$$

with

$$H(s) = \frac{Y(s)}{U(s)} = \frac{m/k}{\frac{m}{k}s^2 + \frac{f}{k}s + 1}$$

## Example: resonance, in more details, through a spring-mass system

$$\dot{\boldsymbol{x}} = \begin{bmatrix} 0 & 1 \\ -\frac{k}{m} & -\frac{f}{m} \end{bmatrix} \boldsymbol{x} + \begin{bmatrix} 0 \\ \frac{1}{m} \end{bmatrix} \boldsymbol{u} \qquad \boldsymbol{y} = \begin{bmatrix} 1 & 0 \end{bmatrix} \boldsymbol{x}$$

$$\boldsymbol{y} = \begin{bmatrix} 1 & 0 \end{bmatrix} \boldsymbol{x}$$

with

$$H(s) = \frac{Y(s)}{U(s)} = \frac{m/k}{\frac{m}{k}s^2 + \frac{f}{k}s + 1}$$

$$(s) = \frac{1}{k} \int_{-\infty}^{\infty} \int_$$

letting: 
$$\omega_0 = \sqrt{\frac{k}{m}} \quad \zeta = \frac{1}{2} \frac{f}{\sqrt{mk}} \quad K = \frac{m}{k}$$
 then


$$H(s) = \frac{K}{1 + 2\zeta \frac{s}{\omega_0} + \left(\frac{s}{\omega_0}\right)^2} \implies H(i\omega) = \frac{K}{1 + 2i\zeta \frac{\omega}{\omega_0} - \left(\frac{\omega}{\omega_0}\right)^2}$$


## Example: resonance, in more details, through a spring-mass system

$$H(i\omega) = \frac{K}{1 + 2i\zeta \frac{\omega}{\omega_0} - \left(\frac{\omega}{\omega_0}\right)^2}$$

#### Discussion:

- what happens to  $|H(i\omega)|$  when  $\omega \to 0$ ?
- what happens to  $|H(i\omega)|$  when  $\omega \to +\infty$ ?
- what happens to  $|H(i\omega)|$  when  $\zeta \to 0$  and  $\omega \to \omega_0$ ?





#### What is the inner structure of Bode plots?

Assumption: H(s) rational, so that

$$H(s) = \frac{G_1(s) \cdots G_m(s)}{F_1(s) \cdots F_n(s)}$$

#### What is the inner structure of Bode plots?

Assumption: H(s) rational, so that

$$H(s) = \frac{G_1(s) \cdots G_m(s)}{F_1(s) \cdots F_n(s)}$$

This implies

$$H(j\omega) = \frac{G_1(j\omega)\cdots G_m(j\omega)}{F_1(j\omega)\cdots F_n(j\omega)}$$

### What is the inner structure of Bode plots?

Assumption: H(s) rational, so that

$$H(s) = \frac{G_1(s) \cdots G_m(s)}{F_1(s) \cdots F_n(s)}$$

This implies

$$H(j\omega) = \frac{G_1(j\omega)\cdots G_m(j\omega)}{F_1(j\omega)\cdots F_n(j\omega)}$$

$$= \frac{|G_1(j\omega)|e^{i\angle G_1(j\omega)}\cdots |G_m(j\omega)|e^{i\angle G_m(j\omega)}}{|F_1(j\omega)|e^{i\angle F_1(j\omega)}\cdots |F_n(j\omega)|e^{i\angle F_n(j\omega)}}$$

#### What is the inner structure of Bode plots?

Assumption: H(s) rational, so that

$$H(s) = \frac{G_1(s) \cdots G_m(s)}{F_1(s) \cdots F_n(s)}$$

This implies

$$H(j\omega) = \frac{G_1(j\omega)\cdots G_m(j\omega)}{F_1(j\omega)\cdots F_n(j\omega)}$$

$$= \frac{|G_1(j\omega)|e^{i\angle G_1(j\omega)}\cdots |G_m(j\omega)|e^{i\angle G_m(j\omega)}}{|F_1(j\omega)|e^{i\angle F_1(j\omega)}\cdots |F_n(j\omega)|e^{i\angle F_n(j\omega)}}$$

Rearranging amplitudes with amplitudes and phases with phases:

$$\angle H(j\omega) = \angle G_1(j\omega) + \angle G_m(j\omega) - \angle F_1(j\omega) - \angle F_n(j\omega)$$

$$\log |H(j\omega)| = \log |G_1(j\omega)| + \ldots + \log |G_m(j\omega)| - \log |F_1(j\omega)| - \ldots - \log |F_n(j\omega)|$$

#### What does it mean?

$$\angle H(j\omega) = \angle G_1(j\omega) + \angle G_m(j\omega) - \angle F_1(j\omega) - \angle F_n(j\omega)$$

$$\log |H(j\omega)| = \log |G_1(j\omega)| + \ldots + \log |G_m(j\omega)| - \log |F_1(j\omega)| - \ldots - \log |F_n(j\omega)|$$

 $\,\Longrightarrow\,$  every pole and zero contributes by its own

#### What does it mean?

$$\angle H(j\omega) = \angle G_1(j\omega) + \angle G_m(j\omega) - \angle F_1(j\omega) - \angle F_n(j\omega)$$

$$\log |H(j\omega)| = \log |G_1(j\omega)| + \ldots + \log |G_m(j\omega)| - \log |F_1(j\omega)| - \ldots - \log |F_n(j\omega)|$$

 $\implies$  every pole and zero contributes by its own  $\implies$  we can decompose the Bode plot in "atomic" contributions!

#### What does it mean?

$$\angle H(j\omega) = \angle G_1(j\omega) + \angle G_m(j\omega) - \angle F_1(j\omega) - \angle F_n(j\omega)$$

$$\log |H(j\omega)| = \log |G_1(j\omega)| + \ldots + \log |G_m(j\omega)| - \log |F_1(j\omega)| - \ldots - \log |F_n(j\omega)|$$

 $\implies$  every pole and zero contributes by its own  $\implies$  we can decompose the Bode plot in "atomic" contributions!

#### Example:


Bode plot of 
$$\frac{s+3}{s(s-2)(s-3)}$$
 = "sum" of the Bode plots of


$$s+3 \qquad \frac{1}{s} \qquad \frac{1}{s-2} \qquad \frac{1}{s-3}$$

(with the meaning of "sum" explained better below)

# What is the contribution of $\frac{1}{s}$ , i.e., an integrator?

- contribution in amplitude:  $\left| \frac{1}{i\omega} \right| [dB] = -20 \log \omega$
- contribution in phase:  $\angle \frac{1}{i\omega} = -\frac{\pi}{2}$





# What is the contribution of $\frac{1}{Ts+1}$ , i.e., a real pole? Contribution in amplitude, letting $\omega = \frac{1}{T}$ :

$$\left| \frac{1}{1+iT\omega} \right| [dB] = \frac{1}{\sqrt{1+(T\omega)^2}} [dB]$$

$$= -20\log\sqrt{1+(T\omega)^2}$$

$$= \begin{cases} \approx 0[dB] & \text{for } \omega \ll 1/T \\ -20\log\sqrt{2} \approx -3[dB] & \text{for } \omega = 1/T \\ \approx -20\log\omega - 20\log T & \text{for } \omega \gg 1/T \end{cases}$$

# What is the contribution of $\frac{1}{Ts+1}$ , i.e., a real pole?

Contribution in phase, letting  $\omega = \frac{1}{T}$ :

$$\angle \frac{1}{1+iT\omega} = \left\{ \begin{array}{ll} \approx 0 & \text{for } \omega \ll 1/T \\ = -\frac{\pi}{4} = -45^{\circ} & \text{for } \omega = 1/T \\ \approx -\frac{\pi}{2} = -90^{\circ} & \text{for } \omega \gg 1/T \end{array} \right.$$

What is the contribution of  $\frac{1}{\frac{s^2}{\omega_0^2} + 2\frac{\zeta}{\omega_0}s + 1}$ , i.e., a pair of complex

## conjugate poles?

Contribution in amplitude:

$$\left| \frac{1}{1 - \left(\frac{\omega}{\omega_0}\right)^2 + i2\zeta\frac{\omega}{\omega_0}} \right| [dB] = \frac{1}{\sqrt{\left(1 - \left(\frac{\omega}{\omega_0}\right)^2\right)^2 + \left(2\zeta\frac{\omega}{\omega_0}\right)^2}} [dB]$$

$$= -20\log\sqrt{\left(1 - \left(\frac{\omega}{\omega_0}\right)^2\right)^2 + \left(2\zeta\frac{\omega}{\omega_0}\right)^2}$$

$$= \begin{cases} \approx 0[dB] & \text{for } \omega \ll \omega_0 \\ = -20\log 2\zeta & \text{for } \omega = \omega_0 \\ \approx -40\log \omega + 40\log \omega_0 & \text{for } \omega \gg \omega_0 \end{cases}$$

What is the contribution of  $\frac{1}{\frac{s^2}{\omega_0^2}+2\frac{\zeta}{\omega_0}s+1}$ , i.e., a pair of complex


# conjugate poles?


Contribution in phase:

$$\angle \frac{1}{1 - \left(\frac{\omega}{\omega_0}\right)^2 + i2\zeta\frac{\omega}{\omega_0}} = -\operatorname{atan} \frac{2\zeta\frac{\omega}{\omega_0}}{1 - \left(\frac{\omega}{\omega_0}\right)^2} \\
= \begin{cases}
\approx 0 & \text{for } \omega \ll \omega_0 \\
= -\frac{\pi}{2} = -90^\circ & \text{for } \omega = \omega_0 \\
\approx -\pi = -180^\circ & \text{for } \omega \gg \omega_0
\end{cases}$$

#### What is the contribution of s, i.e., a derivator?

- contribution in amplitude:  $|i\omega|$  [dB] =  $20\log\omega$
- contribution in phase:  $\angle i\omega = \frac{\pi}{2}$





#### What is the contribution of Ts + 1, i.e., a zero?

Contribution in amplitude, letting  $\omega = \frac{1}{T}$ :

$$|1+iT\omega| \left[dB\right] = 20\log\sqrt{1+\left(\omega T\right)^2} = \begin{cases} \approx 0 & \text{for } \omega \ll \omega_0 \\ 20\log\sqrt{2} & \text{for } \omega = \omega_0 \\ \approx 20\log\omega + 20\log T & \text{for } \omega \gg \omega_0 \end{cases}$$

#### What is the contribution of Ts + 1, i.e., a zero?

Contribution in phase, letting  $\omega = \frac{1}{T}$ :

$$\angle 1 + iT\omega = \begin{cases} \approx 0 & \text{for } \omega \ll 1/T \\ -\frac{\pi}{4} = 45^{\circ} & \text{for } \omega = 1/T \\ \approx \frac{\pi}{2} = 90^{\circ} & \text{for } \omega \gg 1/T \end{cases}$$

#### What is the contribution of Ts + 1, i.e., a zero?

Contribution in phase, letting  $\omega = \frac{1}{T}$ :

$$\angle 1 + iT\omega = \left\{ \begin{array}{ll} \approx 0 & \text{for } \omega \ll 1/T \\ -\frac{\pi}{4} = 45^{\circ} & \text{for } \omega = 1/T \\ \approx \frac{\pi}{2} = 90^{\circ} & \text{for } \omega \gg 1/T \end{array} \right.$$

*Discussion:* what happens if a zero is in the right-hand plane? → non-minimum phase systems, will see them soon!

# Summary of the most important contributions

#### constant

$$H(s) = K \mapsto |H(j\omega)|[dB] = 20 \log K dB \angle H(j\omega) = 0^{\circ} \forall \omega$$

#### single pole

$$H(s) = \frac{1}{1+Ts} \quad \begin{cases} |H(j\omega)|[dB] = 0dB & \angle H(j\omega) = 0^{\circ} & \text{for } \omega \ll \frac{1}{T} \\ |H(j\omega)|[dB] = -20dB & \angle H(j\omega) = -90^{\circ} & \text{for } \omega \gg \frac{1}{T} \end{cases}$$

#### single zero

$$H(s) = 1 + Ts \quad \begin{cases} |H(j\omega)|[dB] = 0dB & \angle H(j\omega) = 0^{\circ} & \text{for } \omega \ll \frac{1}{T} \\ |H(j\omega)|[dB] = 20dB & \angle H(j\omega) = 90^{\circ} & \text{for } \omega \gg \frac{1}{T} \end{cases}$$

# Summary of the most important contributions

#### And the others?

integrators and derivators = limit cases for  $T \to +\infty$ 

Note: nobody nows draw stuff by hand. You should nonetheless remember the general behaviors, so to do not need to actually draw Bode plots if you just need to check something (and in any case you should know the concepts)

?

Non-minimum phase systems

#### Roadmap


- what is a minumum phase system?
- how can I see if a LTI system is non-minimum phase from its Bode plot?
- which properties do minimum phase systems have?

# Example 1: putting some wood in a fireplace

• does the amount of heat produced by the fireplace increase immediately?


### Example 2: changing the altitude of an airplane

• does the altitude of the plane increase immediately?



# Example 3: parking a car backwards

• does the distance from the curb decrease immediately?



Non-minimum-phase systems: systems that have a step response that start "in the wrong direction"

Non-minimum-phase systems: systems that have a step response that start "in the wrong direction"

How do we see this from Bode plots? → this module

# Considerations about Bode plots

#### Considerations about Bode plots

• typically Bode plots have phase plots that are entirely negative

#### Considerations about Bode plots

- typically Bode plots have phase plots that are entirely negative
- there may be different H(s) that have the same  $|H(i\omega)|$  but different  $\angle H(i\omega)$

# Example about "there may be different H(s) that have the same $|H(i\omega)|$ but different $\angle H(i\omega)$ "

$$H_1(s) = \frac{K(1-T_3s)}{(1+T_1s)(1+T_2s)} \qquad H_2(s) = \frac{K(1+T_3s)}{(1+T_1s)(1+T_2s)}$$

But if "there may be different H(s) that have the same  $|H(i\omega)|$  but different  $\angle H(i\omega)$ ", then which H(s) is that one that has the "most negative" phase?

But if "there may be different H(s) that have the same  $|H(i\omega)|$  but different  $\angle H(i\omega)$ ", then which H(s) is that one that has the "most negative" phase?

#### Conditions:

- ullet all the poles of H(s) are in the left plane
- ullet all the zeros of H(s) are in the left plane
- $\bullet$  H(s) does not contain delays (i.e.,  $e^{-as}$ ). In other words, H(s) is rational

But if "there may be different H(s) that have the same  $|H(i\omega)|$  but different  $\angle H(i\omega)$ ", then which H(s) is that one that has the "most negative" phase?

#### Conditions:

- ullet all the poles of H(s) are in the left plane
- ullet all the zeros of H(s) are in the left plane
- H(s) does not contain delays (i.e.,  $e^{-as}$ ). In other words, H(s) is rational

one can show that flipping the zeros on the right plane does not change the amplitude response, but changes the phase one!

## Sometimes systems are always minimum phase


Example: spring-mass systems for which m, f, k > 0:

$$H(s) = \frac{m/k}{\frac{m}{k}s^2 + \frac{f}{k}s + 1}$$

### Sometimes systems are always non-minimum phase

Example: system with time-delay:

$$H(s) = \frac{e^{-s/T_2}}{1 + T_1 s}$$





### Sometimes systems are always non-minimum phase

Example: system with time-delay:

$$H(s) = \frac{e^{-s/T_2}}{1 + T_1 s}$$

Note how  $H'(s) = \frac{1}{1 + T_1 s}$  has the same amplitude response, but higher phase response:







#### Another example


$$H_1(s) = \frac{(s+3)(s+7)}{(s+0.5)(s+2)(s+8)}$$

$$H_2(s) = -\frac{(s-3)(s+7)}{(s+0.5)(s+2)(s+8)}$$





The most important concept in this topic: the smallest the phase, the 'earliest' the impulse response happens



### **Filters**

#### Roadmap

- motivations
- the simplest filters
- hints on how to make them more complicated

#### Why and where do we use filters?

Example 1: managing time signals, e.g., to

- eliminate some undesired frequencies
- separate different signals with different components
- create models that can then be used to do data-compression
- removing trends and biases

#### Why and where do we use filters?

Example 2: make the actuators only follow meaningful signals, e.g., by

- remove dithering
- remove offsets and low-frequency biases

#### Why and where do we use filters?

Example 3: help the estimation of the state of the system, e.g., by

filtering noise

(this is connected with the topics of Luenberger observers and Kalman filters)


# The 4 fundamental types of filters

- low-pass
- high-pass
- band-pass
- notch / band-stop


#### Low-pass filters, conceptually

- make the frequencies that are sufficiently low pass undisturbed
- stop the higher frequencies

## Low-pass filters, Bode plots



## Low-pass filters, Bode plots




Simplest low pass filter:

$$H(s) = \frac{1}{1+Ts} \implies \begin{cases} |H(i\omega)| \approx 1 \text{ for } \omega \ll 1/T \\ |H(i\omega)| \approx 0 \text{ for } \omega \gg 1/T \end{cases}$$


## High-pass filters, conceptually

- stop frequencies that are sufficiently low
- make the higher frequencies pass undisturbed

# High-pass filters, Bode plots



# High-pass filters, Bode plots




Simplest high pass filter:

$$H(s) = \frac{Ts}{1 + Ts} \implies \begin{cases} |H(i\omega)| \approx 0 \text{ for } \omega \ll 1/T \\ |H(i\omega)| \approx 1 \text{ for } \omega \gg 1/T \end{cases}$$

# Do you like electronics? Then you may build your own RC-filter!

#### Concepts:


- condensers work as low-pass filters
- resistances can be used to work as high-pass filters



# Do you like electronics? Then you may build your own RC-filter!

#### Concepts:

- condensers work as low-pass filters
- resistances can be used to work as high-pass filters



this is how filters were all implemented once, and this is still a valid strategy in cheap embedded systems

#### Band-pass filters, conceptually


- make frequencies within a defined band pass undisturbed
- stop frequencies that are either too low or too high

#### Band-pass filters, conceptually


- make frequencies within a defined band pass undisturbed
- stop frequencies that are either too low or too high

i.e., combine a low-pass and a high-pass filter

## Band-pass filters, Bode plots




# Band-pass filters, Bode plots



Simplest band-pass filter: series (i.e., kind of a logical "and") of low- and high-pass:


$$H_{\rm lp}(s) = \frac{1}{1 + T_1 s}$$
 and  $H_{\rm hp}(s) = \frac{s}{1 + T_2 s}$  thus  $H(s) = \frac{s}{1 + (T_1 + T_2) s + T_1 T_2 s^2}$ 

#### Band-pass filters, Bode plots



- all the frequencies  $\gg 1/T_1$  will be stopped by the low pass part
- ullet all the frequencies  $\ll 1/T_2$  will be stopped by the high pass part


# Band-pass via RLC-circuits




#### Notch / band-stop filters, conceptually

- stop a certain band of frequencies
- let the others pass

## Notch / band-stop filters, Bode plots




## Notch / band-stop filters, Bode plots



Simplest band-stop filter: parallel (i.e., kind of a logical "or") of high- and low-pass filter

$$H_{\rm lp}(s) = \frac{1}{1 + T_1 s}$$
 or  $H_{\rm hp}(s) = \frac{s T_2}{1 + T_2 s}$  thus  $H(s) = \frac{T_2 s}{T_1 T_2 s^2 + (T_1 + T_2) s + 1}$ 


# Notch / band-stop via RLC-circuits



-

# An interesting filter: all-pass, but adding some phase

#### Motivation: model or compensate for time-delays:



# An interesting filter: all-pass, but adding some phase

requirement:  $|H(i\omega)| = 1$  for all the  $\omega$ 's but  $\angle H(i\omega) \neq 0$ . Simplest one:

$$H(s) = \frac{s - p}{s + p} \quad p > 0$$

# An interesting filter: all-pass, but adding some phase

requirement:  $|H(i\omega)| = 1$  for all the  $\omega$ 's but  $\angle H(i\omega) \neq 0$ . Simplest one:

$$H(s) = \frac{s - p}{s + p} \quad p > 0$$


#### Notes:

- ullet this is the 1-st order Pade-approximation of  $e^{-\frac{2}{p}s}$
- all the frequencies have no distortions in the amplitudes, but the higher frequencies are delayed of half a period

?


# Problem: the filters we saw up to now are not too "sharp"


...i.e., there are a too many frequencies that are in between "low" and "high". We would like the transitions "low" to "high" to be sharper!



#### Butterworth filters


Motivation: design "sharper" filters






#### Butterworth filters

Motivation: design "sharper" filters







Strategy: add poles and zeros opportunely. They come in all the forms: low-pass, high-pass, band-pass, notch / band-stop

#### Butterworth filters

Motivation: design "sharper" filters





Strategy: add poles and zeros opportunely. They come in all the forms: low-pass, high-pass, band-pass, notch / band-stop

interested in more info? check wikipedia!