

## Chapter III-15 — Platform-Related Issues

The coordinates specify the location of the content region, in Macintosh terminology, or the client area, in Windows terminology, of the window. They do not specify the location of the window frame or border.

On Macintosh, a point is always interpreted to be one pixel except on Retina displays where it is two.

On Windows, the correspondence between a point and a pixel can be controlled by the user using system settings. Since Igor stores window positions in units of points, if the user changes the number of pixels per point, the size of Igor windows in pixels will change.

### Control Panel Resolution on Windows

In the past, by default, Windows screens ran at 96 DPI (dots-per-inch) resolution. In recent years, high-resolution displays, also called UltraHD displays and 4K displays, have become common.

In Igor6 and before, commands that create control panels and controls use screen pixel units to specify sizes and coordinates. This results in tiny controls on high-resolution displays.

In Igor7 and later, control panels and control sizes and coordinates can be specified in units of points instead of pixels. Since a point is a resolution-independent unit, this results in controls that are the same logical size regardless of the physical resolution of the screen.

By default, panels are drawn using pixels if the screen resolution is 96 DPI but using points for higher-DPI settings. This gives backward compatibility on standard screens and reasonably-sized controls on high-resolution screens.

You can change the way control panel coordinates and control sizes are interpreted using two different methods:

1. Control Panel Expansion (Igor Pro 9.00 and later)
2. You can set control panel expansion using the Expansion submenu in the Panel menu or using the Expansion setting in the Panel section of the Miscellaneous Settings dialog. If you are using Igor Pro 9.00 or later, this method is preferred.

See the **Control Panel Expansion** on page III-443 for further discussion.

3. SetIgorOption with the PanelResolution keyword.

This method requires executing commands as described in the next section. It can make panels larger than normal but not smaller. It is not recommended in Igor Pro 9.00 or later.

See also **Control Panel Units** on page III-444.

### SetIgorOption PanelResolution

In Igor Pro 9.00 and later we recommend that you use **Control Panel Expansion** instead of SetIgorOption PanelResolution.

You set this option by executing a command of the form:

```
SetIgorOption PanelResolution = <resolution>
```

The <resolution> parameter controls how Igor interprets coordinates and sizes in control panels. It must be one of these values:

- 0: Coordinates and sizes are treated as points regardless of the screen resolution.
- 1: Coordinates and sizes are treated as pixels if the screen resolution is 96 DPI, points otherwise. This is the default setting in effect when Igor starts.
- 72: Coordinates and sizes are treated as pixels regardless of the screen resolution (Igor6 mode).
- >96 If <resolution> is greater than 96, panel coordinates and sizes are treated as points regardless of the screen resolution. Larger values make larger panels and controls. For example on a 96 DPI screen SetIgorOption PanelResolution = 192 makes them twice as large as normal.

This setting is not remembered across Igor sessions.

The resolution for a panel is set when the panel is created so changing the panel resolution does not affect already-existing control panels.

Programmers are encouraged to test their control panels at various resolution settings.

For the most part, Igor6 control panels will work fine in Igor7 and later. However, if you have panels that rearrange their components depending on the window size, you probably have some code that uses the ratio of 72 and ScreenResolution. For example, here is a snippet from the WaveMetrics procedure AxisSlider.ipf:

```
case "Resize":  
    GetWindow kwTopWin, gsize           // Returns points  
                                         // Controls are positioned in pixels  
    grfName= WinName(0, 1)  
    V_left *= ScreenResolution / 72   // Convert points to pixels  
    V_right *= ScreenResolution / 72  
    Slider WMAxS1S1, size={V_right-V_left-kSliderLMargin, 16}  
    break
```

To make this work properly at variable resolution, we use the **PanelResolution** function, added in Igor Pro 7.00:

```
case "Resize":  
    GetWindow kwTopWin, gsize           // Returns points  
    grfName= WinName(0, 1)  
    V_left *= ScreenResolution / PanelResolution(grfName)      // Variable  
    V_right *= ScreenResolution / PanelResolution(grfName)     // resolution  
    Slider WMAxS1S1, size={V_right-V_left-kSliderLMargin, 16}  
    break
```

The PanelResolution function, when called with "" as the parameter returns the current global default setting for panel resolution in pixels per inch or, if in Igor6 mode, 72. When called with the name of a control panel or graph, it returns the current resolution of the specified window in pixels per inch.

If you want your procedures to work with Igor6, you should insert this into each procedure file that needs the PanelResolution function:

```
#if Exists("PanelResolution") != 3  
Static Function PanelResolution(wName)      // For compatibility with Igor7  
    String wName  
    return 72  
End  
#endif
```

To find other examples, use the Help Browser to search procedure files for PanelResolution.

See also **Control Panel Units** on page III-444.