

IMAGINEART
PRESENTS



POWERED BY SEEDANCE 2.0

THE COMPLETE ONBOARDING GUIDE

From your first project to production-ready films.

A practical, no-prior-experience-required guide for
creators, filmmakers, and storytellers.

CONTENTS

Find your way.

Eleven chapters, four production modules, one quick-reference card. The guide is built so each section stands on its own — start anywhere, jump anywhere.

01	Welcome to Film Studio	03	02	Before You Begin	05
03	Getting Started · Your First Project	06	04	Understanding the Workspace	07
05	Module 1 · Creating Images	09	5.1	Upload or Generate	09
5.2	Storyboard mode	09	5.3	The Cinematographer's Toolkit	10
5.4	Saving & reusing presets	14	06	Module 2 · Creating Videos	15
6.1	Single-shot videos	15	6.2	Multi-shot videos	15
6.3	Genres explained	16	6.4	Camera movements	17
6.5	Speed ramps	19	6.6	Scene & shot timing	20
07	Module 3 · Editing an Existing Video	22	08	Module 4 · Extending a Video	24
09	Pro Tips & Best Practices	25	10	Glossary	27
11	Quick Reference Card	29			

CHAPTER 01

Welcome to Film Studio.

A complete production environment for visual storytellers — the controls of a real cinematographer, paired with generative AI.

ImagineArt Film Studio is a complete production environment for visual storytellers. Whether you are a solo creator with a single idea or a team building a multi-shot trailer, Film Studio gives you the tools that a traditional cinematographer would use — **cameras, lenses, focal lengths, apertures, movements, genres** — and pairs them with generative AI so you can produce production-ready images and films from a prompt.

This guide is designed to take you from "never opened Film Studio" to "comfortably producing your own multi-shot film" in one focused read. You do not need any prior filmmaking experience to use the tool, and you do not need to read this guide in one sitting. Each module is self-contained, so you can jump to the section that matches what you want to do today.

How this guide is organized

The guide follows a simple principle: **learn the smallest useful thing first, then build on it.** We start with the workspace and a basic image, then add cinematographic controls, then move into video, and finally cover editing and extending your work.

- **Sections 1–4** cover orientation: what Film Studio is, what you need, and how the workspace is laid out.
- **Section 5** covers Image creation — the foundation for everything else, because a great frame is the seed of a great shot.
- **Section 6** covers Video creation — single-shot and multi-shot workflows.
- **Sections 7–8** cover Edit and Extend — tools for refining and lengthening existing video.
- **Sections 9–11** are reference material: tips, glossary, and a one-page cheat sheet you can print.

How to use this guide

READ THIS FIRST If you only have ten minutes, read **Section 3 (Getting Started)** and **Section 4 (Workspace)**. That alone is enough to start producing.

Come back to the other sections when you want more control.

Throughout the guide you will see three kinds of callouts:

PRO TIP

A shortcut or non-obvious technique that saves time.

TRY THIS

A small exercise to lock in what you just learned.

HEADS UP

A limit, a constraint, or a common mistake to avoid.

WHAT YOU WILL BE ABLE TO DO

By the end of this guide.

Seven concrete capabilities — the ones that take you from blank workspace to multi-shot film with a consistent look.

- 01 Start a new project on **imagine.art / film-studio** and find your way around the workspace.
- 02 Generate a single image from a prompt and control its look using **camera, lens, focal length, and aperture**.
- 03 Build a **multi-scene storyboard** for any production.
- 04 Generate a single-shot video, then graduate to **multi-shot films up to 15 seconds** long.
- 05 Apply **genres, camera movements, and speed ramps** to give your footage a deliberate, cinematic feel.
- 06 Edit an existing video with a prompt, and extend an existing video into a longer sequence.
- 07 Save your favorite camera setups as **presets**, so your work has a consistent look across projects.



A note on philosophy

Film Studio is a director's tool, not a slot machine. The more deliberate your direction — your camera choice, your aperture, your shot rhythm — the more deliberate your result. This guide is structured to help you make those choices with intention.

CHAPTER 02

Before you begin.

Film Studio runs entirely in your browser. There is nothing to install — but a few minutes of preparation will save you frustration later.

What you need

BROWSER

A modern browser — **Chrome, Edge, Safari, or Firefox**, kept reasonably up to date.

INTERNET

A **stable connection** — generation runs on our servers, so a steady link makes for a smoother experience.

ACCOUNT

An **ImagineArt account** — sign up or log in at imagine.art before opening Film Studio.

REFERENCES (OPTIONAL)

Any **photos, mood-board images, or video clips** you want to influence the look. Keep them on your computer so you can upload quickly.

A useful mindset

Film Studio rewards specificity. A prompt like *"a person walking"* will get you something generic. A prompt like *"a tired detective in a long beige coat walking down a wet alley at 2 a.m., neon reflections in puddles"* will get you something cinematic.

As you go through this guide, you will learn how the camera, lens, focal length, aperture, genre, and movement controls let you be even more specific — but the prompt is always the foundation.

PRO TIP Treat each prompt the way a director would brief a crew. Tell the system **who is in the shot, what they are doing, where they are, what time of day it is, and what mood you are after.** The richer the brief, the closer the result.

CHAPTER 03

Your first project.

Follow this section once and the rest of the guide will make a lot more sense.

Step 1 — Open Film Studio

- 01 Open your browser and go to **imagine.art / film-studio**.
- 02 Sign in if you are not already logged in.
- 03 You will land on the Film Studio home view, which lists your existing projects on the left side.

Step 2 — Start a new project

- 01 Click the "+" button next to *Projects* in the top-left corner.
- 02 Give your project a name. A descriptive name (e.g. "*Cyberpunk Trailer V1*") is easier to find later than the default "*Untitled Project*".
- 03 Press **Enter** or click outside the field to save.

HEADS UP Every piece of work you create — images, videos, storyboards, presets — lives inside a project. **Make a habit of starting a new project for each idea**, the same way a film team would treat each production as its own folder.

Step 3 — Open the project

Click the project name in the left sidebar. The main workspace opens. You are now ready to create — the next section walks through what each part of the workspace does.

CHAPTER 04

Understanding the workspace.

Three areas, four core actions, one top bar. Learn this once and every later section gets faster.

The four core actions

Across the top of the left panel you will see four tabs. These are the four things you can do in Film Studio, and the rest of this guide is organized around them:

01



Image

Generate or upload still images, with full cinematographic controls.

WHEN

Designing a frame, building a storyboard, or producing key art.

02



Create Video

Generate a video from prompts — single shot, or multi-shot up to 15 seconds.

WHEN

You want to produce new motion footage from scratch.

03



Edit Video

Take an existing video and re-direct it with a prompt — change the look, the genre, or the motion.

WHEN

You have footage that is close but not quite right.

04




Extend


Take an existing video and continue it forward — new frames that follow on naturally.

WHEN

You have a clip and want a longer version of it.

The three workspace areas





01 Control panel (left)

Set up your shot — prompt, references, camera, lens, aspect, resolution. Hit Generate.

02 Canvas (center)

Your viewer. Generated images & videos appear here. Zoom, compare versions, inspect detail.

03 Scene timeline (bottom)

Where multi-shot work lives. Add, rename, reorder, and time your shots.

The top bar

The top bar gives you account-level controls — **project navigation, search, contact sales, plan upgrades, notifications, and your profile**. The *Assets* button on the right opens a library of all the media you have generated or uploaded in this project, so you can reuse anything you have already made.

Reading the left panel

The **left panel changes based on the tab you are in**. In *Image*, you see prompt, references, output chips (variations, aspect, resolution), and the camera panel. In *Create Video*, you also see motion controls — genre, movement, speed ramp — plus optional start and end frames. *Edit* and *Extend* require a source video before the prompt becomes active.

Reading the timeline

The bottom strip is your **scene timeline**. When you work on a single image, you will only see one scene. When you build a multi-shot video, each shot appears as a card you can drag to reorder, resize to retime, or click to focus.

TRY THIS Before you read further, open Film Studio, create a project called "**Practice Project**," and click through each of the four tabs (Image, Create Video, Edit Video, Extend). You do not need to generate anything yet — just notice how the left panel changes based on the tab. That five-minute tour will make the rest of this guide much easier to follow.

KEEP IN MIND

Anything you make in any tab is automatically available in the others. Generate an image, then drop it as a start frame for a video. Render a video, then use Extend to continue it. The four actions are designed to compose.

WHERE THINGS LIVE

All output is filed under the current project. Use the **Assets** button (top right) to browse everything you have made — sorted by type, date, or shot. Drag from there directly into any new prompt.

MODULE 01 · CHAPTER 05

Creating images.

Images are the foundation of everything you will do in Film Studio. Even when your goal is a video, you will often start by generating images for individual frames, then bring them into the video tab as references.

5.1 Two ways to start: Upload or Generate

When you open the Image tab, you have two starting points:

- **Upload media.** Use this when you already have an image you want to work with — a photograph, concept art, a frame from another video. Click *Upload media* in the optional media box and pick the file. You can also click *Select* to pull from media you have generated earlier in this project.
- **Generate from a prompt.** Skip the upload box and just write a description in the Prompt field. The system will create the image for you. Add reference media via *Add media* inside the prompt area if you want to influence style or composition.

These two are not mutually exclusive. The most common workflow is to **upload a reference image and then write a prompt** that tells the system what to change or what to use the reference for.

OUTPUT CONTROLS — THE THREE CHIPS BELOW THE PROMPT

CHIP	WHAT IT CONTROLS	WHEN TO CHANGE IT
1/4	Number of variations generated per click. Increase to compare options; decrease to save credits.	Increase when exploring; decrease when iterating on something you already like.
16:9	Aspect ratio. 16:9 is cinematic widescreen; portrait and square ratios also available.	Pick the ratio that matches the final delivery — social vertical, web horizontal, or print square.
4K	Output resolution. Higher means more detail and a larger file.	Use 4K for final deliverables. Drop it lower for fast iteration.

5.2 Storyboard mode

A storyboard is a sequence of frames that map out a film before you shoot it. Film Studio gives you a **Storyboard toggle** (just below the upload area on the Image tab) that lets you generate a full sequence of frames in one go, instead of generating each frame separately. When Storyboard is on, the system reads your prompt as a sequence of shots rather than a single frame, and produces a series of images that share a consistent style.

PRO TIP Use Storyboard mode **early**. Even if you only plan to deliver a single hero image at the end, generating a storyboard first helps you decide on framing, color palette, and pacing before you commit to a final look.

SECTION 5.3

The Cinematographer's Toolkit.

Four dials separate Film Studio from a generic image generator: camera body, lens, focal length, aperture. These choices, more than anything else, shape the personality of your image.

01 · BODY

Sets the underlying **texture** — digital cleanliness, film grain, large-format scale.

02 · LENS

Sets the **optical character** — anamorphic, swirly, surgical, vintage.

03 · FOCAL

Sets the **field of view** — how much of the world you see, how compressed.

**04 ·
APERTURE**

Sets the **depth of field** — how much of the image is in sharp focus.

5.3.1 Camera bodies

Cameras fall into two families: **digital** (clean, modern, color-rich) and **film** (grainy, organic, classic). Pick the family first, then the specific model based on the feel you want.

CAMERA	CHARACTER	GREAT FOR
DIGITAL CAMERAS		
ARRI Alexa	Industry standard for high-end cinema. Soft highlights, natural skin tones, restrained color.	Premium dramatic features, character-driven scenes, anywhere you want "this looks like a real movie."
Sony FX6	Compact cinema-style camera. Versatile, slightly cleaner and sharper than Alexa.	Documentary, indie films, run-and-gun shoots, modern naturalistic stories.
Red V Raptor	High-resolution 8K with vibrant, saturated color. Crisp detail in every frame.	Action, sci-fi, VFX-heavy scenes, music videos, anywhere maximum detail matters.
FILM CAMERAS		

CAMERA	CHARACTER	GREAT FOR
ARRI Flex (35mm)	Classic film texture. Visible grain, warm tonality, organic falloff in shadows.	Period pieces, nostalgic looks, music videos, anywhere you want a hand-made feel.
IMAX	Large-format film. Massive resolution, vast dynamic range, epic scope.	Landscapes, scale shots, sci-fi spectacle — Nolan films, blockbusters, anything that should feel huge.

PRO TIP If you are unsure which camera to pick, **start with ARRI Alexa**. It is the safest choice for almost any narrative scene and tends to produce the most universally pleasing results.

SECTION 5.3.2

Lenses.


Where the camera body sets the underlying texture, the lens sets the optical personality. Lenses fall into two groups — **anamorphic** (cinematic widescreen) and **spherical** (everything else).

LENS	CHARACTER	GREAT FOR
ANAMORPHIC		
Anamorphic	Cinematic widescreen with characteristic horizontal lens flares, oval bokeh, slight stretch.	Hollywood-style epics, sci-fi, action — anywhere the audience should immediately feel "this is a movie."
SPHERICAL		
Fish eye	Extreme curved distortion, near-180° field of view.	POV action, skating, surreal sequences, dream logic.
Macro	Surgical detail on small subjects, very shallow focus.	Textures, eyes, food, mechanisms, jewelry — anything where detail is the subject.
Petzval	Vintage portrait lens with a famous swirly bokeh around the edges.	Romantic portraits, dream sequences, fashion editorials.
Probe	Long, thin lens that can reach into tight spaces and exaggerate depth.	Tabletop, hyper-detail shots, unique angles into small worlds — food, models, miniatures.
Spherical	The neutral, naturalistic cinema lens.	Most narrative work — the safe, transparent choice when you want the lens to disappear.
Vintage	Soft contrast, lower sharpness, character flaws.	Period pieces, music videos, dreamy retro aesthetics, mood-first scenes.

SECTION 5.3.3

Focal length.

Measured in millimeters; controls two things at once — **how wide your field of view is**, and **how compressed your perspective looks**. Wide focal lengths make space feel deep. Long focal lengths make space feel flat and stacked.



CATEGORY	FOCAL	WHAT IT DOES	GREAT FOR
Fish eye	8 MM	Extreme wide with strong curved distortion.	POV action, skate videos, surrealism.
Ultra wide	14 MM	Very wide, mild distortion at the edges.	Tight interiors, big landscapes, immersive scenes.
Ultra wide	18 MM	Slightly more controlled ultra-wide.	Landscapes, architecture, environmental establishing shots.
Wide	35 MM	Documentary-style wide. Sees more than the eye does.	Environmental portraits, dialogue, anywhere context matters.
Standard	50 MM	Matches the natural perspective of the human eye.	Naturalistic narrative — the most versatile choice.
Portrait	85 MM	Slight background compression, beautiful subject isolation.	Portraits, close-ups, emotional reactions.
Portrait	100 MM	More compression, tighter framing, dreamier separation.	Beauty shots, intimate close-ups, hero moments.

PRO TIP Focal length is the **single biggest lever** for how a scene "feels." Wide lenses (8–35mm) make spaces feel large, energetic, immersive. Long lenses (85–100mm) make spaces feel intimate, compressed, emotional. **When in doubt, start with 35mm or 50mm** — the workhorse focal lengths of cinema.

SECTION 5.3.4

Aperture.

Controls **depth of field** — how much of your image is in sharp focus. Wide-open (small f-number) gives creamy background blur and razor-thin focus. Stopped-down (large f-number) keeps everything sharp from foreground to horizon.



CATEGORY	APERTURE	WHAT IT DOES	GREAT FOR
Wide open	F/1.4	Maximum background blur, very shallow focus.	Dreamy portraits, romantic scenes, isolating a subject from chaos.
Near wide	F/2.0	Soft, blurred background with slightly more in-focus subject.	Standard portraits, interviews, intimate dialogue scenes.
Middle range	F/2.8	Balanced look — subject sharp, background pleasantly soft.	Most cinematic scenes; the go-to default.
Stopped down	F/5.6	More of the scene in focus, less background blur.	Group shots, documentary-style work, scenes with multiple subjects.
Deep focus	F/16	Everything from foreground to horizon in sharp focus.	Landscapes, epic establishing shots, classic deep-focus cinema.

SECTION 5.3.5

Putting it together.

Reading tables one row at a time is useful — but the magic comes from combining them. Seven starter combos you can copy directly into a project.

— Premium drama

CAMERA	ARRI Alexa
LENS	Spherical
FOCAL	50mm
APERTURE	f/2.0

The safe, classic cinema look. If you take one combo from this page, take this one.

— Hollywood epic

CAMERA	IMAX
LENS	Anamorphic
FOCAL	35mm
APERTURE	f/2.8

Big scale, widescreen flares. Trailer energy, the-big-screen feel.

— Music video / dream

CAMERA	ARRI Flex
LENS	Vintage
FOCAL	85mm
APERTURE	f/1.4

Grainy, soft, romantic. Reach for this when you want texture and warmth.

— Cyberpunk action

CAMERA	Red V Raptor
LENS	Anamorphic
FOCAL	35mm
APERTURE	f/2.0

Crisp, vivid, widescreen. Neon-on-wet-asphalt territory.

— Documentary

CAMERA	Sony FX6
LENS	Spherical
FOCAL	35mm
APERTURE	f/5.6

Naturalistic, lots in focus. Honest, observational.

— Beauty close-up

CAMERA	ARRI Alexa
LENS	Petzval
FOCAL	85mm
APERTURE	f/1.4

Swirly bokeh, soft glow. Fashion, beauty, hero portraits.

— Surreal POV

CAMERA	Red V Raptor	LENS	Fish eye	FOCAL	8mm	APERTURE	f/2.8
--------	--------------	------	----------	-------	-----	----------	-------

SECTION 5.4

Saving & reusing presets.

Consistency is the difference between a collection of nice images and a film. A preset captures camera, lens, focal length, and aperture under one name — apply it with a single click.

Once you find a camera/lens/focal/aperture combination that works for your project, **save it as a preset**. A preset captures all four settings under a name you choose, so you can apply it again with one click on a future image or video — without having to remember what you picked.

Saving presets matters because **consistency is what makes a series of images feel like a film**. If every frame of your project uses the same preset, your work will feel like it came from the same hand. Without that, even strong individual images can feel disconnected.

How to save a preset

- 01 In the Camera panel, set the four values (camera, lens, focal length, aperture) the way you want them.
- 02 Click the **save icon** next to the Camera title.
- 03 Give the preset a clear name — for example, *"Project Hero Look."*
- 04 Apply it later from the same panel by selecting it from your saved presets list.

TRY THIS For your first project, build **exactly one preset** and use it for every image and every video. This single discipline will do more for the consistency of your work than any other technique in this guide.

END OF MODULE 1

You now have the four cinematographic dials, seven proven combos, and a discipline for keeping your look consistent. Next, motion.

02

MODULE 02 · CHAPTER 06

Creating videos.

From frames to motion. Same cameras, same lenses — plus how the camera moves, how time bends, which genre the result feels like, and how long each piece of the shot lasts. Two flavors: single-shot and multi-shot, up to 15 seconds.

6.1 Single-shot videos

A single-shot video is **one continuous clip generated from one prompt**. This is the right starting point when you want a quick result, when your idea is one moment rather than a sequence, or when you are testing how a particular look behaves in motion.

HOW TO MAKE A SINGLE-SHOT VIDEO

- 01 Open the **Create Video** tab in your project.
- 02 Optionally upload a **start frame** and an **end frame**. The system will treat these as the bookends of your shot.
- 03 Optionally add **reference images** using the *Add media* button. References influence style without dictating exact content.
- 04 Write your **prompt**. Describe subject, action, setting, and mood.
- 05 Set the cinematic controls (genre, camera movement, speed ramp, camera/lens/focal/aperture).
- 06 Hit **Generate**.

HEADS UP Start and end frames are powerful, but they constrain the result. Use them when you specifically want to control where the shot begins or ends. **If you just want the system to be creative, leave them empty.**

6.2 Multi-shot videos

A multi-shot video is a **single piece of footage made up of several distinct shots** that the system will stitch together into one continuous film. This is how you build a sequence — a scene followed by a closeup followed by a wide reveal — without combining clips manually.

THE 5-SHOT, 15-SECOND RULE

5

MAX SHOTS PER VIDEO

15s

MAX TOTAL LENGTH

If you use all 5 shots, each averages **3 seconds**. If your story needs a long establishing shot, you might use 1 shot for 8 seconds and 3 short shots of 2–3 seconds each. The choice is yours — but the total never exceeds 15 seconds and you never have more than 5 shots.

HOW TO BUILD A MULTI-SHOT VIDEO

- 01 Open the **Create Video** tab and switch to multi-shot mode.
- 02 For each shot, write its own **prompt**. Treat each as a complete brief for that moment.
- 03 For each shot, set the **duration**. The interface will show how many seconds are left in your 15-second budget.
- 04 For each shot, you can also add reference media and adjust cinematic controls (camera movement, speed ramp, etc.).
- 05 Click the "+" icon in the scene timeline to add another shot. **Drag** shots to reorder.
- 06 When all shots are configured, hit **Generate**.

PRO TIP Write each prompt as if briefing a film crew on each scene of a one-page script. Keep your **subject and style consistent** across shots, but vary the framing and the action. **Wide → medium → close-up** is a classic three-shot rhythm that almost always works.

6.3 Genres explained

Selecting a genre tells the system what **emotional and visual vocabulary** to draw from. Genres are stylistic shortcuts — they change lighting, color palette, pacing cues, and reference material the system uses. Pick one that matches the story you are telling.



Action

Fast, kinetic, high-energy.

Visuals: Sharp contrast, bold color, hard light, motion blur. **Use for:** chases, fights, sports.



Adventure

Larger than life, journey-driven.

Visuals: Wide vistas, golden hour, rich earthy palette. **Use for:** exploration, hero's-journey moments.



Crime & Mystery

Tense, investigative, shadowed.

Visuals: Low-key lighting, muted colors, hard edges. **Use for:** detective scenes, noir.



Cyberpunk

Neon-soaked, urban dystopian future.

Visuals: Magenta & cyan, rain, holograms, dense cities. **Use for:** sci-fi cities, hacker scenes.

SECTION 6.3 (CONTINUED)

Genres, continued.



Historical

Grounded, period-accurate, classical.

Visuals: Restrained color, soft natural light, era-correct detail. **Use for:** period pieces, biographical drama.



Horror

Dread, unease, claustrophobic.

Visuals: Deep shadows, desaturated palette, off-balance framing. **Use for:** scary scenes, suspense.



Romance

Warm, intimate, soft.

Visuals: Warm light, soft focus, pastel and golden palette. **Use for:** love scenes, tender moments, dreamy memories.



Speculative

Imaginative, otherworldly, "what if."

Visuals: Surreal color, unusual physics, dreamlike composition. **Use for:** fantasy, sci-fi, magical realism.



Thriller

Psychological tension, simmering dread.

Visuals: Cool tones, tight framing, restrained motion. **Use for:** suspense, slow-burn dread, paranoia.



Wild West

Dusty, sun-baked, mythic.

Visuals: Warm yellows and oranges, harsh sun, wide vistas. **Use for:** westerns, frontier scenes, desert showdowns.

SECTION 6.4

Camera movements.

How the camera moves is part of how your scene speaks. A pan reveals. A dolly emphasizes. A handheld engages. A static shot pauses. **Pick the movement that matches the feeling of the moment, not just the geography of it.**

MOVEMENT	WHAT IT DOES	USE IT WHEN YOU WANT TO...
Static	No camera movement at all.	Hold a quiet moment, signal control or stillness, let action move within the frame.
Camera follows	The camera tracks alongside a moving subject.	Show someone moving through space — running, walking, driving — and stay with them.
Dolly in	The camera moves forward toward the subject.	Build tension, focus the audience, signal that something important is happening.
Dolly out	The camera moves backward, away from the subject.	Reveal context, signal isolation, end a scene or a thought.
Dolly left / right	The camera slides sideways while staying parallel to the subject.	Show parallel motion, reveal something hidden offscreen, add gentle motion to a static scene.
Drone shot	A high aerial view from above, often moving.	Establish scale, open a film, geographic reveal.
Handheld	Camera operated by hand — slightly shaky, organic.	Add intimacy, urgency, or chaos. Documentary and action.
Jib up	The camera rises smoothly on a crane.	Build hope, reveal what is above, end on a sweeping note.
Jib down	The camera descends smoothly on a crane.	Reveal what is below, descend into a scene, ground the audience.

Orbit around

The camera circles the subject.

Examine a subject from all sides, emphasize importance, add motion to a static figure.

MOVEMENT	WHAT IT DOES	USE IT WHEN YOU WANT TO...
Pan left / right	The camera rotates horizontally on a fixed axis.	Follow action across a space, reveal something to the side, scan an environment.
Tilt up	The camera angles upward.	Convey grandeur, scale, intimidation, or hope.
Tilt down	The camera angles downward.	Convey power dynamics, reveal something below, end on a grounded note.
Zoom in	The lens zooms in toward the subject.	Snap audience attention, mark an emotional beat, hint at obsession.
Zoom out	The lens zooms out away from the subject.	Provide context, reveal scale, isolate a subject within a larger world.

6.5 Speed ramps

A speed ramp is a **controlled change in playback speed** over the course of a shot. Speed ramps are a hallmark of modern cinema — used to emphasize an impact, stretch out a beautiful moment, or accelerate through a transition.

SPEED RAMP	WHAT IT DOES	USE IT WHEN...
Linear	Constant speed for the entire shot. No ramping.	You want a natural, even pace — the default for most scenes.
Slo Mo	The whole shot plays in slow motion.	You want a beautiful, dramatic moment — the lead-up, the reveal, the kiss, the punch.
Speed Up	The whole shot plays faster than real time.	You want energy, urgency, compressed time — montages, transitions, action.
Impact	The shot ramps sharply at a key moment — typically slow on either side of a fast burst.	You want to emphasize one specific frame inside the shot — the hit, the explosion, the snap.

Custom

You define your own speed curve across the shot.


You have a specific rhythm in mind that the presets do not match.

PRO TIP Speed ramps are best used **sparingly**. If every shot uses Slo Mo or Impact, none of them will feel special. Use Linear as your default, and bring in a ramp on the one or two shots where you really want to draw attention.

SECTION 6.6

Scene & shot timing.

At the bottom of the workspace you will see your timeline — one card per scene, with each shot laid out inside the scene. The timeline is where you control pacing.



From the timeline you can:

- Adjust the **duration** of any individual shot by dragging its edges.
- **Reorder shots** by dragging the cards.
- **Add new shots** with the "+" button.
- **Delete** shots you no longer want.
- **Rename scenes** for your own organization.

HEADS UP Remember the **15-second total ceiling**. The timeline shows how much of your budget each shot is consuming. If you try to extend a shot past your remaining budget, you will need to shorten another shot first.

03

MODULE 03 · CHAPTER 07

Editing an existing video.

For when you already have footage and want to redirect it. Provide the video, write a prompt describing what should change — the system produces a new version of the clip that follows your instruction. The original footage shapes the result.

When to use Edit Video

- You have a generated clip that is close but not quite right (wrong color, wrong mood, wrong genre).
- You have a real video and want to apply a stylized look to it.
- You want to keep the composition and motion of an existing shot but change its subject or setting.

How to edit a video

- 01 Open the **Edit Video** tab.
- 02 Provide the source video. Upload a file or pick one of your existing generations from the project library.
- 03 Write a prompt that describes what you want to change. **Be specific about what should stay the same and what should change.**
- 04 Optionally add reference media to influence the new style.
- 05 Set the cinematic controls — apply a new genre and new camera movements just as you would for a brand-new video.
- 06 Hit **Generate**. You will get back an edited version of your clip.

PRO TIP Edit Video works best when you give it **one clear instruction at a time**. *"Change the time of day to sunset"* produces a cleaner result than *"Change the time of day to sunset, add a horse, make it look like a Western, and slow it down."* If you have multiple changes to make — edit, review, then edit again.

Tips for consistent results

- Use the **same camera preset** you used for the original — this keeps the visual style consistent across the edit.
- Keep your prompts focused on **the change**, not on re-describing the entire scene.

- Use **reference images** when language alone isn't enough — a mood board is faster than a long description.

MODULE 04 · CHAPTER 08

Extending a video.

For when you have a video you love and want more of it. Provide the source clip, write a prompt describing what should happen next — the system generates new frames that continue naturally from where the original left off.

When to use Extend

- You generated a clip that ends too soon and you want to see more of the same.
- You have a 5-second moment and want it to play out for 10 seconds.
- You want a sequel-style continuation — **same subject, same world, what happens next.**

How to extend a video

- 01 Open the **Extend** tab.
- 02 Provide the source video — upload a file or pick from your project library.
- 03 Write a prompt that describes what should happen in the extension. The system will use the end of your original clip as the starting point, and your prompt as the direction forward.
- 04 Optionally add reference media and tune cinematic controls (genre, movements) for the extended portion.
- 05 Hit **Generate**. You will receive a new clip that continues from the original.

HEADS UP Extend is **forward-only**. It continues from the end of your source, not before the start. If you want a lead-in to a clip, generate that as a separate shot and assemble the two in a multi-shot video.

Tips for natural-feeling extensions

- Describe an action that naturally follows the end of your source. *"She turns and walks away"* is easier to extend from a clip of someone standing than *"she suddenly flies into space."*
- **Reuse your camera preset** so the optical character matches across the seam.
- Keep the lighting consistent in your prompt — sudden changes in lighting are the most common reason extensions feel disjointed.

CHAPTER 09

Pro tips & best practices.

Once you are comfortable with the basics, these habits will lift your output from "good generation" to "good film."

PROMPTING

- Write prompts the way a director briefs a crew: **subject, action, setting, time of day, mood.**
- Mention only what matters. Long prompts with conflicting instructions confuse the result.
- Lean on references for things hard to describe in words — a shade of teal, a face, a silhouette.

VIDEO STRUCTURE

- Build **storyboards before videos.** Cheap to iterate, easy to share.
- Use the **wide → medium → close-up** rhythm for multi-shot scenes. Classic for a reason.
- Save your strongest budget for the moment that matters most. Not every shot has to be the same length.

CINEMATOGRAPHY

- Pick a camera/lens/focal/aperture preset for your project and **stick to it.**
- Default to **35mm or 50mm.** Reach for ultra-wide or long lenses when the story specifically calls for it.
- Aperture **f/2.0–f/2.8** covers most narrative scenes. Use f/1.4 for romance and dreams; f/16 for landscapes and epic reveals.

PRODUCTION RHYTHM

- Work in iterations. **Four variations → pick one → refine → move on.** Trying to nail it in one click is slower.
- Name projects, scenes, and presets descriptively. *"Hero Shot V3"* beats *"Untitled."*
- Use the **Assets library.** Anything you generate is available to reuse.

Common mistakes to avoid

MISTAKE 01

Loading **every cinematic control** at once on your first try. Start with prompt + camera preset, then add movements and ramps.

MISTAKE 02

Asking for too many things in a single edit. **One change per pass.**

MISTAKE 03

Ignoring the **15-second ceiling** on multi-shot videos until the timeline forces you to. Plan your time budget before generating.

CHAPTER 10

Glossary.

A quick reference to terms used throughout this guide and inside Film Studio.

TERM	MEANING
Anamorphic	A lens type that produces widescreen cinematic images with characteristic horizontal flares and oval-shaped bokeh.
Aperture	The opening in a lens that controls how much of the image is in focus. Smaller f-numbers = more background blur.
Aspect ratio	The shape of the image, expressed as width:height. 16:9 is widescreen; 9:16 is vertical / social.
Bokeh	The visual quality of out-of-focus areas in an image.
Depth of field	How much of the image, from front to back, is in sharp focus.
Dolly	A camera move along the ground — forward, backward, left, or right.
Focal length	Measured in millimeters; controls field of view and perspective compression.
Genre	A stylistic category that informs lighting, color, and reference material the system uses.

Handheld

A camera operated by hand, with characteristic small movements.

IMAX

A large-format film camera known for massive resolution and epic scale.

CHAPTER 10 (CONTINUED)

Glossary, continued.

TERM	MEANING
Jib	A camera mounted on a crane that moves vertically (up or down).
Multi-shot video	A video made of multiple distinct shots stitched into one clip — up to 5 shots and 15 seconds total in Film Studio.
Pan	A horizontal camera rotation on a fixed axis.
Preset	A saved combination of camera body, lens, focal length, and aperture — reusable across images and videos.
Reference media	Images or clips you attach to a prompt to influence the style or content of the result.
Scene	An organizational unit in the timeline. A scene contains one or more shots.
Shot	A single continuous piece of footage within a scene.
Speed ramp	A controlled change in playback speed across a shot.
Spherical lens	The standard, naturalistic cinema lens family — the default optical look.
Storyboard	A sequence of frames that plan out a film before it is produced.
Tilt	A vertical camera rotation on a fixed axis (up or down).
Zoom	A change in focal length within a shot — optical rather than physical motion.

CHAPTER 11 · TEAR-OUT PAGE

Quick reference card.

One-page summary you can return to whenever you forget which dial does what.

IMAGINEART FILM STUDIO

CHEAT SHEET

V 1.0

IMAGINE.ART / FILM-STUDIO

STARTING FRESH

- Open** imagine.art / film-studio → "+"
Projects → name → click in.
- Pick a tab** Image · Create Video · Edit Video
· Extend.

THE FOUR IMAGE DIALS

- Body** Texture · Alexa, FX6, Raptor, ARRI
Flex, IMAX.
- Lens** Optical · anamorphic / fish eye /
macro / petzval / probe /
spherical / vintage.
- Focal** FoV · 8mm fish eye → 100mm
portrait.
- Aperture** Depth · f/1.4 dreamy → f/16 deep
focus.

EDITING & EXTENDING

- Edit Video** Existing video + prompt →
modified version.
- Extend** Existing video + prompt →
continues forward in time.

VIDEO LIMITS

- Max shots** 5 per video.
- Max length** 15 seconds total.
- Mode** Single-shot for one moment;
Multi-shot for a sequence.

VIDEO CONTROLS

- Genre** Picks the visual vocabulary.
- Movement** Pan · tilt · dolly · jib · orbit · drone ·
handheld · static · zoom.
- Speed ramp** Linear · Slo Mo · Speed Up ·
Impact · Custom.

DISCIPLINE THAT PAYS OFF

- One preset** Build one per project. Use it
everywhere.
- Storyboard** Before you video.
- One change** Per edit pass.
- Budget** Save 15-second budget for the
moment that matters most.

SAFE DEFAULT

ARRI ALEXA · SPHERICAL · 50MM · F/2.0 — the classic cinema look.
When in doubt, start here.

THE FINAL WORD

Film Studio is most powerful when you treat it like a real production. Plan in storyboards. Commit to a look with a preset. Direct each shot the way you would direct a crew. The tool is generous — give it specific direction, and it will give you a film.

● END OF GUIDE · SEE YOU IN THE WORKSPACE