Thermal Physics Notes

Refined Landau Style $\left(k_B=1\right)$

April 4, 2025

Contents

1	Foundations: Probability and Statistics	3
	1.1 The Random Walk and Binomial Distribution	3
	1.2 Moments of a Distribution	3
	1.3 Gaussian Approximation (Large N Limit)	3
	1.4 Multivariable Probability and Change of Variables	4
2	The Statistical Basis of Thermodynamics	4
	2.1 Microstates and Macrostates	4
	2.2 The Fundamental Postulate	5
	2.3 Statistical Definition of Macroscopic Parameters	5
	2.4 Density of States	5
3	Interaction Between Systems and Laws of Thermodynamics	5
	3.1 Types of Interaction: Heat and Work	6
	3.2 The First Law of Thermodynamics	6
	3.3 Quasistatic Processes and Generalized Forces	6
	3.4 Thermal Equilibrium, Entropy, and Temperature	7
	3.5 The Second Law of Thermodynamics	7
	3.6 The Fundamental Thermodynamic Relation	7
	3.7 Summary of Thermodynamic Laws	8
	5.7 Summary of Thermodynamic Laws	0
4	Thermodynamic Response Functions	8
	4.1 Heat Capacities	8
	4.2 Compressibility and Expansivity	9
5	Application: The Ideal Gas	9
	5.1 Statistical Derivation (Monatomic)	9
	5.2 Ideal Gas Law and Molar Quantities	9
	5.3 Specific Heats (Monatomic)	9
	5.4 Adiabatic Index	10
	5.5 Ideal Gas Processes	10
6	Thermodynamic Potentials	10
7	Maxwell Relations	11
	7.1 Relation between Heat Capacities	11
	7.2 Implications of the Third Law $(S \to S_0 \text{ as } T \to 0)$	
8	Calculating Entropy and Energy from Measurables	12
	8.1 Entropy $S(T,V)$	12
	8.2 Internal Energy $E(T, V)$	12

9	Thermodynamic Processes	13
	9.1 Free Expansion (Joule Expansion)	13
	9.2 Joule-Thomson Process (Throttling)	13
10	Heat Engines and Refrigerators	14
	10.1 Heat Engine	14
	10.2 Refrigerator	14
11	Canonical Ensemble (Constant T, V, N)	15
	11.1 Connection to Thermodynamics: Helmholtz Free Energy	15
	11.2 First and Second Laws in Canonical Ensemble	
	11.3 Example: Maxwell Velocity Distribution	16
12	Grand Canonical Ensemble (Constant T, V, μ)	17
	12.1 Connection to Thermodynamics: Grand Potential	17
13	Classical Ideal Gas Revisited	17
	13.1 Partition Function (Canonical Ensemble)	17
14	Equipartition Theorem	18
	14.1 Examples	19
15	Quantum Statistics Examples	19
	15.1 Harmonic Oscillator (Quantum)	19
	15.2 Einstein Solid	
	15.3 Paramagnetism (Spin J)	20
16	Elements of Kinetic Theory	21
	16.1 Maxwell Velocity and Speed Distributions	21
	16.2 Particle Flux and Effusion	
	16.3 Pressure of an Ideal Gas	

Part 1: Foundations and Thermodynamics

1 Foundations: Probability and Statistics

Statistical mechanics builds upon probability theory to describe systems with many degrees of freedom. We first review essential concepts using the random walk as a concrete example.

1.1 The Random Walk and Binomial Distribution

Consider a simple model: a one-dimensional random walk over N steps, each of length l. The probability of moving right is p, and left is q = 1 - p. Let n_R be the number of steps right and n_L be the number of steps left, such that $N = n_R + n_L$. The final position is $x = (n_R - n_L)l$. We can express the number of steps in terms of the net displacement m = x/l:

$$n_R = \frac{N+m}{2}, \qquad n_L = \frac{N-m}{2}$$

The number of distinct paths leading to m steps net displacement to the right is given by the binomial coefficient $\binom{N}{n_R}$. The probability of any specific path is $p^{n_R}q^{n_L}$. Therefore, the probability of ending at position x = ml after N steps follows the Binomial Distribution:

$$P_N(m) = \binom{N}{n_R} p^{n_R} q^{n_L} = \frac{N!}{n_R! n_L!} p^{n_R} (1 - p)^{n_L}$$
(1)

where $n_R = (N + m)/2$.

1.2 Moments of a Distribution

Key characteristics of a probability distribution $P(x_i)$ are its moments:

- Mean (average value): $\langle x \rangle = \sum_i P(x_i) x_i$
- Variance (spread squared): $var(x) = \sigma^2 = \langle (x \langle x \rangle)^2 \rangle = \langle x^2 \rangle (\langle x \rangle)^2$
- Standard Deviation (RMS fluctuation): $\Delta x_{\rm rms} = \sqrt{{\rm var}(x)}$

For the number of right steps n_R in the binomial distribution:

$$\langle n_R \rangle = Np \tag{2}$$

$$var(n_R) = Npq \tag{3}$$

$$\Delta n_{R,\text{rms}} = \sqrt{Npq} \tag{4}$$

The relative width measures the distribution's sharpness around the mean:

$$\frac{\Delta n_{R,\text{rms}}}{\langle n_R \rangle} = \frac{\sqrt{Npq}}{Np} = \sqrt{\frac{q}{p}} \frac{1}{\sqrt{N}}$$
 (5)

For large N, the relative width approaches zero ($\propto 1/\sqrt{N}$), indicating the distribution becomes highly peaked.

1.3 Gaussian Approximation (Large N Limit)

In the limit of many steps $(N \gg 1)$, calculations involving factorials become cumbersome. We use Stirling's approximation for large N:

$$\ln N! \approx N \ln N - N + \frac{1}{2} \ln(2\pi N)$$
 (or often just $N \ln N - N$)

Applying this to the Binomial distribution and expanding around the mean $\mu = Np$, we find it approaches a continuous Gaussian (Normal) distribution:

$$P_N(n_R) \approx \frac{1}{\sqrt{2\pi\sigma^2}} \exp\left[-\frac{(n_R - \mu)^2}{2\sigma^2}\right]$$
 (6)

where $\mu = Np$ is the mean and $\sigma^2 = Npq$ is the variance. This approximation is excellent when the mean number of steps is far from the boundaries, i.e., $Npq \gg 1$.

1.4 Multivariable Probability and Change of Variables

We often deal with multiple random variables or need to find the distribution of a function of a random variable.

- Marginal Probability: $P_u(u_i) = \sum_j P(u_i, v_j)$ (integrating out other variables).
- Uncorrelated Variables: $P(u_i, v_i) = P_u(u_i)P_v(v_i)$.
- Change of Variables: If y = f(x) and x has probability density p(x), the density for y is $\tilde{p}(y)$. It accounts for the mapping of probability density: $\tilde{p}(y)dy = \sum p(x_i)dx_i$.

$$\tilde{p}(y) = \sum_{i} p(x_i) \left| \frac{\mathrm{d}x}{\mathrm{d}y} \right|_{x=x_i} = \sum_{i} \frac{p(x_i)}{\left| \frac{\mathrm{d}y}{\mathrm{d}x} \right|_{x=x_i}}$$
(7)

where the sum is over all roots x_i such that $f(x_i) = y$.

Example: Component of a Random 2D Vector

Consider a 2D vector \vec{B} of fixed magnitude B with uniform random orientation $\theta \in [0, 2\pi)$. The probability density for the angle is $p(\theta) = 1/(2\pi)$. We seek the probability density $\tilde{p}(B_x)$ for the x-component, $B_x = B\cos\theta$. For a given B_x ($|B_x| < B$), there are two angles $\theta_1 = \arccos(B_x/B)$ and $\theta_2 = 2\pi - \theta_1$. The Jacobian is $\frac{dB_x}{d\theta} = -B\sin\theta$, so $\left|\frac{d\theta}{dB_x}\right| = 1/|-B\sin\theta| = 1/\sqrt{B^2 - B_x^2}$. Applying the change of variables formula:

$$\tilde{p}(B_x) = p(\theta_1) \left| \frac{\mathrm{d}\theta}{\mathrm{d}B_x} \right|_{\theta_1} + p(\theta_2) \left| \frac{\mathrm{d}\theta}{\mathrm{d}B_x} \right|_{\theta_2} \tag{8}$$

$$= \frac{1}{2\pi} \frac{1}{\sqrt{B^2 - B_x^2}} + \frac{1}{2\pi} \frac{1}{\sqrt{B^2 - B_x^2}}$$
 (9)

$$=\frac{1}{\pi\sqrt{B^2 - B_x^2}}\tag{10}$$

The resulting probability density is:

$$\tilde{p}(B_x) = \begin{cases} \frac{1}{\pi\sqrt{B^2 - B_x^2}} & \text{if } |B_x| < B\\ 0 & \text{otherwise} \end{cases}$$
(11)

2 The Statistical Basis of Thermodynamics

Here we connect the microscopic world of particles to macroscopic thermodynamics.

2.1 Microstates and Macrostates

A microstate specifies the exact state of every particle (e.g., all positions and momenta in classical mechanics, or the overall quantum state). A macrostate is defined by observable macroscopic parameters like total energy E, volume V, and particle number N. A single macrostate typically corresponds to a vast number of microstates.

2.2 The Fundamental Postulate

For an isolated macroscopic system in equilibrium, characterized by fixed (E, V, N) (within small tolerances), let $\Omega(E, V, N)$ denote the total number of distinct microstates accessible to the system. The cornerstone of statistical mechanics is the fundamental postulate: All accessible microstates of an isolated system in equilibrium are equally probable. The probability of finding the system in any specific accessible microstate μ_i is therefore:

$$P(\mu_i) = \frac{1}{\Omega(E, V, N)}$$

2.3 Statistical Definition of Macroscopic Parameters

If a macroscopic parameter y (e.g., pressure, magnetization) can take value y_k in certain microstates, the probability of observing y_k is proportional to the number of microstates $\Omega(E; y_k)$ consistent with both E and y_k :

$$P(y_k) = \frac{\Omega(E; y_k)}{\Omega(E)}, \quad \text{where } \Omega(E) = \sum_k \Omega(E; y_k)$$
 (12)

The average value (expectation value) of y is calculated using these probabilities:

$$\langle y \rangle = \sum_{k} y_k P(y_k) = \frac{\sum_{k} y_k \Omega(E; y_k)}{\Omega(E)}$$
 (13)

Example: Three Spin-1/2 Particles

Consider 3 non-interacting spins in a field H. Single spin energy is $\mp \mu H$ for $m_s = \pm 1/2$. Suppose the total energy is fixed at $E = -\mu H$. This requires two spins up (+1/2) and one spin down (-1/2). The accessible microstates are (+,+,-), (+,-,+), (-,+,+). Thus, $\Omega(E=-\mu H)=3$. Now consider the state of the first spin. The microstates where $m_1 = +1/2$ are (+,+,-) and (+,-,+). So, $\Omega(E;m_1=+1/2)=2$. The probability that the first spin is up is $P(m_1=+1/2)=\Omega(E;m_1=+1/2)/\Omega(E)=2/3$.

2.4 Density of States

For systems with continuous or quasi-continuous energy levels (like classical systems or quantum systems in the thermodynamic limit), it's useful to define the *density of states* $\omega(E)$, such that $\omega(E)\delta E$ is the number of microstates with energy between E and $E + \delta E$. We often write this number simply as $\Omega(E)$, understanding the implicit energy shell δE :

$$\Omega(E) \equiv \omega(E)\delta E$$

Example: Classical Monatomic Ideal Gas

For N classical point particles in volume V, the Hamiltonian is $H = \sum_{i=1}^N \frac{\vec{p}_i^2}{2m}$. The number of states $\Omega(E)$ corresponds to the volume of phase space within the energy shell $[E, E + \delta E]$. The position part gives V^N . The momentum part is the volume of a thin hyperspherical shell in 3N-dimensional momentum space. The volume of a D-dimensional hypersphere of radius R scales as R^D . Here D = 3N and $R = \sqrt{2mE}$. The phase space volume $\Sigma(E)$ with energy *up to* E scales as $V^N(\sqrt{E})^{3N} = V^N E^{3N/2}$. The density of states is $\omega(E) = d\Sigma/dE \propto V^N E^{3N/2-1}$. For large N, the term -1 is negligible. It is common practice (though slightly imprecise) to approximate the number of states in the shell $\Omega(E)$ as being proportional to the dominant term:

$$\Omega(E) \propto V^N E^{3N/2}$$
 (Large N approximation)

The proportionality constants and δE are often absorbed when defining entropy via logarithms.

3 Interaction Between Systems and Laws of Thermodynamics

Now we consider how macroscopic systems interact and exchange energy, leading to the fundamental laws of thermodynamics.

3.1 Types of Interaction: Heat and Work

Consider a system interacting with its surroundings. Energy transfer can occur via two macroscopic mechanisms:

- Heat (Q): Energy transfer due to a temperature difference, occurring when external parameters (like volume) are held fixed. By definition, $Q = \Delta \langle E \rangle$ under these conditions. Heat is energy transfer associated with microscopic degrees of freedom.
- Work (W): Energy transfer due to changes in macroscopic external parameters (e.g., volume change against external pressure, changing magnetic field). Work done by the system is defined as $W = -\langle \Delta_x E \rangle$, where $\Delta_x E$ is the energy change solely due to the change in parameter x. Work is energy transfer associated with macroscopic degrees of freedom.

For a general interaction involving both mechanisms, the total change in the system's average energy $\Delta \langle E \rangle$ is related to heat absorbed Q and work done W by:

$$Q = \Delta \langle E \rangle + W \implies \Delta \langle E \rangle = Q - W$$

3.2 The First Law of Thermodynamics

This is the principle of energy conservation applied to thermodynamic processes. For an infinitesimal change, the change in internal energy dE (we now drop the average notation $\langle E \rangle$) equals the infinitesimal heat absorbed δQ minus the infinitesimal work done by the system δW :

$$dE = \delta Q - \delta W \tag{14}$$

Here, E is a state function, meaning dE is an exact differential; its change depends only on the initial and final states. However, δQ and δW are inexact differentials; the heat and work depend on the specific path taken between states.

3.3 Quasistatic Processes and Generalized Forces

A quasistatic process occurs so slowly that the system remains infinitesimally close to equilibrium at all stages. This allows macroscopic parameters (like T, P) to be well-defined throughout the system. If the system's Hamiltonian H(q,p;x) depends on an external parameter x (like volume V), a change dx causes an energy change $dE = (\partial H/\partial x)dx$. Averaging over an equilibrium ensemble: $dE = \langle \partial H/\partial x \rangle dx$. This energy change corresponds to work done *on* the system. The work done *by* the system is $\delta W = -dE = -\langle \partial H/\partial x \rangle dx$. We define the generalized force χ conjugate to the parameter x as:

$$\chi \equiv -\left\langle \frac{\partial H}{\partial x} \right\rangle \tag{15}$$

Then the quasistatic work done by the system is:

$$\delta W = \chi dx \tag{16}$$

Example: Piston

If the external parameter is volume V, the conjugate generalized force is the pressure P. The definition implies $P = -\langle \partial H/\partial V \rangle$. (Thermodynamically, $P = -\frac{\partial E}{\partial V}$). The quasistatic work done by the system during a volume change dV is:

$$\delta W = PdV$$

For a finite volume change from V_i to V_f , the total work is $W = \int_{V_i}^{V_f} P(V) dV$.

3.4 Thermal Equilibrium, Entropy, and Temperature

Consider two systems (1 and 2) in thermal contact, forming an isolated composite system with total energy $E=E_1+E_2$. The number of microstates of the combined system, when system 1 has energy E_1 , is $\Omega_{total}(E_1)=\Omega_1(E_1)\Omega_2(E-E_1)$. In equilibrium, the system will be found in the macrostate that maximizes the total number of microstates Ω_{total} . Since $\ln x$ is monotonic, this is equivalent to maximizing $\ln \Omega_{total}=\ln \Omega_1(E_1)+\ln \Omega_2(E-E_1)$. The condition for maximum is $\frac{d}{dE_1}(\ln \Omega_1+\ln \Omega_2)=0$:

$$\frac{\partial \ln \Omega_1}{\partial E_1} + \frac{\partial \ln \Omega_2}{\partial E_2} \frac{\partial E_2}{\partial E_1} = 0 \implies \frac{\partial \ln \Omega_1}{\partial E_1}_{E_1 = \tilde{E}_1} = \frac{\partial \ln \Omega_2}{\partial E_2}_{E_2 = E - \tilde{E}_1}$$

where \tilde{E}_1 is the most probable energy distribution. This suggests defining a quantity whose equality signifies equilibrium. We define the dimensionless *statistical entropy* S as:

$$S(E, V, N) \equiv \ln \Omega(E, V, N) \tag{17}$$

Entropy is additive for combined systems $(S_{total} = S_1 + S_2)$. Equilibrium maximizes total entropy. We define the *statistical temperature* T (with units of energy since $k_B = 1$) as:

$$\frac{1}{T} \equiv \frac{\partial S}{\partial E_{V,N}} \tag{18}$$

With these definitions, the condition for thermal equilibrium becomes simply $T_1 = T_2$. For macroscopic systems (large N), the function $\Omega_{total}(E_1)$ is incredibly sharply peaked around the equilibrium energy \tilde{E}_1 . Fluctuations $\Delta E/\langle E \rangle$ are typically negligible, scaling as $1/\sqrt{N}$. Stability requires the entropy S to be a concave function of E, meaning $\frac{\partial^2 S}{\partial E^2}_V \leq 0$, which implies $\frac{\partial^2 S}{\partial E^2}_V \leq 0$.

3.5 The Second Law of Thermodynamics

When two isolated systems initially at different temperatures $T_1 \neq T_2$ are brought into thermal contact, energy dE_1 flows spontaneously until equilibrium is reached. The change in total entropy is:

$$dS_{total} = dS_1 + dS_2 = \frac{\partial S_1}{\partial E_1} dE_1 + \frac{\partial S_2}{\partial E_2} dE_2 = \frac{1}{T_1} dE_1 + \frac{1}{T_2} (-dE_1) = \left(\frac{1}{T_1} - \frac{1}{T_2}\right) dE_1$$

Energy flows from hot to cold: if $T_2 > T_1$, then $dE_1 > 0$, and $(1/T_1 - 1/T_2) > 0$, so $dS_{total} > 0$. If $T_1 > T_2$, then $dE_1 < 0$, and $(1/T_1 - 1/T_2) < 0$, so $dS_{total} > 0$. In general, for any spontaneous process in an isolated system, the entropy increases or stays the same. This leads to the Second Law: For any process occurring in an isolated system, the total entropy never decreases:

$$\Delta S_{total} \ge 0 \tag{19}$$

The equality holds for idealized *reversible* processes (sequences of equilibrium states), while the inequality holds for *irreversible* (spontaneous, real-world) processes.

3.6 The Fundamental Thermodynamic Relation

Consider a system undergoing an infinitesimal, quasistatic process involving changes in both entropy (due to heat) and volume (due to work). The total differential of energy E(S, V) is:

$$dE = \frac{\partial E}{\partial S_V} dS + \frac{\partial E}{\partial V_S} dV$$

From the definitions of temperature $T = (\partial E/\partial S)_V$ and pressure $P = -(\partial E/\partial V)_S$, we obtain the fundamental thermodynamic relation for a closed system (N fixed):

$$dE = TdS - PdV$$
 (20)

This central equation combines the First Law ($dE = \delta Q - \delta W$) and the Second Law (through T and S) for reversible processes. Comparing dE = TdS - PdV with $dE = \delta Q_{rev} - PdV$ (for quasistatic PV work), we identify the reversible heat transfer:

$$\delta Q_{rev} = T dS \implies dS = \frac{\delta Q_{rev}}{T}$$
 (21)

This provides a way to calculate entropy changes macroscopically from reversible heat measurements. For an adiabatic reversible process $(\delta Q_{rev}=0)$, dS=0, so such processes are *isentropic*. We can also write S=S(E,V), giving $dS=\frac{\partial S}{\partial E}_V dE+\frac{\partial S}{\partial V}_E dV=\frac{1}{T} dE+\frac{P}{T} dV$. This yields another useful relation:

$$\frac{P}{T} = \frac{\partial S}{\partial V_E}$$

Equilibrium between two systems (1, 2) that can exchange energy and volume $(E = E_1 + E_2, V = V_1 + V_2)$ requires maximization of $S = S_1(E_1, V_1) + S_2(E - E_1, V - V_1)$. This leads to $\partial S/\partial E_1 = 0 \implies T_1 = T_2$, and $\partial S/\partial V_1 = 0 \implies P_1/T_1 = P_2/T_2$. Together, these imply mechanical equilibrium $P_1 = P_2$.

3.7 Summary of Thermodynamic Laws

The four fundamental laws governing macroscopic systems:

- 0. **Zeroth Law:** If systems A and B are separately in thermal equilibrium with C, then A and B are in thermal equilibrium with each other. (Establishes temperature as a valid concept).
- 1. First Law: $dE = \delta Q \delta W$. (Energy is conserved).
- 2. **Second Law:** $\Delta S_{total} \geq 0$ for an isolated system. For a system interacting with a reservoir at T, $dS \geq \delta Q/T$. (Defines direction of spontaneous change, limits efficiency).
- 3. **Third Law:** As temperature approaches absolute zero $(T \to 0)$, the entropy approaches a constant value S_0 , independent of other parameters. Often $S_0 = 0$ for systems with a unique ground state. $(\lim_{T\to 0} S(T,X) = S_0)$. (Implies absolute zero is unattainable).

4 Thermodynamic Response Functions

These measurable quantities characterize how a system's state variables change in response to external stimuli. (Recall $k_B = 1$, T is energy, S is dimensionless, $R = N_A$).

4.1 Heat Capacities

Heat capacity relates the heat absorbed to the temperature change under specific conditions: $\delta Q = C_x dT$ (quasistatic, constant x).

• Heat Capacity at Constant Volume (C_V) : At constant V, $dE = \delta Q_V$. Using $\delta Q_{rev} = TdS$:

$$C_V = \left(\frac{\delta Q}{dT}\right)_V = T\frac{\partial S}{\partial T_V} = \frac{\partial E}{\partial T_V}$$
 (22)

• Heat Capacity at Constant Pressure (C_P) : Use enthalpy H = E + PV, so dH = TdS + VdP. At constant P, $dH = TdS = \delta Q_P$.

$$C_P = \left(\frac{\delta Q}{dT}\right)_P = T\frac{\partial S}{\partial T_P} = \frac{\partial H}{\partial T_P}$$
(23)

Heat capacities allow calculation of entropy changes with temperature at constant x:

$$S(T_2, x) - S(T_1, x) = \int_{T_1}^{T_2} \frac{\delta Q_x}{T} = \int_{T_1}^{T_2} \frac{C_x(T)}{T} dT$$
 (24)

4.2 Compressibility and Expansivity

These describe mechanical responses:

• Isothermal Compressibility (κ_T): Relative volume change with pressure at constant T.

$$\kappa_T = -\frac{1}{V} \frac{\partial V}{\partial P_T} \quad (\kappa_T > 0 \text{ for stability})$$
(25)

• Isobaric Expansion Coefficient (α_P) : Relative volume change with temperature at constant P.

$$\alpha_P = \frac{1}{V} \frac{\partial V}{\partial T_P} \tag{26}$$

5 Application: The Ideal Gas

The ideal gas provides a simple, exactly solvable model illustrating many thermodynamic concepts. It describes non-interacting point particles.

5.1 Statistical Derivation (Monatomic)

We use the approximate entropy derived from $\Omega(E) \propto V^N E^{3N/2}$:

$$S(E, V, N) = \ln \Omega \approx N \ln V + \frac{3N}{2} \ln E + \text{const.}$$

Applying the statistical definitions of T and P:

- 1. Temperature: $\frac{1}{T} = \frac{\partial S}{\partial E}_{V,N} = \frac{3N}{2E} \implies E = \frac{3}{2}NT$. The internal energy of a classical ideal monatomic gas depends only on temperature.
- 2. Pressure: $\frac{P}{T} = \frac{\partial S}{\partial V}_{EN} = \frac{N}{V} \implies PV = NT$. This is the ideal gas equation of state.

5.2 Ideal Gas Law and Molar Quantities

Writing particle number N in terms of moles ν and Avogadro's number N_A : $N = \nu N_A$. The gas constant is $R = N_A k_B = N_A$ (since $k_B = 1$).

$$PV = \nu N_A T \tag{27}$$

$$E = \frac{3}{2}\nu N_A T \tag{28}$$

5.3 Specific Heats (Monatomic)

Molar specific heat $c_x = C_x/\nu$.

• Constant Volume:

$$c_v = \frac{C_V}{\nu} = \frac{1}{\nu} \frac{\partial E}{\partial T_V} = \frac{1}{\nu} \frac{\mathrm{d}}{\mathrm{d}T} \left(\frac{3}{2} \nu N_A T \right) = \frac{3}{2} N_A \tag{29}$$

• Constant Pressure: Use $H = E + PV = E + \nu N_A T$. Since E = E(T), H = H(T).

$$c_p = \frac{C_P}{\nu} = \frac{1}{\nu} \frac{\partial H}{\partial T_P} = \frac{1}{\nu} \frac{\mathrm{d}}{\mathrm{d}T} \left(\frac{3}{2} \nu N_A T + \nu N_A T \right) = \frac{5}{2} N_A \tag{30}$$

The general relation $c_p - c_v = N_A (=R)$ holds for any ideal gas because E = E(T) and $PV = \nu N_A T$. Also, $dE = C_V dT = \nu c_v dT$ generally for ideal gases.

5.4 Adiabatic Index

The ratio of specific heats $\gamma = c_p/c_v$ is important for adiabatic processes. For a monatomic ideal gas:

$$\gamma = \frac{c_p}{c_v} = \frac{5/2N_A}{3/2N_A} = \frac{5}{3} \tag{31}$$

5.5 Ideal Gas Processes

- **Isothermal** (T=const): From PV = NT, we have PV = const..
- Adiabatic (Q=0, S=const): For a quasistatic adiabatic process, $dE = \delta Q \delta W = -PdV$. Also $dE = C_V dT = \nu c_v dT$.

$$\nu c_v dT + P dV = 0$$

Substitute $P = \nu N_A T/V$ and use $N_A = c_p - c_v$:

$$\nu c_v dT + \frac{\nu(c_p - c_v)T}{V} dV = 0$$
$$\frac{dT}{T} + \frac{c_p - c_v}{c_v} \frac{dV}{V} = 0$$
$$\frac{dT}{T} + (\gamma - 1) \frac{dV}{V} = 0$$

Integrating this (assuming constant γ): $\ln T + (\gamma - 1) \ln V = \text{const.}$, which leads to:

$$TV^{\gamma-1} = \text{const.}$$
 (32)

Using $T \propto PV$, we can rewrite this in terms of P and V:

$$PV^{\gamma} = \text{const.}$$
 (33)

Part 2: Thermodynamic Potentials, Ensembles, and Applications

We introduce alternative thermodynamic potentials useful for different constraints, explore statistical ensembles beyond the microcanonical (isolated system), and apply the framework to specific physical systems.

6 Thermodynamic Potentials

The internal energy E is naturally expressed as E(S,V,N). By performing Legendre transformations, we can change the natural variables to those more easily controlled experimentally (like T, P), leading to other thermodynamic potentials. Each potential has the property that it is minimized at equilibrium under its respective natural constraints. We include the chemical potential term μdN for systems with variable particle number, where $\mu = \frac{\partial E}{\partial N} S_{,V}$.

Internal Energy E(S, V, N)

$$dE = TdS - PdV + \mu dN$$

Enthalpy H = E + PV. Natural variables H(S, P, N).

$$dH = TdS + VdP + \mu dN$$
 (Useful for constant P processes)

Helmholtz Free Energy F = E - TS. Natural variables F(T, V, N).

$$dF = -SdT - PdV + \mu dN$$
 (Useful for constant T, V; links to canonical ensemble)

Gibbs Free Energy G = H - TS = E - TS + PV. Natural variables G(T, P, N).

 $dG = -SdT + VdP + \mu dN$ (Useful for constant T, P; phase transitions, chemical reactions)

Grand Potential $\Phi = F - \mu N = E - TS - \mu N$. Natural variables $\Phi(T, V, \mu)$.

 $d\Phi = -SdT - PdV - Nd\mu$ (Useful for constant T, V, μ ; links to grand canonical ensemble)

From these differentials, we can read off various partial derivatives, e.g., $T = \frac{\partial E}{\partial S}_V = \frac{\partial H}{\partial S}_P$, $P = -\frac{\partial E}{\partial V}_S = -\frac{\partial F}{\partial V}_T$, $S = -\frac{\partial F}{\partial T}_V = -\frac{\partial G}{\partial T}_P$, $\mu = \frac{\partial E}{\partial N}_{S,V} = \frac{\partial F}{\partial N}_{T,V} = \frac{\partial G}{\partial N}_{T,P}$, etc.

Maxwell Relations 7

Since the thermodynamic potentials are state functions, their differentials are exact. This implies that mixed second partial derivatives are equal (Schwarz's theorem). Applying this to the differentials of E, H, F, G yields the Maxwell relations, which connect seemingly unrelated derivatives. Example: From dF = -SdT - PdV, we have $\frac{\partial^2 F}{\partial V \partial T} = \frac{\partial^2 F}{\partial T \partial V}$. This implies $-\frac{\partial S}{\partial V}_T = -\frac{\partial P}{\partial T}_V$. The four main Maxwell relations are:

$$\frac{\partial T}{\partial V_S} = -\frac{\partial P}{\partial S_V} \tag{from } dE)$$

$$\frac{\partial T}{\partial P_S} = \frac{\partial V}{\partial S_P} \qquad \text{(from } dH)$$

$$\frac{\partial S}{\partial V_T} = \frac{\partial P}{\partial T_V} \qquad \text{(from } dF)$$
(36)

$$\frac{\partial S}{\partial V_T} = \frac{\partial P}{\partial T_V} \tag{from } dF) \tag{36}$$

$$\frac{\partial S}{\partial P_T} = -\frac{\partial V}{\partial T_P} \tag{from } dG) \tag{37}$$

These are powerful tools for relating measurable quantities (like derivatives involving P, V, T) to less directly accessible quantities (like derivatives involving S).

7.1Relation between Heat Capacities

We can derive the general relation between C_P and C_V using Maxwell relations. Consider entropy as a function of T and V, S(T,V). Its differential is $dS = \frac{\partial S}{\partial T_V} dT + \frac{\partial S}{\partial V_T} dV$. Multiply by T: $TdS = T \frac{\partial S}{\partial T_V} dT + T \frac{\partial S}{\partial V_T} dV = C_V dT + T \frac{\partial P}{\partial T_V} dV$, using $C_V = T \frac{\partial S}{\partial T_V}$ and Maxwell relation (36). Now consider S(T,P). $dS = \frac{\partial S}{\partial T_P} dT + \frac{\partial S}{\partial P_T} dP$. Multiply by T: $TdS = C_P dT + T \frac{\partial S}{\partial P_T} dP = C_P dT - T \frac{\partial V}{\partial T_P} dP$, using $C_P = T \frac{\partial S}{\partial T_P} dT$ and Maxwell relation (37). To relate these, express dV in the first equation in terms of dT and dP: $dV = \frac{\partial V}{\partial T_P} dT + \frac{\partial V}{\partial P_T} dP$. Substitute: $TdS = C_V dT + T \frac{\partial P}{\partial T_V} (\frac{\partial V}{\partial T_P} dT + \frac{\partial V}{\partial P_T} dP)$. $TdS = \left[C_V + T \frac{\partial P}{\partial T_V} \frac{\partial V}{\partial T_P}\right] dT + \left[T \frac{\partial P}{\partial T_V} \frac{\partial V}{\partial P_T}\right] dP$. Comparing the coefficients of dT in this expression and the one derived from S(T,P):

$$C_P = C_V + T \frac{\partial P}{\partial T}_V \frac{\partial V}{\partial T}_P$$

Using the cyclic relation $\frac{\partial P}{\partial T}_V \frac{\partial T}{\partial V}_P \frac{\partial V}{\partial P}_T = -1$, we can write $\frac{\partial P}{\partial T}_V = -\frac{\frac{\partial V}{\partial T}_P}{\frac{\partial V}{\partial P}_T}$. Substituting this gives: $C_P - C_V = \frac{\frac{\partial V}{\partial T}_P}{\frac{\partial V}{\partial P}_T}$. $-T\left(\frac{\partial V}{\partial T_P}\right)^2/\frac{\partial V}{\partial P_T}$. Introducing the response functions $\alpha_P = \frac{1}{V}\frac{\partial V}{\partial T_P}$ and $\kappa_T = -\frac{1}{V}\frac{\partial V}{\partial P_T}$.

$$C_P - C_V = \frac{VT\alpha_P^2}{\kappa_T} \tag{38}$$

Since V, T, κ_T are positive for stable systems, and $\alpha_P^2 \geq 0$, this shows $C_P \geq C_V$.

7.2 Implications of the Third Law $(S \to S_0 \text{ as } T \to 0)$

The third law requires that entropy becomes constant as $T \to 0$. This has consequences for response functions:

- $C_V = T \frac{\partial S}{\partial T_V} \to 0 \text{ as } T \to 0.$
- $C_P = T \frac{\partial S}{\partial T_P} \to 0 \text{ as } T \to 0.$
- From Maxwell relation (37), $\frac{\partial S}{\partial P}_T = -\frac{\partial V}{\partial T}_P = -V\alpha_P$. Since $\frac{\partial S}{\partial P}_T$ must remain finite as $T \to 0$, the thermal expansion coefficient must vanish: $\alpha_P \to 0$.
- Similarly, from (36), $\frac{\partial S}{\partial V}_T = \frac{\partial P}{\partial T}_V$. Since $\frac{\partial S}{\partial V}_T$ must remain finite, $\frac{\partial P}{\partial T}_V \to 0$.
- The ratio $\frac{C_P C_V}{C_V} = \frac{V T \alpha_P^2}{\kappa_T C_V}$. The limit depends on how fast α_P and C_V go to zero, but typically $C_P/C_V \to 1$ as $T \to 0$.

8 Calculating Entropy and Energy from Measurables

We can determine S(T, V) and E(T, V) if we know the equation of state P(T, V) and the heat capacity $C_V(T, V_0)$ at some reference volume V_0 .

8.1 Entropy S(T, V)

Starting with S(T,V), the differential is $dS = \frac{\partial S}{\partial T}_V dT + \frac{\partial S}{\partial V}_T dV$. Using $C_V = T \frac{\partial S}{\partial T}_V$ and Maxwell relation $\frac{\partial S}{\partial V}_T = \frac{\partial P}{\partial T}_V$:

$$dS = \frac{C_V(T, V)}{T}dT + \frac{\partial P}{\partial T_V}dV \tag{39}$$

To find S(T, V) relative to a reference state (T_0, V_0) , we integrate dS along a convenient path. For example, path $(T_0, V_0) \to (T_0, V) \to (T, V)$:

$$S(T,V) - S(T_0, V_0) = \int_{V_0}^{V} \frac{\partial P(T_0, V')}{\partial T} dV' + \int_{T_0}^{T} \frac{C_V(T', V)}{T'} dT'$$
(40)

Note that C_V itself might depend on volume. The exactness of dS requires $\frac{\partial^2 S}{\partial V \partial T} = \frac{\partial^2 S}{\partial T \partial V}$, which implies:

$$\frac{\partial}{\partial V_T} \left(\frac{C_V}{T} \right) = \frac{\partial}{\partial T_V} \left(\frac{\partial P}{\partial T_V} \right) \implies \frac{\partial C_V}{\partial V_T} = T \frac{\partial^2 P}{\partial T^2 \partial V}$$

This relation allows us to find $C_V(T,V)$ at any volume if it's known at one volume V_0 :

$$C_V(T, V) = C_V(T, V_0) + \int_{V_0}^{V} T \frac{\partial^2 P(T, V')}{\partial T^2 \partial V} dV'$$

8.2 Internal Energy E(T, V)

From the fundamental relation dE = TdS - PdV, substitute the expression (39) for dS:

$$dE = T\left(\frac{C_V(T, V)}{T}dT + \frac{\partial P}{\partial T_V}dV\right) - PdV$$
$$= C_V(T, V)dT + \left[T\frac{\partial P}{\partial T_V} - P\right]dV$$

This differential shows $\frac{\partial E}{\partial T}_V = C_V$ and the important relation for the volume dependence of energy:

$$\frac{\partial E}{\partial V_T} = T \frac{\partial P}{\partial T_V} - P \tag{41}$$

Integrating dE from (T_0, V_0) to (T, V) along the same path $(T_0, V_0) \to (T_0, V) \to (T, V)$:

$$E(T,V) - E(T_0, V_0) = \int_{V_0}^{V} \left[T_0 \frac{\partial P(T_0, V')}{\partial T}_V - P(T_0, V') \right] dV' + \int_{T_0}^{T} C_V(T', V) dT'$$
 (42)

9 Thermodynamic Processes

We analyze specific irreversible processes.

9.1 Free Expansion (Joule Expansion)

An isolated system (Q = 0) expands into a vacuum (W = 0), e.g., gas initially in volume V_1 expands to fill $V_2 > V_1$. From the First Law, $\Delta E = Q - W = 0$. The internal energy remains constant. The temperature change during this constant-E process is described by the Joule coefficient:

$$\mu_J \equiv \frac{\partial T}{\partial V}_E$$

Using the cyclic relation and $\frac{\partial E}{\partial T}_V = C_V$, $\frac{\partial E}{\partial V}_T$: $\frac{\partial T}{\partial V}_E = -\frac{\frac{\partial E}{\partial V}_T}{\frac{\partial E}{\partial T}_V} = -\frac{1}{C_V}\frac{\partial E}{\partial V}_T$. Using Eq. (41):

$$\mu_J = -\frac{1}{C_V} \left[T \frac{\partial P}{\partial T_V} - P \right] = \frac{1}{C_V} \left[P - T \frac{\partial P}{\partial T_V} \right]$$
(43)

The final temperature is $T_2 = T_1 + \int_{V_1}^{V_2} \mu_J(E, V) dV$ (integral at constant E). Entropy change: At constant E, $dE = 0 = TdS - PdV \implies dS = (P/T)dV$. Since P, T > 0, $\frac{\partial S}{\partial V}_E = P/T > 0$. Free expansion is always irreversible and increases entropy.

$$S_2 - S_1 = \int_{V_1}^{V_2} \frac{P(E, V)}{T(E, V)} dV \quad \text{(integral at constant E)}$$
 (44)

Ideal Gas in Free Expansion

For an ideal gas, E = E(T), so $\frac{\partial E}{\partial V_T} = 0$. Therefore $\mu_J = 0$. Since $\Delta E = 0$, it follows that $\Delta T = 0$. The temperature does not change. The entropy change is $\Delta S = \int_{V_1}^{V_2} \frac{P}{T} dV = \int_{V_1}^{V_2} \frac{N}{V} dV = N \ln(V_2/V_1)$.

Van der Waals Gas in Free Expansion

Equation of State: $(P+a/v^2)(v-b)=N_AT$, where $v=V/\nu$ is molar volume. We found earlier $\frac{\partial E}{\partial V_T}=a/v^2=aN^2/V^2$ (where $N=\nu N_A$). $\mu_J=-\frac{1}{C_V}\frac{\partial E}{\partial V_T}=-\frac{aN^2}{C_VV^2}$. Assuming C_V is roughly constant: $\Delta T=T_2-T_1=\int_{V_1}^{V_2}\mu_JdV\approx -\frac{aN^2}{C_V}\int_{V_1}^{V_2}\frac{dV}{V^2}=-\frac{aN^2}{C_V}\left(\frac{1}{V_1}-\frac{1}{V_2}\right)$. Since $V_2>V_1$, the term in parentheses is positive. Thus $\Delta T<0$. A Van der Waals gas cools upon free expansion due to attractive intermolecular forces (a>0).

9.2 Joule-Thomson Process (Throttling)

Gas flows steadily through a porous plug or valve, separating regions of constant pressure P_1 and P_2 ($P_1 > P_2$). The apparatus is insulated (Q = 0). Consider a fixed amount of gas. Work done on it as it enters: $W_{in} = P_1V_1$. Work done by it as it leaves: $W_{out} = P_2V_2$. Net work done by gas: $W = W_{out} - W_{in} = P_2V_2 - P_1V_1$. First Law: $\Delta E = E_2 - E_1 = Q - W = 0 - (P_2V_2 - P_1V_1)$. $E_2 - E_1 = P_1V_1 - P_2V_2 \implies E_1 + P_1V_1 = E_2 + P_2V_2$. The process occurs at constant enthalpy: $H_1 = H_2$. Temperature change is described by the Joule-Thomson coefficient:

$$\mu_{JT} \equiv \frac{\partial T}{\partial P}_H$$

Using cyclic relation and $C_P = \frac{\partial H}{\partial T_P}$, $\frac{\partial H}{\partial P_T}$: $\frac{\partial T}{\partial P_H} = -\frac{\frac{\partial H}{\partial P_T}}{\frac{\partial H}{\partial T_P}} = -\frac{1}{C_P} \frac{\partial H}{\partial P_T}$. From dH = TdS + VdP, we have $\frac{\partial H}{\partial P_T} = T\frac{\partial S}{\partial P_T} + V$. Using Maxwell (37): $\frac{\partial H}{\partial P_T} = -T\frac{\partial V}{\partial T_P} + V$.

$$\mu_{JT} = -\frac{1}{C_P} \left[V - T \frac{\partial V}{\partial T_P} \right] = \frac{V}{C_P} \left[T \left(\frac{1}{V} \frac{\partial V}{\partial T_P} \right) - 1 \right] = \frac{V}{C_P} (T \alpha_P - 1)$$
(45)

The final temperature is $T_2 = T_1 + \int_{P_1}^{P_2} \mu_{JT}(H,P) dP$ (integral at constant H). Gas cools ($\Delta T < 0$ for $P_2 < P_1$) if $\mu_{JT} > 0$, which occurs when $T\alpha_P > 1$. Gas heats if $\mu_{JT} < 0$. The temperature where $\mu_{JT} = 0$ is the inversion temperature. Entropy change: At constant H, $dH = 0 = TdS + VdP \implies dS = -(V/T)dP$. Since V, T > 0, $\frac{\partial S}{\partial P}_H = -V/T < 0$. Expansion ($P_2 < P_1$, dP < 0) always increases entropy, making the process irreversible. $\Delta S = -\int_{P_1}^{P_2} \frac{V(H,P)}{T(H,P)} dP$.

Ideal Gas in Joule-Thomson Process

For an ideal gas, H = E + PV = E(T) + NT = H(T). Since $\Delta H = 0$, it follows that $\Delta T = 0$. Thus $\mu_{JT} = 0$. Ideal gases show no temperature change upon throttling.

10 Heat Engines and Refrigerators

Thermodynamic cycles are used to convert heat into work (engines) or move heat from cold to hot using work (refrigerators). Their performance is limited by the Second Law. Consider a cycle interacting with a hot reservoir (T_1) and a cold reservoir $(T_2 < T_1)$.

10.1 Heat Engine

A heat engine operates in a cycle, absorbing heat $Q_1 > 0$ from T_1 , rejecting heat $Q_2 > 0$ to T_2 , and producing net work $W = Q_1 - Q_2$. For one cycle, the engine's state returns to the start, so $\Delta S_{engine} = 0$. The reservoirs' entropy changes are $\Delta S_{res} = -Q_1/T_1 + Q_2/T_2$. Second Law requires $\Delta S_{total} = \Delta S_{engine} + \Delta S_{res} \geq 0$:

$$-\frac{Q_1}{T_1} + \frac{Q_2}{T_2} \ge 0 \implies \frac{Q_2}{Q_1} \ge \frac{T_2}{T_1}$$

The efficiency η is the ratio of work output to heat input:

$$\eta = \frac{W}{Q_1} = \frac{Q_1 - Q_2}{Q_1} = 1 - \frac{Q_2}{Q_1}$$

Using the Second Law result:

$$\eta \le 1 - \frac{T_2}{T_1} \tag{46}$$

The maximum possible efficiency, $\eta_{max} = 1 - T_2/T_1$, is the *Carnot efficiency*, achieved only by a reversible engine operating between T_1 and T_2 . The Kelvin statement of the Second Law ("No process is possible whose sole result is the absorption of heat from a reservoir and the conversion of this heat entirely into work") is equivalent to $\eta < 1$ if $T_2 > 0$.

10.2 Refrigerator

A refrigerator operates in a cycle using external work W>0 to extract heat $Q_2>0$ from the cold reservoir T_2 and reject heat $Q_1=Q_2+W$ to the hot reservoir T_1 . Again, $\Delta S_{engine}=0$, and $\Delta S_{total}=-Q_2/T_2+Q_1/T_1\geq 0$.

$$\frac{Q_1}{T_1} \ge \frac{Q_2}{T_2} \implies \frac{Q_2 + W}{T_1} \ge \frac{Q_2}{T_2}$$

Rearranging to find the minimum work required:

$$W \ge Q_2 \left(\frac{T_1}{T_2} - 1\right) = Q_2 \frac{T_1 - T_2}{T_2}$$

The performance is measured by the Coefficient of Performance (COP): $COP_{ref} = Q_2/W$.

$$COP_{ref} \le \frac{T_2}{T_1 - T_2} \tag{47}$$

The maximum COP is achieved by a reversible refrigerator (e.g., a reversed Carnot cycle). The Clausius statement of the Second Law ("No process is possible whose sole result is the transfer of heat from a colder to a hotter body") is equivalent to requiring W > 0 if $T_1 > T_2$.

11 Canonical Ensemble (Constant T, V, N)

This ensemble describes a system in thermal equilibrium with a large heat reservoir (or 'heat bath') at constant temperature T. The system's volume V and particle number N are fixed. Energy can fluctuate as it's exchanged with the reservoir.

The probability P_r of finding the system in a specific microstate r with energy E_r is given by the Boltzmann distribution:

$$P_r = \frac{e^{-E_r/T}}{Z} \tag{48}$$

where the normalization constant Z is the Canonical Partition Function:

$$Z(T, V, N) = \sum_{r} e^{-E_r/T}$$
(49)

The sum is over all distinct microstates r accessible to the system (at fixed V, N). The energies $E_r = E_r(V, N)$ depend on volume and particle number. The average value of any observable O (which has value O_r in state r) is:

$$\langle O \rangle = \sum_{r} O_r P_r = \frac{1}{Z} \sum_{r} O_r e^{-E_r/T} = \frac{\sum_{r} O_r e^{-E_r/T}}{\sum_{r} e^{-E_r/T}}$$
 (50)

For classical systems, the sum over states \sum_r is replaced by an integral over phase space, including the Gibbs factor 1/N! for identical particles and division by h^{3N} (where h is Planck's constant) to make Z dimensionless:

 $Z_{cl} = \frac{1}{N!h^{3N}} \int e^{-H(q,p)/T} d^{3N} q d^{3N} p$

11.1 Connection to Thermodynamics: Helmholtz Free Energy

The partition function provides the crucial link between statistical mechanics and thermodynamics via the Helmholtz Free Energy F:

$$F(T, V, N) = -T \ln Z(T, V, N)$$
(51)

This relation can be justified by comparing the statistical average energy $\langle E \rangle$ with the thermodynamic relation $E = F + TS = F - T \frac{\partial F}{\partial T}_V$. Calculating $\langle E \rangle$ from Z:

$$\langle E \rangle = \sum_{r} E_r P_r = \frac{1}{Z} \sum_{r} E_r e^{-E_r/T} = \frac{1}{Z} \left(-\frac{\partial Z}{\partial \beta} \right)_V = -\frac{\partial (\ln Z)}{\partial \beta}_V$$

where $\beta = 1/T$. Using the chain rule $\frac{\partial}{\partial \beta} = \frac{\partial T}{\partial \beta} \frac{\partial}{\partial T} = -T^2 \frac{\partial}{\partial T}$:

$$\langle E \rangle = T^2 \frac{\partial (\ln Z)}{\partial T}_V \tag{52}$$

Substituting $F = -T \ln Z \implies \ln Z = -F/T$:

$$\langle E \rangle = T^2 \frac{\partial}{\partial T} \left(-\frac{F}{T} \right)_V = T^2 \left(-\frac{1}{T} \frac{\partial F}{\partial T_V} + \frac{F}{T^2} \right) = F - T \frac{\partial F}{\partial T_V}$$

This matches the thermodynamic identity E = F + TS if we identify $S = -\frac{\partial F}{\partial T}V$. Thus, once Z is calculated, all thermodynamic properties follow from $F = -T \ln Z$:

$$S = -\frac{\partial F}{\partial T}_{V,N} = \frac{\partial}{\partial T}_{V,N} \tag{53}$$

$$P = -\frac{\partial F}{\partial V}_{T,N} = T \frac{\partial (\ln Z)}{\partial V}_{T,N} \tag{54}$$

$$\mu = \frac{\partial F}{\partial N_{T,V}} = -T \frac{\partial (\ln Z)}{\partial N_{T,V}} \tag{55}$$

$$E = F + TS = T^{2} \frac{\partial (\ln Z)}{\partial T}_{V,N} = -\frac{\partial \ln Z}{\partial \beta}_{V,N}$$
(56)

Energy fluctuations provide another important connection. The variance of energy is:

$$\langle (\Delta E)^2 \rangle = \langle E^2 \rangle - \langle E \rangle^2$$

We have $\langle E^2 \rangle = \frac{1}{Z} \sum_r E_r^2 e^{-E_r/T} = \frac{1}{Z} \frac{\partial^2 Z}{\partial \beta \partial 2}$. Using $\frac{\partial^2 Z}{\partial \beta \partial 2} = Z \frac{\partial^2 (\ln Z)}{\partial \beta \partial 2} + Z (\frac{\partial \ln Z}{\partial \beta})^2$, we get:

$$\langle E^2 \rangle = \frac{\partial^2 (\ln Z)}{\partial \beta \partial 2} + (\langle E \rangle)^2$$

Therefore, $\langle (\Delta E)^2 \rangle = \frac{\partial^2 (\ln Z)}{\partial \beta \partial 2} = -\frac{\partial \langle E \rangle}{\partial \beta}$. Using the chain rule again:

$$\langle (\Delta E)^2 \rangle = -\frac{\partial \langle E \rangle}{\partial T} \frac{\partial T}{\partial \beta} = -C_V(-T^2) = T^2 C_V$$
 (57)

The energy fluctuations are directly related to the heat capacity. The relative fluctuation $\frac{\sqrt{\langle (\Delta E)^2 \rangle}}{\langle E \rangle} = \frac{\sqrt{T^2 C_V}}{E} \propto \frac{\sqrt{N}}{N} \sim 1/\sqrt{N}$, becoming negligible for macroscopic systems.

11.2 First and Second Laws in Canonical Ensemble

- Second Law perspective: At constant T, V, N, the system seeks equilibrium by minimizing the Helmholtz free energy F.
- First Law interpretation: For a quasistatic change, $d\langle E \rangle = \sum_r E_r dP_r + \sum_r P_r dE_r$. The first term represents change in energy due to redistribution among levels (heat), $\sum E_r dP_r = T dS = \delta Q_{rev}$. The second term represents energy change due to shifting energy levels (work), $\sum P_r dE_r = -\delta W_{rev}$. For volume change, $dE_r = \frac{\partial E_r}{\partial V} dV$, leading to $\delta W_{rev} = -(\sum P_r \frac{\partial E_r}{\partial V}) dV = P dV$.

11.3 Example: Maxwell Velocity Distribution

Consider a single classical particle of mass m in a large gas (reservoir) at temperature T. Its energy is $E = \frac{1}{2}m\vec{v}^2$. The probability density for its velocity \vec{v} is proportional to the Boltzmann factor: $f(\vec{v}) \propto e^{-E/T} = e^{-mv^2/(2T)}$. Normalization requires $\int f(\vec{v})d^3v = 1$. Let $f(\vec{v}) = Ce^{-mv^2/(2T)}$.

$$\begin{split} \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} \int_{-\infty}^{\infty} C \mathrm{e}^{-m(v_x^2 + v_y^2 + v_z^2)/(2T)} dv_x dv_y dv_z &= 1 \\ C \left(\int_{-\infty}^{\infty} \mathrm{e}^{-mv_x^2/(2T)} dv_x \right)^3 &= 1 \\ C (\sqrt{2\pi T/m})^3 &= 1 \implies C = (m/(2\pi T))^{3/2} \end{split}$$

The Maxwell-Boltzmann velocity distribution is:

$$f(\vec{v})d^3v = \left(\frac{m}{2\pi T}\right)^{3/2} e^{-mv^2/(2T)} d^3v$$
 (58)

12 Grand Canonical Ensemble (Constant T, V, μ)

This ensemble describes systems that can exchange both energy and particles with a large reservoir characterized by temperature T and chemical potential μ . The system volume V is fixed. Both energy E and particle number N can fluctuate.

The probability P_r of finding the system in state r (which now specifies both the energy E_r and particle number N_r) is given by:

$$P_r = \frac{e^{-(E_r - \mu N_r)/T}}{\mathcal{Z}} \tag{59}$$

where \mathcal{Z} is the *Grand Partition Function*:

$$\mathcal{Z}(T, V, \mu) = \sum_{r} e^{-(E_r - \mu N_r)/T}$$

$$\tag{60}$$

The sum is over all possible states, including states with different numbers of particles. We can group the sum by particle number N first, and then sum over states r(N) for fixed N:

$$\mathcal{Z}(T, V, \mu) = \sum_{N=0}^{\infty} \sum_{r(N)} e^{-(E_{r(N)} - \mu N)/T} = \sum_{N=0}^{\infty} e^{\mu N/T} \left(\sum_{r(N)} e^{-E_{r(N)}/T} \right)$$
(61)

Recognizing the inner sum as the canonical partition function Z(T, V, N), we have:

$$\mathcal{Z}(T, V, \mu) = \sum_{N=0}^{\infty} e^{\mu N/T} Z(T, V, N) = \sum_{N=0}^{\infty} z^N Z(T, V, N)$$
 (62)

where $z = e^{\mu/T}$ is the fugacity.

12.1 Connection to Thermodynamics: Grand Potential

The grand partition function is related to the Grand Potential $\Phi = E - TS - \mu N$:

$$\Phi(T, V, \mu) = -T \ln \mathcal{Z}(T, V, \mu)$$
(63)

Thermodynamic quantities follow from the differential $d\Phi = -SdT - PdV - Nd\mu$:

$$S = -\frac{\partial \Phi}{\partial T_{V,\mu}} = \frac{\partial}{\partial T_{V,\mu}} \tag{64}$$

$$P = -\frac{\partial \Phi}{\partial V}_{T,\mu} = T \frac{\partial (\ln Z)}{\partial V}_{T,\mu}$$

$$(65)$$

$$\langle N \rangle = -\frac{\partial \Phi}{\partial \mu}_{T,V} = T \frac{\partial (\ln \mathcal{Z})}{\partial \mu}_{T,V} = z \frac{\partial (\ln \mathcal{Z})}{\partial z}_{T,V}$$
 (66)

The average energy is $\langle E \rangle = \Phi + TS + \mu \langle N \rangle$. Particle number fluctuations are given by:

$$\langle (\Delta N)^2 \rangle = \langle N^2 \rangle - \langle N \rangle^2 = T \frac{\partial \langle N \rangle}{\partial \mu}_{TV} = T^2 \frac{\partial^2 (\ln \mathcal{Z})}{\partial \mu^2 \partial T, V}$$
 (67)

The relative fluctuation $\sqrt{\langle (\Delta N)^2 \rangle}/\langle N \rangle \sim 1/\sqrt{N}$.

13 Classical Ideal Gas Revisited

13.1 Partition Function (Canonical Ensemble)

Let's calculate the canonical partition function Z for N indistinguishable, non-interacting monatomic particles. First, the single-particle partition function ζ (treating particles as distinguishable for now):

$$\zeta = Z(T, V, N = 1)_{\text{dist}} = \frac{1}{h^3} \int d^3q \int d^3p \, e^{-p^2/(2mT)}$$

The position integral gives V. The momentum integral is separable: $\int d^3p \cdots = (\int_{-\infty}^{\infty} e^{-p_x^2/(2mT)} dp_x)^3$. Each Gaussian integral yields $\sqrt{2\pi mT}$.

$$\zeta = \frac{V}{h^3} (\sqrt{2\pi mT})^3 = V \left(\frac{2\pi mT}{h^2}\right)^{3/2}$$

It's convenient to define the thermal de Broglie wavelength:

$$\lambda_{th}(T) = \frac{h}{\sqrt{2\pi mT}}$$

This represents the typical quantum wavelength of a particle at temperature T. Then:

$$\zeta = \frac{V}{\lambda_{th}^3} \tag{68}$$

For N non-interacting, distinguishable particles, $Z_{\text{dist}} = \zeta^N$. For indistinguishable particles in the classical (dilute) limit, we correct for overcounting identical states using the Gibbs factor 1/N!:

$$Z(T, V, N) = \frac{Z_{\text{dist}}}{N!} = \frac{\zeta^N}{N!} = \frac{1}{N!} \left(\frac{V}{\lambda_{th}^3}\right)^N$$
(69)

The Helmholtz Free Energy is $F = -T \ln Z = -T(N \ln \zeta - \ln N!)$. Using Stirling's approximation $\ln N! \approx N \ln N - N$:

$$F \approx -T \left(N \ln(V/\lambda_{th}^3) - (N \ln N - N) \right) \tag{70}$$

$$= -NT \left(\ln \left[\frac{V}{N\lambda_{th}^3} \right] + 1 \right) \tag{71}$$

This gives the free energy of a classical ideal gas. Let's check consistency: Pressure: $P = -\frac{\partial F}{\partial V}_{T,N} = -(-NT)\frac{\partial}{\partial V}_{T,N} = NT/V$. Correct. Entropy: $S = -\frac{\partial F}{\partial T}_{V,N}$. From (71), noting $\lambda_{th} \propto T^{-1/2}$, so $\ln \lambda_{th}^3 \propto -\frac{3}{2} \ln T$:

$$\begin{split} F &= -NT \left(\ln(V/N) - \ln\left(\lambda_{th}^3\right) + 1 \right) \\ &= -NT \left(\ln(V/N) + \frac{3}{2} \ln\left(2\pi m/h^2\right) + \frac{3}{2} \ln T + 1 \right) \\ S &= -\frac{\partial F}{\partial T}_{V,N} = N \left(\ln\left[\frac{V}{N\lambda_{th}^3}\right] + 1 \right) + NT \left(\frac{3}{2T}\right) \\ &= N \left(\ln\left[\frac{V}{N\lambda_{th}^3}\right] + \frac{5}{2} \right) \end{split}$$

This is the Sackur-Tetrode equation for entropy. Energy: $E = F + TS = -NT(\cdots + 1) + NT(\cdots + 5/2) = \frac{3}{2}NT$. Correct.

14 Equipartition Theorem

This powerful theorem applies to *classical* systems in thermal equilibrium.

Theorem: For a classical system described by Hamiltonian H(q, p), each degree of freedom x_i (which can be a coordinate q_i or momentum p_i) that appears only as a quadratic term Ax_i^2 in the Hamiltonian contributes $\frac{1}{2}T$ to the average internal energy.

Proof Sketch: Consider a term $H_i = A_i p_i^2$. Its average value is:

$$\langle H_i \rangle = \frac{\int (A_i p_i^2) e^{-H(q,p)/T} d\Gamma}{\int e^{-H(q,p)/T} d\Gamma}$$

Since $H = H_i + H_{rest}$ where H_{rest} doesn't involve p_i , the integral separates:

$$\langle H_i \rangle = \frac{\int_{-\infty}^{\infty} (A_i p_i^2) e^{-A_i p_i^2/T} dp_i}{\int_{-\infty}^{\infty} e^{-A_i p_i^2/T} dp_i} \times \frac{\int e^{-H_{\text{rest}}/T} d\Gamma_{\text{rest}}}{\int e^{-H_{\text{rest}}/T} d\Gamma_{\text{rest}}}$$

The second factor cancels. Let $x = \sqrt{A_i/T}p_i$, $dp_i = \sqrt{T/A_i}dx$.

$$\langle H_i \rangle = \frac{\int Tx^2 e^{-x^2} \sqrt{T/A_i} dx}{\int e^{-x^2} \sqrt{T/A_i} dx} = T \frac{\int x^2 e^{-x^2} dx}{\int e^{-x^2} dx}$$

The integrals are standard Gaussian integrals: $\int e^{-x^2} dx = \sqrt{\pi}$ and $\int x^2 e^{-x^2} dx = \sqrt{\pi}/2$.

$$\langle H_i \rangle = T \frac{\sqrt{\pi}/2}{\sqrt{\pi}} = \frac{1}{2}T$$

The same logic applies to quadratic terms $B_j q_i^2$.

14.1 Examples

- Monatomic ideal gas: $H = \sum_{i=1}^{N} (p_{ix}^2 + p_{iy}^2 + p_{iz}^2)/(2m)$. 3N quadratic momentum terms. $\langle E \rangle = 3N \times (\frac{1}{2}T) = \frac{3}{2}NT$. $C_V = \frac{\partial E}{\partial T_V} = \frac{3}{2}N$.
- Diatomic ideal gas (rigid rotor): Add rotational kinetic energy, e.g., $H_{rot} = (L_x^2 + L_y^2)/(2I)$ (2 axes perpendicular to bond). L_x, L_y involve momenta quadratically. Add $2 \times (\frac{1}{2}T) = T$. Total $\langle E \rangle = \frac{3}{2}NT + T = \frac{5}{2}NT$. $C_V = \frac{5}{2}N$.
- Diatomic ideal gas (with vibration): Add vibrational energy $H_{vib} = p_{\xi}^2/(2\mu) + \frac{1}{2}k\xi^2$. One quadratic momentum term, one quadratic position term. Add $2 \times (\frac{1}{2}T) = T$. Total $\langle E \rangle = \frac{5}{2}NT + T = \frac{7}{2}NT$. $C_V = \frac{7}{2}N$. (Note: Vibration and rotation are often quantized and equipartition fails at low T).
- Solid (Dulong-Petit Law): Model atoms as 3D harmonic oscillators. $H = \sum_{i=1}^{N} (\frac{\vec{p}_i^2}{2m} + \frac{1}{2}m\omega^2\vec{r}_i^2)$. 3N quadratic momentum terms +3N quadratic position terms =6N terms. $\langle E \rangle = 6N \times (\frac{1}{2}T) = 3NT$. $C_V = 3N$. This classical result holds at high temperatures.

15 Quantum Statistics Examples

Equipartition fails when T is comparable to or smaller than the energy level spacing ($\sim h/(2\pi)\omega$). We need quantum statistics.

15.1 Harmonic Oscillator (Quantum)

Energy levels $E_n = h/(2\pi)\omega(n+1/2)$, where $n=0,1,2,\ldots$ Canonical partition function for a single oscillator:

$$Z = \sum_{n=0}^{\infty} e^{-E_n/T} = \sum_{n=0}^{\infty} e^{-h/(2\pi)\omega(n+1/2)/T} = e^{-h/(2\pi)\omega/(2T)} \sum_{n=0}^{\infty} (e^{-h/(2\pi)\omega/T})^n$$

This is a geometric series with $x = e^{-h/(2\pi)\omega/T} < 1$. Sum is 1/(1-x).

$$Z = \frac{e^{-h/(2\pi)\omega/(2T)}}{1 - e^{-h/(2\pi)\omega/T}} = \frac{1}{2\sinh(h/(2\pi)\omega/(2T))}$$
(72)

Average energy $\langle E \rangle = T^2 \frac{\partial (\ln Z)}{\partial T}$.

$$\ln Z = -\frac{h/(2\pi)\omega}{2T} - \ln\left(1 - e^{-h/(2\pi)\omega/T}\right)$$

$$\begin{split} \frac{\partial (\ln Z)}{\partial T} &= \frac{h/(2\pi)\omega}{2T^2} - \frac{1}{1 - \mathrm{e}^{-h/(2\pi)\omega/T}} (-\mathrm{e}^{-h/(2\pi)\omega/T}) (\frac{h/(2\pi)\omega}{T^2}) \\ &= \frac{h/(2\pi)\omega}{T^2} \left[\frac{1}{2} + \frac{\mathrm{e}^{-h/(2\pi)\omega/T}}{1 - \mathrm{e}^{-h/(2\pi)\omega/T}} \right] = \frac{h/(2\pi)\omega}{T^2} \left[\frac{1}{2} + \frac{1}{\mathrm{e}^{h/(2\pi)\omega/T} - 1} \right] \end{split}$$

Multiplying by T^2 :

$$\langle E \rangle = h/(2\pi)\omega \left[\frac{1}{2} + \frac{1}{e^{h/(2\pi)\omega/T} - 1} \right]$$
 (73)

The first term is the zero-point energy. The second term is the Planck distribution describing the average excitation number $\langle n \rangle = 1/(e^{h/(2\pi)\omega/T} - 1)$. Heat capacity $C = \frac{\partial \langle E \rangle}{\partial T}$:

$$C = \frac{\partial}{\partial T} \left[\frac{h/(2\pi)\omega}{e^{h/(2\pi)\omega/T} - 1} \right] = \dots = \left(\frac{h/(2\pi)\omega}{T} \right)^2 \frac{e^{h/(2\pi)\omega/T}}{(e^{h/(2\pi)\omega/T} - 1)^2}$$
(74)

Behavior in limiting cases:

- High T $(T \gg h/(2\pi)\omega)$: $e^{h/(2\pi)\omega/T} \approx 1 + h/(2\pi)\omega/T$. Then $\langle E \rangle \approx h/(2\pi)\omega(\frac{1}{2} + \frac{1}{h/(2\pi)\omega/T}) \approx T$. $C \to 1$ (per oscillator, $k_B = 1$). Equipartition recovered (2 quadratic terms give T).
- Low T $(T \ll h/(2\pi)\omega)$: $e^{h/(2\pi)\omega/T} \gg 1$. $\langle E \rangle \approx h/(2\pi)\omega(\frac{1}{2} + e^{-h/(2\pi)\omega/T}) \rightarrow \frac{1}{2}h/(2\pi)\omega$. $C \approx (\frac{h/(2\pi)\omega}{T})^2 e^{-h/(2\pi)\omega/T} \rightarrow 0$. Heat capacity freezes out exponentially.

15.2 Einstein Solid

A simple model for vibrations in a solid: N atoms treated as 3N independent 1D quantum harmonic oscillators, all with the same frequency ω . Total average energy $\langle E \rangle_{total} = 3N \times \langle E \rangle_{1D~HO}$.

$$\langle E \rangle_{total} = 3Nh/(2\pi)\omega \left[\frac{1}{2} + \frac{1}{\mathrm{e}^{h/(2\pi)\omega/T} - 1} \right]$$

Heat capacity $C_V = \frac{\partial \langle E \rangle_{total}}{\partial T} = 3N \times C_{1D \text{ HO}}$. Define the Einstein Temperature $\Theta_E = h/(2\pi)\omega$.

$$C_V(T) = 3N \left(\frac{\Theta_E}{T}\right)^2 \frac{e^{\Theta_E/T}}{(e^{\Theta_E/T} - 1)^2}$$
(75)

Limits:

- High T $(T \gg \Theta_E)$: $e^{\Theta_E/T} \approx 1 + \Theta_E/T$. $C_V \to 3N$. Recovers classical Dulong-Petit law.
- Low T $(T \ll \Theta_E)$: $C_V \approx 3N(\Theta_E/T)^2 e^{-\Theta_E/T} \to 0$. Captures the freezing out of heat capacity, but the exponential decay is faster than the T^3 dependence observed experimentally (explained by Debye model accounting for collective modes/phonons with a distribution of frequencies).

15.3 Paramagnetism (Spin J)

Consider N non-interacting magnetic moments (e.g., atoms with total angular momentum J) at fixed positions in an external magnetic field $\vec{H} = H\hat{z}$. The energy of a single moment depends on its orientation relative to the field. The z-component of angular momentum is quantized: $J_z = mh/(2\pi)$, where m = -J, -J + 1, ..., J. The magnetic moment is $\vec{\mu} = g\mu_B \vec{J}/h/(2\pi)$. Energy levels are $E_m = -\vec{\mu} \cdot \vec{H} = -\mu_z H = -g\mu_B mH$. Partition function for a single spin Z_1 :

$$Z_1 = \sum_{m=-J}^{J} e^{-E_m/T} = \sum_{m=-J}^{J} e^{g\mu_B mH/T}$$

Let $\eta = g\mu_B H/T$. The sum is a finite geometric series $\sum_{m=-J}^{J} (e^{\eta})^m$.

$$Z_1 = \frac{\sinh((J+1/2)\eta)}{\sinh(\eta/2)} \tag{76}$$

For N such moments (assuming distinguishable sites): $Z=(Z_1)^N$. The average z-component of a single magnetic moment is $\langle \mu_z \rangle = T \frac{\partial (\ln Z_1)}{\partial H}_T$.

$$\langle \mu_z \rangle = T \frac{\partial \eta}{\partial H} \frac{\partial (\ln Z_1)}{\partial \eta} = T \left(\frac{g\mu_B}{T} \right) \frac{\partial}{\partial \eta} [\ln \sinh((J+1/2)\eta) - \ln \sinh(\eta/2)]$$
$$= g\mu_B \left[(J+1/2) \coth((J+1/2)\eta) - (1/2) \coth(\eta/2) \right]$$

This is conveniently written using the Brillouin function $B_J(x)$:

$$B_J(x) = \frac{1}{J} \left[(J + 1/2) \coth((J + 1/2)x) - (1/2) \coth(x/2) \right]$$
(77)

$$\langle \mu_z \rangle = g \mu_B J B_J(\eta) \quad \text{where } \eta = g \mu_B H / T$$
 (78)

The total magnetization M is N times the average moment:

$$M = N \langle \mu_z \rangle = Ng\mu_B J B_J(\eta) \tag{79}$$

Limits:

• High T / Low H ($\eta \ll 1$): Use $\coth(x) \approx 1/x + x/3$ for small x. $B_J(\eta) \approx \frac{J+1}{3}\eta$.

$$M \approx Ng\mu_B J \frac{J+1}{3} \frac{g\mu_B H}{T} = \frac{N(g\mu_B)^2 J(J+1)}{3T} H$$

This is the Curie Law: $M = \chi H$ with magnetic susceptibility $\chi = C/T$, where $C = \frac{N(g\mu_B)^2 J(J+1)}{3}$ is the Curie constant.

• Low T / High H $(\eta \gg 1)$: Use $\coth(x) \to 1$ for large x. $B_J(\eta) \to \frac{1}{J}[(J+1/2)-1/2]=1$.

$$M \to Ng\mu_B J$$

The magnetization saturates as all moments align with the field.

16 Elements of Kinetic Theory

Kinetic theory provides a microscopic perspective on gas properties based on particle motion and collisions. We assume dilute gases (particles mostly independent between collisions).

16.1 Maxwell Velocity and Speed Distributions

We previously found the equilibrium distribution of velocities for classical particles:

$$f(\vec{v})d^3v = \left(\frac{m}{2\pi T}\right)^{3/2} e^{-mv^2/(2T)}d^3v$$

Often we are interested in the distribution of speeds $v = |\vec{v}|$. We integrate $f(\vec{v})$ over the angular variables in velocity space $(d^3v = v^2dvd\Omega = v^2\sin\theta dvd\theta d\phi)$. The integral over $d\Omega$ gives 4π . The Maxwell speed distribution is F(v)dv:

$$F(v)dv = 4\pi \left(\frac{m}{2\pi T}\right)^{3/2} v^2 e^{-mv^2/(2T)} dv$$
(80)

Various characteristic speeds can be calculated from F(v):

• Most probable speed \tilde{v} : Speed where F(v) is maximum. Found from dF/dv = 0.

$$\tilde{v} = \sqrt{2T/m}$$

• Mean speed $\langle v \rangle$: Average value of v.

$$\langle v \rangle = \int_0^\infty v F(v) dv = \sqrt{8T/(\pi m)}$$

• Root-mean-square (RMS) speed v_{rms} : Square root of the average squared speed.

$$\langle v^2 \rangle = \int_0^\infty v^2 F(v) dv = 3T/m \implies v_{rms} = \sqrt{\langle v^2 \rangle} = \sqrt{3T/m}$$

Note the ordering: $\tilde{v}: \langle v \rangle : v_{rms} \approx 1:1.128:1.225.$

16.2 Particle Flux and Effusion

Consider particles crossing a unit area perpendicular to the z-axis. The number flux $\Phi(\vec{v})d^3v$ is the number of particles with velocity near \vec{v} crossing per unit area per unit time. Particles with velocity \vec{v} cross area dA in time dt if they are within a cylinder of volume $v_z dt dA$. The number density of such particles is $nf(\vec{v})d^3v$. Flux = (Number) / (Area × Time) = $(nf(\vec{v})d^3v)(v_z dt dA)/(dAdt) = nv_z f(\vec{v})d^3v$. The total particle flux Φ_0 in the +z direction is obtained by integrating over all velocities with $v_z > 0$:

$$\Phi_0 = \int_{v_x = -\infty}^{\infty} \int_{v_y = -\infty}^{\infty} \int_{v_z = 0}^{\infty} nv_z f(\vec{v}) dv_x dv_y dv_z$$

Performing the integrals yields:

$$\Phi_0 = n\sqrt{\frac{T}{2\pi m}} = \frac{1}{4}n\langle v\rangle \tag{81}$$

Using the ideal gas law P = nT:

$$\Phi_0 = \frac{P}{\sqrt{2\pi mT}} \tag{82}$$

Effusion is the slow leakage of gas from a container through a small hole (area A) into a vacuum. If the hole is small enough not to disturb the equilibrium distribution inside, the rate of particle escape is:

$$I = \Phi_0 A = \frac{PA}{\sqrt{2\pi mT}}$$
 (particles/time) (83)

16.3 Pressure of an Ideal Gas

Pressure arises from momentum transfer during collisions of particles with the container walls. Consider elastic collisions with a wall perpendicular to z. A particle with velocity \vec{v} undergoes a momentum change $\Delta p_z = -2mv_z$ if $v_z < 0$ (hitting the wall). The force on the wall is the rate of momentum transfer. The number of particles hitting area A in time dt with velocity \vec{v} ($v_z > 0$) is $(nf(\vec{v})d^3v)(Av_zdt)$. Each imparts momentum $2mv_z$ to the wall (using v_z of incident particle). Total force $F_z = \int_{v_z>0} (\text{momentum transfer/particle}) \times (\text{number flux hitting wall})$.

$$F_z = \int_{v_z > 0} (2mv_z)(nv_z f(\vec{v})d^3v)A = 2mnA \int_{v_z > 0} v_z^2 f(\vec{v})d^3v$$

Since $f(\vec{v})$ is symmetric, the integral over $v_z > 0$ is half the integral over all v_z :

$$\int_{v_z > 0} v_z^2 f(\vec{v}) d^3 v = \frac{1}{2} \int v_z^2 f(\vec{v}) d^3 v = \frac{1}{2} \left\langle v_z^2 \right\rangle$$

So, $F_z = 2mnA(\frac{1}{2}\langle v_z^2 \rangle) = mnA\langle v_z^2 \rangle$. Pressure $P = F_z/A = mn\langle v_z^2 \rangle$. From isotropy, $\langle v_x^2 \rangle = \langle v_y^2 \rangle = \langle v_z^2 \rangle$. Since $\langle v^2 \rangle = \langle v_x^2 + v_y^2 + v_z^2 \rangle = 3\langle v_z^2 \rangle$. From equipartition (or direct calculation), $\langle v^2 \rangle = 3T/m$. Therefore $\langle v_z^2 \rangle = T/m$. Substituting gives:

$$P = mn(T/m) = nT (84)$$

Kinetic theory successfully reproduces the ideal gas law.