

Configuration of postfix to send mails using gmail.

- update and upgrade all the packages
 sudo apt-get update && sudo apt-get upgrade
- 2. Install Postfix and the libsasl2-modules package sudo apt-get install libsasl2-modules postfix
- 3. Select internet site in the prompt and enter the FQDN as <username>@localhost.com



4. Enable the less secure app access on the gmail account you are going to use to send mails.



5. Configure the Postfix Relay Server

5.1 open file /etc/postfix/main.cf and modify relayhost

```
sudo vi /etc/postfix/main.cf
relayhost = [smtp.gmail.com]:587
```

5.2 At the end of the file, add the following parameters to enable authentication

```
# Enable SASL authentication
smtp_sasl_auth_enable = yes
# Disallow methods that allow anonymous authentication
smtp_sasl_security_options = noanonymous
# Location of sasl_passwd
smtp_sasl_password_maps = hash:/etc/postfix/sasl/sasl_passwd
# Enable STARTTLS encryption
smtp_tls_security_level = encrypt
# Location of CA certificates
smtp_tls_CAfile = /etc/ssl/certs/ca-certificates.crt
```

5.3 Save and close the file

6. Add Gmail Username and Password to Postfix

- Open or create the /etc/postfix/sasl/sasl_passwd file and add the following [smtp.gmail.com]:587 <u>username@gmail.com</u>:password
- 6.2 Create the hash db file for Postfix by running the postmap command sudo postmap /etc/postfix/sasl/sasl_passwd

7. Secure Your Postfix Hash Database and Email Password Files

sudo chown root:root /etc/postfix/sasl/sasl_passwd /etc/postfix/sasl/sasl_passwd.db sudo chmod 0600 /etc/postfix/sasl/sasl_passwd /etc/postfix/sasl/sasl_passwd.db

8. Restart Postfix

```
sudo systemctl restart postfix (For ubuntu 16.04) sudo service postfix restart (For ubuntu 14.04)
```