Root canal treatment procedure Quick Guide

D. de Groot – Kuin, R. van der Horst, A. Bouwman

Radboudumc

Endodontic treatment

Diagnosis

Preconditions: caries-free/good restoration/

DETI

- Endodontic opening
- Rubberdam

Coronal phase

Length determination

Preparation

Channel filling

- Definitive coronal closure
- Control



Starting photo

- Initial photo of course already taken at diagnosis.
 No endostart without initial photo
- Initial photo
 - Visibility of pulp chamber
 Visibility of canals
 Root
 curvatures
 Inclinations
 - Resorpties



Open, rubber dam and rinse








Open = remove pulp roof
The pulp roof is not located on or
coronal to the cementoenamel border


After removing the pulp roof place rubber dam and rinse with sodium hypochlorite

Coronal phase: Defining canal entrance


- Protaper SX
 - Define canal entrance and extract coronal curvature








Coronal phase: Defining canal entrance





Length determination

- Length determination Clinic
- Electronic length meter
 - Final length is -1mm




- Length determination Preclinic
- X-ray

Measuring distance from apex to reference point (lump tip) on initial photo -1mm




Glide path

- Create a glide path with #10 to working length.
 Goldglider to the same length
- Why
 - Anatomical path for files
 Less chance of file breakage
 - Easier to work



Length photo

- Longitudinal photo
 - Minimum #15
 - Get stuck
 - Buccal K-file
 - Lingual/palatal H-file
 - Injected at a mesial angle
 - Write down a clear reference point
 - Mesiobuccal cusp (mbknb)
 - Palatal cusp (pknb)
 - Mesial randlijst (mrnd)





Radboudumc

After each instrument: rinse

Flush debris from canals

Replace sodium hypochlorite •

Dissolve tissue debris •

Disinfect



After each instrument: rinse

Set the flushing needle to WL-1 mm (with rubber stopper or kink in the needle):
 when the shaping is completed, the flushing needle can be placed in
 the canal up to that depth. Rinse during shaping by placing the needle in the
 canal but never letting it get stuck (so not too deep).

HOE DOORPERSEN TE VOORKOMEN?

Stel spoelnaald op juiste lengte in Gebruik 'safe end' naalden? Laat uiteinde van de

naald nooit vastlopen in het kanaal









Apical phase

- WaveOne 25
- WaveOne 35

3x pecking motion
 File must go deeper each time
 Recapitulate



First WaveOne 25 to full length.
 Then WaveOne 35




Preparation complete

- Rinse at WL-1 mm
 Dissolve smear layer with EDTA
- Ultrasonic activated irrigation

EDTA





Disinfection

- Canal preparation from coronal to apical
- Irrigation during preparation: 2 cc NaOCI 2.5% after each instrument
- After completing preparation: dissolve the smear layer with EDTA (10-17%) or citric acid (10-20%)
- Ultrasonic rinsing, to remove debris from unprepared canal parts with NaOCI:
 Irrisafe rinsing needle and Satelec Newtron P5 on setting 4



Fit head pins, dry



- Design with waveone green
 Single cone main pin wave one green
- At working length
- Too short? > repeat preparation
- Too long? > shorten apical post

finishing channel filling

Remove excess with ultrasonic

Vertical condensation with cold hand stopper (correctly fitting = just below pulp chamber floor)

Wash out pulp chamber with alcohol





Cleaning pulp chamber

