



# USSD S-Gateway USSD C/C++ API

User's Guide v1.1



### **Table of Contents**

Introduction		3
Capacity		3
RSA/AES Sec	ured mode	4
	n structure	
	nework	
	re	
	3	
1.	initialize	8
2.	connect	
3.	ussd_request	10
4.	ussd_end	11
5.	pong	
<b>API Callbacks</b>		13
1.	ussd_service	13
2.	ussd_response	14
3.	ussd_end	15
4.	disconnected	15
5.	connected	15
6.	ping	15
<b>Example Mess</b>	sage Sequences	16
1.	Succesfull Application Connection	
2.	Application Disconnection	
3.	Ping-Pong	18
4.	User Initiated USSD Transaction Ended by Application	19
5.	User Initiated USSD Transaction Aborted by User	
Length of the	USSD String	21
<b>USSD</b> Configu	uration	21

Phone: +598 2 6141193 / Fax: +598 2 4816924



### Introduction

LeibICT USSD S-Gateway supports applications over MAP (Mobile Application Part) (phase 2 and 3), either mobile or USSD application originated, using the message set defined in the protocol. The mobile originated data are received by the USSD application and forwarded to the HLR (Home Location Register), where as the network originated messages are forwarded to the HLR at once.

This document presents a description of the USSD C/C++ API supported and managed by the LeibICT's USSD S-Gateway.

The USSD C/C++ API offers a high abstraction layer for C/C++ Applications witch:

- 1) Controls the TCP/IP connection, including reconnection.
- 2) Implements the RSA encryption and decryption.
- 3) Implements the XML creation and parsing.
- 4) Controls the USSD/MAP protocol details.

# Capacity

The current USSD S-Gateway version supports 16384 incoming and outgoing messages by stack, with capability of two stacks running independently, so a total capacity of 32678 incoming and outgoing simultaneous messages

Each USSD transaction is identified by a dialog identifier (field named: *DialogueId*), represented by 16 bits. This parameter must be included in each dialogue message so the USSD application must be capable of controlling such parameter. For each outgoing message coming from the application, the latter must include a *Dialogue Id* between 0 and 16383, where as when it receives a message, it must answer using the same *Dialogue Id* of the incoming message, which will be a digit between 16384 and 32768.

The RSA encryption and decryption process is very high cpu consuming, setting up the right key length is needed to depending of the traffic estimated.

Phone: +598 2 6141193 / Fax: +598 2 4816924




### **RSA/AFS** Secured mode

The USSD S-Gateway may be configured to use secure AES and RSA PKI Encryption. This mode assures a totally secure communication, valid for banking applications over nonsecured lans.

Due to the asymmetric load of the operations of encryption and decryption, the connection transmission and reception can be secured using different key length, or even without it.


For example, if your application vulnerable point is information presentation, you can encrypt the reception with 4096 RSA and 256 AES bits keys, and maintain the transmission unsecured. Otherwise if your application critical information is user input, you can encrypt the transmission.





# Typical system structure

The LeibICT USSD S-Gateway provides Load Balancing and Fault-Tolerance of applications:




Two USSD S-Gateways can be paired to provide Fault-Tolerance on the gateway and GSM Network level.

Phone: +598 2 6141193 / Fax: +598 2 4816924



### **Software Framework**

The USSD C/C++ API Library consists in a group of dynamically linked libraries developed in C++ that are loaded into the Application at run time.



**Application Server** 

Phone: +598 2 6141193 / Fax: +598 2 4816924



### **API Architecture**

The USSD C/C++ API Library enables programmers to access the services provided by USSD S-Gateway and protocol using a C/C++ function and callbacks based interface.

The USSD C/C++ API – USSD S-Gateway communication mechanism used is transparent to the programmer, as all the socket management is performed by the USSD Library.

When the USSD Library is initialized by calling **initialize** and **connect**, a worker thread is started which is responsible for socket management.

Events received from USSD S-Gateway are reported to the user application from this thread using a callback mechanism.

The USSD Library is thread-safe from the user's point of view. However, the user is responsible for protecting any of his own data structures accessible from multiple threads.

The USSD Library worker thread only delivers one event at a time. That is, it does not notify the user application of a new event until the user returns control from the current event handler. However this means that the user needs to avoid using blocking or lengthy operations within callback functions.

Mobile: +598 99 256037

Phone: +598 2 6141193 / Fax: +598 2 4816924



### **API Functions**

The API is centralized in a class: CUSSD, these are the API functions:

Function	Page
initialize	7
connectgw	8
ussd_request	9
ussd_end	10
pong	11

### 1. initialize

int CUSSD::initialize(USSDCallbacks\*));

#### **Description**

The initialize function initializes the USSD Library and declares the call-backs locations.

#### Output

Return values:

0 – An error occurred during initialization

1 - Initialization successfully

Phone: +598 2 6141193 / Fax: +598 2 4816924



### 2. connect

int CUSSD::connect(String addr,int port,int rsaRcv, int rsaSnd);

#### Input

Parameter	Description	Example
addr	IP or Domain Name of the USSD S-Gateway	10.0.0.1
por	TCP port of the USSD S-Getway	5454
rsaRcv	RSA Security used for reception	0- Unsecured
		1- RSA 512bit
		2- RSA 1024bit
		3- RSA 2048bit
		4- RSA 4096bit
rsaSnd	RSA Security used for transmission	Same as rsaRcv

#### **Description**

The connect function tries to connect the USSD S-Gateway. If it success and there is a network failure, there is no need to call this function again, the USSD Library will try to reconnect automatically.

#### Output

Return values:

- 0 An error occurred during socket connection establishment or while securing it.
- 1 Connection and security established successfully

Phone: +598 2 6141193 / Fax: +598 2 4816924



### 3. ussd\_request

int CUSSD::ussd\_request(int dialogId,String prompt);

#### Input

Parameter	Description	Example
dialogld	Dialog of the current USSD Service	1
prompt	String containing a prompo for the user	"Enter the PIN"

#### **Description**

The ussd\_request function sends a message to the user trough the USSD S-Gateway requesting some input.

#### **Output**

Return values:

0 - An error occurred

1 - The command was successfully received by the USSD S-Gateway

Phone: +598 2 6141193 / Fax: +598 2 4816924



### 4. ussd\_end

int CUSSD::ussd\_end(int dialogId,String info);

#### Input

Parameter	Description	Example
dialogld	Dialog of the current USSD Service	1
info	String containing the last message to the user	"Have a nice day"

#### **Description**

The ussd\_end function sends a message to the user trough the USSD S-Gateway finalizing the dialog.

### **Output**

Return values:

0 - An error occurred

1 - The command was successfully received by the USSD S-Gateway

Phone: +598 2 6141193 / Fax: +598 2 4816924



### 5. pong

int CUSSD::pong();

#### **Description**

The pong function sends a pong to the USSD S-Gateway. The pong function must be the response to the ping call-back. If the application does not respond the ping with a pong, the USSD S-Gateway may disconnect the application.

The intervals between pings are defined in the USSD S-Gateways and cannot be determined in the Application side.

#### Output

Return values:

0 - An error occurred

1 – The command was successfully received by the USSD S-Gateway

Mobile: +598 99 256037

Phone: +598 2 6141193 / Fax: +598 2 4816924



### **API Callbacks**

These are the API Callbacks:

Callback	Page
ussd_service	12
ussd_response	13
ussd_end	14
disconnected	14
connected	14
ping	14

### 1. ussd\_service

void ussd\_service(int dialogId,String shortCode,String phoneNumber) {}

#### **Output**

Parameter	Description	Example
dialogld	Dialog of the current USSD Service	1
shortCode	String containing the shortcode entered by the	"*123#"
	user	
phoneNumber	String containing the phone number of the user	"888-123-123"

Phone: +598 2 6141193 / Fax: +598 2 4816924

Mobile: +598 99 256037

### **Description**

The *ussd\_service* call-back is called when a new ussd service is started by the User.



# 2. ussd\_response

void ussd\_response(int dialogId,String str) {}

### Output

Parameter	Description	Example
dialogld	Dialog of the current USSD Service	1
str	String containing the user response of a	"1"
	request.	

### **Description**

The *ussd\_response* call-back is called when a user responses a request.

Phone:+598 2 6141193 / Fax: +598 2 4816924



### 3. ussd\_end

void ussd\_end(int dialogId) {}

#### **Output**

Parameter	Description	Example
dialogld	Dialog of the current USSD Service	1

#### **Description**

The ussd\_end call-back is called when the user, the GSM network or the USSD S-Gateway ends the dialog.

### 4. disconnected

void disconnected() {}

#### **Description**

The disconnected call-back is called when USSD Library gets disconnected from the USSD S-Gateway.

#### 5. connected

void connected() {}

#### **Description**

The connected call-back is called when USSD Library gets connected again to the USSD S-Gateway.

### 6. ping

void ping() {}

#### **Description**

The ping call-back is called when USSD S-Gateway sends a ping to the Application.

Mobile: +598 99 256037


Phone: +598 2 6141193 / Fax: +598 2 4816924



# **Example Message Sequences**

The fallowing chapter gives example message sequences for interacting with USSD C/C++ API.


### 1. Succesfull Application Connection



Phone: +598 2 6141193 / Fax: +598 2 4816924




# 2. Application Disconnection



Phone: +598 2 6141193 / Fax: +598 2 4816924




## 3. Ping-Pong



Phone: +598 2 6141193 / Fax: +598 2 4816924




### 4. User Initiated USSD Transaction Ended by Application



Phone: +598 2 6141193 / Fax: +598 2 4816924



### 5. User Initiated USSD Transaction Aborted by User



Phone: +598 2 6141193 / Fax: +598 2 4816924



# Length of the USSD String

In GSM 0902 160 octets is stated as the maximum length for the USSD string. Due to underlying signalling layers the maximum length of the USSD string depending on the message is:

USSD operation	Max length
Begin, Invoke ProcessUSSDRequest	133
End, Result ProcessUSSDRequest	160
First Continue, Invoke USSDRequest in mobile initiated dialogue	154
Begin, Invoke USSDRequest	144
First Continue, Result USSDRequest in network initiated dialogue	154
Other messages	160

# **USSD** Configuration

The USSD C/C++I Library has on Windows a registry based configuration and on Linux a file based configuration.

Windows USSD:

HKEY\_LOCAL\_MACHINE\SOFTWARE\LeibICT\USSD

Linux USSD:

./USSD.conf

Field	Description	Default Value
Log	Enable or Disable standard logs	1
logDebug	Enable or Disable debug logs	0
logDir	Directory where the logs are placed	c:\logs\
IogErrorsFileName	Name of the file for errors logs	USSDErrors.log
logFileName	Name of the file for standard and debug logs	USSD.log
logTraffic	Enable or Diable traffic logs	0
IogTrafficFileName	Name of the file for traffic logs	USSDTraffic.log

Phone: +598 2 6141193 / Fax: +598 2 4816924