PHY 293 Lecture Notes

Hei Shing Cheung Waves and Modern Physics, Fall 2025

PHY293

The up-to-date version of this document can be found at https://github.com/HaysonC/skulenotes

Chapter 1

Waves

1.1 Harmonic Oscillators

1.1.1 Governing Equations of Harmonic Oscillators

This subsection collects the baseline ODEs for simple, damped, and driven oscillators to set notation used later.

Types of Harmonic Oscillators There are three types of harmonic oscillators: simple, damped, and driven harmonic oscillators. Consider a simple one dimensional harmonic oscillator, they are defined by the following differential equations:

Definition 1.1.1.1 (Simple Harmonic Oscillator). A simple harmonic oscillator is described by Hooke's law:

$$m\frac{d^2x}{dt^2} + kx = 0\tag{1.1}$$

where k is the spring constant, m is the mass, and x is the displacement from equilibrium.

Definition 1.1.1.2 (Damped Harmonic Oscillator). A damped harmonic oscillator is described by the following differential equation, by adding a damping term proportional to \dot{x} to the simple harmonic oscillator equation:

$$m\frac{d^2x}{dt^2} + b\frac{dx}{dt} + kx = 0 ag{1.2}$$

where b is the damping coefficient.

Note on damping parameter conventions. Different texts use different symbols and normalizations:

- Our notes use $\gamma = \frac{b}{m}$, so the ODE reads $\ddot{x} + \gamma \dot{x} + \omega_0^2 x = 0$ and the decay envelope is $e^{-\gamma t/2}$.
- Many texts define $\beta = \frac{b}{2m}$ and may call it γ instead. In that convention the ODE is $\ddot{x} + 2\beta \dot{x} + \omega_0^2 x = 0$ with envelope $e^{-\beta t}$.

Equivalences: $\beta = \frac{\gamma}{2}$ and our underdamped condition $\gamma < 2\omega_0$ corresponds to $\beta < \omega_0$ in the 2β convention. When comparing formulas, check which definition is being used and replace $\gamma \leftrightarrow 2\beta$ accordingly.

Definition 1.1.1.3 (Driven Harmonic Oscillator). A driven harmonic oscillator is described by the following differential equation, which includes an external driving force F(t):

$$m\frac{d^2x}{dt^2} + b\frac{dx}{dt} + kx = F(t)$$
(1.3)

1.1.2 Simple Harmonic Motion

We analyze the undamped solution forms, relate constants to initial conditions, and derive period/frequency relations.

Definition 1.1.2.1 (Simple Harmonic Motion). You should have learned Hooke's law and Newton's second law, which give us the equation of motion for a simple harmonic oscillator. The same as equation (1.1), which can be rewritten as:

$$F = m\ddot{x} = -kx \tag{1.4}$$

By setting $\omega^2 = \frac{k}{m}$, a general solution can be written as:

$$x(t) = x_0 + A_1 \cos(\omega t) + A_2 \sin(\omega t) \tag{1.5}$$

where A_1 and A_2 are constants determined by the IVP, ω is the angular frequency, and ϕ is the phase constant. x_0 is the equilibrium position (often set to 0). The unknown constants can be determined by knowing x, \dot{x} at specific times.

Definition 1.1.2.2 (Period, Frequency, and Angular Frequency). The period T is the time it takes for one complete cycle of the motion, given by:

$$T = 2\pi \sqrt{\frac{m}{k}} \tag{1.6}$$

The frequency f is the number of cycles per unit time, given by:

$$f = \frac{1}{T} = \frac{1}{2\pi} \sqrt{\frac{k}{m}} \tag{1.7}$$

The angular frequency ω is related to the frequency by:

$$\omega = 2\pi f = \sqrt{\frac{k}{m}} \tag{1.8}$$

Example 1.1.2.3. A simple harmonic oscillator consisting of mass m = 11.0 kg attached to a spring with spring constant $k = 201 \text{ N m}^{-1}$. At time t = 0 s the oscillator is at position x(0) = -0.207 m and has velocity $v(0) = -1.33 \text{ m s}^{-1}$. Determine all coefficients of the equation describing the position x(t) of the oscillator as a function of time, assuming the offset is zero.

To solve for A_1 and A_2 , while we assume $x_0 = 0$, we can use the initial conditions:

$$x(0) = A_1 \cos(0) + A_2 \sin(0) = A_1 = -0.207 \text{ m}$$

 $v(0) = -A_1 \omega \sin(0) + A_2 \omega \cos(0) = A_2 \omega = -1.33 \text{ m s}^{-1}$

We can find ω from the given m and k:

$$\omega = \sqrt{\frac{k}{m}} = \sqrt{\frac{201 \text{ N m}^{-1}}{11.0 \text{ kg}}} \approx 4.28 \text{ rad s}^{-1}$$

Therefore, we can solve for A_2 :

$$A_2 = \frac{v(0)}{\omega} = \frac{-1.33 \text{ m s}^{-1}}{4.28 \text{ rad s}^{-1}} \approx -0.311 \text{ m}$$

Thus, the equation describing the position x(t) of the oscillator as a function of time is:

$$x(t) = -0.207\cos(4.28t) - 0.311\sin(4.28t)$$

Theorem 1.1.2.4 (A Trigonometric Identity). We can also express the solution in a more compact form using a single cosine function with a phase shift:

$$x(t) = A\cos(\omega t + \phi) \tag{1.9}$$

where

$$A = \sqrt{A_1^2 + A_2^2},\tag{1.10a}$$

$$\phi = \arctan\left(\frac{-A_2}{A_1}\right) = \arctan\left(\frac{-v(0)/\omega}{x(0)}\right).$$
 (1.10b)

Proof. Let $A = \sqrt{A_1^2 + A_2^2}$ and choose ϕ such that

$$\cos(\phi) = \frac{A_1}{A}, \quad \sin(\phi) = -\frac{A_2}{A}.$$

Then, we can rewrite our original solution as

$$x(t) = A_1 \cos(\omega t) + A_2 \sin(\omega t)$$

$$= A \cos(\phi) \cos(\omega t) - A \sin(\phi) \sin(\omega t)$$

$$= A \left[\cos(\phi) \cos(\omega t) - \sin(\phi) \sin(\omega t)\right]$$

$$= A \cos(\omega t + \phi),$$

by the cosine addition formula.

Example 1.1.2.5. To determine the amplitude A and phase constant ϕ for the oscillator in the previous example, we can use the values of A_1 and A_2 we found:

$$\begin{split} A &= \sqrt{(-0.207)^2 + (-0.311)^2} \approx 0.374 \text{ m} \\ \phi &= \arctan\!\left(\frac{-(-0.311)}{-0.207}\right) \approx 4.12 \text{ rad} \quad \text{(since $A_1 < 0$ and $A_2 < 0$)} \end{split}$$

Therefore, the equation describing the position x(t) of the oscillator as a function of time can also be written as:

$$x(t) = 0.374\cos(4.28t + 4.12)$$

Definition 1.1.2.6 (The Energy of a Simple Harmonic Oscillator). The total mechanical energy E of a simple harmonic oscillator is the sum of its kinetic energy K and potential energy U.

$$E = K + U \tag{1.11}$$

First we consider the change of potential energy from a position x_i to x_f , assuming the path is along the spring or the curve C of the oscillator. The force exerted by the spring is given by Hooke's law, F = -kx. The change in potential energy can be simply parametized and calculated as follows:

$$\Delta U = \int_C F \cdot ds = -\int_{x_i}^{x_f} F \, dx = \int_{x_i}^{x_f} kx \, dx = \left[\frac{1}{2} kx^2 \right]_{x_i}^{x_f} = \frac{1}{2} k(x_f^2 - x_i^2) \tag{1.12}$$

Therefore, the potential energy U at a position x (taking the reference point at x=0) is given by:

$$U(x) = \frac{1}{2}kx^2 (1.13)$$

The kinetic energy K of the oscillator is given by:

$$K = \frac{1}{2}m\dot{x}^2\tag{1.14}$$

Therefore, the total mechanical energy E of the simple harmonic oscillator is:

$$E = K + U = \frac{1}{2}m\dot{x}^2 + \frac{1}{2}kx^2 \tag{1.15}$$

The total mechanical energy E remains constant over time, as energy is conserved in the absence of non-conservative forces (like friction or air resistance).

1.1.3 Damped Harmonic Motion

We solve the damped ODE, classify regimes (underdamped, critical, overdamped), and connect decay rates with parameters.

Definition 1.1.3.1 (Damped Harmonic Motion). For small velocities, the drag force is approximately proportional to the velocity and acts in the opposite direction. This drag force can be modeled as $F_d = -\gamma \dot{x}$, where γ is the damping coefficient. Including this drag force in the equation

of motion for a harmonic oscillator leads to the damped harmonic oscillator equation (1.2). Which could be rewritten as:

$$\ddot{x} + \gamma \dot{x} + \omega_0^2 x = 0 \tag{1.16}$$

where $\omega_0 = \sqrt{\frac{k}{m}}$ is the natural angular frequency of the undamped oscillator, and $\gamma = \frac{b}{m}$ is the damping coefficient per unit mass.

To skip the math, lets assume a solution of the form $x(t) = e^{i\omega t}$, substituting into the differential equation gives us a formulation for ω :

$$-\omega^2 - i\gamma\omega + \omega_0^2 = 0$$

$$\omega = -i\frac{\gamma}{2} \pm \sqrt{\omega_0^2 - \frac{\gamma^2}{4}}$$
(1.17)

Also, we can characterize the real and imaginary parts of ω as:

$$\omega_r = \text{Re}(\omega) = \pm \sqrt{\omega_0^2 - \frac{\gamma^2}{4}}$$
 (1.18a)

$$\omega_i = \operatorname{Im}(\omega) = -\frac{\gamma}{2} \tag{1.18b}$$

The general solution for the damped harmonic oscillator can be written as:

$$x(t) = \exp(\omega_i t) \exp(-i\omega_r t) = \exp\left(-\frac{\gamma}{2}t\right) \exp(\mp i\sqrt{\omega_0^2 - \frac{\gamma^2}{4}}t)$$
 (1.19)

• No Damping ($\gamma = 0$): The system behaves like a simple harmonic oscillator with angular frequency ω_0 . Given by:

$$z = \exp(-i\omega_0 t) \tag{1.20a}$$

• Underdamping $(0 < \gamma < 2\omega_0)$: The system oscillates with a gradually decreasing amplitude. The angular frequency of oscillation is given by $\omega_r = \sqrt{\omega_0^2 - \frac{\gamma^2}{4}}$. Given by:

$$z = \exp\left(-\frac{\gamma}{2}t\right) \exp(-i\omega_r t) \tag{1.20b}$$

The trigonometric form of the solution is:

$$x(t) = A_0 \exp\left(-\frac{\gamma}{2}t\right) \cos(\omega_r t + \phi)$$
 (1.20c)

where A_0 and ϕ are constants determined by the initial conditions From this, we can derive the following cases:

• Critical Damping ($\gamma = 2\omega_0$): The system returns to equilibrium as quickly as possible without oscillating. Consider:

$$x(t) = e^{-\frac{\gamma}{2}t} f(t)$$

Inserting into the differential equation, we get:

$$\ddot{f} + \left(\omega_0^2 - \frac{\gamma^2}{4}\right)f = 0$$

Since $\gamma = 2\omega_0$, we have $\omega_0^2 - \frac{\gamma^2}{4} = 0$, leading to:

$$\ddot{f} = 0 \implies f(t) = A_1 t + A_2$$

Therefore, the general solution for the critically damped case is:

$$x(t) = (A_1t + A_2) \exp\left(-\frac{\gamma}{2}t\right) \tag{1.20d}$$

where A_1 and A_2 are constants determined by

• Overdamping ($\gamma > 2\omega_0$): The system returns to equilibrium without oscillating, but more slowly than in the critically damped case. The solution is given by:

$$z = \exp\left(-\frac{\gamma}{2}t\right) \exp\left(\sqrt{\frac{\gamma^2}{4} - \omega_0^2}t\right)$$
 (1.20e)

So the general solution is (the solution is via a substitution of $x(t) = e^{-\gamma t/2} f(t)$ into the differential equation, which resolves the ODE to a simple form):

$$x(t) = A_1 \exp\left[\left(-\frac{\gamma}{2} + \sqrt{\frac{\gamma^2}{4} - \omega_0^2}\right)t\right] + A_2 \exp\left[\left(-\frac{\gamma}{2} - \sqrt{\frac{\gamma^2}{4} - \omega_0^2}\right)t\right]$$
(1.20f)

where A_1 and A_2 are constants determined by the initial conditions.

1.1.4 Energy and Quality Factor

We study how energy decays under light damping, define the time constant and quality factor Q, and relate them to response.

Definiton 1.1.4.1 (Energy of a Very Light Damping). Consider a very lightly damped harmonic oscillator, where $\gamma \ll \omega_0$. In this case, the angular frequency of oscillation ω_r can be approximated as:

$$\omega_r \approx \omega_0 \left(1 - \frac{\gamma^2}{8\omega_0^2} \right) \approx \omega_0$$

So the motion of the lightly damped oscillator can be approximated as:

$$x(t) \approx A_0 e^{-\frac{\gamma}{2}t} \cos(\omega_0 t + \phi)$$

Then, we can calculate the velocity of the oscillator:

$$\dot{x}(t) = -\frac{\gamma}{2} A_0 e^{-\frac{\gamma}{2}t} \cos(\omega_0 t + \phi) - A_0 \omega_0 e^{-\frac{\gamma}{2}t} \sin(\omega_0 t + \phi)$$
$$= A_0 \omega_0 e^{-\frac{\gamma}{2}t} \left(-\frac{\gamma}{2\omega_0} \cos(\omega_0 t + \phi) - \sin(\omega_0 t + \phi) \right)$$

The total mechanical energy E(t) of the lightly damped oscillator is given by:

$$E(t) = \frac{1}{2}m\dot{x}^2 + \frac{1}{2}kx^2$$

$$= \frac{1}{2}m\left[A_0\omega_0e^{-\frac{\gamma}{2}t}\left(-\frac{\gamma}{2\omega_0}\cos(\omega_0t + \phi) - \sin(\omega_0t + \phi)\right)\right]^2 + \frac{1}{2}k\left[A_0e^{-\frac{\gamma}{2}t}\cos(\omega_0t + \phi)\right]^2$$

$$= \frac{1}{2}mA_0^2\omega_0^2e^{-\gamma t}\left[\left(-\frac{\gamma}{2\omega_0}\cos(\omega_0t + \phi) - \sin(\omega_0t + \phi)\right)^2 + \cos^2(\omega_0t + \phi)\right]$$

$$= \frac{1}{2}mA_0^2\omega_0^2e^{-\gamma t}\left[\sin^2(\omega_0t + \phi) + \cos^2(\omega_0t + \phi) + \frac{\gamma^2}{4\omega_0^2}\cos^2(\omega_0t + \phi) + \frac{\gamma}{\omega_0}\sin(\omega_0t + \phi)\cos(\omega_0t + \phi)\right]$$

$$\approx \frac{1}{2}mA_0^2\omega_0^2e^{-\gamma t}\left[1 + \frac{\gamma^2}{4\omega_0^2}\cos^2(\omega_0t + \phi)\right] \quad \text{(neglecting the small term } \frac{\gamma}{\omega_0}\sin(\omega_0t + \phi)\cos(\omega_0t + \phi)\right]$$

$$\approx \frac{1}{2}mA_0^2\omega_0^2e^{-\gamma t} \quad \text{(since } \frac{\gamma^2}{4\omega_0^2} \text{ is very small)}$$

$$= E_0e^{-\gamma t} \quad \text{where } E_0 = \frac{1}{2}mA_0^2\omega_0^2 \text{ is the initial energy at } t = 0$$

We can also define the time constant τ as the time it takes for the energy to decrease to $\frac{1}{e}$ of its initial value:

$$\tau = \frac{1}{\gamma} \tag{1.21}$$

So we have, for very light damping:

$$E(t) = E_0 e^{-\gamma t} = E_0 e^{-\frac{t}{\tau}}$$
(1.22)

Definiton 1.1.4.2 (Rate of Energy Loss). Taking the time derivative of the total mechanical energy E(t):

$$\frac{dE}{dt} = \frac{d}{dt} \left(\frac{1}{2} m \dot{x}^2 + \frac{1}{2} k x^2 \right)$$
$$= (ma + kx) \dot{x}$$

For a undamped harmonic oscillator, ma + kx = 0, so $\frac{dE}{dt} = 0$, indicating that the total mechanical energy is conserved and obeys Hooke's law completely. However, for a damped harmonic oscillator, $ma + kx = -b\dot{x}$, leading to:

$$\frac{dE}{dt} = -b\dot{x}^2\tag{1.23}$$

Definition 1.1.4.3 (Quality Factor (Q-Factor)). The quality factor Q is a dimensionless parameter that characterizes the damping of a harmonic oscillator. It is defined as:

$$Q = \frac{\omega}{\gamma} = \omega \tau \tag{1.24a}$$

And for very light damping, we can approximate $\omega \approx \omega_0$, leading to:

$$Q \approx \frac{\omega_0}{\gamma} = \omega_0 \tau \tag{1.24b}$$

This allows us to rewrite the equation of a damped harmonic oscillator as:

$$\ddot{x} + \frac{\omega_0}{Q}\dot{x} + \omega_0^2 x = 0 \tag{1.25}$$

and:

$$\omega = \omega_0 \sqrt{1 - \frac{1}{4Q^2}} \tag{1.26}$$

We can also consider the ratio between the energy at one time and the energy one period later:

$$\frac{E(t+T)}{E(t)} = \frac{E_0 e^{-\gamma(t+T)}}{E_0 e^{-\gamma t}}$$
$$= e^{-\gamma T} \approx 1 - \gamma T$$
$$\frac{E(t+T) - E(t)}{E(t)} \approx -\gamma T = -\frac{2\pi}{\omega_0} \gamma = -\frac{2\pi}{Q}$$

Example 1.1.4.4. What is the number of radians through which the damped system oscillates as its energy decreases to 1/e of its initial value?

We have

$$\frac{E}{E_0} = e^{-\gamma t} = \frac{1}{e} \implies \gamma t = 1 \implies t = \frac{1}{\gamma} = \tau$$

So the number of radians is

$$\theta = \omega \tau = \frac{\omega}{\gamma} = Q$$

1.1.5 Undamped Forced Oscillations

We examine steady-state response to sinusoidal driving without losses and identify resonance behavior.

Definition 1.1.5.1 (Undamped Forced Oscillations). Consider a driver force acting on the mass-spring system; the ODE becomes:

$$m\ddot{x} + kx = \eta \tag{1.27}$$

where $\eta = F_0 \cos(\omega t)$ is the driving force with amplitude F_0 and angular frequency ω . The steady-state particular solution is:

$$x(t) = A(\omega)\cos(\omega t - \delta) \tag{1.28}$$

To derive $A(\omega)$ and δ , use the equation of motion:

$$A(\omega)(-\omega^2 + \omega_0^2)\cos(\delta) = \omega_0^2 a$$

where $a = \frac{F_0}{k}$ is the static displacement of the mass when the driving force is constant. We also have:

$$A(\omega)(-\omega^2 + \omega_0^2)\sin(\delta) = 0$$

Now, consider the case when $\delta = 0$, we have:

$$A(\omega) = \frac{\omega_0^2 a}{\omega_0^2 - \omega^2} \tag{1.29}$$

and the case where $\delta = \pi$, we have:

$$A(\omega) = -\frac{\omega_0^2 a}{\omega_0^2 - \omega^2} \tag{1.30}$$

Observe, when $\omega \approx \omega_0$, the amplitude $A(\omega)$ becomes very large, indicating resonance. At resonance, the system oscillates with maximum amplitude, which can lead to significant energy transfer from the driving force to the oscillator.

1.1.6 Damped Forced Oscillations

We add damping to the driven case, derive the frequency response amplitude and phase, and study bandwidth and Q.

Definition 1.1.6.1 (Damped Forced Oscillations). Consider a damped harmonic oscillator subjected to an external driving force. It is described by the following differential equation:

$$m\ddot{x} + b\dot{x} + kx = F_0 \cos(\omega t) \tag{1.31}$$

where F_0 is the amplitude of the driving force, ω is the angular frequency of the driving force, b is the damping coefficient, m is the mass, and k is the spring constant. The general solution to this non-homogeneous differential equation is given by:

$$x(t) = A(\omega)\cos(\omega t - \delta) \tag{1.32}$$

and the amplitude $A(\omega)$ is given by:

$$A(\omega) = \frac{\omega_0^2 a}{\sqrt{\omega^2 \gamma^2 + (\omega^2 - \omega_0^2)^2}}$$
 (1.33)

We can derive the following 4 cases:

- 1. No Damping $(\gamma = 0)$: In this case, the amplitude $A(\omega)$ simplifies to the undamped case we discussed earlier.
- 2. Low-Frequency Limit ($\omega \ll \omega_0$): In this limit, the amplitude $A(\omega)$ approaches the static displacement $a = \frac{F_0}{k}$. This means that at very low frequencies, the system behaves like a static spring, and the mass is displaced by an amount proportional to the applied force.
- 3. **High-Frequency Limit** ($\omega \gg \omega_0$): In this limit, the amplitude $A(\omega)$ decreases with increasing frequency, following the relation $A(\omega) \approx \frac{\omega_0^2 a}{\omega^2}$. This indicates that at very high frequencies, the mass cannot respond quickly enough to the rapidly oscillating driving force, resulting in a smaller amplitude of oscillation.

4. **Resonance** ($\omega \approx \omega_0$): At resonance, the amplitude $A(\omega)$ reaches its maximum value but it does not become infinite due to the presence of damping:

$$A_{\text{max}} = \frac{\omega_0^2 a}{\omega_0 \gamma} = \frac{\omega_0 a}{\gamma} = Qa \tag{1.34}$$

We also have the phase shift δ given by:

$$\tan(\delta) = \frac{\omega \gamma}{\omega_0^2 - \omega^2} \tag{1.35}$$

The phase shift δ indicates how much the oscillation of the mass lags behind the driving force. The behavior of δ can be summarized as follows:

- At low frequencies ($\omega \ll \omega_0$), δ approaches 0, meaning the mass oscillates in phase with the driving force.
- At resonance $(\omega = \omega_0)$, $\delta = \frac{\pi}{2}$, indicating that the mass oscillates a quarter cycle behind the driving force.
- At high frequencies $(\omega \gg \omega_0)$, δ approaches π , meaning the mass oscillates out of phase with the driving force.

Definition 1.1.6.2 (Power absorbed during forced oscillations). We can calculate the velocity of the oscillator:

$$\dot{x}(t) = -\omega A(\omega)\sin(\omega t - \delta) = -v_0\sin(\omega t - \delta) \tag{1.36}$$

where $v_0 = \omega A(\omega)$ is the maximum speed of the oscillator. Energy is lost at the following rate:

$$P(t) = bv(t)^2 \tag{1.37}$$

Substituteing the expression for v(t) into the power equation gives:

$$P(t) = bv_0^2 \sin^2(\omega t - \delta)$$

The average power $\langle P \rangle$ over one complete cycle of the driving force is given by:

$$\bar{P}(\omega) = \frac{bv_0^2}{2} = \frac{\omega^2 F_0^2 \gamma}{2m \left[(\omega^2 - \omega_0^2)^2 + \omega^2 \gamma^2 \right]}$$
(1.38)

If the driving frequency ω is close to ω_0 , use $\omega^2 - \omega_0^2 \approx 2\omega_0\Delta\omega$ with $\Delta\omega = \omega - \omega_0$ to get the Lorentzian form:

$$\bar{P}(\omega) \approx \frac{\omega_0 F_0^2}{2m\gamma \left[1 + \left(\frac{2\Delta\omega}{\gamma}\right)^2\right]} \tag{1.39}$$

The maximum average power occurs at resonance:

$$\bar{P}_{\text{max}} = \frac{\omega_0 F_0^2}{2m\gamma} \tag{1.40}$$

Average Power vs Driving Frequency for Different Quality Factors, Power normalized to $P_{\rm max}=1$




Figure 1.1: Average Power vs Driving Frequency for Different Quality Factors

Full Width Half Height The graph of $\bar{P}(\omega)$ versus ω has a peak at $\omega = \omega_0$ with a maximum value of \bar{P}_{max} . The full width at half maximum (FWHM) is the width of the peak at half of its maximum height. The FWHM is given by:

$$\omega_{\text{FWHM}} = 2\Delta\omega = 2\gamma = \frac{2\omega_0}{Q} \tag{1.41}$$

To illustrate the graph, we can plot $\bar{P}(\omega)$ versus ω for different values of the quality factor Q:

1.1.7 Simple Pendulum

Consider the arc length s of a pendulum bob, we have:

$$s = l\theta \quad m\ddot{s} = -mg\sin(\theta) \tag{1.42}$$

For small angles, we can approximate $\sin(\theta) \approx \theta$, leading to:

$$\ddot{\theta} + \frac{g}{l}\theta = 0 \tag{1.43}$$

And the ODE has solution:

$$\theta(t) = \theta_0 \cos(\omega t + \phi) \tag{1.44}$$

Energy For small angle θ , the total mechanical energy E of the pendulum is given by:

$$E = K + U = \frac{1}{2}ml^2\dot{\theta}^2 + mgl(1 - \cos(\theta)) \approx \frac{1}{2}ml^2\dot{\theta}^2 + \frac{1}{2}mgl\theta^2$$
 (1.45)

This shows that the pendulum behaves like a simple harmonic oscillator with an effective spring constant $k = \frac{mg}{I}$.

The physical pendulum For a rigid body swinging about a pivot point, the equation of motion is given by:

$$I\ddot{\theta} = \tau \tag{1.46}$$

For simple rod of length L and mass m pivoted at one end, the moment of inertia about the pivot point is $I = \frac{1}{3}mL^2$. The torque due to gravity when the rod is displaced by an angle θ from the vertical is $\tau = -mg\frac{L}{2}\sin(\theta)$. For small angles, we can approximate $\sin(\theta) \approx \theta$, leading to:

$$\ddot{\theta} + \frac{3g}{2L}\theta = 0\tag{1.47}$$

And the small angle approximates leads to:

$$\ddot{\theta} + \omega^2 \theta = 0 \tag{1.48}$$

where $\omega = \sqrt{\frac{3g}{2L}}$. The solution to this ODE is:

$$\theta(t) = \theta_0 \cos(\omega t + \phi) \tag{1.49}$$

The angular frequency of oscillation for the physical pendulum is:

$$\omega = \sqrt{\frac{3g}{2L}} \tag{1.50}$$

The LC Circuit An LC circuit consists of an inductor L and a capacitor C connected in series. The charge q(t) on the capacitor satisfies the differential equation:

$$L\frac{d^2q}{dt^2} + \frac{1}{C}q = 0 (1.51)$$

This is analogous to the equation of motion for a simple harmonic oscillator, with the angular frequency given by:

$$\omega = \frac{1}{\sqrt{LC}} \tag{1.52}$$

The RLC Circuit An RLC circuit consists of a resistor R, inductor L, and capacitor C connected in series. The charge q(t) on the capacitor satisfies the differential equation:

$$L\frac{d^2q}{dt^2} + R\frac{dq}{dt} + \frac{1}{C}q = 0 {(1.53)}$$

This is analogous to the resistor behaving as a damped harmonic oscillator, with the angular frequency given by:

$$\omega = \sqrt{\frac{1}{LC} - \left(\frac{R}{2L}\right)^2} \tag{1.54}$$

The following are equations that summarize the analogies between mechanical and electrical oscillators:

Mechanical Oscillator	Electrical Oscillator	Analogy
Mass m	Inductance L	Inertia
Spring constant k	Inverse capacitance $\frac{1}{C}$	Restoring force
Damping coefficient b	Resistance R	Energy dissipation
Displacement x	Charge q	Position
Velocity \dot{x}	Current $I = \frac{dq}{dt}$	Rate of change of position
Force F	Voltage V	Driving force

Table 1.1: Analogies between Mechanical and Electrical Oscillators

1.1.8 Coupled Oscillators

Definition 1.1.8.1 (Coupled Oscillators). Consider two masses m_1 and m_2 on two pendulum connected by springs with spring constant k. The equations of motion for the two masses are given by:

$$\begin{cases} \ddot{x}_1 &= -\frac{g}{L}x_1 + \frac{k}{m_1}(x_1 - x_2) & (a) \\ \ddot{x}_2 &= -\frac{g}{L}x_2 - \frac{k}{m_2}(x_1 - x_2) & (b) \end{cases}$$
 (1.55)

where x_1 and x_2 are the displacements of masses m_1 and m_2 from their equilibrium positions, respectively. Now if we add and subtract the two equations, we get:

$$\begin{cases} \ddot{x}_1 + \ddot{x}_2 &= -\frac{g}{L}(x_1 + x_2) \quad (c) \\ \ddot{x}_1 - \ddot{x}_2 &= -\left(\frac{g}{L} + \frac{k}{m_1} + \frac{k}{m_2}\right)(x_1 - x_2) \quad (d) \end{cases}$$

Let:

$$q_1 = x_1 + x_2$$
 and $q_2 = x_1 - x_2$

also, we let:

$$\omega_1 = \sqrt{\frac{g}{L}}$$
 and $\omega_2 = \sqrt{\frac{g}{L} + \frac{k}{m_1} + \frac{k}{m_2}}$

Then, the equations of motion can be rewritten as:

$$\begin{cases} \ddot{q}_1 &= -\omega_1^2 q_1 \\ \ddot{q}_2 &= -\omega_2^2 q_2 \end{cases}$$

Observe that q_1 and q_2 are decoupled, and each behaves like a simple harmonic oscillator with angular frequencies ω_1 and ω_2 , respectively. The general solutions for $q_1(t)$ and $q_2(t)$ are:

$$\begin{cases} q_1(t) = A_1 \cos(\omega_1 t + \phi_1) \\ q_2(t) = A_2 \cos(\omega_2 t + \phi_2) \end{cases}$$
 (1.56)

where A_1, A_2, ϕ_1 , and ϕ_2 are constants determined by the initial conditions. Finally, we can expressions for $x_1(t)$ and $x_2(t)$ in terms of $q_1(t)$ and $q_2(t)$:

$$\begin{cases} x_1(t) &= \frac{q_1(t) + q_2(t)}{2} = \frac{A_1}{2} \cos(\omega_1 t + \phi_1) + \frac{A_2}{2} \cos(\omega_2 t + \phi_2) \\ x_2(t) &= \frac{q_1(t) - q_2(t)}{2} = \frac{A_1}{2} \cos(\omega_1 t + \phi_1) - \frac{A_2}{2} \cos(\omega_2 t + \phi_2) \end{cases}$$
(1.57)

All parts of the system oscillate with the same normal frequency (eigenvalue) in a normal mode (eigenvector).

Definition 1.1.8.2 (Normal Modes). A **normal mode** is a natural pattern of oscillation in which every part of the system moves in sync with a single frequency.

For the two-mass pendulum system, there are two normal modes:

• In-phase mode (ω_1): both masses swing together, reaching maximum displacement on the same side at the same time.

$$x_1 = x_2$$

• Out-of-phase mode (ω_2): the two masses swing in opposite directions, so when one moves left, the other moves right.

$$x_1 = -x_2$$

Any general motion of the system can be written as a combination (superposition) of these two normal modes.

Energy in Coupled Oscillators The total mechanical energy E of the coupled oscillator system is given by:

$$E = \frac{1}{2}m_1\dot{x}_1^2 + \frac{1}{2}m_2\dot{x}_2^2 + \frac{1}{2}k(x_1 - x_2)^2 + \frac{1}{2}m_1\frac{g}{L}x_1^2 + \frac{1}{2}m_2\frac{g}{L}x_2^2$$
 (1.58)

Substituting the expressions for $x_1 = \frac{q_1 + q_2}{2}$ and $x_2 = \frac{q_1 - q_2}{2}$ into the energy equation, two independent energies terms for q_1 and q_2 emerge:

$$E = \left[\frac{1}{4} m \dot{q}_1^2 + \frac{1}{4} \frac{m_1 g}{L} q_1^2 \right] + \left[\frac{1}{4} m \dot{q}_2^2 + \frac{1}{4} \frac{m_2 g}{L} q_2^2 \right]$$
 (1.59)

This shows that the total energy is the sum of the energies associated with each normal mode, and that no cross term between the modes exists. Thus energy does not flow from one mode to another.

Example 1.1.8.3. Given two coupled pendulums with $x_0(0) = A$, $x_1(0) = 0$, and both masses at rest initially, we have:

$$q_0(t) = C_0 \cos(\omega_0 t)$$

$$q_1(t) = C_1 \cos(\omega_1 t)$$

where C_0 and C_1 are constants determined by the initial conditions. Using the initial conditions. Using the cosine addition formula, which is:

$$\cos(A) + \cos(B) = 2\cos\left(\frac{A+B}{2}\right)\cos\left(\frac{A-B}{2}\right)$$
$$\cos(A) - \cos(B) = -2\sin\left(\frac{A+B}{2}\right)\sin\left(\frac{A-B}{2}\right)$$

we can express the motion of each pendulum as:

$$x_0(t) = \frac{q_0 + q_1}{2} = A\cos\left(\frac{\omega_0 + \omega_1}{2}t\right)\cos\left(\frac{\omega_0 - \omega_1}{2}t\right)$$
$$x_1(t) = \frac{q_0 - q_1}{2} = A\sin\left(\frac{\omega_0 + \omega_1}{2}t\right)\sin\left(\frac{\omega_0 - \omega_1}{2}t\right)$$

Due to the formula for the product of cosines and sines, we see that energy oscillates between the two pendulums with a beat frequency of $\frac{\omega_1-\omega_0}{2}$. The time for all the energy to transfer from one pendulum to the other is given by:

$$T = \frac{2\pi}{\frac{\omega_1 - \omega_0}{2}} = \frac{4\pi}{\omega_1 - \omega_0}$$

1.1.9 Normal Modes

Oscilating Masses Connected by Springs Consider two masses $m_1 = m_2 = m$ connected by three spring with spring constant k and fixed to walls on either side. The equations of motion for the two masses are given by:

$$\begin{cases}
m\ddot{x}_1 &= -kx_1 + k(x_2 - x_1) & (a) = m\ddot{x}_1 = -2kx_1 + kx_2 \\
m\ddot{x}_2 &= -kx_2 - k(x_2 - x_1) & (b) = m\ddot{x}_2 = kx_1 - 2kx_2
\end{cases}$$
(1.60)

To solve these equations, we assume solutions of the form:

$$\begin{cases} x_1(t) &= A\cos(\omega t + \phi) \\ x_2(t) &= B\cos(\omega t + \phi) \end{cases}$$

Substituting these assumed solutions into the equations of motion, we get:

$$\begin{cases} \frac{A}{B} &= \frac{k}{m\omega^2 - 2k} \\ \frac{A}{B} &= \frac{m\omega^2 - 2k}{k} \end{cases}$$
 (1.61)

We can deduce that $A = \pm B$ We can set the equation:

$$(m\omega^2 - 2k)^2 = k^2 \implies m\omega^2 - 2k = \pm k$$

So we can derive two normal mode frequencies:

$$\begin{cases} \omega_1 &= \sqrt{\frac{k}{m}} & \text{(in-phase mode)} \\ \omega_2 &= \sqrt{\frac{3k}{m}} & \text{(out-of-phase mode)} \end{cases}$$
 (1.62)

Solving as an Eigenproblem Alternatively, we can create a system of equations from (1.61):

$$\begin{bmatrix} \frac{2k}{m} & -\frac{k}{m} \\ -\frac{k}{m} & \frac{2k}{m} \end{bmatrix} \begin{bmatrix} A \\ B \end{bmatrix} = \omega^2 \begin{bmatrix} A \\ B \end{bmatrix}$$
 (1.63)

To find the eigenvalues ω^2 , we solve the characteristic equation:

$$\det\left(\begin{bmatrix} \frac{2k}{m} - \omega^2 & -\frac{k}{m} \\ -\frac{k}{m} & \frac{2k}{m} - \omega^2 \end{bmatrix}\right) = 0$$

Calculating the determinant, we have:

$$\left(\frac{2k}{m} - \omega^2\right)^2 - \left(-\frac{k}{m}\right)^2 = 0$$

Expanding and simplifying, we get:

$$\omega^4 - \frac{4k}{m}\omega^2 + \frac{5k^2}{m^2} = 0$$

This gives us the two normal mode frequencies:

$$\begin{cases} \omega_1^2 &= \frac{k}{m} \implies \omega_1 = \sqrt{\frac{k}{m}} \\ \omega_2^2 &= \frac{3k}{m} \implies \omega_2 = \sqrt{\frac{3k}{m}} \end{cases}$$
 (1.64)

Example 1.1.9.1. CConsider two equal masses m suspended from identical springs of spring constant k. The masses are hanged on the celing. We can solve this system's frequency via the eigenvalue method. The equations of motion are:

$$\begin{cases}
 m\ddot{x}_2 &= -k(x_2 - x_1) \\
 m\ddot{x}_1 &= -kx_1 + k(x_2 - x_1) = -2kx_1 + kx_2
\end{cases}$$

Assume solutions of the form:

$$\begin{cases} x_1(t) = A\cos(\omega t + \phi) \\ x_2(t) = B\cos(\omega t + \phi) \end{cases}$$

Substituting these assumed solutions into the equations of motion, we get:

$$\begin{cases}
-A\omega^2 &= -\frac{k}{m}(-2A+B) \\
-B\omega^2 &= -\frac{k}{m}(A-B)
\end{cases}$$

We can rewrite this as an eigenvalue problem:

$$\begin{bmatrix} \frac{2k}{m} & -\frac{k}{m} \\ -\frac{k}{m} & \frac{k}{m} \end{bmatrix} \begin{bmatrix} A \\ B \end{bmatrix} = \omega^2 \begin{bmatrix} A \\ B \end{bmatrix}$$

To find the eigenvalues ω^2 , we solve the characteristic equation:

$$\det\left(\begin{bmatrix} \frac{2k}{m} - \omega^2 & -\frac{k}{m} \\ -\frac{k}{m} & \frac{k}{m} - \omega^2 \end{bmatrix}\right) = 0$$

Calculating the determinant, we have:

$$\omega^2 = \frac{k}{2m}(3 \pm \sqrt{5})$$

Example 1.1.9.2. Consider three equal masses m connected by four identical springs with spring constant k and fixed to walls on either side. The equations of motion for the three masses are given by:

$$\begin{cases} m\ddot{x}_1 &= -2kx_1 + kx_2 \\ m\ddot{x}_2 &= -2kx_2 + kx_1 + kx_3 \\ m\ddot{x}_3 &= -2kx_3 + kx_2 \end{cases}$$

Assume solutions of the form:

$$\begin{cases} x_1(t) &= A\cos(\omega t + \phi) \\ x_2(t) &= B\cos(\omega t + \phi) \\ x_3(t) &= C\cos(\omega t + \phi) \end{cases}$$

Substituting these assumed solutions into the equations of motion, we get:

$$\begin{cases} A\omega^2 &= -\frac{k}{m}(-2A+B) \\ B\omega^2 &= -\frac{k}{m}(A-2B+C) \\ C\omega^2 &= -\frac{k}{m}(B-2C) \end{cases}$$

We can rewrite this as an eigenvalue problem:

$$\begin{bmatrix} -\frac{2k}{m} & \frac{k}{m} & 0\\ \frac{k}{m} & -\frac{2k}{m} & \frac{k}{m}\\ 0 & \frac{k}{m} & -\frac{2k}{m} \end{bmatrix} \begin{bmatrix} A\\ B\\ C \end{bmatrix} = \omega^2 \begin{bmatrix} A\\ B\\ C \end{bmatrix}$$

To find the eigenvalues ω^2 , we solve the characteristic equation:

$$\det \left(\begin{bmatrix} -\frac{2k}{m} - \omega^2 & \frac{k}{m} & 0\\ \frac{k}{m} & -\frac{2k}{m} - \omega^2 & \frac{k}{m} \\ 0 & \frac{k}{m} & -\frac{2k}{m} - \omega^2 \end{bmatrix} \right) = 0$$

Calculating the determinant, we have:

$$\left(\frac{2k}{m} - \omega^2\right) \left[\left(-\frac{2k}{m} - \omega^2 \right)^2 - \left(\frac{k}{m} \right)^2 \right] - \left(\frac{k}{m} \right)^2 \left(\frac{2k}{m} - \omega^2 \right) = 0$$

This gives us the three normal mode frequencies:

$$\begin{cases} \omega_1 &= \sqrt{\frac{2k}{m}} \\ \omega_2 &= \sqrt{\frac{2k}{m}(2 - \sqrt{2})} \\ \omega_3 &= \sqrt{\frac{2k}{m}(2 + \sqrt{2})} \end{cases}$$

Intuition For any perturbation, we can expressed it as a linear combination of the excitations of several normal modes. Each normal mode oscillates at its own frequency, and the overall motion is a superposition of these modes.

1.2 Waves

1.2.1 Travelling Waves

Definition 1.2.1.1 (Travelling Pulse). A travelling pulse is a disturbance that moves through a medium. For any wave function f(x,t), if it satisfies the property:

$$y(x,t) = f(x \pm vt) \tag{1.65}$$

then it represents a wave travelling in the positive (for x - vt) or negative (for x + vt) x-direction with speed v. y could represent displacement, pressure, electric field, etc.

Definition 1.2.1.2 (Sinusoidal Wave). A sinusoidal wave is a wave that can be described by a sine or cosine function. The general form of a sinusoidal wave travelling in the positive x-direction is:

$$y(x,t) = A\cos(kx \pm \omega t + \phi_0) \tag{1.66}$$

where:

- A is the amplitude (maximum displacement)
- $k = \frac{2\pi}{\lambda}$ is the wave number, with λ being the wavelength
- $\omega = 2\pi f$ is the angular frequency, with f being the frequency
- ϕ_0 is the initial phase.

So we can write the wave function as a form of (1.65):

$$y(x,t) = A\cos\left[k(x \pm vt) + \phi_0\right] \tag{1.67}$$

The wave speed v is related to the angular frequency and wave number by:

$$v = \frac{\omega}{k} = f\lambda \tag{1.68}$$

Transverse and Longitudinal Waves There is two (or three) main categories of waves:

- Transverse Waves: In transverse waves, the oscillations are perpendicular to the direction of wave propagation.

 (Examples) Light waves, water waves, and waves on a string.
- Longitudinal Waves: In longitudinal waves, the oscillations are parallel to the direction of wave propagation.

 (Examples) Sound waves and pressure waves in fluids.
- Both: Some waves can exhibit both transverse and longitudinal characteristics. (Examples) Rayleigh surface waves in seismology.

Definition 1.2.1.3 (Velocity of a Fixed Particle). For a fixed particle, we have:

$$v_y = \frac{\partial y}{\partial t} = A\omega \cos(kx \pm \omega t + \phi_0) \tag{1.69}$$

Example 1.2.1.4 (Vibrating String). Consider a string in the xy-plane, stretched along the x-axis with tension τ and linear mass density μ . Now, consider at the end of the string at x makes a small angle θ with the x-axis. Then the components of the tension are:

$$\begin{cases} \tau_x &= \tau \cos(\theta) \approx \tau \\ \tau_y &= \tau \sin(\theta) \approx \tau \frac{\partial y}{\partial x} \end{cases}$$

Now, consider a small segment of the string between x and $x + \delta x$. The vetical force on the other end is given, via linear approximation, by:

$$\tau_y(x + \delta x) \approx \tau_y(x) \left[\frac{\partial y}{\partial x} + \frac{\partial^2 y}{\partial x^2} \delta x \right]$$

So the net force is given by:

$$F_y = \tau_y(x + \delta x) - \tau_y(x) = \tau \frac{\partial^2 y}{\partial x^2} \delta x$$

Becuase F = ma, we have:

$$\tau \frac{\partial^2 y}{\partial x^2} \delta x = dm \frac{\partial^2 y}{\partial t^2}$$

where $dm = \mu \delta x$ is the mass of the small segment. Thus, we have:

$$\frac{\partial^2 y}{\partial t^2} - v^2 \frac{\partial^2 y}{\partial r^2} = 0$$

where $v = \sqrt{\frac{\tau}{\mu}}$ is the wave speed on the string. This is the one-dimensional wave equation.

1.2.2 The Wave Equation

Definition 1.2.2.1 (The Wave Equation). The wave equation is a second-order linear partial differential equation that describes the propagation of waves (sound, EM, water). In one dimension, it is:

$$\frac{\partial^2 u}{\partial t^2} - c^2 \frac{\partial^2 u}{\partial x^2} = 0 \tag{1.70}$$

where u(x,t) is the disturbance, c is the wave speed, x is position, and t is time.

Chapter 2

Modern Physics