


Ch. 1 – Overview and Descriptive Statistics







xkcd.com

Example 1 – Concrete Strength Data

The following measurements of flexural strength (in MPa) were taken from 27 specimens of high-performance concrete obtained by using superplasticizers and certain binders¹:


5.9, 7.2, 7.3, 6.3, 8.1, 6.8, 7.0, 7.6, 6.8, 6.5, 7.0, 6.3, 7.9, 9.0, 8.2, 8.7, 7.8, 9.7, 7.4, 7.7, 9.7, 7.8, 7.7, 11.6, 11.3, 11.8, 10.7

- How can we visualize this distribution?
- How can we quantify the center of the distribution?
- How can we quantify the spread of the distribution?

¹From "Effects of Aggregates and Microfillers on the Flexural Properties of Concrete", **Magazine of Concrete Research**, 1997: 81–98


Dotplot

One simple method of visualization is a **dotplot** (or strip chart). The 27 observations are simply plotted on a line:




Dotplot

One simple method of visualization is a **dotplot** (or strip chart). The 27 observations are simply plotted on a line:



Identical values may be represented by stacking the dots:



Measures of center: Sample Mean and Median

• The sample mean:

$$\overline{x} = \frac{1}{n} \sum_{i=1}^{n} x_i = \frac{x_1 + \dots + x_n}{n}$$

Measures of center: Sample Mean and Median

1 The sample mean:

$$\overline{x} = \frac{1}{n} \sum_{i=1}^{n} x_i = \frac{x_1 + \dots + x_n}{n}$$

3 The **sample median**: Sort the data from smallest to largest. If n is odd, then the sample median \tilde{x} is the middle observation in the list; if n is even, then \tilde{x} is the average of the two middle observations. Explicitly, if $x_1 \leq x_2 \leq \cdots \leq x_n$,

$$\tilde{x} = egin{cases} x_{(n+1)/2} & \text{if } n \text{ is odd} \\ rac{1}{2}(x_{n/2} + x_{n/2+1}) & \text{if } n \text{ is even} \end{cases}$$

Measures of center: Sample Mean and Median

• The sample mean:

$$\overline{x} = \frac{1}{n} \sum_{i=1}^{n} x_i = \frac{x_1 + \dots + x_n}{n}$$

② The **sample median**: Sort the data from smallest to largest. If n is odd, then the sample median \tilde{x} is the middle observation in the list; if n is even, then \tilde{x} is the average of the two middle observations. Explicitly, if $x_1 \leq x_2 \leq \cdots \leq x_n$,

$$\tilde{x} = \begin{cases} x_{(n+1)/2} & \text{if } n \text{ is odd} \\ \frac{1}{2}(x_{n/2} + x_{n/2+1}) & \text{if } n \text{ is even} \end{cases}$$

For example, given data 2, 3, 9, 11, 15, 17 we would have

Sample mean:
$$\overline{x}=\frac{1}{6}(2+3+9+11+15+17)=9.5$$
 Sample median: $\widetilde{x}=\frac{1}{2}(9+11)=10$

The sample mean and sample median for the strength data are $\overline{x}=8.14,\ \tilde{x}=7.7.$



- The mean may be strongly influenced by a few extreme observations, whereas the median is robust against such influence.
- If the largest measurement 11.8 were replaced 118, then the mean would increase to $\overline{x} = 12.07$, while the median would remain $\tilde{x} = 7.7$.

• If the median is robust but the mean isn't, why use the mean?

- If the median is robust but the mean isn't, why use the mean?
- In many cases, the mean is more **efficient** than the median: it achieves greater accuracy with a smaller sample size.

- If the median is robust but the mean isn't, why use the mean?
- In many cases, the mean is more **efficient** than the median: it achieves greater accuracy with a smaller sample size.
- To address the mean's sensitivity to outliers, we may carefully check in advance to screen out any bad data.

- If the median is robust but the mean isn't, why use the mean?
- In many cases, the mean is more **efficient** than the median: it achieves greater accuracy with a smaller sample size.
- To address the mean's sensitivity to outliers, we may carefully check in advance to screen out any bad data.
- To achieve a balanced tradeoff between efficiency and robustness, there are hybrid approaches such as a **trimmed mean**, e.g., discarding the top 10% and bottom 10% and then taking the mean of the remaining data.

- If the median is robust but the mean isn't, why use the mean?
- In many cases, the mean is more **efficient** than the median: it achieves greater accuracy with a smaller sample size.
- To address the mean's sensitivity to outliers, we may carefully check in advance to screen out any bad data.
- To achieve a balanced tradeoff between efficiency and robustness, there are hybrid approaches such as a **trimmed mean**, e.g., discarding the top 10% and bottom 10% and then taking the mean of the remaining data.
- We'll discuss these issues in Chapter 6 (Point Estimation).

Measure of Spread: Sample variance

The **sample variance** is

$$s^{2} = \frac{1}{n-1} \sum_{i=1}^{n} (x_{i} - \overline{x})^{2} = \frac{(x_{1} - \overline{x})^{2} + \dots + (x_{n} - \overline{x})^{2}}{n-1}$$

Measure of Spread: Sample variance

The sample variance is

$$s^{2} = \frac{1}{n-1} \sum_{i=1}^{n} (x_{i} - \overline{x})^{2} = \frac{(x_{1} - \overline{x})^{2} + \dots + (x_{n} - \overline{x})^{2}}{n-1}$$

The **sample standard deviation** is the square root of the sample variance:

$$s = \sqrt{\frac{1}{n-1}\sum_{i=1}^{n}(x_i - \overline{x})^2} = \sqrt{\frac{(x_1 - \overline{x})^2 + \dots + (x_n - \overline{x})^2}{n-1}}$$

Measure of Spread: Sample variance

The sample variance is

$$s^2 = \frac{1}{n-1} \sum_{i=1}^{n} (x_i - \overline{x})^2 = \frac{(x_1 - \overline{x})^2 + \dots + (x_n - \overline{x})^2}{n-1}$$

The **sample standard deviation** is the square root of the sample variance:

$$s = \sqrt{\frac{1}{n-1}\sum_{i=1}^{n}(x_i - \overline{x})^2} = \sqrt{\frac{(x_1 - \overline{x})^2 + \dots + (x_n - \overline{x})^2}{n-1}}$$

Like the mean, the sample variance and sample standard deviation may be strongly influenced by extreme observations.

• Separate the data into the smaller half and larger half. (Include the median \tilde{x} in both halves if n is odd.)

- Separate the data into the smaller half and larger half. (Include the median \tilde{x} in both halves if n is odd.)
- The median of the smaller half is called the **lower fourth**.

- Separate the data into the smaller half and larger half. (Include the median \tilde{x} in both halves if n is odd.)
- The median of the smaller half is called the **lower fourth**.
- The median of the larger half is called the **upper fourth**.

- Separate the data into the smaller half and larger half. (Include the median \tilde{x} in both halves if n is odd.)
- The median of the smaller half is called the lower fourth.
- The median of the larger half is called the **upper fourth**.
- Their difference is called the **fourth spread** f_s :

$$f_s = \text{upper forth} - \text{lower fourth}$$

- Separate the data into the smaller half and larger half. (Include the median \tilde{x} in both halves if n is odd.)
- The median of the smaller half is called the lower fourth.
- The median of the larger half is called the **upper fourth**.
- Their difference is called the **fourth spread** f_s :

$$f_s = \text{upper forth} - \text{lower fourth}$$

Example: Given data 2,3,5,6,8,9,12,13,15 the median is $\tilde{x} = 8$, the lower fourth is 5, the upper fourth is 12, and the fourth spread is 7.

- Separate the data into the smaller half and larger half. (Include the median \tilde{x} in both halves if n is odd.)
- The median of the smaller half is called the **lower fourth**.
- The median of the larger half is called the **upper fourth**.
- Their difference is called the **fourth spread** f_s :

$$f_s = \text{upper forth} - \text{lower fourth}$$

Example: Given data 2,3,5,6,8,9,12,13,15 the median is $\tilde{x} = 8$, the lower fourth is 5, the upper fourth is 12, and the fourth spread is 7.

	Efficient	Robust
Measure of center	\overline{X}	$ ilde{x}$
Measure of spread	S	f_s


Five-number summary and Boxplot

The **five-number summary** consists of

- The minimum observation
- The lower fourth
- The median
- The upper fourth
- The maximum observation

For the concrete strength data:

This is shown graphically in a **boxplot**: The bottom and top of the box show the lower and upper fourths; the horizontal line inside the box shows the median; the whiskers (dotted lines) extend to the minimum and maximum observations.



Example 2 – Power Usage

Power companies need information about customer usage to obtain accurate forecasts of demands. Investigators from a power company determined energy consumption (in BTU) for a sample of 90 homes over a fixed time interval:

```
2.97, 4.00, 5.20, 5.56, 5.94, 5.98, 6.35, 6.62, 6.72, 6.78, 6.80, 6.85, 6.94, 7.15, 7.16, 7.23, 7.39, 7.62, 7.62, 7.69, 7.73, 7.87, 7.93, 8.00, 8.26, 8.29, 8.37, 8.47, 8.56, 8.58, 8.61, 8.67, 8.69, 8.81, 9.07, 9.27, 9.37, 9.43, 9.52, 9.58, 9.60, 9.76, 9.82, 9.83, 9.83, 9.84, 9.96, 10.04, 10.21, 10.28, 10.28, 10.30, 10.35, 10.36, 10.40, 10.49, 10.50, 10.64, 10.95, 11.09, 11.12, 11.21, 11.29, 11.43, 11.62, 11.70, 11.70, 12.16, 12.19, 12.28, 12.31, 12.62, 12.69, 12.71, 12.91, 12.92, 13.11, 13.38, 13.42, 13.43, 13.47, 13.60, 13.96, 14.24, 14.35, 15.12, 15.24, 16.06, 16.90, 18.26
```


Example 2 – Power Usage

The dotplot is less effective here: many dots are packed close together, making it difficult to see where the dots are most concentrated:



Histogram


A **histogram** is constructed by grouping the data into bins of equal width and counting the number of observations within each bin:



Here the bins are the intervals (0,2], (2,4], (4,6], (6,8], ..., (16,18], (18,20].

Normal Distribution


This histogram appears to be a fairly close fit to the symmetric, bell-shaped density curve of a **normal distribution**:



Normal distributions are very common in statistics and will be discussed in Chapter 4.

Weibull Distribution

In contrast, the concrete strength data appears asymmetric and does not seem to fit a normal distribution. A better fit is provided by a **Weibull distribution**.



Stem-and-leaf diagram

```
3
     269
     03678889
     2224667799
     03345666778
 9
     134456688888
10 I
     0023333445569
11 I
     11234677
12 I
     223367799
13 l
     144456
14
     023
15
     12
16
     19
17
18
     3
```

A **stem-and-leaf diagram** is constructed by grouping the data according to their first one or two digits (the **stem**), shown on the left part of the diagram, while the remaining digit (the **leaf**) is displayed on the right.

Here the first few measurements are 3.0, 4.0, 5.2, 5.6, 5.9, 6.0, 6.3, etc.

A stem-and-leaf diagram is similar to a "sideways" histogram. It is visually less appealing but provides more precise information about the data.

• A **population** is a group that we wish to study.

- A **population** is a group that we wish to study.
- A **sample** is an observed subset of a population.

- A **population** is a group that we wish to study.
- A **sample** is an observed subset of a population.
- A parameter is a quantity which describes a population, e.g., the population mean μ .

- A population is a group that we wish to study.
- A **sample** is an observed subset of a population.
- A parameter is a quantity which describes a population, e.g., the population mean μ .
- A **statistic** is a quantity computed from sample data, e.g., the sample mean \overline{x} .

- A population is a group that we wish to study.
- A sample is an observed subset of a population.
- A parameter is a quantity which describes a population, e.g., the population mean μ .
- A **statistic** is a quantity computed from sample data, e.g., the sample mean \overline{x} .
- **Statistical inference** is the method of drawing *probabilistic* conclusions about a population based on sample data.

- A population is a group that we wish to study.
- A **sample** is an observed subset of a population.
- A parameter is a quantity which describes a population, e.g., the population mean μ .
- A **statistic** is a quantity computed from sample data, e.g., the sample mean \overline{x} .
- **Statistical inference** is the method of drawing *probabilistic* conclusions about a population based on sample data.
 - A **confidence interval** gives a range of values in which we can expect a parameter to be, with a specific degree of confidence.


- A population is a group that we wish to study.
- A **sample** is an observed subset of a population.
- A parameter is a quantity which describes a population, e.g., the population mean μ .
- A **statistic** is a quantity computed from sample data, e.g., the sample mean \overline{x} .
- **Statistical inference** is the method of drawing *probabilistic* conclusions about a population based on sample data.
 - A **confidence interval** gives a range of values in which we can expect a parameter to be, with a specific degree of confidence.
 - A hypothesis test provides a way to test whether a particular theory is consistent with the data or not. We cannot be certain our conclusion is correct, but we can quantify the degree of uncertainty using probability.

• In the concrete strength data, based on 27 specimens, the sample mean was $\overline{x} = 8.14$.

- In the concrete strength data, based on 27 specimens, the sample mean was $\overline{x}=8.14$.
- If the process were repeated under the same conditions, creating a new sample of 27 specimens, the new sample may have a somewhat different sample mean.

- In the concrete strength data, based on 27 specimens, the sample mean was $\overline{x} = 8.14$.
- If the process were repeated under the same conditions, creating a new sample of 27 specimens, the new sample may have a somewhat different sample mean.
- The sample mean \overline{x} is only an estimate of the true **population mean** μ .

- In the concrete strength data, based on 27 specimens, the sample mean was $\overline{x} = 8.14$.
- If the process were repeated under the same conditions, creating a new sample of 27 specimens, the new sample may have a somewhat different sample mean.
- The sample mean \overline{x} is only an estimate of the true **population mean** μ .
- The accuracy of this estimate may be quantified using a **confidence interval**: In this case, given the sample of 27 specimens, we can say with 95% confidence that the population mean μ is between 7.51 and 8.77.



• Suppose a second method of producing high-strength concrete is tested: 30 specimens have a sample mean flexural strength of $\overline{y} = 8.90$, compared to $\overline{x} = 8.14$ for the original method.


- Suppose a second method of producing high-strength concrete is tested: 30 specimens have a sample mean flexural strength of $\overline{y} = 8.90$, compared to $\overline{x} = 8.14$ for the original method.
- Does the second method produce stronger concrete? Or could the difference be due to chance?

- Suppose a second method of producing high-strength concrete is tested: 30 specimens have a sample mean flexural strength of $\overline{y}=8.90$, compared to $\overline{x}=8.14$ for the original method.
- Does the second method produce stronger concrete? Or could the difference be due to chance?
- To answer this, we need to know the sample standard deviations of the two samples: $s_1 = 1.66$, $s_2 = 1.91$.

- Suppose a second method of producing high-strength concrete is tested: 30 specimens have a sample mean flexural strength of $\overline{y} = 8.90$, compared to $\overline{x} = 8.14$ for the original method.
- Does the second method produce stronger concrete? Or could the difference be due to chance?
- To answer this, we need to know the sample standard deviations of the two samples: $s_1 = 1.66$, $s_2 = 1.91$.
- The appropriate hypothesis test (two-sample t test) gives a P-value of .06, which means that if there is no difference in the population means of the two methods, there is only a 6% chance that the sample means \overline{x} and \overline{y} would differ by as much as they did.

- Suppose a second method of producing high-strength concrete is tested: 30 specimens have a sample mean flexural strength of $\overline{y} = 8.90$, compared to $\overline{x} = 8.14$ for the original method.
- Does the second method produce stronger concrete? Or could the difference be due to chance?
- To answer this, we need to know the sample standard deviations of the two samples: $s_1 = 1.66$, $s_2 = 1.91$.
- The appropriate hypothesis test (two-sample t test) gives a P-value of .06, which means that if there is no difference in the population means of the two methods, there is only a 6% chance that the sample means \overline{x} and \overline{y} would differ by as much as they did.
- This provides some evidence (but not strong evidence) that the second method outperforms the first in mean flexural strength.

Based on the histogram, we remarked that the concrete strength data did not appear to have a normal distribution. However, appearances can be misleading, especially in small samples.



A normality test (Shapiro-Wilk test) gives a P-value of .008, providing strong evidence that indeed the data is not normal.

- Ways to display the distribution of a numerical variable:
 - dotplot, boxplot, histogram, stem-and-leaf diagram

- Ways to display the distribution of a numerical variable:
 - dotplot, boxplot, histogram, stem-and-leaf diagram
- Measures of center: mean, median

- Ways to display the distribution of a numerical variable:
 - dotplot, boxplot, histogram, stem-and-leaf diagram
- Measures of center: mean, median
- Measures of spread: variance, standard deviation, fourth spread

- Ways to display the distribution of a numerical variable:
 - dotplot, boxplot, histogram, stem-and-leaf diagram
- Measures of center: mean, median
- Measures of spread: variance, standard deviation, fourth spread
- Statistical inference: using sample data to draw probabilistic conclusions about a broader population.