JESTER A/A+

AIR-TO-AIR COMBAT ENHANCEMENT



VERSION 1.0 · OCTOBER 2026



A fan-made guide for a community mod. Not an official publication of Heatblur Simulations, Eagle Dynamics or the US Air Force. The emblem is original artwork.

START READ THIS FIRST

OVERVIEW

Jester A/A+ is an add-on for the Heatblur F-4E's Jester AI. Stock Jester sweeps the radar on his own schedule and reacts to whatever it happens to paint. A/A+ gives Jester a *cue*, a bearing to search, instead of leaving him to sweep. He searches there, focuses what he finds, and keeps the radar on it until you take over.

It also cleans up how he handles locks and close-in fights, steps through bandits left to right, and mutes navigation and traffic chatter in a close fight.

This guide assumes you already know the F-4E radar and the context button. It covers what the mod changes and what it cannot do.

YOU WILL NEED

- The DCS F-4E with Jester's mod loader (the `mods\init` folder).
- Nothing else for the basic mod.
- Two optional extras for AWACS and EWRS cues (Section 1).

Written against DCS 2.9.30.

Thank you to Heatblur for making outstanding DCS modules, and for making the F-4 Jester API available to the community.

SYMBOLS

WARNING

Can cost you the fight, or a lock.

CAUTION

Can break your install or open a security hole.

NOTE

Useful details.

CONTENTS

Section 1 Installation 3
Section 2 The wheel and the three modes 5
Section 3 How Jester searches 6
Section 4 Cursor search and the bump 9
Section 5 The context button and stepping 10
Section 6 Locking 11
Section 7 Close in: the scan freeze and BFM 12
Section 8 Limits and troubleshooting 13
Section 9 Settings you may want to change 14
Quick-reference card 15



TERMS

Term	Meaning
Cue	A bearing, and sometimes a range and altitude, that Jester is told to search: an RWR emitter, an AWACS or EWRS report, or your cursor.
Paint	One radar detection of a contact. Jester sees contacts only through their paints.
Bar	One elevation setting of the antenna (the status line and Config call it a band).
Focus	The contact Jester has selected and is following.
Bump	A small up or down move of the cursor, before you let go, that tells Jester which side to search.

`A/A+ never locks a contact without a long press from you.`

SECTION 1 INSTALLATION

INSTALL

1. Close DCS. Open `Saved Games\DCS_F4E\jester\mods` (create the folders if they do not exist) and drag the folders `aaplus` and `init` from the download into it. Choose **Copy and Replace** when Windows asks. The folders merge and only A/A+ files are added.
2. Open `mods\aaplus\Config.lua` and set `Config.SAVED_GAMES` (the line marked `PATH TO EDIT`) to your Saved Games folder, for example `A:\Saved Games`. It is the only path to edit.
3. Start DCS. In a running mission, LShift+R restarts the mission and reloads Jester's Lua.
4. **Optional, but easy to miss:** for AWACS BRAA and EWRS cues, also install the hook from **_EXTRA (DCS Scripts)** and edit `MissionScripting.lua`. The steps are on the next page. Skip this if you only want the basic mod.

The log path and the AWACS file path are built from this setting. The log is used only if you turn on logging, and the AWACS file only by the optional extras on the next page.

NOTE

Three folders ship in this download. **aaplus** and **init** are the whole mod. **_EXTRA (DCS Scripts)** is only for AWACS and EWRS cues. Steps 1 to 3 are enough for everything else.

NOTE

A/A+ replaces no stock Jester file, so a Heatblur update will not undo it. It does wrap several stock functions, so an update to those functions may change how it behaves.

```
Saved Games\DCS_F4E\jester\mods\
    aaplus\
        Director.lua, Search.lua, Cues.lua, ... (13 Lua files)
        Config.lua ← edit this one
        DESIGN.md (developer notes)
    init\
        aaplus\
            LaunchAAPlus.lua
```

FIGURE 1-1. WHERE THE FILES GO

CHECK THAT IT LOADED

Open the Jester wheel in the aircraft. Under **Radar** you should see an entry called **A/A Plus**. If it is there, the mod is running and starts in **Unified** mode.



1 The A/A Plus entry

FIGURE 1-2. THE A/A PLUS ENTRY ON THE RADAR WHEEL

No entry? Section 8 lists the usual causes.

SECTION 1 INSTALLATION (CONT.)

INSTALL STEP 4 (OPTIONAL): AWACS, BRAA AND EWRS CUES

Without this step A/A+ still searches from the RWR and from the cursor. With it, Jester can also search from an AWACS BRAA reply and from an EWRS picture (EWRS is a popular mission script that reports contacts as text messages). These cues carry range and altitude, so the search can start at the contact's elevation instead of sweeping every bar.

Supported sources

- **Stock DCS AWACS.** Jester's own BRAA ("bogey dope") reply.
- **EWRS**, the Early Warning Radar Script, written by Steggles for the DCS forums. Community missions such as Foothold use it to send you bearing, range and altitude text for threats that friendly radars see.

Support for other AWACS and picture sources can be added in future versions.

It needs two things:

1. **The hook.** Drag the folder `Scripts` from **_EXTRA (DCS Scripts)** into `Saved Games\DCS` (open beta: `Saved Games\DCS.openbeta`) and choose Copy and Replace. It adds `Scripts\Hooks\AAPlusMessages.lua`. It writes `Logs\aaplus_messages.txt`. The hook logs every on-screen text message DCS passes to your client, plus a list of nearby aircraft, and rewrites the file at each DCS start. DCS must be fully restarted once, because hooks load only at start-up. `Config.AWACS_FILE` already points at that file.
2. **File access for Jester's Lua.** Jester's Lua must be allowed to read that file, which means turning the `io` library back on.

CAUTION


DCS removes `io` from mission scripts in `<DCS install>\Scripts\MissionScripting.lua` (the `sanitizeModule('io')` line). Commenting that line out gives **every** mission script file access to your PC. That is a real risk if you ever load missions you do not trust. A DCS update also puts the line back, so the AWACS cues will stop until you repeat the edit.

FEATURES BY INSTALL

Feature	Basic install	With the optional extras
Search from an RWR emitter	Yes	Yes
Search from the cursor (park it, bump it)	Yes	Yes
Search from an AWACS BRAA reply	No	Yes
Search from an EWRS picture	No	Yes
Search starts at the contact's altitude	No (sweeps every bar)	Yes (when a report gives altitude)
Lock handling, stepping, BFM	Yes	Yes

FALLBACK BEHAVIOR

If the hook file cannot be read, A/A+ does not fail. The AWACS feature switches itself off, one line is written to the log, and everything else carries on as normal. You lose the BRAA and EWRS cues and nothing more.



1. A stock AWACS BRA reply: bearing 070, 27 NM, 25,000 ft
2. An EWRS line: bearing, range, altitude, aspect and type, one per group

FIGURE 1-3. TWO MESSAGE SOURCES THAT BECOME CUES

NOTE

The bearings in AWACS and EWRS messages are magnetic. A/A+ compensates for the magnetic variation of each map, using the same per-map values as MOOSE. See Section 8.

SECTION 2 THE WHEEL AND THE THREE MODES


Open the Jester wheel and go to **Radar › A/A Plus**. The three entries set who runs the radar search. Jester answers a mode change with a Roger.

THE STATUS LINE

With the A/A Plus menu open, the text in the middle of the wheel is a status line. It reads like this:

```
UNIFIED Jester | NONE | 1 GRP, TOP HOSTILE 32
NM R9 hot 110s
```

From the left: the mode and who holds the cursor (*Jester* or *pilot*); the engagement state (*NONE* here, or a range band such as *BVR* when a bandit is out there); then either what the search is doing or, with no search running, the contact picture: how many groups, and the top threat. In this example, *R9* means 9 degrees right of the nose, *HOT* means closing, and the last number is the time to merge in seconds. During a search that last part reads like *SEARCH L12 band 2/10* (a search 12 degrees left of the nose, on bar 2 of 10), and *SEARCH found* means he has a contact and is holding the beam on it.



1. The three modes: Unified, Pilot, Off
2. The status line. The last item is 110s, 110 seconds; the in-game font draws the s like a 5

FIGURE 2-1. THE A/A PLUS SUBMENU

WHICH MODE

Mode	Who searches	Cursor	Use it when
Unified (default)	Jester starts his own searches from the RWR, AWACS and EWRS cues, and focuses what he finds.	Jester's, until you slew it. Then it is yours.	You want Jester to start searches himself.
Pilot	You. Jester searches where you park the cursor, or when you press the context button with no contact on the scope. He starts no searches from cues of his own.	Yours. Once a contact is focused, highlighted or locked, Jester holds it until you double-press.	You want to say where he looks, and nowhere else.
Off	Stock Jester, unchanged.	Stock.	You want to compare, or fly without A/A+.

PASSING THE CURSOR BACK AND FORTH (UNIFIED)




FIGURE 2-2. WHO HAS THE CURSOR IN UNIFIED MODE

> Jester stops his own searches when you take the cursor and resumes when you hand it back.

SECTION 3 HOW JESTER SEARCHES

Every search follows the same four steps.




FIGURE 3-1. A SEARCH FROM CUE TO FOCUS

WHAT COUNTS AS A CUE

Cue	Where it comes from	Needs
RWR emitter	An emitter on Jester's RWR. It gives a clock position and a rough distance from its place on the scope.	Nothing extra
Cursor	You park the cursor on a bearing and range and let go. Section 4.	Nothing extra
AWACS BRAA	A BRAA reply from AWACS. It gives bearing, range and altitude.	Hook and `io`
EWRS picture	An EWRS contact report, one cue per group of aircraft.	Hook and `io`

WHICH CUE FIRST

With several cues, Jester searches the most threatening one first. In rough order of weight:

- An RWR emitter outranks a bare AWACS bogey, unless the bogey is close and closing fast.
- A hot contact outranks a flanking one, and a flanking one outranks a cold one. Fighters outrank attack aircraft, which outrank everything else. Helicopters rank last.
- Closer beats farther, and a contact above you scores higher than one below.

A new cue interrupts a running search only if it clearly outscores it. A search that has found nothing for 20 seconds gives way to any cue that scores higher.

WHERE HE LOOKS

A search starts only on a cue within 58 degrees of your nose, which is about the limit of the radar gimbal. A cue outside that is kept and searched when it swings inside. A search ends if the cue swings past 62 degrees, and once a search for a cue ends, that cue waits 20 seconds before it is searched again.

NOTE

What Jester sees is not the scope picture. He reads the radar's contact list, which is built from individual detections, called paints. Stock lists a contact after two paints and generally calls it out only after many more (about ten in testing). A return can sit on your scope and still not exist for Jester.

NOTE


A hostile that shows only as an IFF return, with no radar paint, is invisible to Jester, so he cannot start a search from it. You can park the cursor on it and he will search there, but he finds it only if the radar also paints it.

> `In Unified, Jester chooses the cue. Slewing the cursor takes over from him.`

SECTION 3 HOW JESTER SEARCHES (CONT.)

THE ELEVATION BARS

The F-4E radar sees a thin slice of sky. Jester steps the antenna through a stack of slices, called *bars*, and dwells on each one long enough to catch a paint. Each bar is one beam wide, so together they leave no gap.



1. Bar 1 is level. Bars 2 to 6 step up by 3.5 degrees each, to +17.5 degrees.
2. Down bars are not shown. There are four, in 2.5 degree steps, to -10 degrees.

FIGURE 3-2. THE LEVEL BAR AND THE FIVE UP BARS, WHEN JESTER DOES NOT KNOW THE CONTACT'S ALTITUDE

Altitude unknown

Level first, then up through the five up bars, then down through the four down bars. Each up bar dwells 2.5 seconds and each down bar 3.5, because a low target in ground clutter paints only now and then.

Altitude known

When an AWACS or EWRS report gives the contact's altitude, the search works a tight pattern around that elevation (center, 2 degrees up, center, 2 degrees down), three times over, dwelling 3.5 seconds on each step. It skips down bars that would only see ground before reaching the contact.


Gain

Jester sets a different radar gain for looking up and looking down, and keeps it for as long as he is working the contact, including after the find. The gain returns to your setting once the contact has been off the scope for 15 seconds with nothing focused, highlighted or locked. While a search or a hold is running, Jester re-sets the gain knob, so a manual adjustment may be overwritten.

SECTION 3 AFTER THE FIND

When a bar paints the contact, the search stops and Jester holds the beam on it. Jester puts the cursor on the contact's measured bearing and range, and focuses it, even beyond stock's own focus limit of about 30 NM. A contact that paints steadily is focused at once. A faint one is held for up to a minute while the radar builds up paints.

Stock Jester then does what he always does: challenges the IFF and calls the contact out. A/A+ stays out of the way.




1 The cursor, parked where Jester is looking

FIGURE 3-3. SEARCHING

Periodic IFF

Jester also presses the IFF challenge every 15 seconds, whether or not the radar holds a contact, and at once when a new contact appears or a lock is made. He does it only while the radar is the picture on the scope: not with the radar off or in standby, and not while the scope shows the Pave Spike, a Maverick or any other video. In BFM nothing changes (Section 7). It is quiet, with no call. Turn it off with `IFF_PERIODIC`.



1 The contact, painted and under the cursor

FIGURE 3-4. FOUND AND FOCUSED

IF THE CONTACT PAINTS ONCE AND FADES

A contact that paints once near the cue but not yet twice is not a track. Jester points the beam at its altitude and gives it 12 more seconds for a second paint before moving on.

WARNING

A contact well above you at long range may paint only now and then, even with the beam aimed at it. In testing, a target at about +3 degrees and 36 NM (25,000 ft against 12,000 ft) painted roughly once every 25 seconds, too seldom for stock to call it out or focus it. For a high contact at long range, lock it yourself.

```
Jester holds the beam on the contact he found. He gives it up when you take the cursor.
```

SECTION 4 CURSOR SEARCH AND THE BUMP

You do not need a cue to send Jester looking. Slew the cursor to a bearing and range, let go, and about a third of a second later he starts a search there. The cursor's range sets how far out he looks, with a minimum of 5 NM.


This works in both Unified and Pilot modes.

THE BUMP

If you know the contact is high or low, tell Jester which way. Before you leave the cursor, *bump* it up or down on the scope. Jester takes the direction of the cursor's last vertical movement before you let go.

He scans level first, then steps the antenna in the bump direction. A bump up scans level, then up. A bump down scans level, then down. He makes two laps in all. If he finds nothing, the search ends and he returns to his normal scan.


The other direction is never scanned, so a contact on the wrong side of your bump is not found. This is intended: it keeps the search short.



1. Level, then up in 3.5 degree steps to +17.5. Bump down scans level, then down in 2.5 degree steps to -10.

FIGURE 4-1. A BUMP UP: LEVEL, THEN EACH BAR UP, TWICE. THE DOWN BARS ARE NOT SCANNED.

You bumped	Angles scanned, in order, twice
Up	0, +3.5, +7, +10.5, +14, +17.5, then again from 0
Down	0, -2.5, -5, -7.5, -10, then again from 0
No bump yet	Level, then the full pattern up, then down



1. The radar cursor, parked dead center
2. The slewed cursor: the search is about to begin
3. The elevation bar, at the right of the scope, moving as the scan runs after a bump

FIGURE 4-2. PARK, BUMP, SCAN

If you break a search

If you slew the cursor while a search is running, Jester stops the search and leaves the radar where it was. After you break a search, he starts no new search of his own for 30 seconds.

The bump memory

Jester remembers the last bump until you bump the other way or reload the mission. Before your first bump, a search uses the full pattern, up and then down. The bump matters only for cursor searches: when an AWACS or EWRS report gives the contact's altitude, Jester searches around that altitude instead.

WARNING

A contact on the wrong side of your bump is not found. Jester will not find a bandit below if you bump up.

SECTION 5 THE CONTEXT BUTTON AND STEPPING

The context button is the same button as stock. A/A+ changes what a short press steps through, and makes a long press faster. Bind it as you normally do.

Press	Effect
Short	Steps to the next contact, left to right. With no contact on the scope, it starts a search for the next cue.
Long	Locks the focused contact. See Section 6.
Double	Releases the focus and returns the radar to scanning. In Unified, with nothing focused, it hands the cursor back to Jester.

STEPPING

Stock steps through contacts in an order that changes as they close. A/A+ steps through them **left to right across the scope**, then back the other way. At each end the sweep turns around. It never repeats the end contact.




FIGURE 5-1. FOUR CONTACTS AND SEVEN PRESSES


Contacts in the sweep

- Contacts the radar painted in the last 15 seconds.
- Contacts stock has not identified yet, once they have three or more paints.
- The contact you already have highlighted, always.

A contact that has not painted for more than 15 seconds is skipped, because stepping onto it only gets its focus dropped again.

While you step

For six seconds after each press, Jester starts no searches of his own, so he does not move the cursor while you are choosing. A search you started yourself is never pre-empted.



1 The contacts, with the cursor on the lowest one

FIGURE 5-2. SEVERAL CONTACTS ON THE SCOPE

SECTION 6 LOCKING

A long press of the context button locks the focused contact. A/A+ makes three changes to what stock does.

- **Silent lock start.** Stock says "I am locking, left 25, 17 miles" while it works. A/A+ starts the lock silently and gives the lock phase priority over his scan work. The stable-lock call follows once the lock lands.
- **A lock you make by hand is kept.** If you lock a target by hand with the antenna hand controller, Jester keeps it. Stock would unlock it and return to scan.
- **A lost lock is forgotten.** After a lock is abandoned or lost, Jester keeps quiet about the same contact for 20 seconds if the radar finds it again.

LOOK-DOWN LOCKS

Locking a contact in ground clutter is the hard case. When the focused contact is half a degree or more below the horizon, a long press starts a short preparation.





FIGURE 6-1. WHAT A LONG PRESS DOES

If the paint is already steady at the press (four paints in six seconds, the newest within 2.5), the lock starts at once and Jester says nothing before it.

If it is not, he says *Roger*, keeps the cursor and the beam on the contact's predicted position, and fires the lock at the first steady paint. A second long press during the wait locks immediately.

WARNING

A look-down lock can land on the ground behind the target. Nothing Jester can read separates a good lock from a bad one. **You** judge the lock on the scope. The signs of a bad lock: the steering dot wanders unpredictably, and the closure readout at the top right flickers rapidly. Unlock and relock with the context button as often as you need. The best results in testing were inside 6 NM.



1. The radar cursor
2. The steering dot wanders unpredictably
3. The closure readout flickers rapidly

FIGURE 6-2. A LOOK-DOWN LOCK ON GROUND CLUTTER

SECTION 7 CLOSE IN: THE SCAN FREEZE AND BFM




FIGURE 7-1. WHAT CHANGES AS A BANDIT CLOSES

INSIDE 5 NM

With the radar uncaged and no lock, stock keeps sweeping the antenna in the background. Inside 5 NM, when you are heads out, that sweep is a distraction. A/A+ freezes it. The antenna stays where you left it, and the sweep resumes when the closest bandit is outside 5 NM again.

The freeze never applies during a lock, during one of A/A+'s own searches, or during lock preparation.

BFM MODE

BFM starts when you select boresight or cage and a bandit is inside 3 NM, or when a bandit is inside Heatblur's own dogfight distance whatever the radar is doing. It ends when no bandit has been inside 5 NM for 8 seconds, or when you leave boresight or cage for 2 seconds in a fight that is not a merge. In Unified, if you held the cursor when BFM starts, Jester takes it and keeps it when BFM ends.

Muted


Navigation chatter, traffic calls, Pave Spike operation and scope set-up. A/A+ stops searching.

Still active

Lookout and clock calls, RWR, missile warnings, countermeasures and damage reports.

Added

- **Speed calls.** Jester calls your indicated airspeed when you are 50 knots or more above or below the speed for Mach 0.8 at your altitude. He repeats the call every 10 seconds, and calls once more when you are back within 40 knots of it.
- **IFF on lock.** He challenges the IFF when a lock lands and says "checking IFF".



1. The 5 NM range scale
2. Boresighted contact

FIGURE 7-2. CLOSE IN, 5 NM SCALE

SECTION 8 LIMITS AND TROUBLESHOOTING

WHAT A/A+ CANNOT DO

Limit	What it means for you
Needs the radar to paint	Jester searches with the radar. A contact that never paints is never found. A target far above you at long range paints only now and then.
IFF-only returns are invisible	A hostile that shows only as an IFF return with no radar paint cannot start a search. Parking the cursor on it works only if the radar also paints it.
AWACS and EWRS cues need extras	The hook and the `io` change in Section 1. Without them, those cues are off and one log line says so.
Gimbal limit	A search starts only on a cue within 58 degrees of the nose. Outside that, the cue waits.
Gain window is narrow	A higher look-up gain can stop a high contact painting. Change it only if you will test the result.
Magnetic variation	AWACS and EWRS bearings are magnetic. A/A+ compensates with a built-in table of variation per map, using the values MOOSE uses. They are approximate, because variation also drifts with the mission date. A map with no entry, such as a new release, is treated as 0 degrees of variation. The current hook is needed to report the map; without it the Caucasus figures are used.
Not for other radar mods	Do not run it with a mod that replaces Jester's radar files. Two searches would both drive the cursor.
AWACS and EWRS range and age	Reports beyond 60 NM are ignored. A cue expires after 45 seconds and a contact after 90. EWRS keeps five groups. Stock AWACS reports only the closest bogey, so farther groups are not seen while a nearer cue is live.
When A/A+ is active	Only with the radar powered and active, in the air-to-air context, not in boresight and not in BFM. Outside that, Jester behaves as stock.
Cursor slew drops the focus	In Unified, slewing the cursor releases Jester's focus and turns auto-focus off until the cursor is handed back. It is refused while a lock exists.
Time acceleration	Radar paints are counted per frame. Judge searches at normal time.

TROUBLESHOOTING

Symptom	Check
No A/A Plus entry on the Radar wheel	Both folders copied, the `init\aaplus` one included? Press LShift+R. After a respawn the entry returns in about three seconds.
Jester never searches	Mode is not Off. You do not hold the cursor (Unified mode status says *pilot*). The cue is within 58 degrees of the nose.
AWACS cues never start	Hook installed and DCS fully restarted. `Logs\aaplus_messages.txt` exists and grows. The `io` edit has not been undone by a DCS update.
He searches the wrong place	Check that the hook is the current version (it reports the map), and that the BRAA call was the one you meant.
Something odd, and you want to report it	Set `LOG_TO_FILE = true` in Config.lua, fly it again, and send `mods\aaplus\aaplus.log`. It needs `io` too.

Section 9 SETTINGS YOU MAY WANT TO CHANGE

Everything is in `mods\aaplus\Config.lua`. Most settings are commented there. Save the file and press LShift+R in the mission (it restarts the mission), or restart DCS.

Setting	Default	Description
DEFAULT_MODE	UNIFIED	Mode on spawn: UNIFIED, PILOT or OFF.
MENU_NAME	A/A Plus	Name of the wheel entry. Leave the **+** out: the wheel matches names as patterns, and + breaks that.
SEARCH_STEP_DEG	3.5	Elevation step for up bars.
SEARCH_UP_STEPS	5	Up bars above level.
SEARCH_DOWN_STEP_DEG / STEPS	2.5 / 4	Step and count for down bars.
SEARCH_DWELL / SEARCH_DOWN_DWELL	2.5 s / 3.5 s	Seconds per up bar, per down bar.
SEARCH_BUMP_LAPS	2	How many laps after a bump.
SEARCH_UP_GAIN / DOWN / UNKNOWN	0.73 / 0.63 / 0.73	Radar gain on up bars, down bars, and level or up bars when the altitude is unknown.
HANDBACK_IDLE_S	90	Seconds idle before the cursor returns to Jester (Unified).
DOUBLE_HOLDOFF_S	20	After a double press releases a focus, auto-focus stays off this long.
TRANSITION_NM	5.0	The scan-freeze distance.
BFM_RANGE_NM / BFM_EXIT_NM	3.0 / 5.0	Distance to enter and to leave BFM.
IFF_PERIODIC / IFF_PERIOD_S	true / 15	Jester challenges the IFF on his own, with or without radar contacts (Section 3).
SPEED_STR_MACH / SPEED_STR_BAND_KT	0.8 / 50	The speed Jester calls around, and how far off it before he does.
SAVED_GAMES	your folder	Your Saved Games folder, for example A:\Saved Games. The only path to edit (Section 1).
AWACS_FILE	from SAVED_GAMES	Where the optional hook writes its log, which Jester reads. Built from Config.SAVED_GAMES (Section 1).
LOG_TO_FILE	false	Writes aaplus.log for a bug report.

UNINSTALL

- Delete `mods\init\aaplus` to stop it loading.
- Delete `mods\aaplus` to remove it completely.
- Delete `AAPlusMessages.lua` from your Hooks folder to stop the AWACS log.

> `The init folder is the switch. The other folder is just the files.`

CARD QUICK REFERENCE

WHEEL

Radar › A/A Plus › Unified / Pilot / Off

Mode	Who searches
Unified	Jester, until you slew
Pilot	You park the cursor
Off	Stock

CONTEXT BUTTON

Press	Does
Short	Step left to right
Long	Lock focus
Double	Release focus. Nothing focused: cursor back to Jester

BUMP

Park the cursor, nudge it up or down, let go. Jester scans level plus that side, twice.

Bump	Angles
Up	0 to +17.5
Down	0 to -10

CLOSE IN

Distance	Changes
Inside 5 NM	Background scan freezes
Boresight, inside 3 NM	BFM: speed calls, IFF on lock

WARNING

A look-down lock can land on the ground. Check it. Unlock and relock as needed.

NOTE

A bandit on the wrong side of your bump is not found.

CAUTION

AWACS and EWRS cues need the hook and the `io` change.

> Print at 50% for a kneeboard card.