


Chapter 9: Memory Management

- Background
- Swapping
- Contiguous Allocation
- Paging
- Segmentation
- Segmentation with Paging





Background

- Program must be brought into memory and placed within a process for it to be run.
- Input queue collection of processes on the disk that are waiting to be brought into memory to run the program.
- User programs go through several steps before being run.




Binding of Instructions and Data to Memory

Address binding of instructions and data to memory addresses can happen at three different stages.


- Compile time: If memory location known a priori, absolute code can be generated; must recompile code if starting location changes.
- **Load time**: Must generate *relocatable* code if memory location is not known at compile time.
- **Execution time**: Binding delayed until run time if the process can be moved during its execution from one memory segment to another. Need hardware support for address maps (e.g., base and limit registers).











Logical vs. Physical Address Space

- The concept of a logical address space that is bound to a separate physical address space is central to proper memory management.
 - Logical address generated by the CPU; also referred to as virtual address.
 - Physical address address seen by the memory unit.
- Logical and physical addresses are the same in compiletime and load-time address-binding schemes; logical (virtual) and physical addresses differ in execution-time address-binding scheme.






Memory-Management Unit (мми)

- Hardware device that maps virtual to physical address.
- In MMU scheme, the value in the relocation register is added to every address generated by a user process at the time it is sent to memory.
- The user program deals with *logical* addresses; it never sees the *real* physical addresses.



Dynamic relocation using a relocation register







Dynamic Loading

- Routine is not loaded until it is called
- Better memory-space utilization; unused routine is never loaded.
- Useful when large amounts of code are needed to handle infrequently occurring cases.
- No special support from the operating system is required implemented through program design.





Dynamic Linking

- Linking postponed until execution time.
- Small piece of code, *stub*, used to locate the appropriate memory-resident library routine.
- Stub replaces itself with the address of the routine, and executes the routine.
- Operating system needed to check if routine is in processes' memory address.
- Dynamic linking is particularly useful for libraries.






Overlays

- Keep in memory only those instructions and data that are needed at any given time.
- Needed when process is larger than amount of memory allocated to it.
- Implemented by user, no special support needed from operating system, programming design of overlay structure is complex

The concept of **overlays** is that whenever a process is running it will not use the complete program at the same time, it will use only some part of it. Then overlays concept says that whatever part you required, you load it an once the part is done, then you just unload it, means just pull it back and get the new part you required and run it.

Overlays for a Two-Pass Assembler



best example of overlays is assembler. Consider the assembler has 2 passes, 2 pass means at any time it will be doing only one thing, either the 1st pass or the 2nd pass. Which means it will finish 1st pass first and then 2nd pass. Let assume that available main memory size is 150KB and total code size is 200KB

Pass 1......80KB Symbol table......20KB Common routine......20KB As the total code size is 200KB and main memory size is 150KB, it is not possible to use 2 passes together. So, in this case, we should go with the overlays technique. According to the overlays concept at any time only one pass will be used and both the passes always need symbol table and common routine. Now the question is if overlays-driver* is 10KB, then what is the minimum partition size required? For pass 1 total memory needed is = (70KB + 30KB + 20KB + 10KB) = 130KBand for pass 2 total memory needed is = (80KB + 30KB + 20KB + 10KB) = 140KB.So if we have minimum 140KB size partition then we can run this code very easily

Swapping


- A process can be swapped temporarily out of memory to a backing store, and then brought back into memory for continued execution.
- Backing store fast disk large enough to accommodate copies of all memory images for all users; must provide direct access to these memory images.
- Roll out, roll in swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed.
- Major part of swap time is transfer time; total transfer time is directly proportional to the *amount* of memory swapped.
- Modified versions of swapping are found on many systems, i.e., UNIX, Linux, and Windows.

To replace pages or segments of data in **memory**. **Swapping** is a useful technique that enables a computer to execute programs and manipulate data files larger than main memory. The operating system copies as much data as possible into main memory, and leaves the rest on the disk.

Silberschatz, Galvin and Gagne ©2002



Schematic View of Swapping








Contiguous Allocation

- Main memory usually into two partitions:
 - Resident operating system, usually held in low memory with interrupt vector.
 - User processes then held in high memory.
- Single-partition allocation
 - Relocation-register scheme used to protect user processes from each other, and from changing operating-system code and data.
 - Relocation register contains value of smallest physical address; limit register contains range of logical addresses – each logical address must be less than the limit register.



Hardware Support for Relocation and Limit Registers








Contiguous Allocation (Cont.)

Multiple-partition allocation

- Hole block of available memory; holes of various size are scattered throughout memory.
- When a process arrives, it is allocated memory from a hole large enough to accommodate it.
- Operating system maintains information about:
 a) allocated partitions
 b) free partitions (hole)



Dynamic Storage-Allocation Problem

How to satisfy a request of size *n* from a list of free holes.

- First-fit: Allocate the first hole that is big enough.
- **Best-fit**: Allocate the *smallest* hole that is big enough; must search entire list, unless ordered by size.

 Produces the smallest leftover hole.
- Worst-fit: Allocate the *largest* hole; must also search entire list. Produces the largest leftover hole.

First-fit and best-fit better than worst-fit in terms of speed and storage utilization.







Fragmentation

- External Fragmentation total memory space exists to satisfy a request, but it is not contiguous.
- Internal Fragmentation allocated memory may be slightly larger than requested memory; this size difference is memory internal to a partition, but not being used.
- Reduce external fragmentation by compaction
 - Shuffle memory contents to place all free memory together in one large block.
 - Compaction is possible only if relocation is dynamic, and is done at execution time.
 - I/O problem
 - ✓ Latch job in memory while it is involved in I/O.
 - ✓ Do I/O only into OS buffers.









Paging

- Logical address space of a process can be noncontiguous;(Which is not nearer) process is allocated physical memory whenever the latter is available.
- Divide physical memory into fixed-sized blocks called **frames** (size is power of 2, between 512 bytes and 8192 bytes).
- Divide logical memory into blocks of same size called pages.
- Keep track of all free frames.
- To run a program of size *n* pages, need to find *n* free frames and load program.
- Set up a page table to translate logical to physical addresses.
- Internal fragmentation.






Address Translation Scheme

- Address generated by CPU is divided into:
 - Page number (p) used as an index into a page table which contains base address of each page in physical memory.
 - Page offset (d) combined with base address to define the physical memory address that is sent to the memory unit.






Address Translation Architecture








Paging Example








Paging Example






Free Frames



Before allocation

After allocation





Implementation of Page Table

- Page table is kept in main memory.
- Page-table base register (PTBR) points to the page table.
- Page-table length register (PTLR) indicates size of the page table.
- In this scheme every data/instruction access requires two memory accesses. One for the page table and one for the data/instruction.
- The two memory access problem can be solved by the use of a special fast-lookup hardware cache called associative memory or translation look-aside buffers (TLBs)





Associative Memory

■ Associative memory – parallel search

Page #	Frame #


Address translation (A', A'')

- If A' is in associative register, get frame # out.
- Otherwise get frame # from page table in memory





Paging Hardware With TLB








Memory Protection

- Memory protection implemented by associating protection bit with each frame.
- Valid-invalid bit attached to each entry in the page table:
 - "valid" indicates that the associated page is in the process' logical address space, and is thus a legal page.
 - "invalid" indicates that the page is not in the process' logical address space.



Valid (v) or Invalid (i) Bit In A Page Table





Page Table Structure

- Hierarchical Paging
- Hashed Page Tables
- Inverted Page Tables





Hierarchical Page Tables

- Break up the logical address space into multiple page tables.
- A simple technique is a two-level page table.





Two-Level Paging Example

- A logical address (on 32-bit machine with 4K page size) is divided into:
 - a page number consisting of 20 bits.
 - a page offset consisting of 12 bits.
- Since the page table is paged, the page number is further divided into:
 - a 10-bit page number.
 - → a 10-bit page offset.
- Thus, a logical address is as follows:


page number			page offset
	p_{i}	p_2	d
	10	10	12

where p_i is an index into the outer page table, and p_2 is the displacement within the page of the outer page table.





Two-Level Page-Table Scheme








Address-Translation Scheme

Address-translation scheme for a two-level 32-bit paging architecture








Hashed Page Tables

- Common in address spaces > 32 bits.
- The virtual page number is hashed into a page table. This page table contains a chain of elements hashing to the same location.
- Virtual page numbers are compared in this chain searching for a match. If a match is found, the corresponding physical frame is extracted.





Hashed Page Table







Shared Pages

Shared code


- One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems).
- Shared code must appear in same location in the logical address space of all processes.

Private code and data

- Each process keeps a separate copy of the code and data.
- The pages for the private code and data can appear anywhere in the logical address space.











Segmentation


- Memory-management scheme that supports user view of memory.
- A program is a collection of segments. A segment is a logical unit such as:

```
main program,
procedure,
function,
method,
object,
local variables, global variables,
common block,
stack,
symbol table, arrays
```






User's View of a Program








Logical View of Segmentation



physical memory space






Segmentation Architecture

- Logical address consists of a two tuple:
 - <segment-number, offset>,
- Segment table maps two-dimensional physical addresses; each table entry has:
 - base contains the starting physical address where the segments reside in memory.
 - limit specifies the length of the segment.
- Segment-table base register (STBR) points to the segment table's location in memory.
- Segment-table length register (STLR) indicates number of segments used by a program;
 - segment number s is legal if s < STLR.










Example of Segmentation






We have five segments from 0 to 4. They are stored in physical memory. Segment table has separate entry for each segment. It gives beginning address of segment (base)and length of segment (limit) eg here segment 2 is 400 bytes long and starts from 4300 location so segment 2 ends at location 4300+400=4700.





Sharing of Segments





Sharing of segmentation for data and code is shown here. Editor segment is a shared segment here. It starts from 43062 and ends at 68348.ie, 43062+25286=68348. Data segment stores at different locations. Data 1 starts from 68348 and ends at 72773.



Segmentation with Paging – Intel 386

As shown in the following diagram, the Intel 386 uses segmentation with paging for memory management with a two-level paging scheme.





Intel 30386 Address Translation

