enters and leaves

exists. We'll get into specific controls later in this chapter, but the point is that as one

travels from the outside of the facility toward the most sensitive areas, security controls

should be visible and increasingly tight.

Zero Trust

A threat that is frequently overlooked, even in some fairly secure environments, is that of

the malicious insider. Whether that person is a member of the organization, a contractor,

a partner, or even an impostor, it is not hard to come across news stories describing the

damage malicious insiders have caused from within. Applying the principle of zero trust

to securing our facilities means we need to be able to tell whether someone should be in

a given part of our facility doing whatever it is they're doing. To this end, we could use

badges with different colors or icons. For example, you could divide a site into black, gray,

PART III

suppose your organization develops and sells productivity software. After a bit of threat

modeling, you determine that your likeliest physical security threat is a fire accidentally

started by employees overloading circuits (say, with portable space heaters) and your

most dangerous physical threat is a competitor sneaking into your facility and copying

your source code. So, you focus your attention on mitigating the risk that stems from

those two threats, which allows you to apply your limited resources to the threats that

matter most to you.

Things change, however, so threat modeling (just as the broader risk management) activities are ongoing. You should periodically reassess your threat models to ensure they

remain accurate and up to date. Threat modeling includes not only the source of the

risk (i.e., the threat actor) but also the manner in which that risk becomes manifest (i.e.,

the threat actor's specific actions). Continuing our earlier example, suppose you realize

that your competitors are likelier to bribe an insider to exfiltrate the source code on a

removable drive than to sneak into your facility and steal it themselves, so you update

your threat models and ensure the right controls are in place. Or maybe your company's

CEO makes a controversial statement and now your most dangerous adversary's

course of

action is that angry demonstrators will vandalize your facility. Either way, threat models

need to be updated and security controls adjusted periodically.

♠CISSP All-in-One Exam Guide

420

and gold sections and then label the rooms, hallways, and badges with the appropriate

colors. If you come across someone with a badge that doesn't match the section in which

they are located, you can approach or report them. Similarly, you could have icons on the

badges that denote other authorizations. The following list gives you some ideas of the

types of staff badge icons that are used in real organizations to display a staff member's

restrictions, permissions, or status:

- Escort required
- Allowed to escort visitors
- Custodial staff
- Data center (or operations center, or C-suite) access
- Top secret security clearance
- Allowed to carry weapons

Another aspect of zero trust applied to physical security is the notion of "see something,

say something." Staff members should be required by policy and trained to pay attention

to suspicious situations and respond appropriately. Examples are challenging unbadged

personnel in the hallways, shutting doors that may have been propped open, and reporting a co-worker who is acting in an odd manner. Some organizations deliberately

stage suspicious situations to see which employees respond correctly to them. Those who

do get some token reward; those who don't get additional training.

Trust But Verify

As with logical security, the principles of zero trust and trust but verify can (and oftentimes) coexist within the same organization when it comes to physical security. Perhaps

the most common implementation of the principle of trust but verify is the logging of

physical events, which are then periodically checked by someone else. For example, if

there is a safe or area that needs to be locked after work hours, it could be the responsibility of one individual to lock it (maybe the last one out) and another to verify that it was

locked (maybe a security guard or rotating staff member assigned to after-hours checks).

The critical aspect of this principle is to actually verify that individuals are carrying out

their responsibilities. For example, is anyone checking the physical access logs periodically

and comparing them to what should be happening? Are employees who are on vacation

badging in? This could indicate a stolen badge. Is a staff member coming in at odd

hours for no apparent reason? In multiple, documented cases this has happened because

employees were doing something they didn't want others noticing. Think of your

organization. Are there any things you or your team should be verifying regularly with

regard to physical security? If not, should there be?

Shared Responsibility

Of course, not every aspect of site and facility security will rest on your shoulders as a

security professional. In many cases, organizations share this responsibility with partners,

landlords, and service providers. If you share office space in a building, whoever owns the

♠Chapter 10: Site and Facility Security

421

building has certain responsibilities for its security. They may provide lobby guards and

ensure that all the perimeter doors are locked except those leading to authorized access

points. Or perhaps guards are provided to your organization by a security firm. They will

have clearly defined responsibilities documented in the contract or service agreement.

All too often, however, the delineation of shared responsibilities is not clearly understood

by all who should. A good way to discover points of confusion is to regularly conduct

physical security drills, such as physical penetration tests and tabletop exercises involving

all responsible entities, perhaps extending to local law enforcement as appropriate.

Separation of Duties

Least Privilege

We previously mentioned the need to balance security with functionality, and this is

especially true when it comes to staff authorizations. Staff should have the least amount

of privileges that are absolutely necessary for their jobs, while enabling them to do those

jobs efficiently and effectively. When it comes to site and facility security, this commonly takes the form of access to restricted areas. If employees have to badge in and out

of different facilities, it is important to ensure that each staff member can effortlessly

flow through the ones in which they do their jobs, and no others. For example, if some

employees work at site A, their badges should not allow them entry to site B unless it

is required.

Another example that comes to mind is access to server rooms or data centers. Oftentimes the racks that house the computing and storage devices in these facilities can

and should be locked. Depending on the devices involved and their purpose, it is typical

for different groups to need access to different racks. For example, the IT team may need

access to the racks containing the domain controller and mail servers. The product team

may need to get to the development servers that are on a different rack and subnet. The

security team may need access to the security appliances, such as the network detection

and response systems. Obviously, these groups probably shouldn't be able to access all the

devices in the facility, but only the ones they need to do their jobs. Rather than leave all

racks unlocked or use the same key for expediency, these staff members should be given

only the minimum access possible to just the resources they need.

PART III

Duties can be deliberately separated with regard to physical security to mitigate theft and

unauthorized physical access, among other risks. As an example, it is common for organizations to require one person (typically a receptionist or guard) to sign in guests and

another person to escort them. This reduces the risk that a malicious insider sneaks in

an external conspirator unnoticed. It also means that there are two pairs of eyes on each

visitor to minimize the chances of accidentally letting an impostor in. Another example

of separation of duties concerns receiving shipments. If only one person is involved in

the process, how would we know whether a shipment that person reports as incomplete

was truly incomplete or that person is stealing? To prevent this from easily happening,

some organizations require only one person to sign for the delivery but require at least

one other person to be present when the packages are opened and the property is added

to the inventory.

♠CISSP All-in-One Exam Guide

422

Simplicity

We discussed in Chapter 9 how complexity leads to the introduction of defects that, in

turn, could create vulnerabilities. When it comes to our sites and facilities, the need for simplicity comes in at least two flavors: layout and procedural. The simpler the layout of our

workplaces, the fewer hiding spots we create, the fewer cameras we need, and the more eyes

that will naturally fall on everything that happens there. Whenever you have the choice,

choose the simpler, more open layout to improve your organization's physical security.

Regardless of whether or not you can control the layout of your sites and facilities, you

can almost always influence the security procedures that are implemented. Of course,

you want to make these procedures so simple that they become second nature to all

your organization's staff. From signing in and escorting visitors to safely evacuating the

building in case of emergency, your organization needs procedures that are as simple as

possible. These are normally validated and practiced during drills, which also provide a

good opportunity to verify that no unnecessary complexity has crept into them.

Secure Defaults

As discussed in Chapter 9, secure defaults mean everything starts off in a place of extreme

security that is then intentionally loosened until people can get their jobs done, but no

further. Picture, then, your site schematics. Fence in every outdoor area, block off all

vehicular travel around it, lock every door, and keep everyone out of every space. In other

words, lock the place down as tightly as you know how. Now, take one of your teams, say

IT, and walk through a day in their life. As you step through it, make note of how they'd

drive in, what doors they'd have to use, which locks they need to open, and where they

need to sit. Repeat this process for each organizational team, and then for your partners.

vendors, and general visitors. You'll end up with the minimal relaxation to your extreme

security plan that would be required for your staff members to do their jobs. This is what

secure defaults look like for site security planning.

Fail Securely

This is a good point to discuss the difference between two principles that sound a lot alike

but have very different implications. Recall that a fail-secure configuration is one in which

things like doors default to being locked if there are any problems with the power, because

that is the highest level of security for that system (the lock). If people do not need to use

specific doors for escape during an emergency, then those doors can most likely default to

fail-secure settings. On the other hand, a fail-safe setting means that if a power disruption

occurs that affects the automated locking system, the doors default to being unlocked.

Fail-safe deals directly with protecting people. If people work in an area in which a fire

starts or the power is lost, it is a terrible idea to lock them in. Doorways with automatic

locks can be configured in either mode, but we need to make careful decisions about

which is appropriate and how we mitigate residual risks when we execute a fail-safe setting.

EXAM TIP The protection of human life trumps everything else. Be on the lookout for exam questions involving fail-safe versus fail-secure configurations.

♠Chapter 10: Site and Facility Security

423

Privacy by Design

Finally, we must keep in mind the need for privacy as we plan our site and facility security.

This comes up in a number of areas and, frankly, varies widely between organizations.

On one end of the spectrum, we have military and intelligence agencies wherein privacy

in physical spaces is very limited due to the nature of the work being done. On the other

end, consider healthcare organizations, in which privacy is absolutely essential. Regardless of where your organization falls in that spectrum, privacy definitely plays some role

(e.g., restrooms) in shaping the manner in which you develop your site security. At a

minimum, you should consider what private conversations (e.g., employee counseling,

patient intakes, etc.) will take place in your site and where those would take place.

The Site Planning Process

- Natural environmental threats Floods, earthquakes, storms, volcanic eruptions, pandemics, and so forth
- Supply system threats Power distribution outages, communications interruptions,
- and interruption of other resources such as water, gas, and air filtration
- Manmade threats Deliberate or accidental actions of humans, including fire,

burglary, equipment loss/destruction, active shooters, and even terrorism In all situations, the primary consideration, above all else, is that nothing should

impede life safety goals. Protecting human life is the first priority. Good planning helps

balance life safety concerns and other security measures. For example, barring a door to

prevent unauthorized physical intrusion might prevent individuals from being able to

escape in the event of a fire. Life safety goals should always take precedence over all other

types of goals; thus, this door might allow insiders to exit through it after pushing an

emergency bar, but not allow external entities in.

As with any type of security, most attention and awareness surround the exciting and headline-grabbing tidbits about large crimes being carried out and criminals being

captured. In information security, most people are aware of viruses and hackers, but

not of the components that make up a corporate security program. The same is true for

physical security. Many "water cooler" conversations include talk about current robberies,

murders, and other criminal activity, but not much attention is paid to the necessary

framework that should be erected and maintained to reduce these types of activities.

PART III

Site and facility planning involves much more than physical security. Organizations

should also be addressing issues like functionality, efficiency, cost, compliance, and aesthetics, just to name a few. However, as these (and other) issues are being addressed

by the planning team, it is best to consider how each relates to physical security. For

example, functionality and efficiency can frequently hinder security (and vice versa).

So, we should balance the various requirements to ensure we are enabling the organization's functions while also protecting it from the various threats we've modeled for it.

These threats include the following:

♠CISSP All-in-One Exam Guide

424

An organization's physical security program should address the following goals:

- Crime and disruption prevention through deterrence Fences, security guards, warning signs, and so forth
- Reduction of damage through the use of delaying mechanisms Layers of defenses that slow down the adversary, such as locks, security personnel, and barriers

- Crime or disruption detection Smoke detectors, motion detectors, security cameras, and so forth
- Incident assessment Response of security guards to detected incidents and determination of damage level
- Response procedures Fire suppression mechanisms, emergency response processes, law enforcement notification, and consultation with outside security professionals
- So, an organization should try to prevent crimes and disruptions from taking place,

but must also plan to deal with them when they do happen. Criminals should be delayed

in their activities by having to penetrate several layers of controls before gaining access

to a resource. All types of crimes and disruptions should be able to be detected through

components that make up the physical security program. Once an intrusion is discovered,

a security guard should be called upon to assess the situation. The security guard must

then know how to properly respond to a large range of potentially dangerous activities.

The emergency response activities could be carried out by the organization's internal

security team or by outside experts.

This all sounds straightforward enough, until the team responsible for developing

the physical security program looks at all the possible threats, the finite budget that

the team has to work with, and the complexity of choosing the right combination of

countermeasures and ensuring that they all work together in a manner that ensures no

gaps of protection. All of these components must be understood in depth before the

design of a physical security program can begin.

As with all security programs, it is possible to determine how beneficial and effective

your organization's physical security program is only if it is monitored through a

performance-based approach. This means you should devise measurements and metrics

to gauge the effectiveness of your countermeasures. This enables management to make

informed business decisions when investing in the protection of the organization's

physical security. The goal is to increase the performance of the physical security program

and decrease the risk to the organization in a cost-effective manner. You should establish

a baseline of performance and thereafter continually evaluate performance to make sure

that the organization's protection objectives are being met. The following list provides

some examples of possible performance metrics:

- Number of crimes committed
- Number of disruptions experienced
- Number of crimes attempted
- Number of disruptions prevented
- Time between detection, assessment, and recovery steps

♠Chapter 10: Site and Facility Security

425

- Business impact of disruptions
- Number of false-positive detection alerts
- Time it took for a criminal to defeat a control
- Time it took to restore the operational environment
- Financial loss of a successful crime
- Financial loss of a successful disruption

Capturing and monitoring these types of metrics enables the organization to identify

deficiencies, evaluate improvement measures, and perform cost/benefit analyses.

The physical security team needs to carry out a risk analysis, which will identify the

organization's vulnerabilities, threats, and business impacts. The team should present

these findings to management and work with management to define an acceptable risk

level for the physical security program. From there, the team must develop baselines

(minimum levels of security) and metrics in order to evaluate and determine if

baselines are being met by the implemented countermeasures. Once the team identifies ${\sf countermeasures}$

and implements the countermeasures, the performance of these countermeasures should be continually evaluated and expressed in the previously created metrics. These

performance values are compared to the set baselines. If the baselines are continually

maintained, then the security program is successful because the organization's acceptable

risk level is not being exceeded. This is illustrated in Figure 10-1. Helps to define...

Broken down into...

Used to evalute...

Risk analysis

Acceptable risk level

Baselines of performance

- 1. Identify:
- Vulnerabilities
- Threats
- Level of risk the organization is willing to accept
- Minimum levels of security are defined
- 2. Calculate business
 impact of each
- Guides the team to know what "enough security" means
- Quantitative metrics defined

Implemented
countermeasures

- Construction materials
- Security guards
- Intrusion detection systems
- Fire protection
- Emergency training

To ensure compliance with...

Figure 10-1

Relationships of risk, baselines, and countermeasures

PART III

NOTE Metrics are important in all domains of security because organizations need to allocate the necessary controls and countermeasures to mitigate risks in a cost-beneficial manner. You can't manage what you can't measure.

♠CISSP All-in-One Exam Guide

426

Similarities in Approaches
The risk analysis steps that need to take place for the development of a physical

security program are similar to the steps outlined for the development of an organizational security program and for business impact analysis, because each of these

processes (development of an information security program, a physical security program, or a business continuity plan) accomplishes goals that are similar to the goals

of the other two processes, but with different focuses. Each process requires a

to carry out a risk analysis to determine the organization's threats and risks. $\ensuremath{\Delta n}$

information security program looks at the internal and external threats to resources

and data through business processes and technological means. Business continuity planning looks at how natural disasters and disruptions could damage the organization, while a physical security program looks at internal and external physical

threats to the organization's resources.

Each requires a solid risk analysis process. Review Chapter 2 to understand the core components of every risk analysis.

So, before an effective physical security program can be rolled out, the following steps

must be taken:

1. Identify a team of internal employees and/or external consultants who will build

the physical security program through the following steps.

- 2. Define the scope of the effort: site or facility.
- 3. Carry out a risk analysis to identify the vulnerabilities and threats and to calculate

the business impact of each threat.

- 4. Identify regulatory and legal requirements that the organization must meet
- 5. Work with management to define an acceptable risk level for the physical security program.
- 6. Derive the required performance baselines from the acceptable risk level.
- 7. Create countermeasure performance metrics.
- 8. Develop criteria from the results of the analysis, outlining the level of protection

and performance required for the following categories of the security program:

- Deterrence
- Delaying
- Detection
- Assessment
- Response
- 9. Identify and implement countermeasures for each program category.
- 10. Continuously evaluate countermeasures against the set baselines to ensure the

acceptable risk level is not exceeded.

♠Chapter 10: Site and Facility Security

427

Legal Requirements

Once these steps have taken place, the team is ready to move forward in its actual

design phase. The design will incorporate the controls required for each category of the

program: deterrence, delaying, detection, assessment, and response. We will dig deeper

into these categories and their corresponding controls later in the chapter in the section

"Designing a Physical Security Program."

One of the most commonly used approaches in physical security program development

is described in the following section.

Crime Prevention Through Environmental Design

Crime Prevention Through Environmental Design (CPTED) is a discipline that outlines

how the proper design of a physical environment can reduce crime by directly affecting

human behavior. It provides guidance in loss and crime prevention through proper facility construction and environmental components and procedures.

CPTED concepts were developed in the 1960s. They have been expanded upon and have matured as our environments and crime types have evolved. CPTED has been used

not just to develop corporate physical security programs but also for large-scale activities

such as development of neighborhoods, towns, and cities. It addresses landscaping,

entrances, facility and neighborhood layouts, lighting, road placement, and traffic

circulation patterns. It looks at microenvironments, such as offices and restrooms, and

macroenvironments, like campuses and cities. The crux of CPTED is that the physical

environment can be manipulated to create behavioral effects that will reduce crime and

the fear of crime. It looks at the components that make up the relationship between

humans and their environment. This encompasses the physical, social, and psychological

needs of the users of different types of environments and predictable behaviors of these

users and of potential offenders.

PART III

In physical security there are some regulatory and high-level legal requirements that

must be met, but many of them just have high-level statements, as in "protect personnel" or "implement lifesaving controls." It is up to the organization to figure out

how to actually meet these requirements in a practical manner. In the United States

there is a lot of case law that pertains to physical security requirements, which is

built upon precedence. This means that there have been lawsuits pertaining to specific physical security instances and a judgment was made on liability. For example,

there is no law that dictates that you must put up a yellow sign indicating that a

floor is wet. Many years ago someone somewhere slipped on a wet floor and sued the company, and the judge ruled that the company was negligent and liable for the person's injuries because it didn't warn the person about the wet floor. Now it is

built into many company procedures that after a floor is mopped or there is a spill,

this yellow sign is put in place so no one will fall and sue the company. It is hard to

think about and cover all of these issues since there is no specific checklist to follow.

This is why it is a good idea to consult with a physical security expert when developing a physical security program.

♠CISSP All-in-One Exam Guide

428

CPTED provides guidelines on items some of us might not consider. For example, planters should be placed away from buildings so they cannot be used to gain access to

a window. A data center should be located at the center of a facility so the facility's walls

will absorb any damages from external forces, instead of the data center itself. Street

furnishings (benches and tables) encourage people to sit and watch what is going on

around them, which discourages criminal activity. A corporation's landscape should not

include wooded areas or other places where intruders can hide. Security cameras should

be mounted in full view so that criminals know their activities will be captured and other

people know that the environment is well monitored and thus safer.

CPTED and target hardening are two different approaches. Target hardening focuses on

denying access through physical and artificial barriers (alarms, locks, fences, and so on).

Traditional target hardening can lead to restrictions on the use, enjoyment, and aesthetics

of an environment. Sure, we can implement hierarchies of fences, locks, and intimidating

signs and barriers—but how pretty would that be? If your environment is a prison, this

look might be just what you need. But if your environment is an office building, you're

not looking for Fort Knox décor. Nevertheless, you still must provide the necessary levels

of protection, but your protection mechanisms should be more subtle and unobtrusive.

Let's say your organization's team needs to protect a side door at your

facility. The

traditional target-hardening approach would be to put locks, alarms, and cameras on

the door; install an access control mechanism, such as a proximity reader; and instruct

security guards to monitor this door. The CPTED approach would be to ensure there

is no sidewalk leading to this door from the front of the building if you don't want

customers using it. The CPTED approach would also ensure no tall trees or bushes block

the ability to view someone using this door. Barriers such as trees and bushes may make

intruders feel more comfortable in attempting to break in through a secluded door.

The best approach is usually to build an environment from a CPTED approach and then apply the target-hardening components on top of the design where needed.

If a parking garage were developed using the CPTED approach, the stair towers and

elevators within the garage might have glass windows instead of metal walls, so people

would feel safer, and potential criminals would not carry out crimes in this more visible

environment. Pedestrian walkways would be created such that people could look out across

the rows of cars and see any suspicious activities. The different rows for cars to park in would

be separated by low walls and structural pillars, instead of solid walls, to allow pedestrians

to view activities within the garage. The goal is to not provide any hidden areas where

criminals can carry out their crimes and to provide an open-viewed area so if a criminal

does attempt something malicious, there is a higher likelihood of someone seeing it.

CPTED provides four main strategies to bring together the physical environment and

social behavior to increase overall protection: natural access control, natural surveillance,

territorial reinforcement, and maintenance.

Natural Access Control

Natural access control is the guidance of people entering and leaving a space by the placement of doors, fences, lighting, and even landscaping. For example, an office building

may have external bollards with lights in them, as shown in Figure 10-2. These bollards

actually carry out different safety and security services. The bollards themselves protect

♠Chapter 10: Site and Facility Security

PART III

Figure 10-2

Sidewalks, lights, and landscaping can be used for protection.

the facility from physical destruction by preventing people from driving their cars into

the building. The light emitted helps ensure that criminals do not have a dark place

to hide. And the lights and bollard placement guide people along the sidewalk to the

entrance, instead of using signs or railings. As shown in Figure 10-2, the landscape, sidewalks, lighted bollards, and clear sight lines are used as natural access controls. They work

together to give individuals a feeling of being in a safe environment and help dissuade

criminals by working as deterrents.

NOTE Bollards are short posts commonly used to prevent vehicular access and to protect a building or people walking on a sidewalk from vehicles. They can also be used to direct foot traffic.

Clear lines of sight and transparency can be used to discourage potential offenders.

because of the absence of places to hide or carry out criminal activities. The CPTED model shows how security zones can be created. An environment's space should be divided into zones with different security levels, depending upon who needs to

be in that zone and the associated risk. The zones can be labeled as controlled, restricted,

public, or sensitive. This is conceptually similar to asset classification, as described

in Chapter 5, in which different classifications are created, along with data handling

♠CISSP All-in-One Exam Guide

430

procedures and the level of protection that each classification requires. The same is true

of physical zones. Each zone should have a specific protection level required of it, which

will help dictate the types of controls that should be put into place.

Restricted zone

Restricted zone

Sensitive zone

Controlled

zone

Restricted zone

Security zone Sensitive zone

Restricted zone

Public zone

Public zone

Access control should be in place to control and restrict individuals from going from one security zone to the next. Access control should also be in place for all facility

entrances and exits. The security program development team needs to consider other

ways in which intruders can gain access to buildings, such as by climbing adjacent trees

to access skylights, upper-story windows, and balconies. The following controls are

commonly used for access controls within different organizations:

- Limit the number of entry points.
- Force all guests to go to a front desk and sign in before entering the environment.
- Reduce the number of entry points even further after hours or during the weekend,

when not as many employees are around.

- Implement sidewalks and landscaping to guide the public to a main entrance.
- Implement a back driveway for suppliers and deliveries that is not easily accessible

to the public.

- Provide lighting for the pathways the public should follow to enter a building to help encourage use of only one entry for access.
- ♠Chapter 10: Site and Facility Security

431

- Implement sidewalks and grassy areas to guide vehicle traffic to only enter and
- exit through specific locations.
- Provide parking in the front of the building (not the back or sides) so people will

be directed to enter the intended entrance.

Natural Surveillance

Surveillance can also take place through organized means (security guards), mechanical

means (security cameras), and natural strategies (straight lines of sight, low landscaping,

raised entrances). The goal of natural surveillance is to make criminals feel uncomfortable by providing many ways observers could potentially see them and to make all other

people feel safe and comfortable by providing an open and well-designed environment.

Natural surveillance is the use and placement of physical environmental features,

personnel walkways, and activity areas in ways that maximize visibility. Figure 10-3

illustrates a stairway in a parking garage designed to be open and allow easy observation.

Next time you are walking down a street and see a bench next to a building or you see

a bench in a park, know that the city has not allocated funds for these benches just in case

your legs get tired. These benches are strategically placed so that people will sit and watch

other people. This is a very good surveillance system. The people who are watching

others do not realize that they are actually protecting the area, but many criminals will

identify them and not feel as confident in carrying out some type of malicious deed.

Walkways and bicycle paths are commonly installed so that there will be a steady flow

of pedestrians who could identify malicious activity. Buildings might have large windows

that overlook sidewalks and parking lots for the same reason. Shorter fences might be

installed so people can see what is taking place on both sides of the fence.

Certain highrisk areas have more lighting than what is necessary so that people from a distance can see

what is going on. These high-risk areas could be stairs, parking areas, bus stops, laundry

rooms, children's play areas, dumpsters, and recycling stations. These constructs help

people protect people without even knowing it.

Territorial Reinforcement

The third CPTED strategy is territorial reinforcement, which creates physical designs

that emphasize or extend the organization's physical sphere of influence so legitimate users feel a sense of ownership of that space. Territorial reinforcement can be

PART III

These types of access controls are used all of the time, and we usually do not think

about them. They are built into the natural environment to manipulate us into

doing

what the owner of the facility wants us to do. When you are walking on a sidewalk that

leads to an office front door and there are pretty flowers on both sides of the sidewalk,

know that they are put there because people tend not to step off a sidewalk and crush

pretty flowers. Flowers are commonly placed on both sides of a sidewalk to help ensure

that people stay on the sidewalk. Subtle and sneaky, but these control mechanisms work.

More obvious access barriers can be naturally created (cliffs, rivers, hills), existing

manmade elements (railroad tracks, highways), or artificial forms designed specifically to

impede movement (fences, closing streets). These can be used in tandem or separately to

provide the necessary level of access control.

♠CISSP All-in-One Exam Guide

432

Figure 10-3

Open areas reduce the likelihood of criminal activity.

implemented through the use of walls, fences, landscaping, light fixtures, flags, clearly

marked addresses, and decorative sidewalks. The goal of territorial reinforcement is to

create a sense of a dedicated community. Organizations implement these elements so

employees feel proud of their environment and have a sense of belonging, which they

will defend if required to do so. These elements are also implemented to give potential

offenders the impression that they do not belong there, that their activities are at risk of

being observed, and that their illegal activities will not be tolerated or ignored.

Most corporate environments use a mix of the CPTED and target-hardening approaches. CPTED deals mainly with the construction of the facility, its internal

and external designs, and exterior components such as landscaping and lighting. If the

environment is built based on CPTED, then the target hardening is like icing on the

cake. The target-hardening approach applies more granular protection mechanisms, such

as locks and motion detectors.

♠Chapter 10: Site and Facility Security

Maintenance

Designing a Physical Security Program

If a team is organized to assess the protection level of an existing facility, it needs to

investigate the following:

- Construction materials of walls and ceilings
- Power distribution systems
- Communication paths and types (copper, telephone, fiber)
- Surrounding hazardous materials
- Exterior components:
- Topography
- Proximity to airports, highways, railroads
- Potential electromagnetic interference from surrounding devices
- Climate
- Soil
- Existing fences, detection sensors, cameras, barriers
- Operational activities that depend upon physical resources
- Vehicle activity
- Neighbors

To properly obtain this information, the team should do physical surveys and interview

various employees. All of this collected data will help the team to evaluate the current

controls, identify weaknesses, and ensure operational productivity is not negatively

affected by implementing new controls.

PART III

In the mid-1980s, crime was rampant in New York City subways. Looking for creative

solutions, the Metropolitan Transit Authority (MTA) hired George L. Kelling as a consultant. Kelling had written an influential book titled Broken Windows in which he presented

his theory that visible signs of crime create an environment that encourages more crime.

Make the signs go away, the theory goes, and so does the crime. In a large-scale experiment

involving the "broken windows" theory that extended into 2001, NYC saw a dramatic

decrease in crime, which strongly suggested the theory is valid.

The fourth and final CPTED strategy, maintenance, is an extension of the broken windows theory. It basically states that criminals will be more attracted to facilities that

look unkept because they'll assume that the occupants don't care as much about them

and probably lack the resources to properly maintain and secure them. Faced with a

well-kept facility with no burned-out lamps, no broken windows, and with manicured

lawns, criminals will think those inside the facility are more attentive, well

resourced, and possibly alert.

♠CISSP All-in-One Exam Guide

434

Although there are usually written policies and procedures on what should be taking

place pertaining to physical security, policies and reality do not always match up. It is

important for the team to observe how the facility is used, note daily activities that could

introduce vulnerabilities, and determine how the facility is protected. This information

should be documented and compared to the information within the written policy and

procedures. In most cases, existing gaps must be addressed and fixed. Just writing out a

policy helps no one if it is not actually followed.

Every organization must comply with various regulations, whether they be safety and

health regulations; fire codes; state and local building codes; military, energy, or labor

requirements; or some other agency's regulations. The organization may also have to comply

with requirements of the Occupational Safety and Health Administration (OSHA) and the

Environmental Protection Agency (EPA), if it is operating in the United States, or with

the requirements of equivalent organizations within another country. The physical security

program development team must understand all the regulations the organization must

comply with and how to reach compliance through physical security and safety procedures.

Legal issues must be understood and properly addressed as well. These issues may include

access availability for the disabled, liability issues, the failure to protect assets, and so on. This

long laundry list of items can get an organization into legal trouble if it is not doing what

it is supposed to. Occasionally, the legal trouble may take the form of a criminal case—for

example, if doors default to being locked when power is lost (fail-secure) and, as a result,

several employees are trapped and killed during a fire, criminal negligence may be alleged.

Legal trouble can also come in the form of civil cases—for instance, if a company does not

remove the ice on its sidewalks and a pedestrian falls and breaks his ankle, the pedestrian

may sue the company. The company may be found negligent and held liable for damages.

Every organization should have a facility safety officer, whose main job is to

understand

all the components that make up the facility and what the organization needs to do

to protect its assets and stay within compliance. This person should oversee facility

management duties day in and day out, but should also be heavily involved with the

team that has been organized to evaluate the organization's physical security program.

A physical security program is a collection of controls that are implemented and maintained to provide the protection levels necessary to be in compliance with the

physical security policy. The policy should embody all the regulations and laws that must

be adhered to and should set the risk level the organization is willing to accept.

By this point, the team has carried out a risk analysis, which consisted of identifying

the organization's vulnerabilities, threats, and business impact pertaining to the identified

threats. The program design phase should begin with a structured outline, which will

evolve into a framework. This framework will then be fleshed out with the necessary

controls and countermeasures. The outline should contain the program categories and

the necessary countermeasures. The following is a simplistic example:

- I. Deterrence of criminal activity
- A. Fences
- B. Warning signs
- C. Security guards
- D. Dogs

♠Chapter 10: Site and Facility Security

435

- II. Delay of intruders to help ensure they can be caught
- A. Locks
- B. Defense-in-depth measures
- C. Access controls
- III. Detection of intruders
- A. External intruder sensors
- B. Internal intruder sensors
- IV. Assessment of situations
- A. Security guard procedures
- B. Damage assessment criteria
- A. Communication structure (calling tree)
- B. Response force
- C. Emergency response procedures
- D. Police, fire, medical personnel

The team can then start addressing each phase of the security program, usually

starting with the facility.

Facility

When an organization decides to erect a building, it should consider several factors

before pouring the first batch of concrete. Of course, it should review land prices, customer population, and marketing strategies, but as security professionals, we are more

interested in the confidence and protection that a specific location can provide. Some

organizations that deal with top-secret or confidential information and processes make

their facilities unnoticeable so they do not attract the attention of would-be attackers.

The building may be hard to see from the surrounding roads, the organization's signs and

logos may be small and not easily noticed, and the markings on the building may not

give away any information that pertains to what is going on inside that building. It is a

type of urban camouflage that makes it harder for the enemy to seek out that organization as a target. This is very common for telecommunication facilities that contain critical infrastructure switches and other supporting technologies. When driving down the

road you might pass three of these buildings, but because they have no features that actually stand out, you likely would not even give them a second thought—which is the goal.

An organization should evaluate how close the facility would be to a police station, fire

station, and medical facilities. Many times, the proximity of these entities raises the real

estate value of properties, but for good reason. If a chemical company that manufactures

highly explosive materials needs to build a new facility, it may make good business

sense to put it near a fire station. (Although the fire station might not be so happy.)

If another company that builds and sells expensive electronic devices is expanding and

needs to move operations into another facility, police reaction time may be looked at

PART III

V. Response to intrusions and disruptions

♠CISSP All-in-One Exam Guide

436

when choosing one facility location over another. Each of these issues—police station,

fire station, and medical facility proximity—can also reduce insurance rates and must be

looked at carefully. Remember that a key goal of physical security is to ensure the safety

of personnel. Always keep that in mind when implementing any sort of physical security

control. Protect your fellow humans, be your brother's keeper, and then run. Some buildings are placed in areas surrounded by hills or mountains to help prevent

eavesdropping of electrical signals emitted by the facility's equipment. In some cases, the

organization itself will build hills or use other landscaping techniques to guard against

eavesdropping. Other facilities are built underground or right into the side of a mountain

for concealment and disguise in the natural environment and for protection from radar

tools, spying activities, and aerial bomb attacks.

In the United States there is an Air Force base built into a mountain close to Colorado

Springs, Colorado. The underground Cheyenne Mountain complex is made up of buildings, rooms, and tunnels. It has its own air intake supply, as well as water, fuel, and

sewer lines. This is where the North American Aerospace Defense Command (NORAD) carries out its mission and apparently, according to many popular movies, is where you

should be headed if the world is about to be blown up.

Construction

Physical construction materials and structure composition need to be evaluated for their

appropriateness to the site environment, their protective characteristics, their utility, and

their costs and benefits. Different building materials provide various levels of fire protection

and have different rates of combustibility, which correlate with their fire ratings. When making structural decisions, the decision of what type of construction material to use (wood,

concrete, or steel) needs to be considered in light of what the building is going to be used for.

If an area will be used to store documents and old equipment, it has far different needs and

legal requirements than if it is going to be used for employees to work in every day.

The load (how much weight can be held) of a building's walls, floors, and ceilings

needs to be estimated and projected to ensure the building will not collapse in different

situations. In most cases, this is dictated by local building codes. The walls, ceilings,

and floors must contain the necessary materials to meet the required fire rating and to

protect against water damage. The windows (interior and exterior) may need to provide

ultraviolet (UV) protection, may need to be shatterproof, or may need to be translucent

or opaque, depending on the placement of the window and the contents of the building.

The doors (exterior and interior) may need to have directional openings, have the same

fire rating as the surrounding walls, prohibit forcible entries, display emergency egress

markings, and—depending on placement—have monitoring and attached alarms. In most buildings, raised floors are used to hide and protect wires and pipes, and it is

important to ensure any raised outlets are properly grounded.

Building codes may regulate all of these issues, but there are still many options within

each category that the physical security program development team should review for

extra security protection. The right options should accomplish the organization's security and functionality needs and still be cost-effective.

♠Chapter 10: Site and Facility Security

437

When designing and building a facility, the following major items need to be addressed

from a physical security point of view.

Walls:

- Combustibility of material (wood, steel, concrete)
- Fire rating
- Reinforcements for secured areas

Doors:

Ceilings:

- Combustibility of material (wood, steel, concrete)
- Fire rating
- Weight-bearing rating
- Drop-ceiling considerations

Windows:

- Translucent or opaque requirements
- Shatterproof
- Alarms
- Placement
- Accessibility to intruders

PART III

- Combustibility of material (wood, pressed board, aluminum)
- Fire rating
- Resistance to forcible entry
- Emergency marking
- Placement
- Locked or controlled entrances
- Alarms

- Secure hinges
- Directional opening
- Electric door locks that revert to an unlocked state for safe evacuation in power outages
- Type of glass-shatterproof or bulletproof glass requirements

♠CISSP All-in-One Exam Guide

438

Flooring:

- Weight-bearing rating
- Combustibility of material (wood, steel, concrete)
- Fire rating
- Raised flooring
- Nonconducting surface and material

Heating, ventilation, and air conditioning:

- Positive air pressure
- Protected intake vents
- Dedicated power lines
- Emergency shutoff valves and switches
- Placement

Electric power supplies:

- Backup and alternative power supplies
- Clean and steady power source
- Dedicated feeders to required areas
- Placement and access to distribution panels and circuit breakers Water and gas lines:
- Shutoff valves—labeled and brightly painted for visibility
- Positive flow (material flows out of building, not in)
- Placement-properly located and labeled

Fire detection and suppression:

- Placement of sensors and detectors
- Placement of suppression systems
- Type of detectors and suppression agents

The risk analysis results will help the team determine the type of construction material that should be used when constructing a new facility. Several grades of building

construction are available. For example, light frame construction material provides the

least amount of protection against fire and forcible entry attempts. It is composed of

untreated lumber that would be combustible during a fire. Light frame construction

material is usually used to build homes, primarily because it is cheap, but also

homes typically are not under the same types of fire and intrusion threats that office $\ensuremath{\mathsf{office}}$

buildings are.

439

Entry Points

Understanding the organization's needs and types of entry points for a specific building

is critical. The various types of entry points may include doors, windows, roof access,

fire escapes, chimneys, and service delivery access points. Second and third entry points

must also be considered, such as internal doors that lead into other portions of the building and to exterior doors, elevators, and stairwells. Windows at the ground level should

be fortified because they could be easily broken. Fire escapes, stairwells to the roof, and

chimneys often are overlooked as potential entry points.

NOTE Ventilation ducts and utility tunnels can also be used by intruders and thus must be properly protected with sensors and access control mechanisms.

PART III

Heavy timber construction material is sometimes used for office buildings. Combustible

lumber is still used in this type of construction, but there are requirements on the thickness

and composition of the materials to provide more protection from fire. The construction ${\sf Construction}$

materials must be at least 4 inches in thickness. Denser woods are used and are fastened with

metal bolts and plates. Whereas light frame construction material has a fire survival rate of

30 minutes, the heavy timber construction material has a fire survival rate of one hour.

A building could be made up of incombustible material, such as steel, which provides

a higher level of fire protection than the previously mentioned materials, but loses its

strength under extreme temperatures, something that may cause the building to collapse.

So, although the steel will not burn, it may melt and weaken. If a building consists of

fire-resistant material, the construction material is fire retardant and may have steel rods

encased inside of concrete walls and support beams. This provides the most protection

against fire and forced-entry attempts.

The team should choose its construction material based on the identified threats of the

organization and the fire codes to be complied with. If a company is just going to have some

office workers in a building and has no real adversaries interested in destroying the facility,

then the light frame or heavy timber construction material would be used. Facilities for

government organizations, which are under threat by domestic and foreign terrorists, would

be built with fire-resistant materials. A financial institution would also use fire-resistant

and reinforcement material within its building. This is especially true for its exterior walls,

through which thieves may attempt to drive vehicles to gain access to the vaults.

Calculations of approximate penetration times for different types of explosives and attacks

are based on the thickness of the concrete walls and the gauge of rebar used. (Rebar, short for

reinforcing bar, refers to the steel rods encased within the concrete.) So even if the concrete

were damaged, it would take longer to actually cut or break through the rebar. Using thicker

rebar and properly placing it within the concrete provides even more protection. Reinforced walls, rebar, and the use of double walls can be used as delaying mechanisms.

The idea is that it will take the bad guy longer to get through two reinforced walls, which

gives the response force sufficient time (hopefully) to arrive at the scene and stop the attacker.

♠CISSP All-in-One Exam Guide

440

The weakest portion of the structure, usually its doors and windows, will likely be attacked first. With regard to doors, the weaknesses usually lie within the frames,

hinges, and door material. The bolts, frames, hinges, and material that make up the door

should all provide the same level of strength and protection. For example, if a company

implements a heavy, nonhollow steel door but uses weak hinges that could be easily

extracted, the company is just wasting money. The attacker can just remove the hinges

and remove this strong and heavy door.

The door and surrounding walls and ceilings should also provide the same level of strength. If another company has an extremely fortified and secure door, but the

surrounding wall materials are made out of regular light frame wood, then it is also wasting

money on doors. There is no reason to spend a lot of money on one countermeasure that

can be easily circumvented by breaking a weaker countermeasure in proximity.

Different door types for various functionalities include the following:

• Vault doors

- Personnel doors
- Industrial doors
- Vehicle access doors
- Bullet-resistant doors

Doors can be hollow-core or solid-core. The team needs to understand the various entry types and the potential forced-entry threats, which will help the team determine

what type of door should be implemented. Hollow-core doors can be easily penetrated

by kicking or cutting them; thus, they are usually used internally. The team also has a

choice of solid-core doors, which are made up of various materials to provide different

fire ratings and protection from forced entry. As stated previously, the fire rating and

protection level of the door need to match the fire rating and protection level of the

surrounding walls.

Bulletproof doors are also an option if there is a threat that damage could be done to

resources by shooting through the door. These types of doors are constructed in a manner

that involves sandwiching bullet-resistant and bulletproof material between wood or steel

veneers to still give the door some aesthetic qualities while providing the necessary levels

of protection.

Hinges and strike plates should be secure, especially on exterior doors or doors used

to protect sensitive areas. The hinges should have pins that cannot be removed, and the

door frames must provide the same level of protection as the door itself.

Fire codes dictate the number and placement of doors with panic bars on them. These

are the crossbars that release an internal lock to allow a locked door to open. Panic bars can

be on regular entry doors and also on emergency exit doors. Those are the ones that usually

have the sign that indicates the door is not an exit point and that an alarm will go off if the

door is opened. It might seem like fun and a bit tempting to see if the alarm will really go

off or not-but don't try it. Security people are not known for their sense of humor.

♠Chapter 10: Site and Facility Security

441

Mantraps and turnstiles can be used so unauthorized individuals entering a facility

cannot get in or out if it is activated. A mantrap is a small room with two doors. The first

door is locked; a person is identified and authenticated by a security guard, biometric

system, smart card reader, or swipe card reader. Once the person is authenticated and

access is authorized, the first door opens and allows the person into the mantrap. The

first door locks and the person is trapped. The person must be authenticated again before

the second door unlocks and allows him into the facility. Some mantraps use biometric

systems that weigh the person who enters to ensure that only one person at a time is

entering the mantrap area. This is a control to counter piggybacking.

- Standard No extra protection. The cheapest and lowest level of protection.
- Tempered Glass is heated and then cooled suddenly to increase its integrity and strength.
- Acrylic A type of plastic instead of glass. Polycarbonate acrylics are stronger

than regular acrylics.

- Wired A mesh of wire is embedded between two sheets of glass. This wire helps prevent the glass from shattering.
- Laminated The plastic layer between two outer glass layers. The plastic layer helps increase its strength against breakage.
- Solar window film Provides extra security by being tinted and offers extra strength due to the film's material.
- Security film Transparent film is applied to the glass to increase its strength.

Site and Facility Controls

Having covered the general processes and principles we should use in planning security

for our sites and facilities, we now turn our attention to examples of specific controls we

should consider. The following section discuss the most common or important controls

you should know both for the exam and in the conduct of your job.

Work Area Security

The largest total area in an organization's facilities is usually devoted to workspaces for

its staff. In terms of facility security, these spaces comprise the largest attack surface for

the organization. This is where malicious insiders, thieves, and active shooters will find

the most target-rich environment. For this reason, we need to consider the threats to our

workforce occupying those spaces and implement controls to keep them and their assets

protected. Just like we segment our networks to limit where digital intruders can operate,

PART III

Window Types Though most of us would probably think of doors as the obvious entry

points, windows deserve every bit as much attention in the design of secure facilities. Like

doors, different types of windows afford various degrees of protection against intrusions.

The following sums up the types of windows that can be used:

♠CISSP All-in-One Exam Guide

442

we should separate our workspaces to make it harder for physical intruders to accomplish their objectives. Internal partitions are used to create barriers between one area and

another. These partitions can be used to segment separate work areas, but should not be

used in protected areas that house sensitive systems and devices because they would limit

the ability to detect malicious activity on those systems.

Movement from one area to another should ideally be restricted using keycard entry

systems, which are electronic locks that are unlocked by keycards. Keycards are plastic

cards with magnetic or radio frequency identification (RFID) components that act as

physical keys on special electronic locks. Alternatively, doors between areas could be

remotely locked and unlocked by security guards to restrict the movement of an assailant,

protect occupants, or facilitate evacuations. To facilitate this remote operation, all work

areas should be covered by security cameras that automatically record all activity and save

the video files, at least for several days.

Beware of the dropped ceilings that many office buildings have. These can cause the

interior partitions or even walls to not extend to the true ceiling—only to the dropped

ceiling. An intruder can lift a ceiling panel and climb over the partition. This example

of intrusion is shown in Figure 10-4. In many situations, this would not require forced

entry, specialized tools, or much effort. (In some office buildings, this may even be

possible from a common public-access hallway.) These types of internal partitions should

not be relied upon to provide protection for sensitive areas.

Another common control for work areas is a clean desk policy. This means that, before

staff members leave their desks for extended periods (e.g., lunch, end of day), they remove

all documents and pilferable items and store them in locked drawers. This ensures that

sensitive documents are not lying around for wandering eyes (or cameras) to see. At the

Ceiling panels

Server room

Computer room

Partition

Figure 10-4

An intruder can lift ceiling panels and enter a secured area with little effort.

◆Chapter 10: Site and Facility Security

443

Restricted Areas

In some cases, a work area can be so sensitive that we must take extreme measures

to ensure only authorized personnel are allowed in. Examples of these types of work

areas are sensitive compartmented information facilities (SCIFs) used by governments to protect top secret information; police crime labs, where the integrity of

evidence is absolutely paramount; research and development laboratories conducting particularly sensitive work; and many data centers. The controls we would use

in these sensitive areas are similar to the ones previously discussed but are much

stricter and more rigorously enforced.

Data Processing Facilities

With the growing trend toward cloud computing, data processing facilities such as server

rooms and data centers are less common than once was the case. Still, many organizations, not to mention providers of cloud services, can't get away from having these facilities. Since most servers, routers, switches, mainframes, and data centers can be controlled

remotely and seldom require physical interaction, our data processing facilities have few

people milling around and potentially spilling coffee. This lack of personnel sitting and

working in them for long periods means these data centers can be constructed in a manner that is efficient for equipment instead of people.

On the other hand, there are situations in which people may have to be physically

in the data center, perhaps for very extended periods of time (equipment installations/

upgrades, data center infrastructure upgrades and reconfigurations, incident response,

forensic data acquisition, etc.). Consequently, the inhospitable conditions (cold, dry

environment; lack of comfortable workspaces; extremely high decibel levels)
should be

taken into account when deploying such personnel.

Data centers and server rooms should be located in the core areas of a facility, with

strict access control mechanisms and procedures. The access control mechanisms may be

smart card readers, biometric readers, or combination locks. These restricted areas should

have only one access door, but fire code requirements typically dictate there must be at $\frac{1}{2}$

least two doors to most data centers and server rooms. Only one door should be used

for daily entry and exit, and the other door should be used only in emergency situations.

This second door should not be an access door, which means people should not be able

to come in through this door. It should be locked, but should have a panic bar that will

release the lock if pressed, possibly sounding an alarm.

These restricted areas ideally should not be directly accessible from public areas like

stairways, corridors, loading docks, elevators, and restrooms. This helps ensure that the

people who are by the doors to secured areas have a specific purpose for being there,

versus being on their way to the restroom or standing around in a common area gossiping about the CEO.

PART III

end of the shift or work day, somebody is assigned the task of checking all desks to ensure compliance with the policy.

♠CISSP All-in-One Exam Guide

444

Because data centers usually hold expensive equipment and the organization's critical

data, their protection should be thoroughly thought out before implementation. A data

center should not be located on an upper floor of a building, because that would make

accessing it in a timely fashion in case of a fire more difficult for an emergency crew.

By the same token, data centers should not be located in basements where flooding can

affect the systems. And if a facility is in a hilly area, the data center should be located well

above ground level. Data centers should be located at the core of a building so that if

there is some type of attack on the building, the exterior walls and structures will absorb

the hit and hopefully the data center will not be damaged.

Which access controls and security measures should be implemented for the data

center

depends upon the sensitivity of the data being processed and the protection level required.

Alarms on the doors to the data processing center should be activated during off-hours,

and there should be procedures dictating how to carry out access control during normal

business hours, after hours, and during emergencies. If a combination lock is used to enter

the data processing center, the combination should be changed at least every six months

and also after an employee who knows the code leaves the organization. The various controls discussed next are shown in Figure 10-5. The team responsible

for designing a new data center (or evaluating a current data center) should understand

all the controls shown in Figure 10-5 and be able to choose what is needed. Biometric access and exit sensors

Seismically braced server racks

Continuous video surveillance

Electronic motion sensors

UPS and backup generators

Redundant HVAC controlled environments

Security breach alarm Data Center 24 On-premises security officers

Figure 10-5

7 365 Server operations

monitoring

Gas-based fire suppression system

A data center should have many physical security controls.

♠Chapter 10: Site and Facility Security

445

The data processing center should be constructed as one room rather than different

individual rooms. The room should be away from any of the building's water pipes in

case a break in a line causes a flood. The vents and ducts from the heating, ventilation,

and air conditioning (HVAC) system should be protected with some type of barrier bars

and should be too small for anyone to crawl through and gain access to the center. The

data center must have positive air pressure, so no contaminants can be sucked into the

room and into the computers' fans.

Smoke detectors or fire sensors should be implemented, and portable fire extinguishers

should be located close to the equipment and should be easy to see and access (see "Fire

Safety" later in the chapter for details). Water sensors should be placed under the raised

floors. Since most of the wiring and cables run under the raised floors, it is important that

water does not get to these places and, if it does, that an alarm sound if water is detected.

Water can cause extensive damage to equipment, flooring, walls, computers, and facility foundations. It is important that an organization be able to detect leaks and

unwanted water. The detectors should be under raised floors and on dropped ceilings (to

detect leaks from the floor above it). The location of the detectors should be documented,

and their position marked for easy access. As smoke and fire detectors should be tied to

an alarm system, so should water detectors. The alarms usually just alert the necessary

staff members and not everyone in the building. The staff members who are responsible

for following up when an alarm sounds should be trained properly on how to

any potential water damage. Before anyone pokes around to see where water is or is not

pooling in places it does not belong, the electricity for that particular zone of the building

should be temporarily turned off. Water detectors can help prevent damage to

- Equipment
- Flooring
- Walls
- Computers
- Facility foundations

Location of water detectors should be

- Under raised floors
- On dropped ceilings

PART III

TIP If there is any type of water damage in a data center or facility, mold and mildew could easily become a problem. Instead of allowing things to "dry out on their own," many times it is better to use industry-strength dehumidifiers, water movers, and sanitizers to ensure secondary damage does not occur.

♠CISSP All-in-One Exam Guide

446

It is important to maintain the proper temperature and humidity levels within data

centers, which is why an HVAC system should be implemented specifically for this room. Too high a temperature can cause components to overheat and turn off; too low a

temperature can cause the components to work more slowly. If the humidity is high, then

corrosion of the computer parts can take place; if humidity is low, then static electricity

can be introduced. Because of this, the data center must have its own temperature and

humidity controls that are separate from those for the rest of the building.

It is best if the data center is on a different electrical system than the rest of the building,

if possible. Thus, if anything negatively affects the main building's power, it will not carry

over and affect the center. The data center may require redundant power supplies, which

means two or more feeders coming in from two or more electrical substations. The idea is

that if one of the power company's substations were to go down, the organization would

still be able to receive electricity from the other feeder. But just because an organization

has two or more electrical feeders coming into its facility does not mean true redundancy

is automatically in place. Many organizations have paid for two feeders to come into

their building, only to find out both feeders were coming from the same substation! This

defeats the whole purpose of having two feeders in the first place.

Data centers need to have their own backup power supplies, either an uninterrupted

power supply (UPS) or generators. The different types of backup power supplies are

discussed later in the chapter, but it is important to know at this point that the power

backup must be able to support the load of the data center.

Many organizations choose to use large glass panes for the walls of the data center

so personnel within the center can be viewed at all times. This glass should be shatterresistant since the window is acting as an exterior wall. The center's doors should not

be hollow, but rather secure solid-core doors. Doors should open out rather than in, so

they don't damage equipment when opened. Best practices indicate that the door frame

should be fixed to adjoining wall studs and that there should be at least three hinges per

door. These characteristics would make the doors much more difficult to break down.

Distribution Facilities

Distribution facilities are systems that distribute communications lines, typically dividing higher-bandwidth lines into multiple lower-bandwidth lines. A building typically

has one main distribution facility (MDF) where one or more external data lines are fed

into the server room, data center, and/or other smaller intermediate distribution facilities

(IDFs). An IDF usually provides individual lines or drops to multiple endpoints, though

it is possible to daisy-chain IDFs as needed.

Larger IDFs are usually installed in small rooms normally called wiring closets. All of

the design considerations for unstaffed server rooms and data centers discussed in the

previous section also apply to these facilities. It is critical to think of these as the sensitive

IT facilities that they are and not as just closets. We've seen too many organizations that

allow their IDF rooms to do double duty as janitors' closets.

Smaller IDFs are oftentimes installed in rooms that have a large number of network

endpoints. They can be as small as a single switch and small patch panel on a shelf or as

big as a cabinet. Unlike an MDF, an IDF is usually not enclosed in its own room, which

♠Chapter 10: Site and Facility Security

447

makes it more susceptible to tampering and accidental damage. Whenever possible, an

IDF should be protected by a locked enclosure. Ideally, it is elevated to reduce the risk

of flood or collision damage and to make it more visible should someone tamper with it.

Another consideration that is oftentimes overlooked is placing the IDF away from overhead sprinklers, pipes, or HVAC ducts.

Storage Facilities

Media Storage

We discussed in Chapter 5 that the information life cycle includes an archival phase during which information is not regularly used but we still need to retain it. This happens,

for example, when we close accounts but still need to keep the records for a set number

of years, or when we do backups. In any event, we have to keep a large number of disks,

magnetic tapes, or even paper files for prolonged periods until we either need them or are

able to dispose of them. This has to happen in a secure location that meets the requirements discussed for server rooms and data centers. Unfortunately, media storage is sometimes not given the importance it deserves, which can result in the loss or compromise

of important information.

Evidence Storage

Evidence storage facilities are even more sensitive because any compromise, real or perceived, could render evidence inadmissible in court. We will cover forensic investigations

in Chapter 22, but every organization with a dedicated IT staff should probably have a

secure facility in which to store evidence. The two key requirements for evidence storage

facilities are that they are properly secured and that all access and transfers are logged.

PART III

Storage facilities are often overlooked when it comes to security considerations other

than, perhaps, locking them. While a simple lock may be all we need to think of when

we're storing office supplies and basic tools, we should really think about what it is that

we are protecting. In many cases, the physical locks we use are either low grade (in other

words, easily picked) or have keys that are shared by multiple people. Unlike their modern electronic counterparts, these locks lack built-in auditing tools to see who opened

them and when. If you are storing anything that you'd hate to have go missing, you probably want to think long and hard about who gets a key, how it's signed out, and how to

periodically inventory the storage area.

This is particularly true of storage facilities in which you store computing

equipment.

Depending on your organizational procedures, you may be storing computers with storage devices that have not yet been securely wiped or baselined. This means there are

security risks if someone gets their hands on them apart from that of theft. You also need

to worry about the environmental conditions of the storage facility, since computers

don't do so well in hot, humid areas over long periods.

These are just examples to get you thinking. Whatever is stored in the facility should

impact the security controls you put on it. There are two types of storage facilities that

deserve special attention, which are those we use to store media and those we use to store

evidence. Let's take a closer look at each.

♠CISSP All-in-One Exam Guide

448

Ideally, only select incident handlers and forensic investigators have access to the facility.

Unless forensic investigations are part of your business, you will likely only need a rugged

cabinet with a good lock and a register in which to record who opened/closed it and what

was done in it. This is yet another example of a situation in which a technical control

alone (like the cabinet or safe) won't do the job. You also have to have a good policy (like

logging all access to the contents) that is rigorously enforced.

Utilities

Utilities, as with storage, is another area on which many of us don't spend a lot of time

thinking about security. Still, utilities can pose significant risks to our sites and facilities.

Local construction codes may address safety issues, but they do very little to otherwise

help us protect our organizations.

Water and Wastewater

As the saying goes, water is life. Without clean water and wastewater services, our staffed

facilities would not be able to operate safely for any length of time.

Interruptions to these services, therefore, could require the evacuation of most or all personnel from a facility, which

could degrade its security posture and create a window of opportunity for nefarious activity.

An abundance of water in the wrong place can also cause serious problems. As we discussed previously with regard to data centers and distribution facilities, it is critical to

route water pipes (or, more realistically, position assets) so that a ruptured or leaking pipe

will not cause equipment damage.

During facility construction, the physical security team must make certain that water,

steam, and gas lines have proper shutoff valves, as shown in Figure 10-6, and positive

drains, which means their contents flow out instead of in. If there is ever a break in a main

water pipe, the valve to shut off water flow must be readily accessible. Similarly, in case of

fire in a building, the valve to shut off the gas lines must be readily accessible. In case of

a flood, an organization wants to ensure that material cannot travel up through the water

pipes and into its water supply or facility. Facility, operations, and security personnel

should know where these shutoff valves are, and there should be strict procedures to

follow in these types of emergencies. This will help reduce the potential damage.

Electric Power

Power failure, particularly over a long stretch of time, can be devastating to an unprepared organization. Having good plans to fall back on is crucial to ensure that a business

will not be drastically affected by storms, high winds, hardware failure, lightning, or

other events that can stop or disrupt power supplies. A continuous supply of electricity

assures the availability of organizational resources; thus, a security professional must be

familiar with the threats to electric power and the corresponding countermeasures.

Power Backup Several types of power backup capabilities exist. Before you choose one, you should calculate the total cost of anticipated downtime and its effects. This

information can be gathered from past records and other businesses in the same area on

the same power grid and plugged into the annualized loss expectancy (ALE) formula we

♠Chapter 10: Site and Facility Security

449
Figure 10-6
Water, steam, and gas lines should have emergency shutoff valves.

PART III

discussed in Chapter 2. Essentially, you want to calculate the annual expected cost of

power outages in terms of lost revenue, recovery costs, and the like. This

amount will tell

you whether it makes sense to run a secondary line that is fed by a different grid or to buy

a backup generator, both of which are significant investments.

If you plan to buy a generator, you also have to determine how long it will be expected to run each year, which tells you how big of a fuel storage tank you need and

what the expected fuel costs are. Keep in mind that you will have to periodically run the

generator to ensure that it remains ready, and also be aware that some fuels go bad after

sitting around for several months. As always, we have to ensure the cure is not worse

than the illness.

Just having a generator in the backyard should not give you that warm fuzzy feeling

of protection. An alternative power source should be tested periodically to make sure

it works and to the extent expected. Power interruption drills should be performed

♠CISSP All-in-One Exam Guide

450

periodically to avoid nasty surprises. It is never good to find yourself in an emergency

only to discover that the organization added a bunch of power-hungry assets since you

bought the generator and it is now too small to power them all.

Electric Power Issues Electric power enables us to be productive and functional in many

different ways, but if it is not installed, monitored, and respected properly, it can do us great

harm. When clean power is being provided, the power supply contains no interference

or voltage fluctuation. The possible types of interference (line noise) are electromagnetic

interference (EMI) and radio frequency interference (RFI), which can cause disturbance to the

flow of electric power while it travels across a power line, as shown in Figure 10-7.

EMI is the effect of unwanted energy on an electrical system caused by radiations

from another, nearby, electrical system. EMI can be created by the difference between

three wires—hot, neutral, and ground—and the magnetic field they create. Lightning

and electrical motors can induce EMI, which could then interrupt the proper flow of

electrical current as it travels over wires to, from, and within buildings. RFI, which is the

subset of EMI that occurs in the radio frequency (RF) portion of the electromagnetic

(EM) spectrum, can be caused by anything that creates radio waves. Fluorescent

lighting

is one of the main causes of RFI within buildings today. So, does that mean we need

to rip out all the fluorescent lighting? That's one choice, but we could also just use

shielded cabling where fluorescent lighting could cause a problem. If you take a break

from your reading, climb up into your office's dropped ceiling, and look around, you

would probably see wires bundled and tied up to the true ceiling. If your office is using

fluorescent lighting, the power and data lines should not be running over, or on top of,

the fluorescent lights. This is because the radio frequencies being given off can interfere

with the data or power current as it travels through these wires. Now, get back down from

the ceiling. We have work to do.

Interference interrupts the flow of an electrical current, and fluctuations can actually

deliver a different level of voltage than what was expected. Each fluctuation can be

Fluorescent light

Figure 10-7 RFI and EMI can cause line noise on power lines.

RFI

Power source

Electrical current being affected Motor EMI

♠Chapter 10: Site and Facility Security

451

damaging to devices and people. The following explains the different types of voltage

fluctuations possible with electric power:

Power excess:

- Spike Momentary high voltage
- Surge Prolonged high voltage

Power loss:

- Fault Momentary power outage
- Blackout Prolonged, complete loss of electric power Power degradation:

When an electrical device is turned on, it can draw a large amount of current, which is

referred to as in-rush current. If the device sucks up enough current, it can cause a sag in the

available power for surrounding devices. This could negatively affect their performance.

As stated earlier, it is a good idea to have the data processing center and devices on a

different electrical wiring segment from that of the rest of the facility, if possible, so

the devices will not be affected by these issues. For example, if you are in a building or

house without efficient wiring and you turn on a vacuum cleaner or microwave, you

may see the lights quickly dim because of this in-rush current. The drain on the power

supply caused by in-rush currents still happens in other environments when these types

of electrical devices are used—you just might not be able to see the effects. Any type of

device that would cause such a dramatic in-rush current should not be used on the same

electrical segment as data processing systems.

Because these and other occurrences are common, mechanisms should be in place to detect unwanted power fluctuations and protect the integrity of your data processing

environment. Voltage regulators and line conditioners can be used to ensure a clean and

smooth distribution of power. The primary power runs through a regulator or conditioner.

They have the capability to absorb extra current if there is a spike and to store energy to

add current to the line if there is a sag. The goal is to keep the current flowing at a nice,

steady level so neither motherboard components nor employees get fried.

Many data centers are constructed to take power-sensitive equipment into consideration.

Because surges, sags, brownouts, blackouts, and voltage spikes frequently cause data

corruption, the centers are built to provide a high level of protection against these events.

Other types of environments usually are not built with these things in mind and do not

provide this level of protection. Offices usually have different types of devices connected

and plugged into the same outlets. Outlet strips are plugged into outlet strips, which are

connected to extension cords. This causes more line noise and a reduction of voltage to each

device. Figure 10-8 depicts an environment that can cause line noise, voltage problems, and

possibly a fire hazard.

PART III

- Sag/dip Momentary low-voltage condition, from one cycle to a few seconds
- Brownout Prolonged power supply that is below normal voltage
- In-rush current Initial surge of current required to start a load

♠CISSP All-in-One Exam Guide

452

Figure 10-8 This configuration can cause a lot of line noise and poses a fire hazard.

Power Protection Protecting power can be done in three ways: through online UPSs,

through standby UPSs, and through the power line conditioners discussed in the previous

section. UPSs use battery packs that range in size and capacity. Online UPS systems use

AC line voltage to charge a bank of batteries. When in use, the UPS has an inverter that

changes the DC output from the batteries into the required AC form and regulates the

voltage as it powers computer devices. This conversion process is shown in Figure 10-9.

Online UPS

DC

AC

Inverter

Figure 10-9 A UPS device converts DC current from its internal or external batteries to usable AC by using an inverter.

♠Chapter 10: Site and Facility Security

453

Heating, Ventilation, and Air Conditioning

Improper environmental controls can cause damage to services, hardware, and lives.

Interruption of some services can cause unpredicted and unfortunate results. HVAC systems and air-quality controls can be complex and contain many variables. They all need

to be operating properly and to be monitored regularly.

Most electronic equipment must operate in a climate-controlled atmosphere. Although

it is important to keep the atmosphere at a proper working temperature, you must also

be aware that the components within the equipment can suffer from overheating even

in a climate-controlled atmosphere if the internal computer fans are not cleaned or are

blocked. When devices are overheated, the components can expand and contract, which

causes components to change their electronic characteristics, reducing their effectiveness

or damaging the system overall.

NOTE The climate issues involved with a data processing environment are why it needs its own separate HVAC system. Maintenance procedures should be documented and properly followed. HVAC activities should be recorded and reviewed annually.

Maintaining appropriate temperature and humidity is important in any facility, especially facilities with computer systems. Improper levels of either can cause damage to

computers and electrical devices. High humidity can cause corrosion, and low humidity

can cause excessive static electricity. This static electricity can short out devices and cause

the loss of information.

Lower temperatures can cause mechanisms to slow or stop, and higher temperatures can cause devices to use too much fan power and eventually shut down. Table 10-1 lists

different components and their corresponding damaging temperature levels.

PART III

Online UPS systems have the normal primary power passing through them day in and day out. They constantly provide power from their own inverters, even when the electric

power is in proper use. Since the environment's electricity passes through this type of

UPS all the time, the UPS device is able to quickly detect when a power failure takes

place. An online UPS can provide the necessary electricity and picks up the load after a

power failure much more quickly than a standby UPS.

Standby UPS devices stay inactive until a power line fails. The system has sensors that

detect a power failure, and the load is switched to the battery pack. The switch to the

battery pack is what causes the small delay in electricity being provided. So an online

UPS picks up the load much more quickly than a standby UPS, but costs more, of course.

An organization should identify critical systems that need protection from interrupted

power supplies and then estimate how long secondary power would be needed and how

much power is required per device. Some UPS devices provide just enough power to allow systems to shut down gracefully, whereas others allow the systems to run for a

longer period. An organization needs to determine whether systems should only have

a big enough power supply to allow the organization to shut down properly or should

have sufficient power to keep the organization up and running so that critical operations

remain available.

♠CISSP All-in-One Exam Guide

454
Table 10-1
Components
Affected
by Specific
Temperatures

Material or Component

Damaging Temperature

Computer systems and peripheral devices

175°F

Magnetic storage devices

100°F

Paper products

350°F

Fire Safety

The subject of physical security would not be complete without a discussion on fire safety.

Every site and facility must meet national and local standards pertaining to fire prevention, detection, and suppression methods. Fire prevention includes training employees on

how to prevent fires, how to react properly when faced with a fire, supplying the right

equipment and ensuring it is in working order, making sure there is an easily reachable

fire suppression supply, and storing combustible elements in the proper manner.

prevention may also include using proper noncombustible construction materials and

designing the facility with containment measures that provide barriers to minimize the

spread of fire and smoke. These thermal or fire barriers can be made up of different types

of construction material that is noncombustible and has a fire-resistant coating applied.

Fire detection response systems come in many different forms. Manual detection response systems are the red pull boxes you see on many building walls. Automatic

detection response systems have sensors that react when they detect the presence of fire

or smoke. We will review different types of detection systems in the next section.

Fire suppression is the use of a suppression agent to put out a fire. Fire suppression

can take place manually through handheld portable extinguishers or through automated

systems such as water sprinkler systems or CO2 discharge systems. The upcoming "Fire

Suppression" section reviews the different types of suppression agents and where they are

best used. Automatic sprinkler systems are widely used and highly effective in protecting

buildings and their contents. When deciding upon the type of fire suppression systems

to install, an organization needs to evaluate many factors, including an estimate of the

occurrence rate of a possible fire, the amount of damage that could result, the types of fires

that would most likely take place, and the types of suppression systems to choose from.

Fire protection processes should consist of implementing early smoke or fire detection

devices and shutting down systems until the source of the fire is eliminated. A warning

signal may be sounded by a smoke or fire detector before the suppression agent is released

so that if it is a false alarm or a small fire that can be handled without the automated

suppression system, someone has time to shut down the suppression system.

Types of Fire Detection

Fires present a dangerous security threat because they can damage hardware and data

and risk human life. Smoke, high temperatures, and corrosive gases from a fire can cause

devastating results. It is important to evaluate the fire safety measurements of a building

and the different sections within it.

A fire begins because something ignited a combustible substance (the fuel). Ignition

sources can be failure of an electrical device, improper storage of combustible materials.

♠Chapter 10: Site and Facility Security

455

Figure 10-10 used on.

Portable extinguishers are marked to indicate what type of fire they should be

PART III

carelessly discarded cigarettes, malfunctioning heating devices, and arson. A fire needs

fuel (paper, wood, liquid, and so on) and oxygen to continue to burn and grow.

more fuel per square foot, the more intense the fire will become. A facility should be

built, maintained, and operated to minimize the accumulation of fuels that can feed fires.

There are six classes (A, B, C, D, E, and F) of fire, which are explained in the "Fire

Suppression" section. You need to know the differences between the types of fire so you

know how to properly extinguish each type. Portable fire extinguishers have markings

that indicate what type of fire they should be used on, as illustrated in Figure 10-10.

The markings denote what types of chemicals are within the canisters and what types

of fires they have been approved to be used on. Portable fire extinguishers should be

located within 50 feet of any electrical equipment and also near exits. The extinguishers

should be marked clearly, with an unobstructed view. They should be easily reachable

and operational by employees and inspected quarterly.

A lot of computer systems are made of components that are not combustible but that will melt or char if overheated. Most computer circuits use only 2 to 5 volts of

direct current, which usually cannot start a fire. If a fire does happen in a server room,

it will most likely be an electrical fire caused by overheating of wire insulation or by

overheating components that ignite surrounding plastics. Prolonged smoke usually occurs before combustion.

♠CISSP All-in-One Exam Guide

456

Fire Resistance Ratings

Fire resistance ratings are the result of tests carried out in laboratories using specific

configurations of environmental settings. ASTM International is the organization that creates the standards that dictate how these tests should be performed and how to properly interpret the test results. ASTM International accredited testing

centers carry out the evaluations in accordance with these standards and assign fire

resistance ratings that are then used in federal and state fire codes. The tests evaluate

the fire resistance of different types of materials in various environmental configurations. Fire resistance represents the ability of a laboratory-constructed assembly

to contain a fire for a specific period. For example, a 5/8-inch-thick drywall sheet

installed on each side of a wood stud provides a one-hour rating. If the thickness

of this drywall is doubled, then this would be given a two-hour rating. The rating

system is used to classify different building components.

Several types of detectors are available, each of which works in a different way. The

detector can be activated by smoke or heat.

Smoke Activated Smoke-activated detectors are good for early warning devices.

They can be used to sound a warning alarm before the suppression system activates. A

photoelectric device, also referred to as an optical detector, detects the variation in light

intensity. The detector produces a beam of light across a protected area, and if the beam is

obstructed, the alarm sounds. Figure 10-11 illustrates how a photoelectric device works.

Another type of photoelectric device samples the surrounding air by drawing air into

a pipe. If the light source is obscured, the alarm will sound.

Heat Activated Heat-activated detectors can be configured to sound an alarm either

when a predefined temperature (fixed temperature) is reached or when the temperature

increases over time (rate of rise). Rate-of-rise temperature sensors usually provide a

quicker warning than fixed-temperature sensors because they are more sensitive, but they

Receiver

Beam of light

Photoelectric light emitter Smoke particles

Figure 10-11 A photoelectric device uses a light emitter and a receiver.

♠Chapter 10: Site and Facility Security

457
Figure 10-12
Smoke detectors
should be
located above
suspended
ceilings, below
raised floors, and
in air vents.

Suspended ceiling

Air vent

Smoke detector

can also cause more false alarms. The sensors can either be spaced uniformly throughout

a facility or implemented in a line type of installation, which is operated by a heatsensitive cable.

It is not enough to have these fire and smoke detectors installed in a facility; they must

be installed in the right places. Detectors should be installed both on and above suspended

ceilings and raised floors because organizations run many types of wires in both places

that could start an electrical fire. No one would know about the fire until it broke through

the floor or dropped ceiling if detectors were not placed in these areas. Detectors should

also be located in enclosures and air ducts because smoke can gather in these areas before

entering other spaces. It is important that people are alerted about a fire as quickly as

possible so damage may be reduced, fire suppression activities may start quickly, and lives

may be saved. Figure 10-12 illustrates the proper placement of smoke detectors.

Fire Suppression

It is important to know the different types of fire and what should be done to properly

suppress each type. Each fire type has a class that indicates what materials are burning

and how to suppress the fire. Unfortunately, three slightly different classifications are in

use around the world today (United States, European Union, and Australia). Table 10-2

shows the EU classification fires and their suppression agents. We show this classification

because it provides the most granularity. More important than memorizing the letter

assigned to each class is to know which suppression methods work best for the different

types of fire.

PART III

Raised floor

♠CISSP All-in-One Exam Guide

```
Type of Fire
Elements of Fire
Suppression Agent
Α
Common
combustibles
Wood products, paper, and
laminates
Water, foam, dry
powders, wet chemicals
В
Liquid
Petroleum products and coolants
CO2, foam, dry powders
C
Gases
Butane, propane, or methane
Dry powders
D
Combustible
metals
Aluminum, lithium, or magnesium
Dry powders
Ε
Electrical
Electrical equipment and wires
CO2, dry powders
F
```

458

EU Fire Class