ZigBee mesh links

Serial link

ZigBee bridge

Smart

dimmer switch

Smartphone app
(coordinator)

♠CISSP All-in-One Exam Guide

572

shows a typical implementation of this standard for controlling lights in a smart home.

All light bulbs and switches are able to talk to each other either directly, through the

bridge, or by relaying traffic for destination nodes that are too far from the source node.

Note that the connection between the bridge and the controller is over a serial link, but

this could be implemented as a connection over Wi-Fi, Bluetooth, or any other means.

Because ZigBee is meant to be used in embedded devices that don't have (and can't

afford) a bunch of operating system overhead, it assumes what is called an open trust

model. This means that all applications within a device trust each other, which indirectly

extends to all devices in a network as well. It also means that perimeter protection is

absolutely critical. This protection should be implemented both physically and logically.

At the physical level, ZigBee devices should be tamper-resistant to prevent attackers from

simply reading encryption keys or otherwise gaining physical control of a node and using

it as a beachhead for future attacks. At the logical level, it means controlling access to the

network, which is done primarily through key management.

The ZigBee standard defines three different 128-bit symmetric keys:

- Network key Shared by all nodes to support broadcasts
- Link key Unique for each pair of connected devices and used for unicasts
- Master key Unique for each pair of connected devices and used for the Symmetric-Key Key Establishment (SKKE) protocol from which the other keys are derived

Since embedded devices oftentimes lack a user interface, the ZigBee standard allows

multiple ways to distribute and subsequently manage these keys. The most secure way is

based on a centralized security model in which the coordinator node acts as a Trust Center.

This node is responsible for authenticating new devices that attempt to join the network

and then securely sending them the keys they need. To facilitate this, manufacturers of

ZigBee devices can install unique certificates at the factory, which are then used by the

Trust Center to authenticate them and distribute keys using the Certificate-Based Key

Establishment (CBKE) protocol. This is not all that common of an approach apart from

high-security commercial systems. More commonly, manufacturers install a unique key

in each device, which is then used by the SKKE protocol to derive keys, much like we

would do using the Diffie-Hellman algorithm we covered in Chapter 8. This second approach is less secure, doesn't require a Trust Center, and is typical in consumer systems.

EXAM TIP

Center.

ZigBee is most secure when a coordinator node acts as a Trust

Bluetooth

The Bluetooth wireless technology has a 1- to 3-Mbps transfer rate and works in a range

of approximately 1, 10, or 100 meters. It was originally invented as an alternative to

connecting devices using cables. Unsurprisingly, its most common application today is

in cordless headsets for smartphones. However, the technology has plenty of other uses.

♠Chapter 12: Wireless Networking

573

Other Important Standards

The wireless standards we've covered so far cover the ways in which devices connect to

each other and send data over the radio links they create. Over the years, we've discovered

that there are a bunch of other features we want in our wireless networks, regardless of

the communications standards being used by the radios themselves. These include Quality of Service (QoS), roaming, and spectrum management issues. Let's take a look at

another set of standards you should know.

802.11e

This standard provides QoS and support of multimedia traffic in wireless

transmissions.

Voice, streaming video, and other types of time-sensitive applications have a lower tolerance for delays in data transmission. The problem is that the original 802.11 protocol

treated all traffic equally. In other words, an e-mail message that could safely take minutes to get through had exactly the same priority as a video packet whose tolerable latency

is measured in fractions of a second. To address this, the 802.11e standard defines four

access categories (ACs) in increasing priority: background, best effort, video, and voice.

This QoS provides the capability to prioritize traffic and affords guaranteed delivery.

This standard and its capabilities have opened the door to allow many different types of

data to be transmitted over wireless connections.

PART IV

If you have a cell phone and a tablet that are both Bluetooth-enabled and both have calendar functionality, you could have them update each other without any need to connect

them physically. If you added some information to your cell phone contacts list and task

list, for example, you could just place the phone close to your tablet. The tablet would

sense that the other device is nearby, and it would then attempt to set up a network

connection with it. Once the connection was made, synchronization between the two

devices would take place, and the tablet would add the new contacts list and task list data.

Bluetooth works in a portion of the frequency band used by 802.11 devices (2.4 GHz).

In early versions of Bluetooth, real security risks existed due to protocol vulnerabilities,

but they have been largely mitigated. Still, as with any other technology, it is possible for

attackers to compromise the confidentiality, integrity, or availability of Bluetooth devices.

One attack type to which these devices are vulnerable is called Bluesnarfing, which is the

unauthorized access from a wireless device through a Bluetooth connection. This allows

attackers to read, modify, or delete calendar events, contacts, e-mails, text messages, and

so on. While recent versions of the Bluetooth standard make this much harder, it is still

possible to trick unwary users into accepting an attacker's connection attempts. Another attack type that Bluetooth is vulnerable to is referred to as Bluejacking.

In this attack, someone sends an unsolicited message to a device that is Bluetoothenabled. Bluejackers look for a receiving device (phone, tablet, laptop) and then send

a message to it. The countermeasure is to put the Bluetooth-enabled device into nondiscoverable mode so others cannot identify this device in the first place. If you

receive some type of message this way, just look around you. Bluetooth only works

within a 10-meter distance, so it is coming from someone close by.

♠CISSP All-in-One Exam Guide

574

802.11f

When a user moves around in a WLAN, her wireless device often needs to communicate

with different APs. An AP can cover only a certain distance, and as the user moves out of

the range of the first AP, another AP needs to pick up and maintain her signal to ensure

she does not lose network connectivity. This is referred to as roaming, and for this to

happen seamlessly, the APs need to communicate with each other. If the second AP must

take over this user's communication, it needs to be assured that this user has been properly authenticated and must know the necessary settings for this user's connection. This

means the first AP needs to be able to convey this information to the second AP. The

conveying of this information between the different APs during roaming is what 802.11f

deals with. The process of transferring between one AP and another is sometimes called

handoff. It outlines how this information can be properly shared.

802.11h

Because the ISM bands are unlicensed, devices that operate in them are expected to deal

well with interference from other devices. This was all good and well before the explosion

of WLANs and Bluetooth devices, but quickly became an issue as crowding increased. To

make things worse, the 5-GHz band is used not only for Wi-Fi but also for certain radar

and satellite communications systems. In this increasingly busy portion of the spectrum,

something had to be done to deal with interference.

The 802.11h standard was originally developed to address these issues in Europe, where interference in the 5-GHz band was particularly problematic. However, the techniques it implements are applicable in many countries around the world. Two specific technologies included in the standard are Dynamic Frequency Selection (DFS)

and Transmit Power Control (TPC). DFS is typically implemented in the WLAN AP and

causes it to automatically select channels that have less interference, particularly from

radars. TPC causes any device to automatically reduce its power output when it

detects

interference from other networks.

802.11j

Japan regulates its radio spectrum differently than many other countries, particularly

in the 4.9- and 5-GHz bands. Specifically, Japan uses different frequencies, radio channel widths, and wireless operating settings. In order to allow international devices to be

interoperable in Japan, the IEEE developed the 802.11j standard. The need for this standard underscores the fact that each country has the sovereign right to regulate its radio

spectrum as it sees fit.

Evolution of WLAN Security

To say that security was an afterthought in the first WLANs would be a remarkable

understatement. As with many new technologies, wireless networks were often rushed

to market with a focus on functionality, even if that sometimes came at the expense of

security. Over time, vendors and standards bodies caught on and tried to correct these

omissions. While we have made significant headway in securing our wireless networks,

♠Chapter 12: Wireless Networking

575

as security professionals we must acknowledge that whenever we transmit anything over

the electromagnetic spectrum, we are essentially putting our data in the hands (or at least

within the grasp) of our adversaries.

802.11

When WLANs were being introduced, there was industry-wide consensus that some measures would have to be taken to assure users that their data (now in the air) would be

protected from eavesdropping to the same degree that data on a wired LAN was already

protected. This was the genesis of Wired Equivalent Privacy (WEP). This first WIAN

standard, codified as part of the original IEEE 802.11, had a tremendous number of

security flaws. These were found within the core standard itself, as well as in different

implementations of this standard. Before we delve into these deficiencies, it will be useful

to spend a bit of time with some of the basics of 802.11.

EXAM TIP If you ever come across WEP in the context of wireless security, you know it's the wrong answer (unless the question is asking for the least secure standard).

PART IV

The wireless devices using this protocol can authenticate to the AP in two main ways:

open system authentication (OSA) and shared key authentication (SKA). OSA does not

require the wireless device to prove to the AP it has a specific cryptographic key to allow for

authentication purposes. In many cases, the wireless device needs to provide only the correct

SSID value. In OSA implementations, all transactions are in cleartext because no encryption

is involved. So an intruder can sniff the traffic, capture the necessary steps of authentication,

and walk through the same steps to be authenticated and associated to an AP. When an AP is configured to use SKA, the AP sends a random value to the wireless device. The device encrypts this value with a preshared key (PSK) and returns it. The AP

decrypts and extracts the response, and if it is the same as the original value, the device

is authenticated. In this approach, the wireless device is authenticated to the network by

proving it has the necessary encryption key. The PSK, commonly known as the Wi-Fi

password, is a 64- or 128-bit key.

The three core deficiencies with WEP are the use of static encryption keys, the ineffective use of initialization vectors, and the lack of packet integrity assurance. The

WEP protocol uses the RC4 algorithm, which is a stream-symmetric cipher. Symmetric

means the sender and receiver must use the exact same key for encryption and decryption

purposes. The 802.11 standard does not stipulate how to update these keys through an

automated process, so in most environments, the RC4 symmetric keys are never changed

out. And usually all of the wireless devices and the AP share the exact same key. This is

like having everyone in your company use the exact same password. Not a good idea.

So that is the first issue-static WEP encryption keys on all devices.

The next flaw is how initialization vectors (IVs) are used. An IV is a numeric seeding

value that is used with the symmetric key and RC4 algorithm to provide more randomness

to the encryption process. Randomness is extremely important in encryption because

any patterns can give the bad guys insight into how the process works, which may allow

♠CISSP All-in-One Exam Guide

576

them to uncover the encryption key that was used. The key and 24-bit IV value are

inserted into the RC4 algorithm to generate a key stream. The values (1's and 0's) of

the key stream are XORed with the binary values of the individual packets. The result is

ciphertext, or encrypted packets.

In most WEP implementations, the same IV values are used over and over again in this

process, and since the same symmetric key (or shared secret) is generally used, there is no

way to provide effective randomness in the key stream that is generated by the algorithm.

The appearance of patterns allows attackers to reverse-engineer the process to uncover the

original encryption key, which can then be used to decrypt future encrypted traffic.

So now we are onto the third mentioned weakness, which is the integrity assurance

issue. WLAN products that use only the 802.11 standard introduce a vulnerability that

is not always clearly understood. An attacker can actually change data within the wireless

packets by flipping specific bits and altering the Integrity Check Value (ICV) so the

receiving end is oblivious to these changes. The ICV works like a cyclic redundancy

check (CRC) function; the sender calculates an ICV and inserts it into a frame's header.

The receiver calculates his own ICV and compares it with the ICV sent with the frame.

If the ICVs are the same, the receiver can be assured that the frame was not modified

during transmission. If the ICVs are different, it indicates a modification did indeed take

place and thus the receiver discards the frame. In WEP, there are certain circumstances in

which the receiver cannot detect whether an alteration to the frame has taken place; thus,

there is no true integrity assurance.

So the problems identified with the 802.11 standard include poor authentication, static WEP keys that can be easily obtained by attackers, IV values that are repetitive and

do not provide the necessary degree of randomness, and a lack of data integrity. The next

section describes the measures taken to remedy these problems.

NOTE 802.11 and WEP were deprecated years ago, are inherently insecure, and should not be used.

802.11i

IEEE came out with a standard in 2004 that deals with the security issues of the original

802.11 standard, which is called IEEE 802.11i or Wi-Fi Protected Access 2 (WPA2). Why

the number 2? Because while the formal standard was being ratified by the IEEE, the

Wi-Fi Alliance pushed out WPA (the first one) based on the draft of the standard. For

this reason, WPA is sometimes referred to as the draft IEEE 802.11i. This rush to push

out WPA required the reuse of elements of WEP, which ultimately made WPA vulnerable to some of the same attacks that doomed its predecessor. Let's start off by looking at

WPA in depth, since this protocol is still in use despite its weaknesses. WPA employs different approaches that provide much more security and protection than the methods used in the original 802.11 standard. For starters, the PSK size was

increased to 256 bits and is salted with the SSID of the WLAN to make it harder to

crack. This is good, but the greatest enhancement of security is accomplished through

♠Chapter 12: Wireless Networking

577

specific protocols, technologies, and algorithms. The first protocol is Temporal Key

Integrity Protocol (TKIP), which is backward-compatible with the WLAN devices based

upon the original 802.11 standard. TKIP actually works with WEP by feeding it keying

material, which is data to be used for generating new dynamic keys. TKIP generates a

new key for every frame that is transmitted. These changes constitute the variety of this

standard known as WPA Personal, which is geared at consumers.

NOTE TKIP was developed by the IEEE 802.11i task group and the Wi-Fi Alliance. The goal of this protocol was to increase the strength of WEP or replace it fully without the need for hardware replacement. TKIP provides a key mixing function, which allows the RC4 algorithm to provide a higher degree of protection. It also provides a sequence counter to protect against replay attacks and implements a message integrity check mechanism.

PART IV

There is also a more robust version called WPA Enterprise. The main difference is that

it also integrates 802.1X port authentication and Extensible Authentication Protocol

(EAP) authentication methods. The use of the 802.1X technology (which we'll discuss

in its own section shortly) provides access control by restricting network access until

full authentication and authorization have been completed, and provides a robust authentication framework that allows for different EAP modules to be plugged in.

two technologies (802.1X and EAP) work together to enforce mutual authentication between the wireless device and authentication server. So what about the static keys,

IV value, and integrity issues?

TKIP addresses the deficiencies of WEP pertaining to static WEP keys and inadequate

use of IV values. Two hacking tools, AirSnort and WEPCrack, can be used to easily crack

WEP's encryption by taking advantage of these weaknesses and the ineffective use of

the key scheduling algorithm within the WEP protocol. If a company is using products

that implement only WEP encryption and is not using a third-party encryption solution

(such as a VPN), these programs can break its encrypted traffic within minutes. There is

no "maybe" pertaining to breaking WEP's encryption. Using these tools means it will be

broken whether a 40-bit or 128-bit key is being used—it doesn't matter. This is one of the

most serious and dangerous vulnerabilities pertaining to the original 802.11 standard.

The use of TKIP provides the ability to rotate encryption keys to help fight against

these types of attacks. The protocol increases the length of the IV value and ensures that

every frame has a different IV value. This IV value is combined with the transmitter's

MAC address and the original WEP key, so even if the WEP key is static, the resulting

encryption key will be different for every frame. (WEP key + IV value + MAC address =

new encryption key.) So what does that do for us? This brings more randomness to the

encryption process, and it is randomness that is necessary to properly thwart cryptanalysis

and attacks on cryptosystems. The changing IV values and resulting keys make the resulting key stream less predictable, which makes it much harder for the attacker to

reverse-engineer the process and uncover the original key.

TKIP also deals with the integrity issues by using a message integrity check (MIC)

instead of an ICV function. If you are familiar with a message authentication code

♠CISSP All-in-One Exam Guide

578

(MAC) function, this is the same thing. A symmetric key is used with a hashing function,

which is similar to a CRC function but stronger. The use of a MIC instead of an ICV function ensures the receiver will be properly alerted if changes to the frame take

place during transmission. The sender and receiver calculate their own separate $\mbox{\sc MIC}$

values. If the receiver generates a MIC value different from the one sent with the frame,

the frame is seen as compromised and it is discarded.

The types of attacks that have been carried out on WEP devices and networks that just

depend upon WEP are numerous and unnerving. Wireless traffic can be easily sniffed,

data can be modified during transmission without the receiver being notified, rogue APs

can be erected (which users can authenticate to and communicate with, not knowing

it is a malicious entity), and encrypted wireless traffic can be decrypted quickly and

easily. Unfortunately, these vulnerabilities usually provide doorways to the actual wired

network where the more destructive attacks can begin.

The full 802.11i (WPA2) has a major advantage over WPA by providing encryption protection with the use of the AES algorithm in counter mode with CBC-MAC (CCM), which is referred to as the Counter Mode Cipher Block Chaining Message Authentication

Code Protocol (CCM Protocol or CCMP). AES is a more appropriate algorithm for wireless than RC4 and provides a higher level of protection. WPA2 defaults to CCMP,

but can switch down to TKIP and RC4 to provide backward compatibility with WPA devices and networks.

802.11w

WPA2 was a huge step forward for WLAN security because it provided effective encryption for most wireless traffic. However, there are certain frames that cannot be encrypted

because every station (even those that have not yet joined the network) must be able to

receive. These are called management frames, and they take care of things like beaconing,

association, and authentication. While we can't encrypt them, we can take measures to

ensure their integrity. The IEEE 802.11w standard provides Management Frame Protection (MFP) that prevents certain types of attacks, such as replay and denial-of-service

(DoS) attacks.

A particularly problematic type of DoS attack on WLANs is called a deauthentication (or

deauth) attack and it exploits a feature of Wi-Fi that allows WAPs to disconnect rogue devices

by sending a deauthentication management frame. You can see how, in an environment

without MFP, it would be trivial for an attacker to spoof such messages, claiming to be the

real WAP. 802.11w solves this problem for WLANs that are not yet on WPA3.

WPA3

Like any other security mechanism, WPA2 began to crack under intensifying attacks. By

2018, the Wi-Fi Alliance decided that a new approach was needed. The result is WPA3,

which is not directly equivalent to any IEEE standard, though it does require 802.11w

to protect management frames. Like its predecessor WPA2, WPA3 comes in two flavors:

Personal and Enterprise.

♠Chapter 12: Wireless Networking

579

WPA3 Personal is aimed at the consumer market and tries to make security transparent

to the average user. One of the most important innovations of this standard is that it

allows users to choose passwords that, though they might be easily guessable, still provide

adequate security. This is done through Simultaneous Authentication of Equals (SAE),

which is defined in IEEE 802.11s, instead of relying on WPA2's preshared keys.

uses the Diffie-Hellman key exchange method but adds an authentication element based

on the (potentially weak) password. The result is a secret session key that is remarkably

resistant to password-cracking attempts.

WPA3 Enterprise is similar to its predecessor (WPA2 Enterprise) but makes use of stronger cryptography. It does this by restricting the allowed algorithms to a handful

of strong ones that use 192-bit keys. It also requires certificates on both the AP and the

wireless device for mutual authentication. The challenge with deploying WPA3 is that

many older wireless interfaces, particularly those on most embedded devices, cannot

support it, which means you may have to upgrade many (or all) of your endpoints.

802.1X

NOTE 802.1X is not a wireless protocol. It is an access control protocol that can be implemented on both wired and wireless networks.

By incorporating 802.1X, the new standard allows for the user to be authenticated,

whereas using only WPA provides system authentication. User authentication provides

a higher degree of confidence and protection than system authentication. The 802.1X

technology actually provides an authentication framework and a method of dynamically

distributing encryption keys. The three main entities in this framework are the supplicant

(wireless device), the authenticator (AP), and the authentication server (usually a

RADIUS server).

The AP controls all communication and allows the wireless device to communicate with the authentication server and wired network only when all authentication steps are

completed successfully. This means the wireless device cannot send or receive HTTP.

DHCP, SMTP, or any other type of traffic until the user is properly authorized. $\ensuremath{\mathsf{WEP}}$

does not provide this type of strict access control.

PART IV

The 802.11i standard can be understood as three main components in two specific layers.

The lower layer contains the improved encryption algorithms and techniques (TKIP and

CCMP), while the layer that resides on top of it contains 802.1X. They work together to

provide more layers of protection than the original 802.11 standard.

The 802.1X standard is a port-based network access control protocol that ensures a user

cannot make a full network connection until he is properly authenticated. This means a user

cannot access network resources and no traffic is allowed to pass, other than authentication

traffic, from the wireless device to the network until the user is properly authenticated. An

analogy is having a chain on your front door that enables you to open the door slightly to

identify a person who knocks before you allow him to enter your house.

♠CISSP All-in-One Exam Guide

580

Another disadvantage of the original 802.11 standard is that mutual authentication

is not possible. When using WEP alone, the wireless device can authenticate to the AP,

but the authentication server is not required to authenticate to the wireless device. This

means a rogue AP can be set up to capture users' credentials and traffic without the users

being aware of this type of attack. 802.11i deals with this issue by using EAP. EAP allows

for mutual authentication to take place between the authentication server and wireless

device and provides flexibility in that users can be authenticated by using passwords.

tokens, one-time passwords, certificates, smart cards, or Kerberos. This allows wireless

users to be authenticated using the current infrastructure's existing authentication

technology. The wireless device and authentication server that are 802.11i-compliant

have different authentication modules that plug into 802.1X to allow for these different

options. So, 802.1X provides the framework that allows for the different EAP modules

to be added by a network administrator. The two entities (supplicant and authenticator)

agree upon one of these authentication methods (EAP modules) during their initial

handshaking process.

The 802.11i standard does not deal with the full protocol stack, but addresses only

what is taking place at the data link layer of the OSI model. Authentication protocols

reside at a higher layer than this, so 802.11i does not specify particular authentication

protocols. The use of EAP, however, allows different protocols to be used by different

vendors. For example, Cisco uses a purely password-based authentication framework

called Lightweight Extensible Authentication Protocol (LEAP). Other vendors, including Microsoft, use EAP and Transport Layer Security (EAP-TLS), which carries

out authentication through digital certificates. And yet another choice is Protected EAP

(PEAP), where only the server uses a digital certificate.

EAP-Tunneled Transport Layer Security (EAP-TTLS) is an EAP protocol that extends TLS. EAP-TTLS is designed to provide authentication that is as strong as EAP-TLS, but

it does not require that each user be issued a certificate. Instead, only the authentication

servers are issued certificates. User authentication is performed by password, but the

password credentials are transported in a securely encrypted tunnel established based

upon the server certificates.

If EAP-TLS is being used, the authentication server and wireless device exchange digital certificates for authentication purposes. If PEAP is being used instead, the user of

the wireless device sends the server a password and the server authenticates to the wireless

device with its digital certificate. In both cases, some type of public key infrastructure

(PKI) needs to be in place. If a company does not have a PKI currently implemented, it can

be an overwhelming and costly task to deploy a PKI just to secure wireless transmissions.

When EAP-TLS is being used, the steps the server takes to authenticate to the wireless

device are basically the same as when a TLS connection is being set up between a web

server and web browser. Once the wireless device receives and validates the server's digital

certificate, it creates a master key, encrypts it with the server's public key, and sends it

over to the authentication server. Now the wireless device and authentication server have

a master key, which they use to generate individual symmetric session keys. Both entities

use these session keys for encryption and decryption purposes, and it is the use of these

keys that sets up a secure channel between the two devices.

Organizations may choose to use PEAP instead of EAP-TLS because they don't want the hassle of installing and maintaining digital certificates on every wireless device.

♠Chapter 12: Wireless Networking

581

Before you purchase a WLAN product, you should understand the requirements and complications of each method to ensure you know what you are getting yourself into and

if it is the right fit for your environment.

A large concern with any WLANs using just WEP is that if individual wireless devices

are stolen, they can easily be authenticated to the wired network. 802.11i has added steps

to require the user to authenticate to the network instead of just requiring the wireless

device to authenticate. By using EAP, the user must send some type of credential set that

is tied to his identity. When using only WEP, the wireless device authenticates itself by

proving it has a symmetric key that was manually programmed into it. Since the user

does not need to authenticate using WEP, a stolen wireless device can allow an attacker

easy access to your precious network resources.

The Answer to All Our Prayers?

PART IV

So, does the use of EAP, 802.1X, AES, and TKIP result in secure and highly trusted

WLAN implementations? Maybe, but we need to understand what we are dealing with here. TKIP was created as a quick fix to WEP's overwhelming problems. It does not provide an overhaul for the wireless standard itself because WEP and TKIP are still based on

the RC4 algorithm, which is not the best fit for this type of technology. The use of AES is

closer to an actual overhaul, but it is not backward-compatible with the original 802.11

implementations. In addition, we should understand that using all of these new components and mixing them with the current 802.11 components will add more complexity

and steps to the process. Security and complexity do not usually get along. The highest

security is usually accomplished with simplistic and elegant solutions to ensure all of the

entry points are clearly understood and protected. These newer technologies add more

flexibility to how vendors can choose to authenticate users and authentication

servers,

but can also bring us interoperability issues because the vendors will not all choose the

same methods. This means that if an organization buys an AP from company A, then the

wireless cards the organization buys from companies B and C may not work seamlessly.

So, does that mean all of this work has been done for naught? No. 802.11i provides

much more protection and security than WEP ever did. The working group has had very knowledgeable people involved and some very large and powerful companies aiding

in the development of these new solutions. But the customers who purchase these new

products need to understand what will be required of them after their purchase. For

example, with the use of EAP-TLS, each wireless device needs its own digital certificate.

Are your current wireless devices programmed to handle certificates? How will the

certificates be properly deployed to all the wireless devices? How will the certificates

be maintained? Will the devices and authentication server verify that certificates have

not been revoked by periodically checking a certificate revocation list (CRL)? What if a

rogue authentication server or AP was erected with a valid digital certificate? The wireless

device would just verify this certificate and trust that this server is the entity it is supposed

to be communicating with.

Today, WLAN products are being developed following the stipulations of this 802.11i

wireless standard. Many products will straddle the fence by providing TKIP for backwardcompatibility with current WLAN implementations and AES for organizations that are

just now thinking about extending their current wired environments with a wireless

♠CISSP All-in-One Exam Guide

582

component. Before buying wireless products, customers should review the Wi-Fi Alliance's

certification findings, which assess systems against the 802.11i proposed standard.

Best Practices for Securing WLANs

There is no silver bullet to protect any of our devices or networks. That being said, there

are a number of things we can do that will increase the cost of the attack for the adversary.

Some of the best practices pertaining to WLAN implementations are as follows:

- Change the default SSID. Each AP comes with a preconfigured default SSID value that may reveal the manufacturer and even model number, which may advertise systems with known vulnerabilities.
- Implement WPA3 Enterprise to provide centralized user authentication (e.g., RADIUS, Kerberos). Before users can access the network, require them to authenticate.
- Use separate VLANs for each class of users, just as you would on a wired LAN.
- If you must support unauthenticated users (e.g., visitors), ensure they are connected to an untrusted VLAN that remains outside your network's perimeter.
- Deploy a wireless intrusion detection system (WIDS).
- Physically put the AP at the center of the building to limit how far outside the

facility the signal will reach (and be reachable). The AP has a specific zone of coverage it can provide.

 \bullet Logically put the AP in a DMZ with a firewall between the DMZ and internal network. Allow the firewall to investigate the traffic before it gets to the wired

network.

• Implement VPN for wireless devices to use. This adds another layer of protection

for data being transmitted.

• Configure the AP to allow only known MAC addresses into the network. Allow only known devices to authenticate. But remember that these MAC addresses are sent in cleartext, so an attacker could capture them and masquerade himself as an

authenticated device.

• Carry out penetration tests on the WLAN. Use the tools described in this section

to identify APs and attempt to break the current encryption scheme being used.

Mobile Wireless Communication

Mobile wireless has now exploded into a trillion-dollar industry, with over 14 billion devices

worldwide, fueled by a succession of new technologies and by industry and international

standard agreements. So what is a mobile phone anyway? It is a device that can send voice

and data over wireless radio links. It connects to a cellular network, which is connected to

the public switched telephone network (PSTN). So instead of needing a physical cord and

♠Chapter 12: Wireless Networking

583

connection that connects your phone and the PSTN, you have a device that allows you to

indirectly connect to the PSTN as you move around a wide geographic area. A cellular network distributes radio signals over delineated areas, called cells. Each

cell has at least one fixed-location transceiver (base station) and is joined to other cells

to provide connections over large geographic areas. So as you are talking on your mobile

phone and you move out of one cell, the base station in the original cell sends your

connection information to the base station in the next cell so that your call is not dropped

and you can continue your conversation.

We do not have an infinite number of frequencies to work with when it comes to mobile communication. Millions of people around the world are using their cell phones

as you read this. How can all of these calls take place if we only have one set of frequencies

to use for such activity? Individual cells can use the same frequency range, as long as they

are not right next to each other. So the same frequency range can be used in every other

cell, which drastically decreases the amount of ranges required to support simultaneous

connections. A rudimentary depiction of a cellular network, in which nonadjacent cells

reuse the frequency sets F0, F1, F2, F3, and F4, is shown in Figure 12-5.

PART IV

F0

F1

F2

F0

F3

F0

Figure 12-5

Nonadjacent cells can use the same frequency ranges.

F2

F4

♠CISSP All-in-One Exam Guide

584

Multiple Access Technologies

The industry has had to come up with other ways to allow millions of users to be able to

use this finite resource (frequency range) in a flexible manner. Over time, mobile wireless

has been made up of progressively more complex and more powerful "multiple access"

technologies, listed here:

- Frequency division multiple access (FDMA)
- Time division multiple access (TDMA)
- Code division multiple access (CDMA)
- Orthogonal frequency division multiple access (OFDMA)

We'll quickly go over the characteristics of each of these technologies because they are the

foundational constructs of the various cellular network generations.

Frequency division multiple access (FDMA) was the earliest multiple access technology

put into practice. The available frequency range is divided into sub-bands (channels),

and one channel is assigned to each subscriber (cell phone). The subscriber has exclusive

use of that channel while the call is made, or until the call is terminated or handed off; no

other calls or conversations can be made on that channel during that call. Using FDMA

in this way, multiple users can share the frequency range without the risk of interference

between the simultaneous calls. FDMA was used in the first generation (1G) of cellular

networks. Various 1G mobile implementations, such as Advanced Mobile Phone System

(AMPS), Total Access Communication System (TACS), and Nordic Mobile Telephone (NMT), used FDMA.

Time division multiple access (TDMA) increases the speed and efficiency of the cellular

network by taking the radio frequency spectrum channels and dividing them into time

slots. At various time periods, multiple users can share the same channel; the systems

within the cell swap from one user to another user, in effect, reusing the available

frequencies. TDMA increased speeds and service quality. A common example of TDMA in action is a conversation. One person talks for a time and then quits, and then a

different person talks. In TDMA systems, time is divided into frames. Each frame is

divided into slots. TDMA requires that each slot's start and end time are known to both

the source and the destination. Mobile communication systems such as Global System

for Mobile Communication (GSM), Digital AMPS (D-AMPS), and Personal Digital Cellular (PDC) use TDMA.

Code division multiple access (CDMA) was developed after FDMA, and as the term "code" implies, CDMA assigns a unique code to each voice call or data transmission

to uniquely identify it from all other transmissions sent over the cellular network. In

a CDMA "spread spectrum" network, calls are spread throughout the entire radio frequency band. CDMA permits every user of the network to simultaneously use every

channel in the network. At the same time, a particular cell can simultaneously

```
with multiple other cells. These features make CDMA a very powerful technology.
♠Chapter 12: Wireless Networking
585
It is the main technology for the mobile cellular networks that presently
dominate the
wireless space.
FDMA
Frequency
(division multiple
access)
TDMA
Time (division
multiple access)
CDMA
Code (division
multiple access)
f2
f1
Time
1 2 3 1 2 3
Time
Frequency
f3
Frequency
Frequency
Code
2
Spread
Code 1
3
Time
Generations of Mobile Wireless
Multiple access technology development was driven by the dramatic growth in
mobile
subscribers worldwide. Mobile wireless technologies have gone through a
whirlwind
of confusing generations. The first generation (1G) dealt with analog
```

interact

transmissions of

voice-only data over circuit-switched networks. This generation provided a throughput

of around 19.2 Kbps. The second generation (2G) allows for digitally encoded voice and

data to be transmitted between wireless devices, such as cell phones, and content providers. TDMA, CDMA, GSM, and PCS all fall under the umbrella of 2G mobile telephony.

This technology can transmit data over circuit-switched networks and supports data

encryption, fax transmissions, and short message services (SMSs).

The third-generation (3G) networks became available around the turn of the century.

Incorporating FDMA, TDMA, and CDMA, 3G has the flexibility to support a great variety of applications and services. Further, 3G replaced circuit switching with packet

switching. Modular in design to allow ready expandability, backward compatibility with

2G networks, and stressing interoperability among mobile systems, 3G services greatly

expanded the applications available to users, such as global roaming (without changing

one's cell phone or cell phone number), as well as Internet services and multimedia.

In addition, reflecting the ever-growing demand from users for greater speed, latency in

3G networks was much reduced as transmission speeds were enhanced. More enhancements

PART IV

Orthogonal frequency division multiple access (OFDMA) is derived from a combination

of FDMA and TDMA. In earlier implementations of FDMA, the different frequencies for each channel were widely spaced to allow analog hardware to separate the different

channels. In OFDMA, each of the channels is subdivided into a set of closely spaced

orthogonal frequencies with narrow subchannels. Each of the different subchannels

can be transmitted and received simultaneously in a multiple input, multiple output

(MIMO) manner. The use of orthogonal frequencies and MIMO allows signal processing

techniques to reduce the impacts of any interference between different subchannels and

to correct for channel impairments, such as noise and selective frequency fading. 4G and

5G require that OFDMA be used.

♠CISSP All-in-One Exam Guide

586

Mobile Technology Generations

Like many technologies, the mobile communication technology has gone through several different generations.

First generation (1G):

- Analog services
- Voice service only

Second generation (2G):

- Primarily voice, some low-speed data (circuit switched)
- Phones were smaller in size
- Added functionality of e-mail, paging, and caller ID Generation 2% (2.5G):
- Higher data rates than 2G
- "Always on" technology for e-mail and pages Third generation (3G):
- Integration of voice and data
- Packet-switched technology, instead of circuit-switched Generation 3.5 G (3GPP)
- Higher data rates
- Use of OFDMA technology Fourth generation (4G)
- Based on an all-IP packet-switched network
- Data exchange at 100 Mbps to 1 Gbps Fifth generation (5G)
- Higher frequency ranges, which cut down range and make interference a bigger deal
- Data rates of 20 Gbps possible
- Supports dense deployment of high-speed, low-latency services to 3G networks, often referred to as 3.5G or as mobile broadband, took place under the

rubric of the Third Generation Partnership Project (3GPP). 3GPP resulted in a number of

new or enhanced technologies. These include Enhanced Data Rates for GSM Evolution

(EDGE), High-Speed Downlink Packet Access (HSDPA), CDMA2000, and Worldwide Interoperability for Microwave Access (WiMAX).

♠Chapter 12: Wireless Networking

587

NOTE While it would be great if the mobile wireless technology generations broke down into clear-cut definitions, they do not. This is because various parts

of the world use different foundational technologies, and there are several competing vendors in the space with their own proprietary approaches.

4G

5G

Spectrum

1,800 MHz

2 GHz

Various

Various 3-86 GHz

Bandwidth

25 MHz

25 MHz

100 MHz

30-300 MHz

Multiplexing Type

TDMA

CDMA

OFDMA

OFDMA

New Features Introduced

Digital voice, SMS, MMS

Mobile Internet access, video

Mobile broadband, HD video

Ultra-HD and 3D video

Data Rate

115-128 Kbps

384 kbps

100 Mbps (moving)
1 Gbps (stationary)

Up to 10 Gbps

Introduction

1993

2001

2009

2018

Table 12-2 The Different Characteristics of Mobile Technology

PART IV

At the time of writing, 4th generation (4G) mobile networks are dominant (though,

as we're about to see, that's going to change soon). Initially, there were two competing

technologies that fell under the umbrella of 4G: Mobile WiMAX and Long-Term Evolution (LTE). Eventually, however, LTE won out and WiMAX is no longer used in mobile wireless networks. (Though, as we've already discussed, WiMAX is still used

as an alternative to traditional ISP services in WANs.) A 4G system does not support

traditional circuit-switched telephony service as 3G does, but works over a purely packetbased network. 4G devices are IP-based and are based upon OFDMA instead of the

previously used multiple carrier access technologies. In theory, 4G devices should be able

to reach 2-Gbps data rates, though that is seldom the case in practice.

Fifth generation (5G) is the technology that is all the rage right now. Its biggest

advantage, at least from users' perspectives, over 4G is speed. 5G is capable of reaching a

whopping 20 Gbps, which puts it in the neighborhood of the latest Wi-Fi 6 standard. What

are the drawbacks of 5G? In order to achieve those jaw-dropping speeds, 5G uses higher

frequencies that, as we already discussed, have shorter ranges and are more susceptible to

interference. This means that carriers will have to put up more cellular towers. Each of the different mobile communication generations has taken advantage of the

improvement of hardware technology and processing power. The increase in hardware

has allowed for more complicated data transmission between users and hence the desire

for more users to use mobile communications.

Table 12-2 illustrates some of the main features of the 2G through 5G networks. It is

important to note that this table does not and cannot easily cover all the aspects of each

generation. Earlier generations of mobile communication have considerable variability

between countries. The variability was due to country-sponsored efforts before agreedupon international standards were established. Various efforts between the ITU and

countries have attempted to minimize the differences.

♠CISSP All-in-One Exam Guide

588

Hacking Mobile Phones

2G networks (which are still around, believe it or not) lack the ability to authenticate towers to phones. In other words, an attacker can easily set up a rogue tower

with more power than the nearby legitimate ones and cause the target's mobile phone to connect to it. This type of attack allows attackers to intercept all mobile

phone traffic. Though 3G and 4G networks corrected this serious vulnerability, it is sometimes still possible to force most phones to switch down to 2G mode by jamming 3G, 4G, and 5G towers. In an effort to maintain some form of connectivity, handsets may then switch down to the vulnerable 2G mode, making the attack

possible again.

Devices designed to perform this type of attack are called International Mobile Subscriber Identity (IMSI) catchers. Initially intended for law enforcement and intelligence agency use, IMSI catchers are increasingly available to criminals in the black markets. Moreover, it is possible for anyone to build one of these attack platforms for less than \$1,500, as Chris Paget demonstrated at DefCon in 2010. This is yet another example of how backward compatibility can perpetuate vulnerabilities in older protocols.

Satellites

Today, satellites are used to provide wireless connectivity between distant stations. For

two different locations to communicate via satellite links, they must be within the satellite's line of sight and footprint (area covered by the satellite), which tends to be large even

for low Earth orbit satellites. The sender of information (ground station) modulates the

data onto a radio signal that is transmitted to the satellite. A transponder on the satellite

receives this signal, amplifies it, and relays it to the receiver. The receiver must have a

type of antenna—one of those circular, dish-like things we see on top of buildings. The

antenna contains one or more microwave receivers, depending upon how many satellites

it is accepting data from.

Satellites provide broadband transmission that is commonly used for television channels

and Internet access. If a user is receiving TV data, then the transmission is set up as a

one-way (broadcast) network. If a user is using this connection for Internet connectivity,

then the transmission is set up as a two-way network. The available bandwidth depends

upon the antenna and terminal type and the service provided by the service provider.

Time-sensitive applications, such as voice and video conferencing, can suffer from the

delays experienced as the data goes to and from the satellite.

There are two types of orbits that are commonly used in satellite communications networks: geosynchronous and low Earth. Traditional networks, like the ones that broadcast TV and carry transoceanic data links for the major carriers, orbit at an altitude

of 22,236 miles, which means they rotate at the same rate as the Earth does. This is

called a geosynchronous orbit, and it makes the satellites appear to be stationary over the

same spot on the ground. The key benefit is that the ground station antenna doesn't have

♠Chapter 12: Wireless Networking

589

to move. The main drawbacks are that, with that kind of range, you need a pretty big

antenna and have to wait about a second for a radio wave to go up to the satellite and

come back to Earth. This latency can create challenges for real-time communications like

video conferencing.

Other satellites use a low Earth orbit (LEO), which is typically between 99 and 1,243 miles above the surface of the Earth. This means there is not as much distance

between the ground stations and the satellites as in other types of satellites. In turn, this

means smaller receivers can be used, which makes LEO satellites ideal for international

cellular communication and Internet use. The catch is that the data rates tend to be

much smaller than geosynchronous satellites and the service plans are pretty expensive.

In most cases, organizations use a system known as a very small aperture terminal

(VSAT), which links a station (such as a remote office) to the Internet through a satellite

gateway facility run by a service provider, as shown in Figure 12-6. Alternatively, VSATs

can be deployed in stand-alone networks in which the organization also places a VSAT

at a central location and has all the remote ones reach into it with no need for a gateway

facility. The data rates available can range from a few Kbps to several Mbps. Dropping

prices have rendered this technology affordable to many midsized organizations, though

it is still far from being inexpensive.

PART IV

Satellite Satellite link

Earth station (HUB)

VSAT

Fiber optics

Internet backbone LAN

Figure 12-6

Satellite broadband

♠CISSP All-in-One Exam Guide

590

Chapter Review

Wireless networking is ubiquitous and, over the years, the security community has made

great strides to ensure the confidentiality, integrity, and availability of our systems using

these technologies. Still, risk can never be driven to zero, and this is particularly true

when you transmit into free space, whether you do so using radio or light waves. Best

practices for securing wireless networks include using strong cryptography, controlling

access, and periodically testing the effectiveness of our controls.

As security professionals, we must always be aware of the myriad of new wireless technologies being developed and sold. For each, we have to compare the benefits (which are always touted by the vendors) to the risks (which may be less obvious and

more difficult to identify). The market will constantly push products that promise new

features and functionality, even if they come at the cost of security. To be clear, most

new technologies incorporate at least some basic security features (and in many cases,

advanced security features too), but these are not always implemented in a systematic

manner by their adopters. That's where security professionals need to weigh in.

Ouick Review

- Wireless communication systems modulate data onto electromagnetic signals like radio and light waves.
- Normally, a higher frequency can carry more data, but over a shorter distance and with more susceptibility to interference.
- Wireless communication systems typically use carrier sense multiple access with
- collision avoidance (CSMA/CA) as a medium access control (MAC) protocol.
- A radio frequency band is a subset of the radio spectrum designated for a specific use.
- Wi-Fi systems operate in the 2.4-GHz and 5-GHz bands.
- Most wireless communication systems use one of two modulation techniques: spread spectrum or orthogonal frequency division multiplexing (OFDM).
- Spread spectrum modulation techniques include frequency hopping spread spectrum (FHSS) and direct sequence spread spectrum (DSSS).
- DSSS spreads the data being transmitted over a wider spectrum than would otherwise be needed in order to overcome interference and relies on a chip sequence to let receiving stations know how to reconstruct the transmitted data.
- FHSS uses a single subchannel at a time, but rapidly changes channels in a particular hop sequence.
- Wireless local area networks (WLANs) come in two forms: infrastructure and ad hoc.
- Environments can be segmented into different WLANs by using different SSIDs.
- 802.11a provides up to 54 Mbps and operates in the 5-GHz band.
- ♠Chapter 12: Wireless Networking

591

PART IV

- 802.11b provides a transfer rate of up to 11 Mbps and works in the 2.4-GHz frequency range.
- 802.11g operates in the 2.4-GHz band and supports data rates of up to 54 Mbps.
- 802.11n, also known as Wi-Fi 4, supports throughputs of up to 100 Mbps and works in the 5-GHz band.
- IEEE 802.11ac (Wi-Fi 5) is an extension of 802.11n that increases throughput to 1.3 Gbps and is backward compatible with 802.11a, 802.11b, 802.11g, and 802.11n.
- The 802.11ax standard aims to address efficiency rather than faster speeds.
- Li-Fi is a wireless networking technology that uses light rather than radio waves

to transmit and receive data.

• 802.16 is a metropolitan area network (MAN) wireless standard that allows wireless traffic to cover large geographical areas where stations can be as far as

70 km apart, using the 2.4-GHz and 5-GHz bands.

• The 802.15.4 standard defines the physical layer and Media Access Control sublayer

of wireless personal area networks (WPANs).

• ZigBee is a standard for layers 3 (network) and 7 (application) that is built on

top of 802.15.4 and is most commonly used in Internet of Things (IoT) and

Industrial IoT systems.

- Bluetooth is another standard for WPANs, which is most commonly used to replace the cables connecting peripherals to computers and mobile devices.
- ullet The 802.11e standard provides Quality of Service (QoS) and support of multimedia

traffic in wireless transmissions.

• 802.11f standardizes the processes by which access points transfer active connections

among themselves, enabling users to roam across APs.

- The 802.11h standard was developed to address interference issues in the 5-GHz band, particularly with regard to radar and satellite systems, through Dynamic Frequency Selection (DFS) and Transmit Power Control (TPC) techniques.
- 802.11j is an example of standards that allow common technologies such as WLANs to be employed in countries (in this case Japan) where local regulations conflict with portions of a broader standard (in this case 802.11).
- 802.11 was the original WLAN standard, which included Wired Equivalent Privacy (WEP); it is now obsolete.
- 802.11i defines Wi-Fi Protected Access 2 (WPA2) and is the most common standard in use in WLANs today.
- The IEEE 802.11w standard provides Management Frame Protection (MFP) that prevents certain types of attacks, such as replay and DoS attacks.
- WPA3 was developed by the Wi-Fi alliance (not IEEE) and is quickly replacing WPA2 for both personal and enterprise use.

★CISSP All-in-One Exam Guide

592

- 802.1X is an access control protocol that can be implemented on both wired and wireless networks for user authentication and key distribution.
- Mobile telephony has gone through different generations and multiple access technologies: 1G (FDMA), 2G (TDMA), 3G (CDMA), 4G (OFDM), and 5G (OFDM).
- Satellite communications links provide connectivity across very long distances and in places that would otherwise not be reachable, but may introduce latency challenges.

Ouestions

Please remember that these questions are formatted and asked in a certain way for a

reason. Keep in mind that the CISSP exam is asking questions at a conceptual level.

Questions may not always have the perfect answer, and the candidate is advised against

always looking for the perfect answer. Instead, the candidate should look for the best

answer in the list.

- 1. Which of the following is not a characteristic of the IEEE 802.11a standard?
- A. It works in the 5-GHz range.
- B. It uses the OFDM spread-spectrum technology.
- C. It provides 52 Mbps in bandwidth.
- D. It covers a smaller distance than 802.11b.
- 2. Wireless LAN technologies have gone through different versions over the years to address some of the inherent security issues within the original IEEE 802.11

standard. Which of the following provides the correct characteristics of WPA2 in Enterprise mode?

- A. IEEE 802.1X, WEP, MAC
- B. IEEE 802.1X, EAP, TKIP
- C. IEEE 802.1X, EAP, WEP
- D. IEEE 802.1X, EAP, CCMP
- 3. Which of the following is not a characteristic of Li-Fi networks?
- A. Support for high client densities
- B. High latency
- C. Constrained coverage area
- D. Can work on the infrared spectrum
- 4. How would you best ensure the security of a ZigBee system?
- A. Ensure a coordinator acts as a Trust Center
- B. Use 256-bit encryption keys
- C. Deploy in a ring topology with preassigned slots for each device
- D. Use the Symmetric-Key Key Establishment (SKKE) protocol to derive keys

♠Chapter 12: Wireless Networking

593

5. Which of the following is a Bluetooth-specific attack that allows unauthorized

read/write access from a wireless device?

- A. Bluejacking
- B. Replay attack
- C. Smurf attack
- D. Bluesnarfing
- 6. What does the IEEE 802.1X standard cover?
- A. A Management Frame Protection (MFP) that prevents replay and denial-of-

Use the following scenario to answer Questions 8-10. You are planning an upgrade for

the wireless network at one of your manufacturing sites and want to use this as an

opportunity to improve network security. The current system is based on 10-year-old

wireless access points (WAPs) that implement 802.11g. You're using WPA2 in Personal

mode because you have multiple Industrial Internet of Things (IIoT) devices. You can

update the firmware on the WAPs, but you really think it's time for an upgrade.

- 8. What could make it harder for you to switch from WPA2 Personal mode to Enterprise mode?
- A. Enterprise mode requires licenses that can be costly.
- B. The WAPs may not support Enterprise mode.
- C. IIoT devices may not support Enterprise mode.
- D. The return on investment is insufficient.
- 9. What is the best technology to which you should consider upgrading?
- A. IEEE 802.16
- B. IEEE 802.11w

- C. IEEE 802.11f
- D. IEEE 802.11ax

PART IV

service (DoS) attacks

- B. Wi-Fi Protected Access 2 (WPA2)
- C. Security extensions to the physical layer (PHY) and Media Access Control (MAC) sublayer of the data link layer in the OSI model
- D. An access control protocol for user authentication and key distribution
- 7. Which of the following is not a disadvantage of satellite networks compared to

terrestrial ones?

- A. Latency
- B. Cost
- C. Bandwidth
- D. Video conferencing

♠CISSP All-in-One Exam Guide

594

10. The existing wireless network has recently become unusable, and you suspect you

may be the target of a persistent Wi-Fi deauthentication attack. How can you best mitigate this threat?

- A. Deploy WPA3 access points across the facility
- B. Perform MAC address filtering to keep the rogue stations off the network
- C. Immediately update the firmware on the access points to support 802.11w
- D. Change the channel used by the WAPs

Answers

- 1. C. The IEEE standard 802.11a uses the OFDM spread-spectrum technology, works in the 5-GHz frequency band, and provides bandwidth of up to 54 Mbps. The operating range is smaller because it works at a higher frequency.
- 2. D. Wi-Fi Protected Access 2 requires IEEE 802.1X or preshared keys for access control, Extensible Authentication Protocol (EAP) or preshared keys for authentication, and the Advanced Encryption Standard (AES) algorithm in counter mode with CBC-MAC Protocol (CCMP) for encryption.
- 3. B. Latency is the delay in data transfers, which is extremely low in Li-Fi networks.
- 4. A. Using a Trust Center provides a way to centrally authenticate devices and securely manage encryption keys, which are 128 bits (not 256). Without a Trust Center, the SKKE protocol can be used to derive keys, but this approach is not as

secure. ZigBee does not support ring topologies.

5. D. Bluesnarfing could allow an attacker to read, modify, or delete calendar events, contacts, e-mails, text messages, and so on. Bluejacking is the only other

Bluetooth attack option, but this refers to someone sending an unsolicited message to a device.

6. D. 802.1X is an access control protocol that can be implemented on both wired and wireless networks for user authentication and key distribution. MFP is covered in 802.11w, WPA2 is covered in 802.11i, and the other option (security extensions) was a distracter.

7. C. If you have the budget for it, data rates on satellite networks are comparable

with other modes of communication. These systems, however, are typically more expensive and have high latencies, which means they are not well suited for time-sensitive applications, such as voice and video conferencing.

8. D. If a WAP supports WPA2, it would do so in either Personal or Enterprise mode as long as it can be connected to the needed backend services (e.g., a RADIUS server), with no need for additional licensing. Thus, the change would not typically be expected to have ROI issues. However, many embedded devices, including IIoT, do not support this mode and would have to be replaced.

♠Chapter 12: Wireless Networking

595

- 9. D. 802.11ax is the only standard describing a WLAN among the list of options. 802.16 is used in metropolitan area networks (MANs). 802.11w covers Management Frame Protection (MFP) in wireless networks. 802.11f deals with users roaming among access points.
- 10. C. 802.11w provides Management Frame Protection (MFP) capabilities that would mitigate this type of attack. This is included in WPA3, so either answer would generally work. However, it is probably faster, cheaper, and safer to roll out 802.11w upgrades first, which would likely have no negative effects on the networks, while research and planning continue on how to best implement a WPA3 solution across the enterprise. This is a good example of the types of ambiguous questions you'll see on the CISSP exam.

PART IV

♠This page intentionally left blank

↑13

CHAPTER

Securing the Network
This chapter presents the following:

- Secure networking
- Secure protocols
- Multilayer protocols
- Converged protocols
- Micro-segmentation

More connections to more devices means more vulnerabilities.

-Marc Goodman

Having developed a foundational understanding of networking technologies, we now turn our attention to building secure networks upon this foundation. In this chapter,

we circle back to the core networking and service protocols introduced in Chapter 11

and discuss the threats against them and how to mitigate those threats. This discussion

is grounded in the secure design principles covered in Chapter 9. We'll take the same

approach as we expand our scope of interest from those core protocols and

services to

include other services, such as e-mail, that are critical to modern networks.

These networks are not as neatly divided as the OSI model could lead us to believe.

Increasingly, we are relying on multilayer and converged protocols where concepts from

different layers and even network components overlap in ways that have important security implications. The goal of this chapter is to show how, through a thoughtful

application of secure protocols and best practices, we can secure our networks and the

services they provide.

Applying Secure Design Principles

to Network Architectures

A network architecture is just a model of a network. Like any model, it is not 100 percent

representative of reality and uses abstractions to simplify some details so that we can

focus on the others. By ignoring the little details (for now), we make it easier on ourselves

to focus on the more important elements. For example, before we decide how many web

servers we need and which operating systems and software we need to run on them, we

should first identify the classes of servers and where we would put them. We might have

597

♠CISSP All-in-One Exam Guide

598

a set of externally accessible servers for our web presence, but we may also need some

servers that are for internal use only by all employees, and yet another set that is only for

web developers. Where do we put each set and how might we need different controls

for them? Maybe we need a demilitarized zone (DMZ), an internal sharing cluster, and

a development virtual local area network (VLAN), each with specific sets of controls

meant to mitigate their differing risk profiles. A network architecture allows us to answer

these high-level questions before we start configuring any boxes.

Now, once we go through all the trouble of coming up with an architecture that works, we shouldn't have to reinvent the wheel. Network architectures also serve as

templates for future systems. What's more, they can be codified and shared among similar

organizations to reduce work and ensure we all follow best practices. Even if a lot of the

details are different, a sound architecture can be reused time and again.

Many of these best practices relate to security. Since we intend our architectures to be

reusable, it is imperative that we apply secure design principles when we implement them.

In the sections that follow, we will discuss a (wide) variety of networking concepts and

technologies that you will need to understand to implement secure design principles in

network architectures. Periodically, we circle back and discuss some of these important

secure design principles. It is important to note that there is no one-size-fits-all solution

in this effort, so you will have to be selective about which of these principles you apply in

any specific situation. Still, as a CISSP, you are expected to be conversant with all of them.

Let's start by reviewing the 11 secure design principles we covered in Chapter 9 and

look at how they apply to network architectures.

• Threat modeling Everything we do in cybersecurity should be grounded in a good understanding of the threats we face. In this chapter, we focus our attention

on network security, so we'll illustrate the threats we face as we discuss the various

technologies and protocols involved in operating and securing our networks.

- Least privilege Traffic should be allowed to flow between any two points that are required to communicate in order to satisfy a valid organizational requirement, and nowhere else. We cover this in depth when we address network segmentation later in this chapter.
- Defense in depth While some IT and security professionals equate this principle with having a DMZ for public-facing servers, the principle applies throughout the network and requires that we build concentric defenses around our most valuable assets.
- Secure defaults Perhaps the simplest illustration of this principle as it applies

to our networks is ensuring firewalls' default configurations are to deny all traffic

from any source to any destination (deny all all). However, the principle should apply throughout our network and be consistent with least privilege.

• Fail securely The key to applying this principle is asking two questions: What happens when this network system fails? What happens when a packet doesn't match an "allow" rule on the firewall? (Hint: it should not be allowed through.)

♠Chapter 13: Securing the Network

599

EXAM TIP You should be prepared to map the various secure design principles to specific scenarios.

With these principles in mind, let's look at specific ways in which we can assess and

implement network architectures securely.

Secure Networking

The most prevalent networking standards and protocols we use today (Ethernet, TCP/IP,

and so on) were born decades ago (before many of us). Back then, the world was kinder

and gentler (at least in the digital realm) and security just wasn't the sort of thing folks

thought about when it came to computers and networks. With the explosion of the Internet came immense opportunities for both the law abiding and the criminals. The

need for secure networking became apparent, but it was too late. We've been trying to

catch up ever since by bolting security onto insecure technologies. One of the most

common ways of securing our networks is through the use of encryption, particularly in

trusted tunnels through untrusted networks.

PART IV

• Separation of duties Speaking of firewall (and other security appliance) rules,

who is in charge of those in your organization? Any sensitive duties should be split up among vetted staff members. At a minimum, if you don't have enough staff, everybody's sensitive work should be regularly checked by someone else.

• Keep it simple Unless you are architecting a global network for a multinational

corporation, you should try to develop an architecture that can be depicted in a single PowerPoint slide and still describe all the important components.

- Zero trust Services and traffic on your network should all be authenticated and encrypted. When two servers are part of a system (e.g., the web server and its backend database), they should authenticate each other and have rules around what requests each is allowed to make of the other.
- Privacy by design Encrypting your network traffic is a good start toward protecting privacy, but where is the data being collected and for what purpose? For example, as we prepare for auditability (see the next principle), we need to ensure that we are not casting too wide of a net in terms of the data we log.
- Trust but verify Everything that happens on the network should be auditable, meaning that there should be a record of who is talking with whom, when, and why. This is normally done by ensuring logs are properly configured and protected against tampering or accidental loss.
- Shared responsibility Odds are that your network architecture will include at least a handful of service providers. Whether these are Internet service providers,

cloud service providers, or managed services providers, it is critical to agree on

who has responsibility over which aspects of your network.

♠CISSP All-in-One Exam Guide

600

Link Encryption vs. End-to-End Encryption

In each of the networking technologies discussed in this chapter, encryption can be

performed at different levels, each with different types of protection and implications.

Two general modes of encryption implementation are link encryption and end-to-end

encryption. Link encryption encrypts all the data along a specific communication path,

as in a satellite link, a terrestrial T3 leased line, or even between hosts on the same LAN.

Because link encryption happens at layers 1 and 2, not only is the user information

encrypted, but the (layer 3 and higher) headers, trailers, addresses, and routing data that

are part of the packets are also encrypted. The only traffic not encrypted in this technology is the data link control messaging information, which includes instructions and

parameters that the different link devices use to synchronize communication methods.

Reading this information won't give an attacker any insights into what is being transmitted or where it is ultimately going.

End-to-end encryption (E2EE) occurs at the session layer (or higher), which means

the headers, addresses, routing information, and trailer information are not encrypted,

enabling attackers to learn more about a captured packet and where it is headed. Transport

Layer Security (TLS), which we will discuss shortly, is the most common example of

E2EE. Because the routing information is sent in plaintext, attackers can perform traffic

analysis to learn details about the network, such as which hosts play which roles in it.

Link encryption, which is sometimes called online encryption, is usually provided by

service providers and is incorporated into network protocols. All of the information

is encrypted, and the packets must be decrypted at each hop so the router, or other

intermediate device, knows where to send the packet next. The router must decrypt

the header portion of the packet, read the routing and address information within the

header, and then re-encrypt it and send it on its way.

With end-to-end encryption, the packets do not need to be decrypted and then encrypted again at each hop because the headers and trailers are not encrypted. The

devices in between the origin and destination just read the necessary routing information

and pass the packets on their way.

End-to-end encryption is usually initiated by the user of the originating computer.

It provides more flexibility for the user to be able to determine whether or not certain

Encryption at Different Layers

Encryption can (and typically does) happen at different layers of an operating system

and network stack. The following are just a few examples:

- End-to-end encryption happens within the applications.
- TLS encryption takes place at the session layer.
- Point-to-Point Tunneling Protocol (PPTP) encryption takes place at the data link layer.
- Link encryption takes place at the data link and physical layers.

♠Chapter 13: Securing the Network

601

messages will get encrypted. It is called "end-to-end encryption" because the message

stays encrypted from one end of its journey to the other. Link encryption has to decrypt

the packets at every device between the two ends.

Link encryption occurs at the data link and physical layers, as depicted in Figure 13-1.

Hardware encryption devices interface with the physical layer and encrypt all data that

passes through them. Because no part of the data is available to an attacker, the attacker

cannot learn basic information about how data flows through the environment. This is

referred to as traffic-flow security.

NOTE A hop is a device that helps a packet reach its destination. It is usually a router that looks at the packet address to determine where the packet needs to go next. Packets usually go through many hops between the sending and receiving computers.

Advantages of end-to-end encryption include the following:

The disadvantage of end-to-end encryption is the following:

• Headers, addresses, and routing information are not encrypted, and therefore not

protected.

End-to-end encryption happens at higher

layers and does not encrypt headers and trailers.

1010

Encrypted message

1011

Encrypted message Link encryption happens at lower layers and encrypts headers and trailers of the packet.

Figure 13-1

Link and end-to-end encryption happen at different OSI layers.

PART IV

- It provides more flexibility to the user in choosing what gets encrypted and how.
- Higher granularity of functionality is available because each application or user

can choose specific configurations.

• Each hop device on the network does not need to have a key to decrypt each packet.

♠CISSP All-in-One Exam Guide

602

Hardware vs. Software Cryptography Systems

Encryption can be done through software or hardware, and there are trade-offs with each. Generally, software is less expensive and provides a slower throughput

than hardware mechanisms. Software cryptography methods can be more easily modified and disabled compared to hardware systems, but it depends on the application and the hardware product.

If an organization needs to perform high-end encryption functions at a higher speed, it will most likely implement a hardware solution.

Advantages of link encryption include the following:

- All data is encrypted, including headers, addresses, and routing information.
- Users do not need to do anything to initiate it. It works at a lower layer in the

OSI model.

Disadvantages of link encryption include the following:

- Key distribution and management are more complex because each hop device must receive a key, and when the keys change, each must be updated.
- Packets are decrypted at each hop; thus, more points of vulnerability exist.

TLS

The most prevalent form of end-to-end encryption is Transport Layer Security (TLS).

TLS is a security protocol that provides confidentiality and data integrity for network

communications. It replaced the (now insecure) Secure Sockets Layer (SSL) standard.

These two protocols coexisted for many years, and most people thought that there were

very few differences between SSL and TLS (TLS is currently in version 1.3). However,

the Padding Oracle On Downgraded Legacy Encryption (POODLE) attack in 2014 was the death knell of SSL and demonstrated that TLS was superior security-wise. The key

to the attack was to force SSL to downgrade its security, which was allowed for

the sake

of interoperability.

EXAM TIP Because SSL and TLS were (for a time) very closely related, the terms are sometimes still used interchangeably to describe network encryption in general. However, the SSL protocol has been insecure for many years and should not be the correct answer to an encryption question (unless it is asking for an insecure protocol).

Backward compatibility has long been a thorn in the side of those of us trying to

improve cybersecurity. TLS 1.3 represents a switch to a focus on security, which shows

in the limited number of cipher suites that it supports (just five). This means attackers

♠Chapter 13: Securing the Network

603

can no longer trick a server into using an insecure cryptosystem during the connection

establishment negotiation. One of the key features of TLS 1.3 is that the handshake used

to establish a new connection requires only one client message to the server and one

response from the server. There's a lot that happens in there, though, so let's take a look

at a summarized version of this handshake.

1. Client "Hello" message, which includes

NOTE While TLS 1.3 minimizes the plaintext information transferred between hosts, TLS 1.2 (and earlier) passes a lot more information in the clear, potentially including the server name (e.g., www.goodsite.com).

As mentioned, TLS 1.3 has dramatically reduced the number of recommended cipher suites from 37 (in previous versions) to just five. This is an important improvement because

some of those 37 suites were known (or suspected) to be vulnerable to cryptanalysis. By

reducing the suites to five and ensuring these provide strong protection, TLS 1.3 makes

it harder for attackers to downgrade the security of a system by forcing a server to use a

weaker suite. The allowed suites in the latest version of TLS are as follows:

- TLS_AES_256_GCM_SHA384 The encryption algorithm here is AES with a 256-bit key in Galois/Counter Mode (GCM). GCM is a mode of operation that provides message authentication. The hashing algorithm is SHA-384. This suite provides the best protection but requires the most computing resources.
- TLS_AES_128_GCM_SHA256 This suite is almost identical to the preceding one, but saves on resources by using a smaller 128-bit key for encryption and a slightly faster SHA-256 for hashing. It is ideally suited for systems with hardware

support for encryption.

TLS_AES_128_CCM_SHA256 In this suite, AES (again, with a 128-bit key)

runs in Counter mode with CBC-MAC (CCM), which uses 16-byte tags to provide message authentication (much like GCM does).

PART IV

- A list of cipher suites and protocols supported by the client
- Client inputs for the key exchange
- 2. Server "Hello" message, which includes
- The server's selection of cipher suite and protocol version
- Server inputs for the key exchange
- 3. Server authentication, which includes
- The server's digital certificate
- Proof that the server owns the certificate's private key
- 4. (Optionally) Client authentication, which includes
- The client's digital certificate
- Proof that the client owns the certificate's private key

♠CISSP All-in-One Exam Guide

604

- TLS_AES_128_CCM_8_SHA256 This suite is almost identical to the preceding one, but Counter mode with CBC-MAC uses 8-byte tags (instead of 16-byte ones), which makes it better suited for embedded devices.
- TLS_CHACHA20_POLY1305_SHA256 The ChaCha stream cipher (doing 20 rounds), combined with the Poly1305 message authentication code (MAC), is a cipher suite that is a good choice for software-based encryption systems. Many modern systems rely on hardware-based encryption, so the authors of TLS 1.3 wanted to ensure the recommended suites supported multiple devices. Besides, it just makes sense to have at least one encryption algorithm that is not AES. We already discussed AES (and briefly mentioned ChaCha20) in Chapter 8, and CCM in Chapter 12, but this is the first time we bring up GCM and Poly1305. These

are approaches to provide authenticated symmetric key encryption. Authenticated encryption (AE) provides assurances that a message was not modified in transit and could

only come from a sender who knows the secret key. This is similar to the MAC approach

discussed in Chapter 8 but is applied to stream ciphers. TLS 1.3 takes the AE concept to

the next level in what is known as authenticated encryption with additional data (AEAD).

AEAD essentially computes the MAC over both ciphertext and plaintext when these are

sent together. For example, when sending network traffic, there are certain fields (e.g.,

source and destination addresses) that cannot be encrypted. An attacker could replay an

encrypted message later using a different packet, but if we're using AEAD (as TLS 1.3

requires), this bogus packet would automatically be discarded.

Another key feature of TLS 1.3 (which was optional in TLS 1.2 and prior) is its use of

ephemeral keys, which are only used for one communication session and then discarded,

using the Diffie-Hellman Ephemeral (DHE) algorithm. This provides forward secrecy

(sometimes called perfect forward secrecy), which means that if attackers were somehow

able to crack or otherwise obtain the secret key, it would only give them the ability to

decrypt a small portion of the ciphertext. They wouldn't be able to decrypt everything going forward.

Attackers Use TLS Too!

While TLS is often our first line of defense in protecting our network traffic from

prying eyes, attackers use it too, precisely for the same reason. There are many known examples of malware using TLS. Banking Trojans, such as TrickBot, Emotet, and Dyre, make use of TLS to communicate data back to their master server. Ransomware families, such as Jigsaw, Locky, and Petya, have also used TLS to infect

machines and transfer information. They way in which attackers use TLS, however, is usually quite different from how it is used in legitimate connections. Analyzing

network traffic can often point out some of these differences, such as:

- Offering weak or obsolete cipher suites
- Rarely offering more than one extension (enterprise clients use up to nine)
- Using self-signed certificates

♠Chapter 13: Securing the Network

605

While we focused on TLS 1.3 in this section, it is worth noting that, as of this writing,

the Internet Society reports that only 58 percent of the world's top 1,000 websites support

this latest version. What does this mean to you? You should balance the enhanced security

may want to ask what percentage of your user base would not be able to communicate

securely if you switched. All major browsers support it, so odds are that you'd be in good

shape. But even if you're still on TLS 1.2, keep in mind that most of the features described

in this section that make 1.3 so much better are optional in the previous version. This

should give you a path to gradually improve your security while taking care of your

stakeholders. Whatever your situation, TLS is probably the most important encryption

technology for securing our networks, particularly our virtual private ones. NOTE TLS 1.0 and TLS 1.1 were never formally deprecated but are widely considered insecure.

Private link provided by VPN

Remote user

Figure 13-2

Server

A VPN provides a virtual dedicated link between two entities across a public network.

PART IV

A virtual private network (VPN) is a secure, private connection through an untrusted

network, as shown in Figure 13-2. It is a private connection because the encryption and

tunneling protocols are used to ensure the confidentiality and integrity of the data in

transit. It is important to remember that VPN technology requires a tunnel to work and

it assumes encryption.

We need VPNs because we send so much confidential information from system to system and network to network. The information can be credentials, bank account data,

Social Security numbers, medical information, or any other type of data we do not want

to share with the world. The demand for securing data transfers has increased over the

years, and as our networks have increased in complexity, so have our VPN solutions.

♠CISSP All-in-One Exam Guide

606

Point-to-Point Tunneling Protocol

One of the early approaches to building VPNs was Microsoft's Point-to-Point Tunneling

Protocol (PPTP), which uses Generic Routing Encapsulation (GRE) and TCP to encapsulate Point-to-Point Protocol (PPP) connections and extend them through an IP network

(running on TCP port 1723, by default). Since most Internet-based communication first

started over telecommunication links, the industry needed a way to secure PPP connections, which were prevalent back then. The original goal of PPTP was to provide a way

to tunnel PPP connections through an IP network, but most implementations included

security features also since protection was becoming an important requirement for network transmissions at that time. PPTP, like many security protocols, did not age well and

is now considered insecure and obsolete.

Layer 2 Tunneling Protocol

The Layer 2 Tunneling Protocol (L2TP), currently in version 3, is a combination of Cisco's

Layer 2 Forwarding (L2F) protocol and Microsoft's PPTP. L2TP tunnels PPP traffic over

various network types (IP, ATM, X.25, etc.); thus, it is not just restricted to IP networks

as PPTP was. PPTP and L2TP have very similar focuses, which is to get PPP traffic to

an end point that is connected to some type of network that does not understand PPP.

Unlike PPTP, L2TP runs on UDP (default port 1701), which makes it a bit more efficient. However, just like PPTP, L2TP does not actually provide much protection for the

PPP traffic it is moving around, but it integrates with protocols that do provide security

features. L2TP inherits PPP authentication and integrates with IPSec to provide confidentiality, integrity, and potentially another layer of authentication.

It can get confusing when several protocols are involved with various levels of encapsulation, but if you do not understand how they work together, you cannot identify

if certain traffic links lack security. To figure out if you understand how these protocols

work together and why, ask yourself these questions:

- 1. If the Internet is an IP-based network, why do we even need PPP?
- 2. If L2TP does not actually secure data, then why does it even exist?
- 3. If a connection is using IP, PPP, and L2TP, where does IPSec come into play?

Let's go through the answers together. Let's say that you are a remote user and work

from your home office. You do not have a dedicated link from your house to your company's network; instead, your traffic needs to go through the Internet to be able

to communicate with the corporate network. The line between your house and your ISP is a point-to-point telecommunications link, one point being your home router

and the other point being the ISP's switch, as shown in Figure 13-3. Point-to-point

telecommunication devices do not understand IP, so your router has to encapsulate

your traffic in a protocol the ISP's device will understand—PPP. Now your traffic is not

headed toward some website on the Internet; instead, it has a target of your company's

corporate network. This means that your traffic has to be "carried through" the Internet

to its ultimate destination through a tunnel. The Internet does not understand PPP, so

your PPP traffic has to be encapsulated with a protocol that can work on the Internet

and create the needed tunnel.

♠Chapter 13: Securing the Network

607 Enterprise remote office

ISP local POP

ISP core network

Enterprise headquarters

Enterprise intranet LNS

LAC

Client

ΙP

PPP

L2TP

PPP

ΙP

IPSec

Figure 13-3

IP, PPP, L2TP, and IPSec can work together.

- 1. If the Internet is an IP-based network, why do we even need PPP? Answer: The point-to-point line devices that connect individual systems to the Internet do not understand IP, so the traffic that travels over these links has to be encapsulated in PPP.
- 2. If L2TP does not actually secure data, then why does it even exist? Answer: It extends PPP connections by providing a tunnel through networks that do not understand PPP.
- 3. If a connection is using IP, PPP, and L2TP, where does IPSec come into play? Answer: IPSec provides the encryption, data integrity, and system-based authentication.

Here is another question: Does all of this PPP, L2TP, and IPSec encapsulation have

to happen for every single VPN used on the Internet? No, only when connections over

point-to-point connections are involved. When two gateway routers are connected over

the Internet and provide VPN functionality, they only have to use IPSec.

Internet Protocol Security

Internet Protocol Security (IPSec) is a suite of protocols that was developed to specifically

protect IP traffic. IPv4 does not have any integrated security, so IPSec was developed to

"bolt onto" IP and secure the data the protocol transmits. Where L2TP works at the data

link layer, IPSec works at the network layer of the OSI model.

PART IV

So your IP packets are wrapped up in PPP, and are then wrapped up in L2TP. But you

still have no encryption involved, so your data is actually not protected. This is where

IPSec comes in. IPSec is used to encrypt the data that will pass through the L2TP tunnel.

Once your traffic gets to the corporate network's perimeter device, it will decrypt the

packets, take off the L2TP and PPP headers, add the necessary Ethernet headers, and

send these packets to their ultimate destination.

Here are the answers to our questions:

♠CISSP All-in-One Exam Guide

608

The main protocols that make up the IPSec suite and their basic functionality are

as follows:

- Authentication Header (AH) Provides data integrity, data-origin authentication,
- and protection from replay attacks
- Encapsulating Security Payload (ESP) Provides confidentiality, data-origin authentication, and data integrity
- Internet Security Association and Key Management Protocol (ISAKMP)

Provides a framework for security association creation and key exchange

 \bullet Internet Key Exchange (IKE) Provides authenticated keying material for use with ISAKMP

AH and ESP can be used separately or together in an IPSec VPN configuration. The AH protocols can provide data-origin authentication (system authentication) and protection from unauthorized modification, but do not provide encryption capabilities. If the

VPN needs to provide confidentiality, then ESP has to be enabled and configured properly.

When two routers need to set up an IPSec VPN connection, they have a list of security

attributes that need to be agreed upon through handshaking processes. The two routers

have to agree upon algorithms, keying material, protocol types, and modes of use, which

will all be used to protect the data that is transmitted between them.

Let's say that you and Juan are routers that need to protect the data you will pass back

and forth to each other. Juan sends you a list of items that you will use to process the

packets he sends to you. His list contains AES-128, SHA-1, and ESP tunnel mode. You

take these parameters and store them in a security association (SA). When Juan sends you

packets one hour later, you will go to this SA and follow these parameters so that you know

how to process this traffic. You know what algorithm to use to verify the integrity of the

packets, the algorithm to use to decrypt the packets, and which protocol to activate and

in what mode. Figure 13-4 illustrates how SAs are used for inbound and outbound traffic.

Outbound SA

Outbound SA

To

Protocol

Authentication

Encryption

Joe

ESP

SHA-1, x

AES, y

Inbound SA

То

Protocol

Authentication

Mary

AΗ

MD 5, z

Encryption

Inbound SA

From Protocol Authentication Joe AΗ MD 5, z Encryption From Protocol Authentication Encryption Mary **ESP** SHA-1, xAES, y Authenticate and encrypt Verify and decrypt IPSec packet Authenticate Verify IPSec packet Figure 13-4 IPSec uses security associations to store VPN parameters. ♠Chapter 13: Securing the Network 609 NOTE The U.S. National Security Agency (NSA) uses a protocol encryptor that is based upon IPSec. A HAIPE (High Assurance Internet Protocol Encryptor) is a Type 1 encryption device that is based on IPSec with additional

restrictions, enhancements, and capabilities. A HAIPE is typically a secure

gateway that allows two enclaves to exchange data over an untrusted or lower-classification network. Since this technology works at the network layer, secure end-to-end connectivity can take place in heterogeneous environments. This technology has largely replaced link layer encryption technology implementations.

IPSec

ESP

AΗ

AΗ

Tunnel SA

Local

network

Internet

Local

network

PART IV

IPSec can be configured to provide transport adjacency, which just means that more

than one security protocol (ESP and AH) is used in a VPN tunnel. IPSec can also be configured to provide iterated tunneling, in which an IPSec tunnel is tunneled

through another IPSec tunnel, as shown in the following diagram. Iterated tunneling would be used if the traffic needed different levels of protection at different

junctions of its path. For example, if the IPSec tunnel started from an internal host

and terminated at an internal border router, this may not require encryption, so only the AH protocol would be used. But when that data travels from that border router throughout the Internet to another network, then the data requires more protection. So the first packets travel through a semisecure tunnel until they get

ready to hit the Internet and then they go through a very secure second tunnel.

♠CISSP All-in-One Exam Guide

610

The most common implementation types of TLS VPN are as follows:

• TLS portal VPN An individual uses a single standard TLS connection to a website to securely access multiple network services. The website accessed is typically called a portal because it is a single location that provides access to other

resources. The remote user accesses the TLS VPN gateway using a web browser, is authenticated, and is then presented with a web page that acts as the portal to the

other services.

• TLS tunnel VPN An individual uses a web browser to securely access multiple network services, including applications and protocols that are not web-based, through a TLS tunnel. This commonly requires custom programming to allow the services to be accessible through a web-based connection.

Summary of Tunneling Protocols Layer 2 Tunneling Protocol (L2TP):

- Hybrid of L2F and PPTP
- Extends and protects PPP connections
- Works at the data link layer
- Transmits over multiple types of networks, not just IP
- Combined with IPSec for security

IPSec:

- Handles multiple VPN connections at the same time
- Provides secure authentication and encryption
- Supports only IP networks
- Focuses on LAN-to-LAN communication rather than user-to-user communication
- Works at the network layer and provides security on top of IP Transport Layer Security (TLS):
- Works at the session layer and protects mainly web and e-mail traffic
- Offers granular access control and configuration
- Easy to deploy since TLS is already embedded into web browsers
- Can only protect a small number of protocol types, thus is not an infrastructure-level VPN solution

♠Chapter 13: Securing the Network

611

Since TLS VPNs are closer to the application layer, they can provide more granular

access control and security features compared to the other VPN solutions. But since they

are dependent on the application layer protocol, there are a smaller number of traffic

types that can be protected through this VPN type.

One VPN solution is not necessarily better than the other; they just have their own

focused purposes:

- L2TP is used when a PPP connection needs to be extended through a network.
- IPSec is used to protect IP-based traffic and is commonly used in gateway-togateway connections.
- TLS VPN is used when a specific application layer traffic type needs protection.

Secure Protocols

TLS may be one of the most talked-about technologies when it comes to network security. Still, there are other protocols, and other applications of TLS, that you should know.

This section addresses each of the main network services, web, DNS, and e-mail.

Let's

start with how we secure web services.

Many people hear the term "web services" and think of websites and the web servers that

do the work behind the scenes. In reality, however, this is but a portion of what the term

actually covers. A web service is a client/server system in which clients and servers communicate using HTTP over a network such as the Internet. Sure, this definition covers

static web pages written in HTML being served out of an old Apache server somewhere,

but it can also cover much more.

For example, suppose you are a retailer and don't want to pay for a huge storage space

for merchandise that may or may not sell anytime soon. You could implement a justin-time logistics system that keeps track of your inventory and past selling patterns, and

then automatically order merchandise so that it arrives just before you start running low.

This kind of system is typically implemented using a business-to-business (B2B) web

service and is depicted in Figure 13-5. Each icon in the figure represents a distinct web

service component.

When we look at web services this way, it becomes clear that we have much more to

worry about than simply the interaction between customers and our website. Let's look at

ways in which we could implement some of the secure design principles in this example.

The following list is meant to be illustrative, not all-inclusive:

- Least privilege The forecasting service should have read-only access to some of the data in the inventory system. It doesn't need any additional access.
- Secure defaults The inventory service should refuse all connection requests from any endpoint other than those explicitly authorized (point of sale and forecasting). If any other connections are required, those should be added as exceptions after a careful review.

PART IV

Web Services

♠CISSP All-in-One Exam Guide

612 Organizational environment

Inventory

Up

da

```
te
s
```

Figure 13-5 Example just-intime logistics B2B web service

ipm

en

ts

Updates

Orders

Customers

Sh

Point of sale

ers

Ord

Suppliers

Forecasting

• Fail securely The forecasting service has the ability to spend money by placing

orders from suppliers. It should not process any order that is malformed or otherwise fails any checks.

• Separation of duties The forecasting service can place orders but cannot receive

shipments and update inventory. Ordering and receiving should be two separate duties performed by different people/systems to mitigate the risk of fraud.

- Zero trust Before any two components collaborate, they should both be required to authenticate with each other and encrypt all communications. This is particularly true (and the authentication protocol should be more rigorous) when dealing with external parties like customers and suppliers.
- Privacy by design Customer information should not be shared outside the pointof-sale (PoS) system, particularly since the other two internal systems (inventory

and forecasting) communicate with an external third party. This example is overly

simplistic, but the point is that customer data should be limited to the components

that absolutely need it.

• Trust but verify All components (with the possible exception of the user) should