```
Cooking oils
and fats
Typically found in food
preparation and storage areas
Wet chemicals
Table 10-2
Six EU Types of Fires and Their Suppression Methods
At the risk of confusing things, we also list here the U.S. classification of
fires for
reference.
U.S. Class
Type of Fire
Common combustibles (same as EU)
В
Liquids and gases (EU Classes B and C combined)
C
Electrical (EU Class E)
D
Metals (same as EU)
Κ
Cooking oils and fats (EU Class F)
You can suppress a fire in several ways, all of which require taking certain
precautions.
A fire suppression agent is the substance used to extinguish it. The agent can
be delivered
in a variety of ways such as a portable fire extinguisher or an overhead
distribution system
(e.g., water sprinklers). When designing and implementing fire controls, it is
critical to
match the right suppression agent with the specific facility we're trying to
protect. Overhead water sprinklers may be fine for regular work areas but would
be catastrophic in a
data center. Gases, such as CO2 will reduce damage to our data assets but could
suffocate
humans in confined spaces. If you use CO2, the suppression-releasing device
```

should have

a delay mechanism within it that makes sure the agent does not start applying CO2 to the

area until after an audible alarm has sounded and people have been given time to evacuate. CO2 is a colorless, odorless substance that is potentially lethal because it removes

oxygen from the air. Gas masks do not provide protection against CO2. This type of fire

suppression mechanism is best used in unattended facilities and areas.

For all types of fires except those involving cooking oils and fats, specific types of dry

powders can be used, which include sodium or potassium bicarbonate, calcium carbonate, or monoammonium phosphate. The first three powders interrupt the chemical combustion of a fire. Monoammonium phosphate melts at low temperatures and excludes

oxygen from the fuel.

♠Chapter 10: Site and Facility Security

459

Combustion Element

Suppression Agent

How Suppression Works

Fuel

Soda acid

Removes fuel

0xygen

Carbon dioxide

Displaces oxygen

Temperature

Water

Reduces temperature

Chemical reaction

FM-200 (Halon substitute)

Interferes with the chemical reactions between elements

Table 10-3

How Different Substances Interfere with Elements of Fire

Water Sprinklers

Water sprinklers are typically the simpler and less expensive fire suppression systems but

can cause water damage. In an electrical fire, the water can increase the intensity of the

fire because it can work as a conductor for electricity—only making the situation worse.

If water is going to be used in any type of environment with electrical equipment, the

electricity must be turned off before the water is released. Sensors should be used to shut

down the electric power before water sprinklers activate. Each sprinkler head should

activate individually to avoid wide-area damage, and there should be shutoff valves so the

water supply can be stopped if necessary.

Plenum Area

Wiring and cables are strung through plenum areas, such as the space above dropped

ceilings, the space in wall cavities, and the space under raised floors. Plenum areas

should have fire detectors. Also, only plenum-rated cabling should be used in plenum areas, which is cabling that is made out of material that does not release hazardous gases if it burns.

PART III

Foams are mainly water-based and contain a foaming agent that allows them to

on top of a burning substance to exclude the oxygen.

Wet chemical fire extinguishers contain a potassium solution that cools the fire. However, they have an added benefit of chemically reacting with hot oil or fat, creating a

soapy film on the surface of these fuels, which starves the fire. For this reason, wet chemical extinguishers are the preferred way of putting out fires involving cooking oils and fats.

These extinguishers are also useful for putting put out Class A fires. A fire needs fuel, oxygen, and high temperatures to sustain its chemical reactions. Fire

suppression approaches target one of these three required elements, or the chemical reaction itself. Table 10-3 shows how different suppression substances interfere with these

elements of fire.

The HVAC system should be connected to the fire alarm and suppression system so that it properly shuts down if a fire is identified. A fire needs oxygen, and this type of

system can feed oxygen to the fire. Plus, the HVAC system can spread deadly smoke into

all areas of the building. Many fire systems can configure the HVAC system to shut down

if a fire alarm is triggered.

460

An organization should take great care in deciding which suppression agent and system is best for it. Four main types of water sprinkler systems are available:

• Wet pipe Wet pipe systems always contain water in the pipes and are usually discharged by temperature control-level sensors. One disadvantage of wet pipe systems is that the water in the pipes may freeze in colder climates. Also, if there

is a nozzle or pipe break, it can cause extensive water damage. These types of systems are also called closed-head systems.

• Dry pipe In dry pipe systems, the water is not actually held in the pipes. The water is contained in a "holding tank" until it is released. The pipes hold pressurized air, which is reduced when a fire or smoke alarm is activated, allowing

the water valve to be opened by the water pressure. Water is not allowed into the

pipes that feed the sprinklers until an actual fire is detected. First, a heat or smoke

sensor is activated; then, the water fills the pipes leading to the sprinkler heads,

the fire alarm sounds, the electric power supply is disconnected, and finally water

is allowed to flow from the sprinklers. These pipes are best used in colder climates

because the pipes will not freeze. Figure 10-13 depicts a dry pipe system.

• Preaction Preaction systems are similar to dry pipe systems in that the water is not held in the pipes, but is released when the pressurized air within the pipes is reduced. Once this happens, the pipes are filled with water, but it is not

released right away. A thermal-fusible link on the sprinkler head has to melt before the water is released. The purpose of combining these two techniques is to give people more time to respond to false alarms or to small fires that can be

handled by other means. Putting out a small fire with a handheld extinguisher is better than losing a lot of electrical equipment to water damage. These systems are usually used only in data processing environments rather than the whole building because of the higher cost of these types of systems.

• Deluge A deluge system has its sprinkler heads wide open to allow a larger volume of water to be released in a shorter period. Because the water being released is in such large volumes, these systems are usually not used in data processing environments.

Figure 10-13 Dry pipe systems do not hold water in the pipes.

Water supply

When temperature meets a predefined value,

the valve opens. Water valve opened Water sprinklers

♠Chapter 10: Site and Facility Security

461

Environmental Issues

Chapter Review

Physical security of our sites and facilities requires a deliberate planning, execution, and

review process. In this chapter, we have discussed the most important topics you'll need

to know about to ensure that your organization's physical spaces are secure, but it's up

to you to apply them in your particular situations. One of the most important aspects

of securing a facility is controlling access in and out of it. In our experience, it is rare for

an auditor (such as a physical penetration tester) to not be able to breach this perimeter

through social engineering, lockpicking, or simply waiting for someone to leave a door

propped open when they shouldn't. This underscores the importance of applying defense

in depth and the other principles we discussed in the first half of the chapter. The practical application of these secure design principles happens through security

controls. Though our focus is on physical security, these controls can be administrative

(e.g., policies and procedures), technical (e.g., keycard entry systems and security

cameras), or physical (e.g., fences and guards). By carefully balancing threats, resources,

and controls in a deliberate manner, we can provide effective site and facility security.

Quick Review

• A site is a geographic area with fixed boundaries that typically contains at least one

building and its supporting structures (e.g., a parking lot or electric substation).

- A facility is a building or a part of a building dedicated to a specific purpose, such
- as corporate headquarters or a data center.
- The secure design principles covered in Chapter 9 for information systems are just as applicable to the design of physical security.
- The value of property within the facility and the value of the facility itself

to be ascertained to determine the proper budget for physical security so that security controls are cost-effective.

PART III

In drier climates, or during the winter, the air contains less moisture, which can cause

static electricity when two dissimilar objects touch each other. This electricity usually

travels through the body and produces a spark from a person's finger that can release

several thousand volts. This can be more damaging than you would think. Usually, the

charge is released on a system casing and is of no concern, but sometimes it is released

directly to an internal computer component and causes damage. People who work on the internal parts of a computer usually wear antistatic armbands to reduce the chance

of this happening.

In more humid climates, or during the summer, more humidity is in the air, which can also affect components. Particles of silver can begin to move away from connectors

onto copper circuits, which cement the connectors into their sockets. This can adversely

affect the electrical efficiency of the connection. A hygrometer is usually used to monitor

humidity. It can be manually read, or an automatic alarm can be set up to go off if the

humidity passes a set threshold.

♠CISSP All-in-One Exam Guide

462

- Some physical security controls may conflict with the safety of people. These issues need to be addressed; human life is always more important than protecting a facility or the assets it contains.
- When looking at locations for a facility, consider local crime; natural disaster

possibilities; and distance to hospitals, police and fire stations, airports, and railroads.

- Crime Prevention Through Environmental Design (CPTED) combines the physical environment and sociology issues that surround it to reduce crime rates and the fear of crime.
- CPTED provides four main strategies, which are natural access control, natural surveillance, territorial reinforcement, and maintenance.
- Natural access control is the guidance of people entering and leaving a space by

the placement of doors, fences, lighting, and even landscaping.

• The goal of natural surveillance is not only to make criminals feel uncomfortable

by providing many ways observers could potentially see them but also to make authorized personnel feel safe and comfortable by providing an open and welldesigned environment.

• Territorial reinforcement creates physical designs (e.g., using walls, fences, landscaping) that emphasize or extend the organization's physical sphere of influence so legitimate users feel a sense of ownership of that space.

- CPTED's maintenance principle focuses on deterring criminal activity by making sites look well cared for, thus implying that site personnel are more attentive, well resourced, and alert.
- Target hardening focuses on denying access through physical and artificial barriers (alarms, locks, fences, and so on).
- If interior partitions do not go all the way up to the true ceiling, an intruder

can remove a ceiling tile and climb over the partition into a critical portion of

the facility.

- The primary power source is what is used in day-to-day operations, and the alternative power source is a backup in case the primary source fails.
- Smoke detectors should be located on and above suspended ceilings, below raised

floors, and in air ducts to provide maximum fire detection.

- A fire needs high temperatures, oxygen, and fuel. To suppress it, one or more of those items needs to be reduced or eliminated.
- Portable fire extinguishers should be located within 50 feet of electrical equipment

and should be inspected quarterly.

• CO2 is a colorless, odorless, and potentially lethal substance because it removes

the oxygen from the air in order to suppress fires.

- Window types that should be understood are standard, tempered, acrylic, wired, and laminated.
- ◆Chapter 10: Site and Facility Security

463

Questions

Please remember that these questions are formatted and asked in a certain way for a

reason. Keep in mind that the CISSP exam is asking questions at a conceptual level.

Questions may not always have the perfect answer, and the candidate is advised against

always looking for the perfect answer. Instead, the candidate should look for the best

answer in the list.

- 1. When should a CO2 fire extinguisher be used?
- A. When electrical equipment is on fire
- B. When gases are on fire
- C. When a combustible metal is on fire
- D. In workspaces with paper products
- A. When electrical equipment is on fire
- B. When gases are on fire
- C. When a combustible metal is on fire
- D. In workspaces with paper products
- 3. Which of the following is not a main component of CPTED?
- A. Natural access control
- B. Natural surveillance
- C. Territorial reinforcement

- D. Target hardening
- 4. Which problems may be caused by humidity in an area with electrical devices?
- A. High humidity causes excess electricity, and low humidity causes corrosion.
- B. High humidity causes corrosion, and low humidity causes static electricity.
- C. High humidity causes power fluctuations, and low humidity causes static

electricity.

- D. High humidity causes corrosion, and low humidity causes power fluctuations.
- 5. The fourth principle of Crime Prevention Through Environmental Design (CPTED) is maintenance. What does this principle entail?
- A. Ensuring that target hardening controls remain in working order
- B. Periodically assessing designs to ensure they remain effective
- C. Maintaining visibility over all elements of the environmental design
- D. Deterring criminal activity by making sites look well cared for

PART III

2. When should a water sprinkler system be used?

♠CISSP All-in-One Exam Guide

464

- 6. Which of the following answers contains a category of controls that does not belong in a physical security program?
- A. Deterrence and delaying
- B. Response and detection
- C. Assessment and detection
- D. Delaying and lighting

Use the following scenario to answer Questions 7-9. You are the CISO for a data analytics

company and, after reading this chapter, have decided to review the physical security of

your facility. You currently lease the top three floors of a high-rise building in a major

metropolitan area. The top floor contains the executive suites and conference facilities.

The next floor down houses your data center and research and development (R&D) and

software development teams. The lower floor is where your administrative and sales staff

workspaces are located.

7. As part of your lease agreement, the building owners provide a reception area in

the lobby with receptionists, security guards, keycard-based access controls, and

security cameras. What secure design principle is this arrangement an example of?

- A. Zero trust
- B. Trust but verify
- C. Shared responsibility
- D. Separation of duties
- 8. As you ride the elevator up, you notice that your company employees can use

their keycards to access any of the top three floors. What secure design principle

could this violate?

- A. Shared responsibility
- B. Simplicity
- C. Defense in depth
- D. Secure defaults
- 9. Based on your preliminary findings, you are concerned about the security of your

facility and decide to redo the entire plan. What would you do first?

- A. Determine the resources available to you
- B. Conduct an audit of the current posture
- C. Apply the secure design principles
- D. Conduct a risk assessment

♠Chapter 10: Site and Facility Security

465

Answers

1. A. CO2 fire extinguishers work by displacing oxygen and thus choking the fire.

This approach can put human lives in danger of also choking, so it should not be used in workspaces. It is also not ideal for gas or metal fires. It is, however,

very well suited for electrical fires since it minimizes the risk of electric shock and

damage to the equipment.

2. D. Water sprinklers are very effective against wood and paper fires and are safe

for humans, so they are a good choice for use in regular workspaces. They are, however, particularly bad choices to use against the other types of fires listed (electric, gas, metal).

- 4. B. High humidity can cause corrosion, and low humidity can cause excessive static electricity. Static electricity can short out devices or cause loss of information.
- 5. D. CPTED's maintenance principle focuses on deterring criminal activity by making sites look well cared for, thus implying that site personnel are more attentive, well resourced, and possibly alert.
- 6. D. The categories of controls that should make up any physical security program

are deterrence, delaying, detection, assessment, and response. Lighting is a control

itself, not a category of controls.

7. C. Shared responsibility usually involves different organizations that have a services agreement, such as leasing office spaces and having the landlord provide

security in the entry points. Separation of duties is similar but applies to

responsibilities divided between individuals to deter and prevent any one party from damaging the company. While elements of zero trust and trust but verify are present in the scenario, they are not the salient ones.

8. C. Defense in depth means you should create concentric rings around your most

critical resources. In this case, only certain individuals should have access to the

executive spaces and, possibly, the data center floor, unless you have additional

security controls in place as soon as someone enters those two floors.

9. D. Site and facility security, like any other type of security, must start with an

understanding of the risks faced by the organization. These risks determine the required resources for the effort and the manner in which the secure design principles are applied to your particular situation.

PART III

3. D. Target hardening has to do with implementing locks, security guards, and proximity devices. Natural access control is the use of the environment to control

access to entry points, such as using landscaping and bollards. An example of natural surveillance is the construction of pedestrian walkways so there is a clear

line of sight of all the activities in the surroundings. Territorial reinforcement

gives people a sense of ownership of a property, giving them a greater tendency to

protect it. These concepts are all parts of CPTED.

♠This page intentionally left blank

♠PART IV

Communication and Network Security Chapter 11

Chapter 12

Chapter 13

Chapter 14

Chapter 15

Networking Fundamentals Wireless Networking Securing the Network Network Components Secure Communications Channels

♠This page intentionally left blank

↑CHAPTER

Networking Fundamentals

11

This chapter presents the following:

- Data communications foundations
- Networking protocols

• Local, metropolitan, and wide area networks

The Internet…it's a series of tubes.

-Ted Stevens

Before we dive into communications and network security, it makes sense to review (and

maybe pick up a bit of new information on) the fundamentals of data communications

networks. Data communications and networking are complex topics, mainly because so

many technologies are involved. Our current technologies are constantly evolving, and

every month there seems to be new "emerging" ones that we have to learn, understand,

implement, and secure. As security professionals, we need a solid grasp of networking

software, protocols, services, and devices. We have to be able to identify and deal with

interoperability issues (ideally before developing or acquiring a new system). Armed with

all this knowledge and skill, we need to anticipate or discover vulnerabilities, both in

individual components and in their interactions with each other, and devise effective

controls for them. This can be a challenging task. However, if you are knowledgeable,

have a solid practical skill set, and are willing to continue to learn, you can have more

career opportunities than you know what to do with.

In this chapter we will start with the basics of data communications and networking,

and then build upon them and identify many of the security issues that are involved.

We'll follow up in the next chapter with a discussion of wireless technologies that take

the place of the cables described in this chapter. Then, in Chapter 13 we'll dive into the

protocols that drive the Internet. This will set the stage for understanding how we secure

this hodgepodge of technologies, the focus of Chapters 14 and 15.

Data Communications Foundations

Data communications have made amazing advances in a relatively short period of time.

In the beginning of the Computer Age, mainframes were the name of the game. They were isolated powerhouses, and many had "dumb" terminals hanging off them, but this

469

♠CISSP All-in-One Exam Guide

470

was not true networking. In the late 1960s and early 1970s, some technical

researchers

came up with ways of connecting all the mainframes and Unix systems to enable them to

communicate. This marked the Internet's first baby steps.

While access to shared resources was a major drive in the evolution of networking, today

the infrastructure that supports these shared resources and the services these components

provide is really the secret to the secret sauce. As we will see, networks are made up

of routers, switches, servers, proxies, firewalls, intrusion detection/prevention systems

(IDS/IPSs), storage systems, virtual private network (VPN) concentrators, public key

infrastructure, private branch exchanges (PBXs), and more. While functionality is critical,

there are other important requirements that need to be understood when architecting

a network, such as scalability, redundancy, performance, security, manageability, and $% \left(1\right) =\left(1\right) \left(1\right) \left($

maintainability.

Infrastructure provides foundational capabilities that support almost every aspect of

our lives. When most people think of technology, they focus on the end systems that

they interact with—laptops, mobile phones, tablet PCs, workstations, and so on—or the

applications they use, such as e-mail, Facebook, websites, instant messaging, Twitter, and

online banking. Most people do not even give a thought to how this stuff works under

the covers, and many people do not fully realize all the other stuff that is dependent upon

technology: medical devices, critical infrastructure, weapon systems, transportation,

satellites, telephony, and so forth. People say it is love that makes the world go around, but

let them experience one day without the Internet. We are all more dependent upon the

Matrix than we fully realize, and as security professionals we need to not only understand

the Matrix but also secure it.

Before we get into the weeds of actual devices, systems, and services, it will be helpful

to have a reference model so that we can put like pieces in the same bin. This will allow

us to compare things that perform similar functions so that we can better see how they

differ and what those differences may mean for security. Let's start off by introducing the

two most common models for understanding networked systems: the OSI model and the TCP/IP model.

Network Reference Models

In the early 1980s, the International Organization for Standardization (as it is referred

to internationally, but commonly abbreviated as ISO) worked to develop a protocol

set that would be used by all vendors throughout the world to allow the interconnection of network devices. This movement was fueled with the hopes of ensuring that all

vendor products and technologies could communicate and interact across international

and technical boundaries. The actual protocol set did not catch on as a standard, but the

Open Systems Interconnection (OSI) reference model was adopted and is used as an abstract

framework to which most operating systems and protocols adhere.

Many people think that the OSI reference model arrived at the beginning of the computing age as we know it and helped shape and provide direction for many, if not all,

networking technologies. However, this is not true. In fact, it was introduced in 1984, at

which time the basics of the Internet had already been developed and implemented, and

the basic Internet protocols had been in use for many years.

♠Chapter 11: Networking Fundamentals

471
Figure 11-1
The OSI and TCP/
IP networking
models

OSI model

TCP/IP model

Application

Presentation

Application

Session

Transport

Host-to-host

Network

Internet

Data link

Network access

Physical

NOTE The host-to-host layer is sometimes called the transport layer in the TCP/IP model. The application layer in the TCP/IP architecture model is equivalent to a combination of the application, presentation, and session layers in the OSI model.

Protocols

Before we delve into the details of each layer of the OSI model, we need to examine the

concept of network protocols. A network protocol is a standard set of rules that determines

how systems will communicate across networks. Two different systems that use the same

protocol can communicate and understand each other despite their differences, similar to

how two people can communicate and understand each other by using the same language.

PART IV

The Transmission Control Protocol/Internet Protocol (TCP/IP) suite actually has its own model that predates the OSI model by several years. As a bit of background,

the Internet as we know it grew from the Advanced Research Project Agency Network

(ARPANET) program that started in the late 1960s. By 1978, ARPANET researchers realized that a monolithic approach to networking was not going to scale well. That's

when they split what had until then been known as the Transmission Control Program

(which encompassed all aspects of getting data from point A to point B) into two distinct

layers: TCP and IP. Everything that happened below IP was the domain of network access engineers, and everything above TCP was the domain of application developers.

The idea caught on and the TCP/IP reference model was born. It is often used today

when examining and understanding networking issues. Figure 11-1 shows the differences

between the OSI and TCP/IP networking models. In this chapter, we will focus on the $\,$

OSI model.

♠CISSP All-in-One Exam Guide

472

The OSI reference model, as described by ISO Standard 7498-1, provides important guidelines used by vendors, engineers, developers, and others. The model segments the

networking tasks, protocols, and services into different layers. Each layer has its own

responsibilities regarding how two computers communicate over a network. Each

layer

has certain functionalities, and the services and protocols that work within that layer

fulfill them.

The OSI model's goal is to help vendors develop products that will work within an

open network architecture. An open network architecture is one that no vendor owns.

that is not proprietary, and that can easily integrate various technologies and vendor

implementations of those technologies. Vendors have used the OSI model as a jumpingoff point for developing their own networking frameworks. These vendors use the OSI

model as a blueprint and develop their own protocols and services to produce functionality

that is different from, or overlaps, that of other vendors. However, because these vendors

use the OSI model as their starting place, integration of other vendor products is an

easier task, and the interoperability issues are less burdensome than if the vendors had

developed their own networking framework from scratch.

Although computers communicate in a physical sense (electronic signals are passed

from one computer over a wire to the other computer), they also communicate through

logical channels. Each protocol at a specific OSI layer on one computer communicates

with a corresponding protocol operating at the same OSI layer on another computer.

This happens through encapsulation.

Logical data movement

Application

Application

Presentation

Presentation

Session

Session

Transport

Transport

Network

Network

Data link

Data link Physical Physical ♠Chapter 11: Networking Fundamentals 473 Data encapsulation Figure 11-2 **Application** Data Presentation Data Session Data Transport Data Network Data Data link Data Physical Data Each OSI layer protocol adds its own information to the data packet. PART IV Here's how encapsulation works: A message is constructed within a program on one computer and is then passed down through the network protocol's stack. A protocol at each layer adds its own information to the message, creating a protocol data unit (PDU). Thus, the message grows in size as it goes down the protocol stack. The message is then

sent to the destination computer, and the encapsulation is reversed by taking the packet

apart through the same steps used by the source computer that encapsulated it. At the

data link layer, the PDU pertaining to the data link layer is deconstructed, and the

packet is sent up to the next layer. Then at the network layer, the network layer PDU

is stripped and processed, and the message is again passed up to the next layer, and so

on. This is how computers communicate logically. The information stripped off at the

destination computer informs it how to interpret and process the packet properly. Data

encapsulation is shown in Figure 11-2.

A protocol at each layer has specific responsibilities and control functions it performs,

as well as data format syntaxes it expects. Each layer has a special interface (connection

point) that allows it to interact with three other layers: (1) communications from the

interface of the layer above it, (2) communications to the interface of the layer below it,

and (3) communications with the same layer in the interface of the target packet address.

The control functions, added by the protocols at each layer, are in the form of headers

and trailers of the packet.

The benefit of modularizing these layers, and the functionality within each layer, is

that various technologies, protocols, and services can interact with each other and provide

the proper interfaces to enable communications. This means a computer can use an application protocol developed by Microsoft, a transport protocol developed by Apple,

♠CISSP All-in-One Exam Guide

474

Attacks at Different Layers

As we examine the different layers of a common network stack, we will also look at

the specific attack types that can take place at each layer. One concept to understand

at this point is that a network can be used as a channel for an attack, or the network

can be the target of an attack. If the network is a channel for an attack, this means

the attacker is using the network as a resource. For example, when an attacker sends

a virus from one system to another system, the virus travels through the network channel. If an attacker carries out a denial-of-service (DoS) attack, which sends a

large amount of bogus traffic over a network link to bog it down, then the

network

itself is the target. As you will see throughout this book, it is important to understand how attacks take place and where they take place so that the correct countermeasures can be put into place.

and a data link protocol developed by Cisco to construct and send a message over a

network. The protocols, technologies, and computers that operate within the OSI model

are considered open systems. Open systems are capable of communicating with other open

systems because they implement international standard protocols and interfaces. The

specification for each layer's interface is very structured, while the actual code that makes

up the internal part of the software layer is not defined. This makes it easy for vendors to

write plug-ins in a modularized manner. Systems are able to integrate the plug-ins into

the network stack seamlessly, gaining the vendor-specific extensions and functions.

Understanding the functionalities that take place at each OSI layer and the corresponding protocols that work at those layers helps you understand the overall

communication process between computers. Once you understand this process, a more

detailed look at each protocol will show you the full range of options each protocol

provides and the security weaknesses embedded into each of those options.

Application Layer

The application layer, layer 7, works closest to the user and provides file transmissions,

message exchanges, terminal sessions, and much more. This layer does not include the

actual applications, but rather the protocols that support the applications. When an

application needs to send data over the network, it passes instructions and the data to the

protocols that support it at the application layer. This layer processes and properly formats the data and passes it down to the next layer within the OSI model. This happens

until the data the application layer constructed contains the essential information from

each layer necessary to transmit the data over the network. The data is then put on the

network cable and transmitted until it arrives at the destination computer.

As an analogy, let's say that you write a letter that you would like to send to your

congressman. Your job is to write the letter, your clerk's job is to figure out how to get it to

him, and the congressman's job is to read your letter and respond to it. You (the application)

create the content (message) and hand it to your assistant (application layer

protocol).

♠Chapter 11: Networking Fundamentals

475

Outlook

Firefox

Word

API

API

API

SMTP

31111

HTTP

LPD

Figure 11-3 Applications send requests to an API, which is the interface to the supporting protocol.

Presentation Layer

The presentation layer, layer 6, receives information from the application layer protocol

and puts it in a format that any process operating at the same layer on a destination computer following the OSI model can understand. This layer provides a common means of

representing data in a structure that can be properly processed by the end system. This

means that when a user creates a Word document and sends it out to several people, it

does not matter whether the receiving computers have different word processing programs; each of these computers will be able to receive this file and understand and present it to its user as a document. It is the data representation processing that is done at

the presentation layer that enables this to take place. For example, when a Windows 10

computer receives a file from another computer system, information within the file's

header indicates what type of file it is. The Windows 10 operating system has a list of file

types it understands and a table describing what program should be used to open and

PART IV

Your assistant puts the content into an envelope, writes the congressman's address on the

envelope (inserts headers and trailers), and puts it into the mailbox (passes it on to the next

protocol in the network stack). When your assistant checks the mailbox a week

later, there

is a letter from the congressman (the remote application) addressed to you. Your assistant

opens the envelope (strips off headers and trailers) and gives you the message (passes the

message up to the application).

Some examples of the protocols working at the application layer are the Simple Mail

Transfer Protocol (SMTP), the Hypertext Transfer Protocol (HTTP), and the Line Printer Daemon (LPD) protocol. Figure 11-3 shows how applications communicate with the underlying protocols through application programming interfaces (APIs). If a

user makes a request to send an e-mail message through her e-mail client Outlook, the

e-mail client sends this information to SMTP. SMTP adds its information to the user's

message and passes it down to the presentation layer.

♠CISSP All-in-One Exam Guide

476

manipulate each of these file types. For example, suppose the sender e-mails a Portable

Document Format (PDF) file created in Word and the receiver uses a Linux system. The

receiver can open this file because the presentation layer on the sender's system encoded

the file and added a descriptive header in accordance with the Multipurpose Internet

Mail Extensions (MIME) standards, and the receiver's computer interprets the header's

MIME type (Content-Type: application/pdf), decodes the file, and knows to open it

with its PDF viewer application.

The presentation layer is concerned not with the meaning of data but with the syntax

and format of that data. It works as a translator, translating the format an application

is using to a standard format used for passing messages over a network. If a user uses a

graphics application to save a file, for example, the graphic could be a Tagged Image

File Format (TIFF), Graphic Interchange Format (GIF), or Joint Photographic Experts

Group (JPEG) format. The presentation layer adds information to tell the destination $\ensuremath{\mathsf{I}}$

computer the file type and how to process and present it. This way, if the user sends this

graphic to another user who does not have the same graphics application, the receiving

user's operating system can still present the graphic because it has been saved in a standard

format. Figure 11-4 illustrates the conversion of a file into different standard file types.

This layer also handles data compression and encryption issues. If a program requests

a certain file to be compressed and encrypted before being transferred over the network,

the presentation layer provides the necessary information for the destination computer.

It provides information on how the file was encrypted and/or compressed so that the receiving system knows what software and processes are necessary to decrypt and

decompress the file. Let's say Sara compresses a file using WinZip and sends it to you.

When your system receives this file, it looks at data within the header (Content-Type:

application/zip) and knows what application can decompress the file. If your system has

WinZip installed, then the file can be decompressed and presented to you in its original

form. If your system does not have an application that understands the compression/

decompression instructions, the file will be presented to you with an unassociated icon.

Figure 11-4
The presentation
layer receives
data from the
application layer
and puts it into a
standard format.

Application layer

Presentation layer

Compression

Encryption

TIFF

JPEG

♠Chapter 11: Networking Fundamentals

477

Session Layer

When two applications need to communicate or transfer data between themselves, a connection may need to be set up between them. The session layer, layer 5, is responsible for establishing a connection between the two applications, maintaining it during

the transfer of data, and controlling the release of this connection. A good analogy for

the functionality within this layer is a telephone conversation. When Kandy

wants to

call a friend, she uses the telephone. The telephone network circuitry and protocols set

up the connection over the telephone lines and maintain that communication path, and when Kandy hangs up, they release all the resources they were using to keep that

connection open.

Similar to how telephone circuitry works, the session layer works in three phases:

connection establishment, data transfer, and connection release. It provides session restart

and recovery if necessary and provides the overall maintenance of the session. When the

conversation is over, this path is broken down and all parameters are set back to their

original settings. This process is known as dialog management. Figure 11-5 depicts the

three phases of a session. Some protocols that work at this layer are the Layer 2 Tunneling

Protocol (L2TP), Point-to-Point Tunneling Protocol (PPTP), and Remote Procedure Call (RPC).

Session layer

Connection establishment

Data transfer

Connection release

PART IV

Figure 11-5
The session
layer sets up
the connection,
maintains it,
and tears it
down once
communication
is completed.

♠CISSP All-in-One Exam Guide

478

The session layer protocol can enable communication between two applications to happen in three different modes:

- Simplex Communication takes place in one direction, though in practice this is very seldom the case.
- Half-duplex Communication takes place in both directions, but only one application can send information at a time.
- Full-duplex Communication takes place in both directions, and both applications can send information at the same time.

Many people have a hard time understanding the difference between what takes place

at the session layer versus the transport layer because their definitions sound similar.

Session layer protocols control application-to-application communication, whereas the

transport layer protocols handle computer-to-computer communication. For example,

if you are using a product that is working in a client/server model, in reality you have a

small piece of the product on your computer (client portion) and the larger piece of the

software product is running on a different computer (server portion). The communication

between these two pieces of the same software product needs to be controlled, which is

why session layer protocols even exist. Session layer protocols take on the functionality of

middleware, which allows software on two different computers to communicate. Session layer protocols provide interprocess communication channels, which allow a piece of software on one system to call upon a piece of software on another system

without the programmer having to know the specifics of the software on the receiving

system. The programmer of a piece of software can write a function call that calls

upon a subroutine. The subroutine could be local to the system or be on a remote system. If the subroutine is on a remote system, the request is carried over a session

layer protocol. The result that the remote system provides is then returned to the

requesting system over the same session layer protocol. This is how RPC works. A piece of software can execute components that reside on another system. This is the

core of distributed computing.

NOTE One security issue common to RPC (and similar interprocess communication systems) is improperly configured authentication or the use of unencrypted communications.

Session layer protocols are the least used protocols in a network environment; thus,

many of them should be disabled on systems to decrease the chance of them being exploited. RPC, NetBIOS, and similar distributed computing calls usually only need to

take place within a network; thus, firewalls should be configured so this type of traffic is

not allowed into or out of a network. Firewall filtering rules should be in place to stop

this type of unnecessary and dangerous traffic.

♠Chapter 11: Networking Fundamentals

Transport Layer

When two computers are going to communicate through a connection-oriented protocol, they first agree on how much information each computer will send at a time, how to

verify the integrity of the data once received, and how to determine whether a packet was

lost along the way. The two computers agree on these parameters through a handshaking

process at the transport layer, layer 4. The agreement on these issues before transferring

data helps provide more reliable data transfer, error detection, correction, recovery, and

flow control, and it optimizes the network services needed to perform these tasks. The

transport layer provides end-to-end data transport services and establishes the logical

connection between two communicating computers.

NOTE Connection-oriented protocols, such as Transmission Control Protocol (TCP), provide reliable data transmission when compared to connectionless protocols, such as User Datagram Protocol (UDP). This distinction is covered in more detail in the "Internet Protocol Networking" section, later in the chapter.

NOTE Different references can place specific protocols at different layers. For example, many references place the Transport Layer Security (TLS) protocol in the session layer, while other references place it in the transport layer. Neither placement is right or wrong. The OSI model tries to draw boxes around reality, but some protocols straddle the different layers.

PART IV

The functionality of the session and transport layers is similar insofar as they both

set up some type of session or virtual connection for communication to take place. The

difference is that protocols that work at the session layer set up connections between

applications, whereas protocols that work at the transport layer set up connections

between computer systems. For example, we can have three different applications on

computer A communicating with three applications on computer B. The session layer

protocols keep track of these different sessions. You can think of the transport laver

protocol as the bus. It does not know or care what applications are communicating

with each other. It just provides the mechanism to get the data from one system to

another.

The transport layer receives data from many different applications and assembles the

data into a stream to be properly transmitted over the network. The main protocols that

work at this layer are the Transmission Control Protocol (TCP) and the User Datagram Protocol (UDP). Information is passed down from different entities at higher layers to the transport layer, which must assemble the information into a stream, as shown Figure 11-6. The stream is made up of the various data segments passed to it. Just like a bus can carry a variety of people, the transport layer protocol can carry a variety of application data types. ♠CISSP All-in-One Exam Guide 480 Firefox Data Outlook Data Data Zoom Data Data Data Transport layer Data Data Data Data Data Data Data Data

Data

Data

Assemble data into a stream

Figure 11-6 TCP formats data from applications into a stream to be prepared for transmission.

Network Layer

The main responsibilities of the network layer, layer 3, are to insert information into the

packet's header so it can be properly addressed and routed, and then to actually route

the packet to its proper destination. In a network, many routes can lead to one destination. The protocols at the network layer must determine the best path for the packet to

take. Routing protocols build and maintain their routing tables. These tables are maps

of the network, and when a packet must be sent from computer A to computer M, the

protocols check the routing table, add the necessary information to the packet's header,

and send it on its way.

The protocols that work at this layer do not ensure the delivery of the packets. They

depend on the protocols at the transport layer to catch any problems and resend packets

if necessary. The Internet Protocol (IP) is the predominant protocol working at the

network layer, although other routing and routed protocols work there as well. Some

of the other protocols are the Internet Control Message Protocol (ICMP), Routing Information Protocol (RIP), Open Shortest Path First (OSPF), Border Gateway Protocol

(BGP), and Internet Group Management Protocol (IGMP). Figure 11-7 shows that a packet can take many routes and that the network layer enters routing information into

the header to help the packet arrive at its destination.

Data Link Layer

As we continue down the protocol stack, we are getting closer to the actual transmission

channel (e.g., network wire) over which all the data will travel. The network layer has

already figured out how to route the packet through the various network devices to its

final destination, but we still need to get the data over to the next, directly connected

device. This happens at the data link layer, layer 2.

♠Chapter 11: Networking Fundamentals

481

Network layer

PART IV

Figure 11-7 The network layer determines the most efficient path for each packet to take.

Different networking technologies, as we will shortly discuss in detail, can use different protocols, network interface cards (NICs), cables, and transmission methods.

Each of these components has a different header data format structure, and they interpret

electromagnetic signals in different ways. The data link layer is where the network

stack knows in what format the data frame must be in order to transmit it properly

over Ethernet, wireless, or frame relay links. If the network is an Ethernet network, for

example, all the computers will expect packet headers to be a certain length, the flags

to be positioned in certain field locations within the header, and the trailer information

to be in a certain place with specific fields. Compared to Ethernet, frame relay network

technology has different frame header lengths, flag values, and header formats. The data link layer can be further divided into two functional sublayers:
Logical Link

Control (LLC), whose job is to interface with the network layer above, and Media Access

Control (MAC), which is designed to interface with the physical layer below. Let's drill

into this a bit. The LLC sublayer, which is defined in the ISO/IEC 8802-2 standard for

Ethernet networks, receives a message (say, an IP packet) from layer 3 and negotiates

the manner in which it should be sent out over the network link. This could include

keeping track of which layer 3 protocol was used, determining what kind of service (e.g.,

♠CISSP All-in-One Exam Guide

482
Figure 11-8
The data link
layer is made up
of two sublayers.

OSI layers Upper layers

IEEE 802 layers LLC Logical Link Control

Data link

MAC Media Access Control Physical

Physical

connectionless or connection-oriented) will be used, and performing flow control so

the link doesn't get saturated. The LLC sublayer then hands over the data to the MAC

sublayer, which encapsulates it into a frame of the right type depending on the networking

technology in use by the physical layer. Generally, LLC is implemented in software (as a

device driver), while MAC is built in firmware on a physical device. Figure 11-8 shows

these two sublayers that make up the data link layer.

As data is passed down the network stack, it has to go from the network layer to the data link layer. The protocol at the network layer does not know if the underlying

network is Ethernet, wireless, or frame relay—it does not need to have this type of

insight. The protocol at the network layer just adds its header and trailer information to

the packet and passes it on to the next layer, which is the LLC sublayer. The LLC sublayer

takes care of flow control and error checking. Data coming from the network layer passes

down through the LLC sublayer and goes to the MAC sublayer. The technology at the

MAC sublayer knows if the network is Ethernet, wireless, or frame relay, so it knows how

to put the last header and trailer on the packet before it "hits the wire" for transmission.

Some of the protocols that work at the data link layer are the Point-to-Point Protocol

(PPP), Asynchronous Transfer Mode (ATM), Layer 2 Tunneling Protocol (L2TP), Fiber

Distributed Data Interface (FDDI), Ethernet, and Token Ring.

Each network technology (Ethernet, wireless, frame relay, and so on) defines the compatible physical transmission type (coaxial, twisted pair, fiber, wireless) that is

required to enable network communication. Each network technology also has defined

electronic signaling and encoding patterns. For example, if we were transmitting a bit

with the value of 1 over an Ethernet network, the MAC sublayer would tell the physical

layer to create a +0.5-volt electric signal. In the "language of Ethernet" this means that

0.5 volts is the encoding value for a bit with the value of 1. If the next bit the MAC

sublayer receives is 0, the MAC layer would tell the physical layer to transmit 0 volts. The

different network types will have different encoding schemes.

NICs bridge the data link and physical layers. Data is passed down through the first six

layers and reaches the NIC at the data link layer. Depending on the network technology

being used, the NIC encodes the bits at the data link layer, which are then turned into

electricity states at the physical layer and placed onto the wire for transmission.

♠Chapter 11: Networking Fundamentals

483

EXAM TIP When the data link layer applies the last header and trailer to the data message, this is referred to as framing. The unit of data is now called a frame.

Physical Layer

The physical layer, layer 1, converts bits into electromagnetic signals for transmission.

Signals and voltage schemes have different meanings for different LAN and WAN technologies, as covered earlier. If a user sends data through the radio transceiver on a smartphone, the data format, electrical signals, and control functionality are much different

than if that user sends data through an Ethernet NIC and onto an unshielded twisted

pair (UTP) wire for LAN communication. The mechanisms that control this data going

onto the radio waves, or the UTP wire, work at the physical layer. This layer controls

synchronization, data rates, line noise, and transmission techniques. Specifications for

the physical layer include the timing of voltage changes, voltage levels, and the physical

connectors for electrical, optical, and mechanical transmission.

Functions and Protocols in the OSI Model

For the CISSP exam, you will need to know the functionality that takes place at the different layers of the OSI model, along with specific protocols that work at each layer. The

following is a quick overview of each layer and its components.

Application

The protocols at the application layer handle file transfer, virtual terminals, network

management, and fulfilling networking requests of applications. A few of the protocols

that work at this layer include

- File Transfer Protocol (FTP)
- Network Time Protocol (NTP)
- Simple Mail Transfer Protocol (SMTP)
- Internet Message Access Protocol (IMAP)
- Hypertext Transfer Protocol (HTTP)

Presentation

The services of the presentation layer handle translation into standard formats, data compression and decompression, and data encryption and decryption. No protocols work at

this layer, just services. The following lists some of the presentation layer standards:

- American Standard Code for Information Interchange (ASCII)
- Tagged Image File Format (TIFF)

PART IV

EXAM TIP To remember all the layers within the OSI model in the correct order, memorize "All People Seem To Need Data Processing." Remember that you are starting at layer 7, the application layer, at the top.

♠CISSP All-in-One Exam Guide

484

- Joint Photographic Experts Group (JPEG)
- Motion Picture Experts Group (MPEG)
- Musical Instrument Digital Interface (MIDI)

Session

The session layer protocols set up connections between applications; maintain dialog

control; and negotiate, establish, maintain, and tear down the communication channel.

Some of the protocols that work at this layer include

- Layer 2 Tunneling Protocol (L2TP)
- Network Basic Input Output System (NetBIOS)
- Password Authentication Protocol (PAP)
- Point-to-Point Tunneling Protocol (PPTP)
- Remote Procedure Call (RPC)

Transport

The protocols at the transport layer handle end-to-end transmission and segmentation of

a data stream. The following protocols work at this layer:

- Transmission Control Protocol (TCP)
- User Datagram Protocol (UDP)
- Stream Control Transmission Protocol (SCTP)
- Resource Reservation Protocol (RSVP)
- QUIC (not an acronym)

Network

The responsibilities of the network layer protocols include internetworking service,

addressing, and routing. The following lists some of the protocols that work at this layer:

- Internet Protocol (IP)
- Internet Control Message Protocol (ICMP)
- Internet Group Management Protocol (IGMP)
- Routing Information Protocol (RIP)
- Open Shortest Path First (OSPF)

Data Link

The protocols at the data link layer convert data into LAN or WAN frames for transmission and define how a computer accesses a network. This layer is divided into the Logical

Link Control (LLC) and the Media Access Control (MAC) sublayers. Some protocols that work at this layer include the following:

♠Chapter 11: Networking Fundamentals

485

- Address Resolution Protocol (ARP)
- Reverse Address Resolution Protocol (RARP)
- Serial Line Internet Protocol (SLIP)
- Ethernet (IEEE 802.3)
- Wireless Ethernet (IEEE 802.11)

Physical

Network interface cards and drivers convert bits into electrical signals and control

the physical aspects of data transmission, including optical, electrical, and mechanical

requirements. The following are some of the standard interfaces at this layer:

Tying the Layers Together

The OSI model is used as a framework for many network-based products and is used by

many types of vendors. Various types of devices and protocols work at different parts of

this seven-layer model. The main reason that a Cisco switch, a Microsoft web server, a

Barracuda firewall, and a Belkin wireless access point can all communicate properly on

one network is because they all work within the OSI model. They do not have their own

individual ways of sending data; they follow a standardized manner of communication,

which allows for interoperability and allows a network to be a network. If a product

does not follow the OSI model, it will not be able to communicate with other devices

on the network because the other devices will not understand its proprietary way of

communicating.

The different device types work at specific OSI layers. For example, computers can interpret and process data at each of the seven layers, but routers can understand

information only up to the network layer because a router's main function is to route

packets, which does not require knowledge about any further information within the

packet. A router peels back the header information until it reaches the network layer

data, where the routing and IP address information is located. The router looks at this

information to make its decisions on where the packet should be routed. Bridges and

switches understand only up to the data link layer, and repeaters understand traffic

only at the physical layer. So if you hear someone mention a "layer 3 device," the

person is referring to a device that works at the network layer. A "layer 2 device" works

at the data link layer. Figure 11-9 shows what layer of the OSI model each type of

device works within.

PART IV

- RS/EIA/TIA-422, RS/EIA/TIA-423, RS/EIA/TIA-449, RS/EIA/TIA-485
- 10Base-T, 10Base2, 10Base5, 100Base-TX, 100Base-FX, 100Base-T, 1000Base-T, 1000Base-SX
- Integrated Services Digital Network (ISDN)
- Digital subscriber line (DSL)
- Synchronous Optical Networking (SONET)

♠CISSP All-in-One Exam Guide

486

Message

Application

Presentation

Encryption, compression, standard formatting

Session maintenance

Session

End-to-end connection

Transport Datagram

Frame

Bits

Session



NOTE Some techies like to joke that all computer problems reside at layer 8. The OSI model does not have an eighth layer, and what these people are referring to is the user of a computer. So if someone states that there is a problem at layer 8, this is code for "the user is the problem."

Let's walk through an example. You just logged into a website and the landing page

includes an image that your web browser automatically requests from the server. The web

server now has to move this file over the network to your computer, so it generates an

HTTP response, which includes a handle to the file, and hands it over to the presentation

layer for encoding. HTTP doesn't directly handle binary files like JPEG images, so the

file must first be "serialized" or converted to a sequence of printable characters, which is

what the presentation layer does.

Once the response is "presentable" (pardon the pun), the presentation layer hands

it to the session layer to figure out which of the clients currently communicating with

♠Chapter 11: Networking Fundamentals

487

the server should receive this image; the session layer figures out that it is for you and

that you have been authenticated. The session layer then forwards the response

transport layer, telling it the connection (or network socket) on which it should go out.

Based on this connection identifier, the transport layer encapsulates the payload it just

got from the session layer in a TCP datagram (which is what HTTP runs on), writes the

protocol and port numbers in its header, and passes it on to layer 3.

The image you're requesting is quite large, so the network layer breaks it up into a

numbered sequence of chunks, encapsulates each in its own IP packet, figures out how

to route the packets, and then hands each to the data link layer. Layer 2 takes each packet

and, based on its destination IP address, determines the next hop on its journey back to

you, which is probably the DMZ firewall. It encapsulates the packet into an Ethernet

frame, writes the MAC address of the firewall in it, and sends it down to the physical

layer, which turns the 1's and 0's into electric currents on the network cable. And, just

like that, your image starts its journey toward your screen.

Local Area Networks

Network Topology

The arrangement of computers and devices is called a network topology refers to

the manner in which a network is physically connected and shows the layout of resources

and systems. A difference exists between the physical network topology and the logical

topology. A network can be configured as a physical star but work logically as a ring, as

in the Token Ring technology.

The best topology for a particular network depends on such things as how nodes are supposed to interact; which protocols are used; the types of applications that are

available; the reliability, expandability, and physical layout of a facility; existing wiring;

and the technologies implemented. The wrong topology or combination of topologies

can negatively affect the network's performance, productivity, and growth possibilities.

This section describes the basic types of network topologies. Most networks are much

more complex and are usually implemented using a combination of topologies.

Bus Topology

In a simple bus topology, a single cable runs the entire length of the network. Nodes are

attached to the network through drop points on this cable. Data communications transmit the length of the medium, and each packet transmitted has the capability of being

PART IV

Now that we've taken a quick look down all seven layers of the OSI model, let's circle

back and take a more detailed look from the ground up. If you connect two generalpurpose computers that are right next to each other, you create a local area network. A

local area network (LAN) is a group of interconnected computers in close physical proximity to each other. A LAN is the basic building block for most organizational networks.

As we'll shortly see, there are multiple ways to build LANs both physically and logically.

In the following sections, we'll discuss the various technologies that allow us to physically

interconnect devices.

♠CISSP All-in-One Exam Guide

488

"looked at" by all nodes. Each node decides to accept or ignore the packet, depending upon the packet's destination address.

Bus topologies are of two main types: linear and tree. The linear bus topology has a

single cable with nodes attached. A tree topology has branches from the single cable, and

each branch can contain many nodes. In simple implementations of a bus topology, if

one workstation fails, other systems can be negatively affected because of the degree of

interdependence. In addition, because all nodes are connected to one main cable, the

cable itself becomes a potential single point of failure.

Bus topologies were common years ago on the first Ethernet networks. Today, you are very unlikely to encounter them in local area networks. However, this topology is

prevalent in vehicular networks, of which the Controller Area Network (CAN) bus is by

far the most popular standard.

Star Topology

In a star topology, all nodes connect to a central device such as a switch. Each node has a

dedicated link to the central device. The central device needs to provide enough throughput that it does not become a detrimental bottleneck for the network as a whole. Because

a central device is required, it is a potential single point of failure, so redundancy may

need to be implemented. Switches can be configured in flat or hierarchical implementations so larger organizations can use them.

When one workstation fails on a star topology, it does not affect other systems, as in

the bus topologies. In a star topology, each system is not as dependent on others as it is

dependent on the central connection device. This topology generally requires less cabling

than other types of topologies. As a result, cut cables are less likely, and detecting cable $% \left\{ 1\right\} =\left\{ 1\right$

problems is an easier task.

Mesh Topology

In a mesh topology, all systems and resources are connected to each other in a way that

does not follow the uniformity of the previous topologies, as shown in Figure 11-10. This

arrangement is usually a network of interconnected routers and switches that provides

Figure 11-10

In a mesh

topology,

each node is

connected to

all other nodes,

which provides

for redundant

paths.

♠Chapter 11: Networking Fundamentals

489

Figure 11-11

A ring topology

forms a closedloop connection.

Ring Topology

A ring topology has a series of devices connected by unidirectional transmission links, as

shown in Figure 11-11. These links form a closed loop and do not connect to a central

system, as in a star topology. In a physical ring formation, each node is dependent upon

the preceding nodes. In simple networks, if one system fails, all other systems could

be negatively affected because of this interdependence. Compensating for such failures,

coupled with the difficulty of installing a ring network in the first place, makes ring

topologies more expensive than other topologies. Although you have to know about ring

topologies for the CISSP exam, you are extremely unlikely to find them in the real world.

Still, who knows? Maybe one day they'll make a comeback.

Network Topologies Summary

A summary of the different network topologies and their important characteristics is provided in Table 11-1.

Medium Access Control Mechanisms

The physical topology of a network is the lower layer, or foundation, of a network. It

determines what type of physical media will be used to connect network devices and

what these connections look like. Medium access control (MAC) mechanisms deal with

how computer systems communicate over these media and are built into the network interfaces. MAC mechanisms set up the rules of how computers will communicate on a LAN, how errors are handled, the maximum transmission unit (MTU) size of frames,

and much more. These rules enable all computers and devices to communicate and

PART IV

multiple paths to all the nodes on the network. In a full mesh topology, every node is

directly connected to every other node, which provides a great degree of redundancy. A

typical Internet of Things (IoT) home automation network using ZigBee is an example

of a full mesh topology. In a partial mesh topology, every node is not directly

connected.

The Internet is an example of a partial mesh topology.

♠CISSP All-in-One Exam Guide

490

Topology

Characteristics

Problems

Bus

Uses a linear, single cable for all computers attached. All traffic travels the full cable and can be viewed by all other computers.

If one station experiences a problem, it can negatively affect surrounding computers on the same cable.

Ring

All computers are connected by a unidirectional transmission link, and the cable is in a closed loop.

If one station experiences a problem, it can negatively affect surrounding computers on the same ring.

Star

All computers are connected to a central device, which provides more resilience for the network.

The central device is a single point of failure.

Tree

A bus topology with branches off of the main cable.

Multiple single points of failure.

Mesh

Computers are connected to each other, which provides redundancy.

Requires more expense in cabling and extra effort to track down cable faults.

Table 11-1

Summary of Network Topologies

recover from problems, and enable users to be productive in accomplishing their networking tasks. Each participating entity needs to know how to communicate properly so

all other systems will understand the transmissions, instructions, and requests. LAN MAC mechanisms reside at the data link layer of the OSI model. Remember that as a message is passed down through a network stack, it is encapsulated by the protocols

and services at each layer. When the data message reaches the data link layer, the protocol

at this layer adds the necessary headers and trailers that will allow the message to traverse

a specific type of network (Ethernet, Token Ring, FDDI, etc.)

No matter what type of medium access technology is being used, the main resource that has to be shared by all systems and devices on the network is the network transmission

channel. This transmission channel could be coaxial cabling, UTP cabling, optical fibers,

or free space (e.g., using radio waves). There must be methods in place to make sure

that each system gets its fair share of access to the channel, that the system's data is not

corrupted during transmission, and that there is a way to control traffic in peak times.

Let's take a closer look at the three most common approaches to MAC: carrier sense

multiple access, Token Ring, and polling.

Carrier Sense Multiple Access

By far, the most common approach to MAC is called carrier sense multiple access (CSMA),

which provides a standard way to access the shared medium, communicate, and recover

from any errors that may occur. A transmission is called a carrier, so if a computer is transmitting frames, it is performing a carrier activity. Despite their best efforts, networked computers sometimes talk over each other, which creates what is called a collision. Think about

it: it takes time for electromagnetic signals to move from point A (where one transmitter

sits) to point B (where another computer also wants to transmit). Both computers listen to

the medium and, detecting no other traffic on it, simultaneously transmit their messages.

♠Chapter 11: Networking Fundamentals

Token Passing

Some of North America's indigenous people devised a clever way to ensure only one of

them spoke (and was not interrupted) at meetings. It was called the talking stick, and

only the one holding it was allowed to speak. Once that person was done, they would

put it down, allowing the next individual to pick it up and speak. This token ensured

that all participants had a chance to speak uninterrupted. Some MAC technologies also

use tokens, which are 24-bit control frames used to control which computers communicate at what intervals. The token is passed from computer to computer, and only the

computer that has the token can actually put frames onto the wire. The token grants a

computer the right to communicate. The token contains the data to be transmitted and

source and destination address information. When a system has data it needs to transmit,

it has to wait to receive the token. The computer then connects its message to the token

and puts it on the wire. Each computer checks this message to determine whether it is

addressed to it, which continues until the destination computer receives the message.

The destination computer makes a copy of the message and flips a bit to tell the source

computer it did indeed get its message. Once this gets back to the source computer, it

removes the frames from the network. The destination computer makes a copy of the

message, but only the originator of the message can remove the message from the token

and the network.

PART IV

Sometime later, these messages meet each other on the medium and collide, or corrupt each

other. There are two variants of CSMA with which you should be familiar: collision detection (CSMA/CD) and collision avoidance (CSMA/CA).

When computers use the carrier sense multiple access with collision detection (CSMA/CD)

protocol, they monitor the transmission activity, or carrier activity, on the wire so they can

determine when would be the best time to transmit data. Each node monitors the wire

continuously and waits until the wire is free before it transmits its data. As an analogy,

consider several people gathered in a group talking here and there about this and that. If a

person wants to talk, she usually listens to the current conversation and waits for a break

before she proceeds to talk. If she does not wait for the first person to stop talking, she will

be speaking at the same time as the other person, and the people around them may not be

able to understand fully what each is trying to say. If a computer puts frames on the wire

and its frames collide with another computer's frames, it will abort its transmission and alert

all other stations that a collision just took place. All stations will start a random collision

timer to force a delay before they attempt to transmit data. This random collision timer is

called the back-off algorithm. CSMA/CD was important in the early days of Ethernet LANs

when hubs and bridges were common, but is now largely deprecated.

The other variant of CSMA is carrier sense multiple access with collision avoidance

(CSMA/CA), in which all stations with data to transmit first check the medium to see

if it's quiet. If it is, they send their data. If it isn't, they start a random timer before they

check again. In some implementations, the station wishing to send data first sends a

request to send (RTS) frame to a controller or the destination and then waits for a clear

to send (CTS) frame before transmitting its data. CSMA/CA is most commonly used in

wireless networks.

♠CISSP All-in-One Exam Guide

492

Carrier-Sensing and Token-Passing Access Methods

Overall, carrier-sensing access methods are faster than token-passing access methods, but the former do have the problem of collisions. A network segment with

many devices can cause too many collisions and slow down the network's performance. Token-passing technologies do not have problems with collisions, but they

do not perform at the speed of carrier-sensing technologies. Network routers can help significantly in isolating the network resources for both the CSMA/CD and the token-passing methods.

If a computer that receives the token does not have a message to transmit, it sends the

token to the next computer on the network. An empty token has a header, data field,

and trailer, but a token that has an actual message has a new header, destination address,

source address, and a new trailer. This type of media-sharing method is used by Token

Ring and FDDI technologies.

NOTE Some applications and network protocols work better if they can communicate at determined intervals, instead of "whenever the data arrives."

In token-passing technologies, traffic arrives in this type of deterministic nature because not all systems can communicate at one time; only the system that has control of the token can communicate.

NOTE When there is just one transmission medium (i.e., UTP cable) that has to be shared by all nodes and devices in a network, this is referred to as a contention-based environment. Each system has to "compete" to use the transmission line, which can cause contention.

Collision and Broadcast Domains

As previously indicated, a collision occurs on Ethernet networks when two computers

transmit data at the same time. Other computers on the network detect this collision

because the overlapping signals of the collision increase the voltage of the signal above a

specific threshold. The more devices on a contention-based network, the more likely collisions will occur, which increases network latency (data transmission delays). A collision

domain is a group of devices that are contending, or competing, for the same shared communication medium. For example, all devices that are connected to a particular wireless

access point (WAP) belong to the same collision domain.

NOTE Collision domains used to be a problem in wired networks back when hubs were more prevalent than switches. You may still come across these examples, but they are exceptionally rare in real networks nowadays.

♠Chapter 11: Networking Fundamentals

493

Sometimes, a network device will want to send a message to all its neighbors.

example, it may need to send a message to Priya, so it shouts out "which of you have

Priya?" In Ethernet networks, the broadcast address is the one consisting of all 1's, which

in hexadecimal looks like this: FF:FF:FF:FF:FF. A broadcast domain consists of all

devices that can receive layer 2 (data link) broadcast messages from each other. If a group

of devices are in the same collision domain, then they must also be in the same broadcast

domain. However, there are cases in which these two domains are different. For example,

as shown in Figure 11-12, you can have wireless and wired clients on a hybrid network in

which all devices are in the same broadcast domain, but there will be different collision

domains. Note that network switches create a separate collision domain for each port. If

there is a single device on each port, collisions are avoided altogether.

EXAM TIP Broadcast domains are sets of computing nodes that all receive a layer 2 broadcast frame. These are normally all nodes that are interconnected, with no routers in between them. Collision domains are sets of computing nodes that may produce collisions when they transmit data. These are

normally nodes connected by hubs, repeaters, or wireless access points.

Figure 11-12
Collision domains
within one
broadcast domain

Router Broadcast domain Collision domain

Switch

Collision domain

Wireless access point

Collision domain

PART IV

Another benefit of restricting and controlling broadcast and collision domains is that

it makes sniffing the network and obtaining useful information more difficult for an

intruder as he traverses the network. A useful tactic for attackers is to install a $\ensuremath{\mathsf{Trojan}}$

horse that sets up a network sniffer on the compromised computer. The sniffer is usually

configured to look for a specific type of information, such as usernames and passwords.

If broadcast and collision domains are in effect, the compromised system will have access

only to the broadcast and collision traffic within its specific subnet or broadcast domain.

♠CISSP All-in-One Exam Guide

494

The compromised system will not be able to listen to traffic on other broadcast and

collision domains, and this can greatly reduce the amount of traffic and information

available to an attacker.

Polling

The third type of media-sharing method, besides CSMA and token passing, is polling.

Polling is a medium access control mechanism that relies on a primary station that periodically polls all others in its collision domain. Each polled device responds by stating

whether or not it has anything to send. In some implementations, the secondary stations

(devices) can also let the primary station know how much data they want to send, where

it's going to, and how urgent it is. After polling all secondary stations, the primary station allocates the channel according to whatever policy it follows. It could, for example,

prioritize traffic from one station, or type, or evenly divide the channel among all stations

that asked to access it.

The main thing to remember about polling MAC is that each device needs to wait until the primary station completes a poll and then tells that device how much of the

channel it can use. Only then can a secondary station transmit data. This approach is

very uncommon in LANs, though it is used in some wireless networks. Polling is much

more common in wide area networks.

Layer 2 Protocols

Now that we've discussed LAN topologies and MAC mechanisms, let's look at how these

are implemented in reality. For the CISSP exam, you should know three layer 2 protocols: Ethernet, Token Ring, and FDDI. In reality, you are almost certainly to only use

Ethernet and its wireless cousin Wi-Fi. Token Ring and FDDI are exceptionally rare

in LANs, though FDDI is still used as the backbone of metropolitan area networks (MANs).

Ethernet

Ethernet is a set of technologies that enables several devices to communicate on the same

network. Ethernet usually uses a bus or star topology. If a linear bus topology is used,

all devices connect to one cable. If a star topology is used, each device is connected to a

cable that is connected to a centralized device, such as a switch. Ethernet was developed

in the 1970s, became commercially available in 1980, and was officially defined through

the IEEE 802.3 standard.

Ethernet has seen quite an evolution in its short history, from purely coaxial cable

installations that worked at 10 Mbps to mostly twisted-pair cable that works at speeds of $\,$

100 Mbps, 1,000 Mbps (1 Gbps), and up to 40 Gbps.

Ethernet is defined by the following characteristics:

- Contention-based technology (all resources use the same shared communication medium)
- Uses broadcast and collision domains
- ♠Chapter 11: Networking Fundamentals

Table 11-2 Ethernet Implementation Types

Ethernet Type

IEEE Standard

Cable Type
(minimum)

Speed

10Base-T

802.3i-1990

Cat3 UTP

10 Mbps

100Base-TX, Fast Ethernet

802.3u-1995

Cat5 UTP

100 Mbps

1000Base-T, Gigabit Ethernet

802.3ab-1999

Cat5 UTP

1,000 Mbps

10GBase-T

802.3an-2006

Cat6a UTP

10,000 Mbps

- Uses the CSMA access method
- Supports full-duplex communication
- Can use coaxial, twisted-pair, or fiber-optic cabling types, but most commonly uses UTP cables
- Is defined by the IEEE 802.3 family of standards

Token Ring

The Token Ring technology was originally developed by IBM and then defined by the

IEEE 802.5 standard. At first, Token Ring technology had the ability to transmit data

at 4 Mbps. Later, it was improved to transmit at 16 Mbps. It uses a

token-passing technology with a star-configured topology. The ring part of the name pertains to how the

signals travel, which is in a logical ring. Each computer is connected to a central hub,

called a Multistation Access Unit (MAU). Physically, the topology can be a star, but the

signals and transmissions are passed in a logical ring.

As previously described, token-passing technology is one in which a device cannot put

data on the network wire without having possession of a token, a control frame that

travels in a logical circle and is "picked up" when a system needs to communicate. This

is different from Ethernet, in which all the devices attempt to communicate at the same

time. This is why Ethernet is referred to as a "chatty protocol" and has collisions. Token

Ring does not endure collisions, since only one system can communicate at a time, but

this also means communication takes place more slowly compared to Ethernet.

PART IV

Ethernet addresses how computers share a common network and how they deal with collisions, data integrity, communication mechanisms, and transmission controls. These

are the common characteristics of Ethernet, but Ethernet does vary in the type of cabling

schemes and transfer rates it can supply. Several types of Ethernet implementations are

available, as outlined in Table 11-2.

10Base-T was considered heaven-sent when it first arrived on the networking scene,

but soon many users were demanding more speed and power. It is now considered a legacy standard and is very rarely seen in organizational networks. There are ongoing

efforts, however, to develop variants of this obsolete standard for use in automotive and

 $\ensuremath{\mathsf{IoT}}$ applications. Today, the most widely deployed type of Ethernet in organizational

networks is 1000Base-T.

♠CISSP All-in-One Exam Guide

496 Figure 11-13 A Token Ring network Frame

Logical ring

MAU

Physical star

Token Ring employs a couple of mechanisms to deal with problems that can occur on

this type of network. The active monitor mechanism removes frames that are continuously

circulating on the network. This can occur if a computer locks up or is taken offline for

one reason or another and cannot properly receive a token destined for it. With the

beaconing mechanism, if a computer detects a problem with the network, it sends a beacon

frame. This frame generates a failure domain, which is between the computer that issued

the beacon and its neighbor downstream. The computers and devices within this failure

domain will attempt to reconfigure certain settings to try to work around the detected

fault. Figure 11-13 depicts a Token Ring network in a physical star configuration. Token

Ring networks were popular in the 1980s and 1990s, and although some are still around,

Ethernet is much more popular.

FDDI

Fiber Distributed Data Interface (FDDI) technology, developed by the American National

Standards Institute (ANSI), is a high-speed, token-passing, medium access technology.

FDDI has a data transmission speed of up to 100 Mbps and is usually used as a backbone network using fiber-optic cabling. FDDI also provides fault tolerance by offering a

second counter-rotating fiber ring. The primary ring has data traveling clockwise and is

used for regular data transmission. The second ring transmits data in a counterclockwise

fashion and is invoked only if the primary ring goes down. Sensors watch the primary

ring and, if it goes down, invoke a ring wrap so the data will be diverted to the second

♠Chapter 11: Networking Fundamentals

497

Devices are connected to both rings in case the primary ring fails.

Connecting to another network

Concentrating hub

Concentrating hub

Patch panel

Secondary ring

Figure 11-14 FDDI rings can be used as backbones to connect different LANs.

ring. Each node on the FDDI network has relays that are connected to both rings, so if

a break in the ring occurs, the two rings can be joined.

When FDDI is used as a backbone network, it usually connects several different networks, as shown in Figure 11-14.

Before Fast Ethernet and Gigabit Ethernet hit the market, FDDI was used mainly as

campus and service provider backbones. Because FDDI can be employed for distances

up to 100 kilometers, it was often used in MANs. The benefit of FDDI is that it can

work over long distances and at high speeds with minimal interference. It enables several

tokens to be present on the ring at the same time, causing more communication to take

place simultaneously, and it provides predictable delays that help connected networks

and devices know what to expect and when.

NOTE A version of FDDI, Copper Distributed Data Interface (CDDI), can work over UTP cabling.

PART IV

Primary ring

♠CISSP All-in-One Exam Guide

498 Figure 11-15 FDDI device types

SAS

SAC

SAS

Primary ring

DAC SAS Secondary ring

DAS

DAS

Devices that connect to FDDI rings fall into one of the following categories:

- Single-attachment station (SAS) Attaches to only one ring (the primary) through a concentrator
- Dual-attachment station (DAS) Has two ports and each port provides a connection for both the primary and the secondary rings
- Single-attached concentrator (SAC) Concentrator that connects an SAS device to the primary ring
- Dual-attached concentrator (DAC) Concentrator that connects DAS, SAS, and SAC devices to both rings

The different FDDI device types are illustrated in Figure 11-15. NOTE Ring topologies are considered deterministic, meaning that the rate of the traffic flow can be predicted. Since traffic can only flow if a token is in

place, the maximum time that a node will have to wait to receive traffic can be determined. This can be beneficial for time-sensitive applications.

Layer 2 Network Protocol Summary
Table 11-3 sums up the important characteristics of the technologies described in the preceding sections.

◆Chapter 11: Networking Fundamentals

499

LAN Implementation

Standard

Characteristics

Ethernet

IEEE 802.3

Uses broadcast and collision domains.
Uses CSMA medium access control method.
Can use coaxial, twisted-pair, or fiber-optic media.

Transmission speeds of 10 Mbps to 10 Gbps.

Token Ring

IEEE 802.5

Token-passing media access method.

Transmission speeds of 4 to 16 Mbps. Uses an active monitor and beaconing. Effectively defunct.

FDDI

ANSI standard Based on IEEE 802.4

Dual counter-rotating rings for fault tolerance. Transmission speeds of 100 Mbps.

Operates over long distances at high speeds and is therefore used as a backbone.

CDDI works over UTP.

Very rarely seen in the enterprise.

Table 11-3

LAN Media Access Methods

A packet may need to be sent to only one workstation, to a set of workstations, or to all

workstations on a particular subnet. If a packet needs to go from the source computer to

one particular system, a unicast transmission method is used. If the packet needs to go

to a specific group of systems, the sending system uses the multicast method. If a system

wants all computers on its subnet to receive a message, it uses the broadcast method.

Unicast is pretty simple because it has a source address and a destination address.

happy. Multicast is a bit different in that it is a one-to-many transmission. Multicasting $\,$

enables one computer to send data to a selective group of computers. A good example of

multicasting is tuning into a radio station on a computer. Some computers have software

that enables the user to determine whether she wants to listen to rock, Latin, or a talk

radio station, for example. Once the user selects one of these genres, the software must

tell the NIC driver to pick up not only packets addressed to its specific MAC address but

also packets that contain a specific multicast address.

The difference between broadcast and multicast is that in a broadcast one-to-all transmission, everyone gets the data, whereas in a multicast, only certain nodes receive

the data. So how does a server three states away multicast to one particular computer

on a specific network and no other networks in between? Suppose a user tunes in to