

many assertion methods in the Python `TestCase` class that raises an exception if its stated condition isn't met. For a full list of the assertion methods, see <https://mng.bz/PZZ2>. The following listing shows the new contents of `home/tests.py`. Update your own copy to match.

Listing 8.1 A test case for the `credits()` view

```
# home/tests.py
from django.test import TestCase

class TestHome(TestCase):
    def test_credits(self):
        response = self.client.get("/credits/")
        self.assertEqual(200, response.status_code)
```

Base class for all Django test cases

Inherit from `TestCase` to define a test case.

Methods that begin with `test_` are run as tests.

The `.client.get()` method calls a view through the URL routing system.

Assert that the HTTP response code was the expected 200.

NOTE The order of arguments to `.assertEqual()` isn't important, but I always put the expected value first. Whatever you do, be consistent—this makes it easier to read the error if an assertion fails.

Django extends the default Python `unittest` runner with its own. Django's runner knows about Django apps and will look for files and modules in apps whose names begin with “test”. You invoke the runner using the “test” management command:

```
(venv) RiffMates$ python manage.py test
Found 1 test(s).
Creating test database for alias 'default'...
System check identified no issues (0 silenced).
.
-----
Ran 1 test in 0.003s

OK
Destroying test database for alias 'default'...
```

You get one period (.) for each test that runs and passes.

The output from the `test` command tells you how many tests got run and alerts you if any failed. To see what failure looks like, change the 200 to 42 in the `.assertEqual()` call, and then run the test again. The results are as follows:

```
(venv) RiffMates$ python manage.py test
Found 1 test(s).
Creating test database for alias 'default'...
System check identified no issues (0 silenced).
F
=====
FAIL: test_credits (home.tests.TestHome.test_credits)
-----
Traceback (most recent call last):
  File "RiffMates/home/tests.py", line 8, in test_credits
    self.assertEqual(42, response.status_code)
```

A failed assertion gets shown as F instead of a period (.). An E gets shown if your code raises an exception not caused by an assertion.