

During its initialization, the scene manager calls the `getSceneKey()` method of each scene, which simply returns its unique scene key. The scene manager then builds an internal dictionary of scene keys and scene objects. When any scene in the program wants to switch to a different scene, it will call `self.goToScene()` (described in the following section) and pass in the scene key of the target scene. The scene manager uses this key in the dictionary to find the associated scene object; it then sets the new scene object as the current scene and calls its methods.

Each scene must contain its own version of `handleInputs()` to handle any events that would typically be handled in the main loop and its own version of `draw()` to draw anything the scene wants to draw in the window. If your scene does not override these two methods, it will not be able to respond to any events and will not draw anything in the window.

Let's take a closer look at the four methods you need to implement for each scene:

```
def __init__(self, window):
```

Each scene should begin with its own `__init__()` method. The `window` parameter is the window into which your program draws. You should start your method with this statement to save the `window` parameter for use in the `draw()` method:

```
    self.window = window
```

After that, you can include any other initialization code you want or need, such as code for instantiating buttons and text fields, loading images and sounds, and so on.

```
def getSceneKey(self):
```

This method must be implemented in every scene that you write. Your method must return the unique scene key associated with this scene.