

```
def update(self):
```

This method is called in every frame. Here, you can perform any actions you would have done in step 8 of the original 12-step template introduced in Chapter 5. For example, you might want this method to move images on the screen, check for collisions, and so on.

```
def leave(self):
```

This method is called by the scene manager whenever the program is about to transition to a different scene. It should do any cleanup that needs to be done before leaving, such as writing information to a file.

Navigating Between Scenes

The scene manager and the `Scene` base class provide a simple way to navigate between scenes. When the program wants to transition to another scene, the current scene should call its own `goToScene()` method, which is in the inherited `Scene` base class, like this:

```
self.goToScene(nextSceneKey, data)
```

The `goToScene()` method communicates to the scene manager that you want to transition to a different scene, whose scene key is `nextSceneKey`. You should make all scene keys available via a file such as *Constants.py*. The `data` parameter is any optional information that you want to pass on to the next scene. If no data needs to be transferred, you can eliminate this argument.

Typical calls would look like this:

```
self.goToScene(SOME_SCENE_KEY) # no data to be passed
# Or
self.goToScene(ANOTHER_SCENE_KEY, data=someValueOrValues) # go to a scene and pass data
```

The value of `data` can take any form, as long as the scenes being left and entered both understand the format. In response to this call, before leaving the current scene, the scene manager calls that scene's `leave()` method. When