

user navigates away. Finally, it has a `reset()` method for resetting the state before starting a new round. [Listing 16-3](#) shows the initialization code.

```
# Play scene - the main game play scene
--- snip imports and showCustomYesNoDialog ---

BOTTOM_RECT = (0, GAME_HEIGHT + 1, WINDOW_WIDTH,
               WINDOW_HEIGHT - GAME_HEIGHT)
STATE_WAITING = 'waiting'
STATE_PLAYING = 'playing'
STATE_GAME_OVER = 'game over'

class ScenePlay(pyghelpers.Scene):

    def __init__(self, window):
        ❶ self.window = window

        self.controlsBackground = pygwidgets.Image(self.window,
            (0, GAME_HEIGHT),
            'images/controlsBackground.jpg')

        self.quitButton = pygwidgets.CustomButton(self.window,
            (30, GAME_HEIGHT + 90),
            up='images/quitNormal.png',
            down='images/quitDown.png',
            over='images/quitOver.png',
            disabled='images/quitDisabled.png')

        self.highScoresButton = pygwidgets.CustomButton(self.window,
            (190, GAME_HEIGHT + 90),
            up='images/gotoHighScoresNormal.png',
            down='images/gotoHighScoresDown.png',
            over='images/gotoHighScoresOver.png',
            disabled='images/gotoHighScoresDisabled.png')

        self.startButton = pygwidgets.CustomButton(self.window,
            (450, GAME_HEIGHT + 90),
            up='images/startNewNormal.png',
            down='images/startNewDown.png',
            over='images/startNewOver.png',
            disabled='images/startNewDisabled.png',
            enterToActivate=True)

        self.soundCheckBox = pygwidgets.TextCheckBox(self.window,
```